

NAME

archive_entry_acl_add_entry, **archive_entry_acl_add_entry_w**,
archive_entry_acl_clear, **archive_entry_acl_count**,
archive_entry_acl_from_text, **archive_entry_acl_from_text_w**,
archive_entry_acl_next, **archive_entry_acl_reset**, **archive_entry_acl_to_text**,
archive_entry_acl_to_text_w, **archive_entry_acl_types** — functions for manipulating
Access Control Lists in archive entry descriptions

LIBRARY

Streaming Archive Library (libarchive, -larchive)

SYNOPSIS

```
#include <archive_entry.h>

void
archive_entry_acl_add_entry(struct archive_entry *a, int type, int permset,
    int tag, int qualifier, const char *name);

void
archive_entry_acl_add_entry_w(struct archive_entry *a, int type,
    int permset, int tag, int qualifier, const wchar_t *name);

void
archive_entry_acl_clear(struct archive_entry *a);

int
archive_entry_acl_count(struct archive_entry *a, int type);

int
archive_entry_acl_from_text(struct archive_entry *a, const char *text,
    int type);

int
archive_entry_acl_from_text_w(struct archive_entry *a,
    const wchar_t *text, int type);

int
archive_entry_acl_next(struct archive_entry *a, int type, int *ret_type,
    int *ret_permset, int *ret_tag, int *ret_qual, const char **ret_name);

int
archive_entry_acl_reset(struct archive_entry *a, int type);

char *
archive_entry_acl_to_text(struct archive_entry *a, ssize_t *len_p,
    int flags);

wchar_t *
archive_entry_acl_to_text_w(struct archive_entry *a, ssize_t *len_p,
    int flags);

int
archive_entry_acl_types(struct archive_entry *a);
```

DESCRIPTION

The “Access Control Lists (ACLs)” extend the standard Unix permission model. The ACL interface of **libarchive** supports both POSIX.1e and NFSv4 style ACLs. Use of ACLs is restricted by various levels

of ACL support in operating systems, file systems and archive formats.

POSIX.1e Access Control Lists

A POSIX.1e ACL consists of a number of independent entries. Each entry specifies the permission set as a bitmask of basic permissions. Valid permissions in the *permset* are:

ARCHIVE_ENTRY_ACL_READ (**r**)
 ARCHIVE_ENTRY_ACL_WRITE (**w**)
 ARCHIVE_ENTRY_ACL_EXECUTE (**x**)

The permissions correspond to the normal Unix permissions.

The *tag* specifies the principal to which the permission applies. Valid values are:

ARCHIVE_ENTRY_ACL_USER	The user specified by the name field.
ARCHIVE_ENTRY_ACL_USER_OBJ	The owner of the file.
ARCHIVE_ENTRY_ACL_GROUP	The group specified by the name field.
ARCHIVE_ENTRY_ACL_GROUP_OBJ	The group which owns the file.
ARCHIVE_ENTRY_ACL_MASK	The maximum permissions to be obtained via group permissions.
ARCHIVE_ENTRY_ACL_OTHER	Any principal who is not the file owner or a member of the owning group.

The principals ARCHIVE_ENTRY_ACL_USER_OBJ, ARCHIVE_ENTRY_ACL_GROUP_OBJ and ARCHIVE_ENTRY_ACL_OTHER are equivalent to user, group and other in the classic Unix permission model and specify non-extended ACL entries.

All files have an access ACL (ARCHIVE_ENTRY_ACL_TYPE_ACCESS). This specifies the permissions required for access to the file itself. Directories have an additional ACL (ARCHIVE_ENTRY_ACL_TYPE_DEFAULT), which controls the initial access ACL for newly-created directory entries.

NFSv4 Access Control Lists

A NFSv4 ACL consists of multiple individual entries called Access Control Entries (ACEs).

There are four possible types of a NFSv4 ACE:

ARCHIVE_ENTRY_ACL_TYPE_ALLOW	Allow principal to perform actions requiring given permissions.
ARCHIVE_ENTRY_ACL_TYPE_DENY	Prevent principal from performing actions requiring given permissions.
ARCHIVE_ENTRY_ACL_TYPE_AUDIT	Log access attempts by principal which require given permissions.
ARCHIVE_ENTRY_ACL_TYPE_ALARM	Trigger a system alarm on access attempts by principal which require given permissions.

The *tag* specifies the principal to which the permission applies. Valid values are:

ARCHIVE_ENTRY_ACL_USER	The user specified by the name field.
ARCHIVE_ENTRY_ACL_USER_OBJ	The owner of the file.
ARCHIVE_ENTRY_ACL_GROUP	The group specified by the name field.
ARCHIVE_ENTRY_ACL_GROUP_OBJ	The group which owns the file.
ARCHIVE_ENTRY_ACL_EVERYONE	Any principal who is not the file owner or a member of the owning group.

Entries with the ARCHIVE_ENTRY_ACL_USER or ARCHIVE_ENTRY_ACL_GROUP tag store the user and group name in the *name* string and optionally the user or group ID in the *qualifier* integer.

NFSv4 ACE permissions and flags are stored in the same *permset* bitfield. Some permissions share the same constant and permission character but have different effect on directories than on files. The following

ACE permissions are supported:

ARCHIVE_ENTRY_ACL_READ_DATA (**r**)
Read data (file).

ARCHIVE_ENTRY_ACL_LIST_DIRECTORY (**r**)
List entries (directory).

ARCHIVE_ENTRY_ACL_WRITE_DATA (**w**)
Write data (file).

ARCHIVE_ENTRY_ACL_ADD_FILE (**w**)
Create files (directory).

ARCHIVE_ENTRY_ACL_EXECUTE (**x**)
Execute file or change into a directory.

ARCHIVE_ENTRY_ACL_APPEND_DATA (**p**)
Append data (file).

ARCHIVE_ENTRY_ACL_ADD_SUBDIRECTORY (**p**)
Create subdirectories (directory).

ARCHIVE_ENTRY_ACL_DELETE_CHILD (**D**)
Remove files and subdirectories inside a directory.

ARCHIVE_ENTRY_ACL_DELETE (**d**)
Remove file or directory.

ARCHIVE_ENTRY_ACL_READ_ATTRIBUTES (**a**)
Read file or directory attributes.

ARCHIVE_ENTRY_ACL_WRITE_ATTRIBUTES (**A**)
Write file or directory attributes.

ARCHIVE_ENTRY_ACL_READ_NAMED_ATTRS (**R**)
Read named file or directory attributes.

ARCHIVE_ENTRY_ACL_WRITE_NAMED_ATTRS (**W**)
Write named file or directory attributes.

ARCHIVE_ENTRY_ACL_READ_ACL (**c**)
Read file or directory ACL.

ARCHIVE_ENTRY_ACL_WRITE_ACL (**C**)
Write file or directory ACL.

ARCHIVE_ENTRY_ACL_WRITE_OWNER (**o**)
Change owner of a file or directory.

ARCHIVE_ENTRY_ACL_SYNCHRONIZE (**s**)
Use synchronous I/O.

The following NFSv4 ACL inheritance flags are supported:

ARCHIVE_ENTRY_ACL_ENTRY_FILE_INHERIT (**f**)
Inherit parent directory ACE to files.

ARCHIVE_ENTRY_ACL_ENTRY_DIRECTORY_INHERIT (**d**)
Inherit parent directory ACE to subdirectories.

ARCHIVE_ENTRY_ACL_ENTRY_INHERIT_ONLY (**i**)
Only inherit, do not apply the permission on the directory itself.

ARCHIVE_ENTRY_ACL_ENTRY_NO_PROPAGATE_INHERIT (**n**)
Do not propagate inherit flags. Only first-level entries inherit ACLs.

ARCHIVE_ENTRY_ACL_ENTRY_SUCCESSFUL_ACCESS (**S**)
Trigger alarm or audit on successful access.

ARCHIVE_ENTRY_ACL_ENTRY_FAILED_ACCESS (**F**)
Trigger alarm or audit on failed access.

ARCHIVE_ENTRY_ACL_ENTRY_INHERITED (**I**)
Mark that ACE was inherited.

Functions

archive_entry_acl_add_entry() and **archive_entry_acl_add_entry_w()** add a single ACL entry. For the access ACL and non-extended principals, the classic Unix permissions are updated. An archive entry cannot contain both POSIX.1e and NFSv4 ACL entries.

archive_entry_acl_clear() removes all ACL entries and resets the enumeration pointer.

archive_entry_acl_count() counts the ACL entries that have the given type mask. *type* can be the bitwise-or of

```
ARCHIVE_ENTRY_ACL_TYPE_ACCESS
ARCHIVE_ENTRY_ACL_TYPE_DEFAULT
```

for POSIX.1e ACLs and

```
ARCHIVE_ENTRY_ACL_TYPE_ALLOW
ARCHIVE_ENTRY_ACL_TYPE_DENY
ARCHIVE_ENTRY_ACL_TYPE_AUDIT
ARCHIVE_ENTRY_ACL_TYPE_ALARM
```

for NFSv4 ACLs. For POSIX.1e ACLs if `ARCHIVE_ENTRY_ACL_TYPE_ACCESS` is included and at least one extended ACL entry is found, the three non-extended ACLs are added.

archive_entry_acl_from_text() and **archive_entry_acl_from_text_w()** add new (or merge with existing) ACL entries from (wide) text. The argument *type* may take one of the following values:

```
ARCHIVE_ENTRY_ACL_TYPE_ACCESS
ARCHIVE_ENTRY_ACL_TYPE_DEFAULT
ARCHIVE_ENTRY_ACL_TYPE_NFS4
```

Supports all formats that can be created with **archive_entry_acl_to_text()** or respectively **archive_entry_acl_to_text_w()**. Existing ACL entries are preserved. To get a clean new ACL from text **archive_entry_acl_clear()** must be called first. Entries prefixed with “default:” are treated as `ARCHIVE_ENTRY_ACL_TYPE_DEFAULT` unless *type* is `ARCHIVE_ENTRY_ACL_TYPE_NFS4`. Invalid entries, non-parseable ACL entries and entries beginning with the ‘#’ character (comments) are skipped.

archive_entry_acl_next() return the next entry of the ACL list. This functions may only be called after **archive_entry_acl_reset()** has indicated the presence of extended ACL entries.

archive_entry_acl_reset() prepare reading the list of ACL entries with **archive_entry_acl_next()**. The function returns 0 if no non-extended ACLs are found. In this case, the access permissions should be obtained by `archive_entry_mode(3)` or set using `chmod(2)`. Otherwise, the function returns the same value as **archive_entry_acl_count()**.

archive_entry_acl_to_text() and **archive_entry_acl_to_text_w()** convert the ACL entries for the given type into a (wide) string of ACL entries separated by newline. If the pointer *len_p* is not NULL, then the function shall return the length of the string (not including the NULL terminator) in the location pointed to by *len_p*. The *flag* argument is a bitwise-or.

The following flags are effective only on POSIX.1e ACL:

```
ARCHIVE_ENTRY_ACL_TYPE_ACCESS
    Output access ACLs.
ARCHIVE_ENTRY_ACL_TYPE_DEFAULT
    Output POSIX.1e default ACLs.
ARCHIVE_ENTRY_ACL_STYLE_MARK_DEFAULT
    Prefix each default ACL entry with the word “default:”.
ARCHIVE_ENTRY_ACL_STYLE_SOLARIS
    The mask and other ACLs don not contain a double colon.
```

The following flags are effective only on NFSv4 ACL:

`ARCHIVE_ENTRY_ACL_STYLE_COMPACT`

Do not output minus characters for unset permissions and flags in NFSv4 ACL permission and flag fields.

The following flags are effective on both POSIX.1e and NFSv4 ACL:

`ARCHIVE_ENTRY_ACL_STYLE_EXTRA_ID`

Add an additional colon-separated field containing the user or group id.

`ARCHIVE_ENTRY_ACL_STYLE_SEPARATOR_COMMA`

Separate ACL entries with comma instead of newline.

If the archive entry contains NFSv4 ACLs, all types of NFSv4 ACLs are returned. If the entry contains POSIX.1e ACLs and none of the flags `ARCHIVE_ENTRY_ACL_TYPE_ACCESS` or `ARCHIVE_ENTRY_ACL_TYPE_DEFAULT` are specified, both access and default entries are returned and default entries are prefixed with “default:”.

archive_entry_acl_types() get ACL entry types contained in an archive entry’s ACL. As POSIX.1e and NFSv4 ACL entries cannot be mixed, this function is a very efficient way to detect if an ACL already contains POSIX.1e or NFSv4 ACL entries.

RETURN VALUES

archive_entry_acl_count() and **archive_entry_acl_reset()** returns the number of ACL entries that match the given type mask. For POSIX.1e ACLS if the type mask includes `ARCHIVE_ENTRY_ACL_TYPE_ACCESS` and at least one extended ACL entry exists, the three classic Unix permissions are counted.

archive_entry_acl_from_text() and **archive_entry_acl_from_text_w()** return `ARCHIVE_OK` if all entries were successfully parsed and `ARCHIVE_WARN` if one or more entries were invalid or non-parseable.

archive_entry_acl_next() returns `ARCHIVE_OK` on success, `ARCHIVE_EOF` if no more ACL entries exist and `ARCHIVE_WARN` if **archive_entry_acl_reset()** has not been called first.

archive_entry_acl_to_text() returns a string representing the ACL entries matching the given type and flags on success or `NULL` on error.

archive_entry_acl_to_text_w() returns a wide string representing the ACL entries matching the given type and flags on success or `NULL` on error.

archive_entry_acl_types() returns a bitmask of ACL entry types or 0 if archive entry has no ACL entries.

SEE ALSO

`archive_entry(3)`, `libarchive(3)`