

GDCM

3.2.2

Generated by Doxygen 1.14.0

1 GDCM Documentation	1
2 Todo List	3
3 Deprecated List	5
4 Bug List	7
5 Namespace Index	9
5.1 Namespace List	9
6 Hierarchical Index	11
6.1 Class Hierarchy	11
7 Class Index	21
7.1 Class List	21
8 File Index	35
8.1 File List	35
9 Namespace Documentation	43
9.1 gdcmm Namespace Reference	43
9.1.1 Detailed Description	58
9.1.2 Typedef Documentation	58
9.1.2.1 AECComp	58
9.1.2.2 ASComp	58
9.1.2.3 BOOL_FUNCTION_PFILE_PFILE_POINTER	58
9.1.2.4 CSComp	58
9.1.2.5 DAComp	59
9.1.2.6 DTComp	59
9.1.2.7 FileList	59
9.1.2.8 IconImage	59
9.1.2.9 LOComp	59
9.1.2.10 LTComp	59
9.1.2.11 MacroEntry	59
9.1.2.12 NestedMacroEntries	59
9.1.2.13 PNComp	60
9.1.2.14 SHComp	60
9.1.2.15 STComp	60
9.1.2.16 TMComp	60
9.1.2.17 UCComp	60
9.1.2.18 UIComp	60

9.1.2.19 URComp	60
9.1.2.20 UTComp	60
9.1.3 Enumeration Type Documentation	60
9.1.3.1 CompOperators	60
9.1.3.2 ECharSet	61
9.1.3.3 ENQueryType	61
9.1.3.4 EQueryLevel	61
9.1.3.5 EQueryType	62
9.1.3.6 ERootType	62
9.1.3.7 LodModeType	62
9.1.4 Function Documentation	63
9.1.4.1 add1()	63
9.1.4.2 backslash()	63
9.1.4.3 Clamp()	63
9.1.4.4 clean()	63
9.1.4.5 doround()	63
9.1.4.6 GetVRFromTag()	64
9.1.4.7 operator"!="() [1/2]	64
9.1.4.8 operator"!="() [2/2]	64
9.1.4.9 operator<<() [1/59]	64
9.1.4.10 operator<<() [2/59]	64
9.1.4.11 operator<<() [3/59]	64
9.1.4.12 operator<<() [4/59]	64
9.1.4.13 operator<<() [5/59]	65
9.1.4.14 operator<<() [6/59]	65
9.1.4.15 operator<<() [7/59]	65
9.1.4.16 operator<<() [8/59]	65
9.1.4.17 operator<<() [9/59]	65
9.1.4.18 operator<<() [10/59]	65
9.1.4.19 operator<<() [11/59]	65
9.1.4.20 operator<<() [12/59]	66
9.1.4.21 operator<<() [13/59]	66
9.1.4.22 operator<<() [14/59]	66
9.1.4.23 operator<<() [15/59]	66
9.1.4.24 operator<<() [16/59]	66
9.1.4.25 operator<<() [17/59]	66
9.1.4.26 operator<<() [18/59]	66
9.1.4.27 operator<<() [19/59]	67
9.1.4.28 operator<<() [20/59]	67

9.1.4.29 operator<<()	[21/59]	67
9.1.4.30 operator<<()	[22/59]	67
9.1.4.31 operator<<()	[23/59]	67
9.1.4.32 operator<<()	[24/59]	67
9.1.4.33 operator<<()	[25/59]	67
9.1.4.34 operator<<()	[26/59]	68
9.1.4.35 operator<<()	[27/59]	68
9.1.4.36 operator<<()	[28/59]	68
9.1.4.37 operator<<()	[29/59]	68
9.1.4.38 operator<<()	[30/59]	68
9.1.4.39 operator<<()	[31/59]	68
9.1.4.40 operator<<()	[32/59]	68
9.1.4.41 operator<<()	[33/59]	69
9.1.4.42 operator<<()	[34/59]	69
9.1.4.43 operator<<()	[35/59]	69
9.1.4.44 operator<<()	[36/59]	69
9.1.4.45 operator<<()	[37/59]	69
9.1.4.46 operator<<()	[38/59]	69
9.1.4.47 operator<<()	[39/59]	69
9.1.4.48 operator<<()	[40/59]	70
9.1.4.49 operator<<()	[41/59]	70
9.1.4.50 operator<<()	[42/59]	70
9.1.4.51 operator<<()	[43/59]	70
9.1.4.52 operator<<()	[44/59]	70
9.1.4.53 operator<<()	[45/59]	70
9.1.4.54 operator<<()	[46/59]	70
9.1.4.55 operator<<()	[47/59]	71
9.1.4.56 operator<<()	[48/59]	71
9.1.4.57 operator<<()	[49/59]	71
9.1.4.58 operator<<()	[50/59]	71
9.1.4.59 operator<<()	[51/59]	71
9.1.4.60 operator<<()	[52/59]	71
9.1.4.61 operator<<()	[53/59]	71
9.1.4.62 operator<<()	[54/59]	72
9.1.4.63 operator<<()	[55/59]	72
9.1.4.64 operator<<()	[56/59]	72
9.1.4.65 operator<<()	[57/59]	72
9.1.4.66 operator<<()	[58/59]	72
9.1.4.67 operator<<()	[59/59]	72

9.1.4.68 operator==()	72
9.1.4.69 operator>>() [1/3]	73
9.1.4.70 operator>>() [2/3]	73
9.1.4.71 operator>>() [3/3]	73
9.1.4.72 Round()	73
9.1.4.73 roundat()	73
9.1.4.74 x16printf()	74
9.1.5 Variable Documentation	74
9.1.5.1 GlobalInstance	74
9.2 gdcm::network Namespace Reference	74
9.2.1 Enumeration Type Documentation	78
9.2.1.1 EEventID	78
9.2.1.2 EStateID	79
9.2.2 Function Documentation	79
9.2.2.1 GetStateIndex()	79
9.2.3 Variable Documentation	80
9.2.3.1 cMaxEventID	80
9.2.3.2 cMaxStateID	80
9.3 gdcm::SegmentHelper Namespace Reference	80
9.4 gdcm::terminal Namespace Reference	80
9.4.1 Detailed Description	81
9.4.2 Enumeration Type Documentation	81
9.4.2.1 Attribute	81
9.4.2.2 Color	81
9.4.2.3 Mode	82
9.4.3 Function Documentation	83
9.4.3.1 setattribute()	83
9.4.3.2 setbgcolor()	83
9.4.3.3 setfgcolor()	83
9.4.3.4 setmode()	83
10 Class Documentation	85
10.1 gdcm::network::AAabortPDU Class Reference	85
10.1.1 Detailed Description	86
10.1.2 Constructor & Destructor Documentation	86
10.1.2.1 AAabortPDU()	86
10.1.3 Member Function Documentation	86
10.1.3.1 IsLastFragment()	86
10.1.3.2 Print()	86

10.1.3.3 Read()	87
10.1.3.4 SetReason()	87
10.1.3.5 SetSource()	87
10.1.3.6 Size()	87
10.1.3.7 Write()	87
10.2 gdcmm::network::AAssociateACPDU Class Reference	88
10.2.1 Detailed Description	89
10.2.2 Member Typedef Documentation	89
10.2.2.1 SizeType	89
10.2.3 Constructor & Destructor Documentation	89
10.2.3.1 AAssociateACPDU()	89
10.2.4 Member Function Documentation	90
10.2.4.1 AddPresentationContextAC()	90
10.2.4.2 GetNumberOfPresentationContextAC()	90
10.2.4.3 GetPresentationContextAC()	90
10.2.4.4 GetUserInfo()	90
10.2.4.5 InitFromRQ()	90
10.2.4.6 IsLastFragment()	90
10.2.4.7 Print()	90
10.2.4.8 Read()	91
10.2.4.9 SetCalledAETitle()	91
10.2.4.10 SetCallingAETitle()	91
10.2.4.11 Size()	91
10.2.4.12 Write()	91
10.2.5 Friends And Related Symbol Documentation	91
10.2.5.1 AAssociateRQPDU	91
10.3 gdcmm::network::AAssociateRJPDU Class Reference	92
10.3.1 Detailed Description	93
10.3.2 Constructor & Destructor Documentation	93
10.3.2.1 AAssociateRJPDU()	93
10.3.3 Member Function Documentation	93
10.3.3.1 IsLastFragment()	93
10.3.3.2 Print()	93
10.3.3.3 Read()	93
10.3.3.4 Size()	93
10.3.3.5 Write()	94
10.4 gdcmm::network::AAssociateRQPDU Class Reference	94
10.4.1 Detailed Description	96
10.4.2 Member Typedef Documentation	96

10.4.2.1 PresentationContextArrayType	96
10.4.2.2 SizeType	96
10.4.3 Constructor & Destructor Documentation	96
10.4.3.1 AAssociateRQPDU() [1/2]	96
10.4.3.2 AAssociateRQPDU() [2/2]	96
10.4.4 Member Function Documentation	96
10.4.4.1 AddPresentationContext()	96
10.4.4.2 GetCalledAETitle()	96
10.4.4.3 GetCallingAETitle()	97
10.4.4.4 GetNumberOfPresentationContext()	97
10.4.4.5 GetPresentationContext()	97
10.4.4.6 GetPresentationContextByAbstractSyntax()	97
10.4.4.7 GetPresentationContextByID()	97
10.4.4.8 GetPresentationContexts()	97
10.4.4.9 GetReserved43_74()	97
10.4.4.10 GetUserInfo()	97
10.4.4.11 IsAETitleValid()	97
10.4.4.12 IsLastFragment()	98
10.4.4.13 Print()	98
10.4.4.14 Read()	98
10.4.4.15 SetCalledAETitle()	98
10.4.4.16 SetCallingAETitle()	98
10.4.4.17 SetUserInfo()	98
10.4.4.18 Size()	99
10.4.4.19 Write()	99
10.4.5 Friends And Related Symbol Documentation	99
10.4.5.1 AAssociateACPDU	99
10.5 gdcmm::AbortEvent Class Reference	99
10.6 gdcmm::network::AbstractSyntax Class Reference	100
10.6.1 Detailed Description	101
10.6.2 Constructor & Destructor Documentation	101
10.6.2.1 AbstractSyntax()	101
10.6.3 Member Function Documentation	101
10.6.3.1 GetAsDataElement()	101
10.6.3.2 GetName()	101
10.6.3.3 operator==()	101
10.6.3.4 Print()	102
10.6.3.5 Read()	102
10.6.3.6 SetName()	102

10.6.3.7 SetNameFromUID()	102
10.6.3.8 Size()	102
10.6.3.9 Write()	102
10.7 gdcm::AnonymizeEvent Class Reference	103
10.7.1 Detailed Description	104
10.7.2 Member Typedef Documentation	104
10.7.2.1 Self	104
10.7.2.2 Superclass	104
10.7.3 Constructor & Destructor Documentation	105
10.7.3.1 AnonymizeEvent() [1/2]	105
10.7.3.2 ~AnonymizeEvent()	105
10.7.3.3 AnonymizeEvent() [2/2]	105
10.7.4 Member Function Documentation	105
10.7.4.1 CheckEvent()	105
10.7.4.2 GetEventName()	105
10.7.4.3 GetTag()	105
10.7.4.4 MakeObject()	106
10.7.4.5 operator=()	106
10.7.4.6 SetTag()	106
10.8 gdcm::Anonymizer Class Reference	106
10.8.1 Detailed Description	109
10.8.2 Constructor & Destructor Documentation	110
10.8.2.1 Anonymizer()	110
10.8.2.2 ~Anonymizer()	110
10.8.3 Member Function Documentation	110
10.8.3.1 BALCPPProtect()	110
10.8.3.2 BasicApplicationLevelConfidentialityProfile()	110
10.8.3.3 CanEmptyTag()	110
10.8.3.4 Clear() [1/2]	110
10.8.3.5 Clear() [2/2]	111
10.8.3.6 ClearInternalUIDs()	111
10.8.3.7 Empty() [1/2]	111
10.8.3.8 Empty() [2/2]	111
10.8.3.9 GetBasicApplicationLevelConfidentialityProfileAttributes()	111
10.8.3.10 GetCryptographicMessageSyntax()	112
10.8.3.11 GetFile()	112
10.8.3.12 New()	112
10.8.3.13 RecurseDataSet()	112
10.8.3.14 Remove() [1/2]	112

10.8.3.15 Remove() [2/2]	112
10.8.3.16 RemoveGroupLength()	113
10.8.3.17 RemovePrivateTags()	113
10.8.3.18 RemoveRetired()	113
10.8.3.19 Replace() [1/4]	113
10.8.3.20 Replace() [2/4]	113
10.8.3.21 Replace() [3/4]	114
10.8.3.22 Replace() [4/4]	114
10.8.3.23 SetCryptographicMessageSyntax()	114
10.8.3.24 SetFile()	114
10.9 gdcmm::AnyEvent Class Reference	115
10.10 gdcmm::network::ApplicationContext Class Reference	116
10.10.1 Detailed Description	117
10.10.2 Constructor & Destructor Documentation	117
10.10.2.1 ApplicationContext()	117
10.10.3 Member Function Documentation	117
10.10.3.1 GetName()	117
10.10.3.2 Print()	117
10.10.3.3 Read()	117
10.10.3.4 SetName()	117
10.10.3.5 Size()	117
10.10.3.6 Write()	118
10.11 gdcmm::ApplicationEntity Class Reference	118
10.11.1 Detailed Description	119
10.11.2 Member Function Documentation	119
10.11.2.1 IsValid()	119
10.11.2.2 Print()	119
10.11.2.3 SetBlob()	119
10.11.2.4 Squeeze()	119
10.11.3 Member Data Documentation	120
10.11.3.1 Internal	120
10.11.3.2 MaxLength	120
10.11.3.3 MaxNumberOfComponents	120
10.11.3.4 Padding	120
10.11.3.5 Separator	120
10.12 gdcmm::network::AReleaseRPPDU Class Reference	120
10.12.1 Detailed Description	121
10.12.2 Constructor & Destructor Documentation	121
10.12.2.1 AReleaseRPPDU()	121

10.12.3 Member Function Documentation	121
10.12.3.1 IsLastFragment()	121
10.12.3.2 Print()	122
10.12.3.3 Read()	122
10.12.3.4 Size()	122
10.12.3.5 Write()	122
10.13 gdcmm::network::AReleaseRQPDU Class Reference	122
10.13.1 Detailed Description	123
10.13.2 Constructor & Destructor Documentation	124
10.13.2.1 AReleaseRQPDU()	124
10.13.3 Member Function Documentation	124
10.13.3.1 IsLastFragment()	124
10.13.3.2 Print()	124
10.13.3.3 Read()	124
10.13.3.4 Size()	124
10.13.3.5 Write()	124
10.14 gdcmm::network::ARTIMTimer Class Reference	125
10.14.1 Detailed Description	125
10.14.2 Constructor & Destructor Documentation	125
10.14.2.1 ARTIMTimer()	125
10.14.3 Member Function Documentation	125
10.14.3.1 GetElapsedTime()	125
10.14.3.2 GetHasExpired()	126
10.14.3.3 GetTimeout()	126
10.14.3.4 SetTimeout()	126
10.14.3.5 Start()	126
10.14.3.6 Stop()	126
10.15 gdcmm::ASN1 Class Reference	126
10.15.1 Detailed Description	127
10.15.2 Constructor & Destructor Documentation	127
10.15.2.1 ASN1() [1/2]	127
10.15.2.2 ~ASN1()	127
10.15.2.3 ASN1() [2/2]	127
10.15.3 Member Function Documentation	127
10.15.3.1 operator=()	127
10.15.3.2 ParseDump()	127
10.15.3.3 ParseDumpFile()	128
10.15.3.4 TestPBKDF2()	128
10.16 gdcmm::network::AsynchronousOperationsWindowSub Class Reference	128

10.16.1 Detailed Description	128
10.16.2 Constructor & Destructor Documentation	128
10.16.2.1 AsynchronousOperationsWindowSub()	128
10.16.3 Member Function Documentation	129
10.16.3.1 Print()	129
10.16.3.2 Read()	129
10.16.3.3 Size()	129
10.16.3.4 Write()	129
10.17 gdcmm::Attribute< Group, Element, TVR, TVM > Class Template Reference	129
10.17.1 Detailed Description	131
10.17.2 Member Typedef Documentation	131
10.17.2.1 ArrayType	131
10.17.3 Member Enumeration Documentation	132
10.17.3.1 anonymous enum	132
10.17.4 Member Function Documentation	132
10.17.4.1 GDCM_STATIC_ASSERT() [1/3]	132
10.17.4.2 GDCM_STATIC_ASSERT() [2/3]	132
10.17.4.3 GDCM_STATIC_ASSERT() [3/3]	132
10.17.4.4 GetAsDataElement()	133
10.17.4.5 GetDictVM()	133
10.17.4.6 GetDictVR()	133
10.17.4.7 GetNumberOfValues()	133
10.17.4.8 GetTag()	134
10.17.4.9 GetValue() [1/2]	134
10.17.4.10 GetValue() [2/2]	134
10.17.4.11 GetValues()	134
10.17.4.12 GetVM()	135
10.17.4.13 GetVR()	135
10.17.4.14 operator!=(())	135
10.17.4.15 operator<()	135
10.17.4.16 operator==(())	135
10.17.4.17 operator[]() [1/2]	136
10.17.4.18 operator[]() [2/2]	136
10.17.4.19 Print()	136
10.17.4.20 Set()	136
10.17.4.21 SetByteValue()	136
10.17.4.22 SetByteValueNoSwap()	137
10.17.4.23 SetFromDataElement()	137
10.17.4.24 SetFromDataSet()	137

10.17.4.25 SetValue()	138
10.17.4.26 SetValues()	138
10.17.5 Member Data Documentation	138
10.17.5.1 Internal	138
10.18 gdcmm::Attribute< Group, Element, TVR, VM::VM1 > Class Template Reference	139
10.18.1 Member Typedef Documentation	141
10.18.1.1 ArrayType	141
10.18.2 Member Enumeration Documentation	141
10.18.2.1 anonymous enum	141
10.18.2.2 anonymous enum	141
10.18.3 Member Function Documentation	142
10.18.3.1 GDCM_STATIC_ASSERT() [1/4]	142
10.18.3.2 GDCM_STATIC_ASSERT() [2/4]	142
10.18.3.3 GDCM_STATIC_ASSERT() [3/4]	142
10.18.3.4 GDCM_STATIC_ASSERT() [4/4]	142
10.18.3.5 GetAsDataElement()	142
10.18.3.6 GetDictVM()	143
10.18.3.7 GetDictVR()	143
10.18.3.8 GetNumberOfValues()	143
10.18.3.9 GetTag()	143
10.18.3.10 GetValue() [1/2]	143
10.18.3.11 GetValue() [2/2]	143
10.18.3.12 GetValues()	143
10.18.3.13 GetVM()	144
10.18.3.14 GetVR()	144
10.18.3.15 operator!=(())	144
10.18.3.16 operator<()	144
10.18.3.17 operator==(())	144
10.18.3.18 operator[]()	144
10.18.3.19 Print()	145
10.18.3.20 Set()	145
10.18.3.21 SetByteValue()	145
10.18.3.22 SetByteValueNoSwap()	145
10.18.3.23 SetFromDataElement()	145
10.18.3.24 SetFromDataSet()	146
10.18.3.25 SetValue()	146
10.18.3.26 SetValues()	146
10.18.4 Member Data Documentation	146
10.18.4.1 Internal	146

10.19 gdcmm::Attribute< Group, Element, TVR, VM::VM1_3 > Class Template Reference	147
10.19.1 Member Typedef Documentation	149
10.19.1.1 ArrayType	149
10.19.2 Member Enumeration Documentation	149
10.19.2.1 anonymous enum	149
10.19.3 Member Function Documentation	149
10.19.3.1 GDCM_STATIC_ASSERT()	149
10.19.3.2 GetAsDataElement()	149
10.19.3.3 GetDictVM()	149
10.19.3.4 GetDictVR()	150
10.19.3.5 GetNumberOfValues()	150
10.19.3.6 GetTag()	150
10.19.3.7 GetValue()	150
10.19.3.8 GetValues()	150
10.19.3.9 GetVM()	150
10.19.3.10 GetVR()	150
10.19.3.11 operator!=(())	150
10.19.3.12 operator<()	150
10.19.3.13 operator==(())	151
10.19.3.14 operator[]()	151
10.19.3.15 Print()	151
10.19.3.16 Set()	151
10.19.3.17 SetByteValue()	151
10.19.3.18 SetByteValueNoSwap()	151
10.19.3.19 SetFromDataElement()	151
10.19.3.20 SetFromDataSet()	151
10.19.3.21 SetValue()	152
10.19.3.22 SetValues()	152
10.19.4 Member Data Documentation	152
10.19.4.1 Internal	152
10.20 gdcmm::Attribute< Group, Element, TVR, VM::VM1_8 > Class Template Reference	152
10.20.1 Member Typedef Documentation	154
10.20.1.1 ArrayType	154
10.20.2 Member Enumeration Documentation	155
10.20.2.1 anonymous enum	155
10.20.3 Member Function Documentation	155
10.20.3.1 GDCM_STATIC_ASSERT()	155
10.20.3.2 GetAsDataElement()	155
10.20.3.3 GetDictVM()	155

10.20.3.4 GetDictVR()	155
10.20.3.5 GetNumberOfValues()	155
10.20.3.6 GetTag()	155
10.20.3.7 GetValue()	155
10.20.3.8 GetValues()	156
10.20.3.9 GetVM()	156
10.20.3.10 GetVR()	156
10.20.3.11 operator"!=(())	156
10.20.3.12 operator<()	156
10.20.3.13 operator==(())	156
10.20.3.14 operator[]()	156
10.20.3.15 Print()	156
10.20.3.16 Set()	157
10.20.3.17 SetByteValue()	157
10.20.3.18 SetByteValueNoSwap()	157
10.20.3.19 SetFromDataElement()	157
10.20.3.20 SetFromDataSet()	157
10.20.3.21 SetValue()	157
10.20.3.22 SetValues()	157
10.20.4 Member Data Documentation	158
10.20.4.1 Internal	158
10.21 gdcm::Attribute< Group, Element, TVR, VM::VM1_n > Class Template Reference	158
10.21.1 Member Typedef Documentation	160
10.21.1.1 ArrayType	160
10.21.2 Member Enumeration Documentation	160
10.21.2.1 anonymous enum	160
10.21.3 Constructor & Destructor Documentation	161
10.21.3.1 Attribute()	161
10.21.3.2 ~Attribute()	161
10.21.4 Member Function Documentation	161
10.21.4.1 GDCM_STATIC_ASSERT() [1/3]	161
10.21.4.2 GDCM_STATIC_ASSERT() [2/3]	161
10.21.4.3 GDCM_STATIC_ASSERT() [3/3]	161
10.21.4.4 GetAsDataElement()	161
10.21.4.5 GetDictVM()	162
10.21.4.6 GetDictVR()	162
10.21.4.7 GetNumberOfValues()	162
10.21.4.8 GetTag()	162
10.21.4.9 GetValue() [1/2]	162

10.21.4.10 GetValue() [2/2]	162
10.21.4.11 GetValues()	163
10.21.4.12 GetVM()	163
10.21.4.13 GetVR()	163
10.21.4.14 operator"!="()	163
10.21.4.15 operator<()	163
10.21.4.16 operator==(())	163
10.21.4.17 operator[]() [1/2]	163
10.21.4.18 operator[]() [2/2]	164
10.21.4.19 Print()	164
10.21.4.20 Set()	164
10.21.4.21 SetByteValue()	164
10.21.4.22 SetByteValueNoSwap()	164
10.21.4.23 SetFromDataElement()	164
10.21.4.24 SetFromDataSet()	165
10.21.4.25 SetNumberOfValues()	165
10.21.4.26 SetValue() [1/2]	165
10.21.4.27 SetValue() [2/2]	165
10.21.4.28 SetValues()	165
10.22 gdcmm::Attribute< Group, Element, TVR, VM::VM2_2n > Class Template Reference	166
10.22.1 Member Typedef Documentation	169
10.22.1.1 ArrayType	169
10.22.2 Member Enumeration Documentation	169
10.22.2.1 anonymous enum	169
10.22.3 Member Function Documentation	169
10.22.3.1 GDCM_STATIC_ASSERT()	169
10.22.3.2 GetAsDataElement()	170
10.22.3.3 GetDictVM()	170
10.22.3.4 GetDictVR()	170
10.22.3.5 GetNumberOfValues()	170
10.22.3.6 GetTag()	170
10.22.3.7 GetValue()	170
10.22.3.8 GetValues()	170
10.22.3.9 GetVM()	170
10.22.3.10 GetVR()	170
10.22.3.11 operator"!="()	171
10.22.3.12 operator<()	171
10.22.3.13 operator==(())	171
10.22.3.14 operator[]()	171

10.22.3.15 Print()	171
10.22.3.16 Set()	171
10.22.3.17 SetByteValue()	171
10.22.3.18 SetByteValueNoSwap()	171
10.22.3.19 SetFromDataElement()	172
10.22.3.20 SetFromDataSet()	172
10.22.3.21 SetValue()	172
10.22.3.22 SetValues()	172
10.22.4 Member Data Documentation	172
10.22.4.1 Internal	172
10.23 gdcmm::Attribute< Group, Element, TVR, VM::VM2_n > Class Template Reference	173
10.23.1 Member Typedef Documentation	175
10.23.1.1 ArrayType	175
10.23.2 Member Enumeration Documentation	175
10.23.2.1 anonymous enum	175
10.23.3 Member Function Documentation	175
10.23.3.1 GDCM_STATIC_ASSERT()	175
10.23.3.2 GetAsDataElement()	175
10.23.3.3 GetDictVM()	175
10.23.3.4 GetDictVR()	176
10.23.3.5 GetNumberOfValues()	176
10.23.3.6 GetTag()	176
10.23.3.7 GetValue()	176
10.23.3.8 GetValues()	176
10.23.3.9 GetVM()	176
10.23.3.10 GetVR()	176
10.23.3.11 operator!=(())	176
10.23.3.12 operator<()	176
10.23.3.13 operator==(())	177
10.23.3.14 operator[]()	177
10.23.3.15 Print()	177
10.23.3.16 Set()	177
10.23.3.17 SetByteValue()	177
10.23.3.18 SetByteValueNoSwap()	177
10.23.3.19 SetFromDataElement()	177
10.23.3.20 SetFromDataSet()	177
10.23.3.21 SetValue()	178
10.23.3.22 SetValues()	178
10.23.4 Member Data Documentation	178

10.23.4.1 Internal	178
10.24 gdcmm::Attribute< Group, Element, TVR, VM::VM3_3n > Class Template Reference	178
10.24.1 Member Typedef Documentation	181
10.24.1.1 ArrayType	181
10.24.2 Member Enumeration Documentation	182
10.24.2.1 anonymous enum	182
10.24.3 Member Function Documentation	182
10.24.3.1 GDCM_STATIC_ASSERT()	182
10.24.3.2 GetAsDataElement()	182
10.24.3.3 GetDictVM()	182
10.24.3.4 GetDictVR()	182
10.24.3.5 GetNumberOfValues()	182
10.24.3.6 GetTag()	182
10.24.3.7 GetValue()	182
10.24.3.8 GetValues()	183
10.24.3.9 GetVM()	183
10.24.3.10 GetVR()	183
10.24.3.11 operator!=(())	183
10.24.3.12 operator<()	183
10.24.3.13 operator==(())	183
10.24.3.14 operator[]()	183
10.24.3.15 Print()	183
10.24.3.16 Set()	184
10.24.3.17 SetByteValue()	184
10.24.3.18 SetByteValueNoSwap()	184
10.24.3.19 SetFromDataElement()	184
10.24.3.20 SetFromDataSet()	184
10.24.3.21 SetValue()	184
10.24.3.22 SetValues()	184
10.24.4 Member Data Documentation	185
10.24.4.1 Internal	185
10.25 gdcmm::Attribute< Group, Element, TVR, VM::VM3_n > Class Template Reference	185
10.25.1 Member Typedef Documentation	187
10.25.1.1 ArrayType	187
10.25.2 Member Enumeration Documentation	187
10.25.2.1 anonymous enum	187
10.25.3 Member Function Documentation	188
10.25.3.1 GDCM_STATIC_ASSERT()	188
10.25.3.2 GetAsDataElement()	188

10.25.3.3 GetDictVM()	188
10.25.3.4 GetDictVR()	188
10.25.3.5 GetNumberOfValues()	188
10.25.3.6 GetTag()	188
10.25.3.7 GetValue()	188
10.25.3.8 GetValues()	188
10.25.3.9 GetVM()	189
10.25.3.10 GetVR()	189
10.25.3.11 operator!=(())	189
10.25.3.12 operator<()	189
10.25.3.13 operator==(())	189
10.25.3.14 operator[]()	189
10.25.3.15 Print()	189
10.25.3.16 Set()	189
10.25.3.17 SetByteValue()	190
10.25.3.18 SetByteValueNoSwap()	190
10.25.3.19 SetFromDataElement()	190
10.25.3.20 SetFromDataSet()	190
10.25.3.21 SetValue()	190
10.25.3.22 SetValues()	190
10.25.4 Member Data Documentation	190
10.25.4.1 Internal	190
10.26 gdcm::AudioCodec Class Reference	191
10.26.1 Detailed Description	192
10.26.2 Constructor & Destructor Documentation	192
10.26.2.1 AudioCodec()	192
10.26.2.2 ~AudioCodec()	193
10.26.3 Member Function Documentation	193
10.26.3.1 CanCode()	193
10.26.3.2 CanDecode()	193
10.26.3.3 Decode()	193
10.27 gdcm::Base64 Class Reference	193
10.27.1 Detailed Description	194
10.27.2 Constructor & Destructor Documentation	194
10.27.2.1 Base64()	194
10.27.3 Member Function Documentation	194
10.27.3.1 Decode()	194
10.27.3.2 Encode()	195
10.27.3.3 GetDecodeLength()	195

10.27.3.4 GetEncodeLength()	195
10.27.3.5 operator=()	195
10.28 gdcmm::network::BaseCompositeMessage Class Reference	196
10.28.1 Detailed Description	196
10.28.2 Constructor & Destructor Documentation	197
10.28.2.1 ~BaseCompositeMessage()	197
10.28.3 Member Function Documentation	197
10.28.3.1 ConstructPDV()	197
10.29 gdcmm::network::BaseNormalizedMessage Class Reference	197
10.29.1 Detailed Description	198
10.29.2 Constructor & Destructor Documentation	199
10.29.2.1 ~BaseNormalizedMessage()	199
10.29.3 Member Function Documentation	199
10.29.3.1 ConstructPDV()	199
10.30 gdcmm::network::BasePDU Class Reference	200
10.30.1 Detailed Description	200
10.30.2 Constructor & Destructor Documentation	201
10.30.2.1 ~BasePDU()	201
10.30.3 Member Function Documentation	201
10.30.3.1 IsLastFragment()	201
10.30.3.2 Print()	201
10.30.3.3 Read()	201
10.30.3.4 Size()	202
10.30.3.5 Write()	202
10.31 gdcmm::BaseQuery Class Reference	202
10.31.1 Detailed Description	204
10.31.2 Constructor & Destructor Documentation	204
10.31.2.1 BaseQuery()	204
10.31.2.2 ~BaseQuery()	204
10.31.3 Member Function Documentation	204
10.31.3.1 AddQueryDataSet()	204
10.31.3.2 GetAbstractSyntaxUID()	205
10.31.3.3 GetQueryDataSet() [1/2]	205
10.31.3.4 GetQueryDataSet() [2/2]	205
10.31.3.5 GetSOPInstanceUID()	205
10.31.3.6 Print()	205
10.31.3.7 SetSearchParameter() [1/3]	205
10.31.3.8 SetSearchParameter() [2/3]	205
10.31.3.9 SetSearchParameter() [3/3]	206

10.31.3.10 SetSOPInstanceUID()	206
10.31.3.11 ValidateQuery()	206
10.31.3.12 ValidDataSet()	206
10.31.3.13 WriteHelpFile()	206
10.31.3.14 WriteQuery()	206
10.31.4 Friends And Related Symbol Documentation	206
10.31.4.1 QueryFactory	206
10.31.5 Member Data Documentation	207
10.31.5.1 mDataSet	207
10.31.5.2 mSopInstanceUID	207
10.32 gdcmm::BaseRootQuery Class Reference	207
10.32.1 Detailed Description	209
10.32.2 Constructor & Destructor Documentation	209
10.32.2.1 BaseRootQuery()	209
10.32.2.2 ~BaseRootQuery()	210
10.32.3 Member Function Documentation	210
10.32.3.1 Construct()	210
10.32.3.2 GetQueryLevelFromQueryRoot()	210
10.32.3.3 GetQueryLevelFromString()	210
10.32.3.4 GetQueryLevelString()	210
10.32.3.5 GetTagListByLevel()	210
10.32.3.6 InitializeDataSet()	211
10.32.3.7 ValidateQuery()	211
10.32.4 Friends And Related Symbol Documentation	211
10.32.4.1 QueryFactory	211
10.32.5 Member Data Documentation	211
10.32.5.1 mHelpDescription	211
10.32.5.2 mImage	212
10.32.5.3 mPatient	212
10.32.5.4 mRootType	212
10.32.5.5 mSeries	212
10.32.5.6 mStudy	212
10.33 gdcmm::SegmentHelper::BasicCodedEntry Struct Reference	212
10.33.1 Detailed Description	214
10.33.2 Constructor & Destructor Documentation	214
10.33.2.1 BasicCodedEntry() [1/3]	214
10.33.2.2 BasicCodedEntry() [2/3]	214
10.33.2.3 BasicCodedEntry() [3/3]	214
10.33.3 Member Function Documentation	214

10.33.3.1 IsEmpty()	214
10.33.4 Member Data Documentation	215
10.33.4.1 CM	215
10.33.4.2 CSD	215
10.33.4.3 CSV	215
10.33.4.4 CV	215
10.34 gdcmm::BasicOffsetTable Class Reference	216
10.34.1 Detailed Description	219
10.34.2 Constructor & Destructor Documentation	219
10.34.2.1 BasicOffsetTable()	219
10.34.3 Member Function Documentation	219
10.34.3.1 Read()	219
10.34.4 Friends And Related Symbol Documentation	219
10.34.4.1 operator<<	219
10.35 gdcmm::Bitmap Class Reference	220
10.35.1 Detailed Description	223
10.35.2 Member Typedef Documentation	223
10.35.2.1 LUTPtr	223
10.35.3 Constructor & Destructor Documentation	223
10.35.3.1 Bitmap()	223
10.35.3.2 ~Bitmap()	223
10.35.4 Member Function Documentation	223
10.35.4.1 AreOverlaysInPixelData()	223
10.35.4.2 Clear()	223
10.35.4.3 ComputeLossyFlag()	224
10.35.4.4 GetBuffer()	224
10.35.4.5 GetBuffer2()	224
10.35.4.6 GetBufferLength()	224
10.35.4.7 GetColumns()	224
10.35.4.8 GetDataElement() [1/2]	224
10.35.4.9 GetDataElement() [2/2]	225
10.35.4.10 GetDimension()	225
10.35.4.11 GetDimensions()	225
10.35.4.12 GetLUT() [1/2]	225
10.35.4.13 GetLUT() [2/2]	225
10.35.4.14 GetNeedByteSwap()	226
10.35.4.15 GetNumberOfDimensions()	226
10.35.4.16 GetPhotometricInterpretation()	226
10.35.4.17 GetPixelFormat() [1/2]	226

10.35.4.18 GetPixelFormat() [2/2]	226
10.35.4.19 GetPlanarConfiguration()	227
10.35.4.20 GetRows()	227
10.35.4.21 GetTransferSyntax()	227
10.35.4.22 IsEmpty()	227
10.35.4.23 IsLossy()	227
10.35.4.24 IsTransferSyntaxCompatible()	227
10.35.4.25 Print()	228
10.35.4.26 SetColumns()	228
10.35.4.27 SetDataElement()	228
10.35.4.28 SetDimension()	228
10.35.4.29 SetDimensions()	229
10.35.4.30 SetLossyFlag()	229
10.35.4.31 SetLUT()	229
10.35.4.32 SetNeedByteSwap()	229
10.35.4.33 SetNumberOfDimensions()	229
10.35.4.34 SetPhotometricInterpretation()	230
10.35.4.35 SetPixelFormat()	230
10.35.4.36 SetPlanarConfiguration()	230
10.35.4.37 SetRows()	230
10.35.4.38 SetTransferSyntax()	231
10.35.4.39 TryJPEG2000Codec()	231
10.35.4.40 TryJPEG2000Codec2()	231
10.35.4.41 TryJPEGCodec()	231
10.35.4.42 TryJPEGCodec2()	231
10.35.4.43 TryJPEGLSCodec()	231
10.35.4.44 TryKAKADUCodec()	232
10.35.4.45 TryPVRGCodec()	232
10.35.4.46 TryRAWCodec()	232
10.35.4.47 TryRLECodec()	232
10.35.4.48 UnusedBitsPresentInPixelData()	232
10.35.5 Friends And Related Symbol Documentation	232
10.35.5.1 ImageChangeTransferSyntax	232
10.35.5.2 PixmapReader	233
10.35.6 Member Data Documentation	233
10.35.6.1 Dimensions	233
10.35.6.2 LossyFlag	233
10.35.6.3 LUT	233
10.35.6.4 NeedByteSwap	233

10.35.6.5 NumberOfDimensions	233
10.35.6.6 PF	233
10.35.6.7 PI	234
10.35.6.8 PixelData	234
10.35.6.9 PlanarConfiguration	234
10.35.6.10 TS	234
10.36 gdcmm::BitmapToBitmapFilter Class Reference	234
10.36.1 Detailed Description	235
10.36.2 Constructor & Destructor Documentation	236
10.36.2.1 BitmapToBitmapFilter()	236
10.36.2.2 ~BitmapToBitmapFilter()	236
10.36.3 Member Function Documentation	236
10.36.3.1 GetOutput()	236
10.36.3.2 GetOutputAsBitmap()	236
10.36.3.3 SetInput()	236
10.36.4 Member Data Documentation	236
10.36.4.1 Input	236
10.36.4.2 Output	237
10.37 gdcmm::BoxRegion Class Reference	237
10.37.1 Detailed Description	238
10.37.2 Constructor & Destructor Documentation	239
10.37.2.1 BoxRegion() [1/2]	239
10.37.2.2 ~BoxRegion()	239
10.37.2.3 BoxRegion() [2/2]	239
10.37.3 Member Function Documentation	239
10.37.3.1 Area()	239
10.37.3.2 BoundingBox()	239
10.37.3.3 Clone()	240
10.37.3.4 ComputeBoundingBox()	240
10.37.3.5 Empty()	240
10.37.3.6 GetXMax()	240
10.37.3.7 GetXMin()	240
10.37.3.8 GetYMax()	240
10.37.3.9 GetYMin()	240
10.37.3.10 GetZMax()	241
10.37.3.11 GetZMin()	241
10.37.3.12 IsValid()	241
10.37.3.13 operator=()	241
10.37.3.14 Print()	241

10.37.3.15 SetDomain()	241
10.38 gdcm::ByteBuffer Class Reference	242
10.38.1 Detailed Description	242
10.38.2 Constructor & Destructor Documentation	242
10.38.2.1 ByteBuffer()	242
10.38.3 Member Function Documentation	242
10.38.3.1 Get()	242
10.38.3.2 GetStart()	242
10.38.3.3 ShiftEnd()	243
10.38.3.4 UpdatePosition()	243
10.39 gdcm::ByteSwap< T > Class Template Reference	243
10.39.1 Detailed Description	243
10.39.2 Member Function Documentation	243
10.39.2.1 Swap()	243
10.39.2.2 SwapFromSwapCodeIntoSystem()	244
10.39.2.3 SwapRange()	244
10.39.2.4 SwapRangeFromSwapCodeIntoSystem()	244
10.39.2.5 SystemIsBigEndian()	244
10.39.2.6 SystemIsLittleEndian()	245
10.40 gdcm::ByteSwapFilter Class Reference	245
10.40.1 Detailed Description	245
10.40.2 Constructor & Destructor Documentation	245
10.40.2.1 ByteSwapFilter() [1/2]	245
10.40.2.2 ~ByteSwapFilter()	246
10.40.2.3 ByteSwapFilter() [2/2]	246
10.40.3 Member Function Documentation	246
10.40.3.1 ByteSwap()	246
10.40.3.2 operator=()	246
10.40.3.3 SetByteSwapTag()	246
10.41 gdcm::ByteValue Class Reference	247
10.41.1 Detailed Description	249
10.41.2 Constructor & Destructor Documentation	249
10.41.2.1 ByteValue() [1/2]	249
10.41.2.2 ByteValue() [2/2]	249
10.41.2.3 ~ByteValue()	249
10.41.3 Member Function Documentation	250
10.41.3.1 Append()	250
10.41.3.2 Clear()	250
10.41.3.3 ComputeLength()	250

10.41.3.4 Fill()	250
10.41.3.5 GetBuffer()	250
10.41.3.6 GetLength()	251
10.41.3.7 GetPointer()	251
10.41.3.8 GetVoidPointer() [1/2]	251
10.41.3.9 GetVoidPointer() [2/2]	251
10.41.3.10 IsEmpty()	252
10.41.3.11 IsPrintable()	252
10.41.3.12 operator const std::vector< char > &()	252
10.41.3.13 operator=()	252
10.41.3.14 operator==([1/2]	252
10.41.3.15 operator==([2/2]	252
10.41.3.16 Print()	253
10.41.3.17 PrintASCII()	253
10.41.3.18 PrintASCIIXML()	253
10.41.3.19 PrintGroupLength()	253
10.41.3.20 PrintHex()	253
10.41.3.21 PrintHexXML()	253
10.41.3.22 PrintPNXML()	253
10.41.3.23 Read() [1/2]	254
10.41.3.24 Read() [2/2]	254
10.41.3.25 SetLength()	254
10.41.3.26 SetLengthOnly()	254
10.41.3.27 Write() [1/2]	254
10.41.3.28 Write() [2/2]	255
10.41.3.29 WriteBuffer()	255
10.42 gdcmm::CAPICryptoFactory Class Reference	255
10.42.1 Constructor & Destructor Documentation	256
10.42.1.1 CAPICryptoFactory()	256
10.42.2 Member Function Documentation	256
10.42.2.1 CreateCMSProvider()	256
10.43 gdcmm::CAPICryptographicMessageSyntax Class Reference	257
10.43.1 Constructor & Destructor Documentation	258
10.43.1.1 CAPICryptographicMessageSyntax()	258
10.43.1.2 ~CAPICryptographicMessageSyntax()	258
10.43.2 Member Function Documentation	258
10.43.2.1 Decrypt()	258
10.43.2.2 Encrypt()	259
10.43.2.3 GetCipherType()	259

10.43.2.4 GetInitialized()	259
10.43.2.5 ParseCertificateFile()	259
10.43.2.6 ParseKeyFile()	259
10.43.2.7 SetCipherType()	259
10.43.2.8 SetPassword()	260
10.44 gdcmm::network::CEchoRQ Class Reference	260
10.44.1 Detailed Description	261
10.44.2 Member Function Documentation	262
10.44.2.1 ConstructPDV()	262
10.44.3 Member Data Documentation	262
10.44.3.1 AffectedSOPClassUID	262
10.44.3.2 MessageID	262
10.45 gdcmm::network::CEchoRSP Class Reference	262
10.45.1 Detailed Description	263
10.45.2 Member Function Documentation	263
10.45.2.1 ConstructPDVByDataSet()	263
10.46 gdcmm::network::CFind Class Reference	263
10.46.1 Detailed Description	264
10.47 gdcmm::network::CFindCancelRQ Class Reference	264
10.47.1 Detailed Description	265
10.47.2 Member Function Documentation	265
10.47.2.1 ConstructPDVByDataSet()	265
10.48 gdcmm::network::CFindRQ Class Reference	265
10.48.1 Detailed Description	266
10.48.2 Member Function Documentation	266
10.48.2.1 ConstructPDV()	266
10.49 gdcmm::network::CFindRSP Class Reference	267
10.49.1 Detailed Description	268
10.49.2 Member Function Documentation	268
10.49.2.1 ConstructPDVByDataSet()	268
10.50 gdcmm::Cleaner Class Reference	268
10.50.1 Detailed Description	271
10.50.2 Member Typedef Documentation	271
10.50.2.1 CodedEntryData	271
10.50.3 Constructor & Destructor Documentation	271
10.50.3.1 Cleaner()	271
10.50.3.2 ~Cleaner()	271
10.50.4 Member Function Documentation	271
10.50.4.1 Clean()	271

10.50.4.2 Empty() [1/4]	272
10.50.4.3 Empty() [2/4]	272
10.50.4.4 Empty() [3/4]	272
10.50.4.5 Empty() [4/4]	272
10.50.4.6 EmptyWhenScrubFails()	272
10.50.4.7 GetFile()	272
10.50.4.8 New()	273
10.50.4.9 Preserve()	273
10.50.4.10 Remove() [1/4]	273
10.50.4.11 Remove() [2/4]	273
10.50.4.12 Remove() [3/4]	273
10.50.4.13 Remove() [4/4]	273
10.50.4.14 RemoveAllGroupLength()	274
10.50.4.15 RemoveAllIllegal()	274
10.50.4.16 RemoveAllMissingPrivateCreator()	274
10.50.4.17 RemoveMissingPrivateCreator()	274
10.50.4.18 ReplaceCodeMeaning()	274
10.50.4.19 Scrub() [1/4]	274
10.50.4.20 Scrub() [2/4]	274
10.50.4.21 Scrub() [3/4]	275
10.50.4.22 Scrub() [4/4]	275
10.50.4.23 SetFile()	275
10.51 gdcm::network::CMoveCancelRq Class Reference	275
10.51.1 Member Function Documentation	276
10.51.1.1 ConstructPDVByDataSet()	276
10.52 gdcm::network::CMoveRQ Class Reference	277
10.52.1 Detailed Description	278
10.52.2 Member Function Documentation	278
10.52.2.1 ConstructPDV()	278
10.53 gdcm::network::CMoveRSP Class Reference	278
10.53.1 Detailed Description	279
10.53.2 Member Function Documentation	279
10.53.2.1 ConstructPDVByDataSet()	279
10.54 gdcm::Codec Class Reference	280
10.54.1 Detailed Description	281
10.55 gdcm::Coder Class Reference	281
10.55.1 Detailed Description	282
10.55.2 Constructor & Destructor Documentation	282
10.55.2.1 ~Coder()	282

10.55.3 Member Function Documentation	282
10.55.3.1 CanCode()	282
10.55.3.2 Code()	282
10.55.3.3 InternalCode()	283
10.56 gdcmm::CodeString Class Reference	283
10.56.1 Detailed Description	284
10.56.2 Member Typedef Documentation	284
10.56.2.1 const_iterator	284
10.56.2.2 const_reference	284
10.56.2.3 const_reverse_iterator	284
10.56.2.4 difference_type	285
10.56.2.5 iterator	285
10.56.2.6 pointer	285
10.56.2.7 reference	285
10.56.2.8 reverse_iterator	285
10.56.2.9 size_type	285
10.56.2.10 value_type	285
10.56.3 Constructor & Destructor Documentation	285
10.56.3.1 CodeString() [1/4]	285
10.56.3.2 CodeString() [2/4]	286
10.56.3.3 CodeString() [3/4]	286
10.56.3.4 CodeString() [4/4]	286
10.56.4 Member Function Documentation	286
10.56.4.1 GetAsString()	286
10.56.4.2 IsValid()	286
10.56.4.3 Size()	286
10.56.4.4 TrimInternal()	286
10.56.5 Friends And Related Symbol Documentation	287
10.56.5.1 operator"!="	287
10.56.5.2 operator<<	287
10.56.5.3 operator==	287
10.57 gdcmm::Command Class Reference	287
10.57.1 Detailed Description	289
10.57.2 Constructor & Destructor Documentation	289
10.57.2.1 Command() [1/2]	289
10.57.2.2 Command() [2/2]	289
10.57.2.3 ~Command()	289
10.57.3 Member Function Documentation	290
10.57.3.1 Execute() [1/2]	290

10.57.3.2 Execute() [2/2]	290
10.57.3.3 operator=()	290
10.58 gdcmm::CommandDataSet Class Reference	291
10.58.1 Detailed Description	293
10.58.2 Constructor & Destructor Documentation	293
10.58.2.1 CommandDataSet()	293
10.58.2.2 ~CommandDataSet()	294
10.58.3 Member Function Documentation	294
10.58.3.1 Insert()	294
10.58.3.2 Read()	294
10.58.3.3 Replace()	294
10.58.3.4 Write()	294
10.58.4 Friends And Related Symbol Documentation	295
10.58.4.1 operator<<	295
10.59 gdcmm::network::CompositeMessageFactory Class Reference	295
10.59.1 Detailed Description	295
10.59.2 Member Function Documentation	296
10.59.2.1 ConstructCEchoRQ()	296
10.59.2.2 ConstructCFindRQ()	296
10.59.2.3 ConstructCMoveRQ()	296
10.59.2.4 ConstructCStoreRQ()	296
10.59.2.5 ConstructCStoreRSP()	296
10.60 gdcmm::CompositeNetworkFunctions Class Reference	296
10.60.1 Detailed Description	297
10.60.2 Member Typedef Documentation	297
10.60.2.1 KeyValuePairArrayType	297
10.60.2.2 KeyValuePairType	298
10.60.3 Member Function Documentation	298
10.60.3.1 CEcho()	298
10.60.3.2 CFind()	298
10.60.3.3 CMove()	299
10.60.3.4 ConstructQuery() [1/2]	299
10.60.3.5 ConstructQuery() [2/2]	300
10.60.3.6 CStore()	300
10.61 gdcmm::ConstCharWrapper Class Reference	301
10.61.1 Detailed Description	301
10.61.2 Constructor & Destructor Documentation	301
10.61.2.1 ConstCharWrapper()	301
10.61.3 Member Function Documentation	301

10.61.3.1 operator const char *()	301
10.62 gdcmm::CP246ExplicitDataElement Class Reference	302
10.62.1 Detailed Description	304
10.62.2 Member Function Documentation	304
10.62.2.1 GetLength()	304
10.62.2.2 Read()	305
10.62.2.3 ReadPreValue()	305
10.62.2.4 ReadValue()	305
10.62.2.5 ReadWithLength()	305
10.63 gdcmm::CryptoFactory Class Reference	305
10.63.1 Detailed Description	306
10.63.2 Member Enumeration Documentation	306
10.63.2.1 CryptoLib	306
10.63.3 Constructor & Destructor Documentation	307
10.63.3.1 CryptoFactory() [1/2]	307
10.63.3.2 CryptoFactory() [2/2]	307
10.63.3.3 ~CryptoFactory()	307
10.63.4 Member Function Documentation	307
10.63.4.1 CreateCMSProvider()	307
10.63.4.2 GetFactoryInstance()	307
10.64 gdcmm::CryptographicMessageSyntax Class Reference	308
10.64.1 Member Enumeration Documentation	308
10.64.1.1 CipherTypes	308
10.64.2 Constructor & Destructor Documentation	309
10.64.2.1 CryptographicMessageSyntax() [1/2]	309
10.64.2.2 ~CryptographicMessageSyntax()	309
10.64.2.3 CryptographicMessageSyntax() [2/2]	309
10.64.3 Member Function Documentation	309
10.64.3.1 Decrypt()	309
10.64.3.2 Encrypt()	310
10.64.3.3 GetCipherType()	310
10.64.3.4 operator=()	310
10.64.3.5 ParseCertificateFile()	310
10.64.3.6 ParseKeyFile()	310
10.64.3.7 SetCipherType()	311
10.64.3.8 SetPassword()	311
10.65 gdcmm::CSAElement Class Reference	311
10.65.1 Detailed Description	313
10.65.2 Member Typedef Documentation	313

10.65.2.1 DataPtr	313
10.65.3 Constructor & Destructor Documentation	313
10.65.3.1 CSAElement() [1/2]	313
10.65.3.2 CSAElement() [2/2]	313
10.65.4 Member Function Documentation	314
10.65.4.1 GetByteValue()	314
10.65.4.2 GetKey()	314
10.65.4.3 GetName()	314
10.65.4.4 GetNoOfItems()	314
10.65.4.5 GetSyngoDT()	315
10.65.4.6 GetValue() [1/2]	315
10.65.4.7 GetValue() [2/2]	315
10.65.4.8 GetVM()	315
10.65.4.9 GetVR()	315
10.65.4.10 IsEmpty()	316
10.65.4.11 operator<()	316
10.65.4.12 operator=()	316
10.65.4.13 operator==()	316
10.65.4.14 SetByteValue()	316
10.65.4.15 SetKey()	317
10.65.4.16 SetName()	317
10.65.4.17 SetNoOfItems()	317
10.65.4.18 SetSyngoDT()	317
10.65.4.19 SetValue()	317
10.65.4.20 SetVM()	317
10.65.4.21 SetVR()	318
10.65.5 Friends And Related Symbol Documentation	318
10.65.5.1 operator<<	318
10.65.6 Member Data Documentation	318
10.65.6.1 DataField	318
10.65.6.2 KeyField	318
10.65.6.3 NameField	318
10.65.6.4 NoOfItemsField	318
10.65.6.5 SyngoDTField	319
10.65.6.6 ValueMultiplicityField	319
10.65.6.7 VRField	319
10.66 gdcM::CSAHeader Class Reference	319
10.66.1 Detailed Description	320
10.66.2 Member Enumeration Documentation	321

10.66.2.1 CSAHeaderType	321
10.66.3 Constructor & Destructor Documentation	321
10.66.3.1 CSAHeader()	321
10.66.3.2 ~CSAHeader()	322
10.66.4 Member Function Documentation	322
10.66.4.1 FindCSAElementByName()	322
10.66.4.2 GetCSADataInfo()	322
10.66.4.3 GetCSAEEnd()	322
10.66.4.4 GetCSAElementByName()	322
10.66.4.5 GetCSAImageHeaderInfoTag()	323
10.66.4.6 GetCSASeriesHeaderInfoTag()	323
10.66.4.7 GetDataSet()	323
10.66.4.8 GetFormat()	323
10.66.4.9 GetInterfile()	323
10.66.4.10 GetMrProtocol()	324
10.66.4.11 LoadFromDataElement()	324
10.66.4.12 Print()	324
10.66.5 Friends And Related Symbol Documentation	324
10.66.5.1 operator<<	324
10.67 gdcmm::CSAHeaderDict Class Reference	325
10.67.1 Detailed Description	325
10.67.2 Member Typedef Documentation	325
10.67.2.1 ConstIterator	325
10.67.2.2 Iterator	326
10.67.2.3 MapCSAHeaderDictEntry	326
10.67.3 Constructor & Destructor Documentation	326
10.67.3.1 CSAHeaderDict() [1/2]	326
10.67.3.2 CSAHeaderDict() [2/2]	326
10.67.4 Member Function Documentation	326
10.67.4.1 AddCSAHeaderDictEntry()	326
10.67.4.2 Begin()	326
10.67.4.3 End()	326
10.67.4.4 GetCSAHeaderDictEntry()	327
10.67.4.5 IsEmpty()	327
10.67.4.6 LoadDefault()	327
10.67.4.7 operator=()	327
10.67.5 Friends And Related Symbol Documentation	327
10.67.5.1 Dicts	327
10.67.5.2 operator<<	327

10.68 gdcmm::CSAHeaderDictEntry Class Reference	328
10.68.1 Detailed Description	328
10.68.2 Constructor & Destructor Documentation	329
10.68.2.1 CSAHeaderDictEntry()	329
10.68.3 Member Function Documentation	329
10.68.3.1 GetDescription()	329
10.68.3.2 GetName()	329
10.68.3.3 GetVM()	329
10.68.3.4 GetVR()	329
10.68.3.5 operator<()	330
10.68.3.6 SetDescription()	330
10.68.3.7 SetName()	330
10.68.3.8 SetVM()	330
10.68.3.9 SetVR()	330
10.68.4 Friends And Related Symbol Documentation	330
10.68.4.1 operator<<	330
10.69 gdcmm::CSAHeaderDictException Class Reference	331
10.70 gdcmm::network::CStoreRQ Class Reference	331
10.70.1 Detailed Description	332
10.70.2 Member Function Documentation	333
10.70.2.1 ConstructPDV()	333
10.71 gdcmm::network::CStoreRSP Class Reference	333
10.71.1 Detailed Description	334
10.71.2 Member Function Documentation	334
10.71.2.1 ConstructPDV()	334
10.72 gdcmm::Curve Class Reference	334
10.72.1 Detailed Description	336
10.72.2 Constructor & Destructor Documentation	336
10.72.2.1 Curve() [1/2]	336
10.72.2.2 ~Curve()	336
10.72.2.3 Curve() [2/2]	336
10.72.3 Member Function Documentation	337
10.72.3.1 Decode()	337
10.72.3.2 GetAsPoints()	337
10.72.3.3 GetCurveDataDescriptor()	337
10.72.3.4 GetDataValueRepresentation()	337
10.72.3.5 GetDimensions()	337
10.72.3.6 GetGroup()	337
10.72.3.7 GetNumberOfCurves()	337

10.72.3.8 GetNumberOfPoints()	337
10.72.3.9 GetTypeInfoData()	338
10.72.3.10 GetTypeInfoDataDescription()	338
10.72.3.11 IsEmpty()	338
10.72.3.12 Print()	338
10.72.3.13 SetCoordinateStartValue()	338
10.72.3.14 SetCoordinateStepValue()	338
10.72.3.15 SetCurve()	338
10.72.3.16 SetCurveDataDescriptor()	338
10.72.3.17 SetCurveDescription()	339
10.72.3.18 SetDataValueRepresentation()	339
10.72.3.19 SetDimensions()	339
10.72.3.20 SetGroup()	339
10.72.3.21 SetNumberOfPoints()	339
10.72.3.22 SetTypeInfoData()	339
10.72.3.23 Update()	339
10.73 gdcmm::DataElement Class Reference	340
10.73.1 Detailed Description	342
10.73.2 Member Typedef Documentation	343
10.73.2.1 ValuePtr	343
10.73.3 Constructor & Destructor Documentation	343
10.73.3.1 DataElement() [1/2]	343
10.73.3.2 DataElement() [2/2]	343
10.73.4 Member Function Documentation	343
10.73.4.1 Clear()	343
10.73.4.2 Empty()	343
10.73.4.3 GetByteValue()	344
10.73.4.4 GetLength()	344
10.73.4.5 GetSequenceOfFragments() [1/2]	344
10.73.4.6 GetSequenceOfFragments() [2/2]	344
10.73.4.7 GetTag() [1/2]	345
10.73.4.8 GetTag() [2/2]	345
10.73.4.9 GetValue() [1/2]	345
10.73.4.10 GetValue() [2/2]	345
10.73.4.11 GetValueAsSQ()	346
10.73.4.12 GetVL() [1/2]	346
10.73.4.13 GetVL() [2/2]	346
10.73.4.14 GetVR()	347
10.73.4.15 IsEmpty()	347

10.73.4.16	IsUndefinedLength()	347
10.73.4.17	operator<()	348
10.73.4.18	operator=()	348
10.73.4.19	operator==()	348
10.73.4.20	Read()	348
10.73.4.21	ReadOrSkip()	348
10.73.4.22	ReadPreValue()	349
10.73.4.23	ReadValue()	349
10.73.4.24	ReadValueWithLength()	349
10.73.4.25	ReadWithLength()	349
10.73.4.26	SetByteValue()	350
10.73.4.27	SetTag()	350
10.73.4.28	SetValue()	351
10.73.4.29	SetValueFieldLength()	351
10.73.4.30	SetVL()	351
10.73.4.31	SetVLToUndefined()	351
10.73.4.32	SetVR()	352
10.73.4.33	Write()	352
10.73.5	Friends And Related Symbol Documentation	352
10.73.5.1	operator<<	352
10.73.6	Member Data Documentation	353
10.73.6.1	TagField	353
10.73.6.2	ValueField	353
10.73.6.3	ValueLengthField	353
10.73.6.4	VRField	353
10.74	gdcm::DataElementException Class Reference	354
10.75	gdcm::DataEvent Class Reference	354
10.75.1	Detailed Description	356
10.75.2	Member Typedef Documentation	356
10.75.2.1	Self	356
10.75.2.2	Superclass	356
10.75.3	Constructor & Destructor Documentation	356
10.75.3.1	DataEvent() [1/2]	356
10.75.3.2	~DataEvent()	357
10.75.3.3	DataEvent() [2/2]	357
10.75.4	Member Function Documentation	357
10.75.4.1	CheckEvent()	357
10.75.4.2	GetData()	357
10.75.4.3	GetDataLength()	357

10.75.4.4 GetEventName()	357
10.75.4.5 MakeObject()	357
10.75.4.6 operator=()	358
10.75.4.7 SetData()	358
10.76 gdcm::DataSet Class Reference	358
10.76.1 Detailed Description	360
10.76.2 Member Typedef Documentation	361
10.76.2.1 ConstIterator	361
10.76.2.2 DataElementSet	361
10.76.2.3 Iterator	361
10.76.2.4 SizeType	361
10.76.3 Member Function Documentation	362
10.76.3.1 Begin() [1/2]	362
10.76.3.2 Begin() [2/2]	362
10.76.3.3 Clear()	362
10.76.3.4 ComputeDataElement()	362
10.76.3.5 ComputeGroupLength()	362
10.76.3.6 End() [1/2]	362
10.76.3.7 End() [2/2]	363
10.76.3.8 FindDataElement() [1/2]	363
10.76.3.9 FindDataElement() [2/2]	363
10.76.3.10 FindNextDataElement()	363
10.76.3.11 GetDataElement() [1/2]	364
10.76.3.12 GetDataElement() [2/2]	364
10.76.3.13 GetDEEnd()	364
10.76.3.14 GetDES() [1/2]	364
10.76.3.15 GetDES() [2/2]	365
10.76.3.16 GetLength()	365
10.76.3.17 GetMediaStorage()	365
10.76.3.18 GetPrivateCreator()	365
10.76.3.19 GetPrivateTag()	365
10.76.3.20 Insert()	366
10.76.3.21 InsertDataElement()	366
10.76.3.22 IsEmpty()	366
10.76.3.23 operator>()	366
10.76.3.24 operator=()	367
10.76.3.25 operator[]()	367
10.76.3.26 Print()	367
10.76.3.27 Read()	367

10.76.3.28 ReadNested()	367
10.76.3.29 ReadSelectedPrivateTags()	367
10.76.3.30 ReadSelectedPrivateTagsWithLength()	368
10.76.3.31 ReadSelectedTags()	368
10.76.3.32 ReadSelectedTagsWithLength()	368
10.76.3.33 ReadUpToTag()	368
10.76.3.34 ReadUpToTagWithLength()	368
10.76.3.35 ReadWithLength()	369
10.76.3.36 Remove()	369
10.76.3.37 Replace()	369
10.76.3.38 ReplaceEmpty()	369
10.76.3.39 Size()	370
10.76.3.40 Write()	370
10.76.4 Friends And Related Symbol Documentation	370
10.76.4.1 CSAHeader	370
10.76.4.2 operator<<	370
10.77 gdcm::DataSetEvent Class Reference	371
10.77.1 Detailed Description	372
10.77.2 Member Typedef Documentation	372
10.77.2.1 Self	372
10.77.2.2 Superclass	372
10.77.3 Constructor & Destructor Documentation	373
10.77.3.1 DataSetEvent() [1/2]	373
10.77.3.2 ~DataSetEvent()	373
10.77.3.3 DataSetEvent() [2/2]	373
10.77.4 Member Function Documentation	373
10.77.4.1 CheckEvent()	373
10.77.4.2 GetDataSet()	373
10.77.4.3 GetEventName()	373
10.77.4.4 MakeObject()	374
10.77.4.5 operator=()	374
10.77.5 Member Data Documentation	374
10.77.5.1 m_DataSet	374
10.78 gdcm::DataSetHelper Class Reference	374
10.78.1 Detailed Description	374
10.78.2 Member Function Documentation	375
10.78.2.1 ComputeVR()	375
10.79 gdcm::Decoder Class Reference	375
10.79.1 Detailed Description	376

10.79.2 Constructor & Destructor Documentation	376
10.79.2.1 ~Decoder()	376
10.79.3 Member Function Documentation	376
10.79.3.1 CanDecode()	376
10.79.3.2 Decode()	376
10.79.3.3 DecodeByStreams()	377
10.80 gdcm::DefinedTerms Class Reference	377
10.80.1 Detailed Description	377
10.80.2 Constructor & Destructor Documentation	377
10.80.2.1 DefinedTerms()	377
10.81 gdcm::Defs Class Reference	378
10.81.1 Detailed Description	378
10.81.2 Constructor & Destructor Documentation	379
10.81.2.1 Defs() [1/2]	379
10.81.2.2 ~Defs()	379
10.81.2.3 Defs() [2/2]	379
10.81.3 Member Function Documentation	379
10.81.3.1 GetIODFromFile()	379
10.81.3.2 GetIODNameFromMediaStorage()	379
10.81.3.3 GetIODs() [1/2]	379
10.81.3.4 GetIODs() [2/2]	380
10.81.3.5 GetMacros() [1/2]	380
10.81.3.6 GetMacros() [2/2]	380
10.81.3.7 GetModules() [1/2]	380
10.81.3.8 GetModules() [2/2]	380
10.81.3.9 GetTypeFromTag()	380
10.81.3.10 IsEmpty()	381
10.81.3.11 LoadDefaults()	381
10.81.3.12 LoadFromFile()	381
10.81.3.13 operator=()	381
10.81.3.14 Verify() [1/2]	381
10.81.3.15 Verify() [2/2]	381
10.81.4 Friends And Related Symbol Documentation	381
10.81.4.1 Global	381
10.82 gdcm::DeltaEncodingCodec Class Reference	382
10.82.1 Detailed Description	384
10.82.2 Constructor & Destructor Documentation	385
10.82.2.1 DeltaEncodingCodec()	385
10.82.2.2 ~DeltaEncodingCodec()	385

10.82.3 Member Function Documentation	385
10.82.3.1 CanDecode()	385
10.82.3.2 Decode() [1/2]	385
10.82.3.3 Decode() [2/2]	385
10.83 gdcmm::DICOMDIR Class Reference	385
10.83.1 Detailed Description	386
10.83.2 Constructor & Destructor Documentation	386
10.83.2.1 DICOMDIR() [1/2]	386
10.83.2.2 DICOMDIR() [2/2]	386
10.84 gdcmm::DICOMDIRGenerator Class Reference	386
10.84.1 Detailed Description	387
10.84.2 Member Typedef Documentation	388
10.84.2.1 FilenamesType	388
10.84.2.2 FilenameType	388
10.84.3 Constructor & Destructor Documentation	388
10.84.3.1 DICOMDIRGenerator()	388
10.84.3.2 ~DICOMDIRGenerator()	388
10.84.4 Member Function Documentation	388
10.84.4.1 AddImageDirectoryRecord()	388
10.84.4.2 AddPatientDirectoryRecord()	388
10.84.4.3 AddSeriesDirectoryRecord()	388
10.84.4.4 AddStudyDirectoryRecord()	388
10.84.4.5 Generate()	389
10.84.4.6 GetFile()	389
10.84.4.7 GetScanner()	389
10.84.4.8 SetDescriptor()	389
10.84.4.9 SetFile()	389
10.84.4.10 SetFilenames()	390
10.84.4.11 SetRootDirectory()	390
10.85 gdcmm::Dict Class Reference	390
10.85.1 Detailed Description	391
10.85.2 Member Typedef Documentation	391
10.85.2.1 ConstIterator	391
10.85.2.2 Iterator	391
10.85.2.3 MapDictEntry	391
10.85.3 Constructor & Destructor Documentation	391
10.85.3.1 Dict() [1/2]	391
10.85.3.2 Dict() [2/2]	392
10.85.4 Member Function Documentation	392

10.85.4.1 AddDictEntry()	392
10.85.4.2 Begin()	392
10.85.4.3 End()	392
10.85.4.4 GetDictEntry()	392
10.85.4.5 GetDictEntryByKeyword()	393
10.85.4.6 GetDictEntryByName()	393
10.85.4.7 GetKeywordFromTag()	393
10.85.4.8 IsEmpty()	393
10.85.4.9 LoadDefault()	393
10.85.4.10 operator=()	394
10.85.5 Friends And Related Symbol Documentation	394
10.85.5.1 Dicts	394
10.85.5.2 operator<<	394
10.86 gdcm::DictConverter Class Reference	394
10.86.1 Detailed Description	395
10.86.2 Member Enumeration Documentation	395
10.86.2.1 OutputTypes	395
10.86.3 Constructor & Destructor Documentation	396
10.86.3.1 DictConverter()	396
10.86.3.2 ~DictConverter()	396
10.86.4 Member Function Documentation	396
10.86.4.1 AddGroupLength()	396
10.86.4.2 Convert()	396
10.86.4.3 ConvertToCXX()	396
10.86.4.4 ConvertToXML()	396
10.86.4.5 GetDictName()	397
10.86.4.6 GetInputFilename()	397
10.86.4.7 GetOutputFilename()	397
10.86.4.8 GetOutputType()	397
10.86.4.9 Readuint16()	397
10.86.4.10 ReadVM()	397
10.86.4.11 ReadVR()	397
10.86.4.12 SetDictName()	397
10.86.4.13 SetInputFileName()	398
10.86.4.14 SetOutputFileName()	398
10.86.4.15 SetOutputType()	398
10.86.4.16 WriteFooter()	398
10.86.4.17 WriteHeader()	398
10.87 gdcm::DictEntry Class Reference	398

10.87.1 Detailed Description	399
10.87.2 Constructor & Destructor Documentation	400
10.87.2.1 DictEntry()	400
10.87.3 Member Function Documentation	400
10.87.3.1 GetKeyword()	400
10.87.3.2 GetName()	400
10.87.3.3 GetRetired()	400
10.87.3.4 GetVM()	400
10.87.3.5 GetVR()	401
10.87.3.6 IsUnique()	401
10.87.3.7 SetElementXX()	401
10.87.3.8 SetGroupXX()	401
10.87.3.9 SetKeyword()	401
10.87.3.10 SetName()	401
10.87.3.11 SetRetired()	402
10.87.3.12 SetVM()	402
10.87.3.13 SetVR()	402
10.87.4 Friends And Related Symbol Documentation	402
10.87.4.1 Dict	402
10.87.4.2 operator<<	402
10.88 gdcmm::DictPrinter Class Reference	403
10.88.1 Detailed Description	405
10.88.2 Constructor & Destructor Documentation	405
10.88.2.1 DictPrinter()	405
10.88.2.2 ~DictPrinter()	405
10.88.3 Member Function Documentation	405
10.88.3.1 Print()	405
10.88.3.2 PrintDataElement2()	405
10.88.3.3 PrintDataSet2()	405
10.89 gdcmm::Dicts Class Reference	406
10.89.1 Detailed Description	407
10.89.2 Member Enumeration Documentation	407
10.89.2.1 ConstructorType	407
10.89.3 Constructor & Destructor Documentation	407
10.89.3.1 Dicts() [1/2]	407
10.89.3.2 ~Dicts()	407
10.89.3.3 Dicts() [2/2]	407
10.89.4 Member Function Documentation	408
10.89.4.1 GetConstructorString()	408

10.89.4.2 GetCSAHeaderDict()	408
10.89.4.3 GetDictEntry() [1/2]	408
10.89.4.4 GetDictEntry() [2/2]	408
10.89.4.5 GetPrivateDict() [1/2]	408
10.89.4.6 GetPrivateDict() [2/2]	409
10.89.4.7 GetPublicDict()	409
10.89.4.8 IsEmpty()	409
10.89.4.9 LoadDefaults()	409
10.89.4.10 operator=()	409
10.89.5 Friends And Related Symbol Documentation	409
10.89.5.1 Global	409
10.89.5.2 operator<<	410
10.90 gdcmm::network::DIMSE Class Reference	410
10.90.1 Detailed Description	410
10.90.2 Member Enumeration Documentation	411
10.90.2.1 CommandTypes	411
10.91 gdcmm::DirectionCosines Class Reference	411
10.91.1 Detailed Description	412
10.91.2 Constructor & Destructor Documentation	412
10.91.2.1 DirectionCosines() [1/2]	412
10.91.2.2 DirectionCosines() [2/2]	413
10.91.2.3 ~DirectionCosines()	413
10.91.3 Member Function Documentation	413
10.91.3.1 ComputeDistAlongNormal()	413
10.91.3.2 Cross()	413
10.91.3.3 CrossDot()	413
10.91.3.4 Dot() [1/2]	413
10.91.3.5 Dot() [2/2]	414
10.91.3.6 IsValid()	414
10.91.3.7 Norm()	414
10.91.3.8 Normalize() [1/2]	414
10.91.3.9 Normalize() [2/2]	414
10.91.3.10 operator const double *()	414
10.91.3.11 Print()	414
10.91.3.12 SetFromString()	415
10.92 gdcmm::Directory Class Reference	415
10.92.1 Detailed Description	416
10.92.2 Member Typedef Documentation	416
10.92.2.1 FilenamesType	416

10.92.2.2 FilenameType	416
10.92.3 Constructor & Destructor Documentation	416
10.92.3.1 Directory()	416
10.92.3.2 ~Directory()	417
10.92.4 Member Function Documentation	417
10.92.4.1 Explore()	417
10.92.4.2 GetDirectories()	417
10.92.4.3 GetFileNames()	417
10.92.4.4 GetToplevel()	417
10.92.4.5 Load()	418
10.92.4.6 Print()	418
10.92.5 Friends And Related Symbol Documentation	418
10.92.5.1 operator<<	418
10.93 gdcmm::DirectoryHelper Class Reference	419
10.93.1 Detailed Description	419
10.93.2 Member Function Documentation	419
10.93.2.1 GetCTImageSeriesUIDs()	419
10.93.2.2 GetFileNamesFromSeriesUIDs()	419
10.93.2.3 GetFrameOfReference()	420
10.93.2.4 GetMRImageSeriesUIDs()	420
10.93.2.5 GetRTStructSeriesUIDs()	420
10.93.2.6 GetSeriesUIDsBySOPClassUID()	420
10.93.2.7 GetSOPClassUID()	420
10.93.2.8 GetStringValueFromTag()	420
10.93.2.9 LoadImageFromFiles()	420
10.93.2.10 RetrieveSOPInstanceUIDFromIndex()	421
10.93.2.11 RetrieveSOPInstanceUIDFromZPosition()	421
10.94 gdcmm::DPath Class Reference	421
10.94.1 Detailed Description	422
10.94.2 Constructor & Destructor Documentation	422
10.94.2.1 DPath()	422
10.94.2.2 ~DPath()	422
10.94.3 Member Function Documentation	422
10.94.3.1 ConstructFromString()	422
10.94.3.2 IsValid()	422
10.94.3.3 Match()	422
10.94.3.4 operator<()	423
10.94.3.5 Print()	423
10.94.4 Friends And Related Symbol Documentation	423

10.94.4.1 operator<<	423
10.95 gdcM::DummyValueGenerator Class Reference	423
10.95.1 Detailed Description	423
10.95.2 Member Function Documentation	424
10.95.2.1 Generate()	424
10.96 gdcM::Dumper Class Reference	424
10.96.1 Detailed Description	426
10.96.2 Constructor & Destructor Documentation	426
10.96.2.1 Dumper()	426
10.96.2.2 ~Dumper()	426
10.97 gdcM::Element< TVR, TVM > Class Template Reference	427
10.97.1 Detailed Description	429
10.97.2 Member Typedef Documentation	429
10.97.2.1 Type	429
10.97.3 Member Function Documentation	429
10.97.3.1 GetAsDataElement()	429
10.97.3.2 GetLength()	430
10.97.3.3 GetValue() [1/2]	430
10.97.3.4 GetValue() [2/2]	430
10.97.3.5 GetValues()	430
10.97.3.6 GetVM()	430
10.97.3.7 GetVR()	431
10.97.3.8 operator[]()	431
10.97.3.9 Print()	431
10.97.3.10 Read()	431
10.97.3.11 Set()	431
10.97.3.12 SetFromDataElement()	432
10.97.3.13 SetNoSwap()	432
10.97.3.14 SetValue()	432
10.97.3.15 Write()	432
10.97.4 Member Data Documentation	433
10.97.4.1 Internal	433
10.98 gdcM::Element< TVR, VM::VM1_2 > Class Template Reference	433
10.98.1 Member Typedef Documentation	436
10.98.1.1 Parent	436
10.98.1.2 Type	436
10.98.2 Member Function Documentation	436
10.98.2.1 GetAsDataElement()	436
10.98.2.2 GetLength()	436

10.98.2.3 GetValue()	436
10.98.2.4 GetValues()	436
10.98.2.5 GetVM()	436
10.98.2.6 GetVR()	437
10.98.2.7 operator[]()	437
10.98.2.8 Print()	437
10.98.2.9 Read()	437
10.98.2.10 Set()	437
10.98.2.11 SetFromDataElement()	437
10.98.2.12 SetLength()	437
10.98.2.13 SetNoSwap()	437
10.98.2.14 SetValue()	438
10.98.2.15 Write()	438
10.98.3 Member Data Documentation	438
10.98.3.1 Internal	438
10.99 gdcM::Element< TVR, VM::VM2_2n > Class Template Reference	438
10.99.1 Member Typedef Documentation	441
10.99.1.1 Parent	441
10.99.1.2 Type	441
10.99.2 Member Function Documentation	441
10.99.2.1 GetAsDataElement()	441
10.99.2.2 GetLength()	441
10.99.2.3 GetValue()	441
10.99.2.4 GetValues()	441
10.99.2.5 GetVM()	441
10.99.2.6 GetVR()	442
10.99.2.7 operator[]()	442
10.99.2.8 Print()	442
10.99.2.9 Read()	442
10.99.2.10 Set()	442
10.99.2.11 SetFromDataElement()	442
10.99.2.12 SetLength()	442
10.99.2.13 SetNoSwap()	442
10.99.2.14 SetValue()	443
10.99.2.15 Write()	443
10.99.3 Member Data Documentation	443
10.99.3.1 Internal	443
10.100 gdcM::Element< TVR, VM::VM3_3n > Class Template Reference	443
10.100.1 Member Typedef Documentation	446

10.100.1.1 Parent	446
10.100.1.2 Type	446
10.100.2 Member Function Documentation	446
10.100.2.1 GetAsDataElement()	446
10.100.2.2 GetLength()	446
10.100.2.3 GetValue()	446
10.100.2.4 GetValues()	446
10.100.2.5 GetVM()	446
10.100.2.6 GetVR()	447
10.100.2.7 operator[]()	447
10.100.2.8 Print()	447
10.100.2.9 Read()	447
10.100.2.10 Set()	447
10.100.2.11 SetFromDataElement()	447
10.100.2.12 SetLength()	447
10.100.2.13 SetNoSwap()	447
10.100.2.14 SetValue()	448
10.100.2.15 Write()	448
10.100.3 Member Data Documentation	448
10.100.3.1 Internal	448
10.101 gdcM::Element< TVR, VM::VM3_4 > Class Template Reference	448
10.101.1 Member Typedef Documentation	451
10.101.1.1 Parent	451
10.101.1.2 Type	451
10.101.2 Member Function Documentation	451
10.101.2.1 GetAsDataElement()	451
10.101.2.2 GetLength()	451
10.101.2.3 GetValue()	451
10.101.2.4 GetValues()	451
10.101.2.5 GetVM()	451
10.101.2.6 GetVR()	452
10.101.2.7 operator[]()	452
10.101.2.8 Print()	452
10.101.2.9 Read()	452
10.101.2.10 Set()	452
10.101.2.11 SetFromDataElement()	452
10.101.2.12 SetLength()	452
10.101.2.13 SetNoSwap()	452
10.101.2.14 SetValue()	453

10.101.2.15 Write()	453
10.101.3 Member Data Documentation	453
10.101.3.1 Internal	453
10.102 gdcmm::Element< VR::AS, VM::VM5 > Class Reference	453
10.102.1 Member Typedef Documentation	455
10.102.1.1 Type	455
10.102.2 Member Function Documentation	455
10.102.2.1 GetAsDataElement()	455
10.102.2.2 GetLength()	455
10.102.2.3 GetValue()	455
10.102.2.4 GetValues()	455
10.102.2.5 GetVM()	456
10.102.2.6 GetVR()	456
10.102.2.7 operator[]()	456
10.102.2.8 Print()	456
10.102.2.9 Read()	456
10.102.2.10 Set()	456
10.102.2.11 SetFromDataElement()	456
10.102.2.12 SetNoSwap()	456
10.102.2.13 SetValue()	457
10.102.2.14 Write()	457
10.102.3 Member Data Documentation	457
10.102.3.1 Internal	457
10.103 gdcmm::Element< VR::OB, VM::VM1 > Class Reference	457
10.103.1 Member Typedef Documentation	460
10.103.1.1 Type	460
10.103.2 Member Function Documentation	460
10.103.2.1 GetAsDataElement()	460
10.103.2.2 GetLength()	460
10.103.2.3 GetValue()	460
10.103.2.4 GetValues()	460
10.103.2.5 GetVM()	460
10.103.2.6 GetVR()	460
10.103.2.7 operator[]()	461
10.103.2.8 Print()	461
10.103.2.9 Read()	461
10.103.2.10 Set()	461
10.103.2.11 SetFromDataElement()	461
10.103.2.12 SetNoSwap()	461

10.103.2.13 SetValue()	461
10.103.2.14 Write()	461
10.103.3 Member Data Documentation	462
10.103.3.1 Internal	462
10.104 gdcM::Element< VR::OW, VM::VM1 > Class Reference	462
10.104.1 Member Typedef Documentation	465
10.104.1.1 Type	465
10.104.2 Member Function Documentation	465
10.104.2.1 GetAsDataElement()	465
10.104.2.2 GetLength()	465
10.104.2.3 GetValue()	465
10.104.2.4 GetValues()	465
10.104.2.5 GetVM()	465
10.104.2.6 GetVR()	465
10.104.2.7 operator[]()	466
10.104.2.8 Print()	466
10.104.2.9 Read()	466
10.104.2.10 Set()	466
10.104.2.11 SetFromDataElement()	466
10.104.2.12 SetNoSwap()	466
10.104.2.13 SetValue()	466
10.104.2.14 Write()	466
10.104.3 Member Data Documentation	467
10.104.3.1 Internal	467
10.105 gdcM::ElementDisableCombinations< TVR, TVM > Class Template Reference	467
10.105.1 Detailed Description	467
10.106 gdcM::ElementDisableCombinations< VR::OB, VM::VM1_n > Class Reference	468
10.107 gdcM::ElementDisableCombinations< VR::OW, VM::VM1_n > Class Reference	469
10.108 gdcM::EmptyMaskGenerator Class Reference	470
10.108.1 Detailed Description	470
10.108.2 Member Enumeration Documentation	471
10.108.2.1 SOPClassUIDMode	471
10.108.3 Constructor & Destructor Documentation	471
10.108.3.1 EmptyMaskGenerator()	471
10.108.3.2 ~EmptyMaskGenerator()	471
10.108.4 Member Function Documentation	471
10.108.4.1 Execute()	471
10.108.4.2 SetInputDirectory()	471
10.108.4.3 SetOutputDirectory()	472

10.108.4.4 SetSOPClassUIDMode()	472
10.109 gdcM::EncapsulatedDocument Class Reference	472
10.109.1 Detailed Description	472
10.109.2 Constructor & Destructor Documentation	473
10.109.2.1 EncapsulatedDocument()	473
10.110 gdcM::EncodingImplementation< T > Class Template Reference	473
10.110.1 Detailed Description	473
10.111 gdcM::EncodingImplementation< VR::VRASCII > Class Reference	474
10.111.1 Member Function Documentation	475
10.111.1.1 Read()	475
10.111.1.2 ReadComputeLength()	475
10.111.1.3 ReadNoSwap()	475
10.111.1.4 Write() [1/2]	476
10.111.1.5 Write() [2/2]	476
10.112 gdcM::EncodingImplementation< VR::VRBINARY > Class Reference	476
10.112.1 Member Function Documentation	477
10.112.1.1 Read()	477
10.112.1.2 ReadComputeLength()	477
10.112.1.3 ReadNoSwap()	478
10.112.1.4 Write()	478
10.113 gdcM::EndEvent Class Reference	478
10.114 gdcM::EnumeratedValues Class Reference	479
10.114.1 Detailed Description	480
10.114.2 Constructor & Destructor Documentation	480
10.114.2.1 EnumeratedValues()	480
10.115 gdcM::EquipmentManufacturer Class Reference	480
10.115.1 Detailed Description	481
10.115.2 Member Enumeration Documentation	481
10.115.2.1 Type	481
10.115.3 Member Function Documentation	481
10.115.3.1 Compute()	481
10.115.3.2 ToString()	481
10.116 gdcM::Event Class Reference	482
10.116.1 Detailed Description	483
10.116.2 Constructor & Destructor Documentation	483
10.116.2.1 Event() [1/2]	483
10.116.2.2 ~Event()	483
10.116.2.3 Event() [2/2]	483
10.116.3 Member Function Documentation	483

10.116.3.1 CheckEvent()	483
10.116.3.2 GetEventName()	484
10.116.3.3 MakeObject()	484
10.116.3.4 operator=()	484
10.116.3.5 Print()	484
10.117 gdcm::Exception Class Reference	485
10.117.1 Detailed Description	486
10.117.2 Constructor & Destructor Documentation	486
10.117.2.1 Exception()	486
10.117.2.2 ~Exception()	486
10.117.3 Member Function Documentation	486
10.117.3.1 GetDescription()	486
10.117.3.2 what()	487
10.118 gdcm::ExitEvent Class Reference	487
10.119 gdcm::ExplicitDataElement Class Reference	488
10.119.1 Detailed Description	491
10.119.2 Member Function Documentation	491
10.119.2.1 GetLength()	491
10.119.2.2 Read()	491
10.119.2.3 ReadPreValue()	492
10.119.2.4 ReadValue()	492
10.119.2.5 ReadWithLength()	492
10.119.2.6 Write()	492
10.120 gdcm::ExplicitImplicitDataElement Class Reference	492
10.120.1 Detailed Description	495
10.120.2 Member Function Documentation	495
10.120.2.1 GetLength()	495
10.120.2.2 Read()	495
10.120.2.3 ReadPreValue()	496
10.120.2.4 ReadValue()	496
10.120.2.5 ReadWithLength()	496
10.121 gdcm::Fiducials Class Reference	496
10.121.1 Detailed Description	496
10.121.2 Constructor & Destructor Documentation	497
10.121.2.1 Fiducials()	497
10.122 gdcm::File Class Reference	497
10.122.1 Detailed Description	499
10.122.2 Constructor & Destructor Documentation	499
10.122.2.1 File()	499

10.122.2.2 ~File()	499
10.122.3 Member Function Documentation	499
10.122.3.1 GetDataSet() [1/2]	499
10.122.3.2 GetDataSet() [2/2]	500
10.122.3.3 GetHeader() [1/2]	500
10.122.3.4 GetHeader() [2/2]	500
10.122.3.5 Read()	500
10.122.3.6 SetDataSet()	501
10.122.3.7 SetHeader()	501
10.122.3.8 Write()	501
10.122.4 Friends And Related Symbol Documentation	501
10.122.4.1 operator<<	501
10.123 gdcm::FileAnonymizer Class Reference	502
10.123.1 Detailed Description	504
10.123.2 Constructor & Destructor Documentation	504
10.123.2.1 FileAnonymizer()	504
10.123.2.2 ~FileAnonymizer()	504
10.123.3 Member Function Documentation	504
10.123.3.1 Empty()	504
10.123.3.2 Remove()	505
10.123.3.3 Replace() [1/2]	505
10.123.3.4 Replace() [2/2]	505
10.123.3.5 SetInputFileName()	505
10.123.3.6 SetOutputFileName()	506
10.123.3.7 Write()	506
10.124 gdcm::FileChangeTransferSyntax Class Reference	506
10.124.1 Detailed Description	508
10.124.2 Constructor & Destructor Documentation	508
10.124.2.1 FileChangeTransferSyntax()	508
10.124.2.2 ~FileChangeTransferSyntax()	509
10.124.3 Member Function Documentation	509
10.124.3.1 Change()	509
10.124.3.2 GetCodec()	509
10.124.3.3 New()	509
10.124.3.4 SetInputFileName()	509
10.124.3.5 SetOutputFileName()	510
10.124.3.6 SetTransferSyntax()	510
10.125 gdcm::FileDecompressLookupTable Class Reference	510
10.125.1 Detailed Description	512

10.125.2 Constructor & Destructor Documentation	512
10.125.2.1 FileDecompressLookupTable()	512
10.125.2.2 ~FileDecompressLookupTable()	512
10.125.3 Member Function Documentation	512
10.125.3.1 Change()	512
10.125.3.2 GetFile()	513
10.125.3.3 GetPixmap() [1/2]	513
10.125.3.4 GetPixmap() [2/2]	513
10.125.3.5 SetFile()	513
10.125.3.6 SetPixmap()	513
10.126 gdcmm::FileDerivation Class Reference	513
10.126.1 Detailed Description	514
10.126.2 Constructor & Destructor Documentation	514
10.126.2.1 FileDerivation()	514
10.126.2.2 ~FileDerivation()	515
10.126.3 Member Function Documentation	515
10.126.3.1 AddDerivationDescription()	515
10.126.3.2 AddPurposeOfReferenceCodeSequence()	515
10.126.3.3 AddReference()	515
10.126.3.4 AddSourceImageSequence()	515
10.126.3.5 Derive()	515
10.126.3.6 GetFile() [1/2]	516
10.126.3.7 GetFile() [2/2]	516
10.126.3.8 SetAppendDerivationHistory()	516
10.126.3.9 SetDerivationCodeSequenceCodeValue()	516
10.126.3.10 SetDerivationDescription()	516
10.126.3.11 SetFile()	517
10.126.3.12 SetPurposeOfReferenceCodeSequenceCodeValue()	517
10.127 gdcmm::FileExplicitFilter Class Reference	517
10.127.1 Detailed Description	518
10.127.2 Constructor & Destructor Documentation	518
10.127.2.1 FileExplicitFilter()	518
10.127.2.2 ~FileExplicitFilter()	518
10.127.3 Member Function Documentation	518
10.127.3.1 Change()	518
10.127.3.2 ChangeFMI()	519
10.127.3.3 GetFile()	519
10.127.3.4 ProcessDataSet()	519
10.127.3.5 SetChangePrivateTags()	519

10.127.3.6 SetFile()	519
10.127.3.7 SetRecomputeItemLength()	520
10.127.3.8 SetRecomputeSequenceLength()	520
10.127.3.9 SetUseVRUN()	520
10.128 gdcm::FileMetaInformation Class Reference	520
10.128.1 Detailed Description	524
10.128.2 Constructor & Destructor Documentation	524
10.128.2.1 FileMetaInformation() [1/2]	524
10.128.2.2 ~FileMetaInformation()	525
10.128.2.3 FileMetaInformation() [2/2]	525
10.128.3 Member Function Documentation	525
10.128.3.1 AppendImplementationClassUID()	525
10.128.3.2 ComputeDataSetMediaStorageSOPClass()	525
10.128.3.3 ComputeDataSetTransferSyntax()	525
10.128.3.4 Default()	525
10.128.3.5 FillFromDataSet()	525
10.128.3.6 GetDataSetTransferSyntax()	526
10.128.3.7 GetFileMetaInformationVersion()	526
10.128.3.8 GetFullLength()	526
10.128.3.9 GetGDCMImplementationClassUID()	526
10.128.3.10 GetGDCMImplementationVersionName()	526
10.128.3.11 GetGDCMSourceApplicationEntityTitle()	526
10.128.3.12 GetImplementationClassUID()	526
10.128.3.13 GetImplementationVersionName()	526
10.128.3.14 GetMediaStorage()	527
10.128.3.15 GetMediaStorageAsString()	527
10.128.3.16 GetMetaInformationTS()	527
10.128.3.17 GetPreamble() [1/2]	527
10.128.3.18 GetPreamble() [2/2]	527
10.128.3.19 GetSourceApplicationEntityTitle()	527
10.128.3.20 Insert()	527
10.128.3.21 IsValid()	527
10.128.3.22 operator=()	528
10.128.3.23 Read()	528
10.128.3.24 ReadCompat()	528
10.128.3.25 ReadCompatInternal()	528
10.128.3.26 Replace()	528
10.128.3.27 SetDataSetTransferSyntax()	528
10.128.3.28 SetImplementationClassUID()	529

10.128.3.29 SetImplementationVersionName()	529
10.128.3.30 SetPreamble()	529
10.128.3.31 SetSourceApplicationEntityTitle()	529
10.128.3.32 Write()	529
10.128.4 Friends And Related Symbol Documentation	529
10.128.4.1 operator<<	529
10.128.5 Member Data Documentation	530
10.128.5.1 DataSetMS	530
10.128.5.2 DataSetTS	530
10.128.5.3 MetaInformationTS	530
10.129 gdcm::Filename Class Reference	530
10.129.1 Detailed Description	531
10.129.2 Constructor & Destructor Documentation	531
10.129.2.1 Filename()	531
10.129.3 Member Function Documentation	531
10.129.3.1 EndWith()	531
10.129.3.2 GetExtension()	531
10.129.3.3 GetFileName()	531
10.129.3.4 GetName()	532
10.129.3.5 GetPath()	532
10.129.3.6 IsEmpty()	532
10.129.3.7 IsIdentical()	532
10.129.3.8 Join()	532
10.129.3.9 operator const char *()	532
10.129.3.10 ToUnixSlashes()	533
10.129.3.11 ToWindowsSlashes()	533
10.130 gdcm::FileNameEvent Class Reference	533
10.130.1 Detailed Description	535
10.130.2 Member Typedef Documentation	535
10.130.2.1 Self	535
10.130.2.2 Superclass	535
10.130.3 Constructor & Destructor Documentation	535
10.130.3.1 FileNameEvent() [1/2]	535
10.130.3.2 ~FileNameEvent()	535
10.130.3.3 FileNameEvent() [2/2]	535
10.130.4 Member Function Documentation	536
10.130.4.1 CheckEvent()	536
10.130.4.2 GetEventName()	536
10.130.4.3 GetFileName()	536

10.130.4.4 MakeObject()	536
10.130.4.5 operator=()	536
10.130.4.6 SetFileName()	536
10.131 gdcmm::FilenameGenerator Class Reference	537
10.131.1 Detailed Description	537
10.131.2 Member Typedef Documentation	538
10.131.2.1 FilenamesType	538
10.131.2.2 FilenameType	538
10.131.2.3 SizeType	538
10.131.3 Constructor & Destructor Documentation	538
10.131.3.1 FilenameGenerator()	538
10.131.3.2 ~FilenameGenerator()	538
10.131.4 Member Function Documentation	538
10.131.4.1 Generate()	538
10.131.4.2 GetFilename()	539
10.131.4.3 GetFilenames()	539
10.131.4.4 GetNumberOfFilenames()	539
10.131.4.5 GetPattern()	539
10.131.4.6 GetPrefix()	539
10.131.4.7 SetNumberOfFilenames()	539
10.131.4.8 SetPattern()	540
10.131.4.9 SetPrefix()	540
10.132 gdcmm::FileSet Class Reference	540
10.132.1 Detailed Description	541
10.132.2 Member Typedef Documentation	541
10.132.2.1 FileType	541
10.132.2.2 FileType	541
10.132.3 Constructor & Destructor Documentation	541
10.132.3.1 FileSet()	541
10.132.4 Member Function Documentation	541
10.132.4.1 AddFile() [1/2]	541
10.132.4.2 AddFile() [2/2]	541
10.132.4.3 GetFiles()	542
10.132.4.4 SetFiles()	542
10.132.5 Friends And Related Symbol Documentation	542
10.132.5.1 operator<<	542
10.133 gdcmm::FileStreamer Class Reference	542
10.133.1 Detailed Description	544
10.133.2 Constructor & Destructor Documentation	545

10.133.2.1 FileStreamer()	545
10.133.2.2 ~FileStreamer()	545
10.133.3 Member Function Documentation	545
10.133.3.1 AppendToDataElement()	545
10.133.3.2 AppendToGroupDataElement()	545
10.133.3.3 CheckDataElement()	545
10.133.3.4 CheckTemplateFileName()	546
10.133.3.5 New()	546
10.133.3.6 ReserveDataElement()	546
10.133.3.7 ReserveGroupDataElement()	546
10.133.3.8 SetOutputFileName()	546
10.133.3.9 SetTemplateFileName()	547
10.133.3.10 StartDataElement()	547
10.133.3.11 StartGroupDataElement()	547
10.133.3.12 StopDataElement()	547
10.133.3.13 StopGroupDataElement()	548
10.134 gdcmm::FileWithName Class Reference	548
10.134.1 Detailed Description	550
10.134.2 Constructor & Destructor Documentation	550
10.134.2.1 FileWithName()	550
10.134.3 Member Data Documentation	550
10.134.3.1 filename	550
10.135 gdcmm::FindPatientRootQuery Class Reference	551
10.135.1 Detailed Description	553
10.135.2 Constructor & Destructor Documentation	553
10.135.2.1 FindPatientRootQuery()	553
10.135.3 Member Function Documentation	553
10.135.3.1 GetAbstractSyntaxUID()	553
10.135.3.2 GetTagListByLevel()	554
10.135.3.3 InitializeDataSet()	554
10.135.3.4 ValidateQuery()	554
10.135.4 Friends And Related Symbol Documentation	554
10.135.4.1 QueryFactory	554
10.136 gdcmm::FindStudyRootQuery Class Reference	555
10.136.1 Detailed Description	557
10.136.2 Constructor & Destructor Documentation	557
10.136.2.1 FindStudyRootQuery()	557
10.136.3 Member Function Documentation	557
10.136.3.1 GetAbstractSyntaxUID()	557

10.136.3.2 GetTagListByLevel()	558
10.136.3.3 InitializeDataSet()	558
10.136.3.4 ValidateQuery()	558
10.136.4 Friends And Related Symbol Documentation	558
10.136.4.1 QueryFactory	558
10.137 gdcM::Fragment Class Reference	559
10.137.1 Detailed Description	561
10.137.2 Constructor & Destructor Documentation	562
10.137.2.1 Fragment()	562
10.137.3 Member Function Documentation	562
10.137.3.1 ComputeLength()	562
10.137.3.2 GetLength()	562
10.137.3.3 Read()	562
10.137.3.4 ReadBacktrack()	562
10.137.3.5 ReadPreValue()	563
10.137.3.6 ReadValue()	563
10.137.3.7 Write()	563
10.137.4 Friends And Related Symbol Documentation	563
10.137.4.1 operator<<	563
10.138 gdcM::Global Class Reference	564
10.138.1 Detailed Description	564
10.138.2 Constructor & Destructor Documentation	565
10.138.2.1 Global() [1/2]	565
10.138.2.2 ~Global()	565
10.138.2.3 Global() [2/2]	565
10.138.3 Member Function Documentation	565
10.138.3.1 Append()	565
10.138.3.2 GetDefs()	565
10.138.3.3 GetDicts() [1/2]	566
10.138.3.4 GetDicts() [2/2]	566
10.138.3.5 GetInstance()	566
10.138.3.6 LoadResourcesFiles()	566
10.138.3.7 Locate()	567
10.138.3.8 operator=()	567
10.138.3.9 Prepend()	567
10.138.4 Friends And Related Symbol Documentation	567
10.138.4.1 operator<<	567
10.139 gdcM::GroupDict Class Reference	567
10.139.1 Detailed Description	568

10.139.2 Member Typedef Documentation	568
10.139.2.1 GroupStringVector	568
10.139.3 Constructor & Destructor Documentation	568
10.139.3.1 GroupDict()	568
10.139.3.2 ~GroupDict()	569
10.139.4 Member Function Documentation	569
10.139.4.1 Add()	569
10.139.4.2 GetAbbreviation()	569
10.139.4.3 GetName()	569
10.139.4.4 Insert()	569
10.139.4.5 Size()	569
10.139.5 Friends And Related Symbol Documentation	570
10.139.5.1 operator<<	570
10.140 gdcm::IconImageFilter Class Reference	570
10.140.1 Detailed Description	571
10.140.2 Constructor & Destructor Documentation	571
10.140.2.1 IconImageFilter()	571
10.140.2.2 ~IconImageFilter()	571
10.140.3 Member Function Documentation	572
10.140.3.1 Extract()	572
10.140.3.2 ExtractIconImages()	572
10.140.3.3 ExtractVeprolIconImages()	572
10.140.3.4 GetFile() [1/2]	572
10.140.3.5 GetFile() [2/2]	572
10.140.3.6 GetIconImage()	572
10.140.3.7 GetNumberOfIconImages()	573
10.140.3.8 SetFile()	573
10.141 gdcm::IconImageGenerator Class Reference	573
10.141.1 Detailed Description	574
10.141.2 Constructor & Destructor Documentation	574
10.141.2.1 IconImageGenerator()	574
10.141.2.2 ~IconImageGenerator()	574
10.141.3 Member Function Documentation	574
10.141.3.1 AutoPixelMinMax()	574
10.141.3.2 ConvertRGBToPaletteColor()	575
10.141.3.3 Generate()	575
10.141.3.4 GetIconImage()	575
10.141.3.5 GetPixmap() [1/2]	575
10.141.3.6 GetPixmap() [2/2]	575

10.141.3.7 SetOutputDimensions()	575
10.141.3.8 SetOutsideValuePixel()	576
10.141.3.9 SetPixelMinMax()	576
10.141.3.10 SetPixmap()	576
10.142 gdcm::ignore_char Struct Reference	576
10.142.1 Constructor & Destructor Documentation	577
10.142.1.1 ignore_char()	577
10.142.2 Member Data Documentation	577
10.142.2.1 m_char	577
10.143 gdcm::Image Class Reference	577
10.143.1 Detailed Description	582
10.143.2 Constructor & Destructor Documentation	582
10.143.2.1 Image()	582
10.143.2.2 ~Image()	582
10.143.3 Member Function Documentation	583
10.143.3.1 GetDirectionCosines() [1/2]	583
10.143.3.2 GetDirectionCosines() [2/2]	583
10.143.3.3 GetIntercept()	583
10.143.3.4 GetOrigin() [1/2]	583
10.143.3.5 GetOrigin() [2/2]	583
10.143.3.6 GetSlope()	583
10.143.3.7 GetSpacing() [1/2]	583
10.143.3.8 GetSpacing() [2/2]	584
10.143.3.9 Print()	584
10.143.3.10 SetDirectionCosines() [1/3]	584
10.143.3.11 SetDirectionCosines() [2/3]	584
10.143.3.12 SetDirectionCosines() [3/3]	584
10.143.3.13 SetIntercept()	584
10.143.3.14 SetOrigin() [1/3]	585
10.143.3.15 SetOrigin() [2/3]	585
10.143.3.16 SetOrigin() [3/3]	585
10.143.3.17 SetSlope()	585
10.143.3.18 SetSpacing() [1/2]	585
10.143.3.19 SetSpacing() [2/2]	585
10.144 gdcm::ImageApplyLookupTable Class Reference	586
10.144.1 Detailed Description	588
10.144.2 Constructor & Destructor Documentation	588
10.144.2.1 ImageApplyLookupTable()	588
10.144.2.2 ~ImageApplyLookupTable()	589

10.144.3 Member Function Documentation	589
10.144.3.1 Apply()	589
10.144.3.2 SetRGB8()	589
10.145 gdcm::ImageChangePhotometricInterpretation Class Reference	589
10.145.1 Detailed Description	592
10.145.2 Constructor & Destructor Documentation	592
10.145.2.1 ImageChangePhotometricInterpretation()	592
10.145.2.2 ~ImageChangePhotometricInterpretation()	592
10.145.3 Member Function Documentation	592
10.145.3.1 Change()	592
10.145.3.2 ChangeMonochrome()	592
10.145.3.3 ChangeRGB2YBR()	592
10.145.3.4 ChangeYBR2RGB()	592
10.145.3.5 GetPhotometricInterpretation()	593
10.145.3.6 RGB2YBR()	593
10.145.3.7 SetPhotometricInterpretation()	593
10.145.3.8 YBR2RGB()	593
10.146 gdcm::ImageChangePlanarConfiguration Class Reference	594
10.146.1 Detailed Description	596
10.146.2 Constructor & Destructor Documentation	597
10.146.2.1 ImageChangePlanarConfiguration()	597
10.146.2.2 ~ImageChangePlanarConfiguration()	597
10.146.3 Member Function Documentation	597
10.146.3.1 Change()	597
10.146.3.2 GetPlanarConfiguration()	597
10.146.3.3 RGBPixelsToRGBPlanes()	597
10.146.3.4 RGBPlanesToRGBPixels()	598
10.146.3.5 SetPlanarConfiguration()	598
10.147 gdcm::ImageChangeTransferSyntax Class Reference	598
10.147.1 Detailed Description	602
10.147.2 Constructor & Destructor Documentation	602
10.147.2.1 ImageChangeTransferSyntax()	602
10.147.2.2 ~ImageChangeTransferSyntax()	602
10.147.3 Member Function Documentation	602
10.147.3.1 Change()	602
10.147.3.2 GetTransferSyntax()	603
10.147.3.3 SetCompressIconImage()	603
10.147.3.4 SetForce()	603
10.147.3.5 SetTransferSyntax()	603

10.147.3.6 SetUserCodec()	604
10.147.3.7 TryJPEG2000Codec()	604
10.147.3.8 TryJPEGCodec()	604
10.147.3.9 TryJPEGLSCodec()	604
10.147.3.10 TryRAWCodec()	604
10.147.3.11 TryRLECodec()	605
10.148 gdcmm::ImageCodec Class Reference	605
10.148.1 Detailed Description	608
10.148.2 Member Typedef Documentation	608
10.148.2.1 LUTPtr	608
10.148.3 Constructor & Destructor Documentation	608
10.148.3.1 ImageCodec()	608
10.148.3.2 ~ImageCodec()	608
10.148.4 Member Function Documentation	608
10.148.4.1 AppendFrameEncode()	608
10.148.4.2 AppendRowEncode()	609
10.148.4.3 CanCode()	609
10.148.4.4 CanDecode()	609
10.148.4.5 CleanupUnusedBits()	609
10.148.4.6 Clone()	609
10.148.4.7 Decode()	610
10.148.4.8 DecodeByStreams()	610
10.148.4.9 DoByteSwap()	610
10.148.4.10 DoInvertMonochrome()	610
10.148.4.11 DoOverlayCleanup()	610
10.148.4.12 DoPaddedCompositePixelCode()	610
10.148.4.13 DoPlanarConfiguration()	611
10.148.4.14 DoSimpleCopy()	611
10.148.4.15 DoYBR()	611
10.148.4.16 DoYBRFull422()	611
10.148.4.17 GetDimensions()	611
10.148.4.18 GetHeaderInfo()	611
10.148.4.19 GetLossyFlag()	611
10.148.4.20 GetLUT()	612
10.148.4.21 GetNeedByteSwap()	612
10.148.4.22 GetNumberOfDimensions()	612
10.148.4.23 GetPhotometricInterpretation()	612
10.148.4.24 GetPixelFormat() [1/2]	612
10.148.4.25 GetPixelFormat() [2/2]	612

10.148.4.26 GetPlanarConfiguration()	612
10.148.4.27 IsFrameEncoder()	613
10.148.4.28 IsLossy()	613
10.148.4.29 IsRowEncoder()	613
10.148.4.30 IsValid()	613
10.148.4.31 SetDimensions() [1/2]	613
10.148.4.32 SetDimensions() [2/2]	613
10.148.4.33 SetLossyFlag()	613
10.148.4.34 SetLUT()	614
10.148.4.35 SetNeedByteSwap()	614
10.148.4.36 SetNeedOverlayCleanup()	614
10.148.4.37 SetNumberOfDimensions()	614
10.148.4.38 SetPhotometricInterpretation()	614
10.148.4.39 SetPixelFormat()	615
10.148.4.40 SetPlanarConfiguration()	615
10.148.4.41 StartEncode()	615
10.148.4.42 StopEncode()	615
10.148.5 Friends And Related Symbol Documentation	615
10.148.5.1 FileChangeTransferSyntax	615
10.148.5.2 ImageChangePhotometricInterpretation	616
10.148.6 Member Data Documentation	616
10.148.6.1 Dimensions	616
10.148.6.2 LossyFlag	616
10.148.6.3 LUT	616
10.148.6.4 NeedByteSwap	616
10.148.6.5 NeedOverlayCleanup	616
10.148.6.6 NumberOfDimensions	616
10.148.6.7 PF	617
10.148.6.8 PI	617
10.148.6.9 PlanarConfiguration	617
10.148.6.10 RequestPaddedCompositePixelCode	617
10.148.6.11 RequestPlanarConfiguration	617
10.149 gdcm::ImageConverter Class Reference	617
10.149.1 Detailed Description	618
10.149.2 Constructor & Destructor Documentation	618
10.149.2.1 ImageConverter()	618
10.149.2.2 ~ImageConverter()	618
10.149.3 Member Function Documentation	618
10.149.3.1 Convert()	618

10.149.3.2 GetOutput()	618
10.149.3.3 SetInput()	618
10.150 gdcm::ImageFragmentSplitter Class Reference	619
10.150.1 Detailed Description	621
10.150.2 Constructor & Destructor Documentation	621
10.150.2.1 ImageFragmentSplitter()	621
10.150.2.2 ~ImageFragmentSplitter()	622
10.150.3 Member Function Documentation	622
10.150.3.1 GetFragmentSizeMax()	622
10.150.3.2 SetForce()	622
10.150.3.3 SetFragmentSizeMax()	622
10.150.3.4 Split()	622
10.151 gdcm::ImageHelper Class Reference	622
10.151.1 Detailed Description	624
10.151.2 Member Function Documentation	624
10.151.2.1 ComputeMediaStorageFromModality()	624
10.151.2.2 ComputeSpacingFromImagePositionPatient()	624
10.151.2.3 GetDimensionsValue()	624
10.151.2.4 GetDirectionCosinesFromDataSet()	625
10.151.2.5 GetDirectionCosinesValue()	625
10.151.2.6 GetForcePixelSpacing()	625
10.151.2.7 GetForceRescaleInterceptSlope()	625
10.151.2.8 GetLUT()	625
10.151.2.9 GetOriginValue()	625
10.151.2.10 GetPhotometricInterpretationValue()	625
10.151.2.11 GetPixelFormatValue()	626
10.151.2.12 GetPlanarConfigurationValue()	626
10.151.2.13 GetPMSRescaleInterceptSlope()	626
10.151.2.14 GetPointerFromElement()	626
10.151.2.15 GetRealWorldValueMappingContent()	626
10.151.2.16 GetRescaleInterceptSlopeValue()	626
10.151.2.17 GetSecondaryCaptureImagePlaneModule()	627
10.151.2.18 GetSpacingTagFromMediaStorage()	627
10.151.2.19 GetSpacingValue()	627
10.151.2.20 GetZSpacingTagFromMediaStorage()	627
10.151.2.21 SetDimensionsValue()	627
10.151.2.22 SetDirectionCosinesValue()	627
10.151.2.23 SetForcePixelSpacing()	627
10.151.2.24 SetForceRescaleInterceptSlope()	628

10.151.2.25 SetOriginValue()	628
10.151.2.26 SetPMSRescaleInterceptSlope()	628
10.151.2.27 SetRescaleInterceptSlopeValue()	628
10.151.2.28 SetSecondaryCaptureImagePlaneModule()	628
10.151.2.29 SetSpacingValue()	629
10.152 gdcm::ImageReader Class Reference	629
10.152.1 Detailed Description	632
10.152.2 Constructor & Destructor Documentation	632
10.152.2.1 ImageReader()	632
10.152.2.2 ~ImageReader()	632
10.152.3 Member Function Documentation	632
10.152.3.1 GetImage() [1/2]	632
10.152.3.2 GetImage() [2/2]	633
10.152.3.3 Read()	633
10.152.3.4 ReadACRNEMAIImage()	633
10.152.3.5 ReadImage()	633
10.153 gdcm::ImageRegionReader Class Reference	634
10.153.1 Detailed Description	637
10.153.2 Constructor & Destructor Documentation	637
10.153.2.1 ImageRegionReader()	637
10.153.2.2 ~ImageRegionReader()	638
10.153.3 Member Function Documentation	638
10.153.3.1 ComputeBufferLength()	638
10.153.3.2 GetRegion()	638
10.153.3.3 Read()	638
10.153.3.4 ReadInformation()	638
10.153.3.5 ReadIntoBuffer()	639
10.153.3.6 SetRegion()	639
10.154 gdcm::ImageToImageFilter Class Reference	639
10.154.1 Detailed Description	641
10.154.2 Constructor & Destructor Documentation	641
10.154.2.1 ImageToImageFilter()	641
10.154.2.2 ~ImageToImageFilter()	641
10.154.3 Member Function Documentation	641
10.154.3.1 GetInput()	641
10.154.3.2 GetOutput()	642
10.155 gdcm::ImageWriter Class Reference	642
10.155.1 Detailed Description	645
10.155.2 Constructor & Destructor Documentation	645

10.155.2.1 ImageWriter()	645
10.155.2.2 ~ImageWriter()	645
10.155.3 Member Function Documentation	645
10.155.3.1 ComputeTargetMediaStorage()	645
10.155.3.2 GetImage() [1/2]	646
10.155.3.3 GetImage() [2/2]	646
10.155.3.4 Write()	646
10.156 gdcmm::network::ImplementationClassUIDSub Class Reference	646
10.156.1 Detailed Description	647
10.156.2 Constructor & Destructor Documentation	647
10.156.2.1 ImplementationClassUIDSub()	647
10.156.3 Member Function Documentation	647
10.156.3.1 Print()	647
10.156.3.2 Read()	647
10.156.3.3 Size()	647
10.156.3.4 Write()	647
10.157 gdcmm::network::ImplementationUIDSub Class Reference	648
10.157.1 Detailed Description	648
10.157.2 Constructor & Destructor Documentation	648
10.157.2.1 ImplementationUIDSub()	648
10.157.3 Member Function Documentation	648
10.157.3.1 Write()	648
10.158 gdcmm::network::ImplementationVersionNameSub Class Reference	648
10.158.1 Detailed Description	649
10.158.2 Constructor & Destructor Documentation	649
10.158.2.1 ImplementationVersionNameSub()	649
10.158.3 Member Function Documentation	649
10.158.3.1 Print()	649
10.158.3.2 Read()	649
10.158.3.3 Size()	649
10.158.3.4 Write()	649
10.159 gdcmm::ImplicitDataElement Class Reference	650
10.159.1 Detailed Description	652
10.159.2 Member Function Documentation	653
10.159.2.1 GetLength()	653
10.159.2.2 Read()	653
10.159.2.3 ReadPreValue()	653
10.159.2.4 ReadValue()	653
10.159.2.5 ReadValueWithLength()	653

10.159.2.6 ReadWithLength()	653
10.159.2.7 Write()	654
10.160 gdcmm::InitializeEvent Class Reference	654
10.161 gdcmm::IOD Class Reference	655
10.161.1 Detailed Description	656
10.161.2 Member Typedef Documentation	656
10.161.2.1 MapIOEntry	656
10.161.2.2 SizeType	656
10.161.3 Constructor & Destructor Documentation	657
10.161.3.1 IOD()	657
10.161.4 Member Function Documentation	657
10.161.4.1 AddIOEntry()	657
10.161.4.2 Clear()	657
10.161.4.3 GetIOEntry()	657
10.161.4.4 GetNumberOfIODs()	657
10.161.4.5 GetTypeFromTag()	657
10.161.5 Friends And Related Symbol Documentation	658
10.161.5.1 operator<<	658
10.162 gdcmm::IOEntry Class Reference	658
10.162.1 Detailed Description	659
10.162.2 Constructor & Destructor Documentation	659
10.162.2.1 IOEntry()	659
10.162.3 Member Function Documentation	659
10.162.3.1 GetIE()	659
10.162.3.2 GetName()	660
10.162.3.3 GetRef()	660
10.162.3.4 GetUsage()	660
10.162.3.5 GetUsageType()	660
10.162.3.6 SetIE()	660
10.162.3.7 SetName()	660
10.162.3.8 SetRef()	660
10.162.3.9 SetUsage()	660
10.162.4 Friends And Related Symbol Documentation	661
10.162.4.1 operator<<	661
10.163 gdcmm::IODs Class Reference	661
10.163.1 Detailed Description	662
10.163.2 Member Typedef Documentation	662
10.163.2.1 IODMapType	662
10.163.2.2 IODMapTypeConstIterator	662

10.163.2.3 IODName	662
10.163.3 Constructor & Destructor Documentation	662
10.163.3.1 IODs()	662
10.163.4 Member Function Documentation	663
10.163.4.1 AddIOD()	663
10.163.4.2 Begin()	663
10.163.4.3 Clear()	663
10.163.4.4 End()	663
10.163.4.5 GetIOD()	663
10.163.5 Friends And Related Symbol Documentation	663
10.163.5.1 operator<<	663
10.164 gdcmm::IPPSorter Class Reference	664
10.164.1 Detailed Description	666
10.164.2 Constructor & Destructor Documentation	666
10.164.2.1 IPPSorter()	666
10.164.3 Member Function Documentation	666
10.164.3.1 GetDirectionCosinesTolerance()	666
10.164.3.2 GetZSpacing()	667
10.164.3.3 GetZSpacingTolerance()	667
10.164.3.4 SetComputeZSpacing()	667
10.164.3.5 SetDirectionCosinesTolerance()	668
10.164.3.6 SetDropDuplicatePositions()	668
10.164.3.7 SetZSpacingTolerance()	668
10.164.3.8 Sort()	668
10.164.4 Member Data Documentation	669
10.164.4.1 ComputeZSpacing	669
10.164.4.2 DirCosTolerance	669
10.164.4.3 DropDuplicatePositions	669
10.164.4.4 ZSpacing	669
10.164.4.5 ZTolerance	669
10.165 gdcmm::Item Class Reference	670
10.165.1 Detailed Description	673
10.165.2 Constructor & Destructor Documentation	673
10.165.2.1 Item() [1/2]	673
10.165.2.2 Item() [2/2]	673
10.165.3 Member Function Documentation	673
10.165.3.1 Clear()	673
10.165.3.2 FindDataElement()	674
10.165.3.3 GetDataElement()	674

10.165.3.4 GetLength()	674
10.165.3.5 GetNestedDataSet() [1/2]	674
10.165.3.6 GetNestedDataSet() [2/2]	674
10.165.3.7 InsertDataElement()	674
10.165.3.8 Read()	675
10.165.3.9 SetNestedDataSet()	675
10.165.3.10 Write()	675
10.165.4 Friends And Related Symbol Documentation	675
10.165.4.1 operator<<	675
10.166 gdcm::IterationEvent Class Reference	676
10.167 gdcm::JPEG12Codec Class Reference	677
10.167.1 Detailed Description	680
10.167.2 Constructor & Destructor Documentation	681
10.167.2.1 JPEG12Codec()	681
10.167.2.2 ~JPEG12Codec()	681
10.167.3 Member Function Documentation	681
10.167.3.1 DecodeByStreams()	681
10.167.3.2 EncodeBuffer()	681
10.167.3.3 GetHeaderInfo()	681
10.167.3.4 InternalCode()	681
10.167.3.5 IsStateSuspension()	682
10.168 gdcm::JPEG16Codec Class Reference	682
10.168.1 Detailed Description	685
10.168.2 Constructor & Destructor Documentation	686
10.168.2.1 JPEG16Codec()	686
10.168.2.2 ~JPEG16Codec()	686
10.168.3 Member Function Documentation	686
10.168.3.1 DecodeByStreams()	686
10.168.3.2 EncodeBuffer()	686
10.168.3.3 GetHeaderInfo()	686
10.168.3.4 InternalCode()	686
10.168.3.5 IsStateSuspension()	687
10.169 gdcm::JPEG2000Codec Class Reference	687
10.169.1 Detailed Description	690
10.169.2 Constructor & Destructor Documentation	690
10.169.2.1 JPEG2000Codec()	690
10.169.2.2 ~JPEG2000Codec()	690
10.169.3 Member Function Documentation	690
10.169.3.1 AppendFrameEncode()	690

10.169.3.2 AppendRowEncode()	691
10.169.3.3 CanCode()	691
10.169.3.4 CanDecode()	691
10.169.3.5 Clone()	691
10.169.3.6 Code()	691
10.169.3.7 Decode()	692
10.169.3.8 DecodeByStreams()	692
10.169.3.9 DecodeExtent()	692
10.169.3.10 GetHeaderInfo()	692
10.169.3.11 GetQuality()	692
10.169.3.12 GetRate()	693
10.169.3.13 IsFrameEncoder()	693
10.169.3.14 IsRowEncoder()	693
10.169.3.15 SetMCT()	693
10.169.3.16 SetNumberOfResolutions()	693
10.169.3.17 SetNumberOfThreadsForDecompression()	693
10.169.3.18 SetQuality()	693
10.169.3.19 SetRate()	694
10.169.3.20 SetReversible()	694
10.169.3.21 SetTileSize()	694
10.169.3.22 StartEncode()	694
10.169.3.23 StopEncode()	694
10.169.4 Friends And Related Symbol Documentation	694
10.169.4.1 Bitmap	694
10.169.4.2 ImageRegionReader	695
10.170 gdcm::JPEG8Codec Class Reference	695
10.170.1 Detailed Description	698
10.170.2 Constructor & Destructor Documentation	699
10.170.2.1 JPEG8Codec()	699
10.170.2.2 ~JPEG8Codec()	699
10.170.3 Member Function Documentation	699
10.170.3.1 DecodeByStreams()	699
10.170.3.2 EncodeBuffer()	699
10.170.3.3 GetHeaderInfo()	699
10.170.3.4 InternalCode()	699
10.170.3.5 IsStateSuspension()	700
10.171 gdcm::JPEGCodec Class Reference	700
10.171.1 Detailed Description	703
10.171.2 Constructor & Destructor Documentation	704

10.171.2.1 JPEGCodec()	704
10.171.2.2 ~JPEGCodec()	704
10.171.3 Member Function Documentation	704
10.171.3.1 AppendFrameEncode()	704
10.171.3.2 AppendRowEncode()	704
10.171.3.3 CanCode()	704
10.171.3.4 CanDecode()	705
10.171.3.5 Clone()	705
10.171.3.6 Code()	705
10.171.3.7 ComputeOffsetTable()	705
10.171.3.8 Decode()	705
10.171.3.9 DecodeByStreams()	706
10.171.3.10 DecodeExtent()	706
10.171.3.11 EncodeBuffer()	706
10.171.3.12 GetHeaderInfo()	706
10.171.3.13 GetLossless()	706
10.171.3.14 GetQuality()	707
10.171.3.15 IsFrameEncoder()	707
10.171.3.16 IsRowEncoder()	707
10.171.3.17 IsStateSuspension()	707
10.171.3.18 IsValid()	707
10.171.3.19 SetBitSample()	707
10.171.3.20 SetLossless()	707
10.171.3.21 SetPixelFormat()	708
10.171.3.22 SetQuality()	708
10.171.3.23 StartEncode()	708
10.171.3.24 StopEncode()	708
10.171.4 Friends And Related Symbol Documentation	708
10.171.4.1 ImageRegionReader	708
10.171.5 Member Data Documentation	709
10.171.5.1 BitSample	709
10.171.5.2 Quality	709
10.172 gdcm::JPEGLSCodec Class Reference	709
10.172.1 Detailed Description	712
10.172.2 Constructor & Destructor Documentation	712
10.172.2.1 JPEGLSCodec()	712
10.172.2.2 ~JPEGLSCodec()	713
10.172.3 Member Function Documentation	713
10.172.3.1 AppendFrameEncode()	713

10.172.3.2 AppendRowEncode()	713
10.172.3.3 CanCode()	713
10.172.3.4 CanDecode()	713
10.172.3.5 Clone()	714
10.172.3.6 Code()	714
10.172.3.7 Decode() [1/2]	714
10.172.3.8 Decode() [2/2]	714
10.172.3.9 DecodeExtent()	714
10.172.3.10 GetBufferLength()	715
10.172.3.11 GetHeaderInfo()	715
10.172.3.12 GetLossless()	715
10.172.3.13 IsFrameEncoder()	715
10.172.3.14 IsRowEncoder()	715
10.172.3.15 SetBufferLength()	715
10.172.3.16 SetLossless()	715
10.172.3.17 SetLossyError()	715
10.172.3.18 StartEncode()	716
10.172.3.19 StopEncode()	716
10.172.4 Friends And Related Symbol Documentation	716
10.172.4.1 ImageRegionReader	716
10.173 gdcm::JSON Class Reference	716
10.173.1 Detailed Description	717
10.173.2 Constructor & Destructor Documentation	717
10.173.2.1 JSON()	717
10.173.2.2 ~JSON()	717
10.173.3 Member Function Documentation	717
10.173.3.1 Code()	717
10.173.3.2 Decode()	717
10.173.3.3 GetPrettyPrint()	717
10.173.3.4 PrettyPrintOff()	718
10.173.3.5 PrettyPrintOn()	718
10.173.3.6 SetPrettyPrint()	718
10.174 gdcm::KAKADUCodec Class Reference	718
10.174.1 Detailed Description	721
10.174.2 Constructor & Destructor Documentation	721
10.174.2.1 KAKADUCodec()	721
10.174.2.2 ~KAKADUCodec()	721
10.174.3 Member Function Documentation	721
10.174.3.1 CanCode()	721

10.174.3.2 CanDecode()	721
10.174.3.3 Clone()	721
10.174.3.4 Code()	722
10.174.3.5 Decode()	722
10.175 gdcmm::LO Class Reference	722
10.175.1 Detailed Description	723
10.175.2 Member Typedef Documentation	724
10.175.2.1 const_iterator	724
10.175.2.2 const_reference	724
10.175.2.3 const_reverse_iterator	724
10.175.2.4 difference_type	724
10.175.2.5 iterator	724
10.175.2.6 pointer	724
10.175.2.7 reference	724
10.175.2.8 reverse_iterator	724
10.175.2.9 size_type	724
10.175.2.10 Superclass	725
10.175.2.11 value_type	725
10.175.3 Constructor & Destructor Documentation	725
10.175.3.1 LO() [1/4]	725
10.175.3.2 LO() [2/4]	725
10.175.3.3 LO() [3/4]	725
10.175.3.4 LO() [4/4]	725
10.175.4 Member Function Documentation	725
10.175.4.1 IsValid()	725
10.176 gdcmm::LookupTable Class Reference	726
10.176.1 Detailed Description	728
10.176.2 Member Enumeration Documentation	728
10.176.2.1 LookupTableType	728
10.176.3 Constructor & Destructor Documentation	728
10.176.3.1 LookupTable() [1/2]	728
10.176.3.2 ~LookupTable()	729
10.176.3.3 LookupTable() [2/2]	729
10.176.4 Member Function Documentation	729
10.176.4.1 Allocate()	729
10.176.4.2 Clear()	729
10.176.4.3 Decode() [1/2]	729
10.176.4.4 Decode() [2/2]	729
10.176.4.5 Decode8()	730

10.176.4.6 GetBitSample()	730
10.176.4.7 GetBufferAsRGBA()	730
10.176.4.8 GetLUT()	730
10.176.4.9 GetLUTDescriptor()	730
10.176.4.10 GetLUTLength()	730
10.176.4.11 GetPointer()	731
10.176.4.12 InitializeBlueLUT()	731
10.176.4.13 Initialized()	731
10.176.4.14 InitializeGreenLUT()	731
10.176.4.15 InitializeLUT()	731
10.176.4.16 InitializeRedLUT()	731
10.176.4.17 IsRGB8()	732
10.176.4.18 Print()	732
10.176.4.19 SetBlueLUT()	732
10.176.4.20 SetGreenLUT()	732
10.176.4.21 SetLUT()	732
10.176.4.22 SetRedLUT()	732
10.176.4.23 WriteBufferAsRGBA()	733
10.176.5 Member Data Documentation	733
10.176.5.1 BitSample	733
10.176.5.2 IncompleteLUT	733
10.176.5.3 Internal	733
10.177 gdcm::Scanner2::ltstr Struct Reference	733
10.177.1 Member Function Documentation	734
10.177.1.1 operator>()	734
10.178 gdcm::Scanner::ltstr Struct Reference	734
10.178.1 Member Function Documentation	734
10.178.1.1 operator>()	734
10.179 gdcm::StrictScanner2::ltstr Struct Reference	734
10.179.1 Member Function Documentation	735
10.179.1.1 operator>()	735
10.180 gdcm::StrictScanner::ltstr Struct Reference	735
10.180.1 Member Function Documentation	735
10.180.1.1 operator>()	735
10.181 gdcm::Macro Class Reference	736
10.181.1 Detailed Description	736
10.181.2 Member Typedef Documentation	736
10.181.2.1 ArrayIncludeMacroType	736
10.181.2.2 MapModuleEntry	737

10.181.3 Constructor & Destructor Documentation	737
10.181.3.1 Macro()	737
10.181.4 Member Function Documentation	737
10.181.4.1 AddMacroEntry()	737
10.181.4.2 Clear()	737
10.181.4.3 FindMacroEntry()	737
10.181.4.4 GetMacroEntry()	737
10.181.4.5 GetName()	737
10.181.4.6 SetName()	738
10.181.4.7 Verify()	738
10.181.5 Friends And Related Symbol Documentation	738
10.181.5.1 operator<<	738
10.182 gdcn::Macros Class Reference	738
10.182.1 Detailed Description	739
10.182.2 Member Typedef Documentation	739
10.182.2.1 ModuleMapType	739
10.182.3 Constructor & Destructor Documentation	739
10.182.3.1 Macros()	739
10.182.4 Member Function Documentation	739
10.182.4.1 AddMacro()	739
10.182.4.2 Clear()	740
10.182.4.3 GetMacro()	740
10.182.4.4 IsEmpty()	740
10.182.5 Friends And Related Symbol Documentation	740
10.182.5.1 operator<<	740
10.183 gdcn::network::MaximumLengthSub Class Reference	740
10.183.1 Detailed Description	741
10.183.2 Constructor & Destructor Documentation	741
10.183.2.1 MaximumLengthSub()	741
10.183.3 Member Function Documentation	741
10.183.3.1 GetMaximumLength()	741
10.183.3.2 Print()	741
10.183.3.3 Read()	741
10.183.3.4 SetMaximumLength()	741
10.183.3.5 Size()	741
10.183.3.6 Write()	742
10.184 gdcn::MD5 Class Reference	742
10.184.1 Detailed Description	742
10.184.2 Member Function Documentation	742

10.184.2.1 Compute()	742
10.184.2.2 ComputeFile()	743
10.185 gdcmm::MEC_MR3 Class Reference	743
10.185.1 Detailed Description	743
10.185.2 Member Function Documentation	743
10.185.2.1 GetCanonMECMR3Tag()	743
10.185.2.2 GetPMTFInformationDataTag()	743
10.185.2.3 GetToshibaMECMR3Tag()	744
10.185.2.4 Print()	744
10.186 gdcmm::MediaStorage Class Reference	744
10.186.1 Detailed Description	747
10.186.2 Member Enumeration Documentation	747
10.186.2.1 MStype	747
10.186.2.2 ObjectType	750
10.186.3 Constructor & Destructor Documentation	750
10.186.3.1 MediaStorage()	750
10.186.4 Member Function Documentation	751
10.186.4.1 GetModality()	751
10.186.4.2 GetModalityDimension()	751
10.186.4.3 GetMSString()	751
10.186.4.4 GetMStype()	751
10.186.4.5 GetNumberOfModality()	751
10.186.4.6 GetNumberOfMSString()	751
10.186.4.7 GetNumberOfMStype()	752
10.186.4.8 GetString()	752
10.186.4.9 GuessFromModality()	752
10.186.4.10 IsImage()	752
10.186.4.11 IsUndefined()	752
10.186.4.12 operator MStype()	753
10.186.4.13 SetFromDataSet()	753
10.186.4.14 SetFromFile()	753
10.186.4.15 SetFromHeader()	753
10.186.4.16 SetFromModality()	753
10.186.4.17 SetFromSourceImageSequence()	753
10.186.5 Friends And Related Symbol Documentation	754
10.186.5.1 operator<<	754
10.187 gdcmm::MemberCommand< T > Class Template Reference	754
10.187.1 Detailed Description	757
10.187.2 Member Typedef Documentation	757

10.187.2.1 Self	757
10.187.2.2 TConstMemberFunctionPointer	757
10.187.2.3 TMemberFunctionPointer	757
10.187.3 Constructor & Destructor Documentation	757
10.187.3.1 MemberCommand() [1/2]	757
10.187.3.2 MemberCommand() [2/2]	757
10.187.3.3 ~MemberCommand()	758
10.187.4 Member Function Documentation	758
10.187.4.1 Execute() [1/2]	758
10.187.4.2 Execute() [2/2]	758
10.187.4.3 New()	758
10.187.4.4 operator=()	758
10.187.4.5 SetCallbackFunction() [1/2]	759
10.187.4.6 SetCallbackFunction() [2/2]	759
10.187.5 Member Data Documentation	759
10.187.5.1 m_ConstMemberFunction	759
10.187.5.2 m_MemberFunction	759
10.187.5.3 m_This	759
10.188 gdcmm::MeshPrimitive Class Reference	760
10.188.1 Detailed Description	762
10.188.2 Member Typedef Documentation	762
10.188.2.1 PrimitivesData	762
10.188.3 Member Enumeration Documentation	762
10.188.3.1 MPTYPE	762
10.188.4 Constructor & Destructor Documentation	763
10.188.4.1 MeshPrimitive()	763
10.188.4.2 ~MeshPrimitive()	763
10.188.5 Member Function Documentation	763
10.188.5.1 AddPrimitiveData()	763
10.188.5.2 GetMPTYPE()	763
10.188.5.3 GetMPTYPEString()	763
10.188.5.4 GetNumberOfPrimitivesData()	763
10.188.5.5 GetPrimitiveData() [1/4]	763
10.188.5.6 GetPrimitiveData() [2/4]	763
10.188.5.7 GetPrimitiveData() [3/4]	764
10.188.5.8 GetPrimitiveData() [4/4]	764
10.188.5.9 GetPrimitivesData() [1/2]	764
10.188.5.10 GetPrimitivesData() [2/2]	764
10.188.5.11 GetPrimitiveType()	764

10.188.5.12 SetPrimitiveData() [1/2]	764
10.188.5.13 SetPrimitiveData() [2/2]	764
10.188.5.14 SetPrimitivesData()	764
10.188.5.15 SetPrimitiveType()	765
10.188.6 Member Data Documentation	765
10.188.6.1 PrimitiveData	765
10.188.6.2 PrimitiveType	765
10.189 gdcmm::ModalityPerformedProcedureStepCreateQuery Class Reference	765
10.189.1 Detailed Description	767
10.189.2 Constructor & Destructor Documentation	767
10.189.2.1 ModalityPerformedProcedureStepCreateQuery()	767
10.189.3 Member Function Documentation	768
10.189.3.1 GetAbstractSyntaxUID()	768
10.189.3.2 GetRequiredDataSet()	768
10.189.3.3 ValidateQuery()	768
10.189.4 Friends And Related Symbol Documentation	768
10.189.4.1 QueryFactory	768
10.190 gdcmm::ModalityPerformedProcedureStepSetQuery Class Reference	769
10.190.1 Detailed Description	771
10.190.2 Constructor & Destructor Documentation	771
10.190.2.1 ModalityPerformedProcedureStepSetQuery()	771
10.190.3 Member Function Documentation	771
10.190.3.1 GetAbstractSyntaxUID()	771
10.190.3.2 GetRequiredDataSet()	771
10.190.3.3 ValidateQuery()	771
10.190.4 Friends And Related Symbol Documentation	772
10.190.4.1 QueryFactory	772
10.191 gdcmm::ModifiedEvent Class Reference	772
10.192 gdcmm::Module Class Reference	773
10.192.1 Detailed Description	774
10.192.2 Member Typedef Documentation	774
10.192.2.1 ArrayIncludeMacrosType	774
10.192.2.2 MapModuleEntry	774
10.192.3 Constructor & Destructor Documentation	775
10.192.3.1 Module()	775
10.192.4 Member Function Documentation	775
10.192.4.1 AddMacro()	775
10.192.4.2 AddModuleEntry()	775
10.192.4.3 Clear()	775

10.192.4.4 FindModuleEntryInMacros()	775
10.192.4.5 GetModuleEntryInMacros()	776
10.192.4.6 GetName()	776
10.192.4.7 SetName()	776
10.192.4.8 Verify()	776
10.192.5 Friends And Related Symbol Documentation	776
10.192.5.1 operator<<	776
10.193 gdcmm::ModuleEntry Class Reference	777
10.193.1 Detailed Description	778
10.193.2 Member Typedef Documentation	778
10.193.2.1 Description	778
10.193.3 Constructor & Destructor Documentation	779
10.193.3.1 ModuleEntry()	779
10.193.3.2 ~ModuleEntry()	779
10.193.4 Member Function Documentation	779
10.193.4.1 GetDescription()	779
10.193.4.2 GetName()	779
10.193.4.3 GetType()	779
10.193.4.4 SetDescription()	780
10.193.4.5 SetName()	780
10.193.4.6 SetType()	780
10.193.5 Friends And Related Symbol Documentation	780
10.193.5.1 operator<<	780
10.193.6 Member Data Documentation	780
10.193.6.1 DataElementType	780
10.193.6.2 DescriptionField	781
10.193.6.3 Name	781
10.194 gdcmm::Modules Class Reference	781
10.194.1 Detailed Description	782
10.194.2 Member Typedef Documentation	782
10.194.2.1 ModuleMapType	782
10.194.3 Constructor & Destructor Documentation	782
10.194.3.1 Modules()	782
10.194.4 Member Function Documentation	782
10.194.4.1 AddModule()	782
10.194.4.2 Clear()	783
10.194.4.3 GetModule()	783
10.194.4.4 IsEmpty()	783
10.194.5 Friends And Related Symbol Documentation	783

10.194.5.1 operator<<	783
10.195 gdcmm::MovePatientRootQuery Class Reference	784
10.195.1 Detailed Description	786
10.195.2 Constructor & Destructor Documentation	786
10.195.2.1 MovePatientRootQuery()	786
10.195.3 Member Function Documentation	786
10.195.3.1 GetAbstractSyntaxUID()	786
10.195.3.2 GetTagListByLevel()	787
10.195.3.3 InitializeDataSet()	787
10.195.3.4 ValidateQuery()	787
10.195.4 Friends And Related Symbol Documentation	787
10.195.4.1 QueryFactory	787
10.196 gdcmm::MoveStudyRootQuery Class Reference	788
10.196.1 Detailed Description	790
10.196.2 Constructor & Destructor Documentation	790
10.196.2.1 MoveStudyRootQuery()	790
10.196.3 Member Function Documentation	790
10.196.3.1 GetAbstractSyntaxUID()	790
10.196.3.2 GetTagListByLevel()	791
10.196.3.3 InitializeDataSet()	791
10.196.3.4 ValidateQuery()	791
10.196.4 Friends And Related Symbol Documentation	791
10.196.4.1 QueryFactory	791
10.197 gdcmm::MrProtocol Class Reference	792
10.197.1 Detailed Description	792
10.197.2 Constructor & Destructor Documentation	792
10.197.2.1 MrProtocol()	792
10.197.2.2 ~MrProtocol()	793
10.197.3 Member Function Documentation	793
10.197.3.1 FindMrProtocolByName()	793
10.197.3.2 GetMrProtocolByName()	793
10.197.3.3 GetSliceArray()	793
10.197.3.4 GetVersion()	793
10.197.3.5 Load()	793
10.197.3.6 Print()	793
10.197.4 Friends And Related Symbol Documentation	794
10.197.4.1 operator<<	794
10.198 gdcmm::network::NActionRQ Class Reference	794
10.198.1 Detailed Description	795

10.198.2 Member Function Documentation	795
10.198.2.1 ConstructPDV()	795
10.199 gdcn::network::NActionRSP Class Reference	795
10.199.1 Detailed Description	796
10.199.2 Member Function Documentation	796
10.199.2.1 ConstructPDVByDataSet()	796
10.200 gdcn::network::NCreateRQ Class Reference	797
10.200.1 Detailed Description	798
10.200.2 Member Function Documentation	798
10.200.2.1 ConstructPDV()	798
10.201 gdcn::network::NCreateRSP Class Reference	798
10.201.1 Detailed Description	799
10.201.2 Member Function Documentation	799
10.201.2.1 ConstructPDVByDataSet()	799
10.202 gdcn::network::NDeleteRQ Class Reference	800
10.202.1 Detailed Description	801
10.202.2 Member Function Documentation	801
10.202.2.1 ConstructPDV()	801
10.203 gdcn::network::NDeleteRSP Class Reference	801
10.203.1 Detailed Description	802
10.203.2 Member Function Documentation	802
10.203.2.1 ConstructPDVByDataSet()	802
10.204 gdcn::NestedModuleEntries Class Reference	803
10.204.1 Detailed Description	805
10.204.2 Member Typedef Documentation	805
10.204.2.1 SizeType	805
10.204.3 Constructor & Destructor Documentation	805
10.204.3.1 NestedModuleEntries()	805
10.204.4 Member Function Documentation	805
10.204.4.1 AddModuleEntry()	805
10.204.4.2 GetModuleEntry() [1/2]	805
10.204.4.3 GetModuleEntry() [2/2]	806
10.204.4.4 GetNumberOfModuleEntries()	806
10.204.5 Friends And Related Symbol Documentation	806
10.204.5.1 operator<<	806
10.205 gdcn::network::NEventReportRQ Class Reference	806
10.205.1 Detailed Description	807
10.205.2 Member Function Documentation	807
10.205.2.1 ConstructPDV()	807

10.206 gdcn::network::NEventReportRSP Class Reference	808
10.206.1 Detailed Description	809
10.206.2 Member Function Documentation	809
10.206.2.1 ConstructPDVByDataSet()	809
10.207 gdcn::network::NGetRQ Class Reference	809
10.207.1 Detailed Description	810
10.207.2 Member Function Documentation	810
10.207.2.1 ConstructPDV()	810
10.208 gdcn::network::NGetRSP Class Reference	811
10.208.1 Detailed Description	812
10.208.2 Member Function Documentation	812
10.208.2.1 ConstructPDVByDataSet()	812
10.209 gdcn::NoEvent Class Reference	812
10.209.1 Detailed Description	813
10.210 gdcn::network::NormalizedMessageFactory Class Reference	813
10.210.1 Member Function Documentation	813
10.210.1.1 ConstructNAction()	813
10.210.1.2 ConstructNCreate()	814
10.210.1.3 ConstructNDelete()	814
10.210.1.4 ConstructNEventReport()	814
10.210.1.5 ConstructNGet()	814
10.210.1.6 ConstructNSet()	814
10.211 gdcn::NormalizedNetworkFunctions Class Reference	814
10.211.1 Detailed Description	815
10.211.2 Member Function Documentation	815
10.211.2.1 ConstructQuery()	815
10.211.2.2 NAction()	816
10.211.2.3 NCreate()	816
10.211.2.4 NDelete()	816
10.211.2.5 NEventReport()	816
10.211.2.6 NGet()	816
10.211.2.7 NSet()	817
10.212 gdcn::network::NSetRQ Class Reference	817
10.212.1 Detailed Description	818
10.212.2 Member Function Documentation	818
10.212.2.1 ConstructPDV()	818
10.213 gdcn::network::NSetRSP Class Reference	818
10.213.1 Detailed Description	819
10.213.2 Member Function Documentation	819

10.213.2.1 ConstructPDVByDataSet()	819
10.214 gdcmm::Object Class Reference	820
10.214.1 Detailed Description	821
10.214.2 Constructor & Destructor Documentation	821
10.214.2.1 Object() [1/2]	821
10.214.2.2 ~Object()	821
10.214.2.3 Object() [2/2]	821
10.214.3 Member Function Documentation	822
10.214.3.1 operator=()	822
10.214.3.2 Print()	822
10.214.3.3 Register()	822
10.214.3.4 UnRegister()	822
10.214.4 Friends And Related Symbol Documentation	822
10.214.4.1 operator<<	822
10.214.4.2 SmartPointer	823
10.215 gdcmm::OpenSSLCryptoFactory Class Reference	823
10.215.1 Constructor & Destructor Documentation	824
10.215.1.1 OpenSSLCryptoFactory()	824
10.215.2 Member Function Documentation	825
10.215.2.1 CreateCMSProvider()	825
10.215.2.2 InitOpenSSL()	825
10.216 gdcmm::OpenSSLCryptographicMessageSyntax Class Reference	825
10.216.1 Constructor & Destructor Documentation	827
10.216.1.1 OpenSSLCryptographicMessageSyntax()	827
10.216.1.2 ~OpenSSLCryptographicMessageSyntax()	827
10.216.2 Member Function Documentation	827
10.216.2.1 Decrypt()	827
10.216.2.2 Encrypt()	827
10.216.2.3 GetCipherType()	827
10.216.2.4 ParseCertificateFile()	828
10.216.2.5 ParseKeyFile()	828
10.216.2.6 SetCipherType()	828
10.216.2.7 SetPassword()	828
10.217 gdcmm::OpenSSLP7CryptoFactory Class Reference	829
10.217.1 Constructor & Destructor Documentation	830
10.217.1.1 OpenSSLP7CryptoFactory()	830
10.217.2 Member Function Documentation	830
10.217.2.1 CreateCMSProvider()	830
10.218 gdcmm::OpenSSLP7CryptographicMessageSyntax Class Reference	831

10.218.1 Detailed Description	832
10.218.2 Constructor & Destructor Documentation	832
10.218.2.1 OpenSSLP7CryptographicMessageSyntax()	832
10.218.2.2 ~OpenSSLP7CryptographicMessageSyntax()	832
10.218.3 Member Function Documentation	832
10.218.3.1 Decrypt()	832
10.218.3.2 Encrypt()	833
10.218.3.3 GetCipherType()	833
10.218.3.4 ParseCertificateFile()	833
10.218.3.5 ParseKeyFile()	833
10.218.3.6 SetCipherType()	833
10.218.3.7 SetPassword()	834
10.219 gdcmm::Orientation Class Reference	834
10.219.1 Detailed Description	835
10.219.2 Member Enumeration Documentation	835
10.219.2.1 OrientationType	835
10.219.3 Constructor & Destructor Documentation	835
10.219.3.1 Orientation()	835
10.219.3.2 ~Orientation()	835
10.219.4 Member Function Documentation	836
10.219.4.1 GetLabel()	836
10.219.4.2 GetMajorAxisFromPatientRelativeDirectionCosine()	836
10.219.4.3 GetObliquityThresholdCosineValue()	836
10.219.4.4 GetType()	836
10.219.4.5 Print()	836
10.219.4.6 SetObliquityThresholdCosineValue()	837
10.219.5 Friends And Related Symbol Documentation	837
10.219.5.1 operator<<	837
10.220 gdcmm::Overlay Class Reference	837
10.220.1 Detailed Description	840
10.220.2 Member Enumeration Documentation	840
10.220.2.1 OverlayType	840
10.220.3 Constructor & Destructor Documentation	840
10.220.3.1 Overlay() [1/2]	840
10.220.3.2 ~Overlay()	841
10.220.3.3 Overlay() [2/2]	841
10.220.4 Member Function Documentation	841
10.220.4.1 Decompress()	841
10.220.4.2 GetBitPosition()	841

10.220.4.3 GetBitsAllocated()	841
10.220.4.4 GetColumns()	841
10.220.4.5 GetDescription()	841
10.220.4.6 GetGroup()	842
10.220.4.7 GetOrigin()	842
10.220.4.8 GetOverlayData()	842
10.220.4.9 GetOverlayTypeAsString()	842
10.220.4.10 GetOverlayTypeFromString()	842
10.220.4.11 GetRows()	842
10.220.4.12 GetType()	842
10.220.4.13 GetTypeAsEnum()	843
10.220.4.14 GetUnpackBuffer()	843
10.220.4.15 GetUnpackBufferLength()	843
10.220.4.16 GrabOverlayFromPixelData()	843
10.220.4.17 IsEmpty()	843
10.220.4.18 IsInPixelData() [1/2]	843
10.220.4.19 IsInPixelData() [2/2]	843
10.220.4.20 IsZero()	844
10.220.4.21 operator=()	844
10.220.4.22 Print()	844
10.220.4.23 SetBitPosition()	844
10.220.4.24 SetBitsAllocated()	844
10.220.4.25 SetColumns()	844
10.220.4.26 SetDescription()	845
10.220.4.27 SetFrameOrigin()	845
10.220.4.28 SetGroup()	845
10.220.4.29 SetNumberOfFrames()	845
10.220.4.30 SetOrigin()	845
10.220.4.31 SetOverlay()	845
10.220.4.32 SetRows()	846
10.220.4.33 SetType()	846
10.220.4.34 Update()	846
10.221 gdcm::ParseException Class Reference	846
10.221.1 Detailed Description	847
10.221.2 Constructor & Destructor Documentation	848
10.221.2.1 ParseException() [1/2]	848
10.221.2.2 ~ParseException()	848
10.221.2.3 ParseException() [2/2]	848
10.221.3 Member Function Documentation	848

10.221.3.1 GetLastElement()	848
10.221.3.2 operator=()	848
10.221.3.3 SetLastElement()	848
10.222 gdcM::Parser Class Reference	849
10.222.1 Detailed Description	850
10.222.2 Member Typedef Documentation	850
10.222.2.1 EndElementHandler	850
10.222.2.2 StartElementHandler	850
10.222.3 Member Enumeration Documentation	850
10.222.3.1 ErrorType	850
10.222.4 Constructor & Destructor Documentation	851
10.222.4.1 Parser()	851
10.222.4.2 ~Parser()	851
10.222.5 Member Function Documentation	851
10.222.5.1 GetBuffer()	851
10.222.5.2 GetCurrentByteIndex()	851
10.222.5.3 GetErrorCode()	851
10.222.5.4 GetErrorString()	851
10.222.5.5 GetUserData()	851
10.222.5.6 Parse()	851
10.222.5.7 ParseBuffer()	852
10.222.5.8 Process()	852
10.222.5.9 SetElementHandler()	852
10.222.5.10 SetUserData()	852
10.223 gdcM::Patient Class Reference	852
10.223.1 Detailed Description	852
10.223.2 Constructor & Destructor Documentation	853
10.223.2.1 Patient()	853
10.224 gdcM::network::PDataTFPDU Class Reference	853
10.224.1 Detailed Description	854
10.224.2 Member Typedef Documentation	854
10.224.2.1 SizeType	854
10.224.3 Constructor & Destructor Documentation	854
10.224.3.1 PDataTFPDU()	854
10.224.4 Member Function Documentation	855
10.224.4.1 AddPresentationDataValue()	855
10.224.4.2 GetNumberOfPresentationDataValues()	855
10.224.4.3 GetPresentationDataValue()	855
10.224.4.4 IsLastFragment()	855

10.224.4.5 Print()	855
10.224.4.6 Read()	855
10.224.4.7 ReadInto()	856
10.224.4.8 Size()	856
10.224.4.9 Write()	856
10.225 gdcmm::PDBelement Class Reference	856
10.225.1 Detailed Description	857
10.225.2 Constructor & Destructor Documentation	857
10.225.2.1 PDBelement()	857
10.225.3 Member Function Documentation	857
10.225.3.1 GetName()	857
10.225.3.2 GetValue()	858
10.225.3.3 operator==(())	858
10.225.3.4 SetName()	858
10.225.3.5 SetValue()	858
10.225.4 Friends And Related Symbol Documentation	858
10.225.4.1 operator<<	858
10.225.5 Member Data Documentation	859
10.225.5.1 NameField	859
10.225.5.2 ValueField	859
10.226 gdcmm::PDBHeader Class Reference	859
10.226.1 Detailed Description	860
10.226.2 Constructor & Destructor Documentation	860
10.226.2.1 PDBHeader()	860
10.226.2.2 ~PDBHeader()	860
10.226.3 Member Function Documentation	860
10.226.3.1 FindPDBelementByName()	860
10.226.3.2 GetPDBeEnd()	861
10.226.3.3 GetPDBelementByName()	861
10.226.3.4 GetPDBInfoTag()	861
10.226.3.5 LoadFromDataElement()	861
10.226.3.6 Print()	861
10.226.4 Friends And Related Symbol Documentation	861
10.226.4.1 operator<<	861
10.227 gdcmm::PDFCodec Class Reference	862
10.227.1 Detailed Description	863
10.227.2 Constructor & Destructor Documentation	863
10.227.2.1 PDFCodec()	863
10.227.2.2 ~PDFCodec()	864

10.227.3 Member Function Documentation	864
10.227.3.1 CanCode()	864
10.227.3.2 CanDecode()	864
10.227.3.3 Decode()	864
10.228 gdcm::network::PDUFactory Class Reference	864
10.228.1 Detailed Description	865
10.228.2 Member Function Documentation	865
10.228.2.1 ConstructAbortPDU()	865
10.228.2.2 ConstructPDU()	865
10.228.2.3 ConstructReleasePDU()	866
10.228.2.4 CreateCEchoPDU()	866
10.228.2.5 CreateCFindPDU()	866
10.228.2.6 CreateCMovePDU()	866
10.228.2.7 CreateCStoreRQPDU()	866
10.228.2.8 CreateCStoreRSPPDU()	866
10.228.2.9 CreateNActionPDU()	866
10.228.2.10 CreateNCreatePDU()	867
10.228.2.11 CreateNDeletePDU()	867
10.228.2.12 CreateNEventReportPDU()	867
10.228.2.13 CreateNGetPDU()	867
10.228.2.14 CreateNSetPDU()	867
10.228.2.15 DetermineEventByPDU()	867
10.228.2.16 GetPDVs()	867
10.229 gdcm::PersonName Class Reference	868
10.229.1 Detailed Description	868
10.229.2 Member Function Documentation	868
10.229.2.1 GetMaxLength()	868
10.229.2.2 GetNumberOfComponents()	869
10.229.2.3 Print()	869
10.229.2.4 SetBlob()	869
10.229.2.5 SetComponents() [1/2]	869
10.229.2.6 SetComponents() [2/2]	869
10.229.3 Member Data Documentation	869
10.229.3.1 Component	869
10.229.3.2 MaxLength	870
10.229.3.3 MaxNumberOfComponents	870
10.229.3.4 Padding	870
10.229.3.5 Separator	870
10.230 gdcm::PGXCodec Class Reference	870

10.230.1 Detailed Description	873
10.230.2 Constructor & Destructor Documentation	873
10.230.2.1 PGXCodec()	873
10.230.2.2 ~PGXCodec()	873
10.230.3 Member Function Documentation	873
10.230.3.1 CanCode()	873
10.230.3.2 CanDecode()	874
10.230.3.3 Clone()	874
10.230.3.4 GetHeaderInfo()	874
10.230.3.5 Read()	874
10.230.3.6 Write()	874
10.231 gdcm::PhotometricInterpretation Class Reference	874
10.231.1 Detailed Description	875
10.231.2 Member Enumeration Documentation	876
10.231.2.1 PType	876
10.231.3 Constructor & Destructor Documentation	876
10.231.3.1 PhotometricInterpretation()	876
10.231.4 Member Function Documentation	876
10.231.4.1 GetPString()	876
10.231.4.2 GetPType()	877
10.231.4.3 GetSamplesPerPixel()	877
10.231.4.4 GetString()	877
10.231.4.5 GetType()	877
10.231.4.6 IsLossless()	877
10.231.4.7 IsLossy()	877
10.231.4.8 IsRetired()	877
10.231.4.9 IsSameColorSpace()	877
10.231.4.10 operator PType()	878
10.231.5 Friends And Related Symbol Documentation	878
10.231.5.1 operator<<	878
10.232 gdcm::PixelFormat Class Reference	878
10.232.1 Detailed Description	880
10.232.2 Member Enumeration Documentation	880
10.232.2.1 ScalarType	880
10.232.3 Constructor & Destructor Documentation	881
10.232.3.1 PixelFormat() [1/3]	881
10.232.3.2 PixelFormat() [2/3]	881
10.232.3.3 PixelFormat() [3/3]	881
10.232.4 Member Function Documentation	881

10.232.4.1 GetBitsAllocated()	881
10.232.4.2 GetBitsStored()	881
10.232.4.3 GetHighBit()	882
10.232.4.4 GetMax()	882
10.232.4.5 GetMin()	882
10.232.4.6 GetPixelRepresentation()	882
10.232.4.7 GetPixelSize()	882
10.232.4.8 GetSamplesPerPixel()	883
10.232.4.9 GetScalarType()	883
10.232.4.10 GetScalarTypeAsString()	883
10.232.4.11 IsCompatible()	883
10.232.4.12 IsValid()	883
10.232.4.13 operator ScalarType()	884
10.232.4.14 operator!=() [1/2]	884
10.232.4.15 operator!=() [2/2]	884
10.232.4.16 operator==() [1/2]	884
10.232.4.17 operator==() [2/2]	884
10.232.4.18 Print()	884
10.232.4.19 SetBitsAllocated()	885
10.232.4.20 SetBitsStored()	885
10.232.4.21 SetHighBit()	885
10.232.4.22 SetPixelRepresentation()	885
10.232.4.23 SetSamplesPerPixel()	885
10.232.4.24 SetScalarType()	886
10.232.4.25 Validate()	886
10.232.5 Friends And Related Symbol Documentation	886
10.232.5.1 Bitmap	886
10.232.5.2 operator<<	886
10.233 gdcm::Pixmap Class Reference	887
10.233.1 Detailed Description	890
10.233.2 Constructor & Destructor Documentation	891
10.233.2.1 Pixmap()	891
10.233.2.2 ~Pixmap()	891
10.233.3 Member Function Documentation	891
10.233.3.1 AreOverlaysInPixelData()	891
10.233.3.2 GetCurve() [1/2]	891
10.233.3.3 GetCurve() [2/2]	891
10.233.3.4 GetIconImage() [1/2]	891
10.233.3.5 GetIconImage() [2/2]	892

10.233.3.6 GetNumberOfCurves()	892
10.233.3.7 GetNumberOfOverlays()	892
10.233.3.8 GetOverlay() [1/2]	892
10.233.3.9 GetOverlay() [2/2]	892
10.233.3.10 Print()	892
10.233.3.11 RemoveOverlay()	893
10.233.3.12 SetIconImage()	893
10.233.3.13 SetNumberOfCurves()	893
10.233.3.14 SetNumberOfOverlays()	893
10.233.3.15 UnusedBitsPresentInPixelData()	893
10.233.4 Member Data Documentation	893
10.233.4.1 Curves	893
10.233.4.2 Icon	894
10.233.4.3 Overlays	894
10.234 gdcm::PixmapReader Class Reference	894
10.234.1 Detailed Description	896
10.234.2 Constructor & Destructor Documentation	897
10.234.2.1 PixmapReader()	897
10.234.2.2 ~PixmapReader()	897
10.234.3 Member Function Documentation	897
10.234.3.1 GetPixmap() [1/2]	897
10.234.3.2 GetPixmap() [2/2]	897
10.234.3.3 Read()	897
10.234.3.4 ReadACRNEMAImage()	898
10.234.3.5 ReadImage()	898
10.234.3.6 ReadImageInternal()	898
10.234.4 Member Data Documentation	898
10.234.4.1 PixelData	898
10.235 gdcm::PixmapToPixmapFilter Class Reference	898
10.235.1 Detailed Description	900
10.235.2 Constructor & Destructor Documentation	900
10.235.2.1 PixmapToPixmapFilter()	900
10.235.2.2 ~PixmapToPixmapFilter()	900
10.235.3 Member Function Documentation	900
10.235.3.1 GetInput()	900
10.235.3.2 GetOutput()	900
10.235.3.3 GetOutputAsPixmap()	901
10.236 gdcm::PixmapWriter Class Reference	901
10.236.1 Detailed Description	903

10.236.2 Constructor & Destructor Documentation	904
10.236.2.1 PixmapWriter()	904
10.236.2.2 ~PixmapWriter()	904
10.236.3 Member Function Documentation	904
10.236.3.1 DolconImage()	904
10.236.3.2 GetImage() [1/2]	904
10.236.3.3 GetImage() [2/2]	904
10.236.3.4 GetPixmap() [1/2]	904
10.236.3.5 GetPixmap() [2/2]	905
10.236.3.6 PrepareWrite()	905
10.236.3.7 SetImage()	905
10.236.3.8 SetPixmap()	905
10.236.3.9 Write()	905
10.236.4 Member Data Documentation	906
10.236.4.1 PixelData	906
10.237 gdcmm::PNMCodec Class Reference	906
10.237.1 Detailed Description	909
10.237.2 Constructor & Destructor Documentation	909
10.237.2.1 PNMCodec()	909
10.237.2.2 ~PNMCodec()	909
10.237.3 Member Function Documentation	909
10.237.3.1 CanCode()	909
10.237.3.2 CanDecode()	910
10.237.3.3 Clone()	910
10.237.3.4 GetBufferLength()	910
10.237.3.5 GetHeaderInfo()	910
10.237.3.6 Read()	910
10.237.3.7 SetBufferLength()	910
10.237.3.8 Write()	911
10.238 gdcmm::Preamble Class Reference	911
10.238.1 Detailed Description	912
10.238.2 Constructor & Destructor Documentation	912
10.238.2.1 Preamble() [1/2]	912
10.238.2.2 ~Preamble()	912
10.238.2.3 Preamble() [2/2]	912
10.238.3 Member Function Documentation	912
10.238.3.1 Clear()	912
10.238.3.2 Create()	913
10.238.3.3 GetInternal()	913

10.238.3.4 GetLength()	913
10.238.3.5 IsEmpty()	913
10.238.3.6 IsValid()	913
10.238.3.7 operator=()	913
10.238.3.8 Print()	913
10.238.3.9 Read()	914
10.238.3.10 Remove()	914
10.238.3.11 Valid()	914
10.238.3.12 Write()	914
10.238.4 Friends And Related Symbol Documentation	914
10.238.4.1 operator<<	914
10.239 gdcmm::PresentationContext Class Reference	915
10.239.1 Detailed Description	916
10.239.2 Member Typedef Documentation	916
10.239.2.1 SizeType	916
10.239.2.2 TransferSyntaxArrayType	916
10.239.3 Constructor & Destructor Documentation	916
10.239.3.1 PresentationContext() [1/2]	916
10.239.3.2 PresentationContext() [2/2]	916
10.239.4 Member Function Documentation	917
10.239.4.1 AddTransferSyntax()	917
10.239.4.2 GetAbstractSyntax()	917
10.239.4.3 GetNumberOfTransferSyntaxes()	917
10.239.4.4 GetPresentationContextID()	917
10.239.4.5 GetTransferSyntax()	917
10.239.4.6 operator==(())	917
10.239.4.7 Print()	917
10.239.4.8 SetAbstractSyntax()	918
10.239.4.9 SetPresentationContextID()	918
10.239.5 Member Data Documentation	918
10.239.5.1 AbstractSyntax	918
10.239.5.2 ID	918
10.239.5.3 TransferSyntaxes	918
10.240 gdcmm::network::PresentationContextAC Class Reference	918
10.240.1 Detailed Description	919
10.240.2 Constructor & Destructor Documentation	919
10.240.2.1 PresentationContextAC()	919
10.240.3 Member Function Documentation	919
10.240.3.1 GetPresentationContextID()	919

10.240.3.2 GetReason()	919
10.240.3.3 GetTransferSyntax()	919
10.240.3.4 Print()	920
10.240.3.5 Read()	920
10.240.3.6 SetPresentationContextID()	920
10.240.3.7 SetReason()	920
10.240.3.8 SetTransferSyntax()	920
10.240.3.9 Size()	920
10.240.3.10 Write()	920
10.241 gdcm::PresentationContextGenerator Class Reference	921
10.241.1 Detailed Description	921
10.241.2 Member Typedef Documentation	922
10.241.2.1 PresentationContextArrayType	922
10.241.2.2 SizeType	922
10.241.3 Constructor & Destructor Documentation	922
10.241.3.1 PresentationContextGenerator()	922
10.241.4 Member Function Documentation	922
10.241.4.1 AddFromFile()	922
10.241.4.2 AddPresentationContext()	922
10.241.4.3 GenerateFromFilenames()	922
10.241.4.4 GenerateFromUID()	923
10.241.4.5 GetDefaultTransferSyntax()	923
10.241.4.6 GetPresentationContexts()	923
10.241.4.7 SetDefaultTransferSyntax()	923
10.241.4.8 SetMergeModeToAbstractSyntax()	923
10.241.4.9 SetMergeModeToTransferSyntax()	923
10.242 gdcm::network::PresentationContextRQ Class Reference	924
10.242.1 Detailed Description	924
10.242.2 Member Typedef Documentation	924
10.242.2.1 SizeType	924
10.242.3 Constructor & Destructor Documentation	925
10.242.3.1 PresentationContextRQ() [1/3]	925
10.242.3.2 PresentationContextRQ() [2/3]	925
10.242.3.3 PresentationContextRQ() [3/3]	925
10.242.4 Member Function Documentation	925
10.242.4.1 AddTransferSyntax()	925
10.242.4.2 GetAbstractSyntax() [1/2]	925
10.242.4.3 GetAbstractSyntax() [2/2]	925
10.242.4.4 GetNumberOfTransferSyntaxes()	925

10.242.4.5 GetPresentationContextID()	926
10.242.4.6 GetTransferSyntax() [1/2]	926
10.242.4.7 GetTransferSyntax() [2/2]	926
10.242.4.8 GetTransferSyntaxes()	926
10.242.4.9 operator==()	926
10.242.4.10 Print()	926
10.242.4.11 Read()	926
10.242.4.12 SetAbstractSyntax()	926
10.242.4.13 SetPresentationContextID()	927
10.242.4.14 Size()	927
10.242.4.15 Write()	927
10.243 gdcmm::network::PresentationDataValue Class Reference	927
10.243.1 Detailed Description	928
10.243.2 Constructor & Destructor Documentation	928
10.243.2.1 PresentationDataValue()	928
10.243.3 Member Function Documentation	928
10.243.3.1 ConcatenatePDVBlobs()	928
10.243.3.2 ConcatenatePDVBlobsAsExplicit()	928
10.243.3.3 GetBlob()	928
10.243.3.4 GetIsCommand()	928
10.243.3.5 GetIsLastFragment()	929
10.243.3.6 GetMessageHeader()	929
10.243.3.7 GetPresentationContextID()	929
10.243.3.8 Print()	929
10.243.3.9 Read()	929
10.243.3.10 ReadInto()	929
10.243.3.11 SetBlob()	929
10.243.3.12 SetCommand()	929
10.243.3.13 SetDataSet()	930
10.243.3.14 SetLastFragment()	930
10.243.3.15 SetMessageHeader()	930
10.243.3.16 SetPresentationContextID()	930
10.243.3.17 Size()	930
10.243.3.18 Write()	930
10.244 gdcmm::Printer Class Reference	931
10.244.1 Detailed Description	932
10.244.2 Member Enumeration Documentation	932
10.244.2.1 PrintStyles	932
10.244.3 Constructor & Destructor Documentation	933

10.244.3.1 Printer()	933
10.244.3.2 ~Printer()	933
10.244.4 Member Function Documentation	933
10.244.4.1 GetPrintStyle()	933
10.244.4.2 Print()	933
10.244.4.3 PrintDataElement()	934
10.244.4.4 PrintDataSet()	934
10.244.4.5 PrintSQ()	934
10.244.4.6 SetColor()	934
10.244.4.7 SetFile()	934
10.244.4.8 SetStyle()	935
10.244.5 Member Data Documentation	935
10.244.5.1 F	935
10.244.5.2 MaxPrintLength	935
10.244.5.3 PrintStyle	935
10.245 gdcm::PrivateDict Class Reference	935
10.245.1 Detailed Description	936
10.245.2 Constructor & Destructor Documentation	936
10.245.2.1 PrivateDict()	936
10.245.2.2 ~PrivateDict()	936
10.245.3 Member Function Documentation	936
10.245.3.1 AddDictEntry()	936
10.245.3.2 FindDictEntry()	936
10.245.3.3 GetDictEntry()	937
10.245.3.4 IsEmpty()	937
10.245.3.5 LoadDefault()	937
10.245.3.6 PrintXML()	937
10.245.3.7 RemoveDictEntry()	937
10.245.4 Friends And Related Symbol Documentation	937
10.245.4.1 Dicts	937
10.245.4.2 operator<<	938
10.246 gdcm::PrivateTag Class Reference	938
10.246.1 Detailed Description	940
10.246.2 Constructor & Destructor Documentation	941
10.246.2.1 PrivateTag() [1/2]	941
10.246.2.2 PrivateTag() [2/2]	941
10.246.3 Member Function Documentation	941
10.246.3.1 GetAsDataElement()	941
10.246.3.2 GetOwner()	941

10.246.3.3 operator"!=() [1 / 2]	941
10.246.3.4 operator"!=() [2 / 2]	942
10.246.3.5 operator<()	942
10.246.3.6 operator=()	942
10.246.3.7 operator==() [1 / 2]	942
10.246.3.8 operator==() [2 / 2]	942
10.246.3.9 ReadFromCommaSeparatedString()	942
10.246.3.10 SetOwner()	943
10.246.4 Friends And Related Symbol Documentation	943
10.246.4.1 operator<<	943
10.247 gdcm::ProgressEvent Class Reference	943
10.247.1 Detailed Description	945
10.247.2 Member Typedef Documentation	945
10.247.2.1 Self	945
10.247.2.2 Superclass	945
10.247.3 Constructor & Destructor Documentation	945
10.247.3.1 ProgressEvent() [1 / 2]	945
10.247.3.2 ~ProgressEvent()	945
10.247.3.3 ProgressEvent() [2 / 2]	945
10.247.4 Member Function Documentation	946
10.247.4.1 CheckEvent()	946
10.247.4.2 GetEventName()	946
10.247.4.3 GetProgress()	946
10.247.4.4 MakeObject()	946
10.247.4.5 operator=()	946
10.247.4.6 SetProgress()	946
10.248 gdcm::PVRGCodec Class Reference	947
10.248.1 Detailed Description	950
10.248.2 Constructor & Destructor Documentation	950
10.248.2.1 PVRGCodec()	950
10.248.2.2 ~PVRGCodec()	950
10.248.3 Member Function Documentation	950
10.248.3.1 CanCode()	950
10.248.3.2 CanDecode()	950
10.248.3.3 Clone()	951
10.248.3.4 Code()	951
10.248.3.5 Decode()	951
10.248.3.6 SetLossyFlag()	951
10.249 gdcm::PythonFilter Class Reference	951

10.249.1 Detailed Description	952
10.249.2 Constructor & Destructor Documentation	952
10.249.2.1 PythonFilter()	952
10.249.2.2 ~PythonFilter()	952
10.249.3 Member Function Documentation	952
10.249.3.1 GetFile() [1/2]	952
10.249.3.2 GetFile() [2/2]	952
10.249.3.3 SetDicts()	952
10.249.3.4 SetFile()	953
10.249.3.5 ToPyObject()	953
10.249.3.6 UseDictAlways()	953
10.250 gdcm::QueryBase Class Reference	953
10.250.1 Detailed Description	954
10.250.2 Constructor & Destructor Documentation	954
10.250.2.1 ~QueryBase()	954
10.250.3 Member Function Documentation	954
10.250.3.1 GetAllRequiredTags()	954
10.250.3.2 GetAllTags()	954
10.250.3.3 GetHierachicalSearchTags()	955
10.250.3.4 GetName()	955
10.250.3.5 GetOptionalTags()	955
10.250.3.6 GetQueryLevel()	955
10.250.3.7 GetRequiredTags()	955
10.250.3.8 GetUniqueTags()	955
10.251 gdcm::QueryFactory Class Reference	956
10.251.1 Detailed Description	956
10.251.2 Member Function Documentation	956
10.251.2.1 GetCharacterFromCurrentLocale()	956
10.251.2.2 ListCharSets()	956
10.251.2.3 ProduceCharacterSetDataElement()	957
10.251.2.4 ProduceQuery() [1/2]	957
10.251.2.5 ProduceQuery() [2/2]	957
10.252 gdcm::QueryImage Class Reference	957
10.252.1 Detailed Description	958
10.252.2 Member Function Documentation	958
10.252.2.1 GetHierachicalSearchTags()	958
10.252.2.2 GetName()	959
10.252.2.3 GetOptionalTags()	959
10.252.2.4 GetQueryLevel()	959

10.252.2.5 GetRequiredTags()	959
10.252.2.6 GetUniqueTags()	959
10.253 gdcM::QueryPatient Class Reference	960
10.253.1 Detailed Description	961
10.253.2 Member Function Documentation	961
10.253.2.1 GetHierarchicalSearchTags()	961
10.253.2.2 GetName()	961
10.253.2.3 GetOptionalTags()	961
10.253.2.4 GetQueryLevel()	961
10.253.2.5 GetRequiredTags()	962
10.253.2.6 GetUniqueTags()	962
10.254 gdcM::QuerySeries Class Reference	962
10.254.1 Detailed Description	963
10.254.2 Member Function Documentation	963
10.254.2.1 GetHierarchicalSearchTags()	963
10.254.2.2 GetName()	964
10.254.2.3 GetOptionalTags()	964
10.254.2.4 GetQueryLevel()	964
10.254.2.5 GetRequiredTags()	964
10.254.2.6 GetUniqueTags()	964
10.255 gdcM::QueryStudy Class Reference	965
10.255.1 Detailed Description	966
10.255.2 Member Function Documentation	966
10.255.2.1 GetHierarchicalSearchTags()	966
10.255.2.2 GetName()	966
10.255.2.3 GetOptionalTags()	966
10.255.2.4 GetQueryLevel()	966
10.255.2.5 GetRequiredTags()	967
10.255.2.6 GetUniqueTags()	967
10.256 gdcM::RAWCodec Class Reference	967
10.256.1 Detailed Description	970
10.256.2 Constructor & Destructor Documentation	970
10.256.2.1 RAWCodec()	970
10.256.2.2 ~RAWCodec()	970
10.256.3 Member Function Documentation	970
10.256.3.1 CanCode()	970
10.256.3.2 CanDecode()	970
10.256.3.3 Clone()	971
10.256.3.4 Code()	971

10.256.3.5 Decode()	971
10.256.3.6 DecodeByStreams()	971
10.256.3.7 DecodeBytes()	971
10.256.3.8 GetHeaderInfo()	972
10.257 gdcm::Reader Class Reference	972
10.257.1 Detailed Description	974
10.257.2 Constructor & Destructor Documentation	975
10.257.2.1 Reader()	975
10.257.2.2 ~Reader()	975
10.257.3 Member Function Documentation	975
10.257.3.1 CanRead()	975
10.257.3.2 GetFile() [1/2]	975
10.257.3.3 GetFile() [2/2]	975
10.257.3.4 GetStreamCurrentPosition()	976
10.257.3.5 GetStreamPtr()	976
10.257.3.6 Read()	976
10.257.3.7 ReadDataSet()	976
10.257.3.8 ReadMetaInformation()	976
10.257.3.9 ReadPreamble()	977
10.257.3.10 ReadSelectedPrivateTags()	977
10.257.3.11 ReadSelectedTags()	977
10.257.3.12 ReadUpToTag()	977
10.257.3.13 SetFile()	977
10.257.3.14 SetFileName()	978
10.257.3.15 SetStream()	978
10.257.4 Friends And Related Symbol Documentation	978
10.257.4.1 StreamImageReader	978
10.257.5 Member Data Documentation	979
10.257.5.1 F	979
10.258 gdcm::RealWorldValueMappingContent Struct Reference	979
10.258.1 Member Data Documentation	980
10.258.1.1 CodeMeaning	980
10.258.1.2 CodeValue	980
10.258.1.3 RealWorldValueIntercept	980
10.258.1.4 RealWorldValueSlope	980
10.259 gdcm::Region Class Reference	980
10.259.1 Detailed Description	981
10.259.2 Constructor & Destructor Documentation	981
10.259.2.1 Region()	981

10.259.2.2 ~Region()	981
10.259.3 Member Function Documentation	981
10.259.3.1 Area()	981
10.259.3.2 Clone()	982
10.259.3.3 ComputeBoundingBox()	982
10.259.3.4 Empty()	982
10.259.3.5 IsValid()	982
10.259.3.6 Print()	982
10.260 gdcm::Rescaler Class Reference	983
10.260.1 Detailed Description	983
10.260.2 Constructor & Destructor Documentation	984
10.260.2.1 Rescaler()	984
10.260.2.2 ~Rescaler()	984
10.260.3 Member Function Documentation	984
10.260.3.1 ComputeInterceptSlopePixelType()	984
10.260.3.2 ComputePixelTypeFromMinMax()	985
10.260.3.3 GetIntercept()	985
10.260.3.4 GetSlope()	985
10.260.3.5 InverseRescale()	985
10.260.3.6 InverseRescaleFunctionIntoBestFit()	985
10.260.3.7 Rescale()	985
10.260.3.8 RescaleFunctionIntoBestFit()	986
10.260.3.9 SetIntercept()	986
10.260.3.10 SetMinMaxForPixelType()	986
10.260.3.11 SetPixelFormat()	986
10.260.3.12 SetSlope()	986
10.260.3.13 SetTargetPixelType()	987
10.260.3.14 SetUseTargetPixelType()	987
10.261 gdcm::RLECodec Class Reference	987
10.261.1 Detailed Description	990
10.261.2 Constructor & Destructor Documentation	990
10.261.2.1 RLECodec()	990
10.261.2.2 ~RLECodec()	990
10.261.3 Member Function Documentation	991
10.261.3.1 AppendFrameEncode()	991
10.261.3.2 AppendRowEncode()	991
10.261.3.3 CanCode()	991
10.261.3.4 CanDecode()	991
10.261.3.5 Clone()	991

10.261.3.6 Code()	992
10.261.3.7 Decode()	992
10.261.3.8 DecodeByStreams()	992
10.261.3.9 DecodeExtent()	992
10.261.3.10 GetBufferLength()	992
10.261.3.11 GetHeaderInfo()	993
10.261.3.12 IsFrameEncoder()	993
10.261.3.13 IsRowEncoder()	993
10.261.3.14 SetBufferLength()	993
10.261.3.15 SetLength()	993
10.261.3.16 StartEncode()	993
10.261.3.17 StopEncode()	993
10.261.4 Friends And Related Symbol Documentation	994
10.261.4.1 ImageRegionReader	994
10.262 gdcm::network::RoleSelectionSub Class Reference	994
10.262.1 Detailed Description	994
10.262.2 Constructor & Destructor Documentation	994
10.262.2.1 RoleSelectionSub()	994
10.262.3 Member Function Documentation	995
10.262.3.1 Print()	995
10.262.3.2 Read()	995
10.262.3.3 SetTuple()	995
10.262.3.4 Size()	995
10.262.3.5 Write()	995
10.263 gdcm::Scanner Class Reference	996
10.263.1 Detailed Description	999
10.263.2 Member Typedef Documentation	999
10.263.2.1 ConstIterator	999
10.263.2.2 MappingType	999
10.263.2.3 TagToValue	999
10.263.2.4 TagToValueValueType	1000
10.263.2.5 ValuesType	1000
10.263.3 Constructor & Destructor Documentation	1000
10.263.3.1 Scanner()	1000
10.263.3.2 ~Scanner()	1000
10.263.4 Member Function Documentation	1000
10.263.4.1 AddPrivateTag()	1000
10.263.4.2 AddSkipTag()	1000
10.263.4.3 AddTag()	1001

10.263.4.4 Begin()	1001
10.263.4.5 ClearSkipTags()	1001
10.263.4.6 ClearTags()	1001
10.263.4.7 End()	1001
10.263.4.8 GetAllFileNamesFromTagToValue()	1001
10.263.4.9 GetFilenameFromTagToValue()	1001
10.263.4.10 GetFileNames()	1002
10.263.4.11 GetKeys()	1002
10.263.4.12 GetMapping()	1002
10.263.4.13 GetMappingFromTagToValue()	1002
10.263.4.14 GetMappings()	1002
10.263.4.15 GetOrderedValues()	1002
10.263.4.16 GetValue()	1003
10.263.4.17 GetValues() [1/2]	1003
10.263.4.18 GetValues() [2/2]	1003
10.263.4.19 IsKey()	1003
10.263.4.20 New()	1004
10.263.4.21 Print()	1004
10.263.4.22 PrintTable()	1004
10.263.4.23 ProcessPublicTag()	1004
10.263.4.24 Scan()	1004
10.263.5 Friends And Related Symbol Documentation	1005
10.263.5.1 operator<<	1005
10.264 gdcm::Scanner2 Class Reference	1005
10.264.1 Detailed Description	1008
10.264.2 Member Typedef Documentation	1009
10.264.2.1 PrivateConstIterator	1009
10.264.2.2 PrivateMappingType	1009
10.264.2.3 PrivateTagToValue	1009
10.264.2.4 PrivateTagToValueValueType	1009
10.264.2.5 PublicConstIterator	1009
10.264.2.6 PublicMappingType	1009
10.264.2.7 PublicTagToValue	1009
10.264.2.8 PublicTagToValueValueType	1009
10.264.2.9 ValuesType	1010
10.264.3 Constructor & Destructor Documentation	1010
10.264.3.1 Scanner2()	1010
10.264.3.2 ~Scanner2()	1010
10.264.4 Member Function Documentation	1010

10.264.4.1 AddPrivateTag()	1010
10.264.4.2 AddPublicTag()	1010
10.264.4.3 AddSkipTag()	1010
10.264.4.4 Begin()	1010
10.264.4.5 ClearPrivateTags()	1011
10.264.4.6 ClearPublicTags()	1011
10.264.4.7 ClearSkipTags()	1011
10.264.4.8 End()	1011
10.264.4.9 GetAllFilenamesFromPrivateTagToValue()	1011
10.264.4.10 GetAllFilenamesFromPublicTagToValue()	1011
10.264.4.11 GetFilenameFromPrivateTagToValue()	1011
10.264.4.12 GetFilenameFromPublicTagToValue()	1011
10.264.4.13 GetFilenames()	1012
10.264.4.14 GetKeys()	1012
10.264.4.15 GetMappingFromPrivateTagToValue()	1012
10.264.4.16 GetMappingFromPublicTagToValue()	1012
10.264.4.17 GetPrivateMapping()	1012
10.264.4.18 GetPrivateMappings()	1012
10.264.4.19 GetPrivateOrderedValues()	1012
10.264.4.20 GetPrivateValue()	1013
10.264.4.21 GetPrivateValues()	1013
10.264.4.22 GetPublicMapping()	1013
10.264.4.23 GetPublicMappings()	1013
10.264.4.24 GetPublicOrderedValues()	1013
10.264.4.25 GetPublicValue()	1013
10.264.4.26 GetPublicValues()	1014
10.264.4.27 GetValues()	1014
10.264.4.28 IsKey()	1014
10.264.4.29 New()	1014
10.264.4.30 Print()	1014
10.264.4.31 PrintTable()	1014
10.264.4.32 PrivateBegin()	1015
10.264.4.33 PrivateEnd()	1015
10.264.4.34 ProcessPrivateTag()	1015
10.264.4.35 ProcessPublicTag()	1015
10.264.4.36 Scan()	1015
10.264.5 Friends And Related Symbol Documentation	1015
10.264.5.1 operator<<	1015
10.265 gdcm::Segment Class Reference	1016

10.265.1 Detailed Description	1018
10.265.2 Member Typedef Documentation	1018
10.265.2.1 BasicCodedEntryVector	1018
10.265.2.2 SurfaceVector	1018
10.265.3 Member Enumeration Documentation	1018
10.265.3.1 ALGOType	1018
10.265.4 Constructor & Destructor Documentation	1019
10.265.4.1 Segment()	1019
10.265.4.2 ~Segment()	1019
10.265.5 Member Function Documentation	1019
10.265.5.1 AddSurface()	1019
10.265.5.2 GetALGOType()	1019
10.265.5.3 GetALGOTypeString()	1019
10.265.5.4 GetAnatomicRegion() [1/2]	1019
10.265.5.5 GetAnatomicRegion() [2/2]	1020
10.265.5.6 GetAnatomicRegionModifiers() [1/2]	1020
10.265.5.7 GetAnatomicRegionModifiers() [2/2]	1020
10.265.5.8 GetPropertyCategory() [1/2]	1020
10.265.5.9 GetPropertyCategory() [2/2]	1020
10.265.5.10 GetPropertyType() [1/2]	1020
10.265.5.11 GetPropertyType() [2/2]	1020
10.265.5.12 GetPropertyTypeModifiers() [1/2]	1020
10.265.5.13 GetPropertyTypeModifiers() [2/2]	1020
10.265.5.14 GetSegmentAlgorithmName()	1020
10.265.5.15 GetSegmentAlgorithmType()	1021
10.265.5.16 GetSegmentDescription()	1021
10.265.5.17 GetSegmentLabel()	1021
10.265.5.18 GetSegmentNumber()	1021
10.265.5.19 GetSurface()	1021
10.265.5.20 GetSurfaceCount()	1021
10.265.5.21 GetSurfaces() [1/2]	1021
10.265.5.22 GetSurfaces() [2/2]	1021
10.265.5.23 SetAnatomicRegion()	1021
10.265.5.24 SetAnatomicRegionModifiers()	1022
10.265.5.25 SetPropertyCategory()	1022
10.265.5.26 SetPropertyType()	1022
10.265.5.27 SetPropertyTypeModifiers()	1022
10.265.5.28 SetSegmentAlgorithmName()	1022
10.265.5.29 SetSegmentAlgorithmType() [1/2]	1022

10.265.5.30 SetSegmentAlgorithmType() [2/2]	1022
10.265.5.31 SetSegmentDescription()	1022
10.265.5.32 SetSegmentLabel()	1023
10.265.5.33 SetSegmentNumber()	1023
10.265.5.34 SetSurfaceCount()	1023
10.265.6 Member Data Documentation	1023
10.265.6.1 AnatomicRegion	1023
10.265.6.2 AnatomicRegionModifiers	1023
10.265.6.3 PropertyCategory	1023
10.265.6.4 PropertyType	1023
10.265.6.5 PropertyTypeModifiers	1023
10.265.6.6 SegmentAlgorithmName	1023
10.265.6.7 SegmentAlgorithmType	1024
10.265.6.8 SegmentDescription	1024
10.265.6.9 SegmentLabel	1024
10.265.6.10 SegmentNumber	1024
10.265.6.11 SurfaceCount	1024
10.265.6.12 Surfaces	1024
10.266 gdcm::SegmentedPaletteColorLookupTable Class Reference	1025
10.266.1 Detailed Description	1027
10.266.2 Constructor & Destructor Documentation	1027
10.266.2.1 SegmentedPaletteColorLookupTable()	1027
10.266.2.2 ~SegmentedPaletteColorLookupTable()	1027
10.266.3 Member Function Documentation	1028
10.266.3.1 Print()	1028
10.266.3.2 SetLUT()	1028
10.267 gdcm::SegmentReader Class Reference	1028
10.267.1 Detailed Description	1031
10.267.2 Member Typedef Documentation	1031
10.267.2.1 SegmentMap	1031
10.267.2.2 SegmentVector	1031
10.267.3 Constructor & Destructor Documentation	1031
10.267.3.1 SegmentReader()	1031
10.267.3.2 ~SegmentReader()	1031
10.267.4 Member Function Documentation	1031
10.267.4.1 GetSegments() [1/2]	1031
10.267.4.2 GetSegments() [2/2]	1031
10.267.4.3 Read()	1032
10.267.4.4 ReadSegment()	1032

10.267.4.5 ReadSegments()	1032
10.267.5 Member Data Documentation	1032
10.267.5.1 Segments	1032
10.268 gdcmm::SegmentWriter Class Reference	1032
10.268.1 Detailed Description	1035
10.268.2 Member Typedef Documentation	1036
10.268.2.1 SegmentVector	1036
10.268.3 Constructor & Destructor Documentation	1036
10.268.3.1 SegmentWriter()	1036
10.268.3.2 ~SegmentWriter()	1036
10.268.4 Member Function Documentation	1036
10.268.4.1 AddSegment()	1036
10.268.4.2 GetNumberOfSegments()	1036
10.268.4.3 GetSegment()	1036
10.268.4.4 GetSegments() [1/2]	1036
10.268.4.5 GetSegments() [2/2]	1036
10.268.4.6 PrepareWrite()	1037
10.268.4.7 SetNumberOfSegments()	1037
10.268.4.8 SetSegments()	1037
10.268.4.9 Write()	1037
10.268.5 Member Data Documentation	1037
10.268.5.1 Segments	1037
10.269 gdcmm::SequenceOfFragments Class Reference	1038
10.269.1 Detailed Description	1040
10.269.2 Member Typedef Documentation	1040
10.269.2.1 ConstIterator	1040
10.269.2.2 FragmentVector	1040
10.269.2.3 Iterator	1040
10.269.2.4 SizeType	1041
10.269.3 Constructor & Destructor Documentation	1041
10.269.3.1 SequenceOfFragments()	1041
10.269.4 Member Function Documentation	1041
10.269.4.1 AddFragment()	1041
10.269.4.2 Begin() [1/2]	1041
10.269.4.3 Begin() [2/2]	1041
10.269.4.4 Clear()	1041
10.269.4.5 ComputeByteLength()	1042
10.269.4.6 ComputeLength()	1042
10.269.4.7 End() [1/2]	1042

10.269.4.8 End() [2/2]	1042
10.269.4.9 GetBuffer()	1042
10.269.4.10 GetFragBuffer()	1042
10.269.4.11 GetFragment()	1042
10.269.4.12 GetLength()	1043
10.269.4.13 GetNumberOfFragments()	1043
10.269.4.14 GetTable() [1/2]	1043
10.269.4.15 GetTable() [2/2]	1043
10.269.4.16 New()	1043
10.269.4.17 operator==()	1043
10.269.4.18 Print()	1044
10.269.4.19 Read()	1044
10.269.4.20 ReadPreValue()	1044
10.269.4.21 ReadValue()	1044
10.269.4.22 SetLength()	1044
10.269.4.23 Write()	1045
10.269.4.24 WriteBuffer()	1045
10.270 gdcmm::SequenceOfItems Class Reference	1045
10.270.1 Detailed Description	1048
10.270.2 Member Typedef Documentation	1048
10.270.2.1 ConstIterator	1048
10.270.2.2 ItemVector	1048
10.270.2.3 Iterator	1049
10.270.2.4 SizeType	1049
10.270.3 Constructor & Destructor Documentation	1049
10.270.3.1 SequenceOfItems()	1049
10.270.4 Member Function Documentation	1049
10.270.4.1 AddItem()	1049
10.270.4.2 AddNewUndefinedLengthItem()	1049
10.270.4.3 Begin() [1/2]	1050
10.270.4.4 Begin() [2/2]	1050
10.270.4.5 Clear()	1050
10.270.4.6 ComputeLength()	1050
10.270.4.7 End() [1/2]	1050
10.270.4.8 End() [2/2]	1050
10.270.4.9 FindDataElement()	1050
10.270.4.10 GetItem() [1/2]	1051
10.270.4.11 GetItem() [2/2]	1051
10.270.4.12 GetLength()	1051

10.270.4.13	GetNumberOfItems()	1051
10.270.4.14	IsEmpty()	1051
10.270.4.15	IsUndefinedLength()	1052
10.270.4.16	New()	1052
10.270.4.17	operator=()	1052
10.270.4.18	operator==()	1052
10.270.4.19	Print()	1052
10.270.4.20	Read()	1053
10.270.4.21	RemoveItemByIndex()	1053
10.270.4.22	SetLength()	1053
10.270.4.23	SetLengthToUndefined()	1053
10.270.4.24	SetNumberOfItems()	1053
10.270.4.25	Write()	1054
10.270.5	Member Data Documentation	1054
10.270.5.1	Items	1054
10.270.5.2	SequenceLengthField	1054
10.271	gdcm::SerieHelper Class Reference	1054
10.271.1	Detailed Description	1056
10.271.2	Member Typedef Documentation	1056
10.271.2.1	Rule	1056
10.271.2.2	SerieRestrictions	1056
10.271.2.3	SingleSerieUIDFileSetmap	1056
10.271.3	Constructor & Destructor Documentation	1057
10.271.3.1	SerieHelper()	1057
10.271.3.2	~SerieHelper()	1057
10.271.4	Member Function Documentation	1057
10.271.4.1	AddFile()	1057
10.271.4.2	AddFileName()	1057
10.271.4.3	AddRestriction() [1/3]	1057
10.271.4.4	AddRestriction() [2/3]	1057
10.271.4.5	AddRestriction() [3/3]	1057
10.271.4.6	Clear()	1058
10.271.4.7	CreateDefaultUniqueSeriesIdentifier()	1058
10.271.4.8	CreateUniqueSeriesIdentifier()	1058
10.271.4.9	FileNameOrdering()	1058
10.271.4.10	GetFirstSingleSerieUIDFileSet()	1058
10.271.4.11	GetNextSingleSerieUIDFileSet()	1058
10.271.4.12	ImageNumberOrdering()	1058
10.271.4.13	ImagePositionPatientOrdering()	1058

10.271.4.14 OrderFileList()	1058
10.271.4.15 SetDirectory()	1059
10.271.4.16 SetLoadMode()	1059
10.271.4.17 SetUseSeriesDetails()	1059
10.271.4.18 UserOrdering()	1059
10.271.5 Member Data Documentation	1059
10.271.5.1 ItFileSetHt	1059
10.271.5.2 SingleSerieUIDFileSetHT	1059
10.272 gdcmm::Series Class Reference	1059
10.272.1 Detailed Description	1060
10.272.2 Constructor & Destructor Documentation	1060
10.272.2.1 Series()	1060
10.273 gdcmm::network::ServiceClassApplicationInformation Class Reference	1060
10.273.1 Detailed Description	1060
10.273.2 Constructor & Destructor Documentation	1060
10.273.2.1 ServiceClassApplicationInformation()	1060
10.273.3 Member Function Documentation	1061
10.273.3.1 Print()	1061
10.273.3.2 Read()	1061
10.273.3.3 SetTuple()	1061
10.273.3.4 Size()	1061
10.273.3.5 Write()	1061
10.274 gdcmm::ServiceClassUser Class Reference	1062
10.274.1 Detailed Description	1064
10.274.2 Constructor & Destructor Documentation	1065
10.274.2.1 ServiceClassUser() [1/2]	1065
10.274.2.2 ~ServiceClassUser()	1065
10.274.2.3 ServiceClassUser() [2/2]	1065
10.274.3 Member Function Documentation	1065
10.274.3.1 GetAETitle()	1065
10.274.3.2 GetCalledAETitle()	1065
10.274.3.3 GetTimeout()	1065
10.274.3.4 InitializeConnection()	1066
10.274.3.5 IsPresentationContextAccepted()	1066
10.274.3.6 New()	1066
10.274.3.7 operator=()	1066
10.274.3.8 SendEcho()	1066
10.274.3.9 SendFind()	1066
10.274.3.10 SendMove() [1/3]	1067

10.274.3.11 SendMove() [2/3]	1067
10.274.3.12 SendMove() [3/3]	1067
10.274.3.13 SendStore() [1/3]	1067
10.274.3.14 SendStore() [2/3]	1067
10.274.3.15 SendStore() [3/3]	1068
10.274.3.16 SetAETitle()	1068
10.274.3.17 SetCalledAETitle()	1068
10.274.3.18 SetHostname()	1068
10.274.3.19 SetPort()	1068
10.274.3.20 SetPortSCP()	1069
10.274.3.21 SetPresentationContexts()	1069
10.274.3.22 SetTimeout()	1069
10.274.3.23 StartAssociation()	1069
10.274.3.24 StopAssociation()	1070
10.275 gdcm::SHA1 Class Reference	1070
10.275.1 Detailed Description	1070
10.275.2 Constructor & Destructor Documentation	1071
10.275.2.1 SHA1() [1/2]	1071
10.275.2.2 ~SHA1()	1071
10.275.2.3 SHA1() [2/2]	1071
10.275.3 Member Function Documentation	1071
10.275.3.1 Compute()	1071
10.275.3.2 ComputeFile()	1071
10.275.3.3 operator=()	1071
10.276 gdcm::SimpleMemberCommand< T > Class Template Reference	1072
10.276.1 Detailed Description	1075
10.276.2 Member Typedef Documentation	1075
10.276.2.1 Self	1075
10.276.2.2 TMemberFunctionPointer	1075
10.276.3 Constructor & Destructor Documentation	1075
10.276.3.1 SimpleMemberCommand() [1/2]	1075
10.276.3.2 SimpleMemberCommand() [2/2]	1075
10.276.3.3 ~SimpleMemberCommand()	1075
10.276.4 Member Function Documentation	1076
10.276.4.1 Execute() [1/2]	1076
10.276.4.2 Execute() [2/2]	1076
10.276.4.3 New()	1076
10.276.4.4 operator=()	1076
10.276.4.5 SetCallbackFunction()	1076

10.276.5 Member Data Documentation	1077
10.276.5.1 m_MemberFunction	1077
10.276.5.2 m_This	1077
10.277 gdcmm::SimpleSubjectWatcher Class Reference	1077
10.277.1 Detailed Description	1078
10.277.2 Constructor & Destructor Documentation	1078
10.277.2.1 SimpleSubjectWatcher() [1/2]	1078
10.277.2.2 ~SimpleSubjectWatcher()	1078
10.277.2.3 SimpleSubjectWatcher() [2/2]	1078
10.277.3 Member Function Documentation	1078
10.277.3.1 EndFilter()	1078
10.277.3.2 operator=()	1078
10.277.3.3 ShowAbort()	1079
10.277.3.4 ShowAnonymization()	1079
10.277.3.5 ShowData()	1079
10.277.3.6 ShowDataSet()	1079
10.277.3.7 ShowFileName()	1079
10.277.3.8 ShowIteration()	1079
10.277.3.9 ShowProgress()	1079
10.277.3.10 StartFilter()	1080
10.277.3.11 TestAbortOff()	1080
10.277.3.12 TestAbortOn()	1080
10.278 gdcmm::MrProtocol::Slice Struct Reference	1080
10.278.1 Member Data Documentation	1081
10.278.1.1 Normal	1081
10.278.1.2 Position	1081
10.279 gdcmm::MrProtocol::SliceArray Struct Reference	1081
10.279.1 Member Data Documentation	1082
10.279.1.1 Slices	1082
10.280 gdcmm::SmartPointer< ObjectType > Class Template Reference	1082
10.280.1 Detailed Description	1083
10.280.2 Constructor & Destructor Documentation	1084
10.280.2.1 SmartPointer() [1/4]	1084
10.280.2.2 SmartPointer() [2/4]	1084
10.280.2.3 SmartPointer() [3/4]	1084
10.280.2.4 SmartPointer() [4/4]	1084
10.280.2.5 ~SmartPointer()	1084
10.280.3 Member Function Documentation	1084
10.280.3.1 GetPointer()	1084

10.280.3.2 operator ObjectType *()	1085
10.280.3.3 operator*()	1085
10.280.3.4 operator->()	1085
10.280.3.5 operator=() [1/3]	1085
10.280.3.6 operator=() [2/3]	1085
10.280.3.7 operator=() [3/3]	1085
10.281 gdcmm::network::SOPClassExtendedNegociationSub Class Reference	1086
10.281.1 Detailed Description	1086
10.281.2 Constructor & Destructor Documentation	1086
10.281.2.1 SOPClassExtendedNegociationSub()	1086
10.281.3 Member Function Documentation	1086
10.281.3.1 Print()	1086
10.281.3.2 Read()	1086
10.281.3.3 SetTuple()	1087
10.281.3.4 Size()	1087
10.281.3.5 Write()	1087
10.282 gdcmm::SOPClassUIDToIOD Class Reference	1087
10.282.1 Detailed Description	1088
10.282.2 Member Typedef Documentation	1088
10.282.2.1 const	1088
10.282.3 Member Function Documentation	1088
10.282.3.1 GetIOD()	1088
10.282.3.2 GetIODFromSOPClassUID()	1088
10.282.3.3 GetNumberOfSOPClassToIOD()	1088
10.282.3.4 GetSOPClassUIDFromIOD()	1088
10.282.3.5 GetSOPClassUIDToIOD()	1089
10.282.3.6 GetSOPClassUIDToIODs()	1089
10.283 gdcmm::Sorter Class Reference	1089
10.283.1 Detailed Description	1090
10.283.2 Member Typedef Documentation	1091
10.283.2.1 SelectionMap	1091
10.283.2.2 SortFunction	1091
10.283.3 Constructor & Destructor Documentation	1091
10.283.3.1 Sorter()	1091
10.283.3.2 ~Sorter()	1091
10.283.4 Member Function Documentation	1091
10.283.4.1 AddSelect()	1091
10.283.4.2 GetFileNames()	1091
10.283.4.3 Print()	1092

10.283.4.4 SetSortFunction()	1092
10.283.4.5 SetTagsToRead()	1092
10.283.4.6 Sort()	1092
10.283.4.7 StableSort()	1093
10.283.5 Friends And Related Symbol Documentation	1093
10.283.5.1 operator<<	1093
10.283.6 Member Data Documentation	1093
10.283.6.1 Filenames	1093
10.283.6.2 Selection	1093
10.283.6.3 SortFunc	1093
10.283.6.4 TagsToRead	1093
10.284 gdcm::Spacing Class Reference	1094
10.284.1 Detailed Description	1094
10.284.2 Member Enumeration Documentation	1095
10.284.2.1 SpacingType	1095
10.284.3 Constructor & Destructor Documentation	1095
10.284.3.1 Spacing()	1095
10.284.3.2 ~Spacing()	1096
10.284.4 Member Function Documentation	1096
10.284.4.1 ComputePixelAspectRatioFromPixelSpacing()	1096
10.285 gdcm::Spectroscopy Class Reference	1096
10.285.1 Detailed Description	1096
10.285.2 Constructor & Destructor Documentation	1096
10.285.2.1 Spectroscopy()	1096
10.286 gdcm::SplitMosaicFilter Class Reference	1097
10.286.1 Detailed Description	1097
10.286.2 Constructor & Destructor Documentation	1098
10.286.2.1 SplitMosaicFilter()	1098
10.286.2.2 ~SplitMosaicFilter()	1098
10.286.3 Member Function Documentation	1098
10.286.3.1 ComputeCSAImageHeaderInfo()	1098
10.286.3.2 ComputeCSASeriesHeaderInfo()	1098
10.286.3.3 ComputeMOSAICDimensions()	1098
10.286.3.4 ComputeMOSAICImagePositionPatient()	1098
10.286.3.5 ComputeMOSAICSliceNormal()	1099
10.286.3.6 ComputeMOSAICSlicePosition()	1099
10.286.3.7 GetAcquisitionSize()	1099
10.286.3.8 GetFile() [1/2]	1099
10.286.3.9 GetFile() [2/2]	1099

10.286.3.10 GetImage() [1/2]	1099
10.286.3.11 GetImage() [2/2]	1099
10.286.3.12 GetNumberOfImagesInMosaic()	1100
10.286.3.13 SetFile()	1100
10.286.3.14 SetImage()	1100
10.286.3.15 Split()	1100
10.287 gdcm::StartEvent Class Reference	1100
10.288 gdcm::static_assert_test< x > Struct Template Reference	1101
10.289 gdcm::STATIC_ASSERTION_FAILURE< x > Struct Template Reference	1102
10.290 gdcm::STATIC_ASSERTION_FAILURE< true > Struct Reference	1102
10.290.1 Member Enumeration Documentation	1103
10.290.1.1 anonymous enum	1103
10.291 gdcm::StreamImageReader Class Reference	1103
10.291.1 Detailed Description	1104
10.291.2 Constructor & Destructor Documentation	1104
10.291.2.1 StreamImageReader()	1104
10.291.2.2 ~StreamImageReader()	1104
10.291.3 Member Function Documentation	1105
10.291.3.1 CanReadImage()	1105
10.291.3.2 DefinePixelExtent()	1105
10.291.3.3 DefineProperBufferLength()	1105
10.291.3.4 GetDimensionsValueForResolution()	1106
10.291.3.5 GetFile()	1106
10.291.3.6 Read()	1106
10.291.3.7 ReadImageInformation()	1106
10.291.3.8 SetFileName()	1107
10.291.3.9 SetStream()	1107
10.292 gdcm::StreamImageWriter Class Reference	1107
10.292.1 Detailed Description	1109
10.292.2 Constructor & Destructor Documentation	1109
10.292.2.1 StreamImageWriter()	1109
10.292.2.2 ~StreamImageWriter()	1109
10.292.3 Member Function Documentation	1110
10.292.3.1 CanWriteFile()	1110
10.292.3.2 DefinePixelExtent()	1110
10.292.3.3 DefineProperBufferLength()	1110
10.292.3.4 SetFile()	1111
10.292.3.5 SetFileName()	1111
10.292.3.6 SetStream()	1111

10.292.3.7 Write()	1111
10.292.3.8 WriteImageInformation()	1112
10.292.3.9 WriteImageSubregionRAW()	1112
10.292.3.10 WriteRawHeader()	1112
10.292.4 Member Data Documentation	1112
10.292.4.1 mElementOffsets	1112
10.292.4.2 mElementOffsets1	1112
10.292.4.3 mspFile	1113
10.292.4.4 mWriter	1113
10.292.4.5 mXMax	1113
10.292.4.6 mXMin	1113
10.292.4.7 mYMax	1113
10.292.4.8 mYMin	1113
10.292.4.9 mZMax	1113
10.292.4.10 mZMin	1113
10.293 gdcmm::StrictScanner Class Reference	1114
10.293.1 Detailed Description	1117
10.293.2 Member Typedef Documentation	1117
10.293.2.1 ConstIterator	1117
10.293.2.2 MappingType	1117
10.293.2.3 TagToValue	1118
10.293.2.4 TagToValueValueType	1118
10.293.2.5 ValuesType	1118
10.293.3 Constructor & Destructor Documentation	1118
10.293.3.1 StrictScanner()	1118
10.293.3.2 ~StrictScanner()	1118
10.293.4 Member Function Documentation	1118
10.293.4.1 AddPrivateTag()	1118
10.293.4.2 AddSkipTag()	1119
10.293.4.3 AddTag()	1119
10.293.4.4 Begin()	1119
10.293.4.5 ClearSkipTags()	1119
10.293.4.6 ClearTags()	1119
10.293.4.7 End()	1119
10.293.4.8 GetAllFilenamesFromTagToValue()	1119
10.293.4.9 GetFilenameFromTagToValue()	1120
10.293.4.10 GetFilenames()	1120
10.293.4.11 GetKeys()	1120
10.293.4.12 GetMapping()	1120

10.293.4.13 GetMappingFromTagToValue()	1120
10.293.4.14 GetMappings()	1120
10.293.4.15 GetOrderedValues()	1121
10.293.4.16 GetValue()	1121
10.293.4.17 GetValues() [1/2]	1121
10.293.4.18 GetValues() [2/2]	1121
10.293.4.19 IsKey()	1121
10.293.4.20 New()	1122
10.293.4.21 Print()	1122
10.293.4.22 PrintTable()	1122
10.293.4.23 ProcessPublicTag()	1122
10.293.4.24 Scan()	1122
10.293.5 Friends And Related Symbol Documentation	1123
10.293.5.1 operator<<	1123
10.294 gdcmm::StrictScanner2 Class Reference	1123
10.294.1 Detailed Description	1126
10.294.2 Member Typedef Documentation	1127
10.294.2.1 PrivateConstIterator	1127
10.294.2.2 PrivateMappingType	1127
10.294.2.3 PrivateTagToValue	1127
10.294.2.4 PrivateTagToValueValueType	1127
10.294.2.5 PublicConstIterator	1127
10.294.2.6 PublicMappingType	1127
10.294.2.7 PublicTagToValue	1127
10.294.2.8 PublicTagToValueValueType	1127
10.294.2.9 ValuesType	1128
10.294.3 Constructor & Destructor Documentation	1128
10.294.3.1 StrictScanner2()	1128
10.294.3.2 ~StrictScanner2()	1128
10.294.4 Member Function Documentation	1128
10.294.4.1 AddPrivateTag()	1128
10.294.4.2 AddPublicTag()	1128
10.294.4.3 AddSkipTag()	1128
10.294.4.4 Begin()	1128
10.294.4.5 ClearPrivateTags()	1129
10.294.4.6 ClearPublicTags()	1129
10.294.4.7 ClearSkipTags()	1129
10.294.4.8 End()	1129
10.294.4.9 GetAllFilenamesFromPrivateTagToValue()	1129

10.294.4.10 GetAllFileNamesFromPublicTagToValue()	1129
10.294.4.11 GetFilenameFromPrivateTagToValue()	1129
10.294.4.12 GetFilenameFromPublicTagToValue()	1129
10.294.4.13 GetFileNames()	1130
10.294.4.14 GetKeys()	1130
10.294.4.15 GetMappingFromPrivateTagToValue()	1130
10.294.4.16 GetMappingFromPublicTagToValue()	1130
10.294.4.17 GetPrivateMapping()	1130
10.294.4.18 GetPrivateMappings()	1130
10.294.4.19 GetPrivateOrderedValues()	1130
10.294.4.20 GetPrivateValue()	1131
10.294.4.21 GetPrivateValues()	1131
10.294.4.22 GetPublicMapping()	1131
10.294.4.23 GetPublicMappings()	1131
10.294.4.24 GetPublicOrderedValues()	1131
10.294.4.25 GetPublicValue()	1131
10.294.4.26 GetPublicValues()	1132
10.294.4.27 GetValues()	1132
10.294.4.28 IsKey()	1132
10.294.4.29 New()	1132
10.294.4.30 Print()	1132
10.294.4.31 PrintTable()	1132
10.294.4.32 PrivateBegin()	1133
10.294.4.33 PrivateEnd()	1133
10.294.4.34 ProcessPrivateTag()	1133
10.294.4.35 ProcessPublicTag()	1133
10.294.4.36 Scan()	1133
10.294.5 Friends And Related Symbol Documentation	1133
10.294.5.1 operator<<	1133
10.295 gdcmm::String< TDelimiter, TMaxLength, TPadChar > Class Template Reference	1134
10.295.1 Detailed Description	1135
10.295.2 Member Typedef Documentation	1135
10.295.2.1 const_iterator	1135
10.295.2.2 const_reference	1136
10.295.2.3 const_reverse_iterator	1136
10.295.2.4 difference_type	1136
10.295.2.5 iterator	1136
10.295.2.6 pointer	1136
10.295.2.7 reference	1136

10.295.2.8 reverse_iterator	1136
10.295.2.9 size_type	1136
10.295.2.10 value_type	1137
10.295.3 Constructor & Destructor Documentation	1137
10.295.3.1 String() [1/4]	1137
10.295.3.2 String() [2/4]	1137
10.295.3.3 String() [3/4]	1137
10.295.3.4 String() [4/4]	1137
10.295.4 Member Function Documentation	1137
10.295.4.1 IsValid()	1137
10.295.4.2 operator const char *()	1138
10.295.4.3 Trim() [1/2]	1138
10.295.4.4 Trim() [2/2]	1138
10.295.4.5 Truncate()	1138
10.296 gdcmm::StringFilter Class Reference	1138
10.296.1 Detailed Description	1139
10.296.2 Constructor & Destructor Documentation	1139
10.296.2.1 StringFilter()	1139
10.296.2.2 ~StringFilter()	1140
10.296.3 Member Function Documentation	1140
10.296.3.1 ExecuteQuery() [1/2]	1140
10.296.3.2 ExecuteQuery() [2/2]	1140
10.296.3.3 FromString()	1140
10.296.3.4 GetFile() [1/2]	1140
10.296.3.5 GetFile() [2/2]	1140
10.296.3.6 SetDicts()	1140
10.296.3.7 SetFile()	1141
10.296.3.8 ToString() [1/3]	1141
10.296.3.9 ToString() [2/3]	1141
10.296.3.10 ToString() [3/3]	1141
10.296.3.11 ToStringPair() [1/3]	1141
10.296.3.12 ToStringPair() [2/3]	1142
10.296.3.13 ToStringPair() [3/3]	1142
10.296.3.14 UseDictAlways()	1142
10.297 gdcmm::Study Class Reference	1142
10.297.1 Detailed Description	1142
10.297.2 Constructor & Destructor Documentation	1142
10.297.2.1 Study()	1142
10.298 gdcmm::Subject Class Reference	1143

10.298.1 Detailed Description	1144
10.298.2 Constructor & Destructor Documentation	1144
10.298.2.1 Subject()	1144
10.298.2.2 ~Subject()	1145
10.298.3 Member Function Documentation	1145
10.298.3.1 AddObserver() [1/2]	1145
10.298.3.2 AddObserver() [2/2]	1145
10.298.3.3 GetCommand()	1145
10.298.3.4 HasObserver()	1145
10.298.3.5 InvokeEvent() [1/2]	1145
10.298.3.6 InvokeEvent() [2/2]	1146
10.298.3.7 RemoveAllObservers()	1146
10.298.3.8 RemoveObserver()	1146
10.299 gdcm::Surface Class Reference	1146
10.299.1 Detailed Description	1149
10.299.2 Member Enumeration Documentation	1149
10.299.2.1 STATES	1149
10.299.2.2 VIEWType	1150
10.299.3 Constructor & Destructor Documentation	1150
10.299.3.1 Surface()	1150
10.299.3.2 ~Surface()	1150
10.299.4 Member Function Documentation	1150
10.299.4.1 GetAlgorithmFamily() [1/2]	1150
10.299.4.2 GetAlgorithmFamily() [2/2]	1150
10.299.4.3 GetAlgorithmName()	1150
10.299.4.4 GetAlgorithmVersion()	1151
10.299.4.5 GetAxisOfRotation()	1151
10.299.4.6 GetCenterOfRotation()	1151
10.299.4.7 GetFiniteVolume()	1151
10.299.4.8 GetManifold()	1151
10.299.4.9 GetMaximumPointDistance()	1151
10.299.4.10 GetMeanPointDistance()	1151
10.299.4.11 GetMeshPrimitive() [1/2]	1151
10.299.4.12 GetMeshPrimitive() [2/2]	1152
10.299.4.13 GetNumberOfSurfacePoints()	1152
10.299.4.14 GetNumberOfVectors()	1152
10.299.4.15 GetPointCoordinatesData() [1/2]	1152
10.299.4.16 GetPointCoordinatesData() [2/2]	1152
10.299.4.17 GetPointPositionAccuracy()	1152

10.299.4.18 GetPointsBoundingBoxCoordinates()	1152
10.299.4.19 GetProcessingAlgorithm() [1/2]	1152
10.299.4.20 GetProcessingAlgorithm() [2/2]	1153
10.299.4.21 GetRecommendedDisplayCIELabValue() [1/2]	1153
10.299.4.22 GetRecommendedDisplayCIELabValue() [2/2]	1153
10.299.4.23 GetRecommendedDisplayGrayscaleValue()	1153
10.299.4.24 GetRecommendedPresentationOpacity()	1153
10.299.4.25 GetRecommendedPresentationType()	1153
10.299.4.26 GetSTATES()	1153
10.299.4.27 GetSTATESString()	1153
10.299.4.28 GetSurfaceComments()	1153
10.299.4.29 GetSurfaceNumber()	1154
10.299.4.30 GetSurfaceProcessing()	1154
10.299.4.31 GetSurfaceProcessingDescription()	1154
10.299.4.32 GetSurfaceProcessingRatio()	1154
10.299.4.33 GetVectorAccuracy()	1154
10.299.4.34 GetVectorCoordinateData() [1/2]	1154
10.299.4.35 GetVectorCoordinateData() [2/2]	1154
10.299.4.36 GetVectorDimensionality()	1154
10.299.4.37 GetVIEWType()	1154
10.299.4.38 GetVIEWTypeString()	1155
10.299.4.39 SetAlgorithmFamily()	1155
10.299.4.40 SetAlgorithmName()	1155
10.299.4.41 SetAlgorithmVersion()	1155
10.299.4.42 SetAxisOfRotation()	1155
10.299.4.43 SetCenterOfRotation()	1155
10.299.4.44 SetFiniteVolume()	1155
10.299.4.45 SetManifold()	1155
10.299.4.46 SetMaximumPointDistance()	1156
10.299.4.47 SetMeanPointDistance()	1156
10.299.4.48 SetMeshPrimitive()	1156
10.299.4.49 SetNumberOfSurfacePoints()	1156
10.299.4.50 SetNumberOfVectors()	1156
10.299.4.51 SetPointCoordinatesData()	1156
10.299.4.52 SetPointPositionAccuracy()	1156
10.299.4.53 SetPointsBoundingBoxCoordinates()	1156
10.299.4.54 SetProcessingAlgorithm()	1157
10.299.4.55 SetRecommendedDisplayCIELabValue() [1/3]	1157
10.299.4.56 SetRecommendedDisplayCIELabValue() [2/3]	1157

10.299.4.57 SetRecommendedDisplayCIELabValue() [3/3]	1157
10.299.4.58 SetRecommendedDisplayGrayscaleValue()	1157
10.299.4.59 SetRecommendedPresentationOpacity()	1157
10.299.4.60 SetRecommendedPresentationType()	1157
10.299.4.61 SetSurfaceComments()	1157
10.299.4.62 SetSurfaceNumber()	1158
10.299.4.63 SetSurfaceProcessing()	1158
10.299.4.64 SetSurfaceProcessingDescription()	1158
10.299.4.65 SetSurfaceProcessingRatio()	1158
10.299.4.66 SetVectorAccuracy()	1158
10.299.4.67 SetVectorCoordinateData()	1158
10.299.4.68 SetVectorDimensionality()	1158
10.300 gdcm::SurfaceHelper Class Reference	1159
10.300.1 Detailed Description	1159
10.300.2 Member Typedef Documentation	1159
10.300.2.1 ColorArray	1159
10.300.3 Member Function Documentation	1160
10.300.3.1 RecommendedDisplayCIELabToRGB() [1/2]	1160
10.300.3.2 RecommendedDisplayCIELabToRGB() [2/2]	1160
10.300.3.3 RGBToRecommendedDisplayCIELab()	1161
10.300.3.4 RGBToRecommendedDisplayGrayscale()	1161
10.301 gdcm::SurfaceReader Class Reference	1162
10.301.1 Detailed Description	1165
10.301.2 Constructor & Destructor Documentation	1165
10.301.2.1 SurfaceReader()	1165
10.301.2.2 ~SurfaceReader()	1165
10.301.3 Member Function Documentation	1165
10.301.3.1 GetNumberOfSurfaces()	1165
10.301.3.2 Read()	1166
10.301.3.3 ReadPointMacro()	1166
10.301.3.4 ReadSurface()	1166
10.301.3.5 ReadSurfaces()	1166
10.302 gdcm::SurfaceWriter Class Reference	1166
10.302.1 Detailed Description	1170
10.302.2 Constructor & Destructor Documentation	1170
10.302.2.1 SurfaceWriter()	1170
10.302.2.2 ~SurfaceWriter()	1170
10.302.3 Member Function Documentation	1170
10.302.3.1 ComputeNumberOfSurfaces()	1170

10.302.3.2	GetNumberOfSurfaces()	1171
10.302.3.3	PrepareWrite()	1171
10.302.3.4	PrepareWritePointMacro()	1171
10.302.3.5	SetNumberOfSurfaces()	1171
10.302.3.6	Write()	1171
10.302.4	Member Data Documentation	1171
10.302.4.1	NumberOfSurfaces	1171
10.303	gdcM::SwapCode Class Reference	1171
10.303.1	Detailed Description	1172
10.303.2	Member Enumeration Documentation	1172
10.303.2.1	SwapCodeType	1172
10.303.3	Constructor & Destructor Documentation	1173
10.303.3.1	SwapCode()	1173
10.303.4	Member Function Documentation	1173
10.303.4.1	GetIndex()	1173
10.303.4.2	GetSwapCodeString()	1173
10.303.4.3	operator SwapCode::SwapCodeType()	1173
10.303.5	Friends And Related Symbol Documentation	1173
10.303.5.1	operator<<	1173
10.304	gdcM::SwapperDoOp Class Reference	1174
10.304.1	Member Function Documentation	1174
10.304.1.1	Swap()	1174
10.304.1.2	SwapArray()	1174
10.305	gdcM::SwapperNoOp Class Reference	1174
10.305.1	Detailed Description	1175
10.305.2	Member Function Documentation	1175
10.305.2.1	Swap()	1175
10.305.2.2	SwapArray()	1175
10.306	gdcM::System Class Reference	1175
10.306.1	Detailed Description	1177
10.306.2	Member Function Documentation	1177
10.306.2.1	ConvertToUNC()	1177
10.306.2.2	DeleteDirectory()	1177
10.306.2.3	EncodeBytes()	1177
10.306.2.4	FileExists()	1177
10.306.2.5	FileIsDirectory()	1178
10.306.2.6	FileIsSymlink()	1178
10.306.2.7	FileSize()	1178
10.306.2.8	FileTime()	1178

10.306.2.9 FormatDateTime()	1179
10.306.2.10 GetCurrentDateTime()	1179
10.306.2.11 GetCurrentModuleFileName()	1179
10.306.2.12 GetCurrentProcessFileName()	1179
10.306.2.13 GetCurrentResourcesDirectory()	1179
10.306.2.14 GetCWD()	1179
10.306.2.15 GetHostName()	1180
10.306.2.16 GetLastSystemError()	1180
10.306.2.17 GetLocaleCharset()	1180
10.306.2.18 GetPermissions()	1180
10.306.2.19 GetTimezoneOffsetFromUTC()	1180
10.306.2.20 MakeDirectory()	1180
10.306.2.21 ParseDateTime() [1/2]	1181
10.306.2.22 ParseDateTime() [2/2]	1181
10.306.2.23 RemoveFile()	1181
10.306.2.24 SetPermissions()	1181
10.306.2.25 StrCaseCmp()	1181
10.306.2.26 StrNCaseCmp()	1182
10.306.2.27 StrSep()	1182
10.306.2.28 StrTokR()	1182
10.307 gdcmm::Table Class Reference	1182
10.307.1 Detailed Description	1184
10.307.2 Member Typedef Documentation	1184
10.307.2.1 MapTableEntry	1184
10.307.3 Constructor & Destructor Documentation	1184
10.307.3.1 Table() [1/2]	1184
10.307.3.2 ~Table()	1184
10.307.3.3 Table() [2/2]	1184
10.307.4 Member Function Documentation	1184
10.307.4.1 GetTableEntry()	1184
10.307.4.2 InsertEntry()	1185
10.307.4.3 operator=()	1185
10.307.5 Friends And Related Symbol Documentation	1185
10.307.5.1 operator<<	1185
10.307.6 Member Data Documentation	1185
10.307.6.1 TableInternal	1185
10.308 gdcmm::TableEntry Class Reference	1185
10.308.1 Detailed Description	1186
10.308.2 Constructor & Destructor Documentation	1186

10.308.2.1 TableEntry()	1186
10.308.2.2 ~TableEntry()	1186
10.309 gdcM::TableReader Class Reference	1186
10.309.1 Detailed Description	1187
10.309.2 Constructor & Destructor Documentation	1187
10.309.2.1 TableReader()	1187
10.309.2.2 ~TableReader()	1187
10.309.3 Member Function Documentation	1188
10.309.3.1 CharacterDataHandler()	1188
10.309.3.2 EndElement()	1188
10.309.3.3 GetDefs()	1188
10.309.3.4 GetFilename()	1188
10.309.3.5 HandleIOD()	1188
10.309.3.6 HandleIODEntry()	1188
10.309.3.7 HandleMacro()	1188
10.309.3.8 HandleMacroEntry()	1189
10.309.3.9 HandleMacroEntryDescription()	1189
10.309.3.10 HandleModule()	1189
10.309.3.11 HandleModuleEntry()	1189
10.309.3.12 HandleModuleEntryDescription()	1189
10.309.3.13 HandleModuleInclude()	1189
10.309.3.14 Read()	1189
10.309.3.15 SetFilename()	1189
10.309.3.16 StartElement()	1190
10.310 gdcM::network::TableRow Class Reference	1190
10.310.1 Constructor & Destructor Documentation	1191
10.310.1.1 TableRow()	1191
10.310.1.2 ~TableRow()	1191
10.310.2 Member Data Documentation	1191
10.310.2.1 transitions	1191
10.311 gdcM::Tag Class Reference	1191
10.311.1 Detailed Description	1193
10.311.2 Constructor & Destructor Documentation	1194
10.311.2.1 Tag() [1/3]	1194
10.311.2.2 Tag() [2/3]	1194
10.311.2.3 Tag() [3/3]	1194
10.311.3 Member Function Documentation	1194
10.311.3.1 GetElement()	1194
10.311.3.2 GetElementTag()	1195

10.311.3.3	GetGroup()	1195
10.311.3.4	GetLength()	1195
10.311.3.5	GetPrivateCreator()	1195
10.311.3.6	IsGroupLength()	1195
10.311.3.7	IsGroupXX()	1196
10.311.3.8	IsIllegal()	1196
10.311.3.9	IsPrivate()	1196
10.311.3.10	IsPrivateCreator()	1196
10.311.3.11	IsPublic()	1197
10.311.3.12	operator"!=(1197
10.311.3.13	operator<()	1197
10.311.3.14	operator<=()	1197
10.311.3.15	operator=()	1197
10.311.3.16	operator==(1197
10.311.3.17	operator[]() [1/2]	1198
10.311.3.18	operator[]() [2/2]	1198
10.311.3.19	PrintAsContinuousString()	1198
10.311.3.20	PrintAsContinuousUpperCaseString()	1198
10.311.3.21	PrintAsPipeSeparatedString()	1198
10.311.3.22	Read()	1199
10.311.3.23	ReadFromCommaSeparatedString()	1199
10.311.3.24	ReadFromContinuousString()	1199
10.311.3.25	ReadFromPipeSeparatedString()	1199
10.311.3.26	SetElement()	1199
10.311.3.27	SetElementTag() [1/2]	1200
10.311.3.28	SetElementTag() [2/2]	1200
10.311.3.29	SetGroup()	1200
10.311.3.30	SetPrivateCreator()	1200
10.311.3.31	Write()	1200
10.311.4	Friends And Related Symbol Documentation	1201
10.311.4.1	operator<<	1201
10.311.4.2	operator>>	1201
10.311.5	Member Data Documentation	1201
10.311.5.1	bytes	1201
10.311.5.2	tag	1201
10.311.5.3	tags	1201
10.312	gdcmm::TagPath Class Reference	1202
10.312.1	Detailed Description	1202
10.312.2	Constructor & Destructor Documentation	1202

10.312.2.1 TagPath()	1202
10.312.2.2 ~TagPath()	1202
10.312.3 Member Function Documentation	1203
10.312.3.1 ConstructFromString()	1203
10.312.3.2 ConstructFromTagList()	1203
10.312.3.3 IsValid()	1203
10.312.3.4 Print()	1203
10.312.3.5 Push() [1/2]	1203
10.312.3.6 Push() [2/2]	1203
10.313 gdcmm::Testing Class Reference	1204
10.313.1 Detailed Description	1205
10.313.2 Member Typedef Documentation	1205
10.313.2.1 MD5DataImagesType	1205
10.313.2.2 MediaStorageDataFilesType	1205
10.313.3 Constructor & Destructor Documentation	1205
10.313.3.1 Testing()	1205
10.313.3.2 ~Testing()	1205
10.313.4 Member Function Documentation	1206
10.313.4.1 ComputeFileMD5()	1206
10.313.4.2 ComputeMD5()	1206
10.313.4.3 GetDataExtraRoot()	1206
10.313.4.4 GetDataRoot()	1206
10.313.4.5 GetFileName()	1207
10.313.4.6 GetFileNames()	1207
10.313.4.7 GetLossyFlagFromFile()	1207
10.313.4.8 GetMD5DataImage()	1207
10.313.4.9 GetMD5DataImages()	1207
10.313.4.10 GetMD5FromBrokenFile()	1207
10.313.4.11 GetMD5FromFile()	1208
10.313.4.12 GetMediaStorageDataFile()	1208
10.313.4.13 GetMediaStorageDataFiles()	1208
10.313.4.14 GetMediaStorageFromFile()	1208
10.313.4.15 GetNumberOfFileNames()	1208
10.313.4.16 GetNumberOfMD5DataImages()	1208
10.313.4.17 GetNumberOfMediaStorageDataFiles()	1208
10.313.4.18 GetPixelSpacingDataRoot()	1209
10.313.4.19 GetSelectedPrivateGroupOffsetFromFile()	1209
10.313.4.20 GetSelectedTagsOffsetFromFile()	1209
10.313.4.21 GetSourceDirectory()	1209

10.313.4.22 GetStreamOffsetFromFile()	1209
10.313.4.23 GetTempDirectory()	1209
10.313.4.24 GetTempDirectoryW()	1210
10.313.4.25 GetTempFilename()	1210
10.313.4.26 GetTempFilenameW()	1210
10.313.4.27 Print()	1210
10.314 gdcmm::Trace Class Reference	1210
10.314.1 Detailed Description	1211
10.314.2 Constructor & Destructor Documentation	1212
10.314.2.1 Trace()	1212
10.314.2.2 ~Trace()	1212
10.314.3 Member Function Documentation	1212
10.314.3.1 DebugOff()	1212
10.314.3.2 DebugOn()	1212
10.314.3.3 ErrorOff()	1212
10.314.3.4 ErrorOn()	1212
10.314.3.5 GetDebugFlag()	1213
10.314.3.6 GetDebugStream()	1213
10.314.3.7 GetErrorFlag()	1213
10.314.3.8 GetErrorStream()	1213
10.314.3.9 GetStream()	1213
10.314.3.10 GetWarningFlag()	1213
10.314.3.11 GetWarningStream()	1213
10.314.3.12 SetDebug()	1213
10.314.3.13 SetDebugStream()	1214
10.314.3.14 SetError()	1214
10.314.3.15 SetErrorStream()	1214
10.314.3.16 SetStream()	1214
10.314.3.17 SetStreamToFile()	1214
10.314.3.18 SetWarning()	1215
10.314.3.19 SetWarningStream()	1215
10.314.3.20 WarningOff()	1215
10.314.3.21 WarningOn()	1215
10.315 gdcmm::TransferSyntax Class Reference	1215
10.315.1 Detailed Description	1217
10.315.2 Member Enumeration Documentation	1217
10.315.2.1 NegotiatedType	1217
10.315.2.2 TSType	1217
10.315.3 Constructor & Destructor Documentation	1218

10.315.3.1 TransferSyntax()	1218
10.315.4 Member Function Documentation	1219
10.315.4.1 CanStoreLossy()	1219
10.315.4.2 GetNegociatedType()	1219
10.315.4.3 GetString()	1219
10.315.4.4 GetSwapCode()	1219
10.315.4.5 GetTSSString()	1219
10.315.4.6 GetTSType()	1220
10.315.4.7 IsEncapsulated()	1220
10.315.4.8 IsEncoded()	1220
10.315.4.9 IsExplicit()	1220
10.315.4.10 IsImplicit()	1220
10.315.4.11 IsLossless()	1220
10.315.4.12 IsLossy()	1220
10.315.4.13 IsValid()	1220
10.315.4.14 operator TSType()	1221
10.315.5 Friends And Related Symbol Documentation	1221
10.315.5.1 operator<<	1221
10.316 gdcm::network::TransferSyntaxSub Class Reference	1221
10.316.1 Detailed Description	1221
10.316.2 Constructor & Destructor Documentation	1222
10.316.2.1 TransferSyntaxSub()	1222
10.316.3 Member Function Documentation	1222
10.316.3.1 GetName()	1222
10.316.3.2 operator==()	1222
10.316.3.3 Print()	1222
10.316.3.4 Read()	1222
10.316.3.5 SetName()	1222
10.316.3.6 SetNameFromUID()	1222
10.316.3.7 Size()	1223
10.316.3.8 Write()	1223
10.317 gdcm::network::Transition Struct Reference	1223
10.317.1 Constructor & Destructor Documentation	1224
10.317.1.1 Transition() [1/2]	1224
10.317.1.2 ~Transition()	1224
10.317.1.3 Transition() [2/2]	1224
10.317.2 Member Function Documentation	1224
10.317.2.1 MakeNew()	1224
10.317.3 Member Data Documentation	1224

10.317.3.1 mAction	1224
10.317.3.2 mEnd	1225
10.318 gdcm::Type Class Reference	1225
10.318.1 Detailed Description	1226
10.318.2 Member Enumeration Documentation	1226
10.318.2.1 TypeType	1226
10.318.3 Constructor & Destructor Documentation	1226
10.318.3.1 Type()	1226
10.318.4 Member Function Documentation	1227
10.318.4.1 GetTypeString()	1227
10.318.4.2 GetTypeType()	1227
10.318.4.3 operator TypeType()	1227
10.318.5 Friends And Related Symbol Documentation	1227
10.318.5.1 operator<<	1227
10.319 gdcm::UI Struct Reference	1227
10.319.1 Friends And Related Symbol Documentation	1228
10.319.1.1 operator<<	1228
10.319.2 Member Data Documentation	1228
10.319.2.1 Internal	1228
10.320 gdcm::UIDGenerator Class Reference	1228
10.320.1 Detailed Description	1229
10.320.2 Constructor & Destructor Documentation	1229
10.320.2.1 UIDGenerator()	1229
10.320.3 Member Function Documentation	1229
10.320.3.1 Generate()	1229
10.320.3.2 GenerateUUID()	1229
10.320.3.3 GetGDCMUID()	1230
10.320.3.4 GetRoot()	1230
10.320.3.5 IsValid()	1230
10.320.3.6 SetRoot()	1230
10.321 gdcm::UIDs Class Reference	1231
10.321.1 Detailed Description	1246
10.321.2 Member Typedef Documentation	1247
10.321.2.1 TransferSyntaxStringsType	1247
10.321.3 Member Enumeration Documentation	1247
10.321.3.1 TSName	1247
10.321.3.2 TSType	1256
10.321.4 Constructor & Destructor Documentation	1266
10.321.4.1 UIDs()	1266

10.321.5 Member Function Documentation	1266
10.321.5.1 GetName()	1266
10.321.5.2 GetNumberOfTransferSyntaxStrings()	1266
10.321.5.3 GetString()	1266
10.321.5.4 GetTransferSyntaxString()	1266
10.321.5.5 GetTransferSyntaxStrings()	1267
10.321.5.6 GetUIDName()	1267
10.321.5.7 GetUIDString()	1267
10.321.5.8 operator TSType()	1267
10.321.5.9 SetFromUID()	1267
10.322 gdcm::network::ULAction Class Reference	1268
10.322.1 Detailed Description	1269
10.322.2 Constructor & Destructor Documentation	1269
10.322.2.1 ULAction() [1/2]	1269
10.322.2.2 ~ULAction()	1270
10.322.2.3 ULAction() [2/2]	1270
10.322.3 Member Function Documentation	1270
10.322.3.1 operator=()	1270
10.322.3.2 PerformAction()	1270
10.323 gdcm::network::ULActionAA1 Class Reference	1271
10.323.1 Member Function Documentation	1272
10.323.1.1 PerformAction()	1272
10.324 gdcm::network::ULActionAA2 Class Reference	1272
10.324.1 Member Function Documentation	1273
10.324.1.1 PerformAction()	1273
10.325 gdcm::network::ULActionAA3 Class Reference	1273
10.325.1 Member Function Documentation	1274
10.325.1.1 PerformAction()	1274
10.326 gdcm::network::ULActionAA4 Class Reference	1275
10.326.1 Member Function Documentation	1276
10.326.1.1 PerformAction()	1276
10.327 gdcm::network::ULActionAA5 Class Reference	1276
10.327.1 Member Function Documentation	1277
10.327.1.1 PerformAction()	1277
10.328 gdcm::network::ULActionAA6 Class Reference	1277
10.328.1 Member Function Documentation	1278
10.328.1.1 PerformAction()	1278
10.329 gdcm::network::ULActionAA7 Class Reference	1279
10.329.1 Member Function Documentation	1280

10.329.1.1 PerformAction()	1280
10.330 gdcn::network::ULActionAA8 Class Reference	1280
10.330.1 Member Function Documentation	1281
10.330.1.1 PerformAction()	1281
10.331 gdcn::network::ULActionAE1 Class Reference	1281
10.331.1 Member Function Documentation	1282
10.331.1.1 PerformAction()	1282
10.332 gdcn::network::ULActionAE2 Class Reference	1283
10.332.1 Member Function Documentation	1284
10.332.1.1 PerformAction()	1284
10.333 gdcn::network::ULActionAE3 Class Reference	1284
10.333.1 Member Function Documentation	1285
10.333.1.1 PerformAction()	1285
10.334 gdcn::network::ULActionAE4 Class Reference	1285
10.334.1 Member Function Documentation	1286
10.334.1.1 PerformAction()	1286
10.335 gdcn::network::ULActionAE5 Class Reference	1287
10.335.1 Member Function Documentation	1288
10.335.1.1 PerformAction()	1288
10.336 gdcn::network::ULActionAE6 Class Reference	1288
10.336.1 Member Function Documentation	1289
10.336.1.1 PerformAction()	1289
10.337 gdcn::network::ULActionAE7 Class Reference	1289
10.337.1 Member Function Documentation	1290
10.337.1.1 PerformAction()	1290
10.338 gdcn::network::ULActionAE8 Class Reference	1291
10.338.1 Member Function Documentation	1292
10.338.1.1 PerformAction()	1292
10.339 gdcn::network::ULActionAR1 Class Reference	1292
10.339.1 Member Function Documentation	1293
10.339.1.1 PerformAction()	1293
10.340 gdcn::network::ULActionAR10 Class Reference	1293
10.340.1 Member Function Documentation	1294
10.340.1.1 PerformAction()	1294
10.341 gdcn::network::ULActionAR2 Class Reference	1295
10.341.1 Member Function Documentation	1296
10.341.1.1 PerformAction()	1296
10.342 gdcn::network::ULActionAR3 Class Reference	1296
10.342.1 Member Function Documentation	1297

10.342.1.1 PerformAction()	1297
10.343 gdcmm::network::ULActionAR4 Class Reference	1297
10.343.1 Member Function Documentation	1298
10.343.1.1 PerformAction()	1298
10.344 gdcmm::network::ULActionAR5 Class Reference	1299
10.344.1 Member Function Documentation	1300
10.344.1.1 PerformAction()	1300
10.345 gdcmm::network::ULActionAR6 Class Reference	1300
10.345.1 Member Function Documentation	1301
10.345.1.1 PerformAction()	1301
10.346 gdcmm::network::ULActionAR7 Class Reference	1301
10.346.1 Member Function Documentation	1302
10.346.1.1 PerformAction()	1302
10.347 gdcmm::network::ULActionAR8 Class Reference	1303
10.347.1 Member Function Documentation	1304
10.347.1.1 PerformAction()	1304
10.348 gdcmm::network::ULActionAR9 Class Reference	1304
10.348.1 Member Function Documentation	1305
10.348.1.1 PerformAction()	1305
10.349 gdcmm::network::ULActionDT1 Class Reference	1305
10.349.1 Member Function Documentation	1306
10.349.1.1 PerformAction()	1306
10.350 gdcmm::network::ULActionDT2 Class Reference	1307
10.350.1 Member Function Documentation	1308
10.350.1.1 PerformAction()	1308
10.351 gdcmm::network::ULBasicCallback Class Reference	1308
10.351.1 Detailed Description	1310
10.351.2 Constructor & Destructor Documentation	1310
10.351.2.1 ULBasicCallback()	1310
10.351.2.2 ~ULBasicCallback()	1310
10.351.3 Member Function Documentation	1310
10.351.3.1 GetDataSets()	1310
10.351.3.2 GetResponses()	1310
10.351.3.3 HandleDataSet()	1310
10.351.3.4 HandleResponse()	1310
10.352 gdcmm::network::ULConnection Class Reference	1311
10.352.1 Detailed Description	1312
10.352.2 Constructor & Destructor Documentation	1312
10.352.2.1 ULConnection() [1/2]	1312

10.352.2.2 ~ULConnection()	1312
10.352.2.3 ULConnection() [2/2]	1312
10.352.3 Member Function Documentation	1312
10.352.3.1 AddAcceptedPresentationContext()	1312
10.352.3.2 FindContext()	1313
10.352.3.3 GetAcceptedPresentationContexts() [1/2]	1313
10.352.3.4 GetAcceptedPresentationContexts() [2/2]	1313
10.352.3.5 GetConnectionInfo()	1313
10.352.3.6 GetMaxPDUSize()	1313
10.352.3.7 GetPresentationContextACByID()	1313
10.352.3.8 GetPresentationContextIDFromPresentationContext()	1313
10.352.3.9 GetPresentationContextRQByID()	1313
10.352.3.10 GetPresentationContexts()	1314
10.352.3.11 GetProtocol()	1314
10.352.3.12 GetState()	1314
10.352.3.13 GetTimer()	1314
10.352.3.14 InitializeConnection()	1314
10.352.3.15 InitializeIncomingConnection()	1314
10.352.3.16 operator=()	1314
10.352.3.17 SetMaxPDUSize()	1314
10.352.3.18 SetPresentationContexts() [1/2]	1315
10.352.3.19 SetPresentationContexts() [2/2]	1315
10.352.3.20 SetState()	1315
10.352.3.21 StopProtocol()	1315
10.352.4 Friends And Related Symbol Documentation	1315
10.352.4.1 ULActionAE6	1315
10.352.4.2 ULConnectionManager	1315
10.353 gdcn::network::ULConnectionCallback Class Reference	1316
10.353.1 Detailed Description	1316
10.353.2 Constructor & Destructor Documentation	1317
10.353.2.1 ULConnectionCallback()	1317
10.353.2.2 ~ULConnectionCallback()	1317
10.353.3 Member Function Documentation	1317
10.353.3.1 DataSetHandled()	1317
10.353.3.2 DataSetHandles()	1317
10.353.3.3 HandleDataSet()	1317
10.353.3.4 HandleResponse()	1317
10.353.3.5 ResetHandledDataSet()	1317
10.353.3.6 SetImplicitFlag()	1318

10.353.4 Member Data Documentation	1318
10.353.4.1 mImplicit	1318
10.354 gdcm::network::ULConnectionInfo Class Reference	1318
10.354.1 Detailed Description	1318
10.354.2 Constructor & Destructor Documentation	1319
10.354.2.1 ULConnectionInfo()	1319
10.354.3 Member Function Documentation	1319
10.354.3.1 GetCalledAETitle()	1319
10.354.3.2 GetCalledComputerName()	1319
10.354.3.3 GetCalledIPAddress()	1319
10.354.3.4 GetCalledIPPort()	1319
10.354.3.5 GetCallingAETitle()	1319
10.354.3.6 GetMaxPDULength()	1319
10.354.3.7 Initialize()	1319
10.354.3.8 SetMaxPDULength()	1320
10.355 gdcm::network::ULConnectionManager Class Reference	1320
10.355.1 Detailed Description	1323
10.355.2 Constructor & Destructor Documentation	1323
10.355.2.1 ULConnectionManager() [1/2]	1323
10.355.2.2 ULConnectionManager() [2/2]	1323
10.355.2.3 ~ULConnectionManager()	1323
10.355.3 Member Function Documentation	1323
10.355.3.1 BreakConnection()	1323
10.355.3.2 BreakConnectionNow()	1323
10.355.3.3 EstablishConnection()	1324
10.355.3.4 EstablishConnectionMove()	1324
10.355.3.5 RunEventLoop()	1324
10.355.3.6 RunMoveEventLoop()	1324
10.355.3.7 SendEcho()	1324
10.355.3.8 SendFind() [1/2]	1325
10.355.3.9 SendFind() [2/2]	1325
10.355.3.10 SendMove() [1/2]	1325
10.355.3.11 SendMove() [2/2]	1325
10.355.3.12 SendNAction() [1/2]	1325
10.355.3.13 SendNAction() [2/2]	1325
10.355.3.14 SendNCreate() [1/2]	1325
10.355.3.15 SendNCreate() [2/2]	1326
10.355.3.16 SendNDelete() [1/2]	1326
10.355.3.17 SendNDelete() [2/2]	1326

10.355.3.18 SendNEventReport() [1/2]	1326
10.355.3.19 SendNEventReport() [2/2]	1326
10.355.3.20 SendNGet() [1/2]	1326
10.355.3.21 SendNGet() [2/2]	1326
10.355.3.22 SendNSet() [1/2]	1326
10.355.3.23 SendNSet() [2/2]	1327
10.355.3.24 SendStore() [1/2]	1327
10.355.3.25 SendStore() [2/2]	1327
10.355.4 Member Data Documentation	1327
10.355.4.1 mConnection	1327
10.355.4.2 mSecondaryConnection	1327
10.355.4.3 mTransitions	1327
10.356 gdcn::network::ULEvent Class Reference	1328
10.356.1 Detailed Description	1328
10.356.2 Constructor & Destructor Documentation	1328
10.356.2.1 ULEvent() [1/2]	1328
10.356.2.2 ULEvent() [2/2]	1328
10.356.2.3 ~ULEvent()	1329
10.356.3 Member Function Documentation	1329
10.356.3.1 GetDataSetPos()	1329
10.356.3.2 GetEvent()	1329
10.356.3.3 GetIStream()	1329
10.356.3.4 GetPDUs()	1329
10.356.3.5 SetEvent()	1329
10.356.3.6 SetPDU()	1329
10.357 gdcn::network::ULTransitionTable Class Reference	1329
10.357.1 Detailed Description	1330
10.357.2 Constructor & Destructor Documentation	1330
10.357.2.1 ULTransitionTable()	1330
10.357.3 Member Function Documentation	1330
10.357.3.1 HandleEvent()	1330
10.357.3.2 PrintTable()	1330
10.358 gdcn::network::ULWritingCallback Class Reference	1331
10.358.1 Constructor & Destructor Documentation	1332
10.358.1.1 ULWritingCallback()	1332
10.358.1.2 ~ULWritingCallback()	1332
10.358.2 Member Function Documentation	1332
10.358.2.1 HandleDataSet()	1332
10.358.2.2 HandleResponse()	1332

10.358.2.3 SetDirectory()	1333
10.359 gdcm::UNExplicitDataElement Class Reference	1333
10.359.1 Detailed Description	1336
10.359.2 Member Function Documentation	1336
10.359.2.1 GetLength()	1336
10.359.2.2 Read()	1336
10.359.2.3 ReadPreValue()	1336
10.359.2.4 ReadValue()	1336
10.359.2.5 ReadWithLength()	1337
10.360 gdcm::UNExplicitImplicitDataElement Class Reference	1337
10.360.1 Detailed Description	1340
10.360.2 Member Function Documentation	1340
10.360.2.1 GetLength()	1340
10.360.2.2 Read()	1340
10.360.2.3 ReadPreValue()	1340
10.360.2.4 ReadValue()	1340
10.361 gdcm::Unpacker12Bits Class Reference	1341
10.361.1 Detailed Description	1341
10.361.2 Member Function Documentation	1341
10.361.2.1 Pack()	1341
10.361.2.2 Unpack()	1342
10.362 gdcm::Usage Class Reference	1342
10.362.1 Detailed Description	1343
10.362.2 Member Enumeration Documentation	1343
10.362.2.1 UsageType	1343
10.362.3 Constructor & Destructor Documentation	1343
10.362.3.1 Usage()	1343
10.362.4 Member Function Documentation	1344
10.362.4.1 GetUsageString()	1344
10.362.4.2 GetUsageType()	1344
10.362.4.3 operator UsageType()	1344
10.362.5 Friends And Related Symbol Documentation	1344
10.362.5.1 operator<<	1344
10.363 gdcm::UserEvent Class Reference	1345
10.364 gdcm::network::UserInformation Class Reference	1346
10.364.1 Detailed Description	1346
10.364.2 Constructor & Destructor Documentation	1347
10.364.2.1 UserInformation() [1/2]	1347
10.364.2.2 ~UserInformation()	1347

10.364.2.3 UserInformation() [2/2]	1347
10.364.3 Member Function Documentation	1347
10.364.3.1 AddRoleSelectionSub()	1347
10.364.3.2 AddSOPClassExtendedNegociationSub()	1347
10.364.3.3 GetMaximumLengthSub() [1/2]	1347
10.364.3.4 GetMaximumLengthSub() [2/2]	1347
10.364.3.5 operator=()	1348
10.364.3.6 Print()	1348
10.364.3.7 Read()	1348
10.364.3.8 Size()	1348
10.364.3.9 Write()	1348
10.365 gdcm::UUIDGenerator Class Reference	1348
10.365.1 Detailed Description	1349
10.365.2 Member Function Documentation	1349
10.365.2.1 Generate()	1349
10.365.2.2 IsValid()	1349
10.366 gdcm::Validate Class Reference	1349
10.366.1 Detailed Description	1350
10.366.2 Constructor & Destructor Documentation	1350
10.366.2.1 Validate()	1350
10.366.2.2 ~Validate()	1351
10.366.3 Member Function Documentation	1351
10.366.3.1 GetValidatedFile()	1351
10.366.3.2 SetFile()	1351
10.366.3.3 Validation()	1351
10.366.4 Member Data Documentation	1351
10.366.4.1 F	1351
10.366.4.2 V	1351
10.367 gdcm::Value Class Reference	1352
10.367.1 Detailed Description	1353
10.367.2 Constructor & Destructor Documentation	1353
10.367.2.1 Value()	1353
10.367.2.2 ~Value()	1353
10.367.3 Member Function Documentation	1354
10.367.3.1 Clear()	1354
10.367.3.2 GetLength()	1354
10.367.3.3 operator==(.)	1354
10.367.3.4 SetLength()	1354
10.367.3.5 SetLengthOnly()	1354

10.367.4 Friends And Related Symbol Documentation	1355
10.367.4.1 DataElement	1355
10.368 gdcM::ValueIO< TDE, TSwap, TType > Class Template Reference	1355
10.368.1 Detailed Description	1355
10.368.2 Member Function Documentation	1355
10.368.2.1 Read()	1355
10.368.2.2 Write()	1356
10.369 gdcM::MrProtocol::Vector3 Struct Reference	1356
10.369.1 Member Data Documentation	1356
10.369.1.1 dCor	1356
10.369.1.2 dSag	1356
10.369.1.3 dTra	1356
10.370 gdcM::Version Class Reference	1357
10.370.1 Detailed Description	1357
10.370.2 Constructor & Destructor Documentation	1357
10.370.2.1 Version()	1357
10.370.2.2 ~Version()	1357
10.370.3 Member Function Documentation	1358
10.370.3.1 GetBuildVersion()	1358
10.370.3.2 GetMajorVersion()	1358
10.370.3.3 GetMinorVersion()	1358
10.370.3.4 GetVersion()	1358
10.370.3.5 Print()	1358
10.370.4 Friends And Related Symbol Documentation	1358
10.370.4.1 operator<<	1358
10.371 gdcM::VL Class Reference	1359
10.371.1 Detailed Description	1360
10.371.2 Member Typedef Documentation	1360
10.371.2.1 Type	1360
10.371.3 Constructor & Destructor Documentation	1360
10.371.3.1 VL()	1360
10.371.4 Member Function Documentation	1360
10.371.4.1 GetLength()	1360
10.371.4.2 GetVL16Max()	1361
10.371.4.3 GetVL32Max()	1361
10.371.4.4 IsOdd()	1361
10.371.4.5 IsUndefined()	1361
10.371.4.6 operator uint32_t()	1361
10.371.4.7 operator++() [1/2]	1361

10.371.4.8 operator++() [2/2]	1361
10.371.4.9 operator+=()	1362
10.371.4.10 Read()	1362
10.371.4.11 Read16()	1362
10.371.4.12 SetToUndefined()	1362
10.371.4.13 Write()	1362
10.371.4.14 Write16()	1362
10.371.5 Friends And Related Symbol Documentation	1363
10.371.5.1 operator<<	1363
10.372 gdcmm::VM Class Reference	1363
10.372.1 Detailed Description	1364
10.372.2 Member Enumeration Documentation	1365
10.372.2.1 VMType	1365
10.372.3 Constructor & Destructor Documentation	1366
10.372.3.1 VM()	1366
10.372.4 Member Function Documentation	1367
10.372.4.1 Compatible()	1367
10.372.4.2 GetIndex()	1367
10.372.4.3 GetLength()	1367
10.372.4.4 GetNumberOfElementsFromArray()	1367
10.372.4.5 GetVMString()	1367
10.372.4.6 GetVMType()	1368
10.372.4.7 GetVMTypeFromLength()	1368
10.372.4.8 IsValid()	1368
10.372.4.9 operator VMType()	1368
10.372.5 Friends And Related Symbol Documentation	1368
10.372.5.1 operator<<	1368
10.373 gdcmm::VMToLength< T > Struct Template Reference	1368
10.374 gdcmm::VR Class Reference	1369
10.374.1 Detailed Description	1370
10.374.2 Member Enumeration Documentation	1370
10.374.2.1 VRType	1370
10.374.3 Constructor & Destructor Documentation	1372
10.374.3.1 VR()	1372
10.374.4 Member Function Documentation	1372
10.374.4.1 CanDisplay()	1372
10.374.4.2 Compatible()	1372
10.374.4.3 GetLength() [1/2]	1372
10.374.4.4 GetLength() [2/2]	1373

10.374.4.5 GetSize()	1373
10.374.4.6 GetSizeof()	1373
10.374.4.7 GetVRString()	1373
10.374.4.8 GetVRStringFromFile()	1373
10.374.4.9 GetVRType()	1373
10.374.4.10 GetVRTypeFromFile()	1373
10.374.4.11 IsASCII()	1374
10.374.4.12 IsASCII2()	1374
10.374.4.13 IsBinary()	1374
10.374.4.14 IsBinary2()	1374
10.374.4.15 IsDual()	1374
10.374.4.16 IsSwap()	1374
10.374.4.17 IsValid() [1/2]	1374
10.374.4.18 IsValid() [2/2]	1374
10.374.4.19 IsVRFile()	1375
10.374.4.20 operator VRType()	1375
10.374.4.21 Read()	1375
10.374.4.22 Write()	1375
10.374.5 Friends And Related Symbol Documentation	1375
10.374.5.1 operator<<	1375
10.375 gdcm::VR16ExplicitDataElement Class Reference	1376
10.375.1 Detailed Description	1378
10.375.2 Member Function Documentation	1378
10.375.2.1 GetLength()	1378
10.375.2.2 Read()	1379
10.375.2.3 ReadPreValue()	1379
10.375.2.4 ReadValue()	1379
10.375.2.5 ReadWithLength()	1379
10.376 gdcm::VRToEncoding< T > Struct Template Reference	1379
10.377 gdcm::VRToType< T > Struct Template Reference	1380
10.377.1 Detailed Description	1380
10.378 gdcm::VRVLSIZE< T > Class Template Reference	1380
10.379 gdcm::VRVLSIZE< 0 > Class Reference	1381
10.379.1 Member Function Documentation	1381
10.379.1.1 Read()	1381
10.379.1.2 Write()	1382
10.380 gdcm::VRVLSIZE< 1 > Class Reference	1382
10.380.1 Member Function Documentation	1383
10.380.1.1 Read()	1383

10.380.1.2 Write()	1383
10.381 vtkGDCMImageReader Class Reference	1383
10.381.1 Detailed Description	1386
10.381.2 Constructor & Destructor Documentation	1386
10.381.2.1 vtkGDCMImageReader()	1386
10.381.2.2 ~vtkGDCMImageReader()	1386
10.381.3 Member Function Documentation	1386
10.381.3.1 CanReadFile()	1386
10.381.3.2 ExecuteData()	1387
10.381.3.3 ExecuteInformation()	1387
10.381.3.4 FillMedicalImageInformation()	1387
10.381.3.5 GetDescriptiveName()	1387
10.381.3.6 GetFileExtensions()	1387
10.381.3.7 GetIconImage()	1387
10.381.3.8 GetOverlay()	1387
10.381.3.9 LoadSingleFile()	1387
10.381.3.10 New()	1388
10.381.3.11 PrintSelf()	1388
10.381.3.12 RequestDataCompat()	1388
10.381.3.13 RequestInformationCompat()	1388
10.381.3.14 SetCurve()	1388
10.381.3.15 SetFileNames()	1389
10.381.3.16 SetFilePattern()	1389
10.381.3.17 SetFilePrefix()	1389
10.381.3.18 SetMedicalImageProperties()	1389
10.381.3.19 vtkBooleanMacro() [1/5]	1389
10.381.3.20 vtkBooleanMacro() [2/5]	1389
10.381.3.21 vtkBooleanMacro() [3/5]	1390
10.381.3.22 vtkBooleanMacro() [4/5]	1390
10.381.3.23 vtkBooleanMacro() [5/5]	1390
10.381.3.24 vtkGetMacro() [1/11]	1390
10.381.3.25 vtkGetMacro() [2/11]	1390
10.381.3.26 vtkGetMacro() [3/11]	1391
10.381.3.27 vtkGetMacro() [4/11]	1391
10.381.3.28 vtkGetMacro() [5/11]	1391
10.381.3.29 vtkGetMacro() [6/11]	1391
10.381.3.30 vtkGetMacro() [7/11]	1391
10.381.3.31 vtkGetMacro() [8/11]	1392
10.381.3.32 vtkGetMacro() [9/11]	1392

10.381.3.33	vtkGetMacro() [10/11]	1392
10.381.3.34	vtkGetMacro() [11/11]	1392
10.381.3.35	vtkGetObjectMacro() [1/4]	1392
10.381.3.36	vtkGetObjectMacro() [2/4]	1392
10.381.3.37	vtkGetObjectMacro() [3/4]	1393
10.381.3.38	vtkGetObjectMacro() [4/4]	1393
10.381.3.39	vtkGetStringMacro() [1/2]	1393
10.381.3.40	vtkGetStringMacro() [2/2]	1393
10.381.3.41	vtkGetVector3Macro()	1393
10.381.3.42	vtkGetVector6Macro()	1393
10.381.3.43	vtkSetMacro() [1/4]	1394
10.381.3.44	vtkSetMacro() [2/4]	1394
10.381.3.45	vtkSetMacro() [3/4]	1394
10.381.3.46	vtkSetMacro() [4/4]	1394
10.381.3.47	vtkSetVector6Macro()	1394
10.381.3.48	vtkTypeMacro()	1395
10.381.4	Member Data Documentation	1395
10.381.4.1	ApplyInverseVideo	1395
10.381.4.2	ApplyLookupTable	1395
10.381.4.3	ApplyPlanarConfiguration	1395
10.381.4.4	ApplyShiftScale	1395
10.381.4.5	ApplyYBRToRGB	1395
10.381.4.6	Curve	1395
10.381.4.7	DirectionCosines	1396
10.381.4.8	FileNames	1396
10.381.4.9	ForceRescale	1396
10.381.4.10	IconDataScalarType	1396
10.381.4.11	IconImageDataExtent	1396
10.381.4.12	IconNumberOfScalarComponents	1396
10.381.4.13	ImageFormat	1396
10.381.4.14	ImageOrientationPatient	1396
10.381.4.15	ImagePositionPatient	1397
10.381.4.16	LoadIconImage	1397
10.381.4.17	LoadOverlays	1397
10.381.4.18	LossyFlag	1397
10.381.4.19	MedicalImageProperties	1397
10.381.4.20	NumberOfIconImages	1397
10.381.4.21	NumberOfOverlays	1397
10.381.4.22	PlanarConfiguration	1398

10.381.4.23 Scale	1398
10.381.4.24 Shift	1398
10.382 vtkGDCMImageReader2 Class Reference	1398
10.382.1 Detailed Description	1401
10.382.2 Constructor & Destructor Documentation	1401
10.382.2.1 vtkGDCMImageReader2()	1401
10.382.2.2 ~vtkGDCMImageReader2()	1401
10.382.3 Member Function Documentation	1401
10.382.3.1 CanReadFile()	1401
10.382.3.2 FillMedicalImageInformation()	1401
10.382.3.3 GetDescriptiveName()	1401
10.382.3.4 GetFileExtensions()	1402
10.382.3.5 GetIconImage()	1402
10.382.3.6 GetIconImagePort()	1402
10.382.3.7 GetOverlay()	1402
10.382.3.8 GetOverlayPort()	1402
10.382.3.9 LoadSingleFile()	1402
10.382.3.10 New()	1402
10.382.3.11 PrintSelf()	1403
10.382.3.12 ProcessRequest()	1403
10.382.3.13 RequestData()	1403
10.382.3.14 RequestDataCompat()	1403
10.382.3.15 RequestInformation()	1403
10.382.3.16 RequestInformationCompat()	1404
10.382.3.17 SetCurve()	1404
10.382.3.18 SetFilePattern()	1404
10.382.3.19 SetFilePrefix()	1404
10.382.3.20 SetMedicalImageProperties()	1404
10.382.3.21 vtkBooleanMacro() [1/5]	1404
10.382.3.22 vtkBooleanMacro() [2/5]	1405
10.382.3.23 vtkBooleanMacro() [3/5]	1405
10.382.3.24 vtkBooleanMacro() [4/5]	1405
10.382.3.25 vtkBooleanMacro() [5/5]	1405
10.382.3.26 vtkGetMacro() [1/11]	1405
10.382.3.27 vtkGetMacro() [2/11]	1406
10.382.3.28 vtkGetMacro() [3/11]	1406
10.382.3.29 vtkGetMacro() [4/11]	1406
10.382.3.30 vtkGetMacro() [5/11]	1406
10.382.3.31 vtkGetMacro() [6/11]	1406

10.382.3.32 vtkGetMacro() [7/11]	1407
10.382.3.33 vtkGetMacro() [8/11]	1407
10.382.3.34 vtkGetMacro() [9/11]	1407
10.382.3.35 vtkGetMacro() [10/11]	1407
10.382.3.36 vtkGetMacro() [11/11]	1407
10.382.3.37 vtkGetObjectMacro() [1/2]	1407
10.382.3.38 vtkGetObjectMacro() [2/2]	1408
10.382.3.39 vtkGetStringMacro() [1/2]	1408
10.382.3.40 vtkGetStringMacro() [2/2]	1408
10.382.3.41 vtkGetVector3Macro()	1408
10.382.3.42 vtkGetVector6Macro()	1408
10.382.3.43 vtkSetMacro() [1/4]	1409
10.382.3.44 vtkSetMacro() [2/4]	1409
10.382.3.45 vtkSetMacro() [3/4]	1409
10.382.3.46 vtkSetMacro() [4/4]	1409
10.382.3.47 vtkSetVector6Macro()	1409
10.382.3.48 vtkTypeMacro()	1410
10.382.4 Member Data Documentation	1410
10.382.4.1 ApplyInverseVideo	1410
10.382.4.2 ApplyLookupTable	1410
10.382.4.3 ApplyPlanarConfiguration	1410
10.382.4.4 ApplyShiftScale	1410
10.382.4.5 ApplyYBRToRGB	1410
10.382.4.6 Curve	1410
10.382.4.7 DirectionCosines	1411
10.382.4.8 ForceRescale	1411
10.382.4.9 IconDataScalarType	1411
10.382.4.10 IconImageDataExtent	1411
10.382.4.11 IconNumberOfScalarComponents	1411
10.382.4.12 ImageFormat	1411
10.382.4.13 ImageOrientationPatient	1411
10.382.4.14 ImagePositionPatient	1411
10.382.4.15 LoadIconImage	1412
10.382.4.16 LoadOverlays	1412
10.382.4.17 LossyFlag	1412
10.382.4.18 NumberOfIconImages	1412
10.382.4.19 NumberOfOverlays	1412
10.382.4.20 PlanarConfiguration	1412
10.382.4.21 Scale	1412

10.382.4.22 Shift	1413
10.383 vtkGDCMImageWriter Class Reference	1413
10.383.1 Detailed Description	1415
10.383.2 Member Enumeration Documentation	1415
10.383.2.1 CompressionTypes	1415
10.383.3 Constructor & Destructor Documentation	1415
10.383.3.1 vtkGDCMImageWriter()	1415
10.383.3.2 ~vtkGDCMImageWriter()	1415
10.383.4 Member Function Documentation	1416
10.383.4.1 GetDescriptiveName()	1416
10.383.4.2 GetFileExtensions()	1416
10.383.4.3 GetFileName()	1416
10.383.4.4 New()	1416
10.383.4.5 PrintSelf()	1416
10.383.4.6 SetDirectionCosines()	1416
10.383.4.7 SetDirectionCosinesFromImageOrientationPatient()	1417
10.383.4.8 SetFileNames()	1417
10.383.4.9 SetMedicalImageProperties()	1417
10.383.4.10 vtkBooleanMacro() [1/2]	1417
10.383.4.11 vtkBooleanMacro() [2/2]	1417
10.383.4.12 vtkGetMacro() [1/7]	1417
10.383.4.13 vtkGetMacro() [2/7]	1418
10.383.4.14 vtkGetMacro() [3/7]	1418
10.383.4.15 vtkGetMacro() [4/7]	1418
10.383.4.16 vtkGetMacro() [5/7]	1418
10.383.4.17 vtkGetMacro() [6/7]	1418
10.383.4.18 vtkGetMacro() [7/7]	1418
10.383.4.19 vtkGetObjectMacro() [1/3]	1418
10.383.4.20 vtkGetObjectMacro() [2/3]	1419
10.383.4.21 vtkGetObjectMacro() [3/3]	1419
10.383.4.22 vtkGetStringMacro() [1/2]	1419
10.383.4.23 vtkGetStringMacro() [2/2]	1419
10.383.4.24 vtkSetMacro() [1/7]	1419
10.383.4.25 vtkSetMacro() [2/7]	1419
10.383.4.26 vtkSetMacro() [3/7]	1419
10.383.4.27 vtkSetMacro() [4/7]	1420
10.383.4.28 vtkSetMacro() [5/7]	1420
10.383.4.29 vtkSetMacro() [6/7]	1420
10.383.4.30 vtkSetMacro() [7/7]	1420

10.383.4.31 vtkSetStringMacro() [1/2]	1420
10.383.4.32 vtkSetStringMacro() [2/2]	1420
10.383.4.33 vtkTypeMacro()	1420
10.383.4.34 Write()	1421
10.383.4.35 WriteGDCMData()	1421
10.383.4.36 WriteSlice()	1421
10.384 vtkGDCMMedicalImageProperties Class Reference	1421
10.384.1 Constructor & Destructor Documentation	1422
10.384.1.1 vtkGDCMMedicalImageProperties()	1422
10.384.1.2 ~vtkGDCMMedicalImageProperties()	1423
10.384.2 Member Function Documentation	1423
10.384.2.1 Clear()	1423
10.384.2.2 GetFile()	1423
10.384.2.3 New()	1423
10.384.2.4 PrintSelf()	1423
10.384.2.5 PushBackFile()	1423
10.384.2.6 vtkTypeMacro()	1423
10.384.3 Friends And Related Symbol Documentation	1424
10.384.3.1 vtkGDCMImageReader	1424
10.384.3.2 vtkGDCMImageReader2	1424
10.384.3.3 vtkGDCMImageWriter	1424
10.385 vtkGDCMPolyDataReader Class Reference	1424
10.385.1 Detailed Description	1426
10.385.2 Constructor & Destructor Documentation	1426
10.385.2.1 vtkGDCMPolyDataReader()	1426
10.385.2.2 ~vtkGDCMPolyDataReader()	1426
10.385.3 Member Function Documentation	1426
10.385.3.1 FillMedicalImageInformation()	1426
10.385.3.2 New()	1426
10.385.3.3 PrintSelf()	1427
10.385.3.4 RequestData()	1427
10.385.3.5 RequestData_HemodynamicWaveformStorage()	1427
10.385.3.6 RequestData_RTStructureSetStorage()	1427
10.385.3.7 RequestInformation()	1427
10.385.3.8 RequestInformation_HemodynamicWaveformStorage()	1427
10.385.3.9 RequestInformation_RTStructureSetStorage()	1427
10.385.3.10 vtkGetObjectMacro() [1/2]	1428
10.385.3.11 vtkGetObjectMacro() [2/2]	1428
10.385.3.12 vtkGetStringMacro()	1428

10.385.3.13 vtkSetStringMacro()	1428
10.385.3.14 vtkTypeMacro()	1428
10.385.4 Member Data Documentation	1428
10.385.4.1 FileName	1428
10.385.4.2 MedicalImageProperties	1429
10.385.4.3 RTStructSetProperties	1429
10.386 vtkGDCMPolyDataWriter Class Reference	1429
10.386.1 Detailed Description	1431
10.386.2 Constructor & Destructor Documentation	1431
10.386.2.1 vtkGDCMPolyDataWriter()	1431
10.386.2.2 ~vtkGDCMPolyDataWriter()	1431
10.386.3 Member Function Documentation	1431
10.386.3.1 InitializeRTStructSet()	1431
10.386.3.2 New()	1431
10.386.3.3 PrintSelf()	1432
10.386.3.4 SetMedicalImageProperties()	1432
10.386.3.5 SetNumberOfInputPorts()	1432
10.386.3.6 SetRTStructSetProperties()	1432
10.386.3.7 vtkTypeMacro()	1432
10.386.3.8 WriteData()	1433
10.386.3.9 WriteRTSTRUCTData()	1433
10.386.3.10 WriteRTSTRUCTInfo()	1433
10.386.4 Member Data Documentation	1433
10.386.4.1 MedicalImageProperties	1433
10.386.4.2 RTStructSetProperties	1433
10.387 vtkGDCMTesting Class Reference	1434
10.387.1 Detailed Description	1435
10.387.2 Member Typedef Documentation	1435
10.387.2.1 MD5MetalImagesType	1435
10.387.3 Constructor & Destructor Documentation	1435
10.387.3.1 vtkGDCMTesting()	1435
10.387.3.2 ~vtkGDCMTesting()	1435
10.387.4 Member Function Documentation	1436
10.387.4.1 GetGDCMDataRoot()	1436
10.387.4.2 GetMD5MetalImage()	1436
10.387.4.3 GetMHDMD5FromFile()	1436
10.387.4.4 GetNumberOfMD5MetalImages()	1436
10.387.4.5 GetRAWMD5FromFile()	1436
10.387.4.6 GetVTKDataRoot()	1436

10.387.4.7 New()	1437
10.387.4.8 PrintSelf()	1437
10.387.4.9 vtkTypeMacro()	1437
10.388 vtkGDCMThreadedImageReader Class Reference	1437
10.388.1 Constructor & Destructor Documentation	1440
10.388.1.1 vtkGDCMThreadedImageReader()	1440
10.388.1.2 ~vtkGDCMThreadedImageReader()	1440
10.388.2 Member Function Documentation	1440
10.388.2.1 ExecuteData()	1440
10.388.2.2 ExecuteInformation()	1441
10.388.2.3 New()	1441
10.388.2.4 PrintSelf()	1441
10.388.2.5 ReadFiles()	1441
10.388.2.6 RequestDataCompat()	1441
10.388.2.7 vtkBooleanMacro()	1441
10.388.2.8 vtkGetMacro()	1441
10.388.2.9 vtkSetMacro() [1/3]	1442
10.388.2.10 vtkSetMacro() [2/3]	1442
10.388.2.11 vtkSetMacro() [3/3]	1442
10.388.2.12 vtkTypeMacro()	1442
10.389 vtkGDCMThreadedImageReader2 Class Reference	1443
10.389.1 Constructor & Destructor Documentation	1444
10.389.1.1 vtkGDCMThreadedImageReader2()	1444
10.389.1.2 ~vtkGDCMThreadedImageReader2()	1444
10.389.2 Member Function Documentation	1445
10.389.2.1 GetFileName()	1445
10.389.2.2 New()	1445
10.389.2.3 PrintSelf()	1445
10.389.2.4 RequestInformation()	1445
10.389.2.5 SetFileName()	1445
10.389.2.6 SetFileNames()	1445
10.389.2.7 SplitExtent()	1445
10.389.2.8 ThreadedRequestData()	1446
10.389.2.9 vtkBooleanMacro() [1/3]	1446
10.389.2.10 vtkBooleanMacro() [2/3]	1446
10.389.2.11 vtkBooleanMacro() [3/3]	1446
10.389.2.12 vtkGetMacro() [1/8]	1446
10.389.2.13 vtkGetMacro() [2/8]	1446
10.389.2.14 vtkGetMacro() [3/8]	1447

10.389.2.15 vtkGetMacro() [4/8]	1447
10.389.2.16 vtkGetMacro() [5/8]	1447
10.389.2.17 vtkGetMacro() [6/8]	1447
10.389.2.18 vtkGetMacro() [7/8]	1447
10.389.2.19 vtkGetMacro() [8/8]	1447
10.389.2.20 vtkGetObjectMacro()	1447
10.389.2.21 vtkGetVector3Macro() [1/2]	1448
10.389.2.22 vtkGetVector3Macro() [2/2]	1448
10.389.2.23 vtkGetVector6Macro()	1448
10.389.2.24 vtkSetMacro() [1/7]	1448
10.389.2.25 vtkSetMacro() [2/7]	1448
10.389.2.26 vtkSetMacro() [3/7]	1448
10.389.2.27 vtkSetMacro() [4/7]	1448
10.389.2.28 vtkSetMacro() [5/7]	1449
10.389.2.29 vtkSetMacro() [6/7]	1449
10.389.2.30 vtkSetMacro() [7/7]	1449
10.389.2.31 vtkSetVector3Macro() [1/2]	1449
10.389.2.32 vtkSetVector3Macro() [2/2]	1449
10.389.2.33 vtkSetVector6Macro()	1449
10.389.2.34 vtkTypeMacro()	1449
10.390 vtkImageColorViewer Class Reference	1450
10.390.1 Detailed Description	1452
10.390.2 Member Enumeration Documentation	1452
10.390.2.1 anonymous enum	1452
10.390.3 Constructor & Destructor Documentation	1453
10.390.3.1 vtkImageColorViewer()	1453
10.390.3.2 ~vtkImageColorViewer()	1453
10.390.4 Member Function Documentation	1453
10.390.4.1 AddInput()	1453
10.390.4.2 AddInputConnection()	1453
10.390.4.3 GetColorLevel()	1453
10.390.4.4 GetColorWindow()	1453
10.390.4.5 GetInput()	1453
10.390.4.6 GetOffScreenRendering()	1453
10.390.4.7 GetOverlayVisibility()	1454
10.390.4.8 GetPosition()	1454
10.390.4.9 GetSize()	1454
10.390.4.10 GetSliceMax()	1454
10.390.4.11 GetSliceMin()	1454

10.390.4.12 GetSliceRange() [1/3]	1454
10.390.4.13 GetSliceRange() [2/3]	1454
10.390.4.14 GetSliceRange() [3/3]	1454
10.390.4.15 GetWindowName()	1455
10.390.4.16 InstallPipeline()	1455
10.390.4.17 New()	1455
10.390.4.18 PrintSelf()	1455
10.390.4.19 Render()	1455
10.390.4.20 SetColorLevel()	1455
10.390.4.21 SetColorWindow()	1455
10.390.4.22 SetDisplayId()	1456
10.390.4.23 SetInput()	1456
10.390.4.24 SetInputConnection()	1456
10.390.4.25 SetOffScreenRendering()	1456
10.390.4.26 SetOverlayVisibility()	1456
10.390.4.27 SetParentId()	1456
10.390.4.28 SetPosition() [1/2]	1456
10.390.4.29 SetPosition() [2/2]	1457
10.390.4.30 SetRenderer()	1457
10.390.4.31 SetRenderWindow()	1457
10.390.4.32 SetSize() [1/2]	1457
10.390.4.33 SetSize() [2/2]	1457
10.390.4.34 SetSlice()	1457
10.390.4.35 SetSliceOrientation()	1458
10.390.4.36 SetSliceOrientationToXY()	1458
10.390.4.37 SetSliceOrientationToXZ()	1458
10.390.4.38 SetSliceOrientationToYZ()	1458
10.390.4.39 SetupInteractor()	1458
10.390.4.40 SetWindowId()	1458
10.390.4.41 UnInstallPipeline()	1458
10.390.4.42 UpdateDisplayExtent()	1459
10.390.4.43 UpdateOrientation()	1459
10.390.4.44 vtkBooleanMacro()	1459
10.390.4.45 vtkGetMacro() [1/2]	1459
10.390.4.46 vtkGetMacro() [2/2]	1459
10.390.4.47 vtkGetObjectMacro() [1/5]	1459
10.390.4.48 vtkGetObjectMacro() [2/5]	1459
10.390.4.49 vtkGetObjectMacro() [3/5]	1460
10.390.4.50 vtkGetObjectMacro() [4/5]	1460

10.390.4.51 vtkGetObjectMacro() [5/5]	1460
10.390.4.52 vtkTypeMacro()	1460
10.390.5 Friends And Related Symbol Documentation	1460
10.390.5.1 vtkImageColorViewerCallback	1460
10.390.6 Member Data Documentation	1461
10.390.6.1 FirstRender	1461
10.390.6.2 ImageActor	1461
10.390.6.3 Interactor	1461
10.390.6.4 InteractorStyle	1461
10.390.6.5 OverlayImageActor	1461
10.390.6.6 Renderer	1461
10.390.6.7 RenderWindow	1461
10.390.6.8 Slice	1462
10.390.6.9 SliceOrientation	1462
10.390.6.10 WindowLevel	1462
10.391 vtkImageMapToColors16 Class Reference	1462
10.391.1 Constructor & Destructor Documentation	1464
10.391.1.1 vtkImageMapToColors16()	1464
10.391.1.2 ~vtkImageMapToColors16()	1464
10.391.2 Member Function Documentation	1464
10.391.2.1 GetMTime()	1464
10.391.2.2 New()	1464
10.391.2.3 PrintSelf()	1464
10.391.2.4 RequestData()	1465
10.391.2.5 RequestInformation()	1465
10.391.2.6 SetLookupTable()	1465
10.391.2.7 SetOutputFormatToLuminance()	1465
10.391.2.8 SetOutputFormatToLuminanceAlpha()	1465
10.391.2.9 SetOutputFormatToRGB()	1465
10.391.2.10 SetOutputFormatToRGBA()	1465
10.391.2.11 ThreadedRequestData()	1466
10.391.2.12 vtkBooleanMacro()	1466
10.391.2.13 vtkGetMacro() [1/3]	1466
10.391.2.14 vtkGetMacro() [2/3]	1466
10.391.2.15 vtkGetMacro() [3/3]	1466
10.391.2.16 vtkGetObjectMacro()	1467
10.391.2.17 vtkSetMacro() [1/3]	1467
10.391.2.18 vtkSetMacro() [2/3]	1467
10.391.2.19 vtkSetMacro() [3/3]	1467

10.391.2.20 vtkTypeMacro()	1467
10.391.3 Member Data Documentation	1467
10.391.3.1 ActiveComponent	1467
10.391.3.2 DataWasPassed	1468
10.391.3.3 LookupTable	1468
10.391.3.4 OutputFormat	1468
10.391.3.5 PassAlphaToOutput	1468
10.392 vtkImageMapToWindowLevelColors2 Class Reference	1468
10.392.1 Constructor & Destructor Documentation	1470
10.392.1.1 vtkImageMapToWindowLevelColors2()	1470
10.392.1.2 ~vtkImageMapToWindowLevelColors2()	1470
10.392.2 Member Function Documentation	1470
10.392.2.1 New()	1470
10.392.2.2 PrintSelf()	1470
10.392.2.3 RequestData()	1470
10.392.2.4 RequestInformation()	1470
10.392.2.5 ThreadedRequestData()	1471
10.392.2.6 vtkGetMacro() [1/2]	1471
10.392.2.7 vtkGetMacro() [2/2]	1471
10.392.2.8 vtkSetMacro() [1/2]	1471
10.392.2.9 vtkSetMacro() [2/2]	1471
10.392.2.10 vtkTypeMacro()	1472
10.392.3 Member Data Documentation	1472
10.392.3.1 Level	1472
10.392.3.2 Window	1472
10.393 vtkImagePlanarComponentsToComponents Class Reference	1472
10.393.1 Constructor & Destructor Documentation	1473
10.393.1.1 vtkImagePlanarComponentsToComponents()	1473
10.393.1.2 ~vtkImagePlanarComponentsToComponents()	1473
10.393.2 Member Function Documentation	1474
10.393.2.1 New()	1474
10.393.2.2 PrintSelf()	1474
10.393.2.3 RequestData()	1474
10.393.2.4 vtkTypeMacro()	1474
10.394 vtkImageRGBToYBR Class Reference	1475
10.394.1 Constructor & Destructor Documentation	1476
10.394.1.1 vtkImageRGBToYBR()	1476
10.394.1.2 ~vtkImageRGBToYBR()	1476
10.394.2 Member Function Documentation	1476

10.394.2.1 New()	1476
10.394.2.2 PrintSelf()	1476
10.394.2.3 ThreadedExecute()	1476
10.394.2.4 vtkTypeMacro()	1477
10.395 vtkImageYBRToRGB Class Reference	1477
10.395.1 Constructor & Destructor Documentation	1478
10.395.1.1 vtkImageYBRToRGB()	1478
10.395.1.2 ~vtkImageYBRToRGB()	1478
10.395.2 Member Function Documentation	1478
10.395.2.1 New()	1478
10.395.2.2 PrintSelf()	1478
10.395.2.3 ThreadedExecute()	1479
10.395.2.4 vtkTypeMacro()	1479
10.396 vtkLookupTable16 Class Reference	1479
10.396.1 Constructor & Destructor Documentation	1480
10.396.1.1 vtkLookupTable16()	1480
10.396.1.2 ~vtkLookupTable16()	1481
10.396.2 Member Function Documentation	1481
10.396.2.1 Build()	1481
10.396.2.2 GetPointer()	1481
10.396.2.3 MapScalarsThroughTable2()	1481
10.396.2.4 New()	1481
10.396.2.5 PrintSelf()	1481
10.396.2.6 SetNumberOfTableValues()	1482
10.396.2.7 vtkTypeMacro()	1482
10.396.2.8 WritePointer()	1482
10.396.3 Member Data Documentation	1482
10.396.3.1 Table16	1482
10.397 vtkRTStructSetProperties Class Reference	1483
10.397.1 Detailed Description	1485
10.397.2 Constructor & Destructor Documentation	1485
10.397.2.1 vtkRTStructSetProperties()	1485
10.397.2.2 ~vtkRTStructSetProperties()	1485
10.397.3 Member Function Documentation	1485
10.397.3.1 AddContourReferencedFrameOfReference()	1485
10.397.3.2 AddReferencedFrameOfReference()	1485
10.397.3.3 AddStructureSetROI()	1486
10.397.3.4 AddStructureSetROIObservation()	1486
10.397.3.5 Clear()	1486

10.397.3.6 DeepCopy()	1486
10.397.3.7 GetContourReferencedFrameOfReferenceClassUID()	1486
10.397.3.8 GetContourReferencedFrameOfReferenceInstanceUID()	1486
10.397.3.9 GetNumberOfContourReferencedFrameOfReferences() [1/2]	1486
10.397.3.10 GetNumberOfContourReferencedFrameOfReferences() [2/2]	1487
10.397.3.11 GetNumberOfReferencedFrameOfReferences()	1487
10.397.3.12 GetNumberOfStructureSetROIs()	1487
10.397.3.13 GetReferencedFrameOfReferenceClassUID()	1487
10.397.3.14 GetReferencedFrameOfReferenceInstanceUID()	1487
10.397.3.15 GetStructureSetObservationNumber()	1487
10.397.3.16 GetStructureSetROIDescription()	1487
10.397.3.17 GetStructureSetROIGenerationAlgorithm()	1487
10.397.3.18 GetStructureSetROIName()	1488
10.397.3.19 GetStructureSetROINumber()	1488
10.397.3.20 GetStructureSetROIObservationLabel()	1488
10.397.3.21 GetStructureSetROIRefFrameRefUID()	1488
10.397.3.22 GetStructureSetRTROIInterpretedType()	1488
10.397.3.23 New()	1488
10.397.3.24 PrintSelf()	1488
10.397.3.25 vtkGetStringMacro() [1/9]	1489
10.397.3.26 vtkGetStringMacro() [2/9]	1489
10.397.3.27 vtkGetStringMacro() [3/9]	1489
10.397.3.28 vtkGetStringMacro() [4/9]	1489
10.397.3.29 vtkGetStringMacro() [5/9]	1489
10.397.3.30 vtkGetStringMacro() [6/9]	1489
10.397.3.31 vtkGetStringMacro() [7/9]	1490
10.397.3.32 vtkGetStringMacro() [8/9]	1490
10.397.3.33 vtkGetStringMacro() [9/9]	1490
10.397.3.34 vtkSetStringMacro() [1/9]	1490
10.397.3.35 vtkSetStringMacro() [2/9]	1490
10.397.3.36 vtkSetStringMacro() [3/9]	1490
10.397.3.37 vtkSetStringMacro() [4/9]	1491
10.397.3.38 vtkSetStringMacro() [5/9]	1491
10.397.3.39 vtkSetStringMacro() [6/9]	1491
10.397.3.40 vtkSetStringMacro() [7/9]	1491
10.397.3.41 vtkSetStringMacro() [8/9]	1491
10.397.3.42 vtkSetStringMacro() [9/9]	1491
10.397.3.43 vtkTypeMacro()	1492
10.397.4 Member Data Documentation	1492

10.397.4.1 Internals	1492
10.397.4.2 ReferenceFrameOfReferenceUID	1492
10.397.4.3 ReferenceSeriesInstanceUID	1492
10.397.4.4 SeriesInstanceUID	1492
10.397.4.5 SOPInstanceUID	1492
10.397.4.6 StructureSetDate	1492
10.397.4.7 StructureSetLabel	1493
10.397.4.8 StructureSetName	1493
10.397.4.9 StructureSetTime	1493
10.397.4.10 StudyInstanceUID	1493
10.398 gdcm::Waveform Class Reference	1493
10.398.1 Detailed Description	1493
10.398.2 Constructor & Destructor Documentation	1494
10.398.2.1 Waveform()	1494
10.399 gdcm::WLMFindQuery Class Reference	1494
10.399.1 Detailed Description	1497
10.399.2 Constructor & Destructor Documentation	1497
10.399.2.1 WLMFindQuery()	1497
10.399.3 Member Function Documentation	1497
10.399.3.1 GetAbstractSyntaxUID()	1497
10.399.3.2 GetTagListByLevel()	1497
10.399.3.3 GetValidDataSet()	1497
10.399.3.4 InitializeDataSet()	1497
10.399.3.5 ValidateQuery()	1498
10.399.4 Friends And Related Symbol Documentation	1498
10.399.4.1 QueryFactory	1498
10.400 gdcm::Writer Class Reference	1498
10.400.1 Detailed Description	1500
10.400.2 Constructor & Destructor Documentation	1501
10.400.2.1 Writer()	1501
10.400.2.2 ~Writer()	1501
10.400.3 Member Function Documentation	1501
10.400.3.1 CheckFileMetaInformationOff()	1501
10.400.3.2 CheckFileMetaInformationOn()	1501
10.400.3.3 GetCheckFileMetaInformation()	1501
10.400.3.4 GetFile()	1501
10.400.3.5 GetStreamPtr()	1502
10.400.3.6 SetCheckFileMetaInformation()	1502
10.400.3.7 SetFile()	1502

10.400.3.8 SetFileName()	1502
10.400.3.9 SetStream()	1503
10.400.3.10 SetWriteDataSetOnly()	1503
10.400.3.11 Write()	1503
10.400.4 Friends And Related Symbol Documentation	1503
10.400.4.1 StreamImageWriter	1503
10.400.5 Member Data Documentation	1503
10.400.5.1 Ofstream	1503
10.400.5.2 Stream	1504
10.401 gdcmm::XMLDictReader Class Reference	1504
10.401.1 Detailed Description	1505
10.401.2 Constructor & Destructor Documentation	1505
10.401.2.1 XMLDictReader()	1505
10.401.2.2 ~XMLDictReader()	1506
10.401.3 Member Function Documentation	1506
10.401.3.1 CharacterDataHandler()	1506
10.401.3.2 EndElement()	1506
10.401.3.3 GetDict()	1506
10.401.3.4 HandleDescription()	1506
10.401.3.5 HandleEntry()	1506
10.401.3.6 StartElement()	1506
10.402 gdcmm::XMLPrinter Class Reference	1507
10.402.1 Member Enumeration Documentation	1508
10.402.1.1 PrintStyles	1508
10.402.2 Constructor & Destructor Documentation	1508
10.402.2.1 XMLPrinter()	1508
10.402.2.2 ~XMLPrinter()	1508
10.402.3 Member Function Documentation	1508
10.402.3.1 GetPrintStyle()	1508
10.402.3.2 HandleBulkData()	1508
10.402.3.3 Print()	1509
10.402.3.4 PrintDataElement()	1509
10.402.3.5 PrintDataSet()	1509
10.402.3.6 PrintSQ()	1509
10.402.3.7 SetFile()	1509
10.402.3.8 SetStyle()	1509
10.402.4 Member Data Documentation	1510
10.402.4.1 F	1510
10.402.4.2 PrintStyle	1510

10.403 gdcmm::XMLPrivateDictReader Class Reference	1510
10.403.1 Detailed Description	1512
10.403.2 Constructor & Destructor Documentation	1512
10.403.2.1 XMLPrivateDictReader()	1512
10.403.2.2 ~XMLPrivateDictReader()	1512
10.403.3 Member Function Documentation	1512
10.403.3.1 CharacterDataHandler()	1512
10.403.3.2 EndElement()	1512
10.403.3.3 GetPrivateDict()	1512
10.403.3.4 HandleDescription()	1513
10.403.3.5 HandleEntry()	1513
10.403.3.6 StartElement()	1513
11 File Documentation	1515
11.1 README.txt File Reference	1515
11.2 TestsList.txt File Reference	1515
11.3 gdcmmASN1.h File Reference	1515
11.4 gdcmmASN1.h	1516
11.5 gdcmmBase64.h File Reference	1517
11.6 gdcmmBase64.h	1517
11.7 gdcmmBoxRegion.h File Reference	1518
11.8 gdcmmBoxRegion.h	1519
11.9 gdcmmByteSwap.h File Reference	1519
11.10 gdcmmByteSwap.h	1520
11.11 gdcmmCAPICryptoFactory.h File Reference	1521
11.12 gdcmmCAPICryptoFactory.h	1522
11.13 gdcmmCAPICryptographicMessageSyntax.h File Reference	1522
11.14 gdcmmCAPICryptographicMessageSyntax.h	1523
11.15 gdcmmCommand.h File Reference	1525
11.16 gdcmmCommand.h	1526
11.17 gdcmmCryptoFactory.h File Reference	1528
11.18 gdcmmCryptoFactory.h	1529
11.19 gdcmmCryptographicMessageSyntax.h File Reference	1530
11.20 gdcmmCryptographicMessageSyntax.h	1531
11.21 gdcmmDataEvent.h File Reference	1532
11.22 gdcmmDataEvent.h	1533
11.23 gdcmmDeflateStream.h File Reference	1534
11.24 gdcmmDeflateStream.h	1534
11.25 gdcmmDirectory.h File Reference	1534

11.26 gdcDirectory.h	1535
11.27 gdcDummyValueGenerator.h File Reference	1537
11.28 gdcDummyValueGenerator.h	1537
11.29 gdcEvent.h File Reference	1538
11.29.1 Macro Definition Documentation	1539
11.29.1.1 gdcEventMacro	1539
11.30 gdcEvent.h	1540
11.31 gdcException.h File Reference	1541
11.31.1 Macro Definition Documentation	1542
11.31.1.1 gdc_assert	1542
11.31.1.2 gdc_debug_assert	1543
11.31.1.3 gdc_forced_assert	1543
11.32 gdcException.h	1543
11.33 gdcFilename.h File Reference	1545
11.34 gdcFilename.h	1545
11.35 gdcFileNameEvent.h File Reference	1546
11.36 gdcFileNameEvent.h	1547
11.37 gdcFilenameGenerator.h File Reference	1548
11.38 gdcFilenameGenerator.h	1548
11.39 gdcLegacyMacro.h File Reference	1549
11.39.1 Macro Definition Documentation	1550
11.39.1.1 GDCM_LEGACY	1550
11.39.1.2 GDCM_LEGACY_BODY	1550
11.39.1.3 GDCM_LEGACY_REPLACED_BODY	1550
11.39.1.4 GDCM_NOOP_STATEMENT	1550
11.40 gdcLegacyMacro.h	1551
11.41 gdcMD5.h File Reference	1552
11.42 gdcMD5.h	1552
11.43 gdcObject.h File Reference	1553
11.44 gdcObject.h	1554
11.45 gdcOpenSSLCryptoFactory.h File Reference	1555
11.46 gdcOpenSSLCryptoFactory.h	1556
11.47 gdcOpenSSLCryptographicMessageSyntax.h File Reference	1556
11.48 gdcOpenSSLCryptographicMessageSyntax.h	1558
11.49 gdcOpenSSLP7CryptoFactory.h File Reference	1558
11.50 gdcOpenSSLP7CryptoFactory.h	1559
11.51 gdcOpenSSLP7CryptographicMessageSyntax.h File Reference	1560
11.52 gdcOpenSSLP7CryptographicMessageSyntax.h	1561
11.53 gdcProgressEvent.h File Reference	1562

11.54 gdcProgressEvent.h	1563
11.55 gdcRegion.h File Reference	1563
11.56 gdcRegion.h	1565
11.57 gdcSHA1.h File Reference	1566
11.58 gdcSHA1.h	1566
11.59 gdcSmartPointer.h File Reference	1567
11.60 gdcSmartPointer.h	1568
11.61 gdcStaticAssert.h File Reference	1569
11.61.1 Macro Definition Documentation	1570
11.61.1.1 GDCM_DO_JOIN	1570
11.61.1.2 GDCM_DO_JOIN2	1570
11.61.1.3 GDCM_JOIN	1570
11.61.1.4 GDCM_STATIC_ASSERT	1570
11.62 gdcStaticAssert.h	1571
11.63 gdcString.h File Reference	1571
11.64 gdcString.h	1573
11.65 gdcSubject.h File Reference	1575
11.66 gdcSubject.h	1575
11.67 gdcSwapCode.h File Reference	1576
11.68 gdcSwapCode.h	1577
11.69 gdcSwapper.h File Reference	1578
11.70 gdcSwapper.h	1579
11.71 gdcSystem.h File Reference	1581
11.72 gdcSystem.h	1581
11.73 gdcTerminal.h File Reference	1583
11.74 gdcTerminal.h	1584
11.75 gdcTestDriver.h File Reference	1585
11.76 gdcTestDriver.h	1585
11.77 gdcTesting.h File Reference	1586
11.78 gdcTesting.h	1586
11.79 gdcTrace.h File Reference	1588
11.79.1 Macro Definition Documentation	1589
11.79.1.1 GDCM_FUNCTION	1589
11.79.1.2 gdcAssertAlwaysMacro	1589
11.79.1.3 gdcAssertMacro	1590
11.79.1.4 gdcDebugMacro	1590
11.79.1.5 gdcErrorMacro	1591
11.79.1.6 gdcWarningMacro	1591
11.80 gdcTrace.h	1592

11.81 gdcTypes.h File Reference	1594
11.82 gdcTypes.h	1594
11.83 gdcUnpacker12Bits.h File Reference	1595
11.84 gdcUnpacker12Bits.h	1596
11.85 gdcVersion.h File Reference	1596
11.86 gdcVersion.h	1597
11.87 gdcWin32.h File Reference	1597
11.87.1 Macro Definition Documentation	1598
11.87.1.1 GDCM_EXPORT	1598
11.88 gdcWin32.h	1598
11.89 gdcCSAHeaderDict.h File Reference	1599
11.90 gdcCSAHeaderDict.h	1600
11.91 gdcCSAHeaderDictEntry.h File Reference	1602
11.92 gdcCSAHeaderDictEntry.h	1603
11.93 gdcDict.h File Reference	1605
11.94 gdcDict.h	1606
11.95 gdcDictConverter.h File Reference	1610
11.96 gdcDictConverter.h	1611
11.97 gdcDictEntry.h File Reference	1612
11.98 gdcDictEntry.h	1613
11.99 gdcDicts.h File Reference	1615
11.100 gdcDicts.h	1616
11.101 gdcGlobal.h File Reference	1617
11.102 gdcGlobal.h	1618
11.103 gdcGroupDict.h File Reference	1619
11.104 gdcGroupDict.h	1620
11.105 gdcSOPClassUIDToIOD.h File Reference	1621
11.106 gdcSOPClassUIDToIOD.h	1621
11.107 gdcUIDs.h File Reference	1622
11.108 gdcUIDs.h	1623
11.109 gdcAttribute.h File Reference	1636
11.110 gdcAttribute.h	1637
11.111 gdcBasicOffsetTable.h File Reference	1650
11.112 gdcBasicOffsetTable.h	1651
11.113 gdcByteBuffer.h File Reference	1653
11.114 gdcByteBuffer.h	1654
11.115 gdcByteSwapFilter.h File Reference	1656
11.116 gdcByteSwapFilter.h	1656
11.117 gdcByteValue.h File Reference	1657

11.118 gdcByteValue.h	1658
11.119 gdcCodeString.h File Reference	1661
11.120 gdcCodeString.h	1662
11.121 gdcCP246ExplicitDataElement.h File Reference	1663
11.122 gdcCP246ExplicitDataElement.h	1664
11.123 gdcCSAElement.h File Reference	1664
11.124 gdcCSAElement.h	1666
11.125 gdcCSAHeader.h File Reference	1668
11.126 gdcCSAHeader.h	1668
11.127 gdcDataElement.h File Reference	1670
11.128 gdcDataElement.h	1671
11.129 gdcDataSet.h File Reference	1674
11.130 gdcDataSet.h	1675
11.131 gdcDataSetEvent.h File Reference	1678
11.132 gdcDataSetEvent.h	1679
11.133 gdcElement.h File Reference	1680
11.134 gdcElement.h	1681
11.135 gdcExplicitDataElement.h File Reference	1692
11.136 gdcExplicitDataElement.h	1693
11.137 gdcExplicitImplicitDataElement.h File Reference	1694
11.138 gdcExplicitImplicitDataElement.h	1695
11.139 gdcFile.h File Reference	1696
11.140 gdcFile.h	1697
11.141 gdcFileMetaInformation.h File Reference	1697
11.142 gdcFileMetaInformation.h	1699
11.143 gdcFileSet.h File Reference	1700
11.144 gdcFileSet.h	1702
11.145 gdcFragment.h File Reference	1702
11.146 gdcFragment.h	1704
11.147 gdcImplicitDataElement.h File Reference	1707
11.148 gdcImplicitDataElement.h	1707
11.149 gdcItem.h File Reference	1708
11.150 gdcItem.h	1709
11.151 gdcLO.h File Reference	1714
11.152 gdcLO.h	1714
11.153 gdcMediaStorage.h File Reference	1715
11.154 gdcMediaStorage.h	1716
11.155 gdcMrProtocol.h File Reference	1719
11.156 gdcMrProtocol.h	1720

11.157 gdcmlParseException.h File Reference	1721
11.158 gdcmlParseException.h	1722
11.159 gdcmlParser.h File Reference	1723
11.160 gdcmlParser.h	1724
11.161 gdcmlPDBelement.h File Reference	1726
11.162 gdcmlPDBelement.h	1727
11.163 gdcmlPDBHeader.h File Reference	1728
11.164 gdcmlPDBHeader.h	1729
11.165 gdcmlPreamble.h File Reference	1730
11.166 gdcmlPreamble.h	1731
11.167 gdcmlPrivateTag.h File Reference	1732
11.168 gdcmlPrivateTag.h	1733
11.169 gdcmlReader.h File Reference	1734
11.170 gdcmlReader.h	1735
11.171 gdcmlSequenceOfFragments.h File Reference	1736
11.172 gdcmlSequenceOfFragments.h	1737
11.173 gdcmlSequenceOfItems.h File Reference	1741
11.174 gdcmlSequenceOfItems.h	1742
11.175 gdcmlTag.h File Reference	1745
11.176 gdcmlTag.h	1747
11.177 gdcmlTagToVR.h File Reference	1750
11.178 gdcmlTagToVR.h	1750
11.179 gdcmlTransferSyntax.h File Reference	1751
11.180 gdcmlTransferSyntax.h	1752
11.181 gdcmlUNExplicitDataElement.h File Reference	1753
11.182 gdcmlUNExplicitDataElement.h	1754
11.183 gdcmlUNExplicitImplicitDataElement.h File Reference	1755
11.184 gdcmlUNExplicitImplicitDataElement.h	1756
11.185 gdcmlValue.h File Reference	1756
11.186 gdcmlValue.h	1757
11.187 gdcmlValueIO.h File Reference	1758
11.188 gdcmlValueIO.h	1759
11.189 gdcmlVL.h File Reference	1759
11.190 gdcmlVL.h	1760
11.191 gdcmlVM.h File Reference	1762
11.191.1 Macro Definition Documentation	1763
11.191.1.1 TYPETOLENGTH	1763
11.192 gdcmlVM.h	1764
11.193 gdcmlVR.h File Reference	1765

11.193.1 Macro Definition Documentation	1767
11.193.1.1 TYPETOENCODING	1767
11.193.1.2 VRTypeTemplateCase	1767
11.194 gdcVR.h	1768
11.195 gdcVR16ExplicitDataElement.h File Reference	1772
11.196 gdcVR16ExplicitDataElement.h	1773
11.197 gdcWriter.h File Reference	1774
11.198 gdcWriter.h	1775
11.199 gdcDefinedTerms.h File Reference	1776
11.200 gdcDefinedTerms.h	1777
11.201 gdcDefs.h File Reference	1777
11.202 gdcDefs.h	1779
11.203 gdcEnumeratedValues.h File Reference	1780
11.204 gdcEnumeratedValues.h	1780
11.205 gdcIOD.h File Reference	1781
11.206 gdcIOD.h	1782
11.207 gdcIODEntry.h File Reference	1784
11.208 gdcIODEntry.h	1786
11.209 gdcIODs.h File Reference	1786
11.210 gdcIODs.h	1788
11.211 gdcMacro.h File Reference	1789
11.212 gdcMacro.h	1790
11.213 gdcMacroEntry.h File Reference	1792
11.213.1 Macro Definition Documentation	1793
11.213.1.1 GDCMMACROENTRY_H	1793
11.214 gdcMacroEntry.h	1794
11.215 gdcMacros.h File Reference	1795
11.216 gdcMacros.h	1796
11.217 gdcModule.h File Reference	1797
11.218 gdcModule.h	1799
11.219 gdcModuleEntry.h File Reference	1800
11.220 gdcModuleEntry.h	1802
11.221 gdcModules.h File Reference	1803
11.222 gdcModules.h	1804
11.223 gdcNestedModuleEntries.h File Reference	1805
11.224 gdcNestedModuleEntries.h	1807
11.225 gdcPatient.h File Reference	1807
11.226 gdcPatient.h	1808
11.227 gdcSeries.h File Reference	1809

11.228 gdcSeries.h	1810
11.229 gdcStudy.h File Reference	1810
11.230 gdcStudy.h	1812
11.231 gdcTable.h File Reference	1812
11.232 gdcTable.h	1813
11.233 gdcTableEntry.h File Reference	1814
11.234 gdcTableEntry.h	1816
11.235 gdcTableReader.h File Reference	1816
11.236 gdcTableReader.h	1818
11.237 gdcType.h File Reference	1819
11.238 gdcType.h	1820
11.239 gdcUsage.h File Reference	1821
11.240 gdcUsage.h	1824
11.241 gdcXMLDictReader.h File Reference	1824
11.242 gdcXMLDictReader.h	1825
11.243 gdcXMLPrivateDictReader.h File Reference	1826
11.244 gdcXMLPrivateDictReader.h	1826
11.245 gdcAnonymizeEvent.h File Reference	1827
11.246 gdcAnonymizeEvent.h	1829
11.247 gdcAnonymizer.h File Reference	1829
11.248 gdcAnonymizer.h	1830
11.249 gdcApplicationEntity.h File Reference	1832
11.250 gdcApplicationEntity.h	1832
11.251 gdcAudioCodec.h File Reference	1833
11.252 gdcAudioCodec.h	1834
11.253 gdcBitmap.h File Reference	1834
11.254 gdcBitmap.h	1835
11.255 gdcBitmapToBitmapFilter.h File Reference	1838
11.256 gdcBitmapToBitmapFilter.h	1838
11.257 gdcCleaner.h File Reference	1839
11.258 gdcCleaner.h	1840
11.259 gdcCodec.h File Reference	1841
11.260 gdcCodec.h	1842
11.261 gdcCoder.h File Reference	1842
11.262 gdcCoder.h	1843
11.263 gdcConstCharWrapper.h File Reference	1844
11.264 gdcConstCharWrapper.h	1844
11.265 gdcCurve.h File Reference	1845
11.266 gdcCurve.h	1846

11.267 gdcDataSetHelper.h File Reference	1847
11.268 gdcDataSetHelper.h	1848
11.269 gdcDecoder.h File Reference	1848
11.270 gdcDecoder.h	1849
11.271 gdcDeltaEncodingCodec.h File Reference	1850
11.272 gdcDeltaEncodingCodec.h	1851
11.273 gdcDICOmdir.h File Reference	1851
11.274 gdcDICOmdir.h	1852
11.275 gdcDICOmdirGenerator.h File Reference	1853
11.276 gdcDICOmdirGenerator.h	1854
11.277 gdcDictPrinter.h File Reference	1855
11.278 gdcDictPrinter.h	1855
11.279 gdcDirectionCosines.h File Reference	1856
11.280 gdcDirectionCosines.h	1857
11.281 gdcDirectoryHelper.h File Reference	1857
11.282 gdcDirectoryHelper.h	1858
11.283 gdcDPath.h File Reference	1859
11.284 gdcDPath.h	1860
11.285 gdcDumper.h File Reference	1861
11.286 gdcDumper.h	1862
11.287 gdcEmptyMaskGenerator.h File Reference	1863
11.288 gdcEmptyMaskGenerator.h	1863
11.289 gdcEncapsulatedDocument.h File Reference	1864
11.290 gdcEncapsulatedDocument.h	1865
11.291 gdcEquipmentManufacturer.h File Reference	1865
11.292 gdcEquipmentManufacturer.h	1866
11.293 gdcFiducials.h File Reference	1867
11.294 gdcFiducials.h	1867
11.295 gdcFileAnonymizer.h File Reference	1868
11.296 gdcFileAnonymizer.h	1869
11.297 gdcFileChangeTransferSyntax.h File Reference	1869
11.298 gdcFileChangeTransferSyntax.h	1870
11.299 gdcFileDecompressLookupTable.h File Reference	1871
11.300 gdcFileDecompressLookupTable.h	1872
11.301 gdcFileDerivation.h File Reference	1873
11.302 gdcFileDerivation.h	1873
11.303 gdcFileExplicitFilter.h File Reference	1874
11.304 gdcFileExplicitFilter.h	1875
11.305 gdcFileStreamer.h File Reference	1876

11.306 gdcmlFileStreamer.h	1876
11.307 gdcmlconImage.h File Reference	1877
11.308 gdcmlconImage.h	1878
11.309 gdcmlconImageFilter.h File Reference	1879
11.310 gdcmlconImageFilter.h	1880
11.311 gdcmlconImageGenerator.h File Reference	1881
11.312 gdcmlconImageGenerator.h	1882
11.313 gdcmlImage.h File Reference	1882
11.314 gdcmlImage.h	1884
11.315 gdcmlImageApplyLookupTable.h File Reference	1885
11.316 gdcmlImageApplyLookupTable.h	1885
11.317 gdcmlImageChangePhotometricInterpretation.h File Reference	1886
11.318 gdcmlImageChangePhotometricInterpretation.h	1887
11.319 gdcmlImageChangePlanarConfiguration.h File Reference	1889
11.320 gdcmlImageChangePlanarConfiguration.h	1889
11.321 gdcmlImageChangeTransferSyntax.h File Reference	1890
11.322 gdcmlImageChangeTransferSyntax.h	1891
11.323 gdcmlImageCodec.h File Reference	1892
11.324 gdcmlImageCodec.h	1893
11.325 gdcmlImageConverter.h File Reference	1895
11.326 gdcmlImageConverter.h	1896
11.327 gdcmlImageFragmentSplitter.h File Reference	1897
11.328 gdcmlImageFragmentSplitter.h	1897
11.329 gdcmlImageHelper.h File Reference	1898
11.330 gdcmlImageHelper.h	1899
11.331 gdcmlImageReader.h File Reference	1900
11.332 gdcmlImageReader.h	1901
11.333 gdcmlImageRegionReader.h File Reference	1902
11.334 gdcmlImageRegionReader.h	1903
11.335 gdcmlImageToImageFilter.h File Reference	1904
11.336 gdcmlImageToImageFilter.h	1904
11.337 gdcmlImageWriter.h File Reference	1905
11.338 gdcmlImageWriter.h	1906
11.339 gdcmlIPPSorter.h File Reference	1906
11.340 gdcmlIPPSorter.h	1907
11.341 gdcmlJPEG12Codec.h File Reference	1908
11.342 gdcmlJPEG12Codec.h	1909
11.343 gdcmlJPEG16Codec.h File Reference	1910
11.344 gdcmlJPEG16Codec.h	1910

11.345 gdcMJPEG2000Codec.h File Reference	1911
11.346 gdcMJPEG2000Codec.h	1912
11.347 gdcMJPEG8Codec.h File Reference	1913
11.348 gdcMJPEG8Codec.h	1914
11.349 gdcMJPEGCodec.h File Reference	1915
11.350 gdcMJPEGCodec.h	1916
11.351 gdcMJPEGLSCCodec.h File Reference	1917
11.352 gdcMJPEGLSCCodec.h	1918
11.353 gdcJSON.h File Reference	1919
11.354 gdcJSON.h	1919
11.355 gdcKAKADUCCodec.h File Reference	1921
11.356 gdcKAKADUCCodec.h	1921
11.357 gdcLookupTable.h File Reference	1922
11.358 gdcLookupTable.h	1923
11.359 gdcMEC_MR3.h File Reference	1924
11.360 gdcMEC_MR3.h	1925
11.361 gdcMeshPrimitive.h File Reference	1925
11.362 gdcMeshPrimitive.h	1927
11.363 gdcOrientation.h File Reference	1928
11.364 gdcOrientation.h	1929
11.365 gdcOverlay.h File Reference	1929
11.366 gdcOverlay.h	1930
11.367 gdcPDFCodec.h File Reference	1932
11.368 gdcPDFCodec.h	1932
11.369 gdcPersonName.h File Reference	1933
11.370 gdcPersonName.h	1934
11.371 gdcPGXCodec.h File Reference	1935
11.372 gdcPGXCodec.h	1936
11.373 gdcPhotometricInterpretation.h File Reference	1936
11.374 gdcPhotometricInterpretation.h	1937
11.375 gdcPixelFormat.h File Reference	1938
11.376 gdcPixelFormat.h	1940
11.377 gdcPixmap.h File Reference	1942
11.378 gdcPixmap.h	1943
11.379 gdcPixmapReader.h File Reference	1945
11.380 gdcPixmapReader.h	1946
11.381 gdcPixmapToPixmapFilter.h File Reference	1947
11.382 gdcPixmapToPixmapFilter.h	1947
11.383 gdcPixmapWriter.h File Reference	1948

11.384 gdcmapWriter.h	1949
11.385 gdcmapPnmCodec.h File Reference	1950
11.386 gdcmapPnmCodec.h	1951
11.387 gdcmapPrinter.h File Reference	1951
11.388 gdcmapPrinter.h	1953
11.389 gdcmapPVRGCodec.h File Reference	1954
11.390 gdcmapPVRGCodec.h	1955
11.391 gdcmapRAWCodec.h File Reference	1956
11.392 gdcmapRAWCodec.h	1956
11.393 gdcmapRescaler.h File Reference	1957
11.394 gdcmapRescaler.h	1958
11.395 gdcmapRLECodec.h File Reference	1959
11.396 gdcmapRLECodec.h	1959
11.397 gdcmapScanner.h File Reference	1960
11.398 gdcmapScanner.h	1961
11.399 gdcmapScanner2.h File Reference	1963
11.400 gdcmapScanner2.h	1964
11.401 gdcmapSegment.h File Reference	1966
11.402 gdcmapSegment.h	1968
11.403 gdcmapSegmentedPaletteColorLookupTable.h File Reference	1970
11.404 gdcmapSegmentedPaletteColorLookupTable.h	1970
11.405 gdcmapSegmentHelper.h File Reference	1971
11.406 gdcmapSegmentHelper.h	1972
11.407 gdcmapSegmentReader.h File Reference	1973
11.408 gdcmapSegmentReader.h	1975
11.409 gdcmapSegmentWriter.h File Reference	1975
11.410 gdcmapSegmentWriter.h	1977
11.411 gdcmapSerieHelper.h File Reference	1977
11.412 gdcmapSerieHelper.h	1979
11.413 gdcmapSimpleSubjectWatcher.h File Reference	1980
11.414 gdcmapSimpleSubjectWatcher.h	1981
11.415 gdcmapSorter.h File Reference	1982
11.416 gdcmapSorter.h	1984
11.417 gdcmapSpacing.h File Reference	1985
11.418 gdcmapSpacing.h	1985
11.419 gdcmapSpectroscopy.h File Reference	1986
11.420 gdcmapSpectroscopy.h	1987
11.421 gdcmapSplitMosaicFilter.h File Reference	1987
11.422 gdcmapSplitMosaicFilter.h	1988

11.423 gdcmlStreamImageReader.h File Reference	1990
11.424 gdcmlStreamImageReader.h	1990
11.425 gdcmlStreamImageWriter.h File Reference	1991
11.426 gdcmlStreamImageWriter.h	1992
11.427 gdcmlStrictScanner.h File Reference	1993
11.428 gdcmlStrictScanner.h	1994
11.429 gdcmlStrictScanner2.h File Reference	1996
11.430 gdcmlStrictScanner2.h	1997
11.431 gdcmlStringFilter.h File Reference	1999
11.432 gdcmlStringFilter.h	2000
11.433 gdcmlSurface.h File Reference	2000
11.434 gdcmlSurface.h	2002
11.435 gdcmlSurfaceHelper.h File Reference	2005
11.436 gdcmlSurfaceHelper.h	2005
11.437 gdcmlSurfaceReader.h File Reference	2007
11.438 gdcmlSurfaceReader.h	2008
11.439 gdcmlSurfaceWriter.h File Reference	2009
11.440 gdcmlSurfaceWriter.h	2010
11.441 gdcmlTagPath.h File Reference	2010
11.442 gdcmlTagPath.h	2011
11.443 gdcmlUIDGenerator.h File Reference	2012
11.444 gdcmlUIDGenerator.h	2013
11.445 gdcmlUUIDGenerator.h File Reference	2014
11.446 gdcmlUUIDGenerator.h	2014
11.447 gdcmlValidate.h File Reference	2015
11.448 gdcmlValidate.h	2016
11.449 gdcmlWaveform.h File Reference	2016
11.450 gdcmlWaveform.h	2017
11.451 gdcmlXMLPrinter.h File Reference	2017
11.452 gdcmlXMLPrinter.h	2018
11.453 gdcmlAAabortPDU.h File Reference	2020
11.454 gdcmlAAabortPDU.h	2021
11.455 gdcmlAAAssociateACPDU.h File Reference	2021
11.456 gdcmlAAAssociateACPDU.h	2022
11.457 gdcmlAAAssociateRJPDU.h File Reference	2024
11.458 gdcmlAAAssociateRJPDU.h	2024
11.459 gdcmlAAAssociateRQPDU.h File Reference	2025
11.460 gdcmlAAAssociateRQPDU.h	2026
11.461 gdcmlAbstractSyntax.h File Reference	2028

11.462 gdcAbstractSyntax.h	2029
11.463 gdcApplicationContext.h File Reference	2030
11.464 gdcApplicationContext.h	2031
11.465 gdcAReleaseRPPDU.h File Reference	2031
11.466 gdcAReleaseRPPDU.h	2032
11.467 gdcAReleaseRQPDU.h File Reference	2033
11.468 gdcAReleaseRQPDU.h	2034
11.469 gdcARTIMTimer.h File Reference	2034
11.470 gdcARTIMTimer.h	2035
11.471 gdcAsynchronousOperationsWindowSub.h File Reference	2036
11.472 gdcAsynchronousOperationsWindowSub.h	2036
11.473 gdcBaseCompositeMessage.h File Reference	2037
11.474 gdcBaseCompositeMessage.h	2038
11.475 gdcBaseNormalizedMessage.h File Reference	2039
11.476 gdcBaseNormalizedMessage.h	2040
11.477 gdcBasePDU.h File Reference	2040
11.478 gdcBasePDU.h	2041
11.479 gdcBaseQuery.h File Reference	2042
11.480 gdcBaseQuery.h	2043
11.481 gdcBaseRootQuery.h File Reference	2044
11.482 gdcBaseRootQuery.h	2045
11.483 gdcCEchoMessages.h File Reference	2046
11.484 gdcCEchoMessages.h	2047
11.485 gdcCFindMessages.h File Reference	2047
11.486 gdcCFindMessages.h	2048
11.487 gdcCMoveMessages.h File Reference	2049
11.488 gdcCMoveMessages.h	2050
11.489 gdcCommandDataSet.h File Reference	2050
11.490 gdcCommandDataSet.h	2051
11.491 gdcCompositeMessageFactory.h File Reference	2052
11.492 gdcCompositeMessageFactory.h	2053
11.493 gdcCompositeNetworkFunctions.h File Reference	2053
11.494 gdcCompositeNetworkFunctions.h	2054
11.495 gdcCStoreMessages.h File Reference	2055
11.496 gdcCStoreMessages.h	2056
11.497 gdcDIMSE.h File Reference	2057
11.498 gdcDIMSE.h	2057
11.499 gdcFindPatientRootQuery.h File Reference	2059
11.500 gdcFindPatientRootQuery.h	2060

11.501 gdcFindStudyRootQuery.h File Reference	2061
11.502 gdcFindStudyRootQuery.h	2061
11.503 gdcImplementationClassUIDSub.h File Reference	2062
11.504 gdcImplementationClassUIDSub.h	2063
11.505 gdcImplementationUIDSub.h File Reference	2064
11.506 gdcImplementationUIDSub.h	2064
11.507 gdcImplementationVersionNameSub.h File Reference	2065
11.508 gdcImplementationVersionNameSub.h	2066
11.509 gdcMaximumLengthSub.h File Reference	2067
11.510 gdcMaximumLengthSub.h	2068
11.511 gdcModalityPerformedProcedureStepCreateQuery.h File Reference	2069
11.512 gdcModalityPerformedProcedureStepCreateQuery.h	2069
11.513 gdcModalityPerformedProcedureStepSetQuery.h File Reference	2070
11.514 gdcModalityPerformedProcedureStepSetQuery.h	2071
11.515 gdcMovePatientRootQuery.h File Reference	2071
11.516 gdcMovePatientRootQuery.h	2072
11.517 gdcMoveStudyRootQuery.h File Reference	2073
11.518 gdcMoveStudyRootQuery.h	2073
11.519 gdcNActionMessages.h File Reference	2074
11.520 gdcNActionMessages.h	2075
11.521 gdcNCreateMessages.h File Reference	2075
11.522 gdcNCreateMessages.h	2076
11.523 gdcNDeleteMessages.h File Reference	2077
11.524 gdcNDeleteMessages.h	2077
11.525 gdcNetworkEvents.h File Reference	2078
11.526 gdcNetworkEvents.h	2079
11.527 gdcNetworkStateID.h File Reference	2080
11.528 gdcNetworkStateID.h	2081
11.529 gdcNEventReportMessages.h File Reference	2082
11.530 gdcNEventReportMessages.h	2083
11.531 gdcNGetMessages.h File Reference	2083
11.532 gdcNGetMessages.h	2084
11.533 gdcNormalizedMessageFactory.h File Reference	2084
11.534 gdcNormalizedMessageFactory.h	2085
11.535 gdcNormalizedNetworkFunctions.h File Reference	2086
11.536 gdcNormalizedNetworkFunctions.h	2087
11.537 gdcNSetMessages.h File Reference	2088
11.538 gdcNSetMessages.h	2088
11.539 gdcPDataTFPDU.h File Reference	2089

11.540 gdcnPDataTFPDU.h	2090
11.541 gdcnPDUFactory.h File Reference	2091
11.542 gdcnPDUFactory.h	2091
11.543 gdcmPresentationContext.h File Reference	2092
11.544 gdcmPresentationContext.h	2094
11.545 gdcmPresentationContextAC.h File Reference	2094
11.546 gdcmPresentationContextAC.h	2096
11.547 gdcmPresentationContextGenerator.h File Reference	2096
11.548 gdcmPresentationContextGenerator.h	2097
11.549 gdcmPresentationContextRQ.h File Reference	2098
11.550 gdcmPresentationContextRQ.h	2099
11.551 gdcmPresentationDataValue.h File Reference	2100
11.552 gdcmPresentationDataValue.h	2101
11.553 gdcmQueryBase.h File Reference	2102
11.554 gdcmQueryBase.h	2104
11.555 gdcmQueryFactory.h File Reference	2105
11.556 gdcmQueryFactory.h	2106
11.557 gdcmQueryImage.h File Reference	2106
11.558 gdcmQueryImage.h	2107
11.559 gdcmQueryPatient.h File Reference	2108
11.560 gdcmQueryPatient.h	2109
11.561 gdcmQuerySeries.h File Reference	2110
11.562 gdcmQuerySeries.h	2111
11.563 gdcmQueryStudy.h File Reference	2112
11.564 gdcmQueryStudy.h	2113
11.565 gdcmRoleSelectionSub.h File Reference	2113
11.566 gdcmRoleSelectionSub.h	2114
11.567 gdcmServiceClassApplicationInformation.h File Reference	2115
11.568 gdcmServiceClassApplicationInformation.h	2116
11.569 gdcmServiceClassUser.h File Reference	2116
11.570 gdcmServiceClassUser.h	2117
11.571 gdcmSOPClassExtendedNegociationSub.h File Reference	2119
11.572 gdcmSOPClassExtendedNegociationSub.h	2119
11.573 gdcmTransferSyntaxSub.h File Reference	2120
11.574 gdcmTransferSyntaxSub.h	2122
11.575 gdcmULAction.h File Reference	2122
11.576 gdcmULAction.h	2123
11.577 gdcmULActionAA.h File Reference	2124
11.578 gdcmULActionAA.h	2125

11.579 gdcmlActionAE.h File Reference	2126
11.580 gdcmlActionAE.h	2127
11.581 gdcmlActionAR.h File Reference	2128
11.582 gdcmlActionAR.h	2129
11.583 gdcmlActionDT.h File Reference	2131
11.584 gdcmlActionDT.h	2131
11.585 gdcmlBasicCallback.h File Reference	2132
11.586 gdcmlBasicCallback.h	2133
11.587 gdcmlConnection.h File Reference	2133
11.588 gdcmlConnection.h	2134
11.589 gdcmlConnectionCallback.h File Reference	2136
11.590 gdcmlConnectionCallback.h	2137
11.591 gdcmlConnectionInfo.h File Reference	2137
11.592 gdcmlConnectionInfo.h	2139
11.593 gdcmlConnectionManager.h File Reference	2139
11.594 gdcmlConnectionManager.h	2140
11.595 gdcmlEvent.h File Reference	2142
11.596 gdcmlEvent.h	2143
11.597 gdcmlTransitionTable.h File Reference	2144
11.598 gdcmlTransitionTable.h	2145
11.599 gdcmlWritingCallback.h File Reference	2147
11.600 gdcmlWritingCallback.h	2147
11.601 gdcmlUserInformation.h File Reference	2148
11.602 gdcmlUserInformation.h	2149
11.603 gdcmlWLMFindQuery.h File Reference	2150
11.604 gdcmlWLMFindQuery.h	2151
11.605 vtkGDCMImageReader.h File Reference	2151
11.605.1 Macro Definition Documentation	2153
11.605.1.1 VTK_CMYK	2153
11.605.1.2 VTK_INVERSE_LUMINANCE	2153
11.605.1.3 VTK_LOOKUP_TABLE	2153
11.605.1.4 VTK_YBR	2153
11.606 vtkGDCMImageReader.h	2153
11.607 vtkGDCMImageReader2.h File Reference	2157
11.607.1 Macro Definition Documentation	2158
11.607.1.1 VTK_CMYK	2158
11.607.1.2 VTK_INVERSE_LUMINANCE	2158
11.607.1.3 VTK_LOOKUP_TABLE	2158
11.607.1.4 VTK_YBR	2158

11.608 vtkGDCMImageReader2.h	2159
11.609 vtkGDCMImageWriter.h File Reference	2162
11.610 vtkGDCMImageWriter.h	2163
11.611 vtkGDCMMedicalImageProperties.h File Reference	2165
11.612 vtkGDCMMedicalImageProperties.h	2166
11.613 vtkGDCMPolyDataReader.h File Reference	2171
11.614 vtkGDCMPolyDataReader.h	2171
11.615 vtkGDCMPolyDataWriter.h File Reference	2172
11.616 vtkGDCMPolyDataWriter.h	2173
11.617 vtkGDCMTesting.h File Reference	2174
11.618 vtkGDCMTesting.h	2175
11.619 vtkGDCMThreadedImageReader.h File Reference	2176
11.620 vtkGDCMThreadedImageReader.h	2176
11.621 vtkGDCMThreadedImageReader2.h File Reference	2178
11.622 vtkGDCMThreadedImageReader2.h	2178
11.623 vtkImageColorViewer.h File Reference	2180
11.624 vtkImageColorViewer.h	2181
11.625 vtkImageMapToColors16.h File Reference	2184
11.626 vtkImageMapToColors16.h	2184
11.627 vtkImageMapToWindowLevelColors2.h File Reference	2186
11.628 vtkImageMapToWindowLevelColors2.h	2186
11.629 vtkImagePlanarComponentsToComponents.h File Reference	2188
11.630 vtkImagePlanarComponentsToComponents.h	2188
11.631 vtkImageRGBToYBR.h File Reference	2189
11.632 vtkImageRGBToYBR.h	2190
11.633 vtkImageYBRToRGB.h File Reference	2191
11.634 vtkImageYBRToRGB.h	2191
11.635 vtkLookupTable16.h File Reference	2192
11.636 vtkLookupTable16.h	2193
11.637 vtkRTStructSetProperties.h File Reference	2194
11.638 vtkRTStructSetProperties.h	2195
11.639 gdcmPythonFilter.h File Reference	2196
11.640 gdcmPythonFilter.h	2197
12 Examples	2199
12.1 TestByteSwap.cxx	2199
12.2 PatchFile.cxx	2201
12.3 SimplePrint.cs	2202
12.4 TestReader.cxx	2204

12.5 TestReader.py	2205
12.6 DecompressJPEGFile.cs	2205
12.7 ManipulateFile.cs	2206
12.8 ClinicalTrialIdentificationWorkflow.cs	2207
12.9 GenerateDICOMDIR.cs	2210
12.10 GenFakelImage.cxx	2211
12.11 ReformatFile.cs	2213
12.12 DecompressImage.cs	2214
12.13 StandardizeFiles.cs	2215
12.14 ScanDirectory.cs	2217
12.15 BasicAnonymizer.cs	2218
12.16 BasicImageAnonymizer.cs	2220
12.17 Cleaner.cs	2221
12.18 CompressLossyJPEG.cs	2222
12.19 DecompressImageMultiframe.cs	2223
12.20 DumpCSA.cs	2225
12.21 ExplicitLittleEndian.cs	2226
12.22 ExtractEncapsulatedFile.cs	2228
12.23 ExtractImageRegion.cs	2229
12.24 ExtractImageRegionWithLUT.cs	2230
12.25 ExtractOneFrame.cs	2232
12.26 FileAnonymize.cs	2233
12.27 FileChangeTS.cs	2233
12.28 FileChangeTSLossy.cs	2236
12.29 FileStreaming.cs	2238
12.30 GetArray.cs	2239
12.31 MpegVideoInfo.cs	2240
12.32 NewSequence.cs	2245
12.33 RescaleImage.cs	2246
12.34 SendFileSCU.cs	2247
12.35 SimplePrintPatientName.cs	2247
12.36 SortImage2.cs	2248
12.37 CStoreQtProgress.cxx	2249
12.38 ChangePrivateTags.cxx	2251
12.39 ChangeSequenceUltrasound.cxx	2252
12.40 CheckBigEndianBug.cxx	2253
12.41 ClinicalTrialAnnotate.cxx	2255
12.42 CompressImage.cxx	2256
12.43 ConvertToQImage.cxx	2257

12.44 CreateARGBImage.cxx	2259
12.45 CreateCMYKImage.cxx	2260
12.46 CreateJPIPDataSet.cxx	2261
12.47 DeriveSeries.cxx	2262
12.48 DiffFile.cxx	2263
12.49 DiscriminateVolume.cxx	2264
12.50 DumpADAC.cxx	2268
12.51 DumpExamCard.cxx	2272
12.52 DumpGEMSMovieGroup.cxx	2281
12.53 DumpImageHeaderInfo.cxx	2287
12.54 DumpPhilipsECHO.cxx	2289
12.55 DumpSiemensBase64.cxx	2295
12.56 DumpToSQLITE3.cxx	2296
12.57 DumpToshibaDTI.cxx	2298
12.58 DumpToshibaDTI2.cxx	2299
12.59 DumpVisusChange.cxx	2301
12.60 DuplicatePCDE.cxx	2303
12.61 ELSCINT1WaveToText.cxx	2305
12.62 EmptyMask.cxx	2307
12.63 EncapsulateFileInRawData.cxx	2308
12.64 ExtractEncryptedContent.cxx	2309
12.65 ExtractIconFromFile.cxx	2310
12.66 Extracting_All_Resolution.cxx	2311
12.67 Fake_Image_Using_Stream_Image_Writer.cxx	2317
12.68 FixBrokenJ2K.cxx	2320
12.69 FixJAIBugJPEGLS.cxx	2322
12.70 FixOrientation.cxx	2325
12.71 GenAllVR.cxx	2326
12.72 GenFakeIdentifyFile.cxx	2328
12.73 GenLongSeqs.cxx	2330
12.74 GenSeqs.cxx	2332
12.75 GenerateStandardSOPClasses.cxx	2333
12.76 GetJPEGSamplePrecision.cxx	2334
12.77 GetSequenceUltrasound.cxx	2336
12.78 GetSubSequenceData.cxx	2337
12.79 HelloVizWorld.cxx	2340
12.80 HelloWorld.cxx	2341
12.81 LargeVRDSExplicit.cxx	2342
12.82 MakeTemplate.cxx	2345

12.83 MergeTwoFiles.cxx	2346
12.84 MrProtocol.cxx	2347
12.85 PrintLUT.cxx	2354
12.86 PublicDict.cxx	2354
12.87 QIDO-RS.cxx	2355
12.88 ReadAndDumpDICOMDIR.cxx	2356
12.89 ReadAndDumpDICOMDIR2.cxx	2359
12.90 ReadAndPrintAttributes.cxx	2364
12.91 ReadExplicitLengthSQIVR.cxx	2365
12.92 ReadGEMSSDO.cxx	2366
12.93 ReadMultiTimesException.cxx	2368
12.94 ReadUTF8QtDir.cxx	2369
12.95 SimpleScanner.cxx	2370
12.96 SortImage.cxx	2372
12.97 StreamImageReaderTest.cxx	2374
12.98 TemplateEmptyImage.cxx	2377
12.99 TraverseModules.cxx	2379
12.100 VolumeSorter.cxx	2380
12.101 csa2img.cxx	2382
12.102 iU22tomultisc.cxx	2384
12.103 pmsct_rgb1.cxx	2386
12.104 rle2img.cxx	2389
12.105 uid_unique.cxx	2392
12.106 DecompressImage.java	2393
12.107 DecompressPixmap.java	2393
12.108 ExtractImageRegion.java	2394
12.109 FileAnonymize.java	2395
12.110 HelloSimple.java	2396
12.111 ReadFiles.java	2397
12.112 ScanDirectory.java	2398
12.113 SimplePrint.java	2402
12.114 AddPrivateAttribute.py	2403
12.115 ConvertMPL.py	2403
12.116 ConvertNumpy.py	2404
12.117 ConvertPIL.py	2405
12.118 CreateRAWStorage.py	2406
12.119 DecompressImage.py	2408
12.120 DumbAnonymizer.py	2409
12.121 ExtractImageRegion.py	2411

12.122 FindAllPatientName.py	2412
12.123 FixCommaBug.py	2412
12.124 GetPortionCSAHeader.py	2413
12.125 HelloWorld.py	2414
12.126 ManipulateFile.py	2414
12.127 ManipulateSequence.py	2416
12.128 MergeFile.py	2417
12.129 NewSequence.py	2417
12.130 PhilipsPrivateRescaleInterceptSlope.py	2418
12.131 PlaySound.py	2419
12.132 PrivateDict.py	2420
12.133 ReWriteSCAsMR.py	2420
12.134 ReadAndDumpDICOMDIR.py	2421
12.135 RemovePrivateTags.py	2424
12.136 ScanDirectory.py	2424
12.137 SortImage.py	2425
12.138 WriteBuffer.py	2425
12.139 HelloActiviz.cs	2426
12.140 HelloActiviz2.cs	2428
12.141 HelloActiviz3.cs	2429
12.142 HelloActiviz4.cs	2430
12.143 HelloActiviz5.cs	2430
12.144 HelloVTKWorld.cs	2432
12.145 HelloVTKWorld2.cs	2433
12.146 MetalImageMD5Activiz.cs	2433
12.147 RefCounting.cs	2435
12.148 Compute3DSpacing.cxx	2435
12.149 Convert16BitsTo8Bits.cxx	2437
12.150 ConvertMultiFrameToSingleFrame.cxx	2438
12.151 ConvertRGBToLuminance.cxx	2439
12.152 ConvertSingleBitTo8Bits.cxx	2440
12.153 CreateFakePET.cxx	2441
12.154 CreateFakeRTDOSE.cxx	2442
12.155 GenerateRTSTRUCT.cxx	2444
12.156 MagnifyFile.cxx	2447
12.157 gdcmortoplanes.cxx	2448
12.158 gdcmrlice.cxx	2454
12.159 gdcmrtonplan.cxx	2456
12.160 gdcmrtpplan.cxx	2460

12.161 gdcmscene.cxx	2464
12.162 gdcmttexture.cxx	2466
12.163 gdcmvolume.cxx	2468
12.164 offscreenimage.cxx	2469
12.165 reslicesphere.cxx	2470
12.166 rtstructapp.cxx	2478
12.167 threadgdc.cxx	2480
12.168 AWTMedical3.java	2483
12.169 HelloVTKWorld.java	2487
12.170 MIPViewer.java	2489
12.171 MPRViewer.java	2491
12.172 MPRViewer2.java	2493
12.173 ReadSeriesIntoVTK.java	2497
12.174 CastConvertPhilips.py	2499
12.175 headsq2dcm.py	2501

Index	2503
--------------	-------------

Chapter 1

GDCM Documentation

This is the developers documentation.

A PDF version of this doxygen documentation can be found here:

<http://gdcm.sourceforge.net/3.2/gdcm-3.2.2.pdf>

A tarball version of this HTML doxygen documentation can be found here:

<http://gdcm.sourceforge.net/3.2/gdcm-3.2.2-doc.tar.gz>

Author

Mathieu Malaterre

Chapter 2

Todo List

Class [gdcm::CSAHeader](#)

MrEvaProtocol in 29,1020 contains ^M that would be nice to get rid of on UNIX system...

Class [gdcm::network::ApplicationContext](#)

Looks like Application Context can only be 64 bytes at max (see Figure 9-1 / PS 3.8 - 2009)

Class [gdcm::Overlay](#)

Is there actually any way to recognize an overlay ? On images with multiple overlay I do not see any way to differentiate them (other than the group tag).

Class [gdcm::SequenceOfFragments](#)

I do not enforce that Sequence of Fragments ends with a SQ end del

Class [gdcm::TransferSyntax](#)

: The implementation is completely retarded -> see [gdcm::UIDs](#) for a replacement We need: IsSupported We need preprocess of raw/xml file We need GetFullName()

Member [gdcm::UIDGenerator::IsValid](#) (const char *uid)

: Move that in DataStructureAndEncoding (see FileMetaInformation::CheckFileMetaInformation)

Chapter 3

Deprecated List

Member `gdcm::CompositeNetworkFunctions::ConstructQuery` (`ERootType` inRootType, `EQueryLevel` inQueryLevel, const `KeyValuePairArrayType` &keys, `EQueryType` queryType=eFind)

Member `gdcm::FileSet::AddFile` (`File` const &)

. Does nothing

Member `gdcm::TransferSyntax::GetSwapCode` () const

Return the `SwapCode` associated with the Transfer Syntax. Be careful with the special GE private syntax the `DataSet` is written in little endian but the Pixel Data is in Big Endian.

Chapter 4

Bug List

Class `gdcm::DICOMDIRGenerator`

: There is a current limitation of not handling Referenced SOP Class UID / Referenced SOP Instance UID simply because the `Scanner` does not allow us See PS 3.11 / [Table D.3-2 STD-GEN Additional DICOMDIR Keys](#)

Member `gdcm::FileStreamer::StartGroupDataElement` (`const PrivateTag &pt`, `size_t maxsize=0`, `uint8_t startoffset=0`)

`maxsize` should be a value lower than the actual total size of the buffer to be copied

Class `gdcm::IPPSorter`

There are currently a couple of bugs in this implementation:

Chapter 5

Namespace Index

5.1 Namespace List

Here is a list of all namespaces with brief descriptions:

gdc	43
gdc::network	74
gdc::SegmentHelper	80
gdc::terminal	
Class for Terminal	80

Chapter 6

Hierarchical Index

6.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

gdcmm::network::AbstractSyntax	100
gdcmm::network::ApplicationContext	116
gdcmm::ApplicationEntity	118
gdcmm::network::ARTIMTimer	125
gdcmm::ASN1	126
gdcmm::network::AsynchronousOperationsWindowSub	128
gdcmm::Attribute< Group, Element, TVR, TVM >	129
gdcmm::Attribute< Group, Element, TVR, VM::VM1 >	139
gdcmm::Attribute< Group, Element, TVR, VM::VM1_n >	158
gdcmm::Attribute< Group, Element, TVR, VM::VM1_3 >	147
gdcmm::Attribute< Group, Element, TVR, VM::VM1_8 >	152
gdcmm::Attribute< Group, Element, TVR, VM::VM2_n >	173
gdcmm::Attribute< Group, Element, TVR, VM::VM2_2n >	166
gdcmm::Attribute< Group, Element, TVR, VM::VM3_n >	185
gdcmm::Attribute< Group, Element, TVR, VM::VM3_3n >	178
gdcmm::Base64	193
gdcmm::network::BaseCompositeMessage	196
gdcmm::network::CEchoRQ	260
gdcmm::network::CEchoRSP	262
gdcmm::network::CFindCancelRQ	264
gdcmm::network::CFindRQ	265
gdcmm::network::CFindRSP	267
gdcmm::network::CMoveCancelRq	275
gdcmm::network::CMoveRQ	277
gdcmm::network::CMoveRSP	278
gdcmm::network::CStoreRQ	331
gdcmm::network::CStoreRSP	333
gdcmm::network::BaseNormalizedMessage	197
gdcmm::network::NActionRQ	794
gdcmm::network::NActionRSP	795

gdcmm::network::NCreateRQ	797
gdcmm::network::NCreateRSP	798
gdcmm::network::NDeleteRQ	800
gdcmm::network::NDeleteRSP	801
gdcmm::network::NEventReportRQ	806
gdcmm::network::NEventReportRSP	808
gdcmm::network::NGetRQ	809
gdcmm::network::NGetRSP	811
gdcmm::network::NSetRQ	817
gdcmm::network::NSetRSP	818
gdcmm::network::BasePDU	200
gdcmm::network::AAabortPDU	85
gdcmm::network::AAAssociateACPDU	88
gdcmm::network::AAAssociateRJPDU	92
gdcmm::network::AAAssociateRQPDU	94
gdcmm::network::AReleaseRPPDU	120
gdcmm::network::AReleaseRQPDU	122
gdcmm::network::PDataTFPDU	853
std::basic_string< Char >	
std::string	
gdcmm::String<"\", 16 >	1134
gdcmm::String<"\", 64 >	1134
gdcmm::String<"\", 4294967294 >	1134
gdcmm::String<"\", 64, 0 >	1134
gdcmm::String< TDelimiter, TMaxLength, TPadChar >	1134
gdcmm::SegmentHelper::BasicCodedEntry	212
gdcmm::BitmapToBitmapFilter	234
gdcmm::PixmapToPixmapFilter	898
gdcmm::ImageToImageFilter	639
gdcmm::ImageApplyLookupTable	586
gdcmm::ImageChangePhotometricInterpretation	589
gdcmm::ImageChangePlanarConfiguration	594
gdcmm::ImageChangeTransferSyntax	598
gdcmm::ImageFragmentSplitter	619
gdcmm::ByteBuffer	242
gdcmm::ByteSwap< T >	243
gdcmm::ByteSwapFilter	245
gdcmm::network::CFind	263
gdcmm::Coder	281
gdcmm::Codec	280
gdcmm::AudioCodec	191
gdcmm::ImageCodec	605
gdcmm::DeltaEncodingCodec	382
gdcmm::JPEG2000Codec	687
gdcmm::JPEGCodec	700
gdcmm::JPEG12Codec	677
gdcmm::JPEG16Codec	682
gdcmm::JPEG8Codec	695
gdcmm::JPEGLSCCodec	709
gdcmm::KAKADUCCodec	718
gdcmm::PGXCodec	870
gdcmm::PNMCodec	906
gdcmm::PVRGCodec	947

gdcmm::RAWCodec	967
gdcmm::RLECodec	987
gdcmm::PDFCodec	862
gdcmm::CodeString	283
gdcmm::network::CompositeMessageFactory	295
gdcmm::CompositeNetworkFunctions	296
gdcmm::ConstCharWrapper	301
gdcmm::CryptoFactory	305
gdcmm::CAPICryptoFactory	255
gdcmm::OpenSSLCryptoFactory	823
gdcmm::OpenSSLP7CryptoFactory	829
gdcmm::CryptographicMessageSyntax	308
gdcmm::CAPICryptographicMessageSyntax	257
gdcmm::OpenSSLCryptographicMessageSyntax	825
gdcmm::OpenSSLP7CryptographicMessageSyntax	831
gdcmm::CSAElement	311
gdcmm::CSAHeader	319
gdcmm::CSAHeaderDict	325
gdcmm::CSAHeaderDictEntry	328
gdcmm::DataElement	340
gdcmm::CP246ExplicitDataElement	302
gdcmm::ExplicitDataElement	488
gdcmm::ExplicitImplicitDataElement	492
gdcmm::Fragment	559
gdcmm::BasicOffsetTable	216
gdcmm::ImplicitDataElement	650
gdcmm::Item	670
gdcmm::UNExplicitDataElement	1333
gdcmm::UNExplicitImplicitDataElement	1337
gdcmm::VR16ExplicitDataElement	1376
gdcmm::DataSet	358
gdcmm::CommandDataSet	291
gdcmm::FileMetaInformation	520
gdcmm::DataSetHelper	374
gdcmm::Decoder	375
gdcmm::Codec	280
gdcmm::DefinedTerms	377
gdcmm::Defs	378
gdcmm::DICOMDIR	385
gdcmm::DICOMDIRGenerator	386
gdcmm::Dict	390
gdcmm::DictConverter	394
gdcmm::DictEntry	398
gdcmm::Dicts	406
gdcmm::network::DIMSE	410
gdcmm::DirectionCosines	411
gdcmm::Directory	415
gdcmm::DirectoryHelper	419
gdcmm::DPath	421
gdcmm::DummyValueGenerator	423
gdcmm::Element< TVR, TVM >	427
gdcmm::Element< TVR, VM::VM1_2 >	433

gdcm::Element< TVR, VM::VM2_2n >	438
gdcm::Element< TVR, VM::VM3_3n >	443
gdcm::Element< TVR, VM::VM3_4 >	448
gdcm::Element< VR::AS, VM::VM5 >	453
gdcm::Element< VR::OB, VM::VM1_n >	427
gdcm::Element< VR::OB, VM::VM1 >	457
gdcm::Element< VR::OW, VM::VM1_n >	427
gdcm::Element< VR::OW, VM::VM1 >	462
gdcm::ElementDisableCombinations< TVR, TVM >	467
gdcm::ElementDisableCombinations< VR::OB, VM::VM1_n >	468
gdcm::ElementDisableCombinations< VR::OW, VM::VM1_n >	469
gdcm::EmptyMaskGenerator	470
gdcm::EncapsulatedDocument	472
gdcm::EncodingImplementation< T >	473
gdcm::EncodingImplementation< VR::VRASCII >	474
gdcm::EncodingImplementation< VR::VRBINARY >	476
gdcm::EnumeratedValues	479
gdcm::EquipmentManufacturer	480
gdcm::Event	482
gdcm::AnyEvent	115
gdcm::AbortEvent	99
gdcm::AnonymizeEvent	103
gdcm::DataEvent	354
gdcm::DataSetEvent	371
gdcm::EndEvent	478
gdcm::ExitEvent	487
gdcm::FileNameEvent	533
gdcm::InitializeEvent	654
gdcm::IterationEvent	676
gdcm::ModifiedEvent	772
gdcm::ProgressEvent	943
gdcm::StartEvent	1100
gdcm::UserEvent	1345
gdcm::NoEvent	812
std::exception	
gdcm::CSAHeaderDictException	331
gdcm::DataElementException	354
gdcm::Exception	485
gdcm::ParseException	846
gdcm::Fiducials	496
gdcm::FileDerivation	513
gdcm::FileExplicitFilter	517
gdcm::Filename	530
gdcm::FilenameGenerator	537
gdcm::FileSet	540
gdcm::Global	564
gdcm::GroupDict	567
gdcm::IconImageFilter	570
gdcm::IconImageGenerator	573
gdcm::ignore_char	576
gdcm::ImageConverter	617
gdcm::ImageHelper	622
gdcm::network::ImplementationClassUIDSub	646

gdcM::network::ImplementationUIDSub	648
gdcM::network::ImplementationVersionNameSub	648
gdcM::IOD	655
gdcM::IODEntry	658
gdcM::IODs	661
gdcM::JSON	716
gdcM::Scanner2::Itstr	733
gdcM::Scanner::Itstr	734
gdcM::StrictScanner2::Itstr	734
gdcM::StrictScanner::Itstr	735
gdcM::Macro	736
gdcM::Macros	738
gdcM::network::MaximumLengthSub	740
gdcM::MD5	742
gdcM::MEC_MR3	743
gdcM::MediaStorage	744
gdcM::Module	773
gdcM::ModuleEntry	777
gdcM::NestedModuleEntries	803
gdcM::Modules	781
gdcM::MrProtocol	792
gdcM::network::NormalizedMessageFactory	813
gdcM::NormalizedNetworkFunctions	814
gdcM::Object	820
gdcM::BaseQuery	202
gdcM::BaseRootQuery	207
gdcM::FindPatientRootQuery	551
gdcM::FindStudyRootQuery	555
gdcM::MovePatientRootQuery	784
gdcM::MoveStudyRootQuery	788
gdcM::WLMFindQuery	1494
gdcM::ModalityPerformedProcedureStepCreateQuery	765
gdcM::ModalityPerformedProcedureStepSetQuery	769
gdcM::Bitmap	220
gdcM::Pixmap	887
gdcM::Image	577
gdcM::Curve	334
gdcM::File	497
gdcM::FileWithName	548
gdcM::LookupTable	726
gdcM::SegmentedPaletteColorLookupTable	1025
gdcM::MeshPrimitive	760
gdcM::Overlay	837
gdcM::Segment	1016
gdcM::Subject	1143
gdcM::Anonymizer	106
gdcM::Cleaner	268
gdcM::Command	287
gdcM::MemberCommand< SimpleSubjectWatcher >	754
gdcM::SimpleMemberCommand< SimpleSubjectWatcher >	1072
gdcM::MemberCommand< T >	754
gdcM::SimpleMemberCommand< T >	1072
gdcM::FileAnonymizer	502

gdcmm::FileChangeTransferSyntax	506
gdcmm::FileDecompressLookupTable	510
gdcmm::FileStreamer	542
gdcmm::Scanner	996
gdcmm::Scanner2	1005
gdcmm::ServiceClassUser	1062
gdcmm::StrictScanner	1114
gdcmm::StrictScanner2	1123
gdcmm::network::ULConnectionManager	1320
gdcmm::Surface	1146
gdcmm::Value	1352
gdcmm::ByteValue	247
gdcmm::SequenceOfFragments	1038
gdcmm::SequenceOfItems	1045
gdcmm::Orientation	834
gdcmm::Parser	849
gdcmm::Patient	852
gdcmm::PDBelement	856
gdcmm::PDBHeader	859
gdcmm::network::PDUFactory	864
gdcmm::PersonName	868
gdcmm::PhotometricInterpretation	874
gdcmm::PixelFormat	878
gdcmm::Preamble	911
gdcmm::PresentationContext	915
gdcmm::network::PresentationContextAC	918
gdcmm::PresentationContextGenerator	921
gdcmm::network::PresentationContextRQ	924
gdcmm::network::PresentationDataValue	927
gdcmm::Printer	931
gdcmm::DictPrinter	403
gdcmm::Dumper	424
gdcmm::PrivateDict	935
gdcmm::PythonFilter	951
gdcmm::QueryBase	953
gdcmm::QueryImage	957
gdcmm::QueryPatient	960
gdcmm::QuerySeries	962
gdcmm::QueryStudy	965
gdcmm::QueryFactory	956
gdcmm::Reader	972
gdcmm::PixmapReader	894
gdcmm::ImageReader	629
gdcmm::ImageRegionReader	634
gdcmm::SegmentReader	1028
gdcmm::SurfaceReader	1162
gdcmm::RealWorldValueMappingContent	979
gdcmm::Region	980
gdcmm::BoxRegion	237
gdcmm::Rescaler	983
gdcmm::network::RoleSelectionSub	994
gdcmm::SerieHelper	1054
gdcmm::Series	1059

gdcm::network::ServiceClassApplicationInformation	1060
gdcm::SHA1	1070
gdcm::SimpleSubjectWatcher	1077
gdcm::MrProtocol::Slice	1080
gdcm::MrProtocol::SliceArray	1081
gdcm::SmartPointer< ObjectType >	1082
gdcm::network::SOPClassExtendedNegociationSub	1086
gdcm::SOPClassUIDToIOD	1087
gdcm::Sorter	1089
gdcm::IPPSorter	664
gdcm::Spacing	1094
gdcm::Spectroscopy	1096
gdcm::SplitMosaicFilter	1097
gdcm::static_assert_test< x >	1101
gdcm::STATIC_ASSERTION_FAILURE< x >	1102
gdcm::STATIC_ASSERTION_FAILURE< true >	1102
gdcm::StreamImageReader	1103
gdcm::StreamImageWriter	1107
String<'\\', 64 >	
gdcm::LO	722
gdcm::StringFilter	1138
gdcm::Study	1142
gdcm::SurfaceHelper	1159
gdcm::SwapCode	1171
gdcm::SwapperDoOp	1174
gdcm::SwapperNoOp	1174
gdcm::System	1175
gdcm::Table	1182
gdcm::TableEntry	1185
gdcm::TableReader	1186
gdcm::XMLDictReader	1504
gdcm::XMLPrivateDictReader	1510
gdcm::network::TableRow	1190
gdcm::Tag	1191
gdcm::PrivateTag	938
gdcm::TagPath	1202
gdcm::Testing	1204
gdcm::Trace	1210
gdcm::TransferSyntax	1215
gdcm::network::TransferSyntaxSub	1221
gdcm::network::Transition	1223
gdcm::Type	1225
gdcm::UI	1227
gdcm::UIDGenerator	1228
gdcm::UIDs	1231
gdcm::network::ULAction	1268
gdcm::network::ULActionAA1	1271
gdcm::network::ULActionAA2	1272
gdcm::network::ULActionAA3	1273
gdcm::network::ULActionAA4	1275
gdcm::network::ULActionAA5	1276
gdcm::network::ULActionAA6	1277
gdcm::network::ULActionAA7	1279

gdcmm::network::ULActionAA8	1280
gdcmm::network::ULActionAE1	1281
gdcmm::network::ULActionAE2	1283
gdcmm::network::ULActionAE3	1284
gdcmm::network::ULActionAE4	1285
gdcmm::network::ULActionAE5	1287
gdcmm::network::ULActionAE6	1288
gdcmm::network::ULActionAE7	1289
gdcmm::network::ULActionAE8	1291
gdcmm::network::ULActionAR1	1292
gdcmm::network::ULActionAR10	1293
gdcmm::network::ULActionAR2	1295
gdcmm::network::ULActionAR3	1296
gdcmm::network::ULActionAR4	1297
gdcmm::network::ULActionAR5	1299
gdcmm::network::ULActionAR6	1300
gdcmm::network::ULActionAR7	1301
gdcmm::network::ULActionAR8	1303
gdcmm::network::ULActionAR9	1304
gdcmm::network::ULActionDT1	1305
gdcmm::network::ULActionDT2	1307
gdcmm::network::ULConnection	1311
gdcmm::network::ULConnectionCallback	1316
gdcmm::network::ULBasicCallback	1308
gdcmm::network::ULWritingCallback	1331
gdcmm::network::ULConnectionInfo	1318
gdcmm::network::ULEvent	1328
gdcmm::network::ULTransitionTable	1329
gdcmm::Unpacker12Bits	1341
gdcmm::Usage	1342
gdcmm::network::UserInformation	1346
gdcmm::UUIDGenerator	1348
gdcmm::Validate	1349
gdcmm::ValueIO< TDE, TSwap, TType >	1355
gdcmm::MrProtocol::Vector3	1356
gdcmm::Version	1357
gdcmm::VL	1359
gdcmm::VM	1363
gdcmm::VMToLength< T >	1368
gdcmm::VR	1369
gdcmm::VRToEncoding< T >	1379
gdcmm::VRToType< T >	1380
gdcmm::VRVLSIZE< T >	1380
gdcmm::VRVLSIZE< 0 >	1381
gdcmm::VRVLSIZE< 1 >	1382
vtkImageAlgorithm	
vtkImagePlanarComponentsToComponents	1472
vtkImageMapToColors	
vtkImageMapToWindowLevelColors2	1468
vtkImageWriter	
vtkGDCMImageWriter	1413
vtkLookupTable	
vtkLookupTable16	1479
vtkMedicalImageProperties	

vtkGDCMMedicalImageProperties1421
vtkMedicalImageReader2	
vtkGDCMImageReader1383
vtkGDCMThreadedImageReader1437
vtkGDCMImageReader21398
vtkObject	
vtkGDCMTesting1434
vtkImageColorViewer1450
vtkRTStructSetProperties1483
vtkPolyDataAlgorithm	
vtkGDCMPolyDataReader1424
vtkPolyDataWriter	
vtkGDCMPolyDataWriter1429
vtkThreadedImageAlgorithm	
vtkGDCMThreadedImageReader21443
vtkImageMapToColors161462
vtkImageRGBToYBR1475
vtkImageYBRToRGB1477
gdcm::Waveform1493
gdcm::Writer1498
gdcm::PixmapWriter901
gdcm::ImageWriter642
gdcm::SegmentWriter1032
gdcm::SurfaceWriter1166
gdcm::XMLPrinter1507

Chapter 7

Class Index

7.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

gdcmm::network::AAAbortPDU	
AAAbortPDU	85
gdcmm::network::AAAssociateACPDU	
AAAssociateACPDU	88
gdcmm::network::AAAssociateRJPDU	
AAAssociateRJPDU	92
gdcmm::network::AAAssociateRQPDU	
AAAssociateRQPDU	94
gdcmm::AbortEvent	99
gdcmm::network::AbstractSyntax	
AbstractSyntax	100
gdcmm::AnonymizeEvent	
AnonymizeEvent	103
gdcmm::Anonymizer	
Anonymizer	106
gdcmm::AnyEvent	115
gdcmm::network::ApplicationContext	
ApplicationContext	116
gdcmm::ApplicationEntity	
ApplicationEntity	118
gdcmm::network::AReleaseRPPDU	
AReleaseRPPDU	120
gdcmm::network::AReleaseRQPDU	
AReleaseRQPDU	122
gdcmm::network::ARTIMTimer	
ARTIMTimer	125
gdcmm::ASN1	
Class for ASN1	126
gdcmm::network::AsynchronousOperationsWindowSub	
AsynchronousOperationsWindowSub	128

gdcmm::Attribute< Group, Element, TVR, TVM >	
Attribute class This class use template metaprograming tricks to let the user know when the template instantiation does not match the public dictionary	129
gdcmm::Attribute< Group, Element, TVR, VM::VM1 >	139
gdcmm::Attribute< Group, Element, TVR, VM::VM1_3 >	147
gdcmm::Attribute< Group, Element, TVR, VM::VM1_8 >	152
gdcmm::Attribute< Group, Element, TVR, VM::VM1_n >	158
gdcmm::Attribute< Group, Element, TVR, VM::VM2_2n >	166
gdcmm::Attribute< Group, Element, TVR, VM::VM2_n >	173
gdcmm::Attribute< Group, Element, TVR, VM::VM3_3n >	178
gdcmm::Attribute< Group, Element, TVR, VM::VM3_n >	185
gdcmm::AudioCodec	
AudioCodec	191
gdcmm::Base64	
Class for Base64	193
gdcmm::network::BaseCompositeMessage	
BaseCompositeMessage	196
gdcmm::network::BaseNormalizedMessage	
BaseNormalizedMessage	197
gdcmm::network::BasePDU	
BasePDU	200
gdcmm::BaseQuery	
BaseQuery	202
gdcmm::BaseRootQuery	
BaseRootQuery	207
gdcmm::SegmentHelper::BasicCodedEntry	
This structure defines a basic coded entry with all of its attributes	212
gdcmm::BasicOffsetTable	
Class to represent a BasicOffsetTable	216
gdcmm::Bitmap	
Bitmap class	220
gdcmm::BitmapToBitmapFilter	
BitmapToBitmapFilter class	234
gdcmm::BoxRegion	
Class for manipulation box region	237
gdcmm::ByteBuffer	
ByteBuffer	242
gdcmm::ByteSwap< T >	
ByteSwap	243
gdcmm::ByteSwapFilter	
ByteSwapFilter	245
gdcmm::ByteValue	
Class to represent binary value (array of bytes)	247
gdcmm::CAPICryptoFactory	255
gdcmm::CAPICryptographicMessageSyntax	257
gdcmm::network::CEchoRQ	
CEchoRQ	260
gdcmm::network::CEchoRSP	
CEchoRSP this file defines the messages for the cecho action	262
gdcmm::network::CFind	263
gdcmm::network::CFindCancelRQ	
CFindCancelRQ this file defines the messages for the cfind action	264
gdcmm::network::CFindRQ	
CFindRQ	265

gdcm::network::CFindRSP	
CFindRSP this file defines the messages for the cfind action	267
gdcm::Cleaner	
Cleaner	268
gdcm::network::CMoveCancelRq	275
gdcm::network::CMoveRQ	
CMoveRQ	277
gdcm::network::CMoveRSP	
CMoveRSP this file defines the messages for the cmove action	278
gdcm::Codec	
Codec class	280
gdcm::Coder	
Coder	281
gdcm::CodeString	
CodeString	283
gdcm::Command	
Command superclass for callback/observer methods	287
gdcm::CommandDataSet	
Class to represent a Command DataSet	291
gdcm::network::CompositeMessageFactory	
CompositeMessageFactory	295
gdcm::CompositeNetworkFunctions	
Composite Network Functions	296
gdcm::ConstCharWrapper	
Do not use me	301
gdcm::CP246ExplicitDataElement	
Class to read/write a DataElement as CP246Explicit Data Element	302
gdcm::CryptoFactory	
Class to do handle the crypto factory	305
gdcm::CryptographicMessageSyntax	308
gdcm::CSAElement	
Class to represent a CSA Element	311
gdcm::CSAHeader	
Class for CSAHeader	319
gdcm::CSAHeaderDict	
Class to represent a map of CSAHeaderDictEntry	325
gdcm::CSAHeaderDictEntry	
Class to represent an Entry in the Dict	328
gdcm::CSAHeaderDictException	331
gdcm::network::CStoreRQ	
CStoreRQ	331
gdcm::network::CStoreRSP	
CStoreRSP this file defines the messages for the cecho action	333
gdcm::Curve	
Curve class to handle element 50xx,3000 Curve Data	334
gdcm::DataElement	
Class to represent a Data Element either Implicit or Explicit	340
gdcm::DataElementException	354
gdcm::DataEvent	
DataEvent	354
gdcm::DataSet	
Class to represent a Data Set (which contains Data Elements)	358
gdcm::DataSetEvent	
DataSetEvent	371

gdcm::DataSetHelper	
DataSetHelper (internal class, not intended for user level)	374
gdcm::Decoder	
Decoder	375
gdcm::DefinedTerms	
Defined Terms are used when the specified explicit Values may be extended by implementors to include additional new Values. These new Values shall be specified in the Conformance Statement (see PS 3.2) and shall not have the same meaning as currently defined Values in this standard. A Data Element with Defined Terms that does not contain a Value equivalent to one of the Values currently specified in this standard shall not be considered to have an invalid value. Note: Interpretation Type ID (4008,0210) is an example of a Data Element having Defined Terms. It is defined to have a Value that may be one of the set of standard Values; REPORT or AMENDMENT (see PS 3.3). Because this Data Element has Defined Terms other Interpretation Type IDs may be defined by the implementor	377
gdcm::Defs	
FIXME I do not like the name 'Defs'	378
gdcm::DeltaEncodingCodec	
DeltaEncodingCodec compression used by some private vendor	382
gdcm::DICOMDIR	
DICOMDIR class	385
gdcm::DICOMDIRGenerator	
DICOMDIRGenerator class	386
gdcm::Dict	
Class to represent a map of DictEntry	390
gdcm::DictConverter	
Class to convert a .dic file into something else:	394
gdcm::DictEntry	
Class to represent an Entry in the Dict	398
gdcm::DictPrinter	
DictPrinter class	403
gdcm::Dicts	
Class to manipulate the sum of knowledge (all the dict user load)	406
gdcm::network::DIMSE	
DIMSE	410
gdcm::DirectionCosines	
Class to handle DirectionCosines	411
gdcm::Directory	
Class for manipulation directories	415
gdcm::DirectoryHelper	
DirectoryHelper	419
gdcm::DPath	
Class to handle a DICOM path While supp 118 did introduced a notion of XPath for XML Native model this convention is too XML-centric. Instead prefer DCMTK style notation https://groups.google.com/g/comp.protocols.dicom/c/IyIH0IOBMPA	421
gdcm::DummyValueGenerator	
Class for generating dummy value	423
gdcm::Dumper	
Codec class	424
gdcm::Element< TVR, TVM >	
Element class	427
gdcm::Element< TVR, VM::VM1_2 >	433
gdcm::Element< TVR, VM::VM2_2n >	438
gdcm::Element< TVR, VM::VM3_3n >	443
gdcm::Element< TVR, VM::VM3_4 >	448

gdcm::Element< VR::AS, VM::VM5 >	453
gdcm::Element< VR::OB, VM::VM1 >	457
gdcm::Element< VR::OW, VM::VM1 >	462
gdcm::ElementDisableCombinations< TVR, TVM >	
A class which is used to produce compile errors for an invalid combination of template parameters	467
gdcm::ElementDisableCombinations< VR::OB, VM::VM1_n >	468
gdcm::ElementDisableCombinations< VR::OW, VM::VM1_n >	469
gdcm::EmptyMaskGenerator	
EmptyMaskGenerator Main class to generate a Empty Mask Series from an input Series . This class takes an input folder and generates a series of DICOM files in the specified output directory. This class handles multiples DICOM Series within the same input directory	470
gdcm::EncapsulatedDocument	
EncapsulatedDocument	472
gdcm::EncodingImplementation< T >	
EncodingImplementation	473
gdcm::EncodingImplementation< VR::VRASCII >	474
gdcm::EncodingImplementation< VR::VRBINARY >	476
gdcm::EndEvent	478
gdcm::EnumeratedValues	
Element. A Data Element with Enumerated Values that does not have a Value equivalent to one of the Values specified in this standard has an invalid value within the scope of a specific Information Object/SOP Class definition. Note:	479
gdcm::EquipmentManufacturer	480
gdcm::Event	
Superclass for callback/observer methods	482
gdcm::Exception	
Exception	485
gdcm::ExitEvent	487
gdcm::ExplicitDataElement	
Class to read/write a DataElement as Explicit Data Element	488
gdcm::ExplicitImplicitDataElement	
Class to read/write a DataElement as ExplicitImplicit Data Element	492
gdcm::Fiducials	
Fiducials	496
gdcm::File	
DICOM File	497
gdcm::FileAnonymizer	
FileAnonymizer	502
gdcm::FileChangeTransferSyntax	
FileChangeTransferSyntax	506
gdcm::FileDecompressLookupTable	
FileDecompressLookupTable class	510
gdcm::FileDerivation	
FileDerivation class	513
gdcm::FileExplicitFilter	
FileExplicitFilter class	517
gdcm::FileMetaInformation	
Class to represent a File Meta Information	520
gdcm::Filename	
Class to manipulate file name's	530
gdcm::FileNameEvent	
FileNameEvent	533
gdcm::FilenameGenerator	
FilenameGenerator	537

gdcm::FileSet	540
gdcm::FileStreamer	
FileStreamer	542
gdcm::FileWithName	
FileWithName	548
gdcm::FindPatientRootQuery	
PatientRootQuery	551
gdcm::FindStudyRootQuery	
FindStudyRootQuery	555
gdcm::Fragment	
Class to represent a Fragment	559
gdcm::Global	
Global	564
gdcm::GroupDict	
Class to represent the mapping from group number to its abbreviation and name	567
gdcm::IconImageFilter	
IconImageFilter	570
gdcm::IconImageGenerator	
IconImageGenerator	573
gdcm::ignore_char	576
gdcm::Image	
Image	577
gdcm::ImageApplyLookupTable	
ImageApplyLookupTable class	586
gdcm::ImageChangePhotometricInterpretation	
ImageChangePhotometricInterpretation class	589
gdcm::ImageChangePlanarConfiguration	
ImageChangePlanarConfiguration class	594
gdcm::ImageChangeTransferSyntax	
ImageChangeTransferSyntax class	598
gdcm::ImageCodec	
ImageCodec	605
gdcm::ImageConverter	
Image Converter	617
gdcm::ImageFragmentSplitter	
ImageFragmentSplitter class	619
gdcm::ImageHelper	
ImageHelper (internal class, not intended for user level)	622
gdcm::ImageReader	
ImageReader	629
gdcm::ImageRegionReader	
ImageRegionReader	634
gdcm::ImageToImageFilter	
ImageToImageFilter class	639
gdcm::ImageWriter	
ImageWriter	642
gdcm::network::ImplementationClassUIDSub	
ImplementationClassUIDSub	646
gdcm::network::ImplementationUIDSub	
ImplementationUIDSub	648
gdcm::network::ImplementationVersionNameSub	
ImplementationVersionNameSub	648
gdcm::ImplicitDataElement	
Class to represent an <i>Implicit VR</i> Data Element	650

gdcm::InitializeEvent	654
gdcm::IOD	
Class for representing a IOD	655
gdcm::IODEntry	
Class for representing a IODEntry	658
gdcm::IODs	
Class for representing a IODs	661
gdcm::IPPSorter	
IPPSorter	664
gdcm::Item	
Class to represent an Item	670
gdcm::IterationEvent	676
gdcm::JPEG12Codec	
Class to do JPEG 12bits (lossy & lossless)	677
gdcm::JPEG16Codec	
Class to do JPEG 16bits (lossless)	682
gdcm::JPEG2000Codec	
Class to do JPEG 2000	687
gdcm::JPEG8Codec	
Class to do JPEG 8bits (lossy & lossless)	695
gdcm::JPEGCodec	
JPEG codec	700
gdcm::JPEGLSCodec	
JPEG-LS	709
gdcm::JSON	716
gdcm::KAKADUCodec	
KAKADUCodec	718
gdcm::LO	
LO	722
gdcm::LookupTable	
LookupTable class	726
gdcm::Scanner2::Itstr	733
gdcm::Scanner::Itstr	734
gdcm::StrictScanner2::Itstr	734
gdcm::StrictScanner::Itstr	735
gdcm::Macro	
Class for representing a Macro	736
gdcm::Macros	
Class for representing a Modules	738
gdcm::network::MaximumLengthSub	
MaximumLengthSub	740
gdcm::MD5	
Class for MD5	742
gdcm::MEC_MR3	
Class for MEC_MR3	743
gdcm::MediaStorage	
MediaStorage	744
gdcm::MemberCommand< T >	
Command subclass that calls a pointer to a member function	754
gdcm::MeshPrimitive	
This class defines surface mesh primitives	760
gdcm::ModalityPerformedProcedureStepCreateQuery	
ModalityPerformedProcedureStepCreateQuery	765

gdcmm::ModalityPerformedProcedureStepSetQuery	
ModalityPerformedProcedureStepSetQuery	769
gdcmm::ModifiedEvent	772
gdcmm::Module	
Class for representing a Module	773
gdcmm::ModuleEntry	
Class for representing a ModuleEntry	777
gdcmm::Modules	
Class for representing a Modules	781
gdcmm::MovePatientRootQuery	
MovePatientRootQuery	784
gdcmm::MoveStudyRootQuery	
MoveStudyRootQuery	788
gdcmm::MrProtocol	
Class for MrProtocol	792
gdcmm::network::NActionRQ	
NActionRQ	794
gdcmm::network::NActionRSP	
NActionRSP this file defines the messages for the NAction action	795
gdcmm::network::NCreateRQ	
NCreateRQ	797
gdcmm::network::NCreateRSP	
NCreateRSP this file defines the messages for the ncreate action	798
gdcmm::network::NDeleteRQ	
NDeleteRQ	800
gdcmm::network::NDeleteRSP	
NDeleteRSP this file defines the messages for the ndelete action	801
gdcmm::NestedModuleEntries	
Class for representing a NestedModuleEntries	803
gdcmm::network::NEventReportRQ	
NEventReportRQ	806
gdcmm::network::NEventReportRSP	
NEventReportRSP this file defines the messages for the neventreport action	808
gdcmm::network::NGetRQ	
NGetRQ	809
gdcmm::network::NGetRSP	
NGetRSP this file defines the messages for the nget action	811
gdcmm::NoEvent	812
gdcmm::network::NormalizedMessageFactory	813
gdcmm::NormalizedNetworkFunctions	
Normalized Network Functions	814
gdcmm::network::NSetRQ	
NSetRQ	817
gdcmm::network::NSetRSP	
NSetRSP this file defines the messages for the nset action	818
gdcmm::Object	
Object	820
gdcmm::OpenSSLCryptoFactory	823
gdcmm::OpenSSLCryptographicMessageSyntax	825
gdcmm::OpenSSLP7CryptoFactory	829
gdcmm::OpenSSLP7CryptographicMessageSyntax	831
gdcmm::Orientation	
Class to handle Orientation	834

gdcm::Overlay	
Overlay class	837
gdcm::ParseException	
ParseException Standard exception handling object	846
gdcm::Parser	
Parser ala XML_Parser from expat (SAX)	849
gdcm::Patient	
See PS 3.3 - 2007 DICOM MODEL OF THE REAL-WORLD, p 54	852
gdcm::network::PDataTFPDU	
PDataTFPDU	853
gdcm::PDBElement	
Class to represent a PDB Element	856
gdcm::PDBHeader	
Class for PDBHeader	859
gdcm::PDFCodec	
PDFCodec class	862
gdcm::network::PDUFactory	
PDUFactory basically, given an initial byte, construct the	864
gdcm::PersonName	
PersonName class	868
gdcm::PGXCodec	
Class to do PGX	870
gdcm::PhotometricInterpretation	
Class to represent an PhotometricInterpretation	874
gdcm::PixelFormat	
PixelFormat	878
gdcm::Pixmap	
Pixmap class	887
gdcm::PixmapReader	
PixmapReader	894
gdcm::PixmapToPixmapFilter	
PixmapToPixmapFilter class	898
gdcm::PixmapWriter	
PixmapWriter	901
gdcm::PNMCodec	
Class to do PNM	906
gdcm::Preamble	
DICOM Preamble (Part 10)	911
gdcm::PresentationContext	
PresentationContext	915
gdcm::network::PresentationContextAC	
PresentationContextAC	918
gdcm::PresentationContextGenerator	
PresentationContextGenerator	921
gdcm::network::PresentationContextRQ	
PresentationContextRQ	924
gdcm::network::PresentationDataValue	
PresentationDataValue	927
gdcm::Printer	
Printer class	931
gdcm::PrivateDict	
Private Dict	935
gdcm::PrivateTag	
Class to represent a Private DICOM Data Element (Attribute) Tag (Group, Element, Owner)	938

gdcm::ProgressEvent	
ProgressEvent	943
gdcm::PVRGCodec	
PVRGCodec	947
gdcm::PythonFilter	
PythonFilter	PythonFilter is the class that make gdcm2.x looks more like gdcm1 and transform the binary blob contained in a DataElement into a string, typically this is a nice feature to have for wrapped language
language	951
gdcm::QueryBase	
QueryBase	953
gdcm::QueryFactory	
QueryFactory.h	956
gdcm::QueryImage	
QueryImage	957
gdcm::QueryPatient	
QueryPatient	960
gdcm::QuerySeries	
QuerySeries	962
gdcm::QueryStudy	
QueryStudy.h	965
gdcm::RAWCodec	
RAWCodec class	967
gdcm::Reader	
Reader	ala DOM (Document Object Model)
gdcm::RealWorldValueMappingContent	979
gdcm::Region	
Class for manipulation region	980
gdcm::Rescaler	
Rescale class	983
gdcm::RLECodec	
Class to do RLE	987
gdcm::network::RoleSelectionSub	
RoleSelectionSub	994
gdcm::Scanner	
Scanner	996
gdcm::Scanner2	
Scanner2	1005
gdcm::Segment	
This class defines a segment	1016
gdcm::SegmentedPaletteColorLookupTable	
SegmentedPaletteColorLookupTable class	1025
gdcm::SegmentReader	
This class defines a segment reader	1028
gdcm::SegmentWriter	
This class defines a segment writer	1032
gdcm::SequenceOfFragments	
Class to represent a Sequence Of Fragments	1038
gdcm::SequenceOfItems	
Class to represent a Sequence Of Items	1045
gdcm::SerieHelper	
SerieHelper	DO NOT USE this class, it is only a temporary solution for ITK migration from GDCM 1.x to GDCM 2.x It will disappear soon, you've been warned
gdcm::Series	1054
Series	1059

gdcm::network::ServiceClassApplicationInformation	1060
gdcm::ServiceClassUser	
ServiceClassUser	1062
gdcm::SHA1	
Class for SHA1	1070
gdcm::SimpleMemberCommand< T >	
Command subclass that calls a pointer to a member function	1072
gdcm::SimpleSubjectWatcher	
SimpleSubjectWatcher	1077
gdcm::MrProtocol::Slice	1080
gdcm::MrProtocol::SliceArray	1081
gdcm::SmartPointer< ObjectType >	
Class for Smart Pointer	1082
gdcm::network::SOPClassExtendedNegociationSub	
SOPClassExtendedNegociationSub	1086
gdcm::SOPClassUIDToIOD	
Class convert a class SOP Class UID into IOD	1087
gdcm::Sorter	
Sorter	1089
gdcm::Spacing	
Class for Spacing	1094
gdcm::Spectroscopy	
Spectroscopy class	1096
gdcm::SplitMosaicFilter	
SplitMosaicFilter class	1097
gdcm::StartEvent	1100
gdcm::static_assert_test< x >	1101
gdcm::STATIC_ASSERTION_FAILURE< x >	1102
gdcm::STATIC_ASSERTION_FAILURE< true >	1102
gdcm::StreamImageReader	
StreamImageReader	1103
gdcm::StreamImageWriter	
StreamImageReader	1107
gdcm::StrictScanner	
StrictScanner	1114
gdcm::StrictScanner2	
StrictScanner2	1123
gdcm::String< TDelimiter, TMaxLength, TPadChar >	
String	1134
gdcm::StringFilter	
StringFilter	1138
gdcm::Study	
Study	1142
gdcm::Subject	
Subject	1143
gdcm::Surface	
This class defines a SURFACE IE	1146
gdcm::SurfaceHelper	
SurfaceHelper	1159
gdcm::SurfaceReader	
This class defines a SURFACE IE reader	1162
gdcm::SurfaceWriter	
This class defines a SURFACE IE writer	1166

gdcmm::SwapCode	
SwapCode representation	1171
gdcmm::SwapperDoOp	1174
gdcmm::SwapperNoOp	1174
gdcmm::System	
Class to do system operation	1175
gdcmm::Table	
Table	1182
gdcmm::TableEntry	
TableEntry	1185
gdcmm::TableReader	
Class for representing a TableReader	1186
gdcmm::network::TableRow	1190
gdcmm::Tag	
Class to represent a DICOM Data Element (Attribute) Tag (Group, Element)	1191
gdcmm::TagPath	
Class to handle a path of tag	1202
gdcmm::Testing	
Class for testing	1204
gdcmm::Trace	
Trace	1210
gdcmm::TransferSyntax	
Class to manipulate Transfer Syntax	1215
gdcmm::network::TransferSyntaxSub	
TransferSyntaxSub	1221
gdcmm::network::Transition	1223
gdcmm::Type	
Type	1225
gdcmm::UI	1227
gdcmm::UIDGenerator	
Class for generating unique UID	1228
gdcmm::UIDs	
All known uids	1231
gdcmm::network::ULAction	
ULAction	1268
gdcmm::network::ULActionAA1	1271
gdcmm::network::ULActionAA2	1272
gdcmm::network::ULActionAA3	1273
gdcmm::network::ULActionAA4	1275
gdcmm::network::ULActionAA5	1276
gdcmm::network::ULActionAA6	1277
gdcmm::network::ULActionAA7	1279
gdcmm::network::ULActionAA8	1280
gdcmm::network::ULActionAE1	1281
gdcmm::network::ULActionAE2	1283
gdcmm::network::ULActionAE3	1284
gdcmm::network::ULActionAE4	1285
gdcmm::network::ULActionAE5	1287
gdcmm::network::ULActionAE6	1288
gdcmm::network::ULActionAE7	1289
gdcmm::network::ULActionAE8	1291
gdcmm::network::ULActionAR1	1292
gdcmm::network::ULActionAR10	1293
gdcmm::network::ULActionAR2	1295

gdcmm::network::ULActionAR3	1296
gdcmm::network::ULActionAR4	1297
gdcmm::network::ULActionAR5	1299
gdcmm::network::ULActionAR6	1300
gdcmm::network::ULActionAR7	1301
gdcmm::network::ULActionAR8	1303
gdcmm::network::ULActionAR9	1304
gdcmm::network::ULActionDT1	1305
gdcmm::network::ULActionDT2	1307
gdcmm::network::ULBasicCallback	
ULBasicCallback	1308
gdcmm::network::ULConnection	
ULConnection	1311
gdcmm::network::ULConnectionCallback	1316
gdcmm::network::ULConnectionInfo	
ULConnectionInfo	1318
gdcmm::network::ULConnectionManager	
ULConnectionManager	1320
gdcmm::network::ULEvent	
ULEvent	1328
gdcmm::network::ULTransitionTable	
ULTransitionTable The transition table of all the ULEvents, new ULActions, and ULStates	1329
gdcmm::network::ULWritingCallback	1331
gdcmm::UNExplicitDataElement	
Class to read/write a DataElement as UNExplicit Data Element	1333
gdcmm::UNExplicitImplicitDataElement	
Class to read/write a DataElement as ExplicitImplicit Data Element	1337
gdcmm::Unpacker12Bits	
Pack/Unpack 12 bits pixel into 16bits	1341
gdcmm::Usage	
Usage	1342
gdcmm::UserEvent	1345
gdcmm::network::UserInformation	
UserInformation	1346
gdcmm::UUIDGenerator	
Class for generating unique UUID	1348
gdcmm::Validate	
Validate class	1349
gdcmm::Value	
Class to represent the value of a Data Element	1352
gdcmm::ValueIO< TDE, TSwap, TType >	
Class to dispatch template calls	1355
gdcmm::MrProtocol::Vector3	1356
gdcmm::Version	
Major/minor and build version	1357
gdcmm::VL	
Value Length	1359
gdcmm::VM	
Value Multiplicity Looking at the DICOMV3 dict only there is very few cases: 1 2 3 4 5 6 8 16 24 1-2 1-3 1-8 1-32 1-99 1-n 2-2n 2-n 3-3n 3-n	1363
gdcmm::VMToLength< T >	1368
gdcmm::VR	
VR class	1369

gdcm::VR16ExplicitDataElement	
Class to read/write a DataElement as Explicit Data Element	1376
gdcm::VRToEncoding< T >	1379
gdcm::VRToType< T >	1380
gdcm::VRVLSize< T >	1380
gdcm::VRVLSize< 0 >	1381
gdcm::VRVLSize< 1 >	1382
vtkGDCMImageReader	1383
vtkGDCMImageReader2	1398
vtkGDCMImageWriter	1413
vtkGDCMMedicalImageProperties	1421
vtkGDCMPolyDataReader	1424
vtkGDCMPolyDataWriter	1429
vtkGDCMTesting	1434
vtkGDCMThreadedImageReader	1437
vtkGDCMThreadedImageReader2	1443
vtkImageColorViewer	1450
vtkImageMapToColors16	1462
vtkImageMapToWindowLevelColors2	1468
vtkImagePlanarComponentsToComponents	1472
vtkImageRGBToYBR	1475
vtkImageYBRToRGB	1477
vtkLookupTable16	1479
vtkRTStructSetProperties	1483
gdcm::Waveform	
Waveform class	1493
gdcm::WLMFindQuery	
PatientRootQuery	1494
gdcm::Writer	
Writer ala DOM (Document Object Model)	1498
gdcm::XMLDictReader	
Class for representing a XMLDictReader	1504
gdcm::XMLPrinter	1507
gdcm::XMLPrivateDictReader	
Class for representing a XMLPrivateDictReader	1510

Chapter 8

File Index

8.1 File List

Here is a list of all files with brief descriptions:

gdcmanSN1.h	1515
gdcmbase64.h	1517
gdcmboxRegion.h	1518
gdcmbyteSwap.h	1519
gdcmcapiCryptoFactory.h	1521
gdcmcapiCryptographicMessageSyntax.h	1522
gdcmmCommand.h	1525
gdcmmCryptoFactory.h	1528
gdcmmCryptographicMessageSyntax.h	1530
gdcmmDataEvent.h	1532
gdcmmDeflateStream.h	1534
gdcmmDirectory.h	1534
gdcmmDummyValueGenerator.h	1537
gdcmmEvent.h	1538
gdcmmException.h	1541
gdcmmFilename.h	1545
gdcmmFileNameEvent.h	1546
gdcmmFilenameGenerator.h	1548
gdcmmLegacyMacro.h	1549
gdcmmMD5.h	1552
gdcmmObject.h	1553
gdcmmOpenSSLCryptoFactory.h	1555
gdcmmOpenSSLCryptographicMessageSyntax.h	1556
gdcmmOpenSSL7CryptoFactory.h	1558
gdcmmOpenSSL7CryptographicMessageSyntax.h	1560
gdcmmProgressEvent.h	1562
gdcmmRegion.h	1563
gdcmmSHA1.h	1566
gdcmmSmartPointer.h	1567
gdcmmStaticAssert.h	1569
gdcmmString.h	1571

gdcmSubject.h	1575
gdcmSwapCode.h	1576
gdcmSwapper.h	1578
gdcmSystem.h	1581
gdcmTerminal.h	1583
gdcmTestDriver.h	1585
gdcmTesting.h	1586
gdcmTrace.h	1588
gdcmTypes.h	1594
gdcmUnpacker12Bits.h	1595
gdcmVersion.h	1596
gdcmWin32.h	1597
gdcmCSAHeaderDict.h	1599
gdcmCSAHeaderDictEntry.h	1602
gdcmDict.h	1605
gdcmDictConverter.h	1610
gdcmDictEntry.h	1612
gdcmDicts.h	1615
gdcmGlobal.h	1617
gdcmGroupDict.h	1619
gdcmSOPClassUIDToIOD.h	1621
gdcmUIDs.h	1622
gdcmAttribute.h	1636
gdcmBasicOffsetTable.h	1650
gdcmByteBuffer.h	1653
gdcmByteSwapFilter.h	1656
gdcmByteValue.h	1657
gdcmCodeString.h	1661
gdcmCP246ExplicitDataElement.h	1663
gdcmCSAElement.h	1664
gdcmCSAHeader.h	1668
gdcmDataElement.h	1670
gdcmDataSet.h	1674
gdcmDataSetEvent.h	1678
gdcmElement.h	1680
gdcmExplicitDataElement.h	1692
gdcmExplicitImplicitDataElement.h	1694
gdcmFile.h	1696
gdcmFileMetaInformation.h	1697
gdcmFileSet.h	1700
gdcmFragment.h	1702
gdcmImplicitDataElement.h	1707
gdcmItem.h	1708
gdcmLO.h	1714
gdcmMediaStorage.h	1715
gdcmMrProtocol.h	1719
gdcmParseException.h	1721
gdcmParser.h	1723
gdcmPDBElement.h	1726
gdcmPDBHeader.h	1728
gdcmPreamble.h	1730
gdcmPrivateTag.h	1732
gdcmReader.h	1734
gdcmSequenceOfFragments.h	1736

gdcmSequenceOfItems.h	1741
gdcmTag.h	1745
gdcmTagToVR.h	1750
gdcmTransferSyntax.h	1751
gdcmUNExplicitDataElement.h	1753
gdcmUNExplicitImplicitDataElement.h	1755
gdcmValue.h	1756
gdcmValueIO.h	1758
gdcmVL.h	1759
gdcmVM.h	1762
gdcmVR.h	1765
gdcmVR16ExplicitDataElement.h	1772
gdcmWriter.h	1774
gdcmDefinedTerms.h	1776
gdcmDefs.h	1777
gdcmEnumeratedValues.h	1780
gdcmIOD.h	1781
gdcmIODEntry.h	1784
gdcmIODs.h	1786
gdcmMacro.h	1789
gdcmMacroEntry.h	1792
gdcmMacros.h	1795
gdcmModule.h	1797
gdcmModuleEntry.h	1800
gdcmModules.h	1803
gdcmNestedModuleEntries.h	1805
gdcmPatient.h	1807
gdcmSeries.h	1809
gdcmStudy.h	1810
gdcmTable.h	1812
gdcmTableEntry.h	1814
gdcmTableReader.h	1816
gdcmType.h	1819
gdcmUsage.h	1821
gdcmXMLDictReader.h	1824
gdcmXMLPrivateDictReader.h	1826
gdcmAnonymizeEvent.h	1827
gdcmAnonymizer.h	1829
gdcmApplicationEntity.h	1832
gdcmAudioCodec.h	1833
gdcmBitmap.h	1834
gdcmBitmapToBitmapFilter.h	1838
gdcmCleaner.h	1839
gdcmCodec.h	1841
gdcmCoder.h	1842
gdcmConstCharWrapper.h	1844
gdcmCurve.h	1845
gdcmDataSetHelper.h	1847
gdcmDecoder.h	1848
gdcmDeltaEncodingCodec.h	1850
gdcmDICOMDIR.h	1851
gdcmDICOMDIRGenerator.h	1853
gdcmDictPrinter.h	1855
gdcmDirectionCosines.h	1856

gdcmDirectoryHelper.h	1857
gdcmDPath.h	1859
gdcmDumper.h	1861
gdcmEmptyMaskGenerator.h	1863
gdcmEncapsulatedDocument.h	1864
gdcmEquipmentManufacturer.h	1865
gdcmFiducials.h	1867
gdcmFileAnonymizer.h	1868
gdcmFileChangeTransferSyntax.h	1869
gdcmFileDecompressLookupTable.h	1871
gdcmFileDerivation.h	1873
gdcmFileExplicitFilter.h	1874
gdcmFileStreamer.h	1876
gdcmIconImage.h	1877
gdcmIconImageFilter.h	1879
gdcmIconImageGenerator.h	1881
gdcmImage.h	1882
gdcmImageApplyLookupTable.h	1885
gdcmImageChangePhotometricInterpretation.h	1886
gdcmImageChangePlanarConfiguration.h	1889
gdcmImageChangeTransferSyntax.h	1890
gdcmImageCodec.h	1892
gdcmImageConverter.h	1895
gdcmImageFragmentSplitter.h	1897
gdcmImageHelper.h	1898
gdcmImageReader.h	1900
gdcmImageRegionReader.h	1902
gdcmImageToImageFilter.h	1904
gdcmImageWriter.h	1905
gdcmIPPSorter.h	1906
gdcmJPEG12Codec.h	1908
gdcmJPEG16Codec.h	1910
gdcmJPEG2000Codec.h	1911
gdcmJPEG8Codec.h	1913
gdcmJPEGCodec.h	1915
gdcmJPEGLSCodec.h	1917
gdcmJSON.h	1919
gdcmKAKADUCodec.h	1921
gdcmLookupTable.h	1922
gdcmMEC_MR3.h	1924
gdcmMeshPrimitive.h	1925
gdcmOrientation.h	1928
gdcmOverlay.h	1929
gdcmPDFCodec.h	1932
gdcmPersonName.h	1933
gdcmPGXCodec.h	1935
gdcmPhotometricInterpretation.h	1936
gdcmPixelFormat.h	1938
gdcmPixmap.h	1942
gdcmPixmapReader.h	1945
gdcmPixmapToPixmapFilter.h	1947
gdcmPixmapWriter.h	1948
gdcmPNMCodec.h	1950
gdcmPrinter.h	1951

gdcmPVRGCodec.h	1954
gdcmRAWCodec.h	1956
gdcmRescaler.h	1957
gdcmRLECodec.h	1959
gdcmScanner.h	1960
gdcmScanner2.h	1963
gdcmSegment.h	1966
gdcmSegmentedPaletteColorLookupTable.h	1970
gdcmSegmentHelper.h	1971
gdcmSegmentReader.h	1973
gdcmSegmentWriter.h	1975
gdcmSerieHelper.h	1977
gdcmSimpleSubjectWatcher.h	1980
gdcmSorter.h	1982
gdcmSpacing.h	1985
gdcmSpectroscopy.h	1986
gdcmSplitMosaicFilter.h	1987
gdcmStreamImageReader.h	1990
gdcmStreamImageWriter.h	1991
gdcmStrictScanner.h	1993
gdcmStrictScanner2.h	1996
gdcmStringFilter.h	1999
gdcmSurface.h	2000
gdcmSurfaceHelper.h	2005
gdcmSurfaceReader.h	2007
gdcmSurfaceWriter.h	2009
gdcmTagPath.h	2010
gdcmUIDGenerator.h	2012
gdcmUUIDGenerator.h	2014
gdcmValidate.h	2015
gdcmWaveform.h	2016
gdcmXMLPrinter.h	2017
gdcmAAbortPDU.h	2020
gdcmAAssociateACPDU.h	2021
gdcmAAssociateRJPDU.h	2024
gdcmAAssociateRQPDU.h	2025
gdcmAbstractSyntax.h	2028
gdcmApplicationContext.h	2030
gdcmAReleaseRPPDU.h	2031
gdcmAReleaseRQPDU.h	2033
gdcmARTIMTimer.h	2034
gdcmAsynchronousOperationsWindowSub.h	2036
gdcmBaseCompositeMessage.h	2037
gdcmBaseNormalizedMessage.h	2039
gdcmBasePDU.h	2040
gdcmBaseQuery.h	2042
gdcmBaseRootQuery.h	2044
gdcmCEchoMessages.h	2046
gdcmCFindMessages.h	2047
gdcmCMoveMessages.h	2049
gdcmCommandDataSet.h	2050
gdcmCompositeMessageFactory.h	2052
gdcmCompositeNetworkFunctions.h	2053
gdcmCStoreMessages.h	2055

gdcmDIMSE.h	2057
gdcmFindPatientRootQuery.h	2059
gdcmFindStudyRootQuery.h	2061
gdcmImplementationClassUIDSub.h	2062
gdcmImplementationUIDSub.h	2064
gdcmImplementationVersionNameSub.h	2065
gdcmMaximumLengthSub.h	2067
gdcmModalityPerformedProcedureStepCreateQuery.h	2069
gdcmModalityPerformedProcedureStepSetQuery.h	2070
gdcmMovePatientRootQuery.h	2071
gdcmMoveStudyRootQuery.h	2073
gdcmNActionMessages.h	2074
gdcmNCreateMessages.h	2075
gdcmNDeleteMessages.h	2077
gdcmNetworkEvents.h	2078
gdcmNetworkStateID.h	2080
gdcmNEventReportMessages.h	2082
gdcmNGetMessages.h	2083
gdcmNormalizedMessageFactory.h	2084
gdcmNormalizedNetworkFunctions.h	2086
gdcmNSetMessages.h	2088
gdcmPDataTFPDU.h	2089
gdcmPDUFactory.h	2091
gdcmPresentationContext.h	2092
gdcmPresentationContextAC.h	2094
gdcmPresentationContextGenerator.h	2096
gdcmPresentationContextRQ.h	2098
gdcmPresentationDataValue.h	2100
gdcmQueryBase.h	2102
gdcmQueryFactory.h	2105
gdcmQueryImage.h	2106
gdcmQueryPatient.h	2108
gdcmQuerySeries.h	2110
gdcmQueryStudy.h	2112
gdcmRoleSelectionSub.h	2113
gdcmServiceClassApplicationInformation.h	2115
gdcmServiceClassUser.h	2116
gdcmSOPClassExtendedNegociationSub.h	2119
gdcmTransferSyntaxSub.h	2120
gdcmULAction.h	2122
gdcmULActionAA.h	2124
gdcmULActionAE.h	2126
gdcmULActionAR.h	2128
gdcmULActionDT.h	2131
gdcmULBasicCallback.h	2132
gdcmULConnection.h	2133
gdcmULConnectionCallback.h	2136
gdcmULConnectionInfo.h	2137
gdcmULConnectionManager.h	2139
gdcmULEvent.h	2142
gdcmULTransitionTable.h	2144
gdcmULWritingCallback.h	2147
gdcmUserInformation.h	2148
gdcmWLMFindQuery.h	2150

vtkGDCMImageReader.h	2151
vtkGDCMImageReader2.h	2157
vtkGDCMImageWriter.h	2162
vtkGDCMMedicalImageProperties.h	2165
vtkGDCMPolyDataReader.h	2171
vtkGDCMPolyDataWriter.h	2172
vtkGDCMTesting.h	2174
vtkGDCMThreadedImageReader.h	2176
vtkGDCMThreadedImageReader2.h	2178
vtkImageColorViewer.h	2180
vtkImageMapToColors16.h	2184
vtkImageMapToWindowLevelColors2.h	2186
vtkImagePlanarComponentsToComponents.h	2188
vtkImageRGBToYBR.h	2189
vtkImageYBRToRGB.h	2191
vtkLookupTable16.h	2192
vtkRTStructSetProperties.h	2194
gdcmPythonFilter.h	2196

Chapter 9

Namespace Documentation

9.1 gdcmm Namespace Reference

Namespaces

- namespace [network](#)
- namespace [SegmentHelper](#)
- namespace [terminal](#)

Class for Terminal.

Classes

- class [AbortEvent](#)
- class [AnonymizeEvent](#)
AnonymizeEvent.
- class [Anonymizer](#)
Anonymizer.
- class [AnyEvent](#)
- class [ApplicationEntity](#)
ApplicationEntity.
- class [ASN1](#)
Class for ASN1.
- class [Attribute](#)
Attribute class This class use template metaprograming tricks to let the user know when the template instantiation does not match the public dictionary.
- class [Attribute< Group, Element, TVR, VM::VM1 >](#)
- class [Attribute< Group, Element, TVR, VM::VM1_3 >](#)
- class [Attribute< Group, Element, TVR, VM::VM1_8 >](#)
- class [Attribute< Group, Element, TVR, VM::VM1_n >](#)
- class [Attribute< Group, Element, TVR, VM::VM2_2n >](#)
- class [Attribute< Group, Element, TVR, VM::VM2_n >](#)
- class [Attribute< Group, Element, TVR, VM::VM3_3n >](#)
- class [Attribute< Group, Element, TVR, VM::VM3_n >](#)

- class [AudioCodec](#)
AudioCodec.
- class [Base64](#)
Class for Base64.
- class [BaseQuery](#)
BaseQuery.
- class [BaseRootQuery](#)
BaseRootQuery.
- class [BasicOffsetTable](#)
Class to represent a BasicOffsetTable.
- class [Bitmap](#)
Bitmap class.
- class [BitmapToBitmapFilter](#)
BitmapToBitmapFilter class.
- class [BoxRegion](#)
Class for manipulation box region.
- class [ByteBuffer](#)
ByteBuffer.
- class [ByteSwap](#)
ByteSwap.
- class [ByteSwapFilter](#)
ByteSwapFilter.
- class [ByteValue](#)
Class to represent binary value (array of bytes)
- class [CAPICryptoFactory](#)
- class [CAPICryptographicMessageSyntax](#)
- class [Cleaner](#)
Cleaner.
- class [Codec](#)
Codec class.
- class [Coder](#)
Coder.
- class [CodeString](#)
CodeString.
- class [Command](#)
Command superclass for callback/observer methods.
- class [CommandDataSet](#)
Class to represent a Command DataSet.
- class [CompositeNetworkFunctions](#)
Composite Network Functions.
- class [ConstCharWrapper](#)
Do not use me.
- class [CP246ExplicitDataElement](#)
Class to read/write a DataElement as CP246Explicit Data Element.
- class [CryptoFactory](#)
Class to do handle the crypto factory.
- class [CryptographicMessageSyntax](#)

- class [CSAElement](#)
Class to represent a CSA [Element](#).
- class [CSAHeader](#)
Class for [CSAHeader](#).
- class [CSAHeaderDict](#)
Class to represent a map of [CSAHeaderDictEntry](#).
- class [CSAHeaderDictEntry](#)
Class to represent an Entry in the [Dict](#).
- class [CSAHeaderDictException](#)
- class [Curve](#)
[Curve](#) class to handle element 50xx,3000 [Curve](#) Data.
- class [DataElement](#)
Class to represent a Data [Element](#) either Implicit or Explicit.
- class [DataElementException](#)
- class [DataEvent](#)
[DataEvent](#).
- class [DataSet](#)
Class to represent a Data Set (which contains Data Elements)
- class [DataSetEvent](#)
[DataSetEvent](#).
- class [DataSetHelper](#)
[DataSetHelper](#) (internal class, not intended for user level)
- class [Decoder](#)
[Decoder](#).
- class [DefinedTerms](#)
Defined Terms are used when the specified explicit Values may be extended by implementors to include additional new Values. These new Values shall be specified in the Conformance Statement (see PS 3.2) and shall not have the same meaning as currently defined Values in this standard. A Data [Element](#) with Defined Terms that does not contain a [Value](#) equivalent to one of the Values currently specified in this standard shall not be considered to have an invalid value. Note: Interpretation [Type](#) ID (4008,0210) is an example of a Data [Element](#) having Defined Terms. It is defined to have a [Value](#) that may be one of the set of standard Values; REPORT or AMENDMENT (see PS 3.3). Because this Data [Element](#) has Defined Terms other Interpretation [Type](#) IDs may be defined by the implementor.
- class [Defs](#)
FIXME I do not like the name 'Defs'.
- class [DeltaEncodingCodec](#)
[DeltaEncodingCodec](#) compression used by some private vendor.
- class [DICOMDIR](#)
[DICOMDIR](#) class.
- class [DICOMDIRGenerator](#)
[DICOMDIRGenerator](#) class.
- class [Dict](#)
Class to represent a map of [DictEntry](#).
- class [DictConverter](#)
Class to convert a .dic file into something else:
- class [DictEntry](#)
Class to represent an Entry in the [Dict](#).
- class [DictPrinter](#)
[DictPrinter](#) class.

- class [Dicts](#)
Class to manipulate the sum of knowledge (all the dict user load)
- class [DirectionCosines](#)
class to handle [DirectionCosines](#)
- class [Directory](#)
Class for manipulation directories.
- class [DirectoryHelper](#)
[DirectoryHelper](#).
- class [DPath](#)
*class to handle a DICOM path While supp 118 did introduced a notion of XPath for XML Native model this convention is too XML-centric. Instead prefer DCMTK style notation <https://groups.google.com/g/comp.protocols>.↔
[dicom/c/IyIH0IOBMPA](#)*
- class [DummyValueGenerator](#)
Class for generating dummy value.
- class [Dumper](#)
[Codec](#) class.
- class [Element](#)
[Element](#) class.
- class [Element< TVR, VM::VM1_2 >](#)
- class [Element< TVR, VM::VM1_n >](#)
- class [Element< TVR, VM::VM2_2n >](#)
- class [Element< TVR, VM::VM2_n >](#)
- class [Element< TVR, VM::VM3_3n >](#)
- class [Element< TVR, VM::VM3_4 >](#)
- class [Element< TVR, VM::VM3_n >](#)
- class [Element< VR::AS, VM::VM5 >](#)
- class [Element< VR::OB, VM::VM1 >](#)
- class [Element< VR::OW, VM::VM1 >](#)
- class [ElementDisableCombinations](#)
A class which is used to produce compile errors for an invalid combination of template parameters.
- class [ElementDisableCombinations< VR::OB, VM::VM1_n >](#)
- class [ElementDisableCombinations< VR::OW, VM::VM1_n >](#)
- class [EmptyMaskGenerator](#)
[EmptyMaskGenerator](#) Main class to generate a Empty Mask [Series](#) from an input [Series](#). This class takes an input folder and generates a series of DICOM files in the specified output directory. This class handles multiples DICOM [Series](#) within the same input directory.
- class [EncapsulatedDocument](#)
[EncapsulatedDocument](#).
- class [EncodingImplementation](#)
[EncodingImplementation](#).
- class [EncodingImplementation< VR::VRASCII >](#)
- class [EncodingImplementation< VR::VRBINARY >](#)
- class [EndEvent](#)
- class [EnumeratedValues](#)
[Element](#). A Data [Element](#) with Enumerated Values that does not have a [Value](#) equivalent to one of the Values specified in this standard has an invalid value within the scope of a specific Information Object/SOP Class definition. Note:
- class [EquipmentManufacturer](#)
- class [Event](#)
superclass for callback/observer methods

- class [Exception](#)
Exception.
- class [ExitEvent](#)
- class [ExplicitDataElement](#)
Class to read/write a [DataElement](#) as Explicit Data [Element](#).
- class [ExplicitImplicitDataElement](#)
Class to read/write a [DataElement](#) as ExplicitImplicit Data [Element](#).
- class [Fiducials](#)
Fiducials.
- class [File](#)
a DICOM File
- class [FileAnonymizer](#)
FileAnonymizer.
- class [FileChangeTransferSyntax](#)
FileChangeTransferSyntax.
- class [FileDecompressLookupTable](#)
FileDecompressLookupTable class.
- class [FileDerivation](#)
FileDerivation class.
- class [FileExplicitFilter](#)
FileExplicitFilter class.
- class [FileMetaInformation](#)
Class to represent a [File](#) Meta Information.
- class [Filename](#)
Class to manipulate file name's.
- class [FileNameEvent](#)
FileNameEvent.
- class [FilenameGenerator](#)
FilenameGenerator.
- class [FileSet](#)
- class [FileStreamer](#)
FileStreamer.
- class [FileWithName](#)
FileWithName.
- class [FindPatientRootQuery](#)
PatientRootQuery.
- class [FindStudyRootQuery](#)
FindStudyRootQuery.
- class [Fragment](#)
Class to represent a [Fragment](#).
- class [Global](#)
Global.
- class [GroupDict](#)
Class to represent the mapping from group number to its abbreviation and name.
- class [IconImageFilter](#)
IconImageFilter.
- class [IconImageGenerator](#)

- [*IconImageGenerator.*](#)
- struct [ignore_char](#)
- class [Image](#)
 - [*Image.*](#)
- class [ImageApplyLookupTable](#)
 - [*ImageApplyLookupTable* class.](#)
- class [ImageChangePhotometricInterpretation](#)
 - [*ImageChangePhotometricInterpretation* class.](#)
- class [ImageChangePlanarConfiguration](#)
 - [*ImageChangePlanarConfiguration* class.](#)
- class [ImageChangeTransferSyntax](#)
 - [*ImageChangeTransferSyntax* class.](#)
- class [ImageCodec](#)
 - [*ImageCodec.*](#)
- class [ImageConverter](#)
 - [*Image* Converter.](#)
- class [ImageFragmentSplitter](#)
 - [*ImageFragmentSplitter* class.](#)
- class [ImageHelper](#)
 - [*ImageHelper* \(internal class, not intended for user level\)](#)
- class [ImageReader](#)
 - [*ImageReader.*](#)
- class [ImageRegionReader](#)
 - [*ImageRegionReader.*](#)
- class [ImageToImageFilter](#)
 - [*ImageToImageFilter* class.](#)
- class [ImageWriter](#)
 - [*ImageWriter.*](#)
- class [ImplicitDataElement](#)
 - [Class to represent an Implicit *VR* Data *Element*.](#)
- class [InitializeEvent](#)
- class [IOD](#)
 - [Class for representing a *IOD*.](#)
- class [IODEntry](#)
 - [Class for representing a *IODEntry*.](#)
- class [IODs](#)
 - [Class for representing a *IODs*.](#)
- class [IPPSorter](#)
 - [*IPPSorter.*](#)
- class [Item](#)
 - [Class to represent an *Item*.](#)
- class [IterationEvent](#)
- class [JPEG12Codec](#)
 - [Class to do JPEG 12bits \(lossy & lossless\)](#)
- class [JPEG16Codec](#)
 - [Class to do JPEG 16bits \(lossless\)](#)
- class [JPEG2000Codec](#)

- Class to do JPEG 2000.*
- class [JPEG8Codec](#)
 - Class to do JPEG 8bits (lossy & lossless)*
- class [JPEGCodec](#)
 - JPEG codec.*
- class [JPEGLSCodec](#)
 - JPEG-LS.*
- class [JSON](#)
- class [KAKADUCodec](#)
 - KAKADUCodec.*
- class [LO](#)
 - LO.*
- class [LookupTable](#)
 - LookupTable class.*
- class [Macro](#)
 - Class for representing a [Macro](#).*
- class [Macros](#)
 - Class for representing a [Modules](#).*
- class [MD5](#)
 - Class for [MD5](#).*
- class [MEC_MR3](#)
 - Class for [MEC_MR3](#).*
- class [MediaStorage](#)
 - MediaStorage.*
- class [MemberCommand](#)
 - Command subclass that calls a pointer to a member function.*
- class [MeshPrimitive](#)
 - This class defines surface mesh primitives.*
- class [ModalityPerformedProcedureStepCreateQuery](#)
 - ModalityPerformedProcedureStepCreateQuery.*
- class [ModalityPerformedProcedureStepSetQuery](#)
 - ModalityPerformedProcedureStepSetQuery.*
- class [ModifiedEvent](#)
- class [Module](#)
 - Class for representing a [Module](#).*
- class [ModuleEntry](#)
 - Class for representing a [ModuleEntry](#).*
- class [Modules](#)
 - Class for representing a [Modules](#).*
- class [MovePatientRootQuery](#)
 - MovePatientRootQuery.*
- class [MoveStudyRootQuery](#)
 - MoveStudyRootQuery.*
- class [MrProtocol](#)
 - Class for [MrProtocol](#).*
- class [NestedModuleEntries](#)
 - Class for representing a [NestedModuleEntries](#).*

- class [NoEvent](#)
- class [NormalizedNetworkFunctions](#)
Normalized Network Functions.
- class [Object](#)
Object.
- class [OpenSSLCryptoFactory](#)
- class [OpenSSLCryptographicMessageSyntax](#)
- class [OpenSSLP7CryptoFactory](#)
- class [OpenSSLP7CryptographicMessageSyntax](#)
- class [Orientation](#)
class to handle [Orientation](#)
- class [Overlay](#)
Overlay class.
- class [ParseException](#)
[ParseException](#) Standard exception handling object.
- class [Parser](#)
[Parser](#) ala XML_Parser from expat (SAX)
- class [Patient](#)
See PS 3.3 - 2007 DICOM MODEL OF THE REAL-WORLD, p 54.
- class [PDBElement](#)
Class to represent a PDB [Element](#).
- class [PDBHeader](#)
Class for [PDBHeader](#).
- class [PDFCodec](#)
[PDFCodec](#) class.
- class [PersonName](#)
[PersonName](#) class.
- class [PGXCodec](#)
Class to do PGX.
- class [PhotometricInterpretation](#)
Class to represent an [PhotometricInterpretation](#).
- class [PixelFormat](#)
[PixelFormat](#).
- class [Pixmap](#)
[Pixmap](#) class.
- class [PixmapReader](#)
[PixmapReader](#).
- class [PixmapToPixmapFilter](#)
[PixmapToPixmapFilter](#) class.
- class [PixmapWriter](#)
[PixmapWriter](#).
- class [PNMCodec](#)
Class to do PNM.
- class [Preamble](#)
DICOM [Preamble](#) (Part 10)
- class [PresentationContext](#)
[PresentationContext](#).

- class [PresentationContextGenerator](#)
PresentationContextGenerator.
- class [Printer](#)
Printer class.
- class [PrivateDict](#)
Private Dict.
- class [PrivateTag](#)
Class to represent a Private DICOM Data [Element](#) ([Attribute](#)) [Tag](#) (Group, [Element](#), Owner)
- class [ProgressEvent](#)
ProgressEvent.
- class [PVRGCodec](#)
PVRGCodec.
- class [PythonFilter](#)
PythonFilter [PythonFilter](#) is the class that make gdcm2.x looks more like gdcm1 and transform the binary blob contained in a [DataElement](#) into a string, typically this is a nice feature to have for wrapped language.
- class [QueryBase](#)
QueryBase.
- class [QueryFactory](#)
QueryFactory.h.
- class [QueryImage](#)
QueryImage.
- class [QueryPatient](#)
QueryPatient.
- class [QuerySeries](#)
QuerySeries.
- class [QueryStudy](#)
QueryStudy.h.
- class [RAWCodec](#)
RAWCodec class.
- class [Reader](#)
Reader ala DOM (Document [Object](#) Model)
- struct [RealWorldValueMappingContent](#)
- class [Region](#)
Class for manipulation region.
- class [Rescaler](#)
Rescale class.
- class [RLECodec](#)
Class to do RLE.
- class [Scanner](#)
Scanner.
- class [Scanner2](#)
Scanner2.
- class [Segment](#)
This class defines a segment.
- class [SegmentedPaletteColorLookupTable](#)
SegmentedPaletteColorLookupTable class.
- class [SegmentReader](#)

This class defines a segment reader.

- class [SegmentWriter](#)

This class defines a segment writer.

- class [SequenceOfFragments](#)

Class to represent a Sequence Of Fragments.

- class [SequenceOfItems](#)

Class to represent a Sequence Of Items.

- class [SerieHelper](#)

[SerieHelper](#) DO NOT USE this class, it is only a temporary solution for ITK migration from GDCM 1.x to GDCM 2.x It will disappear soon, you've been warned.

- class [Series](#)

Series.

- class [ServiceClassUser](#)

ServiceClassUser.

- class [SHA1](#)

Class for [SHA1](#).

- class [SimpleMemberCommand](#)

Command subclass that calls a pointer to a member function.

- class [SimpleSubjectWatcher](#)

SimpleSubjectWatcher.

- class [SmartPointer](#)

Class for Smart Pointer.

- class [SOPClassUIDToIOD](#)

Class convert a class SOP Class UID into [IOD](#).

- class [Sorter](#)

Sorter.

- class [Spacing](#)

Class for [Spacing](#).

- class [Spectroscopy](#)

Spectroscopy class.

- class [SplitMosaicFilter](#)

SplitMosaicFilter class.

- class [StartEvent](#)

- struct [static_assert_test](#)

- struct [STATIC_ASSERTION_FAILURE](#)

- struct [STATIC_ASSERTION_FAILURE< true >](#)

- class [StreamImageReader](#)

StreamImageReader.

- class [StreamImageWriter](#)

StreamImageReader.

- class [StrictScanner](#)

StrictScanner.

- class [StrictScanner2](#)

StrictScanner2.

- class [String](#)

String.

- class [StringFilter](#)

- StringFilter.*
- class [Study](#)
 - Study.*
- class [Subject](#)
 - Subject.*
- class [Surface](#)
 - This class defines a SURFACE IE.*
- class [SurfaceHelper](#)
 - SurfaceHelper.*
- class [SurfaceReader](#)
 - This class defines a SURFACE IE reader.*
- class [SurfaceWriter](#)
 - This class defines a SURFACE IE writer.*
- class [SwapCode](#)
 - SwapCode representation.*
- class [SwapperDoOp](#)
- class [SwapperNoOp](#)
- class [System](#)
 - Class to do system operation.*
- class [Table](#)
 - Table.*
- class [TableEntry](#)
 - TableEntry.*
- class [TableReader](#)
 - Class for representing a [TableReader](#).*
- class [Tag](#)
 - Class to represent a DICOM Data [Element](#) ([Attribute](#)) [Tag](#) (Group, [Element](#)).*
- class [TagPath](#)
 - class to handle a path of tag.*
- class [Testing](#)
 - class for testing*
- class [Trace](#)
 - Trace.*
- class [TransferSyntax](#)
 - Class to manipulate Transfer Syntax.*
- class [Type](#)
 - Type.*
- struct [UI](#)
- class [UIDGenerator](#)
 - Class for generating unique UID.*
- class [UIDs](#)
 - all known uids*
- class [UNExplicitDataElement](#)
 - Class to read/write a [DataElement](#) as UNExplicit Data [Element](#).*
- class [UNExplicitImplicitDataElement](#)
 - Class to read/write a [DataElement](#) as ExplicitImplicit Data [Element](#).*
- class [Unpacker12Bits](#)

- Pack/Unpack 12 bits pixel into 16bits.*
- class [Usage](#)
 - Usage.*
- class [UserEvent](#)
- class [UUIDGenerator](#)
 - Class for generating unique UUID.*
- class [Validate](#)
 - Validate class.*
- class [Value](#)
 - Class to represent the value of a Data [Element](#).*
- class [ValueIO](#)
 - Class to dispatch template calls.*
- class [Version](#)
 - major/minor and build version*
- class [VL](#)
 - Value Length.*
- class [VM](#)
 - Value Multiplicity Looking at the DICOMV3 dict only there is very few cases: 1 2 3 4 5 6 8 16 24 1-2 1-3 1-8 1-32 1-99 1-n 2-2n 2-n 3-3n 3-n.*
- struct [VMToLength](#)
- class [VR](#)
 - VR class.*
- class [VR16ExplicitDataElement](#)
 - Class to read/write a [DataElement](#) as Explicit Data [Element](#).*
- struct [VRToEncoding](#)
- struct [VRToType](#)
- class [VRVLSize](#)
- class [VRVLSize< 0 >](#)
- class [VRVLSize< 1 >](#)
- class [Waveform](#)
 - Waveform class.*
- class [WLMFindQuery](#)
 - PatientRootQuery.*
- class [Writer](#)
 - Writer ala DOM (Document [Object Model](#))*
- class [XMLDictReader](#)
 - Class for representing a [XMLDictReader](#).*
- class [XMLPrinter](#)
- class [XMLPrivateDictReader](#)
 - Class for representing a [XMLPrivateDictReader](#).*

Typedefs

- typedef [String](#)<"\", 16 > [AECComp](#)
- typedef [String](#)<"\", 64 > [ASComp](#)
- typedef bool(* [BOOL_FUNCTION_PFILE_PFILE_POINTER](#)) ([File](#) *, [File](#) *)
- typedef [String](#)<"\", 16 > [CSCComp](#)
- typedef [String](#)<"\", 64 > [DACComp](#)

- typedef [String](#)<"\", 64 > [DTComp](#)
- typedef [std::vector](#)< [SmartPointer](#)< [FileWithName](#) > > [FileList](#)
- typedef [Bitmap](#) [IconImage](#)
- typedef [String](#)<"\", 64 > [LOComp](#)
- typedef [String](#)<"\", 64 > [LTComp](#)
- typedef [ModuleEntry](#) [MacroEntry](#)
- typedef [NestedModuleEntries](#) [NestedMacroEntries](#)
- typedef [String](#)<"\", 64 > [PNComp](#)
- typedef [String](#)<"\", 64 > [SHComp](#)
- typedef [String](#)<"\", 64 > [STComp](#)
- typedef [String](#)<"\", 16 > [TMComp](#)
- typedef [String](#)<"\", 4294967294 > [UCComp](#)
- typedef [String](#)<"\", 64, 0 > [UIComp](#)
- typedef [String](#)<"\", 4294967294 > [URComp](#)
- typedef [String](#)<"\", 64 > [UTComp](#)

Enumerations

- enum [CompOperators](#) {
[GDCM_EQUAL](#) = 0 ,
[GDCM_DIFFERENT](#) ,
[GDCM_GREATER](#) ,
[GDCM_GREATEROREQUAL](#) ,
[GDCM_LESS](#) ,
[GDCM_LESSEOREQUAL](#) }
- enum [ECharSet](#) {
[eLatin1](#) = 0 ,
[eLatin2](#) ,
[eLatin3](#) ,
[eLatin4](#) ,
[eCyrillic](#) ,
[eArabic](#) ,
[eGreek](#) ,
[eHebrew](#) ,
[eLatin5](#) ,
[eJapanese](#) ,
[eThai](#) ,
[eJapaneseKanjiMultibyte](#) ,
[eJapaneseSupplementaryKanjiMultibyte](#) ,
[eKoreanHangulHanjaMultibyte](#) ,
[eUTF8](#) ,
[eGB18030](#) }
- enum [ENQueryType](#) {
[eCreateMMPS](#) = 0 ,
[eSetMMPS](#) }
- enum [EQueryLevel](#) {
[ePatient](#) = 0 ,
[eStudy](#) = 1 ,
[eSeries](#) = 2 ,
[eImage](#) = 3 }

- enum [EQueryType](#) {
 [eFind](#) = 0 ,
 [eMove](#) ,
 [eWLMFind](#) }
- enum [ERootType](#) {
 [ePatientRootType](#) ,
 [eStudyRootType](#) }
- enum [LodModeType](#) {
 [LD_ALL](#) = 0x00000000 ,
 [LD_NOSEQ](#) = 0x00000001 ,
 [LD_NOSHADOW](#) = 0x00000002 ,
 [LD_NOSHADOWSEQ](#) = 0x00000004 }

Functions

- static int [add1](#) (char *buf, int n)
- [ignore_char](#) const [backslash](#) ("\\")
- template<typename T>
 static T [Clamp](#) (int v)
- static void [clean](#) (char *mant)
- static int [doround](#) (char *buf, unsigned int n)
- [VR::VRType](#) [GetVRFromTag](#) ([Tag](#) const &tag)
- bool [operator!=](#) (const [CodeString](#) &ref, const [CodeString](#) &cs)
- bool [operator!=](#) (const [DataElement](#) &lhs, const [DataElement](#) &rhs)
- std::ostream & [operator<<](#) (std::ostream &_os, const [GroupDict](#) &_val)
- std::ostream & [operator<<](#) (std::ostream &_os, const [IOD](#) &_val)
- std::ostream & [operator<<](#) (std::ostream &_os, const [IODEntry](#) &_val)
- std::ostream & [operator<<](#) (std::ostream &_os, const [IODs](#) &_val)
- std::ostream & [operator<<](#) (std::ostream &_os, const [Macro](#) &_val)
- std::ostream & [operator<<](#) (std::ostream &_os, const [Macros](#) &_val)
- std::ostream & [operator<<](#) (std::ostream &_os, const [MediaStorage](#) &ms)
- std::ostream & [operator<<](#) (std::ostream &_os, const [Module](#) &_val)
- std::ostream & [operator<<](#) (std::ostream &_os, const [ModuleEntry](#) &_val)
- std::ostream & [operator<<](#) (std::ostream &_os, const [Modules](#) &_val)
- std::ostream & [operator<<](#) (std::ostream &_os, const [NestedModuleEntries](#) &_val)
- std::ostream & [operator<<](#) (std::ostream &_os, const [Tag](#) &_val)
- std::ostream & [operator<<](#) (std::ostream &_os, const [TransferSyntax](#) &ts)
- std::ostream & [operator<<](#) (std::ostream &_os, const [Type](#) &val)
- std::ostream & [operator<<](#) (std::ostream &_os, const [UI](#) &_val)
- std::ostream & [operator<<](#) (std::ostream &_os, const [UIDs](#) &uid)
- std::ostream & [operator<<](#) (std::ostream &_os, const [Usage](#) &val)
- std::ostream & [operator<<](#) (std::ostream &_os, const [VM](#) &_val)
- std::ostream & [operator<<](#) (std::ostream &_os, const [VR](#) &val)
- std::ostream & [operator<<](#) (std::ostream &os, const [BasicOffsetTable](#) &val)
- std::ostream & [operator<<](#) (std::ostream &os, const [CodeString](#) &str)
- std::ostream & [operator<<](#) (std::ostream &os, const [CommandDataSet](#) &val)
- std::ostream & [operator<<](#) (std::ostream &os, const [CSAElement](#) &val)
- std::ostream & [operator<<](#) (std::ostream &os, const [CSAHeader](#) &d)
- std::ostream & [operator<<](#) (std::ostream &os, const [CSAHeaderDict](#) &val)
- std::ostream & [operator<<](#) (std::ostream &os, const [CSAHeaderDictEntry](#) &val)

- `std::ostream & operator<< (std::ostream &os, const DataElement &val)`
- `std::ostream & operator<< (std::ostream &os, const DataSet &val)`
- `std::ostream & operator<< (std::ostream &os, const Dict &val)`
- `std::ostream & operator<< (std::ostream &os, const DictEntry &val)`
- `std::ostream & operator<< (std::ostream &os, const Dicts &d)`
- `std::ostream & operator<< (std::ostream &os, const Directory &d)`
- `std::ostream & operator<< (std::ostream &os, const DPath &val)`
- `std::ostream & operator<< (std::ostream &os, const Event &e)`

Generic inserter operator for [Event](#) and its subclasses.

- `std::ostream & operator<< (std::ostream &os, const File &val)`
- `std::ostream & operator<< (std::ostream &os, const FileMetaInformation &val)`
- `std::ostream & operator<< (std::ostream &os, const FileSet &f)`
- `std::ostream & operator<< (std::ostream &os, const Fragment &val)`
- `std::ostream & operator<< (std::ostream &os, const Global &g)`
- `std::ostream & operator<< (std::ostream &os, const Item &val)`
- `std::ostream & operator<< (std::ostream &os, const MrProtocol &d)`
- `std::ostream & operator<< (std::ostream &os, const Object &obj)`
- `std::ostream & operator<< (std::ostream &os, const Orientation &o)`
- `std::ostream & operator<< (std::ostream &os, const PDElement &val)`
- `std::ostream & operator<< (std::ostream &os, const PDBHeader &d)`
- `std::ostream & operator<< (std::ostream &os, const PhotometricInterpretation &val)`
- `std::ostream & operator<< (std::ostream &os, const PixelFormat &pf)`
- `std::ostream & operator<< (std::ostream &os, const Preamble &val)`
- `std::ostream & operator<< (std::ostream &os, const PrivateDict &val)`
- `std::ostream & operator<< (std::ostream &os, const PrivateTag &val)`
- `std::ostream & operator<< (std::ostream &os, const Region &r)`
- `std::ostream & operator<< (std::ostream &os, const Scanner &s)`
- `std::ostream & operator<< (std::ostream &os, const Scanner2 &s)`
- `std::ostream & operator<< (std::ostream &os, const Sorter &s)`
- `std::ostream & operator<< (std::ostream &os, const StrictScanner &s)`
- `std::ostream & operator<< (std::ostream &os, const StrictScanner2 &s)`
- `std::ostream & operator<< (std::ostream &os, const SwapCode &sc)`
- `std::ostream & operator<< (std::ostream &os, const Version &v)`
- `std::ostream & operator<< (std::ostream &os, const VL &val)`
- `bool operator== (const CodeString &ref, const CodeString &cs)`
- `std::istream & operator>> (std::istream &_is, Tag &_val)`
- `std::istream & operator>> (std::istream &in, ignore_char const &ic)`
- `template<char TDelimiter, unsigned int TMaxLength, char TPadChar>
std::istream & operator>> (std::istream &is, String< TDelimiter, TMaxLength, TPadChar > &ms)`
- `template<typename T>
static int Round (T x)`
- `static int roundat (char *buf, size_t bufLen, unsigned int i, int iexp)`
- `template<typename Float>
static void x16printf (char *buf, int size, Float f)`

Variables

- static [Global GlobalInstance](#)

9.1.1 Detailed Description

This header defines the classes for the AA Actions, Association Abort Related Actions ([Table 9-9](#) of ps 3.8-2009).

Since each class is essentially a placeholder for a function pointer, I'm breaking with having each class have its own file for the sake of brevity of the number of files.

This header defines the classes for the AE Actions, Association Establishment Related Actions ([Table 9-6](#) of ps 3.8-2009).

Since each class is essentially a placeholder for a function pointer, I'm breaking with having each class have its own file for the sake of brevity of the number of files.

This header defines the classes for the AR Actions, Association Release Related Actions ([Table 9-8](#) of ps 3.8-2009).

Since each class is essentially a placeholder for a function pointer, I'm breaking with having each class have its own file for the sake of brevity of the number of files.

This header defines the classes for the DT Actions, Data Transfer Related Actions ([Table 9-8](#) of ps 3.8-2009).

Since each class is essentially a placeholder for a function pointer, I'm breaking with having each class have its own file for the sake of brevity of the number of files.

9.1.2 Typedef Documentation

9.1.2.1 AECComp

```
typedef String<'\\',16> gdcM::AECComp
```

9.1.2.2 ASComp

```
typedef String<'\\',64> gdcM::ASComp
```

9.1.2.3 BOOL_FUNCTION_PFILE_PFILE_POINTER

```
typedef bool(* gdcM::BOOL\_FUNCTION\_PFILE\_PFILE\_POINTER) (File *, File *)
```

9.1.2.4 CSComp

```
typedef String<'\\',16> gdcM::CSComp
```

9.1.2.5 DAComp

```
typedef String<'\\', 64> gdcm::DAComp
```

Examples

[TemplateEmptyImage.cxx](#).

9.1.2.6 DTComp

```
typedef String<'\\', 64> gdcm::DTComp
```

9.1.2.7 FileList

```
typedef std::vector< SmartPointer<FileWithName> > gdcm::FileList
```

9.1.2.8 IconImage

```
typedef Bitmap gdcm::IconImage
```

Examples

[ExtractIconFromFile.cxx](#).

9.1.2.9 LOComp

```
typedef String<'\\', 64> gdcm::LOComp
```

9.1.2.10 LTComp

```
typedef String<'\\', 64> gdcm::LTComp
```

9.1.2.11 MacroEntry

```
typedef ModuleEntry gdcm::MacroEntry
```

9.1.2.12 NestedMacroEntries

```
typedef NestedModuleEntries gdcm::NestedMacroEntries
```

9.1.2.13 PNComp

```
typedef String<'\\', 64> gdcM::PNComp
```

9.1.2.14 SHComp

```
typedef String<'\\', 64> gdcM::SHComp
```

9.1.2.15 STComp

```
typedef String<'\\', 64> gdcM::STComp
```

9.1.2.16 TMComp

```
typedef String<'\\', 16> gdcM::TMComp
```

Examples

[TemplateEmptyImage.cxx](#).

9.1.2.17 UCComp

```
typedef String<'\\', 4294967294> gdcM::UCComp
```

9.1.2.18 UIComp

```
typedef String<'\\', 64, 0> gdcM::UIComp
```

9.1.2.19 URComp

```
typedef String<'\\', 4294967294> gdcM::URComp
```

9.1.2.20 UTComp

```
typedef String<'\\', 64> gdcM::UTComp
```

9.1.3 Enumeration Type Documentation

9.1.3.1 CompOperators

```
enum gdcM::CompOperators
```

Enumerator

GDCM_EQUAL	
GDCM_DIFFERENT	
GDCM_GREATER	
GDCM_GREATEROREQUAL	
GDCM_LESS	
GDCM_LESOREQUAL	

9.1.3.2 ECharSet

enum `gdcm::ECharSet`

The character sets enumerated in PS 3.3 2009 Annex C, section C.12.1.1.2 The resulting character set is stored in 0008,0005 The conversion to the data element is performed by the [QueryFactory](#) itself

Enumerator

eLatin1	
eLatin2	
eLatin3	
eLatin4	
eCyrillic	
eArabic	
eGreek	
eHebrew	
eLatin5	
eJapanese	
eThai	
eJapaneseKanjiMultibyte	
eJapaneseSupplementaryKanjiMultibyte	
eKoreanHangulHanjaMultibyte	
eUTF8	
eGB18030	

9.1.3.3 ENQueryType

enum `gdcm::ENQueryType`

Enumerator

eCreateMMPS	
eSetMMPS	

9.1.3.4 EQueryLevel

enum `gdcm::EQueryLevel`

Enumerator

ePatient	
eStudy	
eSeries	
eImage	

9.1.3.5 EQueryType

```
enum gdcm::EQueryType
```

Enumerator

eFind	
eMove	
eWLMFind	

9.1.3.6 ERootType

```
enum gdcm::ERootType
```

Enumerator

ePatientRootType	
eStudyRootType	

9.1.3.7 LodModeType

```
enum gdcm::LodModeType
```

Enumerator

LD_ALL	
LD_NOSEQ	
LD_NOSHADOW	
LD_NOSHADOWSEQ	

9.1.4 Function Documentation

9.1.4.1 add1()

```
int gdcm::add1 (
    char * buf,
    int n) [static]
```

References [add1\(\)](#).

Referenced by [add1\(\)](#), and [doround\(\)](#).

9.1.4.2 backslash()

```
ignore_char const gdcm::backslash (
    '\\') 
```

References [backslash\(\)](#).

Referenced by [backslash\(\)](#), and [gdcm::EncodingImplementation< VR::VRASCII >::ReadComputeLength\(\)](#).

9.1.4.3 Clamp()

```
template<typename T>
T gdcm::Clamp (
    int v) [inline], [static]
```

References [gdcm_assert](#).

Referenced by [gdcm::ImageChangePhotometricInterpretation::RGB2YBR\(\)](#), and [gdcm::ImageChangePhotometricInterpretation::YBR2RGB\(\)](#).

9.1.4.4 clean()

```
void gdcm::clean (
    char * mant) [inline], [static]
```

References [clean\(\)](#).

Referenced by [clean\(\)](#), and [x16printf\(\)](#).

9.1.4.5 doround()

```
int gdcm::doround (
    char * buf,
    unsigned int n) [static]
```

References [add1\(\)](#), and [doround\(\)](#).

Referenced by [doround\(\)](#), and [roundat\(\)](#).

9.1.4.6 GetVRFromTag()

```
VR::VRType gdcM::GetVRFromTag (
    Tag const & tag)
```

9.1.4.7 operator"!="() [1/2]

```
bool gdcM::operator!= (
    const CodeString & ref,
    const CodeString & cs) [inline]
```

Referenced by [operator!=\(\)](#).

9.1.4.8 operator"!="() [2/2]

```
bool gdcM::operator!= (
    const DataElement & lhs,
    const DataElement & rhs) [inline]
```

References [operator!=\(\)](#).

9.1.4.9 operator<<() [1/59]

```
std::ostream & gdcM::operator<< (
    std::ostream & _os,
    const GroupDict & _val) [inline]
```

9.1.4.10 operator<<() [2/59]

```
std::ostream & gdcM::operator<< (
    std::ostream & _os,
    const IOD & _val) [inline]
```

9.1.4.11 operator<<() [3/59]

```
std::ostream & gdcM::operator<< (
    std::ostream & _os,
    const IOEntry & _val) [inline]
```

9.1.4.12 operator<<() [4/59]

```
std::ostream & gdcM::operator<< (
    std::ostream & _os,
    const IODs & _val) [inline]
```


9.1.4.13 operator<<() [5/59]

```
std::ostream & gdcm::operator<< (  
    std::ostream & _os,  
    const Macro & _val) [inline]
```

9.1.4.14 operator<<() [6/59]

```
std::ostream & gdcm::operator<< (  
    std::ostream & _os,  
    const Macros & _val) [inline]
```

9.1.4.15 operator<<() [7/59]

```
std::ostream & gdcm::operator<< (  
    std::ostream & _os,  
    const MediaStorage & ms) [inline]
```

9.1.4.16 operator<<() [8/59]

```
std::ostream & gdcm::operator<< (  
    std::ostream & _os,  
    const Module & _val) [inline]
```

9.1.4.17 operator<<() [9/59]

```
std::ostream & gdcm::operator<< (  
    std::ostream & _os,  
    const ModuleEntry & _val) [inline]
```

9.1.4.18 operator<<() [10/59]

```
std::ostream & gdcm::operator<< (  
    std::ostream & _os,  
    const Modules & _val) [inline]
```

9.1.4.19 operator<<() [11/59]

```
std::ostream & gdcm::operator<< (  
    std::ostream & _os,  
    const NestedModuleEntries & _val) [inline]
```

9.1.4.20 operator<<() [12/59]

```
std::ostream & gdcmm::operator<< (
    std::ostream & _os,
    const Tag & _val) [inline]
```

9.1.4.21 operator<<() [13/59]

```
std::ostream & gdcmm::operator<< (
    std::ostream & _os,
    const TransferSyntax & ts) [inline]
```

9.1.4.22 operator<<() [14/59]

```
std::ostream & gdcmm::operator<< (
    std::ostream & _os,
    const Type & val) [inline]
```

9.1.4.23 operator<<() [15/59]

```
std::ostream & gdcmm::operator<< (
    std::ostream & _os,
    const UI & _val) [inline]
```

9.1.4.24 operator<<() [16/59]

```
std::ostream & gdcmm::operator<< (
    std::ostream & _os,
    const UIDs & uid) [inline]
```

References [gdcmm::UIDs::GetName\(\)](#), and [gdcmm::UIDs::GetString\(\)](#).

9.1.4.25 operator<<() [17/59]

```
std::ostream & gdcmm::operator<< (
    std::ostream & _os,
    const Usage & val) [inline]
```

9.1.4.26 operator<<() [18/59]

```
std::ostream & gdcmm::operator<< (
    std::ostream & _os,
    const VM & _val) [inline]
```

9.1.4.27 operator<<() [19/59]

```
std::ostream & gdcm::operator<< (  
    std::ostream & _os,  
    const VR & val) [inline]
```

9.1.4.28 operator<<() [20/59]

```
std::ostream & gdcm::operator<< (  
    std::ostream & os,  
    const BasicOffsetTable & val) [inline]
```

9.1.4.29 operator<<() [21/59]

```
std::ostream & gdcm::operator<< (  
    std::ostream & os,  
    const CodeString & str) [inline]
```

9.1.4.30 operator<<() [22/59]

```
std::ostream & gdcm::operator<< (  
    std::ostream & os,  
    const CommandDataSet & val) [inline]
```

9.1.4.31 operator<<() [23/59]

```
std::ostream & gdcm::operator<< (  
    std::ostream & os,  
    const CSAElement & val) [inline]
```

9.1.4.32 operator<<() [24/59]

```
std::ostream & gdcm::operator<< (  
    std::ostream & os,  
    const CSAHeader & d) [inline]
```

9.1.4.33 operator<<() [25/59]

```
std::ostream & gdcm::operator<< (  
    std::ostream & os,  
    const CSAHeaderDict & val) [inline]
```

9.1.4.34 operator<<() [26/59]

```
std::ostream & gdcmm::operator<< (  
    std::ostream & os,  
    const CSAHeaderDictEntry & val) [inline]
```

9.1.4.35 operator<<() [27/59]

```
std::ostream & gdcmm::operator<< (  
    std::ostream & os,  
    const DataElement & val) [inline]
```

9.1.4.36 operator<<() [28/59]

```
std::ostream & gdcmm::operator<< (  
    std::ostream & os,  
    const DataSet & val) [inline]
```

9.1.4.37 operator<<() [29/59]

```
std::ostream & gdcmm::operator<< (  
    std::ostream & os,  
    const Dict & val) [inline]
```

9.1.4.38 operator<<() [30/59]

```
std::ostream & gdcmm::operator<< (  
    std::ostream & os,  
    const DictEntry & val) [inline]
```

9.1.4.39 operator<<() [31/59]

```
std::ostream & gdcmm::operator<< (  
    std::ostream & os,  
    const Dicts & d) [inline]
```

9.1.4.40 operator<<() [32/59]

```
std::ostream & gdcmm::operator<< (  
    std::ostream & os,  
    const Directory & d) [inline]
```

9.1.4.41 operator<<() [33/59]

```
std::ostream & gdcm::operator<< (
    std::ostream & os,
    const DPath & val) [inline]
```

9.1.4.42 operator<<() [34/59]

```
std::ostream & gdcm::operator<< (
    std::ostream & os,
    const Event & e) [inline]
```

Generic inserter operator for [Event](#) and its subclasses.

References [gdcm::Event::Print\(\)](#).

9.1.4.43 operator<<() [35/59]

```
std::ostream & gdcm::operator<< (
    std::ostream & os,
    const File & val) [inline]
```

9.1.4.44 operator<<() [36/59]

```
std::ostream & gdcm::operator<< (
    std::ostream & os,
    const FileMetaInformation & val) [inline]
```

9.1.4.45 operator<<() [37/59]

```
std::ostream & gdcm::operator<< (
    std::ostream & os,
    const FileSet & f) [inline]
```

9.1.4.46 operator<<() [38/59]

```
std::ostream & gdcm::operator<< (
    std::ostream & os,
    const Fragment & val) [inline]
```

9.1.4.47 operator<<() [39/59]

```
std::ostream & gdcm::operator<< (
    std::ostream & os,
    const Global & g) [inline]
```

9.1.4.48 operator<<() [40/59]

```
std::ostream & gdcmm::operator<< (  
    std::ostream & os,  
    const Item & val) [inline]
```

9.1.4.49 operator<<() [41/59]

```
std::ostream & gdcmm::operator<< (  
    std::ostream & os,  
    const MrProtocol & d) [inline]
```

9.1.4.50 operator<<() [42/59]

```
std::ostream & gdcmm::operator<< (  
    std::ostream & os,  
    const Object & obj) [inline]
```

9.1.4.51 operator<<() [43/59]

```
std::ostream & gdcmm::operator<< (  
    std::ostream & os,  
    const Orientation & o) [inline]
```

9.1.4.52 operator<<() [44/59]

```
std::ostream & gdcmm::operator<< (  
    std::ostream & os,  
    const PDBelement & val) [inline]
```

9.1.4.53 operator<<() [45/59]

```
std::ostream & gdcmm::operator<< (  
    std::ostream & os,  
    const PDBHeader & d) [inline]
```

9.1.4.54 operator<<() [46/59]

```
std::ostream & gdcmm::operator<< (  
    std::ostream & os,  
    const PhotometricInterpretation & val) [inline]
```

9.1.4.55 operator<<() [47/59]

```
std::ostream & gdcm::operator<< (
    std::ostream & os,
    const PixelFormat & pf) [inline]
```

9.1.4.56 operator<<() [48/59]

```
std::ostream & gdcm::operator<< (
    std::ostream & os,
    const Preamble & val) [inline]
```

9.1.4.57 operator<<() [49/59]

```
std::ostream & gdcm::operator<< (
    std::ostream & os,
    const PrivateDict & val) [inline]
```

9.1.4.58 operator<<() [50/59]

```
std::ostream & gdcm::operator<< (
    std::ostream & os,
    const PrivateTag & val) [inline]
```

9.1.4.59 operator<<() [51/59]

```
std::ostream & gdcm::operator<< (
    std::ostream & os,
    const Region & r) [inline]
```

References [gdcm::Region::Print\(\)](#).

9.1.4.60 operator<<() [52/59]

```
std::ostream & gdcm::operator<< (
    std::ostream & os,
    const Scanner & s) [inline]
```

9.1.4.61 operator<<() [53/59]

```
std::ostream & gdcm::operator<< (
    std::ostream & os,
    const Scanner2 & s) [inline]
```

9.1.4.62 operator<<() [54/59]

```
std::ostream & gdcmm::operator<< (  
    std::ostream & os,  
    const Sorter & s) [inline]
```

9.1.4.63 operator<<() [55/59]

```
std::ostream & gdcmm::operator<< (  
    std::ostream & os,  
    const StrictScanner & s) [inline]
```

9.1.4.64 operator<<() [56/59]

```
std::ostream & gdcmm::operator<< (  
    std::ostream & os,  
    const StrictScanner2 & s) [inline]
```

9.1.4.65 operator<<() [57/59]

```
std::ostream & gdcmm::operator<< (  
    std::ostream & os,  
    const SwapCode & sc) [inline]
```

9.1.4.66 operator<<() [58/59]

```
std::ostream & gdcmm::operator<< (  
    std::ostream & os,  
    const Version & v) [inline]
```

9.1.4.67 operator<<() [59/59]

```
std::ostream & gdcmm::operator<< (  
    std::ostream & os,  
    const VL & val) [inline]
```

9.1.4.68 operator==()

```
bool gdcmm::operator==(   
    const CodeString & ref,  
    const CodeString & cs) [inline]
```


9.1.4.69 operator>>() [1/3]

```
std::istream & gdcm::operator>> (
    std::istream & _is,
    Tag & _val) [inline]
```

9.1.4.70 operator>>() [2/3]

```
std::istream & gdcm::operator>> (
    std::istream & in,
    ignore_char const & ic) [inline]
```

References [gdcm::ignore_char::m_char](#).

9.1.4.71 operator>>() [3/3]

```
template<char TDelimiter, unsigned int TMaxLength, char TPadChar>
std::istream & gdcm::operator>> (
    std::istream & is,
    String< TDelimiter, TMaxLength, TPadChar > & ms) [inline]
```

9.1.4.72 Round()

```
template<typename T>
int gdcm::Round (
    T x) [inline], [static]
```

Referenced by [gdcm::ImageChangePhotometricInterpretation::RGB2YBR\(\)](#), and [gdcm::ImageChangePhotometricInterpretation::YBR2RGB\(\)](#).

9.1.4.73 roundat()

```
int gdcm::roundat (
    char * buf,
    size_t bufLen,
    unsigned int i,
    int iexp) [static]
```

References [doround\(\)](#), and [roundat\(\)](#).

Referenced by [roundat\(\)](#), and [x16printf\(\)](#).

9.1.4.74 x16printf()

```
template<typename Float>
void gdcmm::x16printf (
    char * buf,
    int size,
    Float f) [static]
```

References [clean\(\)](#), [roundat\(\)](#), and [x16printf\(\)](#).

Referenced by [gdcmm::EncodingImplementation< VR::VRASCII >::Write\(\)](#), and [x16printf\(\)](#).

9.1.5 Variable Documentation

9.1.5.1 GlobalInstance

```
Global gdcmm::GlobalInstance [static]
```

9.2 gdcmm::network Namespace Reference

Classes

- class [AAbortPDU](#)
AAbortPDU.
- class [AAssociateACPDU](#)
AAssociateACPDU.
- class [AAssociateRJPDU](#)
AAssociateRJPDU.
- class [AAssociateRQPDU](#)
AAssociateRQPDU.
- class [AbstractSyntax](#)
AbstractSyntax.
- class [ApplicationContext](#)
ApplicationContext.
- class [AReleaseRPPDU](#)
AReleaseRPPDU.
- class [AReleaseRQPDU](#)
AReleaseRQPDU.
- class [ARTIMTimer](#)
ARTIMTimer.
- class [AsynchronousOperationsWindowSub](#)
AsynchronousOperationsWindowSub.
- class [BaseCompositeMessage](#)
BaseCompositeMessage.
- class [BaseNormalizedMessage](#)

- BaseNormalizedMessage.*
- class [BasePDU](#)
 - BasePDU.*
- class [CEchoRQ](#)
 - CEchoRQ.*
- class [CEchoRSP](#)
 - CEchoRSP* this file defines the messages for the cecho action.
- class [CFind](#)
- class [CFindCancelRQ](#)
 - CFindCancelRQ* this file defines the messages for the cfind action.
- class [CFindRQ](#)
 - CFindRQ.*
- class [CFindRSP](#)
 - CFindRSP* this file defines the messages for the cfind action.
- class [CMoveCancelRq](#)
- class [CMoveRQ](#)
 - CMoveRQ.*
- class [CMoveRSP](#)
 - CMoveRSP* this file defines the messages for the cmove action.
- class [CompositeMessageFactory](#)
 - CompositeMessageFactory.*
- class [CStoreRQ](#)
 - CStoreRQ.*
- class [CStoreRSP](#)
 - CStoreRSP* this file defines the messages for the cecho action.
- class [DIMSE](#)
 - DIMSE.*
- class [ImplementationClassUIDSub](#)
 - ImplementationClassUIDSub.*
- class [ImplementationUIDSub](#)
 - ImplementationUIDSub.*
- class [ImplementationVersionNameSub](#)
 - ImplementationVersionNameSub.*
- class [MaximumLengthSub](#)
 - MaximumLengthSub.*
- class [NActionRQ](#)
 - NActionRQ.*
- class [NActionRSP](#)
 - NActionRSP* this file defines the messages for the NAction action.
- class [NCreateRQ](#)
 - NCreateRQ.*
- class [NCreateRSP](#)
 - NCreateRSP* this file defines the messages for the ncreate action.
- class [NDeleteRQ](#)
 - NDeleteRQ.*
- class [NDeleteRSP](#)
 - NDeleteRSP* this file defines the messages for the ndelete action.

- class [NEventReportRQ](#)
NEventReportRQ.
- class [NEventReportRSP](#)
NEventReportRSP this file defines the messages for the neventreport action.
- class [NGetRQ](#)
NGetRQ.
- class [NGetRSP](#)
NGetRSP this file defines the messages for the nget action.
- class [NormalizedMessageFactory](#)
- class [NSetRQ](#)
NSetRQ.
- class [NSetRSP](#)
NSetRSP this file defines the messages for the nset action.
- class [PDataTFPDU](#)
PDataTFPDU.
- class [PDUFactory](#)
PDUFactory basically, given an initial byte, construct the.
- class [PresentationContextAC](#)
PresentationContextAC.
- class [PresentationContextRQ](#)
PresentationContextRQ.
- class [PresentationDataValue](#)
PresentationDataValue.
- class [RoleSelectionSub](#)
RoleSelectionSub.
- class [ServiceClassApplicationInformation](#)
- class [SOPClassExtendedNegociationSub](#)
SOPClassExtendedNegociationSub.
- class [TableRow](#)
- class [TransferSyntaxSub](#)
TransferSyntaxSub.
- struct [Transition](#)
- class [ULAction](#)
ULAction.
- class [ULActionAA1](#)
- class [ULActionAA2](#)
- class [ULActionAA3](#)
- class [ULActionAA4](#)
- class [ULActionAA5](#)
- class [ULActionAA6](#)
- class [ULActionAA7](#)
- class [ULActionAA8](#)
- class [ULActionAE1](#)
- class [ULActionAE2](#)
- class [ULActionAE3](#)
- class [ULActionAE4](#)
- class [ULActionAE5](#)
- class [ULActionAE6](#)

- class [ULActionAE7](#)
- class [ULActionAE8](#)
- class [ULActionAR1](#)
- class [ULActionAR10](#)
- class [ULActionAR2](#)
- class [ULActionAR3](#)
- class [ULActionAR4](#)
- class [ULActionAR5](#)
- class [ULActionAR6](#)
- class [ULActionAR7](#)
- class [ULActionAR8](#)
- class [ULActionAR9](#)
- class [ULActionDT1](#)
- class [ULActionDT2](#)
- class [ULBasicCallback](#)
ULBasicCallback.
- class [ULConnection](#)
ULConnection.
- class [ULConnectionCallback](#)
- class [ULConnectionInfo](#)
ULConnectionInfo.
- class [ULConnectionManager](#)
ULConnectionManager.
- class [ULEvent](#)
ULEvent.
- class [ULTransitionTable](#)
ULTransitionTable The transition table of all the ULEvents, new ULActions, and ULStates.
- class [ULWritingCallback](#)
- class [UserInformation](#)
UserInformation.

Enumerations

- enum [EEventID](#) {
[eAASSOCIATERequestLocalUser](#) = 0 ,
[eTransportConnConfirmLocal](#) ,
[eASSOCIATE_ACPDUreceived](#) ,
[eASSOCIATE_RJPDUreceived](#) ,
[eTransportConnIndicLocal](#) ,
[eAASSOCIATE_RQPDUreceived](#) ,
[eAASSOCIATEresponseAccept](#) ,
[eAASSOCIATEresponseReject](#) ,
[ePDATArequest](#) ,
[ePDATATFPDU](#) ,
[eARELEASERequest](#) ,
[eARELEASE_RQPDUReceivedOpen](#) ,
[eARELEASE_RPPDUReceived](#) ,
[eARELEASEResponse](#) ,
[eAABORTRequest](#) ,
[eAABORTPDURceivedOpen](#) ,

- eTransportConnectionClosed ,
- eARTIMTimerExpired ,
- eUnrecognizedPDUReceived ,
- eEventDoesNotExist }
- enum EStateID {
 - eStaDoesNotExist = 0 ,
 - eSta1Idle = 1 ,
 - eSta2Open = 2 ,
 - eSta3WaitLocalAssoc = 4 ,
 - eSta4LocalAssocDone = 8 ,
 - eSta5WaitRemoteAssoc = 16 ,
 - eSta6TransferReady = 32 ,
 - eSta7WaitRelease = 64 ,
 - eSta8WaitLocalRelease = 128 ,
 - eSta9ReleaseCollisionRqLocal = 256 ,
 - eSta10ReleaseCollisionAc = 512 ,
 - eSta11ReleaseCollisionRq = 1024 ,
 - eSta12ReleaseCollisionAcLocal = 2048 ,
 - eSta13AwaitingClose = 4096 }

Functions

- int [GetStateIndex](#) (EStateID inState)

Variables

- const int cMaxEventID = [eEventDoesNotExist](#)
- const int cMaxStateID = 13

9.2.1 Enumeration Type Documentation

9.2.1.1 EEventID

```
enum gdcm::network::EEventID
```

Enumerator

eAASSOCIATERequestLocalUser	
eTransportConnConfirmLocal	
eASSOCIATE_ACPDUreceived	
eASSOCIATE_RJPDUreceived	
eTransportConnIndicLocal	
eAASSOCIATE_RQPDUreceived	
eAASSOCIATEresponseAccept	
eAASSOCIATEresponseReject	
ePDATArequest	
ePDATATFPDU	

Enumerator

eARELEASERequest	
eARELEASE_RQPDURceivedOpen	
eARELEASE_RPPDURceived	
eARELEASEResponse	
eAABORTRequest	
eAABORTPDURceivedOpen	
eTransportConnectionClosed	
eARTIMTimerExpired	
eUnrecognizedPDURceived	
eEventDoesNotExist	

9.2.1.2 EStateID

```
enum gdcmm::network::EStateID
```

Each network connection will be in a particular state at any given time. Those states have IDs as described in the standard ps3.8-2009, roughly 1-13. This enumeration lists those states. The actual ULState class will contain more information about transitions to other states.

name and date: 16 sept 2010 mmr

Enumerator

eStaDoesNotExist	
eSta1Idle	
eSta2Open	
eSta3WaitLocalAssoc	
eSta4LocalAssocDone	
eSta5WaitRemoteAssoc	
eSta6TransferReady	
eSta7WaitRelease	
eSta8WaitLocalRelease	
eSta9ReleaseCollisionRqLocal	
eSta10ReleaseCollisionAc	
eSta11ReleaseCollisionRq	
eSta12ReleaseCollisionAcLocal	
eSta13AwaitingClose	

9.2.2 Function Documentation

9.2.2.1 GetStateIndex()

```
int gdcmm::network::GetStateIndex (
    EStateID inState) [inline]
```

References [eSta10ReleaseCollisionAc](#), [eSta11ReleaseCollisionRq](#), [eSta12ReleaseCollisionAcLocal](#), [eSta13AwaitingClose](#), [eSta1Idle](#), [eSta2Open](#), [eSta3WaitLocalAssoc](#), [eSta4LocalAssocDone](#), [eSta5WaitRemoteAssoc](#), [eSta6TransferReady](#), [eSta7WaitRelease](#), [eSta8WaitLocalRelease](#), [eSta9ReleaseCollisionRqLocal](#), and [eStaDoesNotExist](#).

9.2.3 Variable Documentation

9.2.3.1 cMaxEventID

```
const int gdcn::network::cMaxEventID = eEventDoesNotExist
```

9.2.3.2 cMaxStateID

```
const int gdcn::network::cMaxStateID = 13
```

Referenced by [gdcn::network::TableRow::TableRow\(\)](#), and [gdcn::network::TableRow::~~TableRow\(\)](#).

9.3 gdcn::SegmentHelper Namespace Reference

Classes

- struct [BasicCodedEntry](#)
This structure defines a basic coded entry with all of its attributes.

9.4 gdcn::terminal Namespace Reference

Class for Terminal.

Enumerations

- enum [Attribute](#) {
 [reset](#) = 0 ,
 [bright](#) = 1 ,
 [dim](#) = 2 ,
 [underline](#) = 3 ,
 [blink](#) = 5 ,
 [reverse](#) = 7 ,
 [hidden](#) = 8 }
- enum [Color](#) {
 [black](#) = 0 ,
 [red](#) ,
 [green](#) ,
 [yellow](#) ,
 [blue](#) ,
 [magenta](#) ,
 [cyan](#) ,
 [white](#) }
- enum [Mode](#) {
 [CONSOLE](#) = 0 ,
 [VT100](#) }

Functions

- `GDCM_EXPORT` `std::string` `setattribute` (`Attribute` att)
- `GDCM_EXPORT` `std::string` `setbgcolor` (`Color` c)
- `GDCM_EXPORT` `std::string` `setfgcolor` (`Color` c)
- `GDCM_EXPORT` `void` `setmode` (`Mode` m)

9.4.1 Detailed Description

Class for Terminal.

Allow one to print in color in a shell

- support VT100 compatible shell
- win32 console

9.4.2 Enumeration Type Documentation

9.4.2.1 Attribute

```
enum gdcmm::terminal::Attribute
```

Enumerator

reset	
bright	
dim	
underline	
blink	
reverse	
hidden	

9.4.2.2 Color

```
enum gdcmm::terminal::Color
```

Enumerator

black	
red	
green	
yellow	
blue	
magenta	
cyan	
white	

9.4.2.3 Mode

enum `gdcmm::terminal::Mode`

Enumerator

CONSOLE	
VT100	

9.4.3 Function Documentation

9.4.3.1 setattribute()

```
GDCM_EXPORT std::string gdcm::terminal::setattribute (  
    Attribute att)
```

References [GDCM_EXPORT](#).

9.4.3.2 setbgcolor()

```
GDCM_EXPORT std::string gdcm::terminal::setbgcolor (  
    Color c)
```

References [GDCM_EXPORT](#).

9.4.3.3 setfgcolor()

```
GDCM_EXPORT std::string gdcm::terminal::setfgcolor (  
    Color c)
```

References [GDCM_EXPORT](#).

9.4.3.4 setmode()

```
GDCM_EXPORT void gdcm::terminal::setmode (  
    Mode m)
```

References [GDCM_EXPORT](#).

Chapter 10

Class Documentation

10.1 gdcmm::network::AAabortPDU Class Reference

[AAabortPDU](#).

```
#include <gdcmmAAabortPDU.h>
```

Inheritance diagram for gdcmm::network::AAabortPDU:



Collaboration diagram for gdcmm::network::AAabortPDU:



Public Member Functions

- [AAbortPDU](#) ()
- bool [IsLastFragment](#) () const override
- void [Print](#) (std::ostream &os) const override
- std::istream & [Read](#) (std::istream &is) override
- void [SetReason](#) (const uint8_t r)
- void [SetSource](#) (const uint8_t s)
- size_t [Size](#) () const override
- const std::ostream & [Write](#) (std::ostream &os) const override

Public Member Functions inherited from [gdcm::network::BasePDU](#)

- virtual [~BasePDU](#) ()=default

10.1.1 Detailed Description

[AAbortPDU](#).

[Table 9-26](#) A-ABORT PDU FIELDS

10.1.2 Constructor & Destructor Documentation

10.1.2.1 AAbortPDU()

```
gdcm::network::AAbortPDU::AAbortPDU ()
```

10.1.3 Member Function Documentation

10.1.3.1 IsLastFragment()

```
bool gdcm::network::AAbortPDU::IsLastFragment () const [inline], [override], [virtual]
```

Implements [gdcm::network::BasePDU](#).

10.1.3.2 Print()

```
void gdcm::network::AAbortPDU::Print (
    std::ostream & os) const [override], [virtual]
```

Implements [gdcm::network::BasePDU](#).

10.1.3.3 Read()

```
std::istream & gdcm::network::AAabortPDU::Read (  
    std::istream & is) [override], [virtual]
```

Implements [gdcm::network::BasePDU](#).

10.1.3.4 SetReason()

```
void gdcm::network::AAabortPDU::SetReason (  
    const uint8_t r)
```

10.1.3.5 SetSource()

```
void gdcm::network::AAabortPDU::SetSource (  
    const uint8_t s)
```

10.1.3.6 Size()

```
size_t gdcm::network::AAabortPDU::Size () const [override], [virtual]
```

Implements [gdcm::network::BasePDU](#).

10.1.3.7 Write()

```
const std::ostream & gdcm::network::AAabortPDU::Write (  
    std::ostream & os) const [override], [virtual]
```

Implements [gdcm::network::BasePDU](#).

The documentation for this class was generated from the following file:

- [gdcmAAabortPDU.h](#)

10.2 gdcm::network::AAssociateACPDU Class Reference

[AAssociateACPDU](#).

```
#include <gdcmAAssociateACPDU.h>
```

Inheritance diagram for gdcm::network::AAssociateACPDU:



Collaboration diagram for gdcm::network::AAssociateACPDU:



Public Types

- typedef std::vector< [PresentationContextAC](#) >::size_type [SizeType](#)

Public Member Functions

- [AAssociateACPDU](#) ()
- void [AddPresentationContextAC](#) ([PresentationContextAC](#) const &pcac)
- [SizeType](#) [GetNumberOfPresentationContextAC](#) () const
- const [PresentationContextAC](#) & [GetPresentationContextAC](#) ([SizeType](#) i)
- const [UserInformation](#) & [GetUserInformation](#) () const
- void [InitFromRQ](#) ([AAssociateRQPDU](#) const &rqpdu)
- bool [IsLastFragment](#) () const override
- void [Print](#) (std::ostream &os) const override
- std::istream & [Read](#) (std::istream &is) override
- [SizeType](#) [Size](#) () const override
- const std::ostream & [Write](#) (std::ostream &os) const override

Public Member Functions inherited from [gdcm::network::BasePDU](#)

- virtual [~BasePDU](#) ()=default

Protected Member Functions

- void [SetCalledAETitle](#) (const char calledaetitle[16])
- void [SetCallingAETitle](#) (const char callingaetitle[16])

Friends

- class [AAssociateRQPDU](#)

10.2.1 Detailed Description

[AAssociateACPDU](#).

[Table](#) 9-17 ASSOCIATE-AC PDU fields

10.2.2 Member Typedef Documentation**10.2.2.1 SizeType**

```
typedef std::vector<PresentationContextAC>::size_type gdcm::network::AAssociateACPDU::SizeType
```

10.2.3 Constructor & Destructor Documentation**10.2.3.1 AAssociateACPDU()**

```
gdcm::network::AAssociateACPDU::AAssociateACPDU ()
```

10.2.4 Member Function Documentation

10.2.4.1 AddPresentationContextAC()

```
void gdcmm::network::AAssociateACPDU::AddPresentationContextAC (  
    PresentationContextAC const & pcac)
```

10.2.4.2 GetNumberOfPresentationContextAC()

```
SizeType gdcmm::network::AAssociateACPDU::GetNumberOfPresentationContextAC () const [inline]
```

10.2.4.3 GetPresentationContextAC()

```
const PresentationContextAC & gdcmm::network::AAssociateACPDU::GetPresentationContextAC (  
    SizeType i) [inline]
```

References [gdcmm_assert](#).

10.2.4.4 GetUserInformation()

```
const UserInformation & gdcmm::network::AAssociateACPDU::GetUserInformation () const [inline]
```

10.2.4.5 InitFromRQ()

```
void gdcmm::network::AAssociateACPDU::InitFromRQ (  
    AAssociateRQPDU const & rqpdu)
```

References [AAssociateRQPDU](#).

10.2.4.6 IsLastFragment()

```
bool gdcmm::network::AAssociateACPDU::IsLastFragment () const [inline], [override], [virtual]
```

Implements [gdcmm::network::BasePDU](#).

10.2.4.7 Print()

```
void gdcmm::network::AAssociateACPDU::Print (  
    std::ostream & os) const [override], [virtual]
```

Implements [gdcmm::network::BasePDU](#).

10.2.4.8 Read()

```
std::istream & gdcm::network::AAssociateACPDU::Read (  
    std::istream & is) [override], [virtual]
```

Implements [gdcm::network::BasePDU](#).

10.2.4.9 SetCalledAETitle()

```
void gdcm::network::AAssociateACPDU::SetCalledAETitle (  
    const char calledaetitle[16]) [protected]
```

10.2.4.10 SetCallingAETitle()

```
void gdcm::network::AAssociateACPDU::SetCallingAETitle (  
    const char callingaetitle[16]) [protected]
```

References [AAssociateRQPDU](#).

10.2.4.11 Size()

```
SizeType gdcm::network::AAssociateACPDU::Size () const [override], [virtual]
```

Implements [gdcm::network::BasePDU](#).

10.2.4.12 Write()

```
const std::ostream & gdcm::network::AAssociateACPDU::Write (  
    std::ostream & os) const [override], [virtual]
```

Implements [gdcm::network::BasePDU](#).

10.2.5 Friends And Related Symbol Documentation

10.2.5.1 AAssociateRQPDU

```
friend class AAssociateRQPDU [friend]
```

References [AAssociateRQPDU](#).

Referenced by [AAssociateRQPDU](#), [InitFromRQ\(\)](#), and [SetCallingAETitle\(\)](#).

The documentation for this class was generated from the following file:


- [gdcmAAssociateACPDU.h](#)

10.3 gdcmm::network::AAssociateRJPDU Class Reference


[AAssociateRJPDU](#).

```
#include <gdcmAAssociateRJPDU.h>
```

Inheritance diagram for gdcmm::network::AAssociateRJPDU:



Collaboration diagram for gdcmm::network::AAssociateRJPDU:



Public Member Functions

- [AAssociateRJPDU](#) ()
- bool [IsLastFragment](#) () const override
- void [Print](#) (std::ostream &os) const override
- std::istream & [Read](#) (std::istream &is) override
- size_t [Size](#) () const override
- const std::ostream & [Write](#) (std::ostream &os) const override

Public Member Functions inherited from [gdcmm::network::BasePDU](#)

- virtual [~BasePDU](#) ()=default

10.3.1 Detailed Description

[AAssociateRJPDU](#).

Table 9-21 ASSOCIATE-RJ PDU FIELDS

10.3.2 Constructor & Destructor Documentation

10.3.2.1 AAssociateRJPDU()

```
gdcmm::network::AAssociateRJPDU::AAssociateRJPDU ()
```

10.3.3 Member Function Documentation

10.3.3.1 IsLastFragment()

```
bool gdcmm::network::AAssociateRJPDU::IsLastFragment () const [inline], [override], [virtual]
```

Implements [gdcmm::network::BasePDU](#).

10.3.3.2 Print()

```
void gdcmm::network::AAssociateRJPDU::Print (  
    std::ostream & os) const [override], [virtual]
```

Implements [gdcmm::network::BasePDU](#).

10.3.3.3 Read()

```
std::istream & gdcmm::network::AAssociateRJPDU::Read (  
    std::istream & is) [override], [virtual]
```

Implements [gdcmm::network::BasePDU](#).

10.3.3.4 Size()

```
size_t gdcmm::network::AAssociateRJPDU::Size () const [override], [virtual]
```

Implements [gdcmm::network::BasePDU](#).

10.3.3.5 Write()

```
const std::ostream & gdcm::network::AAssociateRJPDU::Write (  
    std::ostream & os) const [override], [virtual]
```

Implements [gdcm::network::BasePDU](#).

The documentation for this class was generated from the following file:

- [gdcmAAssociateRJPDU.h](#)

10.4 gdcm::network::AAssociateRQPDU Class Reference

[AAssociateRQPDU](#).

```
#include <gdcmAAssociateRQPDU.h>
```

Inheritance diagram for gdcm::network::AAssociateRQPDU:



Collaboration diagram for gdcm::network::AAssociateRQPDU:



Public Types

- typedef std::vector< [PresentationContextRQ](#) > [PresentationContextArrayType](#)
- typedef std::vector< [PresentationContextRQ](#) >::size_type [SizeType](#)

Public Member Functions

- [AAssociateRQPDU](#) ()
- [AAssociateRQPDU](#) (const [AAssociateRQPDU](#) &pdu)
- void [AddPresentationContext](#) ([PresentationContextRQ](#) const &pc)
- std::string [GetCalledAETitle](#) () const
- std::string [GetCallingAETitle](#) () const
- [SizeType](#) [GetNumberOfPresentationContext](#) () const
- [PresentationContextRQ](#) const & [GetPresentationContext](#) ([SizeType](#) i) const
- const [PresentationContextRQ](#) * [GetPresentationContextByAbstractSyntax](#) ([AbstractSyntax](#) const &absyn) const
- const [PresentationContextRQ](#) * [GetPresentationContextByID](#) (uint8_t i) const
- [PresentationContextArrayType](#) const & [GetPresentationContexts](#) ()
- const [UserInfo](#) & [GetUserInfo](#) () const
- bool [IsLastFragment](#) () const override
- void [Print](#) (std::ostream &os) const override
- std::istream & [Read](#) (std::istream &is) override
- void [SetCalledAETitle](#) (const char calledaetitle[16])
Set the Called AE Title.
- void [SetCallingAETitle](#) (const char callingaetitle[16])
Set the Calling AE Title.
- void [SetUserInfo](#) ([UserInfo](#) const &ui)
- size_t [Size](#) () const override
- const std::ostream & [Write](#) (std::ostream &os) const override

Public Member Functions inherited from [gdcm::network::BasePDU](#)

- virtual [~BasePDU](#) ()=default

Static Public Member Functions

- static bool [IsAETitleValid](#) (const char title[16])
Check whether or not the.

Protected Member Functions

- std::string [GetReserved43_74](#) () const

Friends

- class [AAssociateACPDU](#)

10.4.1 Detailed Description

[AAssociateRQPDU](#).

[Table 9-11](#) ASSOCIATE-RQ PDU fields

10.4.2 Member Typedef Documentation

10.4.2.1 PresentationContextArrayType

```
typedef std::vector<PresentationContextRQ> gdcmm::network::AAssociateRQPDU::PresentationContextArrayType
```

10.4.2.2 SizeType

```
typedef std::vector<PresentationContextRQ>::size_type gdcmm::network::AAssociateRQPDU::SizeType
```

10.4.3 Constructor & Destructor Documentation

10.4.3.1 AAssociateRQPDU() [1/2]

```
gdcmm::network::AAssociateRQPDU::AAssociateRQPDU ()
```

Referenced by [AAssociateRQPDU\(\)](#).

10.4.3.2 AAssociateRQPDU() [2/2]

```
gdcmm::network::AAssociateRQPDU::AAssociateRQPDU (  
    const AAssociateRQPDU & pdu) [inline]
```

References [AAssociateRQPDU\(\)](#), and [gdcmm::assert](#).

10.4.4 Member Function Documentation

10.4.4.1 AddPresentationContext()

```
void gdcmm::network::AAssociateRQPDU::AddPresentationContext (  
    PresentationContextRQ const & pc)
```

10.4.4.2 GetCalledAETitle()

```
std::string gdcmm::network::AAssociateRQPDU::GetCalledAETitle () const [inline]
```


10.4.4.3 GetCallingAETitle()

```
std::string gdcmm::network::AAssociateRQPDU::GetCallingAETitle () const [inline]
```

10.4.4.4 GetNumberOfPresentationContext()

```
SizeType gdcmm::network::AAssociateRQPDU::GetNumberOfPresentationContext () const [inline]
```

10.4.4.5 GetPresentationContext()

```
PresentationContextRQ const & gdcmm::network::AAssociateRQPDU::GetPresentationContext (
    SizeType i) const [inline]
```

References [gdcmm_assert](#).

10.4.4.6 GetPresentationContextByAbstractSyntax()

```
const PresentationContextRQ * gdcmm::network::AAssociateRQPDU::GetPresentationContextByAbstract←
Syntax (
    AbstractSyntax const & absyn) const
```

10.4.4.7 GetPresentationContextByID()

```
const PresentationContextRQ * gdcmm::network::AAssociateRQPDU::GetPresentationContextByID (
    uint8_t i) const
```

10.4.4.8 GetPresentationContexts()

```
PresentationContextArrayType const & gdcmm::network::AAssociateRQPDU::GetPresentationContexts ()
[inline]
```

10.4.4.9 GetReserved43_74()

```
std::string gdcmm::network::AAssociateRQPDU::GetReserved43_74 () const [protected]
```

10.4.4.10 GetUserInfo()

```
const UserInformation & gdcmm::network::AAssociateRQPDU::GetUserInfo () const [inline]
```

10.4.4.11 IsAETitleValid()

```
bool gdcmm::network::AAssociateRQPDU::IsAETitleValid (
    const char title[16]) [static]
```

Check whether or not the.

Parameters

<i>title</i>	is a valid AE title
--------------	---------------------

10.4.4.12 IsLastFragment()

```
bool gdcm::network::AAssociateRQPDU::IsLastFragment () const [inline], [override], [virtual]
```

Implements [gdcm::network::BasePDU](#).

10.4.4.13 Print()

```
void gdcm::network::AAssociateRQPDU::Print (  
    std::ostream & os) const [override], [virtual]
```

This function will initialize an [AAssociateACPDU](#) from the fields in the [AAssociateRQPDU](#) structure

Implements [gdcm::network::BasePDU](#).

10.4.4.14 Read()

```
std::istream & gdcm::network::AAssociateRQPDU::Read (  
    std::istream & is) [override], [virtual]
```

Implements [gdcm::network::BasePDU](#).

10.4.4.15 SetCalledAETitle()

```
void gdcm::network::AAssociateRQPDU::SetCalledAETitle (  
    const char calledaetitle[16])
```

Set the Called AE Title.

10.4.4.16 SetCallingAETitle()

```
void gdcm::network::AAssociateRQPDU::SetCallingAETitle (  
    const char callingaetitle[16])
```

Set the Calling AE Title.

10.4.4.17 SetUserInfo()

```
void gdcm::network::AAssociateRQPDU::SetUserInformation (  
    UserInformation const & ui)
```

10.4.4.18 Size()

```
size_t gdcm::network::AAssociateRQPDU::Size () const [override], [virtual]
```

Implements [gdcm::network::BasePDU](#).

10.4.4.19 Write()

```
const std::ostream & gdcm::network::AAssociateRQPDU::Write (  
    std::ostream & os) const [override], [virtual]
```

Implements [gdcm::network::BasePDU](#).

10.4.5 Friends And Related Symbol Documentation

10.4.5.1 AAssociateACPDU

```
friend class AAssociateACPDU [friend]
```

References [AAssociateACPDU](#).

Referenced by [AAssociateACPDU](#).

The documentation for this class was generated from the following file:

- [gdcmAAssociateRQPDU.h](#)


10.5 gdcm::AbortEvent Class Reference

```
#include <gdcmEvent.h>
```

Inheritance diagram for `gdcm::AbortEvent`:



Collaboration diagram for `gdcm::AbortEvent`:



Additional Inherited Members

Public Member Functions inherited from [gdcm::Event](#)

- [Event](#) ()
- [Event](#) (const [Event](#) &)
- virtual [~Event](#) ()
- virtual bool [CheckEvent](#) (const [Event](#) *) const =0
- virtual const char * [GetEventName](#) () const =0
- virtual [Event](#) * [MakeObject](#) () const =0
- void [operator=](#) (const [Event](#) &)=delete
- virtual void [Print](#) (std::ostream &os) const

The documentation for this class was generated from the following file:

- [gdcmEvent.h](#)

10.6 `gdcm::network::AbstractSyntax` Class Reference

[AbstractSyntax](#).

```
#include <gdcmAbstractSyntax.h>
```

Public Member Functions

- [AbstractSyntax](#) ()
- [DataElement GetAsDataElement](#) () const
- const char * [GetName](#) () const
- bool [operator==](#) (const [AbstractSyntax](#) &as) const
- void [Print](#) (std::ostream &os) const
- std::istream & [Read](#) (std::istream &is)
- void [SetName](#) (const char *name)
- void [SetNameFromUID](#) (UIDs::TSName tsname)
- size_t [Size](#) () const
- const std::ostream & [Write](#) (std::ostream &os) const

10.6.1 Detailed Description

[AbstractSyntax](#).

[Table](#) 9-14 ABSTRACT SYNTAX SUB-ITEM FIELDS

10.6.2 Constructor & Destructor Documentation

10.6.2.1 AbstractSyntax()

```
gdcm::network::AbstractSyntax::AbstractSyntax ()
```

Referenced by [operator==\(\)](#).

10.6.3 Member Function Documentation

10.6.3.1 GetAsDataElement()

```
DataElement gdcm::network::AbstractSyntax::GetAsDataElement () const
```

10.6.3.2 GetName()

```
const char * gdcm::network::AbstractSyntax::GetName () const [inline]
```

10.6.3.3 operator==()

```
bool gdcm::network::AbstractSyntax::operator== (
    const AbstractSyntax & as) const [inline]
```

References [AbstractSyntax\(\)](#).

10.6.3.4 Print()

```
void gdcmm::network::AbstractSyntax::Print (  
    std::ostream & os) const
```

10.6.3.5 Read()

```
std::istream & gdcmm::network::AbstractSyntax::Read (  
    std::istream & is)
```

10.6.3.6 SetName()

```
void gdcmm::network::AbstractSyntax::SetName (  
    const char * name) [inline]
```

10.6.3.7 SetNameFromUID()

```
void gdcmm::network::AbstractSyntax::SetNameFromUID (  
    UIDs::TSName tname)
```

10.6.3.8 Size()

```
size_t gdcmm::network::AbstractSyntax::Size () const
```

10.6.3.9 Write()

```
const std::ostream & gdcmm::network::AbstractSyntax::Write (  
    std::ostream & os) const
```

The documentation for this class was generated from the following file:

- [gdcmmAbstractSyntax.h](#)

10.7 gdcm::AnonymizeEvent Class Reference

[AnonymizeEvent](#).

```
#include <gdcmAnonymizeEvent.h>
```

Inheritance diagram for gdcm::AnonymizeEvent:



Collaboration diagram for gdcm::AnonymizeEvent:



Public Types

- typedef [AnonymizeEvent](#) Self
- typedef [AnyEvent](#) Superclass

Public Member Functions

- [AnonymizeEvent](#) (const [Self](#) &s)
- [AnonymizeEvent](#) ([Tag](#) const &tag=0)
- [~AnonymizeEvent](#) () override=default
- bool [CheckEvent](#) (const [::gdcm::Event](#) *e) const override
- const char * [GetEventName](#) () const override
- [Tag](#) const & [GetTag](#) () const
- [::gdcm::Event](#) * [MakeObject](#) () const override
- void [operator=](#) (const [Self](#) &)=delete
- void [SetTag](#) (const [Tag](#) &t)

Public Member Functions inherited from [gdcm::Event](#)

- [Event](#) ()
- [Event](#) (const [Event](#) &)
- virtual [~Event](#) ()
- virtual bool [CheckEvent](#) (const [Event](#) *) const =0
- void [operator=](#) (const [Event](#) &)=delete
- virtual void [Print](#) (std::ostream &os) const

10.7.1 Detailed Description

[AnonymizeEvent](#).

Special type of event triggered during the Anonymization process

See also

[Anonymizer](#)

Examples

[BasicAnonymizer.cs](#), [Cleaner.cs](#), and [ClinicalTrialIdentificationWorkflow.cs](#).

10.7.2 Member Typedef Documentation

10.7.2.1 Self

```
typedef AnonymizeEvent gdcm::AnonymizeEvent::Self
```

10.7.2.2 Superclass

```
typedef AnyEvent gdcm::AnonymizeEvent::Superclass
```


10.7.3 Constructor & Destructor Documentation

10.7.3.1 AnonymizeEvent() [1/2]

```
gdcm::AnonymizeEvent::AnonymizeEvent (  
    Tag const & tag = 0) [inline]
```

10.7.3.2 ~AnonymizeEvent()

```
gdcm::AnonymizeEvent::~~AnonymizeEvent () [override], [default]
```

10.7.3.3 AnonymizeEvent() [2/2]

```
gdcm::AnonymizeEvent::AnonymizeEvent (  
    const Self & s) [inline]
```

10.7.4 Member Function Documentation

10.7.4.1 CheckEvent()

```
bool gdcm::AnonymizeEvent::CheckEvent (  
    const ::gdcm::Event * e) const [inline], [override]
```

10.7.4.2 GetEventName()

```
const char * gdcm::AnonymizeEvent::GetEventName () const [inline], [override], [virtual]
```

Return the StringName associated with the event.

Implements [gdcm::Event](#).

10.7.4.3 GetTag()

```
Tag const & gdcm::AnonymizeEvent::GetTag () const [inline]
```

Examples

[BasicAnonymizer.cs](#), [Cleaner.cs](#), and [ClinicalTrialIdentificationWorkflow.cs](#).

10.7.4.4 MakeObject()

```
::gdcM::Event * gdcM::AnonymizeEvent::MakeObject () const [inline], [override], [virtual]
```

Create an [Event](#) of this type This method work as a Factory for creating events of each particular type.

Implements [gdcM::Event](#).

10.7.4.5 operator=()

```
void gdcM::AnonymizeEvent::operator= (  
    const Self & ) [delete]
```

10.7.4.6 SetTag()

```
void gdcM::AnonymizeEvent::SetTag (  
    const Tag & t) [inline]
```

The documentation for this class was generated from the following file:

- [gdcMAnonymizeEvent.h](#)

10.8 gdcM::Anonymizer Class Reference

[Anonymizer](#).

```
#include <gdcMAnonymizer.h>
```

Inheritance diagram for gdcM::Anonymizer:



Collaboration diagram for gdcm::Anonymizer:



Public Member Functions

- [Anonymizer](#) ()
- [~Anonymizer](#) () override
- bool [BasicApplicationLevelConfidentialityProfile](#) (bool deidentify=true)
- bool [Clear](#) ([PrivateTag](#) const &pt)
- bool [Clear](#) ([Tag](#) const &t)
 - Identical to 'Empty' except no action is done when tag is not present.*
- bool [Empty](#) ([PrivateTag](#) const &pt)
- bool [Empty](#) ([Tag](#) const &t)
 - Make [Tag](#) t empty (if not found tag will be created)*
- const [CryptographicMessageSyntax](#) * [GetCryptographicMessageSyntax](#) () const
- [File](#) & [GetFile](#) ()
- bool [Remove](#) ([PrivateTag](#) const &pt)
- bool [Remove](#) ([Tag](#) const &t)
 - remove a tag (even a SQ can be removed)*
- bool [RemoveGroupLength](#) ()
 - Main function that loop over all elements and remove group length.*
- bool [RemovePrivateTags](#) ()
 - Main function that loop over all elements and remove private tags.*
- bool [RemoveRetired](#) ()
 - Main function that loop over all elements and remove retired element.*
- bool [Replace](#) ([PrivateTag](#) const &t, const char *value)
- bool [Replace](#) ([PrivateTag](#) const &t, const char *value, [VL](#) const &vl)
- bool [Replace](#) ([Tag](#) const &t, const char *value)
- bool [Replace](#) ([Tag](#) const &t, const char *value, [VL](#) const &vl)
- void [SetCryptographicMessageSyntax](#) ([CryptographicMessageSyntax](#) *cms)
 - Set/Get CMS key that will be used to encrypt the dataset within BasicApplicationLevelConfidentialityProfile.*
- void [SetFile](#) (const [File](#) &f)
 - Set/Get [File](#).*

Public Member Functions inherited from [gdcm::Subject](#)

- [Subject](#) ()
- [~Subject](#) () override
- unsigned long [AddObserver](#) (const [Event](#) &event, [Command](#) *)
- unsigned long [AddObserver](#) (const [Event](#) &event, [Command](#) *) const
- [Command](#) * [GetCommand](#) (unsigned long tag)
- bool [HasObserver](#) (const [Event](#) &event) const
- void [InvokeEvent](#) (const [Event](#) &)
- void [InvokeEvent](#) (const [Event](#) &) const
- void [RemoveAllObservers](#) ()
- void [RemoveObserver](#) (unsigned long tag)

Public Member Functions inherited from [gdcm::Object](#)

- [Object](#) ()
- [Object](#) (const [Object](#) &)
- *Special requirement for copy/cstor, assignment operator.*
- virtual [~Object](#) ()
- void [operator=](#) (const [Object](#) &)
- virtual void [Print](#) (std::ostream &) const

Static Public Member Functions

- static void [ClearInternalUIDs](#) ()
- static std::vector< [Tag](#) > [GetBasicApplicationLevelConfidentialityProfileAttributes](#) ()
- *Return the list of [Tag](#) that will be considered when anonymizing a DICOM file.*
- static [SmartPointer](#)< [Anonymizer](#) > [New](#) ()
- *for wrapped language: instantiate a reference counted object*

Protected Member Functions

- bool [BALCPPProtect](#) ([DataSet](#) &ds, [Tag](#) const &tag, const [IOD](#) &iod)
- bool [CanEmptyTag](#) ([Tag](#) const &tag, const [IOD](#) &iod) const
- void [RecurseDataSet](#) ([DataSet](#) &ds)

Protected Member Functions inherited from [gdcm::Object](#)

- void [Register](#) ()
- void [UnRegister](#) ()

10.8.1 Detailed Description

[Anonymizer](#).

This class is a multi purpose anonymizer. It can work in 2 mode:

- Full (irreversible) anonymizer (aka dumb mode)
- reversible de-identifier/re-identifier (aka smart mode). This implements the Basic Application Level Confidentiality Profile, DICOM PS 3.15-2009

1. dumb mode This is a dumb anonymizer implementation. All it allows user is simple operation such as:

[Tag](#) based functions:

- complete removal of DICOM attribute (Remove)
- make a tag empty, ie make it's length 0 (Empty)
- replace with another string-based value (Replace)

[DataSet](#) based functions:

- Remove all group length attribute from a DICOM dataset (Group Length element are deprecated, DICOM 2008)
- Remove all private attributes
- Remove all retired attributes

All function calls actually execute the user specified request. Previous implementation were calling a general Anonymize function but traversing a `std::set` is $O(n)$ operation, while a simple user specified request is $O(\log(n))$ operation. So 'm' user interaction is $O(m \cdot \log(n))$ which is $< O(n)$ complexity.

1. smart mode this mode implements the Basic Application Level Confidentiality Profile (DICOM PS 3.15-2008) In this case, it is extremely important to use the same [Anonymizer](#) class when anonymizing a [FileSet](#). Once the [Anonymizer](#) is destroyed its memory of known (already processed) [UIDs](#) will be lost. which will make the anonymizer behaves incorrectly for attributes such as [Series](#) [UID](#) [Study](#) [UID](#) where user want some consistency. When attribute is [Type](#) 1 / [Type](#) 1C, a dummy generator will take in the existing value and produce a dummy value (a sha1 representation). sha1 algorithm is considered to be cryptographically strong (compared to md5sum) so that we meet the following two conditions:

- Produce the same dummy value for the same input value
- do not provide an easy way to retrieve the original value from the sha1 generated value

This class implement the Subject/Observer pattern trigger the following event:

- [AnonymizeEvent](#)
- [IterationEvent](#)
- [StartEvent](#)
- [EndEvent](#)

See also

[CryptographicMessageSyntax](#)

Examples

[ClinicalTrialAnnotate.cxx](#), [CreateJPIPDataSet.cxx](#), [EncapsulateFileInRawData.cxx](#), [ManipulateFile.cs](#), and [MpegVideoInfo.cs](#).

10.8.2 Constructor & Destructor Documentation

10.8.2.1 Anonymizer()

```
gdcm::Anonymizer::Anonymizer () [inline]
```

Referenced by [New\(\)](#).

10.8.2.2 ~Anonymizer()

```
gdcm::Anonymizer::~~Anonymizer () [override]
```

10.8.3 Member Function Documentation

10.8.3.1 BALCPPProtect()

```
bool gdcm::Anonymizer::BALCPPProtect (
    DataSet & ds,
    Tag const & tag,
    const IOD & iod) [protected]
```

10.8.3.2 BasicApplicationLevelConfidentialityProfile()

```
bool gdcm::Anonymizer::BasicApplicationLevelConfidentialityProfile (
    bool deidentify = true)
```

PS 3.15 / E.1.1 De-Identifier An Application may claim conformance to the Basic Application Level Confidentiality Profile as a deidentifier if it protects all Attributes that might be used by unauthorized entities to identify the patient. NOT THREAD SAFE

Examples

[BasicAnonymizer.cs](#).

10.8.3.3 CanEmptyTag()

```
bool gdcm::Anonymizer::CanEmptyTag (
    Tag const & tag,
    const IOD & iod) const [protected]
```

10.8.3.4 Clear() [1/2]

```
bool gdcm::Anonymizer::Clear (
    PrivateTag const & pt)
```

10.8.3.5 Clear() [2/2]

```
bool gdcm::Anonymizer::Clear (
    Tag const & t)
```

Identical to 'Empty' except no action is done when tag is not present.

10.8.3.6 ClearInternalUIDs()

```
void gdcm::Anonymizer::ClearInternalUIDs () [static]
```

Clear the internal mapping of real [UIDs](#) to generated [UIDs](#)

Warning

the mapping is definitely lost

10.8.3.7 Empty() [1/2]

```
bool gdcm::Anonymizer::Empty (
    PrivateTag const & pt)
```

Make [PrivateTag](#) pt empty (if not found tag will be created) Pay special attention that this code must be done before any call to Empty/Remove of the associated Private Creator, but before any call to Replace.

10.8.3.8 Empty() [2/2]

```
bool gdcm::Anonymizer::Empty (
    Tag const & t)
```

Make [Tag](#) t empty (if not found tag will be created)

Examples

[CreateJPIPDataSet.cxx](#).

10.8.3.9 GetBasicApplicationLevelConfidentialityProfileAttributes()

```
std::vector< Tag > gdcm::Anonymizer::GetBasicApplicationLevelConfidentialityProfileAttributes ()
[static]
```

Return the list of [Tag](#) that will be considered when anonymizing a DICOM file.

Examples

[GenFakeIdentifyFile.cxx](#), and [TraverseModules.cxx](#).

10.8.3.10 GetCryptographicMessageSyntax()

```
const CryptographicMessageSyntax * gdcM::Anonymizer::GetCryptographicMessageSyntax () const
```

10.8.3.11 GetFile()

```
File & gdcM::Anonymizer::GetFile () [inline]
```

Examples

[BasicAnonymizer.cs](#), and [ManipulateFile.cs](#).

10.8.3.12 New()

```
SmartPointer< Anonymizer > gdcM::Anonymizer::New () [inline], [static]
```

for wrapped language: instantiate a reference counted object

References [Anonymizer\(\)](#).

10.8.3.13 RecurseDataSet()

```
void gdcM::Anonymizer::RecurseDataSet (  
    DataSet & ds) [protected]
```

10.8.3.14 Remove() [1/2]

```
bool gdcM::Anonymizer::Remove (  
    PrivateTag const & pt)
```

remove a private tag (even a SQ can be removed) Pay special attention that this code must be done before any call to Empty/Remove of the associated Private Creator, but before any call to Replace. When the private reservation becomes empty, no check is done to automatically remove the private creator

10.8.3.15 Remove() [2/2]

```
bool gdcM::Anonymizer::Remove (  
    Tag const & t)
```

remove a tag (even a SQ can be removed)

10.8.3.16 RemoveGroupLength()

```
bool gdcm::Anonymizer::RemoveGroupLength ()
```

Main function that loop over all elements and remove group length.

Examples

[ClinicalTrialAnnotate.cxx](#), and [ManipulateFile.cs](#).

10.8.3.17 RemovePrivateTags()

```
bool gdcm::Anonymizer::RemovePrivateTags ()
```

Main function that loop over all elements and remove private tags.

Examples

[ClinicalTrialAnnotate.cxx](#), and [ManipulateFile.cs](#).

10.8.3.18 RemoveRetired()

```
bool gdcm::Anonymizer::RemoveRetired ()
```

Main function that loop over all elements and remove retired element.

10.8.3.19 Replace() [1/4]

```
bool gdcm::Anonymizer::Replace (  
    PrivateTag const & t,  
    const char * value)
```

10.8.3.20 Replace() [2/4]

```
bool gdcm::Anonymizer::Replace (  
    PrivateTag const & t,  
    const char * value,  
    VL const & vl)
```

10.8.3.21 Replace() [3/4]

```
bool gdcM::Anonymizer::Replace (
    Tag const & t,
    const char * value)
```

Replace tag with another value, if tag is not found it will be created: WARNING: this function can only execute if tag is a VRASCI

Examples

[ClinicalTrialAnnotate.cxx](#), [CreateJPIPDataSet.cxx](#), [EncapsulateFileInRawData.cxx](#), [ManipulateFile.cs](#), and [MpegVideoInfo.cs](#).

10.8.3.22 Replace() [4/4]

```
bool gdcM::Anonymizer::Replace (
    Tag const & t,
    const char * value,
    VL const & vl)
```

when the value contains \0, it is a good idea to specify the length. This function is required when dealing with VRBINARY tag

10.8.3.23 SetCryptographicMessageSyntax()

```
void gdcM::Anonymizer::SetCryptographicMessageSyntax (
    CryptographicMessageSyntax * cms)
```

Set/Get CMS key that will be used to encrypt the dataset within BasicApplicationLevelConfidentialityProfile.

Examples

[BasicAnonymizer.cs](#), and [ClinicalTrialIdentificationWorkflow.cs](#).

10.8.3.24 SetFile()

```
void gdcM::Anonymizer::SetFile (
    const File & f) [inline]
```

Set/Get [File](#).

Examples

[BasicAnonymizer.cs](#), [ClinicalTrialAnnotate.cxx](#), [CreateJPIPDataSet.cxx](#), [EncapsulateFileInRawData.cxx](#), [ManipulateFile.cs](#), and [MpegVideoInfo.cs](#).

The documentation for this class was generated from the following file:

- [gdcMAnonymizer.h](#)

10.9 gdcm::AnyEvent Class Reference

```
#include <gdcmEvent.h>
```

Inheritance diagram for gdcm::AnyEvent:



Collaboration diagram for `gdcm::AnyEvent`:



Additional Inherited Members

Public Member Functions inherited from [gdcm::Event](#)

- [Event](#) ()
- [Event](#) (const [Event](#) &)
- virtual [~Event](#) ()
- virtual bool [CheckEvent](#) (const [Event](#) *) const =0
- virtual const char * [GetEventName](#) () const =0
- virtual [Event](#) * [MakeObject](#) () const =0
- void [operator=](#) (const [Event](#) &)=delete
- virtual void [Print](#) (std::ostream &os) const

The documentation for this class was generated from the following file:

- [gdcmEvent.h](#)

10.10 `gdcm::network::ApplicationContext` Class Reference

[ApplicationContext](#).

```
#include <gdcmApplicationContext.h>
```

Public Member Functions

- [ApplicationContext](#) ()
- const char * [GetName](#) () const
- void [Print](#) (std::ostream &os) const
- std::istream & [Read](#) (std::istream &is)
- void [SetName](#) (const char *name)
- size_t [Size](#) () const
- const std::ostream & [Write](#) (std::ostream &os) const

10.10.1 Detailed Description

[ApplicationContext](#).

[Table 9-12 APPLICATION CONTEXT ITEM FIELDS](#)

Todo Looks like Application Context can only be 64 bytes at max (see Figure 9-1 / PS 3.8 - 2009)

10.10.2 Constructor & Destructor Documentation

10.10.2.1 ApplicationContext()

```
gdcm::network::ApplicationContext::ApplicationContext ()
```

10.10.3 Member Function Documentation

10.10.3.1 GetName()

```
const char * gdcm::network::ApplicationContext::GetName () const [inline]
```

10.10.3.2 Print()

```
void gdcm::network::ApplicationContext::Print (  
    std::ostream & os) const
```

10.10.3.3 Read()

```
std::istream & gdcm::network::ApplicationContext::Read (  
    std::istream & is)
```

10.10.3.4 SetName()

```
void gdcm::network::ApplicationContext::SetName (  
    const char * name) [inline]
```

10.10.3.5 Size()

```
size_t gdcm::network::ApplicationContext::Size () const
```

10.10.3.6 Write()

```
const std::ostream & gdcn::network::ApplicationContext::Write (  
    std::ostream & os) const
```

The documentation for this class was generated from the following file:


- [gdcnApplicationContext.h](#)

10.11 gdcn::ApplicationEntity Class Reference

[ApplicationEntity](#).

```
#include <gdcnApplicationEntity.h>
```

Collaboration diagram for gdcn::ApplicationEntity:



Public Member Functions

- bool [IsValid](#) () const
- void [Print](#) (std::ostream &os) const
- void [SetBlob](#) (const std::vector< char > &v)
- void [Squeeze](#) ()

Public Attributes

- std::string [Internal](#)

Static Public Attributes

- static const unsigned int [MaxLength](#) = 16
- static const unsigned int [MaxNumberOfComponents](#) = 1
- static const char [Padding](#) = ''
- static const char [Separator](#) = ''

10.11.1 Detailed Description

[ApplicationEntity](#).

- AE Application Entity
- A string of characters that identifies an Application Entity with leading and trailing spaces (20H) being non-significant. A value consisting solely of spaces shall not be used.
- Default Character Repertoire excluding character code 5CH (the BACKSLASH \ in ISO-IR 6), and control characters LF, FF, CR and ESC.
- 16 bytes maximum

10.11.2 Member Function Documentation

10.11.2.1 IsValid()

```
bool gdcm::ApplicationEntity::IsValid () const [inline]
```

10.11.2.2 Print()

```
void gdcm::ApplicationEntity::Print (  
    std::ostream & os) const [inline]
```

References [gdcm_assert](#).

10.11.2.3 SetBlob()

```
void gdcm::ApplicationEntity::SetBlob (  
    const std::vector< char > & v) [inline]
```

References [gdcm_assert](#).

10.11.2.4 Squeeze()

```
void gdcm::ApplicationEntity::Squeeze () [inline]
```

10.11.3 Member Data Documentation

10.11.3.1 Internal

```
std::string gdcM::ApplicationEntity::Internal
```

10.11.3.2 MaxLength

```
const unsigned int gdcM::ApplicationEntity::MaxLength = 16 [static]
```

10.11.3.3 MaxNumberOfComponents

```
const unsigned int gdcM::ApplicationEntity::MaxNumberOfComponents = 1 [static]
```

10.11.3.4 Padding

```
const char gdcM::ApplicationEntity::Padding = ' ' [static]
```

10.11.3.5 Separator

```
const char gdcM::ApplicationEntity::Separator = ' ' [static]
```

The documentation for this class was generated from the following file:

- [gdcMApplicationEntity.h](#)

10.12 gdcM::network::AReleaseRPPDU Class Reference


[AReleaseRPPDU](#).

```
#include <gdcMAReleaseRPPDU.h>
```

Inheritance diagram for gdcM::network::AReleaseRPPDU:



Collaboration diagram for gdcmm::network::AReleaseRPPDU:



Public Member Functions

- [AReleaseRPPDU](#) ()
- bool [IsLastFragment](#) () const override
- void [Print](#) (std::ostream &os) const override
- std::istream & [Read](#) (std::istream &is) override
- size_t [Size](#) () const override
- const std::ostream & [Write](#) (std::ostream &os) const override

Public Member Functions inherited from [gdcmm::network::BasePDU](#)

- virtual [~BasePDU](#) ()=default

10.12.1 Detailed Description

[AReleaseRPPDU](#).

[Table 9-25](#) A-RELEASE-RP PDU fields

10.12.2 Constructor & Destructor Documentation

10.12.2.1 AReleaseRPPDU()

```
gdcmm::network::AReleaseRPPDU::AReleaseRPPDU ()
```

10.12.3 Member Function Documentation

10.12.3.1 IsLastFragment()

```
bool gdcmm::network::AReleaseRPPDU::IsLastFragment () const [inline], [override], [virtual]
```

Implements [gdcmm::network::BasePDU](#).

10.12.3.2 Print()

```
void gdcn::network::AReleaseRPPDU::Print (  
    std::ostream & os) const [override], [virtual]
```

Implements [gdcn::network::BasePDU](#).

10.12.3.3 Read()

```
std::istream & gdcn::network::AReleaseRPPDU::Read (  
    std::istream & is) [override], [virtual]
```

Implements [gdcn::network::BasePDU](#).

10.12.3.4 Size()

```
size_t gdcn::network::AReleaseRPPDU::Size () const [override], [virtual]
```

Implements [gdcn::network::BasePDU](#).

10.12.3.5 Write()

```
const std::ostream & gdcn::network::AReleaseRPPDU::Write (  
    std::ostream & os) const [override], [virtual]
```

Implements [gdcn::network::BasePDU](#).

The documentation for this class was generated from the following file:


- [gdcnAReleaseRPPDU.h](#)

10.13 gdcn::network::AReleaseRQPDU Class Reference


[AReleaseRQPDU](#).

```
#include <gdcnAReleaseRQPDU.h>
```

Inheritance diagram for gdcm::network::AReleaseRQPDU:



Collaboration diagram for gdcm::network::AReleaseRQPDU:



Public Member Functions

- [AReleaseRQPDU](#) ()
- bool [IsLastFragment](#) () const override
- void [Print](#) (std::ostream &os) const override
- std::istream & [Read](#) (std::istream &is) override
- size_t [Size](#) () const override
- const std::ostream & [Write](#) (std::ostream &os) const override

Public Member Functions inherited from [gdcm::network::BasePDU](#)

- virtual [~BasePDU](#) ()=default

10.13.1 Detailed Description

[AReleaseRQPDU](#).

[Table 9-24 A-RELEASE-RQ PDU FIELDS](#)

10.13.2 Constructor & Destructor Documentation

10.13.2.1 AReleaseRQPDU()

```
gdcmm::network::AReleaseRQPDU::AReleaseRQPDU ()
```

10.13.3 Member Function Documentation

10.13.3.1 IsLastFragment()

```
bool gdcmm::network::AReleaseRQPDU::IsLastFragment () const [inline], [override], [virtual]
```

Implements [gdcmm::network::BasePDU](#).

10.13.3.2 Print()

```
void gdcmm::network::AReleaseRQPDU::Print (  
    std::ostream & os) const [override], [virtual]
```

Implements [gdcmm::network::BasePDU](#).

10.13.3.3 Read()

```
std::istream & gdcmm::network::AReleaseRQPDU::Read (  
    std::istream & is) [override], [virtual]
```

Implements [gdcmm::network::BasePDU](#).

10.13.3.4 Size()

```
size_t gdcmm::network::AReleaseRQPDU::Size () const [override], [virtual]
```

Implements [gdcmm::network::BasePDU](#).

10.13.3.5 Write()

```
const std::ostream & gdcmm::network::AReleaseRQPDU::Write (  
    std::ostream & os) const [override], [virtual]
```

Implements [gdcmm::network::BasePDU](#).

The documentation for this class was generated from the following file:

- [gdcmmAReleaseRQPDU.h](#)

10.14 gdcm::network::ARTIMTimer Class Reference

[ARTIMTimer](#).

```
#include <gdcmARTIMTimer.h>
```

Public Member Functions

- [ARTIMTimer](#) ()
- double [GetElapsedTime](#) () const
- bool [GetHasExpired](#) () const
- double [GetTimeout](#) () const
- void [SetTimeout](#) (double inTimeout)
- void [Start](#) ()
- void [Stop](#) ()

10.14.1 Detailed Description

[ARTIMTimer](#).

This file contains the code for the ARTIM timer.

Basically, the ARTIM timer will just get the wall time when it's started, and then can be queried for the current time, and then can be stopped (ie, the start time reset).

Because we're trying to do this without threading, we should be able to 'start' the ARTIM timer by this mechanism, and then when waiting for a particular response, tight loop that with sleep calls and determinations of when the ARTIM timer has reached its peak. As such, this isn't a strict 'timer' in the traditional sense of the word, but more of a time keeper.

There can be only one ARTIM timer per connection.

10.14.2 Constructor & Destructor Documentation

10.14.2.1 ARTIMTimer()

```
gdcm::network::ARTIMTimer::ARTIMTimer ()
```

10.14.3 Member Function Documentation

10.14.3.1 GetElapsedTime()

```
double gdcm::network::ARTIMTimer::GetElapsedTime () const
```

10.14.3.2 GetHasExpired()

```
bool gdcmm::network::ARTIMTimer::GetHasExpired () const
```

10.14.3.3 GetTimeout()

```
double gdcmm::network::ARTIMTimer::GetTimeout () const
```

10.14.3.4 SetTimeout()

```
void gdcmm::network::ARTIMTimer::SetTimeout (
    double inTimeout)
```

10.14.3.5 Start()

```
void gdcmm::network::ARTIMTimer::Start ()
```

10.14.3.6 Stop()

```
void gdcmm::network::ARTIMTimer::Stop ()
```

The documentation for this class was generated from the following file:

- [gdcmmARTIMTimer.h](#)

10.15 gdcmm::ASN1 Class Reference

Class for [ASN1](#).

```
#include <gdcmmASN1.h>
```

Public Member Functions

- [ASN1](#) ()
- [ASN1](#) (const [ASN1](#) &)=delete
- [~ASN1](#) ()
- void [operator=](#) (const [ASN1](#) &)=delete

Static Public Member Functions

- static bool [ParseDump](#) (const char *array, size_t length)
- static bool [ParseDumpFile](#) (const char *filename)

Protected Member Functions

- int [TestPBKDF2](#) ()

10.15.1 Detailed Description

Class for [ASN1](#).

10.15.2 Constructor & Destructor Documentation

10.15.2.1 [ASN1\(\)](#) [1/2]

```
gdcmm::ASN1::ASN1 ()
```

Referenced by [ASN1\(\)](#), and [operator=\(\)](#).

10.15.2.2 [~ASN1\(\)](#)

```
gdcmm::ASN1::~~ASN1 ()
```

10.15.2.3 [ASN1\(\)](#) [2/2]

```
gdcmm::ASN1::ASN1 (  
    const ASN1 & ) [delete]
```

References [ASN1\(\)](#).

10.15.3 Member Function Documentation

10.15.3.1 [operator=\(\)](#)

```
void gdcmm::ASN1::operator= (  
    const ASN1 & ) [delete]
```

References [ASN1\(\)](#).

10.15.3.2 [ParseDump\(\)](#)

```
bool gdcmm::ASN1::ParseDump (  
    const char * array,  
    size_t length) [static]
```

10.15.3.3 ParseDumpFile()

```
bool gdcmm::ASN1::ParseDumpFile (  
    const char * filename) [static]
```

10.15.3.4 TestPBKDF2()

```
int gdcmm::ASN1::TestPBKDF2 () [protected]
```

The documentation for this class was generated from the following file:

- [gdcmmASN1.h](#)

10.16 gdcmm::network::AsynchronousOperationsWindowSub Class Reference

[AsynchronousOperationsWindowSub.](#)

```
#include <gdcmmAsynchronousOperationsWindowSub.h>
```

Public Member Functions

- [AsynchronousOperationsWindowSub](#) ()
- void [Print](#) (std::ostream &os) const
- std::istream & [Read](#) (std::istream &is)
- size_t [Size](#) () const
- const std::ostream & [Write](#) (std::ostream &os) const

10.16.1 Detailed Description

[AsynchronousOperationsWindowSub.](#)

PS 3.7 [Table](#) D.3-7 ASYNCHRONOUS OPERATIONS WINDOW SUB-ITEM FIELDS (A-ASSOCIATE-RQ)

10.16.2 Constructor & Destructor Documentation

10.16.2.1 AsynchronousOperationsWindowSub()

```
gdcmm::network::AsynchronousOperationsWindowSub::AsynchronousOperationsWindowSub ()
```


10.16.3 Member Function Documentation

10.16.3.1 Print()

```
void gdcmm::network::AsynchronousOperationsWindowSub::Print (
    std::ostream & os) const
```

10.16.3.2 Read()

```
std::istream & gdcmm::network::AsynchronousOperationsWindowSub::Read (
    std::istream & is)
```

10.16.3.3 Size()

```
size_t gdcmm::network::AsynchronousOperationsWindowSub::Size () const
```

10.16.3.4 Write()

```
const std::ostream & gdcmm::network::AsynchronousOperationsWindowSub::Write (
    std::ostream & os) const
```

The documentation for this class was generated from the following file:


- [gdcmmAsynchronousOperationsWindowSub.h](#)

10.17 gdcmm::Attribute< Group, Element, TVR, TVM > Class Template Reference


[Attribute](#) class This class use template metaprograming tricks to let the user know when the template instantiation does not match the public dictionary.

```
#include <gdcmmAttribute.h>
```

Inheritance diagram for gdcmm::Attribute< Group, Element, TVR, TVM >:



Collaboration diagram for `gdcm::Attribute< Group, Element, TVR, TVM >`:



Public Types

- enum { `VMType` = `VMToLength<TVM>::Length` }
- typedef `VRTToType< TVR >::Type` `ArrayType`

Public Member Functions

- `GDCM_STATIC_ASSERT` (((((VR::VRTType) TVR & VR::VR_VM1) && ((VM::VMType) TVM == VM::VM1)) || !((VR::VRTType) TVR & VR::VR_VM1)))
- `GDCM_STATIC_ASSERT` (((VM::VMType) TVM & (VM::VMType)(TagToType< Group, Element >::VMType)))
- `GDCM_STATIC_ASSERT` (((VR::VRTType) TVR & (VR::VRTType)(TagToType< Group, Element >::VRTType)))
- `DataElement` `GetAsDataElement` () const
- unsigned int `GetNumberOfValues` () const
- `ArrayType` & `GetValue` (unsigned int idx=0)
- `ArrayType` const & `GetValue` (unsigned int idx=0) const
- const `ArrayType` * `GetValues` () const
- bool `operator!=` (const `Attribute` &att) const
- bool `operator<` (const `Attribute` &att) const
- bool `operator==` (const `Attribute` &att) const
- `ArrayType` & `operator[]` (unsigned int idx)
- `ArrayType` const & `operator[]` (unsigned int idx) const
- void `Print` (std::ostream &os) const
- void `Set` (`DataSet` const &ds)
- void `SetFromDataElement` (`DataElement` const &de)
- void `SetFromDataSet` (`DataSet` const &ds)
- void `SetValue` (`ArrayType` v, unsigned int idx=0)
- void `SetValues` (const `ArrayType` *array, unsigned int numel=`VMType`)

Static Public Member Functions

- static [VM GetDictVM](#) ()
- static [VR GetDictVR](#) ()
- static [Tag GetTag](#) ()
- static [VM GetVM](#) ()
- static [VR GetVR](#) ()

Public Attributes

- [ArrayType Internal](#) [[VMToLength](#)< TVM >::Length]

Protected Member Functions

- void [SetByteValue](#) (const [ByteValue](#) *bv)
- void [SetByteValueNoSwap](#) (const [ByteValue](#) *bv)

10.17.1 Detailed Description

template<uint16_t Group, uint16_t Element, long long TVR = TagToType<Group, Element>::VRType, int TVM = TagToType<Group, Element>::VMType>
class gdcm::Attribute< Group, Element, TVR, TVM >

[Attribute](#) class This class use template metaprograming tricks to let the user know when the template instantiation does not match the public dictionary.

Typical example that compile is: [Attribute<0x0008,0x9007>](#) a = {"ORIGINAL","PRIMARY","T1","NONE"};

Examples that will NOT compile are:

[Attribute<0x0018,0x1182, VR::IS, VM::VM1>](#) fd1 = {}; // not enough parameters [Attribute<0x0018,0x1182, VR::IS, VM::VM2>](#)
 fd2 = {0,1,2}; // too many initializers [Attribute<0x0018,0x1182, VR::IS, VM::VM3>](#) fd3 = {0,1,2}; // VM3 is not valid
[Attribute<0x0018,0x1182, VR::UL, VM::VM2>](#) fd3 = {0,1}; // UL is not valid [VR](#)

Examples

[CreateFakeRTDOSE.cxx](#), [CreateJPIPDataSet.cxx](#), [DeriveSeries.cxx](#), [Extracting_All_Resolution.cxx](#), [Fake_Image_Using_Stream_In](#)
[FixOrientation.cxx](#), [GenFakeIdentifyFile.cxx](#), [GetSequenceUltrasound.cxx](#), [HelloWorld.cxx](#), [LargeVRDSExplicit.cxx](#),
[PatchFile.cxx](#), [ReadAndDumpDICOMDIR2.cxx](#), [ReadAndPrintAttributes.cxx](#), [SortImage.cxx](#), [StreamImageReaderTest.cxx](#),
[VolumeSorter.cxx](#), [gdcmrtionplan.cxx](#), [gdcmrtplan.cxx](#), [pmsct_rgb1.cxx](#), and [rle2img.cxx](#).

10.17.2 Member Typedef Documentation

10.17.2.1 ArrayType

```
template<uint16_t Group, uint16_t Element, long long TVR = TagToType<Group, Element>::VRType, int
TVM = TagToType<Group, Element>::VMType>
typedef VRToType<TVR>::Type gdcm::Attribute< Group, Element, TVR, TVM >::ArrayType
```

Examples

[ReadAndPrintAttributes.cxx](#).

10.17.3 Member Enumeration Documentation

10.17.3.1 anonymous enum

```
template<uint16_t Group, uint16_t Element, long long TVR = TagToType<Group, Element>::VRType, int
TVM = TagToType<Group, Element>::VMType>
anonymous enum
```

Enumerator

VMType	
--------	--

10.17.4 Member Function Documentation

10.17.4.1 GDCM_STATIC_ASSERT() [1/3]

```
template<uint16_t Group, uint16_t Element, long long TVR = TagToType<Group, Element>::VRType, int
TVM = TagToType<Group, Element>::VMType>
gdcmm::Attribute< Group, Element, TVR, TVM >::GDCM_STATIC_ASSERT (
    (((VR::VRType) TVR & VR::VR_VM1) && ((VM::VMType) TVM==VM::VM1)) || !((VR::VRType) TVR
& VR::VR_VM1)) )
```

References [gdcmm::VM::VM1](#), and [gdcmm::VR::VR_VM1](#).

10.17.4.2 GDCM_STATIC_ASSERT() [2/3]

```
template<uint16_t Group, uint16_t Element, long long TVR = TagToType<Group, Element>::VRType, int
TVM = TagToType<Group, Element>::VMType>
gdcmm::Attribute< Group, Element, TVR, TVM >::GDCM_STATIC_ASSERT (
    ((VM::VMType) TVM & (VM::VMType) (TagToType< Group, Element >::VMType)) )
```

10.17.4.3 GDCM_STATIC_ASSERT() [3/3]

```
template<uint16_t Group, uint16_t Element, long long TVR = TagToType<Group, Element>::VRType, int
TVM = TagToType<Group, Element>::VMType>
gdcmm::Attribute< Group, Element, TVR, TVM >::GDCM_STATIC_ASSERT (
    ((VR::VRType) TVR & (VR::VRType) (TagToType< Group, Element >::VRType)) )
```

10.17.4.4 GetAsDataElement()

```
template<uint16_t Group, uint16_t Element, long long TVR = TagToType<Group, Element>::VRType, int
TVM = TagToType<Group, Element>::VMType>
DataElement gdcm::Attribute< Group, Element, TVR, TVM >::GetAsDataElement () const [inline]
```

Examples

[CreateFakeRTDOSE.cxx](#), [CreateJPIPDataSet.cxx](#), [Extracting_All_Resolution.cxx](#), [Fake_Image_Using_Stream_Image_Writer.cxx](#), [FixOrientation.cxx](#), [GenFakeIdentifyFile.cxx](#), [HelloWorld.cxx](#), [LargeVRDSExplicit.cxx](#), [PatchFile.cxx](#), and [StreamImageReaderTest.cxx](#).

References [gdcm_assert](#), [GetNumberOfValues\(\)](#), [GetTag\(\)](#), [GetVR\(\)](#), [gdcm::DataElement::GetVR\(\)](#), [Internal](#), [gdcm::DataElement::SetByteValue\(\)](#), [gdcm::DataElement::SetVR\(\)](#), [gdcm::VR::SQ](#), [gdcm::VR::UI](#), and [gdcm::VR::VRASCII](#).

10.17.4.5 GetDictVM()

```
template<uint16_t Group, uint16_t Element, long long TVR = TagToType<Group, Element>::VRType, int
TVM = TagToType<Group, Element>::VMType>
VM gdcm::Attribute< Group, Element, TVR, TVM >::GetDictVM () [inline], [static]
```

10.17.4.6 GetDictVR()

```
template<uint16_t Group, uint16_t Element, long long TVR = TagToType<Group, Element>::VRType, int
TVM = TagToType<Group, Element>::VMType>
VR gdcm::Attribute< Group, Element, TVR, TVM >::GetDictVR () [inline], [static]
```

10.17.4.7 GetNumberOfValues()

```
template<uint16_t Group, uint16_t Element, long long TVR = TagToType<Group, Element>::VRType, int
TVM = TagToType<Group, Element>::VMType>
unsigned int gdcm::Attribute< Group, Element, TVR, TVM >::GetNumberOfValues () const [inline]
```

Examples

[LargeVRDSExplicit.cxx](#).

Referenced by [GetAsDataElement\(\)](#), [GetValue\(\)](#), [GetValue\(\)](#), [operator!=\(\)](#), [operator<\(\)](#), [gdcm::Attribute< Group, Element, TVR, VM::VMType>::operator==\(\)](#), [Print\(\)](#), [SetByteValue\(\)](#), [SetByteValueNoSwap\(\)](#), [SetValue\(\)](#), and [SetValues\(\)](#).

10.17.4.8 GetTag()

```
template<uint16_t Group, uint16_t Element, long long TVR = TagToType<Group, Element>::VRType, int
TVM = TagToType<Group, Element>::VMType>
Tag gdcmm::Attribute< Group, Element, TVR, TVM >::GetTag () [inline], [static]
```

Examples

[PatchFile.cxx](#), [ReadAndPrintAttributes.cxx](#), [gdcmmrtionplan.cxx](#), and [gdcmmrtplan.cxx](#).

Referenced by [GetAsDataElement\(\)](#), and [Print\(\)](#).

10.17.4.9 GetValue() [1/2]

```
template<uint16_t Group, uint16_t Element, long long TVR = TagToType<Group, Element>::VRType, int
TVM = TagToType<Group, Element>::VMType>
ArrayType & gdcmm::Attribute< Group, Element, TVR, TVM >::GetValue (
    unsigned int idx = 0) [inline]
```

Examples

[DeriveSeries.cxx](#), [FixOrientation.cxx](#), [GetSequenceUltrasound.cxx](#), [PatchFile.cxx](#), [ReadAndDumpDICOMDIR2.cxx](#),
[ReadAndPrintAttributes.cxx](#), [gdcmmrtionplan.cxx](#), [gdcmmrtplan.cxx](#), [pmsct_rgb1.cxx](#), and [rle2img.cxx](#).

References [gdcmm_assert](#), [GetNumberOfValues\(\)](#), and [Internal](#).

Referenced by [operator\[\]\(\)](#), and [operator\[\]\(\)](#).

10.17.4.10 GetValue() [2/2]

```
template<uint16_t Group, uint16_t Element, long long TVR = TagToType<Group, Element>::VRType, int
TVM = TagToType<Group, Element>::VMType>
ArrayType const & gdcmm::Attribute< Group, Element, TVR, TVM >::GetValue (
    unsigned int idx = 0) const [inline]
```

References [gdcmm_assert](#), [GetNumberOfValues\(\)](#), and [Internal](#).

10.17.4.11 GetValues()

```
template<uint16_t Group, uint16_t Element, long long TVR = TagToType<Group, Element>::VRType, int
TVM = TagToType<Group, Element>::VMType>
const ArrayType * gdcmm::Attribute< Group, Element, TVR, TVM >::GetValues () const [inline]
```

Examples

[FixOrientation.cxx](#), [LargeVRDSExplicit.cxx](#), [gdcmmrtionplan.cxx](#), and [gdcmmrtplan.cxx](#).

References [Internal](#).

Referenced by [operator!=\(\)](#), [gdcmm::Attribute< Group, Element, TVR, VM::VM1 >::operator!=\(\)](#), [operator<\(\)](#), [gdcmm::Attribute< Group, Element, TVR, VM::VM1 >::operator<\(\)](#), [operator==\(\)](#), and [gdcmm::Attribute< Group, Element, TVR, VM::VM1 >::operator==\(\)](#).

10.17.4.12 GetVM()

```
template<uint16_t Group, uint16_t Element, long long TVR = TagToType<Group, Element>::VRType, int
TVM = TagToType<Group, Element>::VMType>
VM gdcm::Attribute< Group, Element, TVR, TVM >::GetVM () [inline], [static]
```

10.17.4.13 GetVR()

```
template<uint16_t Group, uint16_t Element, long long TVR = TagToType<Group, Element>::VRType, int
TVM = TagToType<Group, Element>::VMType>
VR gdcm::Attribute< Group, Element, TVR, TVM >::GetVR () [inline], [static]
```

Examples

[LargeVRDSExplicit.cxx](#).

Referenced by [GetAsDataElement\(\)](#), and [SetFromDataElement\(\)](#).

10.17.4.14 operator"!="()

```
template<uint16_t Group, uint16_t Element, long long TVR = TagToType<Group, Element>::VRType, int
TVM = TagToType<Group, Element>::VMType>
bool gdcm::Attribute< Group, Element, TVR, TVM >::operator!= (
    const Attribute< Group, Element, TVR, TVM > & att) const [inline]
```

References [GetNumberOfValues\(\)](#), [GetValues\(\)](#), and [Internal](#).

10.17.4.15 operator<()

```
template<uint16_t Group, uint16_t Element, long long TVR = TagToType<Group, Element>::VRType, int
TVM = TagToType<Group, Element>::VMType>
bool gdcm::Attribute< Group, Element, TVR, TVM >::operator< (
    const Attribute< Group, Element, TVR, TVM > & att) const [inline]
```

References [GetNumberOfValues\(\)](#), [GetValues\(\)](#), and [Internal](#).

10.17.4.16 operator==(())

```
template<uint16_t Group, uint16_t Element, long long TVR = TagToType<Group, Element>::VRType, int
TVM = TagToType<Group, Element>::VMType>
bool gdcm::Attribute< Group, Element, TVR, TVM >::operator==(
    const Attribute< Group, Element, TVR, TVM > & att) const [inline]
```

References [GetNumberOfValues\(\)](#), [GetValues\(\)](#), and [Internal](#).

10.17.4.17 operator[]() [1/2]

```
template<uint16_t Group, uint16_t Element, long long TVR = TagToType<Group, Element>::VRType, int
TVM = TagToType<Group, Element>::VMType>
ArrayType & gdcm::Attribute< Group, Element, TVR, TVM >::operator[] (
    unsigned int idx) [inline]
```

References [GetValue\(\)](#).

10.17.4.18 operator[]() [2/2]

```
template<uint16_t Group, uint16_t Element, long long TVR = TagToType<Group, Element>::VRType, int
TVM = TagToType<Group, Element>::VMType>
ArrayType const & gdcm::Attribute< Group, Element, TVR, TVM >::operator[] (
    unsigned int idx) const [inline]
```

References [GetValue\(\)](#).

10.17.4.19 Print()

```
template<uint16_t Group, uint16_t Element, long long TVR = TagToType<Group, Element>::VRType, int
TVM = TagToType<Group, Element>::VMType>
void gdcm::Attribute< Group, Element, TVR, TVM >::Print (
    std::ostream & os) const [inline]
```

References [GetNumberOfValues\(\)](#), [GetTag\(\)](#), and [Internal](#).

10.17.4.20 Set()

```
template<uint16_t Group, uint16_t Element, long long TVR = TagToType<Group, Element>::VRType, int
TVM = TagToType<Group, Element>::VMType>
void gdcm::Attribute< Group, Element, TVR, TVM >::Set (
    DataSet const & ds) [inline]
```

Examples

[LargeVRDSExplicit.cxx](#), [SortImage.cxx](#), and [VolumeSorter.cxx](#).

References [gdcm::DataSet::GetDataElement\(\)](#), and [SetFromDataElement\(\)](#).

10.17.4.21 SetByteValue()

```
template<uint16_t Group, uint16_t Element, long long TVR = TagToType<Group, Element>::VRType, int
TVM = TagToType<Group, Element>::VMType>
void gdcm::Attribute< Group, Element, TVR, TVM >::SetByteValue (
    const ByteValue * bv) [inline], [protected]
```

References [gdcm_assert](#), [gdcm::ByteValue::GetLength\(\)](#), [GetNumberOfValues\(\)](#), [gdcm::ByteValue::GetPointer\(\)](#), and [Internal](#).

Referenced by [SetFromDataElement\(\)](#).

10.17.4.22 SetByteValueNoSwap()

```
template<uint16_t Group, uint16_t Element, long long TVR = TagToType<Group, Element>::VRType, int
TVM = TagToType<Group, Element>::VMType>
void gdcm::Attribute< Group, Element, TVR, TVM >::SetByteValueNoSwap (
    const ByteValue * bv) [inline], [protected]
```

References [gdcm_assert](#), [gdcm::ByteValue::GetLength\(\)](#), [GetNumberOfValues\(\)](#), [gdcm::ByteValue::GetPointer\(\)](#), and [Internal](#).

Referenced by [SetFromDataElement\(\)](#).

10.17.4.23 SetFromDataElement()

```
template<uint16_t Group, uint16_t Element, long long TVR = TagToType<Group, Element>::VRType, int
TVM = TagToType<Group, Element>::VMType>
void gdcm::Attribute< Group, Element, TVR, TVM >::SetFromDataElement (
    DataElement const & de) [inline]
```

Examples

[GetSequenceUltrasound.cxx](#), [LargeVRDSExplicit.cxx](#), [PatchFile.cxx](#), [ReadAndDumpDICOMDIR2.cxx](#), [gdcmrtionplan.cxx](#), and [gdcmrtplan.cxx](#).

References [gdcm_assert](#), [gdcm::DataElement::GetByteValue\(\)](#), [gdcm::DataElement::GetTag\(\)](#), [GetVR\(\)](#), [gdcm::DataElement::GetVR\(\)](#), [gdcm::VR::INVALID](#), [gdcm::DataElement::IsEmpty\(\)](#), [SetByteValue\(\)](#), [SetByteValueNoSwap\(\)](#), and [gdcm::VR::UN](#).

Referenced by [Set\(\)](#), and [SetFromDataSet\(\)](#).

10.17.4.24 SetFromDataSet()

```
template<uint16_t Group, uint16_t Element, long long TVR = TagToType<Group, Element>::VRType, int
TVM = TagToType<Group, Element>::VMType>
void gdcm::Attribute< Group, Element, TVR, TVM >::SetFromDataSet (
    DataSet const & ds) [inline]
```

Examples

[DeriveSeries.cxx](#), [FixOrientation.cxx](#), [ReadAndPrintAttributes.cxx](#), [pmsct_rgb1.cxx](#), and [rle2img.cxx](#).

References [gdcm::DataSet::FindDataElement\(\)](#), [gdcm::DataSet::GetDataElement\(\)](#), and [SetFromDataElement\(\)](#).

10.17.4.25 SetValue()

```
template<uint16_t Group, uint16_t Element, long long TVR = TagToType<Group, Element>::VRType, int
TVM = TagToType<Group, Element>::VMType>
void gdcm::Attribute< Group, Element, TVR, TVM >::SetValue (
    ArrayType v,
    unsigned int idx = 0) [inline]
```

Examples

[CreateFakeRTDOSE.cxx](#), [CreateJPIPDataSet.cxx](#), [FixOrientation.cxx](#), [HelloWorld.cxx](#), [LargeVRDSEExplicit.cxx](#), and [PatchFile.cxx](#).

References [gdcm_assert](#), [GetNumberOfValues\(\)](#), and [Internal](#).

10.17.4.26 SetValues()

```
template<uint16_t Group, uint16_t Element, long long TVR = TagToType<Group, Element>::VRType, int
TVM = TagToType<Group, Element>::VMType>
void gdcm::Attribute< Group, Element, TVR, TVM >::SetValues (
    const ArrayType * array,
    unsigned int numel = VMType) [inline]
```

Examples

[FixOrientation.cxx](#), and [LargeVRDSEExplicit.cxx](#).

References [gdcm_assert](#), [GetNumberOfValues\(\)](#), [Internal](#), and [VMType](#).

10.17.5 Member Data Documentation

10.17.5.1 Internal

```
template<uint16_t Group, uint16_t Element, long long TVR = TagToType<Group, Element>::VRType, int
TVM = TagToType<Group, Element>::VMType>
ArrayType gdcm::Attribute< Group, Element, TVR, TVM >::Internal[VMToLength< TVM >::Length]
```

Referenced by [GetAsDataElement\(\)](#), [GetValue\(\)](#), [GetValue\(\)](#), [GetValues\(\)](#), [operator!=\(\)](#), [operator<\(\)](#), [operator==\(\)](#), [Print\(\)](#), [SetByteValue\(\)](#), [SetByteValueNoSwap\(\)](#), [SetValue\(\)](#), and [SetValues\(\)](#).


The documentation for this class was generated from the following file:

- [gdcmAttribute.h](#)


10.18 gdcM::Attribute< Group, Element, TVR, VM::VM1 > Class Template Reference

```
#include <gdcMAttribute.h>
```

Inheritance diagram for gdcM::Attribute< Group, Element, TVR, VM::VM1 >:



Collaboration diagram for `gdcM::Attribute< Group, Element, TVR, VM::VM1 >`:



Public Types

- enum
- enum { `VMType` = `VMToLength<VM::VM1>::Length` }
- typedef `VRTToType< TVR >::Type` `ArrayType`

Public Member Functions

- `GDCM_STATIC_ASSERT` (((((VR::VRTType) TVR &VR::VR_VM1) &&((VM::VMType) VM::VM1==VM::VM1))||!((VR::VRTType) TVR &VR::VR_VM1)))
- `GDCM_STATIC_ASSERT` (((VM::VMType) VM::VM1 &(VM::VMType)(TagToType< Group, Element >::VMType)))
- `GDCM_STATIC_ASSERT` (((VR::VRTType) TVR &(VR::VRTType)(TagToType< Group, Element >::VRTType)))
- `GDCM_STATIC_ASSERT` (VMToLength< VM::VM1 >::Length==1)
- `DataElement GetAsDataElement` () const
- unsigned int `GetNumberOfValues` () const
- `ArrayType & GetValue` ()

- [ArrayType](#) const & [GetValue](#) () const
- const [ArrayType](#) * [GetValues](#) () const
- bool [operator!=](#) (const [Attribute](#) &att) const
- bool [operator<](#) (const [Attribute](#) &att) const
- bool [operator==](#) (const [Attribute](#) &att) const
- [ArrayType](#) & [operator\[\]](#) (unsigned int idx)
- void [Print](#) (std::ostream &os) const
- void [Set](#) ([DataSet](#) const &ds)
- void [SetFromDataElement](#) ([DataElement](#) const &de)
- void [SetFromDataSet](#) ([DataSet](#) const &ds)
- void [SetValue](#) ([ArrayType](#) v)
- void [SetValues](#) (const [ArrayType](#) *array, unsigned int numel=[VMType](#))

Static Public Member Functions

- static [VM](#) [GetDictVM](#) ()
- static [VR](#) [GetDictVR](#) ()
- static [Tag](#) [GetTag](#) ()
- static [VM](#) [GetVM](#) ()
- static [VR](#) [GetVR](#) ()

Public Attributes

- [ArrayType](#) [Internal](#)

Protected Member Functions

- void [SetByteValue](#) (const [ByteValue](#) *bv)
- void [SetByteValueNoSwap](#) (const [ByteValue](#) *bv)

10.18.1 Member Typedef Documentation

10.18.1.1 ArrayType

```
template<uint16_t Group, uint16_t Element, long long TVR>
typedef VRToType<TVR>::Type gdcmm::Attribute< Group, Element, TVR, VM::VM1 >::ArrayType
```

10.18.2 Member Enumeration Documentation

10.18.2.1 anonymous enum

```
anonymous enum
```

10.18.2.2 anonymous enum

```
template<uint16_t Group, uint16_t Element, long long TVR>
anonymous enum
```

Enumerator

VMType	
--------	--

10.18.3 Member Function Documentation

10.18.3.1 GDCM_STATIC_ASSERT() [1/4]

```
template<uint16_t Group, uint16_t Element, long long TVR>
gdcmm::Attribute< Group, Element, TVR, VM::VM1 >::GDCM_STATIC_ASSERT (
    (((VR::VRType) TVR &VR::VR_VM1) && ((VM::VMType) VM::VM1==VM::VM1)) || !((VR::VRType)
TVR &VR::VR_VM1)) )
```

References [gdcmm::VM::VM1](#), and [gdcmm::VR::VR_VM1](#).

10.18.3.2 GDCM_STATIC_ASSERT() [2/4]

```
template<uint16_t Group, uint16_t Element, long long TVR>
gdcmm::Attribute< Group, Element, TVR, VM::VM1 >::GDCM_STATIC_ASSERT (
    ((VM::VMType) VM::VM1 & (VM::VMType) (TagToType< Group, Element >::VMType)) )
```

References [gdcmm::VM::VM1](#).

10.18.3.3 GDCM_STATIC_ASSERT() [3/4]

```
template<uint16_t Group, uint16_t Element, long long TVR>
gdcmm::Attribute< Group, Element, TVR, VM::VM1 >::GDCM_STATIC_ASSERT (
    ((VR::VRType) TVR & (VR::VRType) (TagToType< Group, Element >::VRType)) )
```

10.18.3.4 GDCM_STATIC_ASSERT() [4/4]

```
template<uint16_t Group, uint16_t Element, long long TVR>
gdcmm::Attribute< Group, Element, TVR, VM::VM1 >::GDCM_STATIC_ASSERT (
    VMToLength< VM::VM1 >::Length == 1)
```

10.18.3.5 GetAsDataElement()

```
template<uint16_t Group, uint16_t Element, long long TVR>
DataElement gdcmm::Attribute< Group, Element, TVR, VM::VM1 >::GetAsDataElement () const [inline]
```

References [gdcmm::assert](#), [GetNumberOfValues\(\)](#), [GetVR\(\)](#), [gdcmm::DataElement::GetVR\(\)](#), [Internal](#), [gdcmm::DataElement::SetByteValue\(\)](#), [gdcmm::DataElement::SetVR\(\)](#), [gdcmm::VR::SQ](#), [gdcmm::VR::UI](#), and [gdcmm::VR::VRASCII](#).

10.18.3.6 GetDictVM()

```
template<uint16_t Group, uint16_t Element, long long TVR>
VM gdcm::Attribute< Group, Element, TVR, VM::VM1 >::GetDictVM () [inline], [static]
```

10.18.3.7 GetDictVR()

```
template<uint16_t Group, uint16_t Element, long long TVR>
VR gdcm::Attribute< Group, Element, TVR, VM::VM1 >::GetDictVR () [inline], [static]
```

10.18.3.8 GetNumberOfValues()

```
template<uint16_t Group, uint16_t Element, long long TVR>
unsigned int gdcm::Attribute< Group, Element, TVR, VM::VM1 >::GetNumberOfValues () const [inline]
```

Referenced by [GetAsDataElement\(\)](#), [operator!=\(\)](#), [operator<\(\)](#), [operator==\(\)](#), [SetByteValue\(\)](#), and [SetByteValueNoSwap\(\)](#).

10.18.3.9 GetTag()

```
template<uint16_t Group, uint16_t Element, long long TVR>
Tag gdcm::Attribute< Group, Element, TVR, VM::VM1 >::GetTag () [inline], [static]
```

Referenced by [Print\(\)](#).

10.18.3.10 GetValue() [1/2]

```
template<uint16_t Group, uint16_t Element, long long TVR>
ArrayType & gdcm::Attribute< Group, Element, TVR, VM::VM1 >::GetValue () [inline]
```

References [Internal](#).

10.18.3.11 GetValue() [2/2]

```
template<uint16_t Group, uint16_t Element, long long TVR>
ArrayType const & gdcm::Attribute< Group, Element, TVR, VM::VM1 >::GetValue () const [inline]
```

References [Internal](#).

10.18.3.12 GetValues()

```
template<uint16_t Group, uint16_t Element, long long TVR>
const ArrayType * gdcm::Attribute< Group, Element, TVR, VM::VM1 >::GetValues () const [inline]
```

References [Internal](#).

10.18.3.13 GetVM()

```
template<uint16_t Group, uint16_t Element, long long TVR>
VM gdcmm::Attribute< Group, Element, TVR, VM::VM1 >::GetVM () [inline], [static]
```

References [gdcmm::VM::VM1](#).

10.18.3.14 GetVR()

```
template<uint16_t Group, uint16_t Element, long long TVR>
VR gdcmm::Attribute< Group, Element, TVR, VM::VM1 >::GetVR () [inline], [static]
```

Referenced by [GetAsDataElement\(\)](#), and [SetFromDataElement\(\)](#).

10.18.3.15 operator"!="()

```
template<uint16_t Group, uint16_t Element, long long TVR>
bool gdcmm::Attribute< Group, Element, TVR, VM::VM1 >::operator!= (
    const Attribute< Group, Element, TVR, VM::VM1 > & att) const [inline]
```

References [GetNumberOfValues\(\)](#), [gdcmm::Attribute< Group, Element, TVR, TVM >::GetValues\(\)](#), and [Internal](#).

10.18.3.16 operator<()

```
template<uint16_t Group, uint16_t Element, long long TVR>
bool gdcmm::Attribute< Group, Element, TVR, VM::VM1 >::operator< (
    const Attribute< Group, Element, TVR, VM::VM1 > & att) const [inline]
```

References [gdcmm::Attribute< Group, Element, TVR, TVM >::GetNumberOfValues\(\)](#), [GetNumberOfValues\(\)](#), [gdcmm::Attribute< Group, Element, TVR, TVM >::GetValues\(\)](#), and [Internal](#).

10.18.3.17 operator==(())

```
template<uint16_t Group, uint16_t Element, long long TVR>
bool gdcmm::Attribute< Group, Element, TVR, VM::VM1 >::operator==(
    const Attribute< Group, Element, TVR, VM::VM1 > & att) const [inline]
```

References [GetNumberOfValues\(\)](#), [gdcmm::Attribute< Group, Element, TVR, TVM >::GetValues\(\)](#), and [Internal](#).

10.18.3.18 operator[]()

```
ArrayType & gdcmm::Attribute< Group, Element, TVR, TVM >::operator[] (
    unsigned int idx) [inline]
```


10.18.3.19 Print()

```
template<uint16_t Group, uint16_t Element, long long TVR>
void gdcm::Attribute< Group, Element, TVR, VM::VM1 >::Print (
    std::ostream & os) const [inline]
```

References [GetTag\(\)](#), and [Internal](#).

10.18.3.20 Set()

```
template<uint16_t Group, uint16_t Element, long long TVR>
void gdcm::Attribute< Group, Element, TVR, VM::VM1 >::Set (
    DataSet const & ds) [inline]
```

References [gdcm::DataSet::GetDataElement\(\)](#), and [SetFromDataElement\(\)](#).

10.18.3.21 SetByteValue()

```
template<uint16_t Group, uint16_t Element, long long TVR>
void gdcm::Attribute< Group, Element, TVR, VM::VM1 >::SetByteValue (
    const ByteValue * bv) [inline], [protected]
```

References [gdcm_assert](#), [gdcm::ByteValue::GetLength\(\)](#), [GetNumberOfValues\(\)](#), [gdcm::ByteValue::GetPointer\(\)](#), and [Internal](#).

Referenced by [SetFromDataElement\(\)](#).

10.18.3.22 SetByteValueNoSwap()

```
template<uint16_t Group, uint16_t Element, long long TVR>
void gdcm::Attribute< Group, Element, TVR, VM::VM1 >::SetByteValueNoSwap (
    const ByteValue * bv) [inline], [protected]
```

References [gdcm_assert](#), [gdcm::ByteValue::GetLength\(\)](#), [GetNumberOfValues\(\)](#), [gdcm::ByteValue::GetPointer\(\)](#), and [Internal](#).

Referenced by [SetFromDataElement\(\)](#).

10.18.3.23 SetFromDataElement()

```
template<uint16_t Group, uint16_t Element, long long TVR>
void gdcm::Attribute< Group, Element, TVR, VM::VM1 >::SetFromDataElement (
    DataElement const & de) [inline]
```

References [gdcm_assert](#), [gdcm::DataElement::GetByteValue\(\)](#), [gdcm::DataElement::GetTag\(\)](#), [GetVR\(\)](#), [gdcm::DataElement::GetVR\(\)](#), [gdcm::VR::INVALID](#), [gdcm::DataElement::IsEmpty\(\)](#), [SetByteValue\(\)](#), [SetByteValueNoSwap\(\)](#), and [gdcm::VR::UN](#).

Referenced by [Set\(\)](#), and [SetFromDataSet\(\)](#).

10.18.3.24 SetFromDataSet()

```
template<uint16_t Group, uint16_t Element, long long TVR>
void gdcM::Attribute< Group, Element, TVR, VM::VM1 >::SetFromDataSet (
    DataSet const & ds) [inline]
```

References [gdcM::DataSet::FindDataElement\(\)](#), [gdcM::DataSet::GetDataElement\(\)](#), and [SetFromDataElement\(\)](#).

10.18.3.25 SetValue()

```
template<uint16_t Group, uint16_t Element, long long TVR>
void gdcM::Attribute< Group, Element, TVR, VM::VM1 >::SetValue (
    ArrayType v) [inline]
```

References [Internal](#).

10.18.3.26 SetValues()

```
void gdcM::Attribute< Group, Element, TVR, TVM >::SetValues (
    const ArrayType * array,
    unsigned int numel = VMType) [inline]
```

10.18.4 Member Data Documentation

10.18.4.1 Internal

```
template<uint16_t Group, uint16_t Element, long long TVR>
ArrayType gdcM::Attribute< Group, Element, TVR, VM::VM1 >::Internal
```

Referenced by [GetAsDataElement\(\)](#), [GetValue\(\)](#), [GetValue\(\)](#), [GetValues\(\)](#), [operator!=\(\)](#), [operator<\(\)](#), [operator==\(\)](#), [Print\(\)](#), [SetByteValue\(\)](#), [SetByteValueNoSwap\(\)](#), and [SetValue\(\)](#).


The documentation for this class was generated from the following file:

- [gdcMAttribute.h](#)

10.19 gdcm::Attribute< Group, Element, TVR, VM::VM1_3 > Class Template Reference

```
#include <gdcmAttribute.h>
```

Inheritance diagram for gdcm::Attribute< Group, Element, TVR, VM::VM1_3 >:



Collaboration diagram for gdcm::Attribute< Group, Element, TVR, VM::VM1_3 >:



Public Types

- enum
- typedef [VRTToType< TVR >::Type](#) [ArrayType](#)

Public Types inherited from [gdcm::Attribute< Group, Element, TVR, VM::VM1_n >](#)

- enum
- typedef [VRTToType< TVR >::Type](#) [ArrayType](#)

Public Member Functions

- [GDCM_STATIC_ASSERT](#) (((VR::VRTType) TVR &(VR::VRTType)(TagToType< Group, [Element](#) >::VRTType)))
- [DataElement GetAsDataElement](#) () const
- unsigned int [GetNumberOfValues](#) () const
- [ArrayType](#) & [GetValue](#) (unsigned int idx=0)
- const [ArrayType](#) * [GetValues](#) () const
- [VM](#) [GetVM](#) () const
- bool [operator!=](#) (const [Attribute](#) &att) const
- bool [operator<](#) (const [Attribute](#) &att) const
- bool [operator==](#) (const [Attribute](#) &att) const
- [ArrayType](#) & [operator\[\]](#) (unsigned int idx)
- void [Print](#) (std::ostream &os) const
- void [Set](#) ([DataSet](#) const &ds)
- void [SetFromDataElement](#) ([DataElement](#) const &de)
- void [SetFromDataSet](#) ([DataSet](#) const &ds)
- void [SetValue](#) ([ArrayType](#) v, unsigned int idx=0)
- void [SetValues](#) (const [ArrayType](#) *array, unsigned int numel=[VMType](#))

Public Member Functions inherited from**gdcm::Attribute< Group, Element, TVR, VM::VM1_n >**

- [Attribute](#) ()
- [~Attribute](#) ()
- [GDCM_STATIC_ASSERT](#) (((((VR::VRType) TVR &VR::VR_VM1) &&((VM::VMType) TagToType< Group, [Element](#) >::VMType==VM::VM1))||!((VR::VRType) TVR &VR::VR_VM1)))
- [GDCM_STATIC_ASSERT](#) (((VR::VRType) TVR &(VR::VRType)(TagToType< Group, [Element](#) >::VRType)))
- [GDCM_STATIC_ASSERT](#) ((VM::VM1_n &(VM::VMType)(TagToType< Group, [Element](#) >::VMType)))
- [DataElement](#) [GetAsDataElement](#) () const
- unsigned int [GetNumberOfValues](#) () const
- [ArrayType](#) & [GetValue](#) (unsigned int idx=0)
- [ArrayType](#) const & [GetValue](#) (unsigned int idx=0) const
- const [ArrayType](#) * [GetValues](#) () const
- bool [operator!=](#) (const [Attribute](#) &att) const
- bool [operator<](#) (const [Attribute](#) &att) const
- bool [operator==](#) (const [Attribute](#) &att) const
- [ArrayType](#) & [operator\[\]](#) (unsigned int idx)
- [ArrayType](#) const & [operator\[\]](#) (unsigned int idx) const
- void [Print](#) (std::ostream &os) const
- void [Set](#) ([DataSet](#) const &ds)
- void [SetFromDataElement](#) ([DataElement](#) const &de)
- void [SetFromDataSet](#) ([DataSet](#) const &ds)
- void [SetNumberOfValues](#) (unsigned int numel)
- void [SetValue](#) ([ArrayType](#) v)
- void [SetValue](#) (unsigned int idx, [ArrayType](#) v)
- void [SetValues](#) (const [ArrayType](#) *array, unsigned int numel, bool own=false)

Static Public Member Functions

- static [VM](#) [GetDictVM](#) ()
- static [VR](#) [GetDictVR](#) ()
- static [Tag](#) [GetTag](#) ()
- static [VR](#) [GetVR](#) ()

Static Public Member Functions inherited from**gdcm::Attribute< Group, Element, TVR, VM::VM1_n >**

- static [VM](#) [GetDictVM](#) ()
- static [VR](#) [GetDictVR](#) ()
- static [Tag](#) [GetTag](#) ()
- static [VM](#) [GetVM](#) ()
- static [VR](#) [GetVR](#) ()

Public Attributes

- [ArrayType](#) [Internal](#) [[VMToLength](#)< TVM >::Length]

Protected Member Functions

- void [SetByteValue](#) (const [ByteValue](#) *bv)
- void [SetByteValueNoSwap](#) (const [ByteValue](#) *bv)

Protected Member Functions inherited from [gdcM::Attribute< Group, Element, TVR, VM::VM1_n >](#)

- void [SetByteValue](#) (const [ByteValue](#) *bv)
- void [SetByteValueNoSwap](#) (const [ByteValue](#) *bv)

10.19.1 Member Typedef Documentation

10.19.1.1 ArrayType

```
typedef VRToType<TVR>::Type gdcM::Attribute< Group, Element, TVR, TVM >::ArrayType
```

10.19.2 Member Enumeration Documentation

10.19.2.1 anonymous enum

```
anonymous enum
```

10.19.3 Member Function Documentation

10.19.3.1 GDCM_STATIC_ASSERT()

```
gdcM::Attribute< Group, Element, TVR, TVM >::GDCM_STATIC_ASSERT (
    ((VR::VRType) TVR & (VR::VRType) (TagToType< Group, Element >::VRType)) )
```

10.19.3.2 GetAsDataElement()

```
DataElement gdcM::Attribute< Group, Element, TVR, TVM >::GetAsDataElement () const [inline]
```

10.19.3.3 GetDictVM()

```
VM gdcM::Attribute< Group, Element, TVR, TVM >::GetDictVM () [inline], [static]
```

10.19.3.4 GetDictVR()

```
VR gdcM::Attribute< Group, Element, TVR, TVM >::GetDictVR () [inline], [static]
```

10.19.3.5 GetNumberOfValues()

```
unsigned int gdcM::Attribute< Group, Element, TVR, TVM >::GetNumberOfValues () const [inline]
```

10.19.3.6 GetTag()

```
Tag gdcM::Attribute< Group, Element, TVR, TVM >::GetTag () [inline], [static]
```

10.19.3.7 GetValue()

```
ArrayType & gdcM::Attribute< Group, Element, TVR, TVM >::GetValue (
    unsigned int idx = 0) [inline]
```

10.19.3.8 GetValues()

```
const ArrayType * gdcM::Attribute< Group, Element, TVR, TVM >::GetValues () const [inline]
```

10.19.3.9 GetVM()

```
template<uint16_t Group, uint16_t Element, long long TVR>
VM gdcM::Attribute< Group, Element, TVR, VM::VM1_3 >::GetVM () const [inline]
```

References [gdcM::VM::VM1_3](#).

10.19.3.10 GetVR()

```
VR gdcM::Attribute< Group, Element, TVR, TVM >::GetVR () [inline], [static]
```

10.19.3.11 operator"!=(

```
bool gdcM::Attribute< Group, Element, TVR, TVM >::operator!= (
    const Attribute< Group, Element, TVR, VM::VM1_3 > & att) const [inline]
```

10.19.3.12 operator<()

```
bool gdcM::Attribute< Group, Element, TVR, TVM >::operator< (
    const Attribute< Group, Element, TVR, VM::VM1_3 > & att) const [inline]
```

10.19.3.13 operator==()

```
bool gdcm::Attribute< Group, Element, TVR, TVM >::operator== (
    const Attribute< Group, Element, TVR, VM::VM1_3 > & att) const [inline]
```

10.19.3.14 operator[]()

```
ArrayType & gdcm::Attribute< Group, Element, TVR, TVM >::operator[] (
    unsigned int idx) [inline]
```

10.19.3.15 Print()

```
void gdcm::Attribute< Group, Element, TVR, TVM >::Print (
    std::ostream & os) const [inline]
```

10.19.3.16 Set()

```
void gdcm::Attribute< Group, Element, TVR, TVM >::Set (
    DataSet const & ds) [inline]
```

10.19.3.17 SetByteValue()

```
void gdcm::Attribute< Group, Element, TVR, TVM >::SetByteValue (
    const ByteValue * bv) [inline], [protected]
```

10.19.3.18 SetByteValueNoSwap()

```
void gdcm::Attribute< Group, Element, TVR, TVM >::SetByteValueNoSwap (
    const ByteValue * bv) [inline], [protected]
```

10.19.3.19 SetFromDataElement()

```
void gdcm::Attribute< Group, Element, TVR, TVM >::SetFromDataElement (
    DataElement const & de) [inline]
```

10.19.3.20 SetFromDataSet()

```
void gdcm::Attribute< Group, Element, TVR, TVM >::SetFromDataSet (
    DataSet const & ds) [inline]
```

10.19.3.21 SetValue()

```
void gdcM::Attribute< Group, Element, TVR, TVM >::SetValue (
    ArrayType v,
    unsigned int idx = 0) [inline]
```

10.19.3.22 SetValues()

```
void gdcM::Attribute< Group, Element, TVR, TVM >::SetValues (
    const ArrayType * array,
    unsigned int numel = VMType) [inline]
```

10.19.4 Member Data Documentation

10.19.4.1 Internal

```
ArrayType gdcM::Attribute< Group, Element, TVR, TVM >::Internal[VMToLength< TVM >::Length]
```

The documentation for this class was generated from the following file:

- [gdcMAttribute.h](#)


10.20 gdcM::Attribute< Group, Element, TVR, VM::VM1_8 > Class Template Reference

```
#include <gdcMAttribute.h>
```

Inheritance diagram for gdcM::Attribute< Group, Element, TVR, VM::VM1_8 >:



Collaboration diagram for gdcM::Attribute< Group, Element, TVR, VM::VM1_8 >:



Public Types

- enum
- typedef [VRToType](#)< TVR >::Type [ArrayType](#)

Public Types inherited from [gdcm::Attribute](#)< [Group](#), [Element](#), [TVR](#), [VM::VM1_n](#) >

- enum
- typedef [VRToType](#)< TVR >::Type [ArrayType](#)

Public Member Functions

- [GDCM_STATIC_ASSERT](#) ((([VR::VRType](#)) TVR &([VR::VRType](#))(TagToType< [Group](#), [Element](#) >::VRType)))
- [DataElement](#) GetAsDataElement () const
- unsigned int [GetNumberOfValues](#) () const
- [ArrayType](#) & [GetValue](#) (unsigned int idx=0)
- const [ArrayType](#) * [GetValues](#) () const
- [VM](#) GetVM () const
- bool [operator!=](#) (const [Attribute](#) &att) const
- bool [operator<](#) (const [Attribute](#) &att) const
- bool [operator==](#) (const [Attribute](#) &att) const
- [ArrayType](#) & [operator\[\]](#) (unsigned int idx)
- void [Print](#) (std::ostream &os) const
- void [Set](#) ([DataSet](#) const &ds)
- void [SetFromDataElement](#) ([DataElement](#) const &de)
- void [SetFromDataSet](#) ([DataSet](#) const &ds)
- void [SetValue](#) ([ArrayType](#) v, unsigned int idx=0)
- void [SetValues](#) (const [ArrayType](#) *array, unsigned int numel=[VMType](#))

Public Member Functions inherited from [gdcm::Attribute](#)< [Group](#), [Element](#), [TVR](#), [VM::VM1_n](#) >

- [Attribute](#) ()
- [~Attribute](#) ()
- [GDCM_STATIC_ASSERT](#) (((((([VR::VRType](#)) TVR &[VR::VR_VM1](#)) &&(([VM::VMType](#)) TagToType< [Group](#), [Element](#) >::VMType==[VM::VM1](#)))||!(([VR::VRType](#)) TVR &[VR::VR_VM1](#))))
- [GDCM_STATIC_ASSERT](#) ((([VR::VRType](#)) TVR &([VR::VRType](#))(TagToType< [Group](#), [Element](#) >::VRType)))
- [GDCM_STATIC_ASSERT](#) (([VM::VM1_n](#) &([VM::VMType](#))(TagToType< [Group](#), [Element](#) >::VMType)))
- [DataElement](#) GetAsDataElement () const
- unsigned int [GetNumberOfValues](#) () const
- [ArrayType](#) & [GetValue](#) (unsigned int idx=0)
- [ArrayType](#) const & [GetValue](#) (unsigned int idx=0) const
- const [ArrayType](#) * [GetValues](#) () const
- bool [operator!=](#) (const [Attribute](#) &att) const
- bool [operator<](#) (const [Attribute](#) &att) const
- bool [operator==](#) (const [Attribute](#) &att) const
- [ArrayType](#) & [operator\[\]](#) (unsigned int idx)
- [ArrayType](#) const & [operator\[\]](#) (unsigned int idx) const

- void [Print](#) (std::ostream &os) const
- void [Set](#) ([DataSet](#) const &ds)
- void [SetFromDataElement](#) ([DataElement](#) const &de)
- void [SetFromDataSet](#) ([DataSet](#) const &ds)
- void [SetNumberOfValues](#) (unsigned int numel)
- void [SetValue](#) ([ArrayType](#) v)
- void [SetValue](#) (unsigned int idx, [ArrayType](#) v)
- void [SetValues](#) (const [ArrayType](#) *array, unsigned int numel, bool own=false)

Static Public Member Functions

- static [VM GetDictVM](#) ()
- static [VR GetDictVR](#) ()
- static [Tag GetTag](#) ()
- static [VR GetVR](#) ()

Static Public Member Functions inherited from [gdcmm::Attribute< Group, Element, TVR, VM::VM1_n >](#)

- static [VM GetDictVM](#) ()
- static [VR GetDictVR](#) ()
- static [Tag GetTag](#) ()
- static [VM GetVM](#) ()
- static [VR GetVR](#) ()

Public Attributes

- [ArrayType Internal](#) [[VMToLength](#)< TVM >::Length]

Protected Member Functions

- void [SetByteValue](#) (const [ByteValue](#) *bv)
- void [SetByteValueNoSwap](#) (const [ByteValue](#) *bv)

Protected Member Functions inherited from [gdcmm::Attribute< Group, Element, TVR, VM::VM1_n >](#)

- void [SetByteValue](#) (const [ByteValue](#) *bv)
- void [SetByteValueNoSwap](#) (const [ByteValue](#) *bv)

10.20.1 Member Typedef Documentation

10.20.1.1 ArrayType

```
typedef VRToType<TVR>::Type gdcmm::Attribute< Group, Element, TVR, TVM >::ArrayType
```

10.20.2 Member Enumeration Documentation

10.20.2.1 anonymous enum

anonymous enum

10.20.3 Member Function Documentation

10.20.3.1 GDCM_STATIC_ASSERT()

```
gdcm::Attribute< Group, Element, TVR, TVM >::GDCM_STATIC_ASSERT (
    ((VR::VRType) TVR & (VR::VRType) (TagToType< Group, Element >::VRType)) )
```

10.20.3.2 GetAsDataElement()

```
DataElement gdcm::Attribute< Group, Element, TVR, TVM >::GetAsDataElement () const [inline]
```

10.20.3.3 GetDictVM()

```
VM gdcm::Attribute< Group, Element, TVR, TVM >::GetDictVM () [inline], [static]
```

10.20.3.4 GetDictVR()

```
VR gdcm::Attribute< Group, Element, TVR, TVM >::GetDictVR () [inline], [static]
```

10.20.3.5 GetNumberOfValues()

```
unsigned int gdcm::Attribute< Group, Element, TVR, TVM >::GetNumberOfValues () const [inline]
```

10.20.3.6 GetTag()

```
Tag gdcm::Attribute< Group, Element, TVR, TVM >::GetTag () [inline], [static]
```

10.20.3.7 GetValue()

```
ArrayType & gdcm::Attribute< Group, Element, TVR, TVM >::GetValue (
    unsigned int idx = 0) [inline]
```

10.20.3.8 GetValues()

```
const ArrayType * gdcM::Attribute< Group, Element, TVR, TVM >::GetValues () const [inline]
```

10.20.3.9 GetVM()

```
template<uint16_t Group, uint16_t Element, long long TVR>
VM gdcM::Attribute< Group, Element, TVR, VM::VM1_8 >::GetVM () const [inline]
```

References [gdcM::VM::VM1_8](#).

10.20.3.10 GetVR()

```
VR gdcM::Attribute< Group, Element, TVR, TVM >::GetVR () [inline], [static]
```

10.20.3.11 operator"!="()

```
bool gdcM::Attribute< Group, Element, TVR, TVM >::operator!= (
    const Attribute< Group, Element, TVR, VM::VM1_8 > & att) const [inline]
```

10.20.3.12 operator<()

```
bool gdcM::Attribute< Group, Element, TVR, TVM >::operator< (
    const Attribute< Group, Element, TVR, VM::VM1_8 > & att) const [inline]
```

10.20.3.13 operator==(())

```
bool gdcM::Attribute< Group, Element, TVR, TVM >::operator==(
    const Attribute< Group, Element, TVR, VM::VM1_8 > & att) const [inline]
```

10.20.3.14 operator[]()

```
ArrayType & gdcM::Attribute< Group, Element, TVR, TVM >::operator[] (
    unsigned int idx) [inline]
```

10.20.3.15 Print()

```
void gdcM::Attribute< Group, Element, TVR, TVM >::Print (
    std::ostream & os) const [inline]
```

10.20.3.16 Set()

```
void gdcm::Attribute< Group, Element, TVR, TVM >::Set (  
    DataSet const & ds) [inline]
```

10.20.3.17 SetByteValue()

```
void gdcm::Attribute< Group, Element, TVR, TVM >::SetByteValue (  
    const ByteValue * bv) [inline], [protected]
```

10.20.3.18 SetByteValueNoSwap()

```
void gdcm::Attribute< Group, Element, TVR, TVM >::SetByteValueNoSwap (  
    const ByteValue * bv) [inline], [protected]
```

10.20.3.19 SetFromDataElement()

```
void gdcm::Attribute< Group, Element, TVR, TVM >::SetFromDataElement (  
    DataElement const & de) [inline]
```

10.20.3.20 SetFromDataSet()

```
void gdcm::Attribute< Group, Element, TVR, TVM >::SetFromDataSet (  
    DataSet const & ds) [inline]
```

10.20.3.21 SetValue()

```
void gdcm::Attribute< Group, Element, TVR, TVM >::SetValue (  
    ArrayType v,  
    unsigned int idx = 0) [inline]
```

10.20.3.22 SetValues()

```
void gdcm::Attribute< Group, Element, TVR, TVM >::SetValues (  
    const ArrayType * array,  
    unsigned int numel = VMType) [inline]
```

10.20.4 Member Data Documentation

10.20.4.1 Internal

```
ArrayType gdcM::Attribute< Group, Element, TVR, TVM >::Internal[VMToLength< TVM >::Length]
```


The documentation for this class was generated from the following file:

- [gdcMAttribute.h](#)


10.21 gdcM::Attribute< Group, Element, TVR, VM::VM1_n > Class Template Reference

```
#include <gdcMAttribute.h>
```

Inheritance diagram for gdcM::Attribute< Group, Element, TVR, VM::VM1_n >:



Collaboration diagram for gdcm::Attribute< Group, Element, TVR, VM::VM1_n >:



Public Types

- enum
- typedef `VRToType< TVR >::Type` `ArrayType`

Public Member Functions

- `Attribute()`
- `~Attribute()`
- `GDCM_STATIC_ASSERT((((VR::VRType) TVR & VR::VR_VM1) && ((VM::VMType) TagToType< Group, Element >::VMType == VM::VM1)) || !((VR::VRType) TVR & VR::VR_VM1))`
- `GDCM_STATIC_ASSERT(((VR::VRType) TVR & (VR::VRType)(TagToType< Group, Element >::VRType)))`
- `GDCM_STATIC_ASSERT((VM::VM1_n & (VM::VMType)(TagToType< Group, Element >::VMType)))`
- `DataElement GetAsDataElement() const`
- `unsigned int GetNumberOfValues() const`
- `ArrayType & GetValue(unsigned int idx=0)`

- [ArrayType](#) const & [GetValue](#) (unsigned int idx=0) const
- const [ArrayType](#) * [GetValues](#) () const
- bool [operator!=](#) (const [Attribute](#) &att) const
- bool [operator<](#) (const [Attribute](#) &att) const
- bool [operator==](#) (const [Attribute](#) &att) const
- [ArrayType](#) & [operator\[\]](#) (unsigned int idx)
- [ArrayType](#) const & [operator\[\]](#) (unsigned int idx) const
- void [Print](#) (std::ostream &os) const
- void [Set](#) ([DataSet](#) const &ds)
- void [SetFromDataElement](#) ([DataElement](#) const &de)
- void [SetFromDataSet](#) ([DataSet](#) const &ds)
- void [SetNumberOfValues](#) (unsigned int numel)
- void [SetValue](#) ([ArrayType](#) v)
- void [SetValue](#) (unsigned int idx, [ArrayType](#) v)
- void [SetValues](#) (const [ArrayType](#) *array, unsigned int numel, bool own=false)

Static Public Member Functions

- static [VM](#) [GetDictVM](#) ()
- static [VR](#) [GetDictVR](#) ()
- static [Tag](#) [GetTag](#) ()
- static [VM](#) [GetVM](#) ()
- static [VR](#) [GetVR](#) ()

Protected Member Functions

- void [SetByteValue](#) (const [ByteValue](#) *bv)
- void [SetByteValueNoSwap](#) (const [ByteValue](#) *bv)

10.21.1 Member Typedef Documentation

10.21.1.1 ArrayType

```
template<uint16_t Group, uint16_t Element, long long TVR>
typedef VRToType<TVR>::Type gdcmm::Attribute< Group, Element, TVR, VM::VM1\_n >::ArrayType
```

10.21.2 Member Enumeration Documentation

10.21.2.1 anonymous enum

```
anonymous enum
```


10.21.3 Constructor & Destructor Documentation

10.21.3.1 Attribute()

```
template<uint16_t Group, uint16_t Element, long long TVR>
gdcm::Attribute< Group, Element, TVR, VM::VM1_n >::Attribute () [inline], [explicit]
```

10.21.3.2 ~Attribute()

```
template<uint16_t Group, uint16_t Element, long long TVR>
gdcm::Attribute< Group, Element, TVR, VM::VM1_n >::~~Attribute () [inline]
```

10.21.4 Member Function Documentation

10.21.4.1 GDCM_STATIC_ASSERT() [1/3]

```
template<uint16_t Group, uint16_t Element, long long TVR>
gdcm::Attribute< Group, Element, TVR, VM::VM1_n >::GDCM_STATIC_ASSERT (
    (((VR::VRType) TVR & VR::VR_VM1) && ((VM::VMType) TagToType< Group, Element >::VMType==VM::VM1)) || ((VR
TVR & VR::VR_VM1)) )
```

References [gdcm::VM::VM1](#), and [gdcm::VR::VR_VM1](#).

10.21.4.2 GDCM_STATIC_ASSERT() [2/3]

```
template<uint16_t Group, uint16_t Element, long long TVR>
gdcm::Attribute< Group, Element, TVR, VM::VM1_n >::GDCM_STATIC_ASSERT (
    ((VR::VRType) TVR & (VR::VRType) (TagToType< Group, Element >::VRType)) )
```

10.21.4.3 GDCM_STATIC_ASSERT() [3/3]

```
template<uint16_t Group, uint16_t Element, long long TVR>
gdcm::Attribute< Group, Element, TVR, VM::VM1_n >::GDCM_STATIC_ASSERT (
    (VM::VM1_n & (VM::VMType) (TagToType< Group, Element >::VMType)) )
```

References [gdcm::VM::VM1_n](#).

10.21.4.4 GetAsDataElement()

```
template<uint16_t Group, uint16_t Element, long long TVR>
DataElement gdcm::Attribute< Group, Element, TVR, VM::VM1_n >::GetAsDataElement () const [inline]
```

References [gdcm_assert](#), [GetNumberOfValues\(\)](#), [GetTag\(\)](#), [GetVR\(\)](#), [gdcm::DataElement::GetVR\(\)](#), [gdcm::DataElement::SetByteValue\(\)](#), [gdcm::DataElement::SetVR\(\)](#), [gdcm::VR::SQ](#), [gdcm::VR::UI](#), and [gdcm::VR::VRASCII](#).

10.21.4.5 GetDictVM()

```
template<uint16_t Group, uint16_t Element, long long TVR>
VM gdcmm::Attribute< Group, Element, TVR, VM::VM1_n >::GetDictVM () [inline], [static]
```

References [GetVM\(\)](#).

10.21.4.6 GetDictVR()

```
template<uint16_t Group, uint16_t Element, long long TVR>
VR gdcmm::Attribute< Group, Element, TVR, VM::VM1_n >::GetDictVR () [inline], [static]
```

10.21.4.7 GetNumberOfValues()

```
template<uint16_t Group, uint16_t Element, long long TVR>
unsigned int gdcmm::Attribute< Group, Element, TVR, VM::VM1_n >::GetNumberOfValues () const [inline]
```

Referenced by [GetAsDataElement\(\)](#), [GetValue\(\)](#), [GetValue\(\)](#), [Print\(\)](#), [SetValue\(\)](#), and [SetValues\(\)](#).

10.21.4.8 GetTag()

```
template<uint16_t Group, uint16_t Element, long long TVR>
Tag gdcmm::Attribute< Group, Element, TVR, VM::VM1_n >::GetTag () [inline], [static]
```

Referenced by [GetAsDataElement\(\)](#), [Print\(\)](#), [Set\(\)](#), [SetFromDataElement\(\)](#), and [SetFromDataSet\(\)](#).

10.21.4.9 GetValue() [1/2]

```
template<uint16_t Group, uint16_t Element, long long TVR>
ArrayType & gdcmm::Attribute< Group, Element, TVR, VM::VM1_n >::GetValue (
    unsigned int idx = 0) [inline]
```

References [gdcmm_assert](#), and [GetNumberOfValues\(\)](#).

Referenced by [operator\[\]\(\)](#), and [operator\[\]\(\)](#).

10.21.4.10 GetValue() [2/2]

```
template<uint16_t Group, uint16_t Element, long long TVR>
ArrayType const & gdcmm::Attribute< Group, Element, TVR, VM::VM1_n >::GetValue (
    unsigned int idx = 0) const [inline]
```

References [gdcmm_assert](#), and [GetNumberOfValues\(\)](#).

10.21.4.11 GetValues()

```
template<uint16_t Group, uint16_t Element, long long TVR>
const ArrayType * gdcmm::Attribute< Group, Element, TVR, VM::VM1_n >::GetValues () const [inline]
```

10.21.4.12 GetVM()

```
template<uint16_t Group, uint16_t Element, long long TVR>
VM gdcmm::Attribute< Group, Element, TVR, VM::VM1_n >::GetVM () [inline], [static]
```

References [gdcmm::VM::VM1_n](#).

Referenced by [GetDictVM\(\)](#), and [Print\(\)](#).

10.21.4.13 GetVR()

```
template<uint16_t Group, uint16_t Element, long long TVR>
VR gdcmm::Attribute< Group, Element, TVR, VM::VM1_n >::GetVR () [inline], [static]
```

Referenced by [GetAsDataElement\(\)](#), [Print\(\)](#), and [SetFromDataElement\(\)](#).

10.21.4.14 operator"!="()

```
bool gdcmm::Attribute< Group, Element, TVR, TVM >::operator!= (
    const Attribute< Group, Element, TVR, VM::VM1_n > & att) const [inline]
```

10.21.4.15 operator<()

```
bool gdcmm::Attribute< Group, Element, TVR, TVM >::operator< (
    const Attribute< Group, Element, TVR, VM::VM1_n > & att) const [inline]
```

10.21.4.16 operator==(())

```
bool gdcmm::Attribute< Group, Element, TVR, TVM >::operator==(
    const Attribute< Group, Element, TVR, VM::VM1_n > & att) const [inline]
```

10.21.4.17 operator[]() [1/2]

```
template<uint16_t Group, uint16_t Element, long long TVR>
ArrayType & gdcmm::Attribute< Group, Element, TVR, VM::VM1_n >::operator[] (
    unsigned int idx) [inline]
```

References [GetValue\(\)](#).

10.21.4.18 operator[]() [2/2]

```
template<uint16_t Group, uint16_t Element, long long TVR>
ArrayType const & gdcM::Attribute< Group, Element, TVR, VM::VM1_n >::operator[] (
    unsigned int idx) const [inline]
```

References [GetValue\(\)](#).

10.21.4.19 Print()

```
template<uint16_t Group, uint16_t Element, long long TVR>
void gdcM::Attribute< Group, Element, TVR, VM::VM1_n >::Print (
    std::ostream & os) const [inline]
```

References [GetNumberOfValues\(\)](#), [GetTag\(\)](#), [GetVM\(\)](#), and [GetVR\(\)](#).

10.21.4.20 Set()

```
template<uint16_t Group, uint16_t Element, long long TVR>
void gdcM::Attribute< Group, Element, TVR, VM::VM1_n >::Set (
    DataSet const & ds) [inline]
```

References [gdcM::DataSet::GetDataElement\(\)](#), [GetTag\(\)](#), and [SetFromDataElement\(\)](#).

10.21.4.21 SetByteValue()

```
template<uint16_t Group, uint16_t Element, long long TVR>
void gdcM::Attribute< Group, Element, TVR, VM::VM1_n >::SetByteValue (
    const ByteValue * bv) [inline], [protected]
```

References [gdcM_assert](#), [gdcM::ByteValue::GetLength\(\)](#), [gdcM::ByteValue::GetPointer\(\)](#), and [SetValues\(\)](#).

Referenced by [SetFromDataElement\(\)](#).

10.21.4.22 SetByteValueNoSwap()

```
void gdcM::Attribute< Group, Element, TVR, TVM >::SetByteValueNoSwap (
    const ByteValue * bv) [inline], [protected]
```

10.21.4.23 SetFromDataElement()

```
template<uint16_t Group, uint16_t Element, long long TVR>
void gdcM::Attribute< Group, Element, TVR, VM::VM1_n >::SetFromDataElement (
    DataElement const & de) [inline]
```

References [gdcM_assert](#), [gdcM::DataElement::GetByteValue\(\)](#), [GetTag\(\)](#), [gdcM::DataElement::GetTag\(\)](#), [GetVR\(\)](#), [gdcM::DataElement::GetVR\(\)](#), [gdcM::DataElement::IsEmpty\(\)](#), and [SetByteValue\(\)](#).

Referenced by [Set\(\)](#), and [SetFromDataSet\(\)](#).

10.21.4.24 SetFromDataSet()

```
template<uint16_t Group, uint16_t Element, long long TVR>
void gdcm::Attribute< Group, Element, TVR, VM::VM1_n >::SetFromDataSet (
    DataSet const & ds) [inline]
```

References [gdcm::DataSet::FindDataElement\(\)](#), [gdcm::DataSet::GetDataElement\(\)](#), [GetTag\(\)](#), and [SetFromDataElement\(\)](#).

10.21.4.25 SetNumberOfValues()

```
template<uint16_t Group, uint16_t Element, long long TVR>
void gdcm::Attribute< Group, Element, TVR, VM::VM1_n >::SetNumberOfValues (
    unsigned int numel) [inline]
```

References [SetValues\(\)](#).

10.21.4.26 SetValue() [1/2]

```
template<uint16_t Group, uint16_t Element, long long TVR>
void gdcm::Attribute< Group, Element, TVR, VM::VM1_n >::SetValue (
    ArrayType v) [inline]
```

References [SetValue\(\)](#).

Referenced by [SetValue\(\)](#).

10.21.4.27 SetValue() [2/2]

```
template<uint16_t Group, uint16_t Element, long long TVR>
void gdcm::Attribute< Group, Element, TVR, VM::VM1_n >::SetValue (
    unsigned int idx,
    ArrayType v) [inline]
```

References [gdcm_assert](#), and [GetNumberOfValues\(\)](#).

10.21.4.28 SetValues()

```
template<uint16_t Group, uint16_t Element, long long TVR>
void gdcm::Attribute< Group, Element, TVR, VM::VM1_n >::SetValues (
    const ArrayType * array,
    unsigned int numel,
    bool own = false) [inline]
```

References [gdcm_assert](#), and [GetNumberOfValues\(\)](#).

Referenced by [SetByteValue\(\)](#), and [SetNumberOfValues\(\)](#).


The documentation for this class was generated from the following file:

- [gdcmAttribute.h](#)


10.22 `gdcM::Attribute< Group, Element, TVR, VM::VM2_2n >` Class Template Reference

```
#include <gdcMAttribute.h>
```

Inheritance diagram for `gdcM::Attribute< Group, Element, TVR, VM::VM2_2n >`:



Collaboration diagram for `gdcM::Attribute< Group, Element, TVR, VM::VM2_2n >`:



Public Types

- enum
- typedef `VRTToType< TVR >::Type` `ArrayType`

Public Types inherited from `gdcM::Attribute< Group, Element, TVR, VM::VM2_n >`

- enum
- typedef `VRTToType< TVR >::Type` `ArrayType`

Public Types inherited from `gdcM::Attribute< Group, Element, TVR, VM::VM1_n >`

- enum
- typedef `VRTToType< TVR >::Type` `ArrayType`

Public Member Functions

- [GDCM_STATIC_ASSERT](#) (((VR::VRType) TVR &(VR::VRType)(TagToType< Group, [Element](#) >::VRType)))
- [DataElement GetAsDataElement](#) () const
- unsigned int [GetNumberOfValues](#) () const
- [ArrayType](#) & [GetValue](#) (unsigned int idx=0)
- const [ArrayType](#) * [GetValues](#) () const
- bool [operator!=](#) (const [Attribute](#) &att) const
- bool [operator<](#) (const [Attribute](#) &att) const
- bool [operator==](#) (const [Attribute](#) &att) const
- [ArrayType](#) & [operator\[\]](#) (unsigned int idx)
- void [Print](#) (std::ostream &os) const
- void [Set](#) ([DataSet](#) const &ds)
- void [SetFromDataElement](#) ([DataElement](#) const &de)
- void [SetFromDataSet](#) ([DataSet](#) const &ds)
- void [SetValue](#) ([ArrayType](#) v, unsigned int idx=0)
- void [SetValues](#) (const [ArrayType](#) *array, unsigned int numel=[VMType](#))

Public Member Functions inherited from**[gdcm::Attribute< Group, Element, TVR, VM::VM2_n >](#)**

- [GDCM_STATIC_ASSERT](#) (((VR::VRType) TVR &(VR::VRType)(TagToType< Group, [Element](#) >::VRType)))
- [DataElement GetAsDataElement](#) () const
- unsigned int [GetNumberOfValues](#) () const
- [ArrayType](#) & [GetValue](#) (unsigned int idx=0)
- const [ArrayType](#) * [GetValues](#) () const
- [VM](#) [GetVM](#) () const
- bool [operator!=](#) (const [Attribute](#) &att) const
- bool [operator<](#) (const [Attribute](#) &att) const
- bool [operator==](#) (const [Attribute](#) &att) const
- [ArrayType](#) & [operator\[\]](#) (unsigned int idx)
- void [Print](#) (std::ostream &os) const
- void [Set](#) ([DataSet](#) const &ds)
- void [SetFromDataElement](#) ([DataElement](#) const &de)
- void [SetFromDataSet](#) ([DataSet](#) const &ds)
- void [SetValue](#) ([ArrayType](#) v, unsigned int idx=0)
- void [SetValues](#) (const [ArrayType](#) *array, unsigned int numel=[VMType](#))

Public Member Functions inherited from**[gdcm::Attribute< Group, Element, TVR, VM::VM1_n >](#)**

- [Attribute](#) ()
- [~Attribute](#) ()
- [GDCM_STATIC_ASSERT](#) ((((((VR::VRType) TVR &VR::VR_VM1) &&((VM::VMType) TagToType< Group, [Element](#) >::VMType==VM::VM1))||!((VR::VRType) TVR &VR::VR_VM1)))
- [GDCM_STATIC_ASSERT](#) (((VR::VRType) TVR &(VR::VRType)(TagToType< Group, [Element](#) >::VRType)))
- [GDCM_STATIC_ASSERT](#) ((VM::VM1_n &(VM::VMType)(TagToType< Group, [Element](#) >::VMType)))
- [DataElement GetAsDataElement](#) () const
- unsigned int [GetNumberOfValues](#) () const

- [ArrayType](#) & [GetValue](#) (unsigned int idx=0)
- [ArrayType](#) const & [GetValue](#) (unsigned int idx=0) const
- const [ArrayType](#) * [GetValues](#) () const
- bool [operator!=](#) (const [Attribute](#) &att) const
- bool [operator<](#) (const [Attribute](#) &att) const
- bool [operator==](#) (const [Attribute](#) &att) const
- [ArrayType](#) & [operator\[\]](#) (unsigned int idx)
- [ArrayType](#) const & [operator\[\]](#) (unsigned int idx) const
- void [Print](#) (std::ostream &os) const
- void [Set](#) ([DataSet](#) const &ds)
- void [SetFromDataElement](#) ([DataElement](#) const &de)
- void [SetFromDataSet](#) ([DataSet](#) const &ds)
- void [SetNumberOfValues](#) (unsigned int numel)
- void [SetValue](#) ([ArrayType](#) v)
- void [SetValue](#) (unsigned int idx, [ArrayType](#) v)
- void [SetValues](#) (const [ArrayType](#) *array, unsigned int numel, bool own=false)

Static Public Member Functions

- static [VM](#) [GetDictVM](#) ()
- static [VR](#) [GetDictVR](#) ()
- static [Tag](#) [GetTag](#) ()
- static [VM](#) [GetVM](#) ()
- static [VR](#) [GetVR](#) ()

Static Public Member Functions inherited from [gdcmm::Attribute< Group, Element, TVR, VM::VM2_n >](#)

- static [VM](#) [GetDictVM](#) ()
- static [VR](#) [GetDictVR](#) ()
- static [Tag](#) [GetTag](#) ()
- static [VR](#) [GetVR](#) ()

Static Public Member Functions inherited from [gdcmm::Attribute< Group, Element, TVR, VM::VM1_n >](#)

- static [VM](#) [GetDictVM](#) ()
- static [VR](#) [GetDictVR](#) ()
- static [Tag](#) [GetTag](#) ()
- static [VM](#) [GetVM](#) ()
- static [VR](#) [GetVR](#) ()

Public Attributes

- [ArrayType](#) [Internal](#) [[VMToLength](#)< TVM >::Length]

Public Attributes inherited from [gdcm::Attribute< Group, Element, TVR, VM::VM2_n >](#)

- [ArrayType](#) [Internal](#) [[VMToLength](#)< TVM >::Length]

Protected Member Functions

- void [SetByteValue](#) (const [ByteValue](#) *bv)
- void [SetByteValueNoSwap](#) (const [ByteValue](#) *bv)

Protected Member Functions inherited from [gdcm::Attribute< Group, Element, TVR, VM::VM2_n >](#)

- void [SetByteValue](#) (const [ByteValue](#) *bv)
- void [SetByteValueNoSwap](#) (const [ByteValue](#) *bv)

Protected Member Functions inherited from [gdcm::Attribute< Group, Element, TVR, VM::VM1_n >](#)

- void [SetByteValue](#) (const [ByteValue](#) *bv)
- void [SetByteValueNoSwap](#) (const [ByteValue](#) *bv)

10.22.1 Member Typedef Documentation**10.22.1.1 ArrayType**

```
typedef VRToType<TVR>::Type gdcm::Attribute< Group, Element, TVR, TVM >::ArrayType
```

10.22.2 Member Enumeration Documentation**10.22.2.1 anonymous enum**

```
anonymous enum
```

10.22.3 Member Function Documentation**10.22.3.1 GDCM_STATIC_ASSERT()**

```
gdcm::Attribute< Group, Element, TVR, TVM >::GDCM_STATIC_ASSERT (
    ((VR::VRType) TVR & (VR::VRType) (TagToType< Group, Element >::VRType)) )
```

10.22.3.2 GetAsDataElement()

```
DataElement gdcM::Attribute< Group, Element, TVR, TVM >::GetAsDataElement () const [inline]
```

10.22.3.3 GetDictVM()

```
VM gdcM::Attribute< Group, Element, TVR, TVM >::GetDictVM () [inline], [static]
```

10.22.3.4 GetDictVR()

```
VR gdcM::Attribute< Group, Element, TVR, TVM >::GetDictVR () [inline], [static]
```

10.22.3.5 GetNumberOfValues()

```
unsigned int gdcM::Attribute< Group, Element, TVR, TVM >::GetNumberOfValues () const [inline]
```

10.22.3.6 GetTag()

```
Tag gdcM::Attribute< Group, Element, TVR, TVM >::GetTag () [inline], [static]
```

10.22.3.7 GetValue()

```
ArrayType & gdcM::Attribute< Group, Element, TVR, TVM >::GetValue (
    unsigned int idx = 0) [inline]
```

10.22.3.8 GetValues()

```
const ArrayType * gdcM::Attribute< Group, Element, TVR, TVM >::GetValues () const [inline]
```

10.22.3.9 GetVM()

```
template<uint16_t Group, uint16_t Element, long long TVR>
VM gdcM::Attribute< Group, Element, TVR, VM::VM2_2n >::GetVM () [inline], [static]
```

References [gdcM::VM::VM2_2n](#).

10.22.3.10 GetVR()

```
VR gdcM::Attribute< Group, Element, TVR, TVM >::GetVR () [inline], [static]
```

10.22.3.11 operator"!=()

```
bool gdcmm::Attribute< Group, Element, TVR, TVM >::operator!= (
    const Attribute< Group, Element, TVR, VM::VM2_2n > & att) const [inline]
```

10.22.3.12 operator<()

```
bool gdcmm::Attribute< Group, Element, TVR, TVM >::operator< (
    const Attribute< Group, Element, TVR, VM::VM2_2n > & att) const [inline]
```

10.22.3.13 operator==(())

```
bool gdcmm::Attribute< Group, Element, TVR, TVM >::operator==(
    const Attribute< Group, Element, TVR, VM::VM2_2n > & att) const [inline]
```

10.22.3.14 operator[]()

```
ArrayType & gdcmm::Attribute< Group, Element, TVR, TVM >::operator[] (
    unsigned int idx) [inline]
```

10.22.3.15 Print()

```
void gdcmm::Attribute< Group, Element, TVR, TVM >::Print (
    std::ostream & os) const [inline]
```

10.22.3.16 Set()

```
void gdcmm::Attribute< Group, Element, TVR, TVM >::Set (
    DataSet const & ds) [inline]
```

10.22.3.17 SetByteValue()

```
void gdcmm::Attribute< Group, Element, TVR, TVM >::SetByteValue (
    const ByteValue * bv) [inline], [protected]
```

10.22.3.18 SetByteValueNoSwap()

```
void gdcmm::Attribute< Group, Element, TVR, TVM >::SetByteValueNoSwap (
    const ByteValue * bv) [inline], [protected]
```

10.22.3.19 SetFromDataElement()

```
void gdcM::Attribute< Group, Element, TVR, TVM >::SetFromDataElement (
    DataElement const & de) [inline]
```

10.22.3.20 SetFromDataSet()

```
void gdcM::Attribute< Group, Element, TVR, TVM >::SetFromDataSet (
    DataSet const & ds) [inline]
```

10.22.3.21 SetValue()

```
void gdcM::Attribute< Group, Element, TVR, TVM >::SetValue (
    ArrayType v,
    unsigned int idx = 0) [inline]
```

10.22.3.22 SetValues()

```
void gdcM::Attribute< Group, Element, TVR, TVM >::SetValues (
    const ArrayType * array,
    unsigned int numel = VMType) [inline]
```

10.22.4 Member Data Documentation

10.22.4.1 Internal

```
ArrayType gdcM::Attribute< Group, Element, TVR, TVM >::Internal[VMToLength< TVM >::Length]
```

The documentation for this class was generated from the following file:

- [gdcMAttribute.h](#)

10.23 gdcmm::Attribute< Group, Element, TVR, VM::VM2_n > Class Template Reference

```
#include <gdcmmAttribute.h>
```

Inheritance diagram for gdcmm::Attribute< Group, Element, TVR, VM::VM2_n >:



Collaboration diagram for gdcmm::Attribute< Group, Element, TVR, VM::VM2_n >:



Public Types

- enum
- typedef [VRTToType< TVR >::Type](#) [ArrayType](#)

Public Types inherited from [gdcmm::Attribute< Group, Element, TVR, VM::VM1_n >](#)

- enum
- typedef [VRTToType< TVR >::Type](#) [ArrayType](#)

Public Member Functions

- [GDCM_STATIC_ASSERT](#) ((([VR::VRTType](#)) TVR &([VR::VRTType](#))([TagToType< Group, Element >::VRTType](#))))
- [DataElement GetAsDataElement](#) () const
- unsigned int [GetNumberOfValues](#) () const
- [ArrayType](#) & [GetValue](#) (unsigned int idx=0)
- const [ArrayType](#) * [GetValues](#) () const
- [VM](#) [GetVM](#) () const
- bool [operator!=](#) (const [Attribute](#) &att) const
- bool [operator<](#) (const [Attribute](#) &att) const
- bool [operator==](#) (const [Attribute](#) &att) const
- [ArrayType](#) & [operator\[\]](#) (unsigned int idx)
- void [Print](#) (std::ostream &os) const
- void [Set](#) ([DataSet](#) const &ds)
- void [SetFromDataElement](#) ([DataElement](#) const &de)
- void [SetFromDataSet](#) ([DataSet](#) const &ds)
- void [SetValue](#) ([ArrayType](#) v, unsigned int idx=0)
- void [SetValues](#) (const [ArrayType](#) *array, unsigned int numel=[VMType](#))

Public Member Functions inherited from**gdcm::Attribute< Group, Element, TVR, VM::VM1_n >**

- [Attribute](#) ()
- [~Attribute](#) ()
- [GDCM_STATIC_ASSERT](#) (((((VR::VRType) TVR &VR::VR_VM1) &&((VM::VMType) TagToType< Group, [Element](#) >::VMType==VM::VM1))||!((VR::VRType) TVR &VR::VR_VM1)))
- [GDCM_STATIC_ASSERT](#) (((VR::VRType) TVR &(VR::VRType)(TagToType< Group, [Element](#) >::VRType)))
- [GDCM_STATIC_ASSERT](#) ((VM::VM1_n &(VM::VMType)(TagToType< Group, [Element](#) >::VMType)))
- [DataElement](#) [GetAsDataElement](#) () const
- unsigned int [GetNumberOfValues](#) () const
- [ArrayType](#) & [GetValue](#) (unsigned int idx=0)
- [ArrayType](#) const & [GetValue](#) (unsigned int idx=0) const
- const [ArrayType](#) * [GetValues](#) () const
- bool [operator!=](#) (const [Attribute](#) &att) const
- bool [operator<](#) (const [Attribute](#) &att) const
- bool [operator==](#) (const [Attribute](#) &att) const
- [ArrayType](#) & [operator\[\]](#) (unsigned int idx)
- [ArrayType](#) const & [operator\[\]](#) (unsigned int idx) const
- void [Print](#) (std::ostream &os) const
- void [Set](#) ([DataSet](#) const &ds)
- void [SetFromDataElement](#) ([DataElement](#) const &de)
- void [SetFromDataSet](#) ([DataSet](#) const &ds)
- void [SetNumberOfValues](#) (unsigned int numel)
- void [SetValue](#) ([ArrayType](#) v)
- void [SetValue](#) (unsigned int idx, [ArrayType](#) v)
- void [SetValues](#) (const [ArrayType](#) *array, unsigned int numel, bool own=false)

Static Public Member Functions

- static [VM](#) [GetDictVM](#) ()
- static [VR](#) [GetDictVR](#) ()
- static [Tag](#) [GetTag](#) ()
- static [VR](#) [GetVR](#) ()

Static Public Member Functions inherited from**gdcm::Attribute< Group, Element, TVR, VM::VM1_n >**

- static [VM](#) [GetDictVM](#) ()
- static [VR](#) [GetDictVR](#) ()
- static [Tag](#) [GetTag](#) ()
- static [VM](#) [GetVM](#) ()
- static [VR](#) [GetVR](#) ()

Public Attributes

- [ArrayType](#) [Internal](#) [[VMToLength](#)< TVM >::Length]

Protected Member Functions

- void [SetByteValue](#) (const [ByteValue](#) *bv)
- void [SetByteValueNoSwap](#) (const [ByteValue](#) *bv)

Protected Member Functions inherited from [gdcM::Attribute< Group, Element, TVR, VM::VM1_n >](#)

- void [SetByteValue](#) (const [ByteValue](#) *bv)
- void [SetByteValueNoSwap](#) (const [ByteValue](#) *bv)

10.23.1 Member Typedef Documentation

10.23.1.1 ArrayType

```
typedef VRToType<TVR>::Type gdcM::Attribute< Group, Element, TVR, TVM >::ArrayType
```

10.23.2 Member Enumeration Documentation

10.23.2.1 anonymous enum

```
anonymous enum
```

10.23.3 Member Function Documentation

10.23.3.1 GDCM_STATIC_ASSERT()

```
gdcM::Attribute< Group, Element, TVR, TVM >::GDCM_STATIC_ASSERT (
    ((VR::VRType) TVR & (VR::VRType) (TagToType< Group, Element >::VRType)) )
```

10.23.3.2 GetAsDataElement()

```
DataElement gdcM::Attribute< Group, Element, TVR, TVM >::GetAsDataElement () const [inline]
```

10.23.3.3 GetDictVM()

```
VM gdcM::Attribute< Group, Element, TVR, TVM >::GetDictVM () [inline], [static]
```

10.23.3.4 GetDictVR()

```
VR gdcM::Attribute< Group, Element, TVR, TVM >::GetDictVR () [inline], [static]
```

10.23.3.5 GetNumberOfValues()

```
unsigned int gdcM::Attribute< Group, Element, TVR, TVM >::GetNumberOfValues () const [inline]
```

10.23.3.6 GetTag()

```
Tag gdcM::Attribute< Group, Element, TVR, TVM >::GetTag () [inline], [static]
```

10.23.3.7 GetValue()

```
ArrayType & gdcM::Attribute< Group, Element, TVR, TVM >::GetValue (
    unsigned int idx = 0) [inline]
```

10.23.3.8 GetValues()

```
const ArrayType * gdcM::Attribute< Group, Element, TVR, TVM >::GetValues () const [inline]
```

10.23.3.9 GetVM()

```
template<uint16_t Group, uint16_t Element, long long TVR>
VM gdcM::Attribute< Group, Element, TVR, VM::VM2_n >::GetVM () const [inline]
```

References [gdcM::VM::VM2_n](#).

10.23.3.10 GetVR()

```
VR gdcM::Attribute< Group, Element, TVR, TVM >::GetVR () [inline], [static]
```

10.23.3.11 operator"!=(

```
bool gdcM::Attribute< Group, Element, TVR, TVM >::operator!= (
    const Attribute< Group, Element, TVR, VM::VM2_n > & att) const [inline]
```

10.23.3.12 operator<()

```
bool gdcM::Attribute< Group, Element, TVR, TVM >::operator< (
    const Attribute< Group, Element, TVR, VM::VM2_n > & att) const [inline]
```


10.23.3.13 operator==()

```
bool gdcmm::Attribute< Group, Element, TVR, TVM >::operator==(
    const Attribute< Group, Element, TVR, VM::VM2_n > & att) const [inline]
```

10.23.3.14 operator[]()

```
ArrayType & gdcmm::Attribute< Group, Element, TVR, TVM >::operator[] (
    unsigned int idx) [inline]
```

10.23.3.15 Print()

```
void gdcmm::Attribute< Group, Element, TVR, TVM >::Print (
    std::ostream & os) const [inline]
```

10.23.3.16 Set()

```
void gdcmm::Attribute< Group, Element, TVR, TVM >::Set (
    DataSet const & ds) [inline]
```

10.23.3.17 SetByteValue()

```
void gdcmm::Attribute< Group, Element, TVR, TVM >::SetByteValue (
    const ByteValue * bv) [inline], [protected]
```

10.23.3.18 SetByteValueNoSwap()

```
void gdcmm::Attribute< Group, Element, TVR, TVM >::SetByteValueNoSwap (
    const ByteValue * bv) [inline], [protected]
```

10.23.3.19 SetFromDataElement()

```
void gdcmm::Attribute< Group, Element, TVR, TVM >::SetFromDataElement (
    DataElement const & de) [inline]
```

10.23.3.20 SetFromDataSet()

```
void gdcmm::Attribute< Group, Element, TVR, TVM >::SetFromDataSet (
    DataSet const & ds) [inline]
```

10.23.3.21 SetValue()

```
void gdcmm::Attribute< Group, Element, TVR, TVM >::SetValue (
    ArrayType v,
    unsigned int idx = 0) [inline]
```

10.23.3.22 SetValues()

```
void gdcmm::Attribute< Group, Element, TVR, TVM >::SetValues (
    const ArrayType * array,
    unsigned int numel = VMType) [inline]
```

10.23.4 Member Data Documentation

10.23.4.1 Internal

```
ArrayType gdcmm::Attribute< Group, Element, TVR, TVM >::Internal[VMToLength< TVM >::Length]
```


The documentation for this class was generated from the following file:

- [gdcmmAttribute.h](#)


10.24 gdcmm::Attribute< Group, Element, TVR, VM::VM3_3n > Class Template Reference

```
#include <gdcmmAttribute.h>
```

Inheritance diagram for gdcmm::Attribute< Group, Element, TVR, VM::VM3_3n >:



Collaboration diagram for gdcmm::Attribute< Group, Element, TVR, VM::VM3_3n >:



Public Types

- enum
- typedef `VRToType< TVR >::Type` `ArrayType`

Public Types inherited from `gdcmm::Attribute< Group, Element, TVR, VM::VM3_n >`

- enum
- typedef `VRToType< TVR >::Type` `ArrayType`

Public Types inherited from `gdcmm::Attribute< Group, Element, TVR, VM::VM1_n >`

- enum
- typedef `VRToType< TVR >::Type` `ArrayType`

Public Member Functions

- `GDCM_STATIC_ASSERT` (((`VR::VRType`) TVR &(`VR::VRType`)(`TagToType< Group, Element >::VRType`)))
- `DataElement` `GetAsDataElement` () const
- unsigned int `GetNumberOfValues` () const
- `ArrayType` & `GetValue` (unsigned int idx=0)
- const `ArrayType` * `GetValues` () const
- bool `operator!=` (const `Attribute` &att) const
- bool `operator<` (const `Attribute` &att) const
- bool `operator==` (const `Attribute` &att) const
- `ArrayType` & `operator[]` (unsigned int idx)
- void `Print` (std::ostream &os) const
- void `Set` (`DataSet` const &ds)
- void `SetFromDataElement` (`DataElement` const &de)
- void `SetFromDataSet` (`DataSet` const &ds)
- void `SetValue` (`ArrayType` v, unsigned int idx=0)
- void `SetValues` (const `ArrayType` *array, unsigned int numel=`VMType`)

Public Member Functions inherited from `gdcmm::Attribute< Group, Element, TVR, VM::VM3_n >`

- `GDCM_STATIC_ASSERT` (((`VR::VRType`) TVR &(`VR::VRType`)(`TagToType< Group, Element >::VRType`)))
- `DataElement` `GetAsDataElement` () const
- unsigned int `GetNumberOfValues` () const
- `ArrayType` & `GetValue` (unsigned int idx=0)
- const `ArrayType` * `GetValues` () const
- bool `operator!=` (const `Attribute` &att) const
- bool `operator<` (const `Attribute` &att) const
- bool `operator==` (const `Attribute` &att) const
- `ArrayType` & `operator[]` (unsigned int idx)
- void `Print` (std::ostream &os) const
- void `Set` (`DataSet` const &ds)
- void `SetFromDataElement` (`DataElement` const &de)
- void `SetFromDataSet` (`DataSet` const &ds)
- void `SetValue` (`ArrayType` v, unsigned int idx=0)
- void `SetValues` (const `ArrayType` *array, unsigned int numel=`VMType`)

Public Member Functions inherited from [gdcm::Attribute< Group, Element, TVR, VM::VM1_n >](#)

- [Attribute](#) ()
- [~Attribute](#) ()
- [GDCM_STATIC_ASSERT](#) (((((VR::VRType) TVR &VR::VR_VM1) &&((VM::VMType) TagToType< Group, [Element](#) >::VMType==VM::VM1))||!((VR::VRType) TVR &VR::VR_VM1)))
- [GDCM_STATIC_ASSERT](#) (((VR::VRType) TVR &(VR::VRType)(TagToType< Group, [Element](#) >::VRType)))
- [GDCM_STATIC_ASSERT](#) ((VM::VM1_n &(VM::VMType)(TagToType< Group, [Element](#) >::VMType)))
- [DataElement](#) [GetAsDataElement](#) () const
- unsigned int [GetNumberOfValues](#) () const
- [ArrayType](#) & [GetValue](#) (unsigned int idx=0)
- [ArrayType](#) const & [GetValue](#) (unsigned int idx=0) const
- const [ArrayType](#) * [GetValues](#) () const
- bool [operator!=](#) (const [Attribute](#) &att) const
- bool [operator<](#) (const [Attribute](#) &att) const
- bool [operator==](#) (const [Attribute](#) &att) const
- [ArrayType](#) & [operator\[\]](#) (unsigned int idx)
- [ArrayType](#) const & [operator\[\]](#) (unsigned int idx) const
- void [Print](#) (std::ostream &os) const
- void [Set](#) ([DataSet](#) const &ds)
- void [SetFromDataElement](#) ([DataElement](#) const &de)
- void [SetFromDataSet](#) ([DataSet](#) const &ds)
- void [SetNumberOfValues](#) (unsigned int numel)
- void [SetValue](#) ([ArrayType](#) v)
- void [SetValue](#) (unsigned int idx, [ArrayType](#) v)
- void [SetValues](#) (const [ArrayType](#) *array, unsigned int numel, bool own=false)

Static Public Member Functions

- static [VM](#) [GetDictVM](#) ()
- static [VR](#) [GetDictVR](#) ()
- static [Tag](#) [GetTag](#) ()
- static [VM](#) [GetVM](#) ()
- static [VR](#) [GetVR](#) ()

Static Public Member Functions inherited from [gdcm::Attribute< Group, Element, TVR, VM::VM3_n >](#)

- static [VM](#) [GetDictVM](#) ()
- static [VR](#) [GetDictVR](#) ()
- static [Tag](#) [GetTag](#) ()
- static [VM](#) [GetVM](#) ()
- static [VR](#) [GetVR](#) ()

Static Public Member Functions inherited from [gdcmm::Attribute< Group, Element, TVR, VM::VM1_n >](#)

- static [VM GetDictVM](#) ()
- static [VR GetDictVR](#) ()
- static [Tag GetTag](#) ()
- static [VM GetVM](#) ()
- static [VR GetVR](#) ()

Public Attributes

- [ArrayType Internal](#) [[VMToLength](#)< TVM >::Length]

Public Attributes inherited from [gdcmm::Attribute< Group, Element, TVR, VM::VM3_n >](#)

- [ArrayType Internal](#) [[VMToLength](#)< TVM >::Length]

Protected Member Functions

- void [SetByteValue](#) (const [ByteValue](#) *bv)
- void [SetByteValueNoSwap](#) (const [ByteValue](#) *bv)

Protected Member Functions inherited from [gdcmm::Attribute< Group, Element, TVR, VM::VM3_n >](#)

- void [SetByteValue](#) (const [ByteValue](#) *bv)
- void [SetByteValueNoSwap](#) (const [ByteValue](#) *bv)

Protected Member Functions inherited from [gdcmm::Attribute< Group, Element, TVR, VM::VM1_n >](#)

- void [SetByteValue](#) (const [ByteValue](#) *bv)
- void [SetByteValueNoSwap](#) (const [ByteValue](#) *bv)

10.24.1 Member Typedef Documentation

10.24.1.1 ArrayType

```
typedef VRToType<TVR>::Type gdcmm::Attribute< Group, Element, TVR, TVM >::ArrayType
```

10.24.2 Member Enumeration Documentation

10.24.2.1 anonymous enum

anonymous enum

10.24.3 Member Function Documentation

10.24.3.1 GDCM_STATIC_ASSERT()

```
gdcmm::Attribute< Group, Element, TVR, TVM >::GDCM_STATIC_ASSERT (
    ((VR::VRType) TVR & (VR::VRType) (TagToType< Group, Element >::VRType)) )
```

10.24.3.2 GetAsDataElement()

```
DataElement gdcmm::Attribute< Group, Element, TVR, TVM >::GetAsDataElement () const [inline]
```

10.24.3.3 GetDictVM()

```
VM gdcmm::Attribute< Group, Element, TVR, TVM >::GetDictVM () [inline], [static]
```

10.24.3.4 GetDictVR()

```
VR gdcmm::Attribute< Group, Element, TVR, TVM >::GetDictVR () [inline], [static]
```

10.24.3.5 GetNumberOfValues()

```
unsigned int gdcmm::Attribute< Group, Element, TVR, TVM >::GetNumberOfValues () const [inline]
```

10.24.3.6 GetTag()

```
Tag gdcmm::Attribute< Group, Element, TVR, TVM >::GetTag () [inline], [static]
```

10.24.3.7 GetValue()

```
ArrayType & gdcmm::Attribute< Group, Element, TVR, TVM >::GetValue (
    unsigned int idx = 0) [inline]
```

10.24.3.8 GetValues()

```
const ArrayType * gdcmm::Attribute< Group, Element, TVR, TVM >::GetValues () const [inline]
```

10.24.3.9 GetVM()

```
template<uint16_t Group, uint16_t Element, long long TVR>
VM gdcmm::Attribute< Group, Element, TVR, VM::VM3_3n >::GetVM () [inline], [static]
```

References [gdcmm::VM::VM3_3n](#).

10.24.3.10 GetVR()

```
VR gdcmm::Attribute< Group, Element, TVR, TVM >::GetVR () [inline], [static]
```

10.24.3.11 operator"!="()

```
bool gdcmm::Attribute< Group, Element, TVR, TVM >::operator!= (
    const Attribute< Group, Element, TVR, VM::VM3_3n > & att) const [inline]
```

10.24.3.12 operator<()

```
bool gdcmm::Attribute< Group, Element, TVR, TVM >::operator< (
    const Attribute< Group, Element, TVR, VM::VM3_3n > & att) const [inline]
```

10.24.3.13 operator==(())

```
bool gdcmm::Attribute< Group, Element, TVR, TVM >::operator==(
    const Attribute< Group, Element, TVR, VM::VM3_3n > & att) const [inline]
```

10.24.3.14 operator[]()

```
ArrayType & gdcmm::Attribute< Group, Element, TVR, TVM >::operator[] (
    unsigned int idx) [inline]
```

10.24.3.15 Print()

```
void gdcmm::Attribute< Group, Element, TVR, TVM >::Print (
    std::ostream & os) const [inline]
```

10.24.3.16 Set()

```
void gdcmm::Attribute< Group, Element, TVR, TVM >::Set (  
    DataSet const & ds) [inline]
```

10.24.3.17 SetByteValue()

```
void gdcmm::Attribute< Group, Element, TVR, TVM >::SetByteValue (  
    const ByteValue * bv) [inline], [protected]
```

10.24.3.18 SetByteValueNoSwap()

```
void gdcmm::Attribute< Group, Element, TVR, TVM >::SetByteValueNoSwap (  
    const ByteValue * bv) [inline], [protected]
```

10.24.3.19 SetFromDataElement()

```
void gdcmm::Attribute< Group, Element, TVR, TVM >::SetFromDataElement (  
    DataElement const & de) [inline]
```

10.24.3.20 SetFromDataSet()

```
void gdcmm::Attribute< Group, Element, TVR, TVM >::SetFromDataSet (  
    DataSet const & ds) [inline]
```

10.24.3.21 SetValue()

```
void gdcmm::Attribute< Group, Element, TVR, TVM >::SetValue (  
    ArrayType v,  
    unsigned int idx = 0) [inline]
```

10.24.3.22 SetValues()

```
void gdcmm::Attribute< Group, Element, TVR, TVM >::SetValues (  
    const ArrayType * array,  
    unsigned int numel = VMType) [inline]
```


10.24.4 Member Data Documentation

10.24.4.1 Internal

```
ArrayType gdcm::Attribute< Group, Element, TVR, TVM >::Internal[VMToLength< TVM >::Length]
```


The documentation for this class was generated from the following file:

- [gdcmAttribute.h](#)

10.25 gdcm::Attribute< Group, Element, TVR, VM::VM3_n > Class Template Reference

```
#include <gdcmAttribute.h>
```

Inheritance diagram for gdcm::Attribute< Group, Element, TVR, VM::VM3_n >:



Collaboration diagram for gdcm::Attribute< Group, Element, TVR, VM::VM3_n >:



Public Types

- enum
- typedef [VRTToType< TVR >::Type](#) [ArrayType](#)

Public Types inherited from [gdcm::Attribute< Group, Element, TVR, VM::VM1_n >](#)

- enum
- typedef [VRTToType< TVR >::Type](#) [ArrayType](#)

Public Member Functions

- [GDCM_STATIC_ASSERT](#) ((([VR::VRType](#)) TVR &([VR::VRType](#))(TagToType< Group, [Element](#) >::VRType)))
- [DataElement](#) [GetAsDataElement](#) () const
- unsigned int [GetNumberOfValues](#) () const
- [ArrayType](#) & [GetValue](#) (unsigned int idx=0)
- const [ArrayType](#) * [GetValues](#) () const
- bool [operator!=](#) (const [Attribute](#) &att) const
- bool [operator<](#) (const [Attribute](#) &att) const
- bool [operator==](#) (const [Attribute](#) &att) const
- [ArrayType](#) & [operator\[\]](#) (unsigned int idx)
- void [Print](#) (std::ostream &os) const
- void [Set](#) ([DataSet](#) const &ds)
- void [SetFromDataElement](#) ([DataElement](#) const &de)
- void [SetFromDataSet](#) ([DataSet](#) const &ds)
- void [SetValue](#) ([ArrayType](#) v, unsigned int idx=0)
- void [SetValues](#) (const [ArrayType](#) *array, unsigned int numel=[VMType](#))

Public Member Functions inherited from

[gdcm::Attribute](#)< Group, [Element](#), TVR, [VM::VM1_n](#) >

- [Attribute](#) ()
- [~Attribute](#) ()
- [GDCM_STATIC_ASSERT](#) (((((([VR::VRType](#)) TVR &[VR::VR_VM1](#)) &&(([VM::VMType](#)) TagToType< Group, [Element](#) >::VMType==[VM::VM1](#)))||!(([VR::VRType](#)) TVR &[VR::VR_VM1](#))))
- [GDCM_STATIC_ASSERT](#) ((([VR::VRType](#)) TVR &([VR::VRType](#))(TagToType< Group, [Element](#) >::VRType)))
- [GDCM_STATIC_ASSERT](#) (([VM::VM1_n](#) &([VM::VMType](#))(TagToType< Group, [Element](#) >::VMType)))
- [DataElement](#) [GetAsDataElement](#) () const
- unsigned int [GetNumberOfValues](#) () const
- [ArrayType](#) & [GetValue](#) (unsigned int idx=0)
- [ArrayType](#) const & [GetValue](#) (unsigned int idx=0) const
- const [ArrayType](#) * [GetValues](#) () const
- bool [operator!=](#) (const [Attribute](#) &att) const
- bool [operator<](#) (const [Attribute](#) &att) const
- bool [operator==](#) (const [Attribute](#) &att) const
- [ArrayType](#) & [operator\[\]](#) (unsigned int idx)
- [ArrayType](#) const & [operator\[\]](#) (unsigned int idx) const
- void [Print](#) (std::ostream &os) const
- void [Set](#) ([DataSet](#) const &ds)
- void [SetFromDataElement](#) ([DataElement](#) const &de)
- void [SetFromDataSet](#) ([DataSet](#) const &ds)
- void [SetNumberOfValues](#) (unsigned int numel)
- void [SetValue](#) ([ArrayType](#) v)
- void [SetValue](#) (unsigned int idx, [ArrayType](#) v)
- void [SetValues](#) (const [ArrayType](#) *array, unsigned int numel, bool own=false)

Static Public Member Functions

- static [VM GetDictVM](#) ()
- static [VR GetDictVR](#) ()
- static [Tag GetTag](#) ()
- static [VM GetVM](#) ()
- static [VR GetVR](#) ()

Static Public Member Functions inherited from
[gdcmm::Attribute< Group, Element, TVR, VM::VM1_n >](#)

- static [VM GetDictVM](#) ()
- static [VR GetDictVR](#) ()
- static [Tag GetTag](#) ()
- static [VM GetVM](#) ()
- static [VR GetVR](#) ()

Public Attributes

- [ArrayType Internal](#) [[VMToLength](#)< TVM >::Length]

Protected Member Functions

- void [SetByteValue](#) (const [ByteValue](#) *bv)
- void [SetByteValueNoSwap](#) (const [ByteValue](#) *bv)

Protected Member Functions inherited from
[gdcmm::Attribute< Group, Element, TVR, VM::VM1_n >](#)

- void [SetByteValue](#) (const [ByteValue](#) *bv)
- void [SetByteValueNoSwap](#) (const [ByteValue](#) *bv)

10.25.1 Member Typedef Documentation**10.25.1.1 ArrayType**

```
typedef VRToType<TVR>::Type gdcmm::Attribute< Group, Element, TVR, TVM >::ArrayType
```

10.25.2 Member Enumeration Documentation**10.25.2.1 anonymous enum**

```
anonymous enum
```

10.25.3 Member Function Documentation

10.25.3.1 GDCM_STATIC_ASSERT()

```
gdcM::Attribute< Group, Element, TVR, TVM >::GDCM_STATIC_ASSERT (
    ((VR::VRType) TVR & (VR::VRType) (TagToType< Group, Element >::VRType)) )
```

10.25.3.2 GetAsDataElement()

```
DataElement gdcM::Attribute< Group, Element, TVR, TVM >::GetAsDataElement () const [inline]
```

10.25.3.3 GetDictVM()

```
VM gdcM::Attribute< Group, Element, TVR, TVM >::GetDictVM () [inline], [static]
```

10.25.3.4 GetDictVR()

```
VR gdcM::Attribute< Group, Element, TVR, TVM >::GetDictVR () [inline], [static]
```

10.25.3.5 GetNumberOfValues()

```
unsigned int gdcM::Attribute< Group, Element, TVR, TVM >::GetNumberOfValues () const [inline]
```

10.25.3.6 GetTag()

```
Tag gdcM::Attribute< Group, Element, TVR, TVM >::GetTag () [inline], [static]
```

10.25.3.7 GetValue()

```
ArrayType & gdcM::Attribute< Group, Element, TVR, TVM >::GetValue (
    unsigned int idx = 0) [inline]
```

10.25.3.8 GetValues()

```
const ArrayType * gdcM::Attribute< Group, Element, TVR, TVM >::GetValues () const [inline]
```

10.25.3.9 GetVM()

```
template<uint16_t Group, uint16_t Element, long long TVR>
VM gdcmm::Attribute< Group, Element, TVR, VM::VM3_n >::GetVM () [inline], [static]
```

References [gdcmm::VM::VM3_n](#).

10.25.3.10 GetVR()

```
VR gdcmm::Attribute< Group, Element, TVR, TVM >::GetVR () [inline], [static]
```

10.25.3.11 operator"!="()

```
bool gdcmm::Attribute< Group, Element, TVR, TVM >::operator!= (
    const Attribute< Group, Element, TVR, VM::VM3_n > & att) const [inline]
```

10.25.3.12 operator<()

```
bool gdcmm::Attribute< Group, Element, TVR, TVM >::operator< (
    const Attribute< Group, Element, TVR, VM::VM3_n > & att) const [inline]
```

10.25.3.13 operator==(())

```
bool gdcmm::Attribute< Group, Element, TVR, TVM >::operator==(
    const Attribute< Group, Element, TVR, VM::VM3_n > & att) const [inline]
```

10.25.3.14 operator[]()

```
ArrayType & gdcmm::Attribute< Group, Element, TVR, TVM >::operator[] (
    unsigned int idx) [inline]
```

10.25.3.15 Print()

```
void gdcmm::Attribute< Group, Element, TVR, TVM >::Print (
    std::ostream & os) const [inline]
```

10.25.3.16 Set()

```
void gdcmm::Attribute< Group, Element, TVR, TVM >::Set (
    DataSet const & ds) [inline]
```

10.25.3.17 SetByteValue()

```
void gdcmm::Attribute< Group, Element, TVR, TVM >::SetByteValue (
    const ByteValue * bv) [inline], [protected]
```

10.25.3.18 SetByteValueNoSwap()

```
void gdcmm::Attribute< Group, Element, TVR, TVM >::SetByteValueNoSwap (
    const ByteValue * bv) [inline], [protected]
```

10.25.3.19 SetFromDataElement()

```
void gdcmm::Attribute< Group, Element, TVR, TVM >::SetFromDataElement (
    DataElement const & de) [inline]
```

10.25.3.20 SetFromDataSet()

```
void gdcmm::Attribute< Group, Element, TVR, TVM >::SetFromDataSet (
    DataSet const & ds) [inline]
```

10.25.3.21 SetValue()

```
void gdcmm::Attribute< Group, Element, TVR, TVM >::SetValue (
    ArrayType v,
    unsigned int idx = 0) [inline]
```

10.25.3.22 SetValues()

```
void gdcmm::Attribute< Group, Element, TVR, TVM >::SetValues (
    const ArrayType * array,
    unsigned int numel = VMType) [inline]
```

10.25.4 Member Data Documentation**10.25.4.1 Internal**

```
ArrayType gdcmm::Attribute< Group, Element, TVR, TVM >::Internal[VMToLength< TVM >::Length]
```

The documentation for this class was generated from the following file:


- [gdcmmAttribute.h](#)

10.26 gdcm::AudioCodec Class Reference


[AudioCodec.](#)

```
#include <gdcmAudioCodec.h>
```

Inheritance diagram for gdcm::AudioCodec:



Collaboration diagram for gdcm::AudioCodec:



Public Member Functions

- [AudioCodec](#) ()
- [~AudioCodec](#) () override
- bool [CanCode](#) ([TransferSyntax](#) const &) const override
Return whether this coder support this transfer syntax (can code it)
- bool [CanDecode](#) ([TransferSyntax](#) const &) const override
Return whether this decoder support this transfer syntax (can decode it)
- bool [Decode](#) ([DataElement](#) const &is, [DataElement](#) &os) override
Decode.

Public Member Functions inherited from [gdcm::Coder](#)

- virtual [~Coder](#) ()=default
- virtual bool [Code](#) ([DataElement](#) const &in_, [DataElement](#) &out_)
Code.

Public Member Functions inherited from [gdcm::Decoder](#)

- virtual [~Decoder](#) ()=default

Additional Inherited Members

Protected Member Functions inherited from [gdcm::Coder](#)

- virtual bool [InternalCode](#) (const char *bv, unsigned long len, std::ostream &os)

Protected Member Functions inherited from [gdcm::Decoder](#)

- virtual bool [DecodeByStreams](#) (std::istream &, std::ostream &)

10.26.1 Detailed Description

[AudioCodec](#).

10.26.2 Constructor & Destructor Documentation

10.26.2.1 AudioCodec()

```
gdcm::AudioCodec::AudioCodec ()
```


10.26.2.2 ~AudioCodec()

```
gdcm::AudioCodec::~~AudioCodec () [override]
```

10.26.3 Member Function Documentation

10.26.3.1 CanCode()

```
bool gdcm::AudioCodec::CanCode (
    TransferSyntax const & ) const [inline], [override], [virtual]
```

Return whether this coder support this transfer syntax (can code it)

Implements [gdcm::Coder](#).

10.26.3.2 CanDecode()

```
bool gdcm::AudioCodec::CanDecode (
    TransferSyntax const & ) const [inline], [override], [virtual]
```

Return whether this decoder support this transfer syntax (can decode it)

Implements [gdcm::Decoder](#).

10.26.3.3 Decode()

```
bool gdcm::AudioCodec::Decode (
    DataElement const & ,
    DataElement & ) [override], [virtual]
```

Decode.

Reimplemented from [gdcm::Decoder](#).

The documentation for this class was generated from the following file:

- [gdcmAudioCodec.h](#)

10.27 gdcm::Base64 Class Reference

Class for [Base64](#).

```
#include <gdcmBase64.h>
```

Public Member Functions

- [Base64](#) (const [Base64](#) &)=delete
- void [operator=](#) (const [Base64](#) &)=delete

Static Public Member Functions

- static size_t [Decode](#) (char *dst, size_t dlen, const char *src, size_t slen)
Decode a base64-formatted buffer.
- static size_t [Encode](#) (char *dst, size_t dlen, const char *src, size_t slen)
Encode a buffer into base64 format.
- static size_t [GetDecodeLength](#) (const char *src, size_t len)
- static size_t [GetEncodeLength](#) (const char *src, size_t srclen)

10.27.1 Detailed Description

Class for [Base64](#).

10.27.2 Constructor & Destructor Documentation

10.27.2.1 Base64()

```
gdcm::Base64::Base64 (
    const Base64 & ) [delete]
```

References [Base64\(\)](#).

Referenced by [Base64\(\)](#), and [operator=\(\)](#).

10.27.3 Member Function Documentation

10.27.3.1 Decode()

```
size_t gdcm::Base64::Decode (
    char * dst,
    size_t dlen,
    const char * src,
    size_t slen) [static]
```

Decode a base64-formatted buffer.

Parameters

<i>dst</i>	destination buffer
<i>dlen</i>	size of the buffer
<i>src</i>	source buffer
<i>slen</i>	amount of data to be decoded

Returns

0 if not successful, size of decoded otherwise

Examples

[DumpExamCard.cxx](#), and [DumpSiemensBase64.cxx](#).

10.27.3.2 Encode()

```
size_t gdcm::Base64::Encode (
    char * dst,
    size_t dlen,
    const char * src,
    size_t slen) [static]
```

Encode a buffer into base64 format.

Parameters

<i>dst</i>	destination buffer
<i>dlen</i>	size of the buffer
<i>src</i>	source buffer
<i>slen</i>	amount of data to be encoded

Returns

0 if not successful, size of encoded otherwise

10.27.3.3 GetDecodeLength()

```
size_t gdcm::Base64::GetDecodeLength (
    const char * src,
    size_t len) [static]
```

Call this function to obtain the required buffer size

Examples

[DumpExamCard.cxx](#), and [DumpSiemensBase64.cxx](#).

10.27.3.4 GetEncodeLength()

```
size_t gdcm::Base64::GetEncodeLength (
    const char * src,
    size_t srclen) [static]
```

Call this function to obtain the required buffer size

10.27.3.5 operator=()

```
void gdcm::Base64::operator= (
    const Base64 & ) [delete]
```

References [Base64\(\)](#).

The documentation for this class was generated from the following file:


- [gdcmBase64.h](#)

10.28 gdcm::network::BaseCompositeMessage Class Reference

[BaseCompositeMessage](#).

```
#include <gdcmBaseCompositeMessage.h>
```

Inheritance diagram for gdcm::network::BaseCompositeMessage:



Public Member Functions

- virtual [~BaseCompositeMessage](#) ()=default
- virtual std::vector< [PresentationDataValue](#) > [ConstructPDV](#) (const [ULConnection](#) &inConnection, const [BaseRootQuery](#) *inRootQuery)=0

10.28.1 Detailed Description

[BaseCompositeMessage](#).

The Composite events described in section 3.7-2009 of the DICOM standard all use their own messages. These messages are constructed using Presentation Data Values, from section 3.8-2009 of the standard, and then fill in appropriate values in their datasets.

So, for the five composites:

- C-ECHO
- C-FIND
- C-MOVE
- C-GET
- C-STORE there are a series of messages. However, all of these messages are obtained as part of a PDataPDU, and all have to be placed there. Therefore, since they all have shared functionality and construction tropes, that will be put into a base class. Further, the base class will be then returned by the factory class, gdcmCompositePDUFactory.

This is an abstract class. It cannot be instantiated on its own.

10.28.2 Constructor & Destructor Documentation

10.28.2.1 ~BaseCompositeMessage()

```
virtual gdcm::network::BaseCompositeMessage::~BaseCompositeMessage () [virtual], [default]
```

10.28.3 Member Function Documentation

10.28.3.1 ConstructPDV()

```
virtual std::vector< PresentationDataValue > gdcm::network::BaseCompositeMessage::ConstructPDV (
    const ULConnection & inConnection,
    const BaseRootQuery * inRootQuery) [pure virtual]
```

Implemented in [gdcm::network::CEchoRQ](#), [gdcm::network::CFindRQ](#), and [gdcm::network::CMoveRQ](#).

The documentation for this class was generated from the following file:


- [gdcmBaseCompositeMessage.h](#)

10.29 gdcm::network::BaseNormalizedMessage Class Reference

[BaseNormalizedMessage](#).

```
#include <gdcmBaseNormalizedMessage.h>
```

Inheritance diagram for `gdcm::network::BaseNormalizedMessage`:



Public Member Functions

- virtual `~BaseNormalizedMessage()`=default
- virtual `std::vector< PresentationDataValue > ConstructPDV (const ULConnection &inConnection, const BaseQuery *inQuery)=0`

10.29.1 Detailed Description

[BaseNormalizedMessage](#).

The Normalized events described in section 3.7-2011 of the DICOM standard all use their own messages. These messages are constructed using Presentation Data Values, from section 3.8-2011 of the standard, and then fill in appropriate values in their datasets.

So, for the five normalized:

- N-ACTION
- N-CREATE
- N-DELETE
- N-EVENT
- N-GET
- N-SET there are a series of messages. However, all of these messages are obtained as part of a PData←PDU, and all have to be placed there. Therefore, since they all have shared functionality and construction tropes, that will be put into a base class. Further, the base class will be then returned by the factory class, [gdcmNormalizedMessageFactory.h](#).

This is an abstract class. It cannot be instantiated on its own.

10.29.2 Constructor & Destructor Documentation

10.29.2.1 ~BaseNormalizedMessage()

```
virtual gdcm::network::BaseNormalizedMessage::~~BaseNormalizedMessage () [virtual], [default]
```

10.29.3 Member Function Documentation

10.29.3.1 ConstructPDV()

```
virtual std::vector< PresentationDataValue > gdcm::network::BaseNormalizedMessage::ConstructPDV (  
    const ULConnection & inConnection,  
    const BaseQuery * inQuery) [pure virtual]
```

Implemented in [gdcm::network::NActionRQ](#), [gdcm::network::NCreateRQ](#), [gdcm::network::NDeleteRQ](#), [gdcm::network::NEventReportRQ](#), [gdcm::network::NGetRQ](#), and [gdcm::network::NSetRQ](#).

The documentation for this class was generated from the following file:


- [gdcmBaseNormalizedMessage.h](#)

10.30 gdcm::network::BasePDU Class Reference

[BasePDU](#).

```
#include <gdcmBasePDU.h>
```

Inheritance diagram for gdcm::network::BasePDU:



Public Member Functions

- virtual [~BasePDU](#) ()=default
- virtual bool [IsLastFragment](#) () const =0
- virtual void [Print](#) (std::ostream &os) const =0
- virtual std::istream & [Read](#) (std::istream &is)=0
- virtual size_t [Size](#) () const =0
- virtual const std::ostream & [Write](#) (std::ostream &os) const =0

10.30.1 Detailed Description

[BasePDU](#).

base class for PDUs

all PDUs start with the first ten bytes as specified: 01 PDU type 02 reserved 3-6 PDU Length (unsigned) 7-10 variable

on some, 7-10 are split (7-8 as protocol version in Associate-RQ, for instance, while associate-rj splits those four bytes differently).

Also common to all the PDUs is their ability to read and write to a stream.

So, let's just get them all bunched together into one (abstract) class, shall we?

Why? 1) so that the [ULEvent](#) can have the PDU stored in it, since the event takes PDUs and not other class structures (other class structures get converted into PDUs) 2) to make reading PDUs in the event loop cleaner

10.30.2 Constructor & Destructor Documentation

10.30.2.1 ~BasePDU()

```
virtual gdcmm::network::BasePDU::~BasePDU () [virtual], [default]
```

10.30.3 Member Function Documentation

10.30.3.1 IsLastFragment()

```
virtual bool gdcmm::network::BasePDU::IsLastFragment () const [pure virtual]
```

Implemented in [gdcmm::network::AAabortPDU](#), [gdcmm::network::AAssociateACPDU](#), [gdcmm::network::AAssociateRJPDU](#), [gdcmm::network::AAssociateRQPDU](#), [gdcmm::network::AReleaseRPPDU](#), [gdcmm::network::AReleaseRQPDU](#), and [gdcmm::network::PDataTFPDU](#).

10.30.3.2 Print()

```
virtual void gdcmm::network::BasePDU::Print (
    std::ostream & os) const [pure virtual]
```

Implemented in [gdcmm::network::AAabortPDU](#), [gdcmm::network::AAssociateACPDU](#), [gdcmm::network::AAssociateRJPDU](#), [gdcmm::network::AAssociateRQPDU](#), [gdcmm::network::AReleaseRPPDU](#), [gdcmm::network::AReleaseRQPDU](#), and [gdcmm::network::PDataTFPDU](#).

10.30.3.3 Read()

```
virtual std::istream & gdcmm::network::BasePDU::Read (
    std::istream & is) [pure virtual]
```

Implemented in [gdcmm::network::AAabortPDU](#), [gdcmm::network::AAssociateACPDU](#), [gdcmm::network::AAssociateRJPDU](#), [gdcmm::network::AAssociateRQPDU](#), [gdcmm::network::AReleaseRPPDU](#), [gdcmm::network::AReleaseRQPDU](#), and [gdcmm::network::PDataTFPDU](#).

10.30.3.4 Size()

```
virtual size_t gdcm::network::BasePDU::Size () const [pure virtual]
```

Implemented in [gdcm::network::AAbortPDU](#), [gdcm::network::AAssociateACPDU](#), [gdcm::network::AAssociateRJPDU](#), [gdcm::network::AAssociateRQPDU](#), [gdcm::network::AReleaseRPPDU](#), [gdcm::network::AReleaseRQPDU](#), and [gdcm::network::PDataTFPDU](#).

10.30.3.5 Write()

```
virtual const std::ostream & gdcm::network::BasePDU::Write (
    std::ostream & os) const [pure virtual]
```

Implemented in [gdcm::network::AAbortPDU](#), [gdcm::network::AAssociateACPDU](#), [gdcm::network::AAssociateRJPDU](#), [gdcm::network::AAssociateRQPDU](#), [gdcm::network::AReleaseRPPDU](#), [gdcm::network::AReleaseRQPDU](#), and [gdcm::network::PDataTFPDU](#).

The documentation for this class was generated from the following file:


- [gdcmBasePDU.h](#)

10.31 gdcm::BaseQuery Class Reference


[BaseQuery](#).

```
#include <gdcmBaseQuery.h>
```

Inheritance diagram for `gdcm::BaseQuery`:



Collaboration diagram for gdcm::BaseQuery:



Public Member Functions

- [~BaseQuery](#) () override
- void [AddQueryDataSet](#) (const [DataSet](#) &ds)
- virtual [UIDs::TSName](#) [GetAbstractSyntaxUID](#) () const =0
- [DataSet](#) & [GetQueryDataSet](#) ()
- [DataSet](#) const & [GetQueryDataSet](#) () const
- *Set/Get the internal representation of the query as a [DataSet](#).*
- std::string [GetSOPInstanceUID](#) () const
- void [Print](#) (std::ostream &os) const override
- void [SetSearchParameter](#) (const std::string &inKeyword, const std::string &inValue)
- void [SetSearchParameter](#) (const [Tag](#) &inTag, const std::string &inValue)
- void [SetSOPInstanceUID](#) (const std::string &iSopInstanceUID)
- virtual bool [ValidateQuery](#) (bool inStrict=true) const =0
- const std::ostream & [WriteHelpFile](#) (std::ostream &os)
- bool [WriteQuery](#) (const std::string &inFileName)

Public Member Functions inherited from [gdcm::Object](#)

- [Object](#) ()
- [Object](#) (const [Object](#) &)
- *Special requirement for copy/cstor, assignment operator.*
- virtual [~Object](#) ()
- void [operator=](#) (const [Object](#) &)

Protected Member Functions

- [BaseQuery](#) ()
- void [SetSearchParameter](#) (const [Tag](#) &inTag, const [DictEntry](#) &inDictEntry, const std::string &inValue)
- bool [ValidDataSet](#) (const [DataSet](#) &dataSetToValid, const [DataSet](#) &dataSetReference) const

Protected Member Functions inherited from [gdcm::Object](#)

- void [Register](#) ()
- void [UnRegister](#) ()

Protected Attributes

- [DataSet](#) [mDataSet](#)
- std::string [mSopInstanceUID](#)

Friends

- class [QueryFactory](#)

10.31.1 Detailed Description

[BaseQuery](#).

contains: a baseclass which will produce a dataset for all dimse messages

10.31.2 Constructor & Destructor Documentation**10.31.2.1 BaseQuery()**

```
gdcm::BaseQuery::BaseQuery () [protected]
```

10.31.2.2 ~BaseQuery()

```
gdcm::BaseQuery::~~BaseQuery () [override]
```

10.31.3 Member Function Documentation**10.31.3.1 AddQueryDataSet()**

```
void gdcm::BaseQuery::AddQueryDataSet (
    const DataSet & ds)
```

10.31.3.2 GetAbstractSyntaxUID()

```
virtual UIDs::TSName gdcm::BaseQuery::GetAbstractSyntaxUID () const [pure virtual]
```

Implemented in [gdcm::FindPatientRootQuery](#), [gdcm::FindStudyRootQuery](#), [gdcm::ModalityPerformedProcedureStepCreateQuery](#), [gdcm::ModalityPerformedProcedureStepSetQuery](#), [gdcm::MovePatientRootQuery](#), [gdcm::MoveStudyRootQuery](#), and [gdcm::WLMFindQuery](#).

10.31.3.3 GetQueryDataSet() [1/2]

```
DataSet & gdcm::BaseQuery::GetQueryDataSet ()
```

10.31.3.4 GetQueryDataSet() [2/2]

```
DataSet const & gdcm::BaseQuery::GetQueryDataSet () const
```

Set/Get the internal representation of the query as a [DataSet](#).

10.31.3.5 GetSOPInstanceUID()

```
std::string gdcm::BaseQuery::GetSOPInstanceUID () const [inline]
```

References [mSopInstanceUID](#).

10.31.3.6 Print()

```
void gdcm::BaseQuery::Print (  
    std::ostream & os) const [override], [virtual]
```

Reimplemented from [gdcm::Object](#).

10.31.3.7 SetSearchParameter() [1/3]

```
void gdcm::BaseQuery::SetSearchParameter (  
    const std::string & inKeyword,  
    const std::string & inValue)
```

10.31.3.8 SetSearchParameter() [2/3]

```
void gdcm::BaseQuery::SetSearchParameter (  
    const Tag & inTag,  
    const DictEntry & inDictEntry,  
    const std::string & inValue) [protected]
```

10.31.3.9 SetSearchParameter() [3/3]

```
void gdcm::BaseQuery::SetSearchParameter (
    const Tag & inTag,
    const std::string & inValue)
```

10.31.3.10 SetSOPInstanceUID()

```
void gdcm::BaseQuery::SetSOPInstanceUID (
    const std::string & iSopInstanceUID) [inline]
```

References [mSopInstanceUID](#).

10.31.3.11 ValidateQuery()

```
virtual bool gdcm::BaseQuery::ValidateQuery (
    bool inStrict = true) const [pure virtual]
```

Implemented in [gdcm::BaseRootQuery](#), [gdcm::FindPatientRootQuery](#), [gdcm::FindStudyRootQuery](#), [gdcm::ModalityPerformedProcedureS](#), [gdcm::ModalityPerformedProcedureStepSetQuery](#), [gdcm::MovePatientRootQuery](#), [gdcm::MoveStudyRootQuery](#), and [gdcm::WLMFindQuery](#).

10.31.3.12 ValidDataSet()

```
bool gdcm::BaseQuery::ValidDataSet (
    const DataSet & dataSetToValid,
    const DataSet & dataSetReference) const [protected]
```

10.31.3.13 WriteHelpFile()

```
const std::ostream & gdcm::BaseQuery::WriteHelpFile (
    std::ostream & os)
```

10.31.3.14 WriteQuery()

```
bool gdcm::BaseQuery::WriteQuery (
    const std::string & inFileName)
```

10.31.4 Friends And Related Symbol Documentation

10.31.4.1 QueryFactory

```
friend class QueryFactory [friend]
```

References [QueryFactory](#).

Referenced by [QueryFactory](#).

10.31.5 Member Data Documentation

10.31.5.1 mDataSet

`DataSet` `gdcm::BaseQuery::mDataSet` [protected]

10.31.5.2 mSopInstanceUID

`std::string` `gdcm::BaseQuery::mSopInstanceUID` [protected]

Referenced by [GetSOPInstanceUID\(\)](#), and [SetSOPInstanceUID\(\)](#).

The documentation for this class was generated from the following file:


- [gdcmBaseQuery.h](#)

10.32 gdcm::BaseRootQuery Class Reference


[BaseRootQuery](#).

```
#include <gdcmBaseRootQuery.h>
```

Inheritance diagram for `gdcm::BaseRootQuery`:



Collaboration diagram for `gdcm::BaseRootQuery`:



Public Member Functions

- [~BaseRootQuery](#) () override=default
- [EQueryLevel](#) [GetQueryLevelFromQueryRoot](#) ([ERootType](#) roottype)
- virtual [std::vector< Tag >](#) [GetTagListByLevel](#) (const [EQueryLevel](#) &inQueryLevel)=0
- virtual void [InitializeDataSet](#) (const [EQueryLevel](#) &inQueryLevel)=0
- bool [ValidateQuery](#) (bool inStrict=true) const override=0

Public Member Functions inherited from [gdcm::BaseQuery](#)

- [~BaseQuery](#) () override
- void [AddQueryDataSet](#) (const [DataSet](#) &ds)
- virtual [UIDs::TSName](#) [GetAbstractSyntaxUID](#) () const =0
- [DataSet](#) & [GetQueryDataSet](#) ()
- [DataSet](#) const & [GetQueryDataSet](#) () const
Set/Get the internal representation of the query as a [DataSet](#).
- [std::string](#) [GetSOPInstanceUID](#) () const
- void [Print](#) ([std::ostream](#) &os) const override
- void [SetSearchParameter](#) (const [std::string](#) &inKeyword, const [std::string](#) &inValue)
- void [SetSearchParameter](#) (const [Tag](#) &inTag, const [std::string](#) &inValue)
- void [SetSOPInstanceUID](#) (const [std::string](#) &iSopInstanceUID)
- const [std::ostream](#) & [WriteHelpFile](#) ([std::ostream](#) &os)
- bool [WriteQuery](#) (const [std::string](#) &inFileName)

Public Member Functions inherited from [gdcm::Object](#)

- [Object](#) ()
- [Object](#) (const [Object](#) &)
Special requirement for copy/cstor, assignment operator.
- virtual [~Object](#) ()
- void [operator=](#) (const [Object](#) &)

Static Public Member Functions

- static [QueryBase](#) * [Construct](#) ([ERootType](#) inRootType, [EQueryLevel](#) qllevel)
- static int [GetQueryLevelFromString](#) (const char *str)
- static const char * [GetQueryLevelString](#) ([EQueryLevel](#) ql)

Protected Member Functions

- [BaseRootQuery](#) ()

Protected Member Functions inherited from [gdcm::BaseQuery](#)

- [BaseQuery](#) ()
- void [SetSearchParameter](#) (const [Tag](#) &inTag, const [DictEntry](#) &inDictEntry, const [std::string](#) &inValue)
- bool [ValidDataSet](#) (const [DataSet](#) &dataSetToValid, const [DataSet](#) &dataSetReference) const

Protected Member Functions inherited from [gdcm::Object](#)

- void [Register](#) ()
- void [UnRegister](#) ()

Protected Attributes

- std::string [mHelpDescription](#)
- [QueryImage](#) [mImage](#)
- [QueryPatient](#) [mPatient](#)
- [ERootType](#) [mRootType](#)
- [QuerySeries](#) [mSeries](#)
- [QueryStudy](#) [mStudy](#)

Protected Attributes inherited from [gdcm::BaseQuery](#)

- [DataSet](#) [mDataSet](#)
- std::string [mSopInstanceUID](#)

Friends

- class [QueryFactory](#)

10.32.1 Detailed Description

[BaseRootQuery](#).

contains: a baseclass which will produce a dataset for c-find and c-move with patient/study root

This class contains the functionality used in patient c-find and c-move queries. [PatientRootQuery](#) and [StudyRootQuery](#) derive from this class.

Namely: 1) list all tags associated with a particular query type 2) produce a query dataset via tag association

Eventually, it can be used to validate a particular dataset type.

The dataset held by this object (or, really, one of its derivatives) should be passed to a c-find or c-move query.

10.32.2 Constructor & Destructor Documentation

10.32.2.1 [BaseRootQuery](#)()

```
gdcm::BaseRootQuery::BaseRootQuery () [protected]
```

10.32.2.2 ~BaseRootQuery()

```
gdcmm::BaseRootQuery::~~BaseRootQuery () [override], [default]
```

10.32.3 Member Function Documentation

10.32.3.1 Construct()

```
QueryBase * gdcmm::BaseRootQuery::Construct (
    ERootType inRootType,
    EQueryLevel qllevel) [static]
```

10.32.3.2 GetQueryLevelFromQueryRoot()

```
EQueryLevel gdcmm::BaseRootQuery::GetQueryLevelFromQueryRoot (
    ERootType roottype)
```

10.32.3.3 GetQueryLevelFromString()

```
int gdcmm::BaseRootQuery::GetQueryLevelFromString (
    const char * str) [static]
```

10.32.3.4 GetQueryLevelString()

```
const char * gdcmm::BaseRootQuery::GetQueryLevelString (
    EQueryLevel ql) [static]
```

10.32.3.5 GetTagListByLevel()

```
virtual std::vector< Tag > gdcmm::BaseRootQuery::GetTagListByLevel (
    const EQueryLevel & inQueryLevel) [pure virtual]
```

this function will return all tags at a given query level, so that they maybe selected for searching. The boolean forFind is true if the query is a find query, or false for a move query.

Implemented in [gdcmm::FindPatientRootQuery](#), [gdcmm::FindStudyRootQuery](#), [gdcmm::MovePatientRootQuery](#), [gdcmm::MoveStudyRootQuery](#), and [gdcmm::WLMFindQuery](#).

10.32.3.6 InitializeDataSet()

```
virtual void gdcm::BaseRootQuery::InitializeDataSet (  
    const EQueryLevel & inQueryLevel) [pure virtual]
```

this function sets tag 8,52 to the appropriate value based on query level also fills in the right unique tags, as per the standard's requirements should allow for connection with dcmTk

Implemented in [gdcm::FindPatientRootQuery](#), [gdcm::FindStudyRootQuery](#), [gdcm::MovePatientRootQuery](#), [gdcm::MoveStudyRootQuery](#), and [gdcm::WLMFindQuery](#).

10.32.3.7 ValidateQuery()

```
bool gdcm::BaseRootQuery::ValidateQuery (  
    bool inStrict = true) const [override], [pure virtual]
```

have to be able to ensure that 0x8,0x52 is set (which will be true if InitializeDataSet is called...) that the level is appropriate (ie, not setting PATIENT for a study query that the tags in the query match the right level (either required, unique, optional) by default, this function checks to see if the query is for finding, which is more permissive than for moving. For moving, only the unique tags are allowed. 10 Jan 2011: adding in the 'strict' mode. according to the standard (at least, how I've read it), only tags for a particular level should be allowed in a particular query (ie, just series level tags in a series level query). However, it seems that dcm4chee doesn't share that interpretation. So, if 'inStrict' is false, then tags from the current level and all higher levels are now considered valid. So, if you're doing a non-strict series-level query, tags from the patient and study level can be passed along as well.

Implements [gdcm::BaseQuery](#).

Implemented in [gdcm::FindPatientRootQuery](#), [gdcm::FindStudyRootQuery](#), [gdcm::MovePatientRootQuery](#), [gdcm::MoveStudyRootQuery](#), and [gdcm::WLMFindQuery](#).

10.32.4 Friends And Related Symbol Documentation

10.32.4.1 QueryFactory

```
friend class QueryFactory [friend]
```

References [QueryFactory](#).

Referenced by [QueryFactory](#).

10.32.5 Member Data Documentation

10.32.5.1 mHelpDescription

```
std::string gdcm::BaseRootQuery::mHelpDescription [protected]
```

10.32.5.2 mImage

[QueryImage](#) `gdcm::BaseRootQuery::mImage` [protected]

10.32.5.3 mPatient

[QueryPatient](#) `gdcm::BaseRootQuery::mPatient` [protected]

10.32.5.4 mRootType

[ERootType](#) `gdcm::BaseRootQuery::mRootType` [protected]

10.32.5.5 mSeries

[QuerySeries](#) `gdcm::BaseRootQuery::mSeries` [protected]

10.32.5.6 mStudy

[QueryStudy](#) `gdcm::BaseRootQuery::mStudy` [protected]

The documentation for this class was generated from the following file:


- [gdcmBaseRootQuery.h](#)

10.33 gdcm::SegmentHelper::BasicCodedEntry Struct Reference

This structure defines a basic coded entry with all of its attributes.

```
#include <gdcmSegmentHelper.h>
```

Collaboration diagram for gdcm::SegmentHelper::BasicCodedEntry:



Public Member Functions

- [BasicCodedEntry](#) ()
Constructor.
- [BasicCodedEntry](#) (const char *_a_CV, const char *_a_CSD, const char *_a_CM)
constructor which defines type 1 attributes.
- [BasicCodedEntry](#) (const char *_a_CV, const char *_a_CSD, const char *_a_CSV, const char *_a_CM)
constructor which defines attributes.
- bool [IsEmpty](#) (const bool checkOptionalAttributes=false) const
Check if each attributes of the basic coded entry is defined.

Public Attributes

- std::string [CM](#)
Coding Scheme [Version](#) attribute.
- std::string [CSD](#)
Code [Value](#) attribute.
- std::string [CSV](#)
Coding Scheme Designator attribute.
- std::string [CV](#)

10.33.1 Detailed Description

This structure defines a basic coded entry with all of its attributes.

See also

PS 3.3 section 8.8.

10.33.2 Constructor & Destructor Documentation

10.33.2.1 BasicCodedEntry() [1/3]

```
gdcm::SegmentHelper::BasicCodedEntry::BasicCodedEntry () [inline]
```

Constructor.

References [CM](#), [CSD](#), [CSV](#), and [CV](#).

10.33.2.2 BasicCodedEntry() [2/3]

```
gdcm::SegmentHelper::BasicCodedEntry::BasicCodedEntry (  
    const char * a_CV,  
    const char * a_CSD,  
    const char * a_CM) [inline]
```

constructor which defines type 1 attributes.

References [CM](#), [CSD](#), [CSV](#), and [CV](#).

10.33.2.3 BasicCodedEntry() [3/3]

```
gdcm::SegmentHelper::BasicCodedEntry::BasicCodedEntry (  
    const char * a_CV,  
    const char * a_CSD,  
    const char * a_CSV,  
    const char * a_CM) [inline]
```

constructor which defines attributes.

References [CM](#), [CSD](#), [CSV](#), and [CV](#).

10.33.3 Member Function Documentation

10.33.3.1 IsEmpty()

```
bool gdcm::SegmentHelper::BasicCodedEntry::IsEmpty (  
    const bool checkOptionalAttributes = false) const
```

Check if each attributes of the basic coded entry is defined.

Parameters

<i>checkOptionalAttributes</i>	Check also type 1C attributes.
--------------------------------	--------------------------------

10.33.4 Member Data Documentation

10.33.4.1 CM

```
std::string gdcm::SegmentHelper::BasicCodedEntry::CM
```

Coding Scheme [Version](#) attribute.

Referenced by [BasicCodedEntry\(\)](#), [BasicCodedEntry\(\)](#), and [BasicCodedEntry\(\)](#).

10.33.4.2 CSD

```
std::string gdcm::SegmentHelper::BasicCodedEntry::CSD
```

Code [Value](#) attribute.

Referenced by [BasicCodedEntry\(\)](#), [BasicCodedEntry\(\)](#), and [BasicCodedEntry\(\)](#).

10.33.4.3 CSV

```
std::string gdcm::SegmentHelper::BasicCodedEntry::CSV
```

Coding Scheme Designator attribute.

Referenced by [BasicCodedEntry\(\)](#), [BasicCodedEntry\(\)](#), and [BasicCodedEntry\(\)](#).

10.33.4.4 CV

```
std::string gdcm::SegmentHelper::BasicCodedEntry::CV
```

Referenced by [BasicCodedEntry\(\)](#), [BasicCodedEntry\(\)](#), and [BasicCodedEntry\(\)](#).

The documentation for this struct was generated from the following file:


- [gdcmSegmentHelper.h](#)

10.34 gdcm::BasicOffsetTable Class Reference


Class to represent a [BasicOffsetTable](#).

```
#include <gdcmBasicOffsetTable.h>
```

Inheritance diagram for gdcm::BasicOffsetTable:



Collaboration diagram for gdcm::BasicOffsetTable:



Public Member Functions

- [BasicOffsetTable](#) ()
- `template<typename TSwap>`
`std::istream & Read (std::istream &is)`

Public Member Functions inherited from [gdcm::Fragment](#)

- [Fragment](#) ()
- [VL ComputeLength](#) () const
- [VL GetLength](#) () const
- `template<typename TSwap>`
`std::istream & Read (std::istream &is)`
- `template<typename TSwap>`
`std::istream & ReadBacktrack (std::istream &is)`
- `template<typename TSwap>`
`std::istream & ReadPreValue (std::istream &is)`
- `template<typename TSwap>`
`std::istream & ReadValue (std::istream &is)`
- `template<typename TSwap>`
`std::ostream & Write (std::ostream &os) const`

Public Member Functions inherited from [gdcm::DataElement](#)

- [DataElement](#) (const [DataElement](#) &_val)
- [DataElement](#) (const [Tag](#) &t=[Tag](#)(0), const [VL](#) &vl=0, const [VR](#) &vr=[VR::INVALID](#))
- void [Clear](#) ()
Clear Data [Element](#) (make [Value](#) empty and invalidate [Tag](#) & [VR](#))
- void [Empty](#) ()
Make Data [Element](#) empty (no [Value](#))
- const [ByteValue](#) * [GetByteValue](#) () const
- `template<typename TDE>`
[VL GetLength](#) () const
- [SequenceOfFragments](#) * [GetSequenceOfFragments](#) ()
- const [SequenceOfFragments](#) * [GetSequenceOfFragments](#) () const
- [Tag](#) & [GetTag](#) ()
- const [Tag](#) & [GetTag](#) () const
Get [Tag](#).
- [Value](#) & [GetValue](#) ()
- [Value](#) const & [GetValue](#) () const
Set/Get [Value](#) (bytes array, SQ of items, SQ of fragments):
- [SmartPointer](#)< [SequenceOfItems](#) > [GetValueAsSQ](#) () const
- [VL](#) & [GetVL](#) ()
- const [VL](#) & [GetVL](#) () const
Get [VL](#).
- [VR](#) const & [GetVR](#) () const
- bool [IsEmpty](#) () const
Check if Data [Element](#) is empty.

- bool [IsUndefinedLength](#) () const
return if [Value](#) Length if of undefined length
- bool [operator<](#) (const [DataElement](#) &de) const
- [DataElement](#) & [operator=](#) (const [DataElement](#) &)=default
- bool [operator==](#) (const [DataElement](#) &de) const
- template<typename TDE, typename TSwap>
std::istream & [Read](#) (std::istream &is)
- template<typename TDE, typename TSwap>
std::istream & [ReadOrSkip](#) (std::istream &is, std::set< [Tag](#) > const &skiptags)
- template<typename TDE, typename TSwap>
std::istream & [ReadPreValue](#) (std::istream &is, std::set< [Tag](#) > const &skiptags)
- template<typename TDE, typename TSwap>
std::istream & [ReadValue](#) (std::istream &is, std::set< [Tag](#) > const &skiptags)
- template<typename TDE, typename TSwap>
std::istream & [ReadValueWithLength](#) (std::istream &is, [VL](#) &length, std::set< [Tag](#) > const &skiptags)
- template<typename TDE, typename TSwap>
std::istream & [ReadWithLength](#) (std::istream &is, [VL](#) &length)
- void [SetByteValue](#) (const char *array, [VL](#) length)
- void [SetTag](#) (const [Tag](#) &t)
- void [SetValue](#) ([Value](#) const &vl)
- void [SetVL](#) (const [VL](#) &vl)
- void [SetVLToUndefined](#) ()
- void [SetVR](#) ([VR](#) const &vr)
- template<typename TDE, typename TSwap>
const std::ostream & [Write](#) (std::ostream &os) const

Friends

- std::ostream & [operator<<](#) (std::ostream &os, const [BasicOffsetTable](#) &val)

Additional Inherited Members

Protected Types inherited from [gdcm::DataElement](#)

- typedef [SmartPointer](#)< [Value](#) > [ValuePtr](#)

Protected Member Functions inherited from [gdcm::DataElement](#)

- void [SetValueFieldLength](#) ([VL](#) vl, bool readvalues)

Protected Attributes inherited from [gdcm::DataElement](#)

- [Tag](#) TagField
- [ValuePtr](#) ValueField
- [VL](#) ValueLengthField
- [VR](#) VRField

10.34.1 Detailed Description

Class to represent a [BasicOffsetTable](#).

10.34.2 Constructor & Destructor Documentation

10.34.2.1 BasicOffsetTable()

```
gdcm::BasicOffsetTable::BasicOffsetTable () [inline]
```

References [gdcm::Fragment::Fragment\(\)](#).

Referenced by [operator<<](#).

10.34.3 Member Function Documentation

10.34.3.1 Read()

```
template<typename TSwap>
std::istream & gdcm::BasicOffsetTable::Read (
    std::istream & is) [inline]
```

References [gdcm_assert](#), [gdcmAssertAlwaysMacro](#), [gdcm::ParseException::SetLastElement\(\)](#), [gdcm::DataElement::TagField](#), [gdcm::DataElement::ValueField](#), and [gdcm::DataElement::ValueLengthField](#).

10.34.4 Friends And Related Symbol Documentation

10.34.4.1 operator<<

```
std::ostream & operator<< (
    std::ostream & os,
    const BasicOffsetTable & val) [friend]
```

References [BasicOffsetTable\(\)](#), [gdcm_assert](#), [gdcm::DataElement::GetByteValue\(\)](#), [operator<<](#), [gdcm::DataElement::ValueField](#), and [gdcm::DataElement::ValueLengthField](#).

Referenced by [operator<<](#).

The documentation for this class was generated from the following file:


- [gdcmBasicOffsetTable.h](#)

10.35 gdcm::Bitmap Class Reference


[Bitmap](#) class.

```
#include <gdcmBitmap.h>
```

Inheritance diagram for `gdcm::Bitmap`:



Collaboration diagram for `gdcm::Bitmap`:



Public Member Functions

- [Bitmap](#) ()
- [~Bitmap](#) () override
- virtual bool [AreOverlaysInPixelData](#) () const
- void [Clear](#) ()
- bool [GetBuffer](#) (char *buffer) const
Access the raw data.
- unsigned long [GetBufferLength](#) () const
- unsigned int [GetColumns](#) () const
- [DataElement](#) & [GetDataElement](#) ()
- const [DataElement](#) & [GetDataElement](#) () const
- unsigned int [GetDimension](#) (unsigned int idx) const
- const unsigned int * [GetDimensions](#) () const
Return the dimension of the pixel data, first dimension (x), then 2nd (y), then 3rd (z)...
- [LookupTable](#) & [GetLUT](#) ()
- const [LookupTable](#) & [GetLUT](#) () const
- bool [GetNeedByteSwap](#) () const
INTERNAL do not use.
- unsigned int [GetNumberOfDimensions](#) () const
Return the number of dimension of the pixel data bytes; for example 2 for a 2D matrices of values.
- const [PhotometricInterpretation](#) & [GetPhotometricInterpretation](#) () const
return the photometric interpretation
- [PixelFormat](#) & [GetPixelFormat](#) ()
- const [PixelFormat](#) & [GetPixelFormat](#) () const
Get/Set PixelFormat.
- unsigned int [GetPlanarConfiguration](#) () const
return the planar configuration
- unsigned int [GetRows](#) () const
- const [TransferSyntax](#) & [GetTransferSyntax](#) () const
- bool [IsEmpty](#) () const
- bool [IsLossy](#) () const
Return whether or not the image was compressed using a lossy compressor or not.
- bool [IsTransferSyntaxCompatible](#) ([TransferSyntax](#) const &ts) const
- void [Print](#) (std::ostream &) const override
- void [SetColumns](#) (unsigned int col)
- void [SetDataElement](#) ([DataElement](#) const &de)
- void [SetDimension](#) (unsigned int idx, unsigned int dim)
- void [SetDimensions](#) (const unsigned int dims[3])
- void [SetLossyFlag](#) (bool f)
Specifically set that the image was compressed using a lossy compression mechanism.
- void [SetLUT](#) ([LookupTable](#) const &lut)
Set/Get LUT.
- void [SetNeedByteSwap](#) (bool b)
- void [SetNumberOfDimensions](#) (unsigned int dim)
- void [SetPhotometricInterpretation](#) ([PhotometricInterpretation](#) const &pi)
- void [SetPixelFormat](#) ([PixelFormat](#) const &pf)
- void [SetPlanarConfiguration](#) (unsigned int pc)
- void [SetRows](#) (unsigned int rows)
- void [SetTransferSyntax](#) ([TransferSyntax](#) const &ts)
Transfer syntax.
- virtual bool [UnusedBitsPresentInPixelData](#) () const

Public Member Functions inherited from [gdcm::Object](#)

- [Object](#) ()
- [Object](#) (const [Object](#) &)
Special requirement for copy/cstor, assignment operator.
- virtual [~Object](#) ()
- void [operator=](#) (const [Object](#) &)

Protected Types

- typedef [SmartPointer](#)< [LookupTable](#) > [LUTPtr](#)

Protected Member Functions

- bool [ComputeLossyFlag](#) ()
- bool [GetBuffer2](#) (std::ostream &os) const
- bool [TryJPEG2000Codec](#) (char *buffer, bool &lossyflag) const
- bool [TryJPEG2000Codec2](#) (std::ostream &os) const
- bool [TryJPEGCodec](#) (char *buffer, bool &lossyflag) const
- bool [TryJPEGCodec2](#) (std::ostream &os) const
- bool [TryJPEGLSCodec](#) (char *buffer, bool &lossyflag) const
- bool [TryKAKADUCodec](#) (char *buffer, bool &lossyflag) const
- bool [TryPVRGCodec](#) (char *buffer, bool &lossyflag) const
- bool [TryRAWCodec](#) (char *buffer, bool &lossyflag) const
- bool [TryRLECodec](#) (char *buffer, bool &lossyflag) const

Protected Member Functions inherited from [gdcm::Object](#)

- void [Register](#) ()
- void [UnRegister](#) ()

Protected Attributes

- std::vector< unsigned int > [Dimensions](#)
- bool [LossyFlag](#)
- [LUTPtr](#) [LUT](#)
- bool [NeedByteSwap](#)
- unsigned int [NumberOfDimensions](#)
- [PixelFormat](#) [PF](#)
- [PhotometricInterpretation](#) [PI](#)
- [DataElement](#) [PixelData](#)
- unsigned int [PlanarConfiguration](#)
- [TransferSyntax](#) [TS](#)

Friends

- class [ImageChangeTransferSyntax](#)
- class [PixmapReader](#)

10.35.1 Detailed Description

[Bitmap](#) class.

A bitmap based image. Used as parent for both [IconImage](#) and the main Pixel Data [Image](#) It does not contains any World Space information (IPP, IOP)

10.35.2 Member Typedef Documentation

10.35.2.1 LUTPtr

```
typedef SmartPointer<LookupTable> gdcm::Bitmap::LUTPtr [protected]
```

10.35.3 Constructor & Destructor Documentation

10.35.3.1 Bitmap()

```
gdcm::Bitmap::Bitmap ()
```

10.35.3.2 ~Bitmap()

```
gdcm::Bitmap::~~Bitmap () [override]
```

10.35.4 Member Function Documentation

10.35.4.1 AreOverlaysInPixelData()

```
virtual bool gdcm::Bitmap::AreOverlaysInPixelData () const [inline], [virtual]
```

Reimplemented in [gdcm::Pixmap](#).

10.35.4.2 Clear()

```
void gdcm::Bitmap::Clear ()
```

10.35.4.3 ComputeLossyFlag()

```
bool gdcm::Bitmap::ComputeLossyFlag () [protected]
```

10.35.4.4 GetBuffer()

```
bool gdcm::Bitmap::GetBuffer (
    char * buffer) const
```

Access the raw data.

Examples

[BasicImageAnonymizer.cs](#), [ConvertToQImage.cxx](#), [DecompressImage.cs](#), [DecompressImageMultiframe.cs](#), [DecompressJPEGFile.cs](#), [GetArray.cs](#), [ReadMultiTimesException.cxx](#), and [threadgdcm.cxx](#).

10.35.4.5 GetBuffer2()

```
bool gdcm::Bitmap::GetBuffer2 (
    std::ostream & os) const [protected]
```

10.35.4.6 GetBufferLength()

```
unsigned long gdcm::Bitmap::GetBufferLength () const
```

Return the length of the image after decompression WARNING for palette color: It will NOT take into account the Palette Color thus you need to multiply this length by 3 if computing the size of equivalent RGB image

Examples

[BasicImageAnonymizer.cs](#), [ConvertToQImage.cxx](#), [DecompressImage.cs](#), [DecompressImageMultiframe.cs](#), [DecompressJPEGFile.cs](#), [GetArray.cs](#), [PatchFile.cxx](#), [ReadMultiTimesException.cxx](#), [RescaleImage.cs](#), and [threadgdcm.cxx](#).

10.35.4.7 GetColumns()

```
unsigned int gdcm::Bitmap::GetColumns () const [inline]
```

References [GetDimension\(\)](#).

10.35.4.8 GetDataElement() [1/2]

```
DataElement & gdcm::Bitmap::GetDataElement () [inline]
```

References [PixelData](#).

10.35.4.9 GetDataElement() [2/2]

```
const DataElement & gdcm::Bitmap::GetDataElement () const [inline]
```

Examples

[ExtractIconFromFile.cxx](#).

References [PixelData](#).

10.35.4.10 GetDimension()

```
unsigned int gdcm::Bitmap::GetDimension (  
    unsigned int idx) const
```

Examples

[BasicImageAnonymizer.cs](#), [DecompressImage.cs](#), and [GetArray.cs](#).

Referenced by [GetColumns\(\)](#), and [GetRows\(\)](#).

10.35.4.11 GetDimensions()

```
const unsigned int * gdcm::Bitmap::GetDimensions () const
```

Return the dimension of the pixel data, first dimension (x), then 2nd (y), then 3rd (z)...

Examples

[ConvertToQImage.cxx](#), [ExtractIconFromFile.cxx](#), [FixJAIBugJPEGLS.cxx](#), [HelloVizWorld.cxx](#), and [threadgdcm.cxx](#).

10.35.4.12 GetLUT() [1/2]

```
LookupTable & gdcm::Bitmap::GetLUT () [inline]
```

References [LUT](#).

10.35.4.13 GetLUT() [2/2]

```
const LookupTable & gdcm::Bitmap::GetLUT () const [inline]
```

Examples

[ExtractIconFromFile.cxx](#), [ExtractImageRegionWithLUT.cs](#), and [PrintLUT.cxx](#).

References [LUT](#).

10.35.4.14 GetNeedByteSwap()

```
bool gdcm::Bitmap::GetNeedByteSwap () const [inline]
```

INTERNAL do not use.

References [NeedByteSwap](#).

10.35.4.15 GetNumberOfDimensions()

```
unsigned int gdcm::Bitmap::GetNumberOfDimensions () const
```

Return the number of dimension of the pixel data bytes; for example 2 for a 2D matrices of values.

Examples

[DecompressImage.cs](#), [GetArray.cs](#), [HelloVizWorld.cxx](#), and [threadgdcm.cxx](#).

10.35.4.16 GetPhotometricInterpretation()

```
const PhotometricInterpretation & gdcm::Bitmap::GetPhotometricInterpretation () const
```

return the photometric interpretation

Examples

[ConvertToQImage.cxx](#), [DecompressImage.cs](#), [ExtractIconFromFile.cxx](#), and [HelloVizWorld.cxx](#).

10.35.4.17 GetPixelFormat() [1/2]

```
PixelFormat & gdcm::Bitmap::GetPixelFormat () [inline]
```

References [PF](#).

10.35.4.18 GetPixelFormat() [2/2]

```
const PixelFormat & gdcm::Bitmap::GetPixelFormat () const [inline]
```

Get/Set [PixelFormat](#).

Examples

[ConvertToQImage.cxx](#), [DecompressImage.cs](#), [ExtractIconFromFile.cxx](#), [FixJAIBugJPEGLS.cxx](#), [GetArray.cs](#), [GetJPEGSamplePrecision.cxx](#), [RescaleImage.cs](#), [TemplateEmptyImage.cxx](#), and [threadgdcm.cxx](#).

References [PF](#).

10.35.4.19 GetPlanarConfiguration()

```
unsigned int gdcm::Bitmap::GetPlanarConfiguration () const
```

return the planar configuration

10.35.4.20 GetRows()

```
unsigned int gdcm::Bitmap::GetRows () const [inline]
```

References [GetDimension\(\)](#).

10.35.4.21 GetTransferSyntax()

```
const TransferSyntax & gdcm::Bitmap::GetTransferSyntax () const [inline]
```

Examples

[ExtractIconFromFile.cxx](#).

References [TS](#).

10.35.4.22 IsEmpty()

```
bool gdcm::Bitmap::IsEmpty () const [inline]
```

References [Dimensions](#).

10.35.4.23 IsLossy()

```
bool gdcm::Bitmap::IsLossy () const
```

Return whether or not the image was compressed using a lossy compressor or not.

10.35.4.24 IsTransferSyntaxCompatible()

```
bool gdcm::Bitmap::IsTransferSyntaxCompatible (  
    TransferSyntax const & ts) const
```

10.35.4.25 Print()

```
void gdcm::Bitmap::Print (
    std::ostream & ) const [override], [virtual]
```

Reimplemented from [gdcm::Object](#).

Reimplemented in [gdcm::Image](#), and [gdcm::Pixmap](#).

Examples

[ExtractIconFromFile.cxx](#).

10.35.4.26 SetColumns()

```
void gdcm::Bitmap::SetColumns (
    unsigned int col) [inline]
```

References [SetDimension\(\)](#).

10.35.4.27 SetDataElement()

```
void gdcm::Bitmap::SetDataElement (
    DataElement const & de) [inline]
```

Examples

[BasicImageAnonymizer.cs](#), [CreateARGBImage.cxx](#), [CreateCMYKImage.cxx](#), [DecompressImage.cs](#), [DecompressImageMultiframe.c](#), [DecompressJPEGFile.cs](#), [FileChangeTS.cs](#), [FileChangeTSLossy.cs](#), [MpegVideoInfo.cs](#), [csa2img.cxx](#), and [iU22tomultisc.cxx](#).

References [PixelData](#).

10.35.4.28 SetDimension()

```
void gdcm::Bitmap::SetDimension (
    unsigned int idx,
    unsigned int dim)
```

Examples

[DecompressImageMultiframe.cs](#), [DecompressJPEGFile.cs](#), [FileChangeTS.cs](#), [FileChangeTSLossy.cs](#), [MpegVideoInfo.cs](#), [csa2img.cxx](#), and [iU22tomultisc.cxx](#).

Referenced by [SetColumns\(\)](#), and [SetRows\(\)](#).

10.35.4.29 SetDimensions()

```
void gdcm::Bitmap::SetDimensions (
    const unsigned int dims[3])
```

Examples

[CreateARGBImage.cxx](#), [CreateCMYKImage.cxx](#), and [DecompressImage.cs](#).

10.35.4.30 SetLossyFlag()

```
void gdcm::Bitmap::SetLossyFlag (
    bool f) [inline]
```

Specifically set that the image was compressed using a lossy compression mechanism.

References [LossyFlag](#).

10.35.4.31 SetLUT()

```
void gdcm::Bitmap::SetLUT (
    LookupTable const & lut) [inline]
```

Set/Get LUT.

References [LUT](#), and [gdcm::Object::SmartPointer](#).

10.35.4.32 SetNeedByteSwap()

```
void gdcm::Bitmap::SetNeedByteSwap (
    bool b) [inline]
```

References [NeedByteSwap](#).

10.35.4.33 SetNumberOfDimensions()

```
void gdcm::Bitmap::SetNumberOfDimensions (
    unsigned int dim)
```

Examples

[CreateARGBImage.cxx](#), [CreateCMYKImage.cxx](#), [DecompressImage.cs](#), [DecompressImageMultiframe.cs](#), [DecompressJPEGFile.cs](#), [FileChangeTS.cs](#), [FileChangeTSLossy.cs](#), [MpegVideoInfo.cs](#), [csa2img.cxx](#), and [iU22tomultisc.cxx](#).

10.35.4.34 SetPhotometricInterpretation()

```
void gdcM::Bitmap::SetPhotometricInterpretation (
    PhotometricInterpretation const & pi)
```

Examples

[CreateARGBImage.cxx](#), [CreateCMYKImage.cxx](#), [DecompressImage.cs](#), [DecompressImageMultiframe.cs](#), [DecompressJPEGFile.cs](#), [FileChangeTS.cs](#), [FileChangeTSLossy.cs](#), [MpegVideoInfo.cs](#), [csa2img.cxx](#), and [iU22tomultisc.cxx](#).

10.35.4.35 SetPixelFormat()

```
void gdcM::Bitmap::SetPixelFormat (
    PixelFormat const & pf) [inline]
```

Examples

[CreateARGBImage.cxx](#), [CreateCMYKImage.cxx](#), [DecompressImage.cs](#), [DecompressImageMultiframe.cs](#), [DecompressJPEGFile.cs](#), [MpegVideoInfo.cs](#), [csa2img.cxx](#), and [iU22tomultisc.cxx](#).

References [PF](#).

10.35.4.36 SetPlanarConfiguration()

```
void gdcM::Bitmap::SetPlanarConfiguration (
    unsigned int pc)
```

Warning

you need to call `SetPixelFormat` first (before `SetPlanarConfiguration`) for consistency checking

10.35.4.37 SetRows()

```
void gdcM::Bitmap::SetRows (
    unsigned int rows) [inline]
```

References [SetDimension\(\)](#).

10.35.4.38 SetTransferSyntax()

```
void gdcm::Bitmap::SetTransferSyntax (
    TransferSyntax const & ts) [inline]
```

Transfer syntax.

Examples

[BasicImageAnonymizer.cs](#), [CreateARGBImage.cxx](#), [CreateCMYKImage.cxx](#), [DecompressImageMultiframe.cs](#), [DecompressJPEGFile.cs](#), [MergeTwoFiles.cxx](#), and [MpegVideoInfo.cs](#).

References [TS](#).

10.35.4.39 TryJPEG2000Codec()

```
bool gdcm::Bitmap::TryJPEG2000Codec (
    char * buffer,
    bool & lossyflag) const [protected]
```

10.35.4.40 TryJPEG2000Codec2()

```
bool gdcm::Bitmap::TryJPEG2000Codec2 (
    std::ostream & os) const [protected]
```

10.35.4.41 TryJPEGCodec()

```
bool gdcm::Bitmap::TryJPEGCodec (
    char * buffer,
    bool & lossyflag) const [protected]
```

10.35.4.42 TryJPEGCodec2()

```
bool gdcm::Bitmap::TryJPEGCodec2 (
    std::ostream & os) const [protected]
```

10.35.4.43 TryJPEGLSCodec()

```
bool gdcm::Bitmap::TryJPEGLSCodec (
    char * buffer,
    bool & lossyflag) const [protected]
```

10.35.4.44 TryKAKADUCodec()

```
bool gdcmm::Bitmap::TryKAKADUCodec (
    char * buffer,
    bool & lossyflag) const [protected]
```

10.35.4.45 TryPVRGCodec()

```
bool gdcmm::Bitmap::TryPVRGCodec (
    char * buffer,
    bool & lossyflag) const [protected]
```

10.35.4.46 TryRAWCodec()

```
bool gdcmm::Bitmap::TryRAWCodec (
    char * buffer,
    bool & lossyflag) const [protected]
```

10.35.4.47 TryRLECodec()

```
bool gdcmm::Bitmap::TryRLECodec (
    char * buffer,
    bool & lossyflag) const [protected]
```

10.35.4.48 UnusedBitsPresentInPixelData()

```
virtual bool gdcmm::Bitmap::UnusedBitsPresentInPixelData () const [inline], [virtual]
```

Reimplemented in [gdcmm::Pixmap](#).

10.35.5 Friends And Related Symbol Documentation

10.35.5.1 ImageChangeTransferSyntax

```
friend class ImageChangeTransferSyntax [friend]
```

References [ImageChangeTransferSyntax](#).

Referenced by [ImageChangeTransferSyntax](#).

10.35.5.2 PixmapReader

friend class [PixmapReader](#) [friend]

References [PixmapReader](#).

Referenced by [PixmapReader](#).

10.35.6 Member Data Documentation

10.35.6.1 Dimensions

`std::vector<unsigned int> gdcm::Bitmap::Dimensions` [protected]

Referenced by [IsEmpty\(\)](#).

10.35.6.2 LossyFlag

`bool gdcm::Bitmap::LossyFlag` [protected]

Referenced by [SetLossyFlag\(\)](#).

10.35.6.3 LUT

`LUTPtr gdcm::Bitmap::LUT` [protected]

Referenced by [GetLUT\(\)](#), [GetLUT\(\)](#), and [SetLUT\(\)](#).

10.35.6.4 NeedByteSwap

`bool gdcm::Bitmap::NeedByteSwap` [protected]

Referenced by [GetNeedByteSwap\(\)](#), and [SetNeedByteSwap\(\)](#).

10.35.6.5 NumberOfDimensions

`unsigned int gdcm::Bitmap::NumberOfDimensions` [protected]

10.35.6.6 PF

`PixelFormat gdcm::Bitmap::PF` [protected]

Referenced by [GetPixelFormat\(\)](#), [GetPixelFormat\(\)](#), and [SetPixelFormat\(\)](#).

10.35.6.7 PI

`PhotometricInterpretation` `gdcm::Bitmap::PI` [protected]

10.35.6.8 PixelData

`DataElement` `gdcm::Bitmap::PixelData` [protected]

Referenced by [GetDataElement\(\)](#), [GetDataElement\(\)](#), and [SetDataElement\(\)](#).

10.35.6.9 PlanarConfiguration

`unsigned int` `gdcm::Bitmap::PlanarConfiguration` [protected]

10.35.6.10 TS

`TransferSyntax` `gdcm::Bitmap::TS` [protected]

Referenced by [GetTransferSyntax\(\)](#), and [SetTransferSyntax\(\)](#).

The documentation for this class was generated from the following file:


- [gdcmBitmap.h](#)

10.36 gdcm::BitmapToBitmapFilter Class Reference


[BitmapToBitmapFilter](#) class.

```
#include <gdcmBitmapToBitmapFilter.h>
```

Inheritance diagram for `gdcm::BitmapToBitmapFilter`:



Collaboration diagram for gdcm::BitmapToBitmapFilter:



Public Member Functions

- [BitmapToBitmapFilter](#) ()
- [~BitmapToBitmapFilter](#) ()=default
- const [Bitmap](#) & [GetOutput](#) () const
Get Output image.
- const [Bitmap](#) & [GetOutputAsBitmap](#) () const
- void [SetInput](#) (const [Bitmap](#) &image)
Set input image.

Protected Attributes

- [SmartPointer](#)< [Bitmap](#) > [Input](#)
- [SmartPointer](#)< [Bitmap](#) > [Output](#)

10.36.1 Detailed Description

[BitmapToBitmapFilter](#) class.

Super class for all filter taking an image and producing an output image

10.36.2 Constructor & Destructor Documentation

10.36.2.1 `BitmapToBitmapFilter()`

```
gdcmm::BitmapToBitmapFilter::BitmapToBitmapFilter ()
```

10.36.2.2 `~BitmapToBitmapFilter()`

```
gdcmm::BitmapToBitmapFilter::~~BitmapToBitmapFilter () [default]
```

10.36.3 Member Function Documentation

10.36.3.1 `GetOutput()`

```
const Bitmap & gdcmm::BitmapToBitmapFilter::GetOutput () const [inline]
```

Get Output image.

References [Output](#).

10.36.3.2 `GetOutputAsBitmap()`

```
const Bitmap & gdcmm::BitmapToBitmapFilter::GetOutputAsBitmap () const
```

10.36.3.3 `SetInput()`

```
void gdcmm::BitmapToBitmapFilter::SetInput (  
    const Bitmap & image)
```

Set input image.

Examples

[BasicImageAnonymizer.cs](#), [CompressImage.cxx](#), [CompressLossyJPEG.cs](#), [ExplicitLittleEndian.cs](#), and [StandardizeFiles.cs](#).

10.36.4 Member Data Documentation

10.36.4.1 `Input`

```
SmartPointer<Bitmap> gdcmm::BitmapToBitmapFilter::Input [protected]
```

10.36.4.2 Output

`SmartPointer<Bitmap> gdcm::BitmapToBitmapFilter::Output` [protected]

Referenced by [GetOutput\(\)](#).

The documentation for this class was generated from the following file:


- [gdcmBitmapToBitmapFilter.h](#)

10.37 gdcm::BoxRegion Class Reference


Class for manipulation box region.

```
#include <gdcmBoxRegion.h>
```

Inheritance diagram for gdcm::BoxRegion:



Collaboration diagram for gdcm::BoxRegion:



Public Member Functions

- [BoxRegion](#) ()
- [BoxRegion](#) (const [BoxRegion](#) &)
copy/cstor and al.
- [~BoxRegion](#) () override
- [size_t Area](#) () const override
compute the area
- [Region * Clone](#) () const override
- [BoxRegion ComputeBoundingBox](#) () override
Return the Axis-Aligned minimum bounding box for all regions.
- [bool Empty](#) () const override
return whether this domain is empty:
- [unsigned int GetXMax](#) () const
- [unsigned int GetXMin](#) () const
Get domain.
- [unsigned int GetYMax](#) () const
- [unsigned int GetYMin](#) () const
- [unsigned int GetZMax](#) () const
- [unsigned int GetZMin](#) () const
- [bool IsValid](#) () const override
return whether this is valid domain
- [void operator=](#) (const [BoxRegion](#) &)
- [void Print](#) (std::ostream &os=std::cout) const override
Print.
- [void SetDomain](#) (unsigned int xmin, unsigned int xmax, unsigned int ymin, unsigned int ymax, unsigned int zmin, unsigned int zmax)
Set domain.

Public Member Functions inherited from [gdcm::Region](#)

- [Region](#) ()
- virtual [~Region](#) ()

Static Public Member Functions

- static [BoxRegion BoundingBox](#) ([BoxRegion](#) const &b1, [BoxRegion](#) const &b2)
Helper class to compute the bounding box of two [BoxRegion](#).

10.37.1 Detailed Description

Class for manipulation box region.

This is a very simple implementation of the [Region](#) class. It only support 3D box type region. It assumes the 3D Box does not have a tilt Origin is as (0,0,0)

Examples

[ExtractImageRegion.cs](#), and [ExtractImageRegionWithLUT.cs](#).

10.37.2 Constructor & Destructor Documentation

10.37.2.1 BoxRegion() [1/2]

```
gdcm::BoxRegion::BoxRegion ()
```

Referenced by [BoxRegion\(\)](#), [BoundingBox\(\)](#), [ComputeBoundingBox\(\)](#), and [operator=\(\)](#).

10.37.2.2 ~BoxRegion()

```
gdcm::BoxRegion::~~BoxRegion () [override]
```

10.37.2.3 BoxRegion() [2/2]

```
gdcm::BoxRegion::BoxRegion (  
    const BoxRegion & )
```

copy/cstor and al.

References [BoxRegion\(\)](#).

10.37.3 Member Function Documentation

10.37.3.1 Area()

```
size_t gdcm::BoxRegion::Area () const [override], [virtual]
```

compute the area

Implements [gdcm::Region](#).

10.37.3.2 BoundingBox()

```
BoxRegion gdcm::BoxRegion::BoundingBox (  
    BoxRegion const & b1,  
    BoxRegion const & b2) [static]
```

Helper class to compute the bounding box of two [BoxRegion](#).

References [BoxRegion\(\)](#).

10.37.3.3 Clone()

```
Region * gdcM::BoxRegion::Clone () const [override], [virtual]
```

Implements [gdcM::Region](#).

References [gdcM::Region::Region\(\)](#).

10.37.3.4 ComputeBoundingBox()

```
BoxRegion gdcM::BoxRegion::ComputeBoundingBox () [override], [virtual]
```

Return the Axis-Aligned minimum bounding box for all regions.

Implements [gdcM::Region](#).

References [BoxRegion\(\)](#).

10.37.3.5 Empty()

```
bool gdcM::BoxRegion::Empty () const [override], [virtual]
```

return whether this domain is empty:

Implements [gdcM::Region](#).

10.37.3.6 GetXMax()

```
unsigned int gdcM::BoxRegion::GetXMax () const
```

10.37.3.7 GetXMin()

```
unsigned int gdcM::BoxRegion::GetXMin () const
```

Get domain.

10.37.3.8 GetYMax()

```
unsigned int gdcM::BoxRegion::GetYMax () const
```

10.37.3.9 GetYMin()

```
unsigned int gdcM::BoxRegion::GetYMin () const
```


10.37.3.10 GetZMax()

```
unsigned int gdcm::BoxRegion::GetZMax () const
```

10.37.3.11 GetZMin()

```
unsigned int gdcm::BoxRegion::GetZMin () const
```

10.37.3.12 IsValid()

```
bool gdcm::BoxRegion::IsValid () const [override], [virtual]
```

return whether this is valid domain

Implements [gdcm::Region](#).

10.37.3.13 operator=()

```
void gdcm::BoxRegion::operator= (
    const BoxRegion & )
```

References [BoxRegion\(\)](#).

10.37.3.14 Print()

```
void gdcm::BoxRegion::Print (
    std::ostream & os = std::cout) const [override], [virtual]
```

Print.

Reimplemented from [gdcm::Region](#).

10.37.3.15 SetDomain()

```
void gdcm::BoxRegion::SetDomain (
    unsigned int xmin,
    unsigned int xmax,
    unsigned int ymin,
    unsigned int ymax,
    unsigned int zmin,
    unsigned int zmax)
```

Set domain.

Examples

[ExtractImageRegion.cs](#), and [ExtractImageRegionWithLUT.cs](#).

The documentation for this class was generated from the following file:

- [gdcmBoxRegion.h](#)

10.38 gdcm::ByteBuffer Class Reference

[ByteBuffer](#).

```
#include <gdcmByteBuffer.h>
```

Public Member Functions

- [ByteBuffer](#) ()
- char * [Get](#) (int len)
- const char * [GetStart](#) () const
- void [ShiftEnd](#) (int len)
- void [UpdatePosition](#) ()

10.38.1 Detailed Description

[ByteBuffer](#).

Detailed description here

Note

looks like a std::streambuf or std::filebuf class with the get and peek pointer

10.38.2 Constructor & Destructor Documentation

10.38.2.1 ByteBuffer()

```
gdcm::ByteBuffer::ByteBuffer () [inline]
```

10.38.3 Member Function Documentation

10.38.3.1 Get()

```
char * gdcm::ByteBuffer::Get (  
    int len) [inline]
```

References [gdcm_assert](#).

10.38.3.2 GetStart()

```
const char * gdcm::ByteBuffer::GetStart () const [inline]
```

10.38.3.3 ShiftEnd()

```
void gdcm::ByteBuffer::ShiftEnd (
    int len) [inline]
```

10.38.3.4 UpdatePosition()

```
void gdcm::ByteBuffer::UpdatePosition () [inline]
```

The documentation for this class was generated from the following file:

- [gdcmByteBuffer.h](#)

10.39 gdcm::ByteSwap< T > Class Template Reference

[ByteSwap](#).

```
#include <gdcmByteSwap.h>
```

Static Public Member Functions

- static void [Swap](#) (T &p)
- static void [SwapFromSwapCodeIntoSystem](#) (T &p, [SwapCode](#) const &sc)
- static void [SwapRange](#) (T *p, unsigned int num)
- static void [SwapRangeFromSwapCodeIntoSystem](#) (T *p, [SwapCode](#) const &sc, std::streamoff num)
- static bool [SystemIsBigEndian](#) ()
- static bool [SystemIsLittleEndian](#) ()

10.39.1 Detailed Description

```
template<class T>
class gdcm::ByteSwap< T >
```

[ByteSwap](#).

Perform machine dependent byte swapping (Little Endian, Big Endian, Bad Little Endian, Bad Big Endian). TODO: bswap_32 / bswap_64 ...

10.39.2 Member Function Documentation

10.39.2.1 Swap()

```
template<class T>
void gdcm::ByteSwap< T >::Swap (
    T & p) [static]
```

10.39.2.2 SwapFromSwapCodeIntoSystem()

```
template<class T>
void gdcmm::ByteSwap< T >::SwapFromSwapCodeIntoSystem (
    T & p,
    SwapCode const & sc) [static]
```

Examples

[TestByteSwap.cxx](#).

10.39.2.3 SwapRange()

```
template<class T>
void gdcmm::ByteSwap< T >::SwapRange (
    T * p,
    unsigned int num) [static]
```

10.39.2.4 SwapRangeFromSwapCodeIntoSystem()

```
template<class T>
void gdcmm::ByteSwap< T >::SwapRangeFromSwapCodeIntoSystem (
    T * p,
    SwapCode const & sc,
    std::streamoff num) [static]
```

Examples

[TestByteSwap.cxx](#).

10.39.2.5 SystemIsBigEndian()

```
template<class T>
bool gdcmm::ByteSwap< T >::SystemIsBigEndian () [static]
```

Query the machine Endian-ness.

Examples

[TestByteSwap.cxx](#).

10.39.2.6 SystemIsLittleEndian()

```
template<class T>
bool gdcm::ByteSwap< T >::SystemIsLittleEndian () [static]
```

Examples

[TestByteSwap.cxx](#).

The documentation for this class was generated from the following file:

- [gdcmByteSwap.h](#)

10.40 gdcm::ByteSwapFilter Class Reference

[ByteSwapFilter](#).

```
#include <gdcmByteSwapFilter.h>
```

Public Member Functions

- [ByteSwapFilter](#) (const [ByteSwapFilter](#) &)=delete
- [ByteSwapFilter](#) ([DataSet](#) &ds)
- [~ByteSwapFilter](#) ()=default
- bool [ByteSwap](#) ()
- [ByteSwapFilter](#) & [operator=](#) (const [ByteSwapFilter](#) &)=delete
- void [SetByteSwapTag](#) (bool b)

10.40.1 Detailed Description

[ByteSwapFilter](#).

In place byte-swapping of a dataset FIXME: FL status ??

10.40.2 Constructor & Destructor Documentation

10.40.2.1 ByteSwapFilter() [1/2]

```
gdcm::ByteSwapFilter::ByteSwapFilter (
    DataSet & ds) [inline]
```

Referenced by [ByteSwapFilter\(\)](#), and [operator=\(\)](#).

10.40.2.2 ~ByteSwapFilter()

```
gdcm::ByteSwapFilter::~~ByteSwapFilter () [default]
```

10.40.2.3 ByteSwapFilter() [2/2]

```
gdcm::ByteSwapFilter::ByteSwapFilter (  
    const ByteSwapFilter & ) [delete]
```

References [ByteSwapFilter\(\)](#).

10.40.3 Member Function Documentation

10.40.3.1 ByteSwap()

```
bool gdcm::ByteSwapFilter::ByteSwap ()
```

Referenced by [gdcm::Item::Read\(\)](#).

10.40.3.2 operator=()

```
ByteSwapFilter & gdcm::ByteSwapFilter::operator= (  
    const ByteSwapFilter & ) [delete]
```

References [ByteSwapFilter\(\)](#).

10.40.3.3 SetByteSwapTag()

```
void gdcm::ByteSwapFilter::SetByteSwapTag (  
    bool b) [inline]
```

Referenced by [gdcm::Item::Read\(\)](#).

The documentation for this class was generated from the following file:


- [gdcmByteSwapFilter.h](#)

10.41 gdcm::ByteValue Class Reference


Class to represent binary value (array of bytes)

```
#include <gdcmByteValue.h>
```

Inheritance diagram for gdcm::ByteValue:



Collaboration diagram for gdcm::ByteValue:



Public Member Functions

- [ByteValue](#) (const char *array=nullptr, [VL](#) const &vl=0)
- [ByteValue](#) (std::vector< char > &v)
- [~ByteValue](#) () override
- void [Append](#) ([ByteValue](#) const &bv)
- void [Clear](#) () override
- [VL ComputeLength](#) () const
- void [Fill](#) (char c)
- bool [GetBuffer](#) (char *buffer, unsigned long length) const
- [VL GetLength](#) () const override
- const char * [GetPointer](#) () const
- void * [GetVoidPointer](#) ()
- const void * [GetVoidPointer](#) () const
- bool [IsEmpty](#) () const
- bool [IsPrintable](#) ([VL](#) length) const

Checks whether a 'ByteValue' is printable or not (in order to avoid corrupting the terminal of invocation when printing) I don't think this function is working since it does not handle UNICODE or character set...
- [operator const std::vector< char > &](#) () const
- [ByteValue](#) & [operator=](#) (const [ByteValue](#) &val)
- bool [operator==](#) (const [ByteValue](#) &val) const
- bool [operator==](#) (const [Value](#) &val) const override
- void [PrintASCII](#) (std::ostream &os, [VL](#) maxlength) const
- void [PrintASCIIXML](#) (std::ostream &os) const
- void [PrintGroupLength](#) (std::ostream &os)
- void [PrintHex](#) (std::ostream &os, [VL](#) maxlength) const
- void [PrintHexXML](#) (std::ostream &os) const
- void [PrintPNXML](#) (std::ostream &os) const
- template<typename TSwap>
 [std::istream & Read](#) (std::istream &is)
- template<typename TSwap, typename TType>
 [std::istream & Read](#) (std::istream &is, bool readvalues=true)
- void [SetLength](#) ([VL](#) vl) override
- template<typename TSwap, typename TType>
 [std::ostream const & Write](#) (std::ostream &os) const
- template<typename TSwap>
 [std::ostream const & Write](#) (std::ostream &os) const
- bool [WriteBuffer](#) (std::ostream &os) const

Public Member Functions inherited from [gdcm::Value](#)

- [Value](#) ()=default
- [~Value](#) () override=default

Public Member Functions inherited from [gdcm::Object](#)

- [Object](#) ()
- [Object](#) (const [Object](#) &)
- *Special requirement for copy/cstor, assignment operator.*
- virtual [~Object](#) ()
- void [operator=](#) (const [Object](#) &)

Protected Member Functions

- void [Print](#) (std::ostream &os) const override
- void [SetLengthOnly](#) ([VL](#) vl) override

Protected Member Functions inherited from [gdcm::Object](#)

- void [Register](#) ()
- void [UnRegister](#) ()

10.41.1 Detailed Description

Class to represent binary value (array of bytes)

Examples

[DumpADAC.cxx](#), [DumpExamCard.cxx](#), [DumpGEMSMovieGroup.cxx](#), [DumpImageHeaderInfo.cxx](#), [DumpPhilipsECHO.cxx](#), [DumpSiemensBase64.cxx](#), [DumpToshibaDTI.cxx](#), [DumpToshibaDTI2.cxx](#), [DuplicatePCDE.cxx](#), [ELSCINT1WaveToText.cxx](#), [ExtractEncapsulatedFile.cs](#), [ExtractEncryptedContent.cxx](#), [ExtractIconFromFile.cxx](#), [FixBrokenJ2K.cxx](#), [FixJAIBugJPEGLS.cxx](#), [GetSubSequenceData.cxx](#), [MrProtocol.cxx](#), [PatchFile.cxx](#), [ReadExplicitLengthSQIVR.cxx](#), [pmsct_rgb1.cxx](#), and [rle2img.cxx](#).

10.41.2 Constructor & Destructor Documentation

10.41.2.1 ByteValue() [1/2]

```
gdcm::ByteValue::ByteValue (
    const char * array = nullptr,
    VL const & vl = 0) [inline]
```

Referenced by [Append\(\)](#), [operator=\(\)](#), [operator==\(\)](#), and [operator==\(\)](#).

10.41.2.2 ByteValue() [2/2]

```
gdcm::ByteValue::ByteValue (
    std::vector< char > & v) [inline]
```

Warning

casting to uint32_t

10.41.2.3 ~ByteValue()

```
gdcm::ByteValue::~~ByteValue () [inline], [override]
```

10.41.3 Member Function Documentation

10.41.3.1 Append()

```
void gdcM::ByteValue::Append (  
    ByteValue const & bv)
```

References [ByteValue\(\)](#).

10.41.3.2 Clear()

```
void gdcM::ByteValue::Clear () [inline], [override], [virtual]
```

Implements [gdcM::Value](#).

10.41.3.3 ComputeLength()

```
VL gdcM::ByteValue::ComputeLength () const [inline]
```

Referenced by [gdcM::Fragment::Write\(\)](#).

10.41.3.4 Fill()

```
void gdcM::ByteValue::Fill (  
    char c) [inline]
```

Examples

[DuplicatePCDE.cxx](#).

10.41.3.5 GetBuffer()

```
bool gdcM::ByteValue::GetBuffer (  
    char * buffer,  
    unsigned long length) const
```

Examples

[ExtractEncapsulatedFile.cs](#), and [FixJAIBugJPEGLS.cxx](#).

10.41.3.6 GetLength()

```
VL gdcm::ByteValue::GetLength () const [inline], [override], [virtual]
```

Implements [gdcm::Value](#).

Examples

[DumpADAC.cxx](#), [DumpExamCard.cxx](#), [DumpGEMSMovieGroup.cxx](#), [DumpImageHeaderInfo.cxx](#), [DumpPhilipsECHO.cxx](#), [DumpSiemensBase64.cxx](#), [DumpToshibaDTI.cxx](#), [DumpToshibaDTI2.cxx](#), [ELSCINT1WaveToText.cxx](#), [ExtractEncapsulatedFile.cs](#), [ExtractEncryptedContent.cxx](#), [ExtractIconFromFile.cxx](#), [FixBrokenJ2K.cxx](#), [FixJAI BugJPEGLS.cxx](#), [GetSubSequenceData.cxx](#), [MrProtocol.cxx](#), [PatchFile.cxx](#), [ReadExplicitLengthSQIVR.cxx](#), [ReadGEMSSDO.cxx](#), [pmsct_rgb1.cxx](#), and [rle2img.cxx](#).

Referenced by [gdcm::CSAElement::operator<<](#), [gdcm::SequenceOfFragments::ReadValue\(\)](#), [gdcm::Element< TVR, TVM >::Set\(\)](#), [gdcm::Attribute< Group, Element, TVR, TVM >::SetByteValue\(\)](#), [gdcm::Attribute< Group, Element, TVR, VM::VM1 >::SetByteValue\(\)](#), [gdcm::Attribute< Group, Element, TVR, VM::VM1_n >::SetByteValue\(\)](#), [gdcm::Attribute< Group, Element, TVR, TVM >::SetByteValueNoSwap\(\)](#), [gdcm::Attribute< Group, Element, TVR, VM::VM1 >::SetByteValueNoSwap\(\)](#), [gdcm::Element< TVR, TVM >::SetNoSwap\(\)](#), and [gdcm::Fragment::Write\(\)](#).

10.41.3.7 GetPointer()

```
const char * gdcm::ByteValue::GetPointer () const [inline]
```

Examples

[DumpADAC.cxx](#), [DumpExamCard.cxx](#), [DumpGEMSMovieGroup.cxx](#), [DumpImageHeaderInfo.cxx](#), [DumpPhilipsECHO.cxx](#), [DumpSiemensBase64.cxx](#), [DumpToshibaDTI.cxx](#), [DumpToshibaDTI2.cxx](#), [ELSCINT1WaveToText.cxx](#), [ExtractEncryptedContent.cxx](#), [ExtractIconFromFile.cxx](#), [GetSubSequenceData.cxx](#), [MrProtocol.cxx](#), [ReadExplicitLengthSQIVR.cxx](#), [ReadGEMSSDO.cxx](#), [pmsct_rgb1.cxx](#), and [rle2img.cxx](#).

Referenced by [gdcm::CSAElement::operator<<](#), [gdcm::SequenceOfFragments::ReadValue\(\)](#), [gdcm::Element< TVR, TVM >::Set\(\)](#), [gdcm::Attribute< Group, Element, TVR, TVM >::SetByteValue\(\)](#), [gdcm::Attribute< Group, Element, TVR, VM::VM1 >::SetByteValue\(\)](#), [gdcm::Attribute< Group, Element, TVR, VM::VM1_n >::SetByteValue\(\)](#), [gdcm::Attribute< Group, Element, TVR, TVM >::SetByteValueNoSwap\(\)](#), [gdcm::Attribute< Group, Element, TVR, VM::VM1 >::SetByteValueNoSwap\(\)](#), and [gdcm::Element< TVR, TVM >::SetNoSwap\(\)](#).

10.41.3.8 GetVoidPointer() [1/2]

```
void * gdcm::ByteValue::GetVoidPointer () [inline]
```

10.41.3.9 GetVoidPointer() [2/2]

```
const void * gdcm::ByteValue::GetVoidPointer () const [inline]
```

Examples

[FixBrokenJ2K.cxx](#).

Referenced by [Read\(\)](#).

10.41.3.10 IsEmpty()

```
bool gdcm::ByteValue::IsEmpty () const [inline]
```

References [gdcm_assert](#).

10.41.3.11 IsPrintable()

```
bool gdcm::ByteValue::IsPrintable (
    VL length) const [inline]
```

Checks whether a 'ByteValue' is printable or not (in order to avoid corrupting the terminal of invocation when printing) I don't think this function is working since it does not handle UNICODE or character set...

References [gdcm_assert](#).

Referenced by [Print\(\)](#).

10.41.3.12 operator const std::vector< char > &()

```
gdcm::ByteValue::operator const std::vector< char > & () const [inline]
```

10.41.3.13 operator=()

```
ByteValue & gdcm::ByteValue::operator= (
    const ByteValue & val) [inline]
```

References [ByteValue\(\)](#).

10.41.3.14 operator==() [1/2]

```
bool gdcm::ByteValue::operator== (
    const ByteValue & val) const [inline]
```

References [ByteValue\(\)](#).

10.41.3.15 operator==() [2/2]

```
bool gdcm::ByteValue::operator== (
    const Value & val) const [inline], [override], [virtual]
```

Implements [gdcm::Value](#).

References [ByteValue\(\)](#), and [gdcm::Value::Value\(\)](#).

10.41.3.16 Print()

```
void gdcmm::ByteValue::Print (
    std::ostream & os) const    [inline], [override], [protected], [virtual]
```

Reimplemented from [gdcmm::Object](#).

References [IsPrintable\(\)](#).

10.41.3.17 PrintASCII()

```
void gdcmm::ByteValue::PrintASCII (
    std::ostream & os,
    VL maxlength) const
```

10.41.3.18 PrintASCIIXML()

```
void gdcmm::ByteValue::PrintASCIIXML (
    std::ostream & os) const
```

10.41.3.19 PrintGroupLength()

```
void gdcmm::ByteValue::PrintGroupLength (
    std::ostream & os) [inline]
```

References [gdcmm_assert](#).

10.41.3.20 PrintHex()

```
void gdcmm::ByteValue::PrintHex (
    std::ostream & os,
    VL maxlength) const
```

10.41.3.21 PrintHexXML()

```
void gdcmm::ByteValue::PrintHexXML (
    std::ostream & os) const
```

10.41.3.22 PrintPNXML()

```
void gdcmm::ByteValue::PrintPNXML (
    std::ostream & os) const
```

To Print Values in Native DICOM format

10.41.3.23 Read() [1/2]

```
template<typename TSwap>
std::istream & gdcm::ByteValue::Read (
    std::istream & is) [inline]
```

References [Read\(\)](#).

10.41.3.24 Read() [2/2]

```
template<typename TSwap, typename TType>
std::istream & gdcm::ByteValue::Read (
    std::istream & is,
    bool readvalues = true) [inline]
```

References [gdcm_assert](#), and [GetVoidPointer\(\)](#).

Referenced by [Read\(\)](#).

10.41.3.25 SetLength()

```
void gdcm::ByteValue::SetLength (
    VL vl) [override], [virtual]
```

Implements [gdcm::Value](#).

10.41.3.26 SetLengthOnly()

```
void gdcm::ByteValue::SetLengthOnly (
    VL vl) [inline], [override], [protected], [virtual]
```

Reimplemented from [gdcm::Value](#).

10.41.3.27 Write() [1/2]

```
template<typename TSwap, typename TType>
std::ostream const & gdcm::ByteValue::Write (
    std::ostream & os) const [inline]
```

References [gdcm_assert](#).

Referenced by [Write\(\)](#), and [gdcm::Fragment::Write\(\)](#).

10.41.3.28 Write() [2/2]

```
template<typename TSwap>
std::ostream const & gdcm::ByteValue::Write (
    std::ostream & os) const [inline]
```

References [Write\(\)](#).

10.41.3.29 WriteBuffer()

```
bool gdcm::ByteValue::WriteBuffer (
    std::ostream & os) const [inline]
```

References [gdcm_assert](#).


The documentation for this class was generated from the following file:

- [gdcmByteValue.h](#)


10.42 gdcm::CAPICryptoFactory Class Reference

```
#include <gdcmCAPICryptoFactory.h>
```

Inheritance diagram for gdcm::CAPICryptoFactory:



Collaboration diagram for gdcm::CAPICryptoFactory:



Public Member Functions

- [CAPICryptoFactory](#) ([CryptoLib](#) id)
- [CryptographicMessageSyntax](#) * [CreateCMSProvider](#) ()

Additional Inherited Members

Public Types inherited from [gdcmm::CryptoFactory](#)

- enum [CryptoLib](#) {
 [DEFAULT](#) = 0 ,
 [OPENSSL](#) = 1 ,
 [CAPI](#) = 2 ,
 [OPENSSL7](#) = 3 }

Static Public Member Functions inherited from [gdcmm::CryptoFactory](#)

- static [CryptoFactory](#) * [GetFactoryInstance](#) ([CryptoLib](#) id=[DEFAULT](#))

Protected Member Functions inherited from [gdcmm::CryptoFactory](#)

- [CryptoFactory](#) ()=default
- [CryptoFactory](#) ([CryptoLib](#) id)
- [~CryptoFactory](#) ()=default

10.42.1 Constructor & Destructor Documentation

10.42.1.1 CAPICryptoFactory()

```
gdcmm::CAPICryptoFactory::CAPICryptoFactory (  
    CryptoLib id)
```

Referenced by [CreateCMSProvider\(\)](#).

10.42.2 Member Function Documentation

10.42.2.1 CreateCMSProvider()

```
CryptographicMessageSyntax * gdcmm::CAPICryptoFactory::CreateCMSProvider () [virtual]
```

Implements [gdcmm::CryptoFactory](#).

References [CAPICryptoFactory\(\)](#).


The documentation for this class was generated from the following file:

- [gdcmmCAPICryptoFactory.h](#)


10.43 gdcm::CAPICryptographicMessageSyntax Class Reference

```
#include <gdcmCAPICryptographicMessageSyntax.h>
```

Inheritance diagram for gdcm::CAPICryptographicMessageSyntax:



Collaboration diagram for gdcm::CAPICryptographicMessageSyntax:



Public Member Functions

- [CAPICryptographicMessageSyntax](#) ()
- [~CAPICryptographicMessageSyntax](#) ()
- bool [Decrypt](#) (char *output, size_t &outlen, const char *array, size_t len) const
decrypt content from a CMS envelopedData structure
- bool [Encrypt](#) (char *output, size_t &outlen, const char *array, size_t len) const
create a CMS envelopedData structure
- [CipherTypes GetCipherType](#) () const

- bool [GetInitialized](#) () const
- bool [ParseCertificateFile](#) (const char *filename)
- bool [ParseKeyFile](#) (const char *filename)
- void [SetCipherType](#) ([CipherTypes](#) type)
- bool [SetPassword](#) (const char *pass, size_t passLen)

Public Member Functions inherited from [gdcmm::CryptographicMessageSyntax](#)

- [CryptographicMessageSyntax](#) ()=default
- [CryptographicMessageSyntax](#) (const [CryptographicMessageSyntax](#) &)=delete
- virtual [~CryptographicMessageSyntax](#) ()=default
- void [operator=](#) (const [CryptographicMessageSyntax](#) &)=delete

Additional Inherited Members

Public Types inherited from [gdcmm::CryptographicMessageSyntax](#)

- enum [CipherTypes](#) {
[DES3_CIPHER](#) ,
[AES128_CIPHER](#) ,
[AES192_CIPHER](#) ,
[AES256_CIPHER](#) }

10.43.1 Constructor & Destructor Documentation

10.43.1.1 [CAPICryptographicMessageSyntax\(\)](#)

```
gdcmm::CAPICryptographicMessageSyntax::CAPICryptographicMessageSyntax ()
```

10.43.1.2 [~CAPICryptographicMessageSyntax\(\)](#)

```
gdcmm::CAPICryptographicMessageSyntax::~~CAPICryptographicMessageSyntax ()
```

10.43.2 Member Function Documentation

10.43.2.1 [Decrypt\(\)](#)

```
bool gdcmm::CAPICryptographicMessageSyntax::Decrypt (
    char * output,
    size_t & outlen,
    const char * array,
    size_t len) const [virtual]
```

decrypt content from a CMS envelopedData structure

Implements [gdcmm::CryptographicMessageSyntax](#).

10.43.2.2 Encrypt()

```
bool gdcmm::CAPICryptographicMessageSyntax::Encrypt (
    char * output,
    size_t & outlen,
    const char * array,
    size_t len) const [virtual]
```

create a CMS envelopedData structure

Implements [gdcmm::CryptographicMessageSyntax](#).

10.43.2.3 GetCipherType()

```
CipherTypes gdcmm::CAPICryptographicMessageSyntax::GetCipherType () const [virtual]
```

Implements [gdcmm::CryptographicMessageSyntax](#).

10.43.2.4 GetInitialized()

```
bool gdcmm::CAPICryptographicMessageSyntax::GetInitialized () const [inline]
```

10.43.2.5 ParseCertificateFile()

```
bool gdcmm::CAPICryptographicMessageSyntax::ParseCertificateFile (
    const char * filename) [virtual]
```

Implements [gdcmm::CryptographicMessageSyntax](#).

10.43.2.6 ParseKeyFile()

```
bool gdcmm::CAPICryptographicMessageSyntax::ParseKeyFile (
    const char * filename) [virtual]
```

Implements [gdcmm::CryptographicMessageSyntax](#).

10.43.2.7 SetCipherType()

```
void gdcmm::CAPICryptographicMessageSyntax::SetCipherType (
    CipherTypes type) [virtual]
```

Implements [gdcmm::CryptographicMessageSyntax](#).

10.43.2.8 SetPassword()

```
bool gdcm::CAPICryptographicMessageSyntax::SetPassword (
    const char * pass,
    size_t passLen) [virtual]
```

Implements [gdcm::CryptographicMessageSyntax](#).

The documentation for this class was generated from the following file:


- [gdcmCAPICryptographicMessageSyntax.h](#)

10.44 gdcm::network::CEchoRQ Class Reference


[CEchoRQ](#).

```
#include <gdcmCEchoMessages.h>
```

Inheritance diagram for gdcm::network::CEchoRQ:



Collaboration diagram for gdcm::network::CEchoRQ:



Public Member Functions

- `std::vector< PresentationDataValue > ConstructPDV` (const [ULConnection](#) &inConnection, const [BaseRootQuery](#) *inRootQuery) override

Public Member Functions inherited from [gdcm::network::BaseCompositeMessage](#)

- virtual `~BaseCompositeMessage` ()=default

Public Attributes

- [UIComp](#) `AffectedSOPClassUID`
- `uint16_t` `MessageID`

10.44.1 Detailed Description

[CEchoRQ](#).

this file defines the messages for the cecho action

10.44.2 Member Function Documentation

10.44.2.1 ConstructPDV()

```
std::vector< PresentationDataValue > gdcn::network::CEchoRQ::ConstructPDV (
    const ULConnection & inConnection,
    const BaseRootQuery * inRootQuery) [override], [virtual]
```

Implements [gdcn::network::BaseCompositeMessage](#).

10.44.3 Member Data Documentation

10.44.3.1 AffectedSOPClassUID

[UIComp](#) gdcn::network::CEchoRQ::AffectedSOPClassUID

10.44.3.2 MessageID

uint16_t gdcn::network::CEchoRQ::MessageID

The documentation for this class was generated from the following files:


- [gdcnCEchoMessages.h](#)
- [gdcnDIMSE.h](#)

10.45 gdcn::network::CEchoRSP Class Reference


[CEchoRSP](#) this file defines the messages for the cecho action.

```
#include <gdcnCEchoMessages.h>
```

Inheritance diagram for gdcn::network::CEchoRSP:



Collaboration diagram for gdcm::network::CEchoRSP:



Public Member Functions

- `std::vector< PresentationDataValue > ConstructPDVByDataSet` (const [DataSet](#) *inDataSet)

Public Member Functions inherited from [gdcm::network::BaseCompositeMessage](#)

- virtual `~BaseCompositeMessage` ()=default
- virtual `std::vector< PresentationDataValue > ConstructPDV` (const [ULConnection](#) &inConnection, const [BaseRootQuery](#) *inRootQuery)=0

10.45.1 Detailed Description

[CEchoRSP](#) this file defines the messages for the cecho action.

10.45.2 Member Function Documentation

10.45.2.1 ConstructPDVByDataSet()

```
std::vector< PresentationDataValue > gdcm::network::CEchoRSP::ConstructPDVByDataSet (
    const DataSet * inDataSet)
```

The documentation for this class was generated from the following file:

- [gdcmCEchoMessages.h](#)

10.46 gdcm::network::CFind Class Reference

```
#include <gdcmDIMSE.h>
```

10.46.1 Detailed Description

PS 3.4 - 2009 [Table B.2-1](#) C-STORE STATUS

The documentation for this class was generated from the following file:


- [gdcmdIMSE.h](#)

10.47 gdcmd::network::CFindCancelRQ Class Reference


[CFindCancelRQ](#) this file defines the messages for the cfind action.

```
#include <gdcmdCFindMessages.h>
```

Inheritance diagram for gdcmd::network::CFindCancelRQ:



Collaboration diagram for gdcmd::network::CFindCancelRQ:



Public Member Functions

- `std::vector< PresentationDataValue > ConstructPDVByDataSet` (const `DataSet *inDataSet`)

Public Member Functions inherited from [gdcm::network::BaseCompositeMessage](#)

- virtual `~BaseCompositeMessage` ()=default
- virtual `std::vector< PresentationDataValue > ConstructPDV` (const `ULConnection &inConnection`, const `BaseRootQuery *inRootQuery`)=0

10.47.1 Detailed Description

[CFindCancelRQ](#) this file defines the messages for the cfind action.

10.47.2 Member Function Documentation**10.47.2.1 ConstructPDVByDataSet()**

```
std::vector< PresentationDataValue > gdcm::network::CFindCancelRQ::ConstructPDVByDataSet (
    const DataSet * inDataSet)
```

The documentation for this class was generated from the following file:


- [gdcmCFindMessages.h](#)

10.48 gdcm::network::CFindRQ Class Reference


[CFindRQ](#).

```
#include <gdcmCFindMessages.h>
```

Inheritance diagram for `gdcm::network::CFindRQ`:



Collaboration diagram for `gdcm::network::CFindRQ`:



Public Member Functions

- `std::vector< PresentationDataValue > ConstructPDV` (`const ULConnection &inConnection`, `const BaseRootQuery *inRootQuery`) override

Public Member Functions inherited from [gdcm::network::BaseCompositeMessage](#)

- virtual `~BaseCompositeMessage` ()=default

10.48.1 Detailed Description

[CFindRQ](#).

this file defines the messages for the cfind action

10.48.2 Member Function Documentation

10.48.2.1 ConstructPDV()

```
std::vector< PresentationDataValue > gdcm::network::CFindRQ::ConstructPDV (
    const ULConnection & inConnection,
    const BaseRootQuery * inRootQuery) [override], [virtual]
```

Implements [gdcm::network::BaseCompositeMessage](#).

The documentation for this class was generated from the following file:


- [gdcmCFindMessages.h](#)

10.49 gdcm::network::CFindRSP Class Reference


[CFindRSP](#) this file defines the messages for the cfind action.

```
#include <gdcmCFindMessages.h>
```

Inheritance diagram for gdcm::network::CFindRSP:



Collaboration diagram for gdcm::network::CFindRSP:



Public Member Functions

- `std::vector< PresentationDataValue > ConstructPDVByDataSet` (const [DataSet](#) *inDataSet)

Public Member Functions inherited from [gdcm::network::BaseCompositeMessage](#)

- virtual `~BaseCompositeMessage` ()=default
- virtual `std::vector< PresentationDataValue > ConstructPDV` (const [ULConnection](#) &inConnection, const [BaseRootQuery](#) *inRootQuery)=0

10.49.1 Detailed Description

[CFindRSP](#) this file defines the messages for the cfind action.

10.49.2 Member Function Documentation

10.49.2.1 ConstructPDVByDataSet()

```
std::vector< PresentationDataValue > gdcmm::network::CFindRSP::ConstructPDVByDataSet (
    const DataSet * inDataSet)
```

The documentation for this class was generated from the following file:


- [gdcmmCFindMessages.h](#)

10.50 gdcmm::Cleaner Class Reference


[Cleaner](#).

```
#include <gdcmmCleaner.h>
```

Inheritance diagram for gdcmm::Cleaner:



Collaboration diagram for gdcm::Cleaner:



Public Types

- typedef std::tuple< std::string, std::string, std::string > [CodedEntryData](#)

Public Member Functions

- [Cleaner](#) ()
- [~Cleaner](#) () override
- bool [Clean](#) ()
main loop
- bool [Empty](#) (DPath const &dpath)
- bool [Empty](#) (PrivateTag const &pt)
- bool [Empty](#) (Tag const &t)
- bool [Empty](#) (VR const &vr)
- void [EmptyWhenScrubFails](#) (bool empty)
Should I empty instead of scrub upon failure.
- [File](#) & [GetFile](#) ()
- bool [Preserve](#) (DPath const &dpath)
Preserve.
- bool [Remove](#) (DPath const &dpath)
- bool [Remove](#) (PrivateTag const &pt)
- bool [Remove](#) (Tag const &t)
- bool [Remove](#) (VR const &vr)
- void [RemoveAllGroupLength](#) (bool remove)
Should I remove all group length (deprecated). Default: true.
- void [RemoveAllIllegal](#) (bool remove)
Should I remove all illegal attribute. Default: true.
- void [RemoveAllMissingPrivateCreator](#) (bool remove)

- bool [RemoveMissingPrivateCreator](#) ([Tag](#) const &t)
- bool [ReplaceCodeMeaning](#) ([CodedEntryData](#) const &ced)

Coded Entry Data.

- bool [Scrub](#) ([DPath](#) const &dpath)
- bool [Scrub](#) ([PrivateTag](#) const &pt)
- bool [Scrub](#) ([Tag](#) const &t)

Clean digital tash (typically SIEMENS CSA header):

- bool [Scrub](#) ([VR](#) const &vr)
- void [SetFile](#) (const [File](#) &f)

Set/Get File.

Public Member Functions inherited from [gdcm::Subject](#)

- [Subject](#) ()
- [~Subject](#) () override
- unsigned long [AddObserver](#) (const [Event](#) &event, [Command](#) *)
- unsigned long [AddObserver](#) (const [Event](#) &event, [Command](#) *) const
- [Command](#) * [GetCommand](#) (unsigned long tag)
- bool [HasObserver](#) (const [Event](#) &event) const
- void [InvokeEvent](#) (const [Event](#) &)
- void [InvokeEvent](#) (const [Event](#) &) const
- void [RemoveAllObservers](#) ()
- void [RemoveObserver](#) (unsigned long tag)

Public Member Functions inherited from [gdcm::Object](#)

- [Object](#) ()
 - [Object](#) (const [Object](#) &)
- Special requirement for copy/cstor, assignment operator.*
- virtual [~Object](#) ()
 - void [operator=](#) (const [Object](#) &)
 - virtual void [Print](#) (std::ostream &) const

Static Public Member Functions

- static [SmartPointer](#)< [Cleaner](#) > [New](#) ()
- for wrapped language: instantiate a reference counted object*

Additional Inherited Members

Protected Member Functions inherited from [gdcm::Object](#)

- void [Register](#) ()
- void [UnRegister](#) ()

10.50.1 Detailed Description

[Cleaner](#).

This class implement the Subject/Observer pattern trigger the following event:

- [AnonymizeEvent](#)
- [IterationEvent](#)
- [StartEvent](#)
- [EndEvent](#)

Examples

[Cleaner.cs](#).

10.50.2 Member Typedef Documentation

10.50.2.1 CodedEntryData

```
typedef std::tuple<std::string, std::string, std::string> gdcmm::Cleaner::CodedEntryData
```

10.50.3 Constructor & Destructor Documentation

10.50.3.1 Cleaner()

```
gdcmm::Cleaner::Cleaner ()
```

Referenced by [New\(\)](#).

10.50.3.2 ~Cleaner()

```
gdcmm::Cleaner::~~Cleaner () [override]
```

10.50.4 Member Function Documentation

10.50.4.1 Clean()

```
bool gdcmm::Cleaner::Clean ()
```

main loop

Examples

[Cleaner.cs](#).

10.50.4.2 Empty() [1/4]

```
bool gdcmm::Cleaner::Empty (
    DPath const & dpath)
```

10.50.4.3 Empty() [2/4]

```
bool gdcmm::Cleaner::Empty (
    PrivateTag const & pt)
```

10.50.4.4 Empty() [3/4]

```
bool gdcmm::Cleaner::Empty (
    Tag const & t)
```

Examples

[Cleaner.cs](#).

10.50.4.5 Empty() [4/4]

```
bool gdcmm::Cleaner::Empty (
    VR const & vr)
```

10.50.4.6 EmptyWhenScrubFails()

```
void gdcmm::Cleaner::EmptyWhenScrubFails (
    bool empty)
```

Should I empty instead of scrub upon failure.

10.50.4.7 GetFile()

```
File & gdcmm::Cleaner::GetFile () [inline]
```

Examples

[Cleaner.cs](#).

10.50.4.8 New()

```
SmartPointer< Cleaner > gdcmm::Cleaner::New () [inline], [static]
```

for wrapped language: instantiate a reference counted object

References [Cleaner\(\)](#).

10.50.4.9 Preserve()

```
bool gdcmm::Cleaner::Preserve (
    DPath const & dpath)
```

Preserve.

Examples

[Cleaner.cs](#).

10.50.4.10 Remove() [1/4]

```
bool gdcmm::Cleaner::Remove (
    DPath const & dpath)
```

10.50.4.11 Remove() [2/4]

```
bool gdcmm::Cleaner::Remove (
    PrivateTag const & pt)
```

10.50.4.12 Remove() [3/4]

```
bool gdcmm::Cleaner::Remove (
    Tag const & t)
```

Examples

[Cleaner.cs](#).

10.50.4.13 Remove() [4/4]

```
bool gdcmm::Cleaner::Remove (
    VR const & vr)
```

10.50.4.14 RemoveAllGroupLength()

```
void gdcM::Cleaner::RemoveAllGroupLength (
    bool remove)
```

Should I remove all group length (deprecated). Default: true.

10.50.4.15 RemoveAllIllegal()

```
void gdcM::Cleaner::RemoveAllIllegal (
    bool remove)
```

Should I remove all illegal attribute. Default: true.

10.50.4.16 RemoveAllMissingPrivateCreator()

```
void gdcM::Cleaner::RemoveAllMissingPrivateCreator (
    bool remove)
```

Should I remove all private tag for which no private creator is found. Default: true

10.50.4.17 RemoveMissingPrivateCreator()

```
bool gdcM::Cleaner::RemoveMissingPrivateCreator (
    Tag const & t)
```

Specify a private tag (odd number) without a private creator (root level only for now):

10.50.4.18 ReplaceCodeMeaning()

```
bool gdcM::Cleaner::ReplaceCodeMeaning (
    CodedEntryData const & ced)
```

Coded Entry Data.

10.50.4.19 Scrub() [1/4]

```
bool gdcM::Cleaner::Scrub (
    DPath const & dpath)
```

10.50.4.20 Scrub() [2/4]

```
bool gdcM::Cleaner::Scrub (
    PrivateTag const & pt)
```

10.50.4.21 Scrub() [3/4]

```
bool gdcm::Cleaner::Scrub (  
    Tag const & t)
```

Clean digital tash (typically SIEMENS CSA header):

Examples

[Cleaner.cs](#).

10.50.4.22 Scrub() [4/4]

```
bool gdcm::Cleaner::Scrub (  
    VR const & vr)
```

10.50.4.23 SetFile()

```
void gdcm::Cleaner::SetFile (  
    const File & f) [inline]
```

Set/Get [File](#).

Examples

[Cleaner.cs](#).


The documentation for this class was generated from the following file:

- [gdcmCleaner.h](#)


10.51 gdcm::network::CMoveCancelRq Class Reference

```
#include <gdcmCMoveMessages.h>
```

Inheritance diagram for gdcm::network::CMoveCancelRq:



Collaboration diagram for `gdcm::network::CMoveCancelRq`:



Public Member Functions

- `std::vector< PresentationDataValue > ConstructPDVByDataSet` (const [DataSet](#) *inDataSet)

Public Member Functions inherited from [gdcm::network::BaseCompositeMessage](#)

- virtual `~BaseCompositeMessage` ()=default
- virtual `std::vector< PresentationDataValue > ConstructPDV` (const [ULConnection](#) &inConnection, const [BaseRootQuery](#) *inRootQuery)=0

10.51.1 Member Function Documentation

10.51.1.1 ConstructPDVByDataSet()

```
std::vector< PresentationDataValue > gdcm::network::CMoveCancelRq::ConstructPDVByDataSet (
    const DataSet * inDataSet)
```

The documentation for this class was generated from the following file:


- [gdcmCMoveMessages.h](#)

10.52 gdcm::network::CMoveRQ Class Reference


[CMoveRQ](#).

```
#include <gdcmCMoveMessages.h>
```

Inheritance diagram for gdcm::network::CMoveRQ:



Collaboration diagram for gdcm::network::CMoveRQ:



Public Member Functions

- `std::vector< PresentationDataValue > ConstructPDV` (const [ULConnection](#) &inConnection, const [BaseRootQuery](#) *inRootQuery) override

Public Member Functions inherited from [gdcm::network::BaseCompositeMessage](#)

- virtual `~BaseCompositeMessage` ()=default

10.52.1 Detailed Description

[CMoveRQ](#).

this file defines the messages for the cmove action

10.52.2 Member Function Documentation

10.52.2.1 ConstructPDV()

```
std::vector< PresentationDataValue > gdcM::network::CMoveRQ::ConstructPDV (
    const ULConnection & inConnection,
    const BaseRootQuery * inRootQuery) [override], [virtual]
```

Implements [gdcM::network::BaseCompositeMessage](#).

The documentation for this class was generated from the following file:


- [gdcMCMoveMessages.h](#)

10.53 gdcM::network::CMoveRSP Class Reference


[CMoveRSP](#) this file defines the messages for the cmove action.

```
#include <gdcMCMoveMessages.h>
```

Inheritance diagram for gdcM::network::CMoveRSP:



Collaboration diagram for gdcm::network::CMoveRSP:



Public Member Functions

- `std::vector< PresentationDataValue > ConstructPDVByDataSet (const DataSet *inDataSet)`

Public Member Functions inherited from [gdcm::network::BaseCompositeMessage](#)

- virtual `~BaseCompositeMessage ()=default`
- virtual `std::vector< PresentationDataValue > ConstructPDV (const ULConnection &inConnection, const BaseRootQuery *inRootQuery)=0`

10.53.1 Detailed Description

[CMoveRSP](#) this file defines the messages for the cmove action.

10.53.2 Member Function Documentation

10.53.2.1 ConstructPDVByDataSet()

```
std::vector< PresentationDataValue > gdcm::network::CMoveRSP::ConstructPDVByDataSet (
    const DataSet * inDataSet)
```

The documentation for this class was generated from the following file:


- [gdcmCMoveMessages.h](#)

10.54 gdcm::Codec Class Reference


[Codec](#) class.

```
#include <gdcmCodec.h>
```

Inheritance diagram for `gdcm::Codec`:



Collaboration diagram for `gdcm::Codec`:



Additional Inherited Members

Public Member Functions inherited from [gdcm::Coder](#)

- virtual `~Coder()` = default
- virtual bool `CanCode(TransferSyntax const &) const` = 0
Return whether this coder support this transfer syntax (can code it)
- virtual bool `Code(DataElement const &in_, DataElement &out_)`
Code.

Public Member Functions inherited from [gdcm::Decoder](#)

- virtual [~Decoder](#) ()=default
- virtual bool [CanDecode](#) ([TransferSyntax](#) const &) const =0
Return whether this decoder support this transfer syntax (can decode it)
- virtual bool [Decode](#) ([DataElement](#) const &, [DataElement](#) &)
Decode.

Protected Member Functions inherited from [gdcm::Coder](#)

- virtual bool [InternalCode](#) (const char *bv, unsigned long len, std::ostream &os)

Protected Member Functions inherited from [gdcm::Decoder](#)

- virtual bool [DecodeByStreams](#) (std::istream &, std::ostream &)

10.54.1 Detailed Description

[Codec](#) class.

The documentation for this class was generated from the following file:


- [gdcmCodec.h](#)

10.55 gdcm::Coder Class Reference

[Coder](#).

```
#include <gdcmCoder.h>
```

Inheritance diagram for [gdcm::Coder](#):



Public Member Functions

- virtual [~Coder](#) ()=default
- virtual bool [CanCode](#) ([TransferSyntax](#) const &) const =0
Return whether this coder support this transfer syntax (can code it)
- virtual bool [Code](#) ([DataElement](#) const &in_, [DataElement](#) &out_)
Code.

Protected Member Functions

- virtual bool [InternalCode](#) (const char *bv, unsigned long len, std::ostream &os)

10.55.1 Detailed Description

[Coder](#).

10.55.2 Constructor & Destructor Documentation

10.55.2.1 ~Coder()

```
virtual gdcm::Coder::~Coder () [virtual], [default]
```

10.55.3 Member Function Documentation

10.55.3.1 CanCode()

```
virtual bool gdcm::Coder::CanCode (
    TransferSyntax const & ) const [pure virtual]
```

Return whether this coder support this transfer syntax (can code it)

Implemented in [gdcm::AudioCodec](#), [gdcm::ImageCodec](#), [gdcm::JPEG2000Codec](#), [gdcm::JPEGCodec](#), [gdcm::JPEGLSCodec](#), [gdcm::KAKADUCodec](#), [gdcm::PDFCodec](#), [gdcm::PGXCodec](#), [gdcm::PNMCodec](#), [gdcm::PVRGCodec](#), [gdcm::RAWCodec](#), and [gdcm::RLECodec](#).

10.55.3.2 Code()

```
virtual bool gdcm::Coder::Code (
    DataElement const & in_,
    DataElement & out_) [inline], [virtual]
```

Code.

Reimplemented in [gdcm::JPEG2000Codec](#), [gdcm::JPEGCodec](#), [gdcm::JPEGLSCodec](#), [gdcm::KAKADUCodec](#), [gdcm::PVRGCodec](#), [gdcm::RAWCodec](#), and [gdcm::RLECodec](#).

10.55.3.3 InternalCode()

```
virtual bool gdcm::Coder::InternalCode (
    const char * bv,
    unsigned long len,
    std::ostream & os) [inline], [protected], [virtual]
```

Reimplemented in [gdcm::JPEG12Codec](#), [gdcm::JPEG16Codec](#), and [gdcm::JPEG8Codec](#).

The documentation for this class was generated from the following file:

- [gdcmCoder.h](#)

10.56 gdcm::CodeString Class Reference

[CodeString](#).

```
#include <gdcmCodeString.h>
```

Public Types

- typedef [InternalClass::const_iterator](#) const_iterator
- typedef [InternalClass::const_reference](#) const_reference
- typedef [InternalClass::const_reverse_iterator](#) const_reverse_iterator
- typedef [InternalClass::difference_type](#) difference_type
- typedef [InternalClass::iterator](#) iterator
- typedef [InternalClass::pointer](#) pointer
- typedef [InternalClass::reference](#) reference
- typedef [InternalClass::reverse_iterator](#) reverse_iterator
- typedef [InternalClass::size_type](#) size_type
- typedef [InternalClass::value_type](#) value_type

Public Member Functions

- [CodeString](#) ()
CodeString constructors.
- [CodeString](#) (const [InternalClass](#) &s, [size_type](#) pos=0, [size_type](#) n=[InternalClass::npos](#))
- [CodeString](#) (const [value_type](#) *s)
- [CodeString](#) (const [value_type](#) *s, [size_type](#) n)
- [std::string](#) [GetAsString](#) () const
Return the full code string as std::string.
- bool [IsValid](#) () const
Check if CodeString obj is correct..
- [size_type](#) [Size](#) () const
Return the size of the string.

Protected Member Functions

- `std::string TrimInternal () const`

Friends

- `bool operator!= (const CodeString &ref, const CodeString &cs)`
- `std::ostream & operator<< (std::ostream &os, const CodeString &str)`
- `bool operator== (const CodeString &ref, const CodeString &cs)`

10.56.1 Detailed Description

[CodeString](#).

This is an implementation of DICOM [VR](#): CS The ctor will properly Trim so that operator== is correct.

Note

the ctor of [CodeString](#) will Trim the string on the fly so as to remove the extra leading and ending spaces. However it will not perform validation on the fly ([CodeString](#) obj can contains invalid char such as lower cases). This design was chosen to be a little tolerant to broken DICOM implementation, and thus allow user to compare lower case CS from there input file without the need to first rewrite them to get rid of invalid character (validation is a different operation from searching, querying).

Warning

when writing out DICOM file it is highly recommended to perform the [IsValid\(\)](#) call, at least to check that the length of the string match the definition in the standard.

10.56.2 Member Typedef Documentation

10.56.2.1 `const_iterator`

```
typedef InternalClass::const\_iterator gdcm::CodeString::const_iterator
```

10.56.2.2 `const_reference`

```
typedef InternalClass::const\_reference gdcm::CodeString::const_reference
```

10.56.2.3 `const_reverse_iterator`

```
typedef InternalClass::const\_reverse\_iterator gdcm::CodeString::const_reverse_iterator
```

10.56.2.4 difference_type

```
typedef InternalClass::difference_type gdcm::CodeString::difference_type
```

10.56.2.5 iterator

```
typedef InternalClass::iterator gdcm::CodeString::iterator
```

10.56.2.6 pointer

```
typedef InternalClass::pointer gdcm::CodeString::pointer
```

10.56.2.7 reference

```
typedef InternalClass::reference gdcm::CodeString::reference
```

10.56.2.8 reverse_iterator

```
typedef InternalClass::reverse_iterator gdcm::CodeString::reverse_iterator
```

10.56.2.9 size_type

```
typedef InternalClass::size_type gdcm::CodeString::size_type
```

10.56.2.10 value_type

```
typedef InternalClass::value_type gdcm::CodeString::value_type
```

10.56.3 Constructor & Destructor Documentation

10.56.3.1 CodeString() [1/4]

```
gdcm::CodeString::CodeString () [inline]
```

[CodeString](#) constructors.

Referenced by [operator!=](#), [operator<<](#), and [operator==](#).

10.56.3.2 CodeString() [2/4]

```
gdcM::CodeString::CodeString (  
    const value_type * s) [inline]
```

10.56.3.3 CodeString() [3/4]

```
gdcM::CodeString::CodeString (  
    const value_type * s,  
    size_type n) [inline]
```

10.56.3.4 CodeString() [4/4]

```
gdcM::CodeString::CodeString (  
    const InternalClass & s,  
    size_type pos = 0,  
    size_type n = InternalClass::npos) [inline]
```

10.56.4 Member Function Documentation

10.56.4.1 GetAsString()

```
std::string gdcM::CodeString::GetAsString () const [inline]
```

Return the full code string as std::string.

10.56.4.2 IsValid()

```
bool gdcM::CodeString::IsValid () const
```

Check if [CodeString](#) obj is correct..

10.56.4.3 Size()

```
size_type gdcM::CodeString::Size () const [inline]
```

Return the size of the string.

10.56.4.4 TrimInternal()

```
std::string gdcM::CodeString::TrimInternal () const [inline], [protected]
```

10.56.5 Friends And Related Symbol Documentation

10.56.5.1 operator"!=

```
bool operator!= (
    const CodeString & ref,
    const CodeString & cs) [friend]
```

References [CodeString\(\)](#).

10.56.5.2 operator<<

```
std::ostream & operator<< (
    std::ostream & os,
    const CodeString & str) [friend]
```

References [CodeString\(\)](#).

10.56.5.3 operator==

```
bool operator== (
    const CodeString & ref,
    const CodeString & cs) [friend]
```

References [CodeString\(\)](#).

The documentation for this class was generated from the following file:


- [gdcmmCodeString.h](#)

10.57 gdcmm::Command Class Reference


[Command](#) superclass for callback/observer methods.

```
#include <gdcmmCommand.h>
```

Inheritance diagram for gdcmm::Command:



Collaboration diagram for `gdcm::Command`:



Public Member Functions

- `Command` (const `Command` &)=delete
- virtual void `Execute` (const `Subject` *caller, const `Event` &event)=0
- virtual void `Execute` (`Subject` *caller, const `Event` &event)=0
- *Abstract method that defines the action to be taken by the command.*
- void `operator=` (const `Command` &)=delete

Public Member Functions inherited from `gdcm::Subject`

- `Subject` ()
- `~Subject` () override
- unsigned long `AddObserver` (const `Event` &event, `Command` *)
- unsigned long `AddObserver` (const `Event` &event, `Command` *) const
- `Command` * `GetCommand` (unsigned long tag)
- bool `HasObserver` (const `Event` &event) const
- void `InvokeEvent` (const `Event` &)
- void `InvokeEvent` (const `Event` &) const
- void `RemoveAllObservers` ()
- void `RemoveObserver` (unsigned long tag)

Public Member Functions inherited from `gdcm::Object`

- `Object` ()
- `Object` (const `Object` &)
- *Special requirement for copy/cstor, assignment operator.*
- virtual `~Object` ()
- void `operator=` (const `Object` &)
- virtual void `Print` (std::ostream &) const

Protected Member Functions

- [Command](#) ()
- [~Command](#) () override

Protected Member Functions inherited from [gdcm::Object](#)

- void [Register](#) ()
- void [UnRegister](#) ()

10.57.1 Detailed Description

[Command](#) superclass for callback/observer methods.

See also

[Subject](#)

10.57.2 Constructor & Destructor Documentation

10.57.2.1 [Command](#)() [1/2]

```
gdcm::Command::Command (
    const Command & )    [delete]
```

References [Command\(\)](#).

Referenced by [Command\(\)](#), and [operator=\(\)](#).

10.57.2.2 [Command](#)() [2/2]

```
gdcm::Command::Command ()    [protected]
```

10.57.2.3 [~Command](#)()

```
gdcm::Command::~~Command ()    [override], [protected]
```

10.57.3 Member Function Documentation

10.57.3.1 Execute() [1/2]

```
virtual void gdcm::Command::Execute (
    const Subject * caller,
    const Event & event) [pure virtual]
```

Abstract method that defines the action to be taken by the command. This variant is expected to be used when requests comes from a const [Object](#)

Implemented in [gdcm::MemberCommand< T >](#), [gdcm::MemberCommand< SimpleSubjectWatcher >](#), [gdcm::SimpleMemberCommand](#) and [gdcm::SimpleMemberCommand< SimpleSubjectWatcher >](#).

References [gdcm::Subject::Subject\(\)](#).

10.57.3.2 Execute() [2/2]

```
virtual void gdcm::Command::Execute (
    Subject * caller,
    const Event & event) [pure virtual]
```

Abstract method that defines the action to be taken by the command.

Implemented in [gdcm::MemberCommand< T >](#), [gdcm::MemberCommand< SimpleSubjectWatcher >](#), [gdcm::SimpleMemberCommand](#) and [gdcm::SimpleMemberCommand< SimpleSubjectWatcher >](#).

References [gdcm::Subject::Subject\(\)](#).

10.57.3.3 operator=()

```
void gdcm::Command::operator= (
    const Command & ) [delete]
```

References [Command\(\)](#).

The documentation for this class was generated from the following file:


- [gdcmCommand.h](#)

10.58 gdcm::CommandDataSet Class Reference


Class to represent a [Command DataSet](#).

```
#include <gdcmCommandDataSet.h>
```

Inheritance diagram for gdcm::CommandDataSet:



Collaboration diagram for gdcm::CommandDataSet:



Public Member Functions

- [CommandDataSet](#) ()=default
- [~CommandDataSet](#) ()=default
- void [Insert](#) (const [DataElement](#) &de)
- std::istream & [Read](#) (std::istream &is)
Read.
- void [Replace](#) (const [DataElement](#) &de)
- std::ostream & [Write](#) (std::ostream &os) const
Write.

Public Member Functions inherited from `gdcm::DataSet`

- `Iterator Begin ()`
- `ConstIterator Begin () const`
- `void Clear ()`
- `template<typename TDE>`
`unsigned int ComputeGroupLength (Tag const &tag) const`
- `Iterator End ()`
- `ConstIterator End () const`
- `bool FindDataElement (const PrivateTag &t) const`
Look up if private tag 't' is present in the dataset:
- `bool FindDataElement (const Tag &t) const`
- `const DataElement & FindNextDataElement (const Tag &t) const`
- `const DataElement & GetDataElement (const PrivateTag &t) const`
Return the dataelement.
- `const DataElement & GetDataElement (const Tag &t) const`
- `DataElementSet & GetDES ()`
- `const DataElementSet & GetDES () const`
- `template<typename TDE>`
`VL GetLength () const`
- `MediaStorage GetMediaStorage () const`
- `std::string GetPrivateCreator (const Tag &t) const`
- `PrivateTag GetPrivateTag (const Tag &t) const`
Return the private tag of the private tag 't', private creator will be set to empty if not found.
- `void Insert (const DataElement &de)`
- `bool IsEmpty () const`
Returns if the dataset is empty.
- `const DataElement & operator() (uint16_t group, uint16_t element) const`
- `DataSet & operator= (DataSet const &)=default`
- `const DataElement & operator[] (const Tag &t) const`
- `void Print (std::ostream &os, std::string const &indent="") const`
- `template<typename TDE, typename TSwap>`
`std::istream & Read (std::istream &is)`
- `template<typename TDE, typename TSwap>`
`std::istream & ReadNested (std::istream &is)`
- `template<typename TDE, typename TSwap>`
`std::istream & ReadSelectedPrivateTags (std::istream &is, const std::set< PrivateTag > &tags, bool readvalues=true)`
- `template<typename TDE, typename TSwap>`
`std::istream & ReadSelectedPrivateTagsWithLength (std::istream &is, const std::set< PrivateTag > &tags, VL &length, bool readvalues=true)`
- `template<typename TDE, typename TSwap>`
`std::istream & ReadSelectedTags (std::istream &is, const std::set< Tag > &tags, bool readvalues=true)`
- `template<typename TDE, typename TSwap>`
`std::istream & ReadSelectedTagsWithLength (std::istream &is, const std::set< Tag > &tags, VL &length, bool readvalues=true)`
- `template<typename TDE, typename TSwap>`
`std::istream & ReadUpToTag (std::istream &is, const Tag &t, std::set< Tag > const &skiptags)`
- `template<typename TDE, typename TSwap>`
`std::istream & ReadUpToTagWithLength (std::istream &is, const Tag &t, std::set< Tag > const &skiptags, VL &length)`

- `template<typename TDE, typename TSwap>`
`std::istream & ReadWithLength (std::istream &is, VL &length)`
- `SizeType Remove` (const `Tag` &tag)
Completely remove a dataelement from the dataset.
- `void Replace` (const `DataElement` &de)
Replace a dataelement with another one.
- `void ReplaceEmpty` (const `DataElement` &de)
Only replace a DICOM attribute when it is missing or empty.
- `SizeType Size` () const
- `template<typename TDE, typename TSwap>`
`std::ostream const & Write` (std::ostream &os) const

Friends

- `std::ostream & operator<<` (std::ostream &_os, const `CommandDataSet` &_val)

Additional Inherited Members

Public Types inherited from `gdcm::DataSet`

- `typedef DataSet::const_iterator` `ConstIterator`
- `typedef std::set< DataElement >` `DataElementSet`
- `typedef DataSet::iterator` `Iterator`
- `typedef DataSet::size_type` `SizeType`

Protected Member Functions inherited from `gdcm::DataSet`

- `Tag ComputeDataElement` (const `PrivateTag` &t) const
- const `DataElement` & `GetDEEnd` () const
- `void InsertDataElement` (const `DataElement` &de)

10.58.1 Detailed Description

Class to represent a `Command DataSet`.

See also

[DataSet](#)

10.58.2 Constructor & Destructor Documentation

10.58.2.1 `CommandDataSet()`

```
gdcm::CommandDataSet::CommandDataSet () [default]
```

Referenced by `~CommandDataSet()`, and `operator<<`.

10.58.2.2 ~CommandDataSet()

```
gdcM::CommandDataSet::~~CommandDataSet () [default]
```

References [CommandDataSet\(\)](#), and [operator<<](#).

10.58.3 Member Function Documentation

10.58.3.1 Insert()

```
void gdcM::CommandDataSet::Insert (
    const DataElement & de) [inline]
```

References [gdcMErrorMacro](#), [gdcM::Tag::GetGroup\(\)](#), [gdcM::DataElement::GetTag\(\)](#), and [gdcM::DataSet::InsertDataElement\(\)](#).

Referenced by [Replace\(\)](#).

10.58.3.2 Read()

```
std::istream & gdcM::CommandDataSet::Read (
    std::istream & is)
```

Read.

10.58.3.3 Replace()

```
void gdcM::CommandDataSet::Replace (
    const DataElement & de) [inline]
```

References [gdcM::DataElement::GetTag\(\)](#), [Insert\(\)](#), and [gdcM::DataSet::Remove\(\)](#).

10.58.3.4 Write()

```
std::ostream & gdcM::CommandDataSet::Write (
    std::ostream & os) const
```

Write.

10.58.4 Friends And Related Symbol Documentation

10.58.4.1 operator<<

```
std::ostream & operator<< (
    std::ostream & _os,
    const CommandDataSet & _val) [friend]
```

References [CommandDataSet\(\)](#), and [gdcm::DataSet::Print\(\)](#).

Referenced by [~CommandDataSet\(\)](#).

The documentation for this class was generated from the following file:

- [gdcmCommandDataSet.h](#)

10.59 gdcm::network::CompositeMessageFactory Class Reference

[CompositeMessageFactory](#).

```
#include <gdcmCompositeMessageFactory.h>
```

Static Public Member Functions

- static std::vector< [PresentationDataValue](#) > [ConstructCEchoRQ](#) (const [ULConnection](#) &inConnection)
- static std::vector< [PresentationDataValue](#) > [ConstructCFindRQ](#) (const [ULConnection](#) &inConnection, const [BaseRootQuery](#) *inRootQuery)
- static std::vector< [PresentationDataValue](#) > [ConstructCMoveRQ](#) (const [ULConnection](#) &inConnection, const [BaseRootQuery](#) *inRootQuery)
- static std::vector< [PresentationDataValue](#) > [ConstructCStoreRQ](#) (const [ULConnection](#) &inConnection, const [File](#) &file, bool writeDataSet=true)
- static std::vector< [PresentationDataValue](#) > [ConstructCStoreRSP](#) (const [DataSet](#) *inDataSet, const [BasePDU](#) *inPC)

10.59.1 Detailed Description

[CompositeMessageFactory](#).

This class constructs PDataPDUs, but that have been specifically constructed for the composite DICOM services (C-Echo, C-Find, C-Get, C-Move, and C-Store). It will also handle parsing the incoming data to determine which of the CompositePDUs the incoming data is, and so therefore allowing the scu to determine what to do with incoming data (if acting as a storescp server, for instance).

10.59.2 Member Function Documentation

10.59.2.1 ConstructCEchoRQ()

```
std::vector< PresentationDataValue > gdcm::network::CompositeMessageFactory::ConstructCEchoRQ (
    const ULConnection & inConnection) [static]
```

10.59.2.2 ConstructCFindRQ()

```
std::vector< PresentationDataValue > gdcm::network::CompositeMessageFactory::ConstructCFindRQ (
    const ULConnection & inConnection,
    const BaseRootQuery * inRootQuery) [static]
```

10.59.2.3 ConstructCMoveRQ()

```
std::vector< PresentationDataValue > gdcm::network::CompositeMessageFactory::ConstructCMoveRQ (
    const ULConnection & inConnection,
    const BaseRootQuery * inRootQuery) [static]
```

10.59.2.4 ConstructCStoreRQ()

```
std::vector< PresentationDataValue > gdcm::network::CompositeMessageFactory::ConstructCStoreRQ (
    const ULConnection & inConnection,
    const File & file,
    bool writeDataSet = true) [static]
```

10.59.2.5 ConstructCStoreRSP()

```
std::vector< PresentationDataValue > gdcm::network::CompositeMessageFactory::ConstructCStoreRSP (
    const DataSet * inDataSet,
    const BasePDU * inPC) [static]
```

The documentation for this class was generated from the following file:

- [gdcmCompositeMessageFactory.h](#)

10.60 gdcm::CompositeNetworkFunctions Class Reference

Composite Network Functions.

```
#include <gdcmCompositeNetworkFunctions.h>
```


Public Types

- typedef std::vector< [KeyValuePairType](#) > [KeyValuePairArrayType](#)
- typedef std::pair< [Tag](#), std::string > [KeyValuePairType](#)

Static Public Member Functions

- static bool [CEcho](#) (const char *remote, uint16_t portno, const char *aetitle=nullptr, const char *call=nullptr)
- static bool [CFind](#) (const char *remote, uint16_t portno, const [BaseRootQuery](#) *query, std::vector< [DataSet](#) > &retDataSets, const char *aetitle=nullptr, const char *call=nullptr)
- static bool [CMove](#) (const char *remote, uint16_t portno, const [BaseRootQuery](#) *query, uint16_t portscp, const char *aetitle=nullptr, const char *call=nullptr, const char *outputdir=nullptr)
- static [BaseRootQuery](#) * [ConstructQuery](#) ([ERootType](#) inRootType, [EQueryLevel](#) inQueryLevel, const [DataSet](#) &queryds, [EQueryType](#) queryType=eFind)
- static [BaseRootQuery](#) * [ConstructQuery](#) ([ERootType](#) inRootType, [EQueryLevel](#) inQueryLevel, const [KeyValuePairArrayType](#) &keys, [EQueryType](#) queryType=eFind)
- static bool [CStore](#) (const char *remote, uint16_t portno, const [Directory::FileNamesType](#) &filenames, const char *aetitle=nullptr, const char *call=nullptr)

10.60.1 Detailed Description

Composite Network Functions.

These functions provide a generic API to the DICOM functions implemented in GDCM. Advanced users can use this code as a template for building their own versions of these functions (for instance, to provide progress bars or some other way of handling returned query information), but for most users, these functions should be sufficient to interface with a PACS to a local machine. Note that these functions are not contained within a static class or some other class-style interface, because multiple connections can be instantiated in the same program. The DICOM standard is much more function oriented rather than class oriented in this instance, so the design of this API reflects that functional approach. These functions implements the following SCU operations:

- C-ECHO SCU
- C-FIND SCU
- C-STORE SCU
- C-MOVE SCU (+internal C-STORE SCP)

Examples

[SendFileSCU.cs](#).

10.60.2 Member Typedef Documentation

10.60.2.1 KeyValuePairArrayType

```
typedef std::vector< KeyValuePairType > gdcmm::CompositeNetworkFunctions::KeyValuePairArrayType
```

10.60.2.2 KeyValuePairType

```
typedef std::pair<Tag, std::string> gdcm::CompositeNetworkFunctions::KeyValuePairType
```

10.60.3 Member Function Documentation

10.60.3.1 CEcho()

```
bool gdcm::CompositeNetworkFunctions::CEcho (
    const char * remote,
    uint16_t portno,
    const char * aetitle = nullptr,
    const char * call = nullptr) [static]
```

The most basic network function. Use this function to ensure that the remote server is responding on the given IP and port number as expected.

Parameters

<i>aetitle</i>	when not set will default to 'GDCMSCU'
<i>call</i>	when not set will default to 'ANY-SCP'

Warning

This is an error to set remote to NULL or portno to 0

Returns

true if it worked.

Examples

[SendFileSCU.cs](#).

10.60.3.2 CFind()

```
bool gdcm::CompositeNetworkFunctions::CFind (
    const char * remote,
    uint16_t portno,
    const BaseRootQuery * query,
    std::vector< DataSet > & retDataSets,
    const char * aetitle = nullptr,
    const char * call = nullptr) [static]
```

This function will use the provided query to determine what files a remote server contains that match the query strings. The return is a vector of datasets that contain tags as reported by the server. If the dataset is empty, then it is possible that an error condition was encountered; in which case, the user should monitor the error and warning streams.

Parameters

<i>aetitle</i>	when not set will default to 'GDCMSCU'
<i>call</i>	when not set will default to 'ANY-SCP'

Warning

This is an error to set remote to NULL or portno to 0

Returns

true if it worked.

10.60.3.3 CMove()

```
bool gdcmm::CompositeNetworkFunctions::CMove (
    const char * remote,
    uint16_t portno,
    const BaseRootQuery * query,
    uint16_t portscp,
    const char * aetitle = nullptr,
    const char * call = nullptr,
    const char * outputdir = nullptr) [static]
```

This function will use the provided query to get files from a remote server. NOTE that this functionality is essentially equivalent to C-GET in the DICOM standard; however, C-GET has been deprecated, so this function allows for the user to ask a remote server for files matching a query and return them to the local machine. Files will be written to the given output directory. If the operation succeeds, the function returns true. This function is a prime candidate for being overwritten by expert users; if the datasets should remain in memory, for instance, that behavior can be changed by creating a user-level version of this function.

Parameters

<i>aetitle</i>	when not set will default to 'GDCMSCU'
<i>call</i>	when not set will default to 'ANY-SCP' This is an error to set remote to NULL or portno to 0 when
<i>outputdir</i>	is not set default to current dir ('.')

Returns

true if it worked.

10.60.3.4 ConstructQuery() [1/2]

```
BaseRootQuery * gdcmm::CompositeNetworkFunctions::ConstructQuery (
    ERootType inRootType,
    EQueryLevel inQueryLevel,
    const DataSet & queryds,
    EQueryType queryType = eFind) [static]
```

This function will take a list of strings and tags and fill in a query that can be used for either CFind or CMove (depending on the input boolean

Parameters

<i>inMove</i>).	Note that the caller is responsible for deleting the constructed query. This function is used to build both a move and a find query (true for inMove if it's move, false if it's find)
------------------	--

References [gdcM::eFind](#).

10.60.3.5 ConstructQuery() [2/2]

```
BaseRootQuery * gdcM::CompositeNetworkFunctions::ConstructQuery (
    ERootType inRootType,
    EQueryLevel inQueryLevel,
    const KeyValuePairArrayType & keys,
    EQueryType queryType = eFind) [static]
```

Deprecated

References [gdcM::eFind](#).

10.60.3.6 CStore()

```
bool gdcM::CompositeNetworkFunctions::CStore (
    const char * remote,
    uint16_t portno,
    const Directory::FileNamesType & filenames,
    const char * aetitle = nullptr,
    const char * call = nullptr) [static]
```

This function will place the provided files into the remote server. The function returns true if it worked for all files.

Warning

the server side can refuse an association on a given file

Parameters

<i>aetitle</i>	when not set will default to 'GDCMSCU'
<i>call</i>	when not set will default to 'ANY-SCP'

Warning

This is an error to set remote to NULL or portno to 0

Returns

true if it worked for all files

Examples

[SendFileSCU.cs](#).

The documentation for this class was generated from the following file:

- [gdcMCompositeNetworkFunctions.h](#)

10.61 gdcm::ConstCharWrapper Class Reference

Do not use me.

```
#include <gdcmConstCharWrapper.h>
```

Public Member Functions

- [ConstCharWrapper](#) (const char *i=0)
- [operator const char * \(\)](#) const

10.61.1 Detailed Description

Do not use me.

10.61.2 Constructor & Destructor Documentation

10.61.2.1 ConstCharWrapper()

```
gdcm::ConstCharWrapper::ConstCharWrapper (  
    const char * i = 0) [inline]
```

10.61.3 Member Function Documentation

10.61.3.1 operator const char *()

```
gdcm::ConstCharWrapper::operator const char * () const [inline]
```

The documentation for this class was generated from the following file:


- [gdcmConstCharWrapper.h](#)

10.62 gdcm::CP246ExplicitDataElement Class Reference


Class to read/write a [DataElement](#) as CP246Explicit Data [Element](#).

```
#include <gdcmCP246ExplicitDataElement.h>
```

Inheritance diagram for gdcm::CP246ExplicitDataElement:



Collaboration diagram for gdcm::CP246ExplicitDataElement:



Public Member Functions

- [VL GetLength](#) () const

- template<typename TSwap>
std::istream & **Read** (std::istream &is)
- template<typename TSwap>
std::istream & **ReadPreValue** (std::istream &is)
- template<typename TSwap>
std::istream & **ReadValue** (std::istream &is, bool readvalues=true)
- template<typename TSwap>
std::istream & **ReadWithLength** (std::istream &is, **VL** &length)

Public Member Functions inherited from **gdcm::DataElement**

- **DataElement** (const **DataElement** &_val)
- **DataElement** (const **Tag** &t=**Tag**(0), const **VL** &vl=0, const **VR** &vr=**VR::INVALID**)
- void **Clear** ()
*Clear Data **Element** (make **Value** empty and invalidate **Tag** & **VR**)*
- void **Empty** ()
*Make Data **Element** empty (no **Value**)*
- const **ByteValue** * **GetByteValue** () const
- template<typename TDE>
VL **GetLength** () const
- **SequenceOfFragments** * **GetSequenceOfFragments** ()
- const **SequenceOfFragments** * **GetSequenceOfFragments** () const
- **Tag** & **GetTag** ()
- const **Tag** & **GetTag** () const
*Get **Tag**.*
- **Value** & **GetValue** ()
- **Value** const & **GetValue** () const
*Set/Get **Value** (bytes array, SQ of items, SQ of fragments):*
- **SmartPointer**< **SequenceOfItems** > **GetValueAsSQ** () const
- **VL** & **GetVL** ()
- const **VL** & **GetVL** () const
*Get **VL**.*
- **VR** const & **GetVR** () const
- bool **IsEmpty** () const
*Check if Data **Element** is empty.*
- bool **IsUndefinedLength** () const
*return if **Value** Length if of undefined length*
- bool **operator**< (const **DataElement** &de) const
- **DataElement** & **operator**= (const **DataElement** &)=default
- bool **operator**== (const **DataElement** &de) const
- template<typename TDE, typename TSwap>
std::istream & **Read** (std::istream &is)
- template<typename TDE, typename TSwap>
std::istream & **ReadOrSkip** (std::istream &is, std::set< **Tag** > const &skiptags)
- template<typename TDE, typename TSwap>
std::istream & **ReadPreValue** (std::istream &is, std::set< **Tag** > const &skiptags)
- template<typename TDE, typename TSwap>
std::istream & **ReadValue** (std::istream &is, std::set< **Tag** > const &skiptags)

- template<typename TDE, typename TSwap>
std::istream & [ReadValueWithLength](#) (std::istream &is, [VL](#) &length, std::set< [Tag](#) > const &skiptags)
- template<typename TDE, typename TSwap>
std::istream & [ReadWithLength](#) (std::istream &is, [VL](#) &length)
- void [SetByteValue](#) (const char *array, [VL](#) length)
- void [SetTag](#) (const [Tag](#) &t)
- void [SetValue](#) ([Value](#) const &vl)
- void [SetVL](#) (const [VL](#) &vl)
- void [SetVLToUndefined](#) ()
- void [SetVR](#) ([VR](#) const &vr)
- template<typename TDE, typename TSwap>
const std::ostream & [Write](#) (std::ostream &os) const

Additional Inherited Members

Protected Types inherited from [gdcm::DataElement](#)

- typedef [SmartPointer](#)< [Value](#) > [ValuePtr](#)

Protected Member Functions inherited from [gdcm::DataElement](#)

- void [SetValueFieldLength](#) ([VL](#) vl, bool readvalues)

Protected Attributes inherited from [gdcm::DataElement](#)

- [Tag](#) TagField
- [ValuePtr](#) ValueField
- [VL](#) ValueLengthField
- [VR](#) VRField

10.62.1 Detailed Description

Class to read/write a [DataElement](#) as CP246Explicit Data [Element](#).

Note

Some system are producing SQ, declare them as UN, but encode the SQ as 'Explicit' instead of Implicit

10.62.2 Member Function Documentation

10.62.2.1 GetLength()

```
VL gdcm::CP246ExplicitDataElement::GetLength () const
```


10.62.2.2 Read()

```
template<typename TSwap>
std::istream & gdcm::CP246ExplicitDataElement::Read (
    std::istream & is)
```

10.62.2.3 ReadPreValue()

```
template<typename TSwap>
std::istream & gdcm::CP246ExplicitDataElement::ReadPreValue (
    std::istream & is)
```

10.62.2.4 ReadValue()

```
template<typename TSwap>
std::istream & gdcm::CP246ExplicitDataElement::ReadValue (
    std::istream & is,
    bool readvalues = true)
```

10.62.2.5 ReadWithLength()

```
template<typename TSwap>
std::istream & gdcm::CP246ExplicitDataElement::ReadWithLength (
    std::istream & is,
    VL & length)
```

The documentation for this class was generated from the following file:


- [gdcmCP246ExplicitDataElement.h](#)

10.63 gdcm::CryptoFactory Class Reference

Class to do handle the crypto factory.

```
#include <gdcmCryptoFactory.h>
```

Inheritance diagram for gdcm::CryptoFactory:



Public Types

- enum `CryptoLib` {
`DEFAULT` = 0 ,
`OPENSSL` = 1 ,
`CAPI` = 2 ,
`OPENSSL7` = 3 }

Public Member Functions

- virtual `CryptographicMessageSyntax` * `CreateCMSProvider` ()=0

Static Public Member Functions

- static `CryptoFactory` * `GetFactoryInstance` (`CryptoLib` id=`DEFAULT`)

Protected Member Functions

- `CryptoFactory` ()=default
- `CryptoFactory` (`CryptoLib` id)
- `~CryptoFactory` ()=default

10.63.1 Detailed Description

Class to do handle the crypto factory.

GDCM needs to access in a platform independent way the user specified crypto engine. It can be:

- CAPI (windows only)
- OPENSSL (portable)
- OPENSSL7 (portable) By default the factory will try: CAPI if on windows OPENSSL if possible OPENSSL7 when older OpenSSL is used.

10.63.2 Member Enumeration Documentation**10.63.2.1 CryptoLib**

```
enum gdcm::CryptoFactory::CryptoLib
```

Enumerator

DEFAULT	
OPENSSL	
CAPI	
OPENSSL7	

10.63.3 Constructor & Destructor Documentation

10.63.3.1 CryptoFactory() [1/2]

```
gdcm::CryptoFactory::CryptoFactory (  
    CryptoLib id) [inline], [protected]
```

Referenced by [gdcm::OpenSSLCryptoFactory::OpenSSLCryptoFactory\(\)](#), [gdcm::OpenSSLP7CryptoFactory::OpenSSLP7CryptoFactory\(\)](#) and [GetFactoryInstance\(\)](#).

10.63.3.2 CryptoFactory() [2/2]

```
gdcm::CryptoFactory::CryptoFactory () [protected], [default]
```

10.63.3.3 ~CryptoFactory()

```
gdcm::CryptoFactory::~~CryptoFactory () [protected], [default]
```

10.63.4 Member Function Documentation

10.63.4.1 CreateCMSProvider()

```
virtual CryptographicMessageSyntax * gdcm::CryptoFactory::CreateCMSProvider () [pure virtual]
```

Implemented in [gdcm::CAPICryptoFactory](#), [gdcm::OpenSSLCryptoFactory](#), and [gdcm::OpenSSLP7CryptoFactory](#).

Examples

[BasicAnonymizer.cs](#), and [ClinicalTrialIdentificationWorkflow.cs](#).

10.63.4.2 GetFactoryInstance()

```
CryptoFactory * gdcm::CryptoFactory::GetFactoryInstance (  
    CryptoLib id = DEFAULT) [static]
```

References [CryptoFactory\(\)](#), and [DEFAULT](#).


The documentation for this class was generated from the following file:

- [gdcmCryptoFactory.h](#)

10.64 gdcm::CryptographicMessageSyntax Class Reference

```
#include <gdcmCryptographicMessageSyntax.h>
```

Inheritance diagram for gdcm::CryptographicMessageSyntax:



Public Types

- enum [CipherTypes](#) {
[DES3_CIPHER](#) ,
[AES128_CIPHER](#) ,
[AES192_CIPHER](#) ,
[AES256_CIPHER](#) }

Public Member Functions

- [CryptographicMessageSyntax](#) ()=default
- [CryptographicMessageSyntax](#) (const [CryptographicMessageSyntax](#) &)=delete
- virtual [~CryptographicMessageSyntax](#) ()=default
- virtual bool [Decrypt](#) (char *output, size_t &outlen, const char *array, size_t len) const =0
decrypt content from a CMS envelopedData structure
- virtual bool [Encrypt](#) (char *output, size_t &outlen, const char *array, size_t len) const =0
create a CMS envelopedData structure
- virtual [CipherTypes](#) [GetCipherType](#) () const =0
- void [operator=](#) (const [CryptographicMessageSyntax](#) &)=delete
- virtual bool [ParseCertificateFile](#) (const char *filename)=0
- virtual bool [ParseKeyFile](#) (const char *filename)=0
- virtual void [SetCipherType](#) ([CipherTypes](#) type)=0
- virtual bool [SetPassword](#) (const char *pass, size_t passLen)=0

10.64.1 Member Enumeration Documentation

10.64.1.1 CipherTypes

```
enum gdcm::CryptographicMessageSyntax::CipherTypes
```

Enumerator

DES3_CIPHER	
AES128_CIPHER	
AES192_CIPHER	
AES256_CIPHER	

10.64.2 Constructor & Destructor Documentation

10.64.2.1 CryptographicMessageSyntax() [1/2]

```
gdcmm::CryptographicMessageSyntax::CryptographicMessageSyntax () [default]
```

Referenced by [CryptographicMessageSyntax\(\)](#), and [operator=\(\)](#).

10.64.2.2 ~CryptographicMessageSyntax()

```
virtual gdcmm::CryptographicMessageSyntax::~~CryptographicMessageSyntax () [virtual], [default]
```

10.64.2.3 CryptographicMessageSyntax() [2/2]

```
gdcmm::CryptographicMessageSyntax::CryptographicMessageSyntax (
    const CryptographicMessageSyntax & ) [delete]
```

References [CryptographicMessageSyntax\(\)](#).

10.64.3 Member Function Documentation

10.64.3.1 Decrypt()

```
virtual bool gdcmm::CryptographicMessageSyntax::Decrypt (
    char * output,
    size_t & outlen,
    const char * array,
    size_t len) const [pure virtual]
```

decrypt content from a CMS envelopedData structure

Implemented in [gdcmm::CAPICryptographicMessageSyntax](#), [gdcmm::OpenSSLCryptographicMessageSyntax](#), and [gdcmm::OpenSSL7CryptographicMessageSyntax](#).

10.64.3.2 Encrypt()

```
virtual bool gdcM::CryptographicMessageSyntax::Encrypt (
    char * output,
    size_t & outlen,
    const char * array,
    size_t len) const [pure virtual]
```

create a CMS envelopedData structure

Implemented in [gdcM::CAPICryptographicMessageSyntax](#), [gdcM::OpenSSLCryptographicMessageSyntax](#), and [gdcM::OpenSSL7CryptographicMessageSyntax](#).

10.64.3.3 GetCipherType()

```
virtual CipherTypes gdcM::CryptographicMessageSyntax::GetCipherType () const [pure virtual]
```

Implemented in [gdcM::CAPICryptographicMessageSyntax](#), [gdcM::OpenSSLCryptographicMessageSyntax](#), and [gdcM::OpenSSL7CryptographicMessageSyntax](#).

10.64.3.4 operator=()

```
void gdcM::CryptographicMessageSyntax::operator= (
    const CryptographicMessageSyntax & ) [delete]
```

References [CryptographicMessageSyntax\(\)](#).

10.64.3.5 ParseCertificateFile()

```
virtual bool gdcM::CryptographicMessageSyntax::ParseCertificateFile (
    const char * filename) [pure virtual]
```

Implemented in [gdcM::CAPICryptographicMessageSyntax](#), [gdcM::OpenSSLCryptographicMessageSyntax](#), and [gdcM::OpenSSL7CryptographicMessageSyntax](#).

Examples

[BasicAnonymizer.cs](#), and [ClinicalTrialIdentificationWorkflow.cs](#).

10.64.3.6 ParseKeyFile()

```
virtual bool gdcM::CryptographicMessageSyntax::ParseKeyFile (
    const char * filename) [pure virtual]
```

Implemented in [gdcM::CAPICryptographicMessageSyntax](#), [gdcM::OpenSSLCryptographicMessageSyntax](#), and [gdcM::OpenSSL7CryptographicMessageSyntax](#).

10.64.3.7 SetCipherType()

```
virtual void gdcm::CryptographicMessageSyntax::SetCipherType (
    CipherTypes type) [pure virtual]
```

Implemented in [gdcm::CAPICryptographicMessageSyntax](#), [gdcm::OpenSSLCryptographicMessageSyntax](#), and [gdcm::OpenSSLP7CryptographicMessageSyntax](#).

10.64.3.8 SetPassword()

```
virtual bool gdcm::CryptographicMessageSyntax::SetPassword (
    const char * pass,
    size_t passLen) [pure virtual]
```

Implemented in [gdcm::CAPICryptographicMessageSyntax](#), [gdcm::OpenSSLCryptographicMessageSyntax](#), and [gdcm::OpenSSLP7CryptographicMessageSyntax](#).

The documentation for this class was generated from the following file:


- [gdcmCryptographicMessageSyntax.h](#)

10.65 gdcm::CSAElement Class Reference

Class to represent a CSA [Element](#).

```
#include <gdcmCSAElement.h>
```

Collaboration diagram for gdcm::CSAElement:



Public Member Functions

- [CSAElement](#) (const [CSAElement](#) &_val)
- [CSAElement](#) (unsigned int kf=0)
- const [ByteValue](#) * [GetByteValue](#) () const
- unsigned int [GetKey](#) () const
Set/Get Key.
- const char * [GetName](#) () const
Set/Get Name.
- unsigned int [GetNoOfItems](#) () const
Set/Get NoOfItems.
- unsigned int [GetSyngoDT](#) () const
Set/Get SyngoDT.
- [Value](#) & [GetValue](#) ()
- [Value](#) const & [GetValue](#) () const
Set/Get Value (bytes array, SQ of items, SQ of fragments):
- const [VM](#) & [GetVM](#) () const
Set/Get VM.
- [VR](#) const & [GetVR](#) () const
Set/Get VR.
- bool [IsEmpty](#) () const
Check if CSA Element is empty.
- bool [operator<](#) (const [CSAElement](#) &de) const
- [CSAElement](#) & [operator=](#) (const [CSAElement](#) &de)=default
- bool [operator==](#) (const [CSAElement](#) &de) const
- void [SetByteValue](#) (const char *array, [VL](#) length)
Set.
- void [SetKey](#) (unsigned int key)
- void [SetName](#) (const char *name)
- void [SetNoOfItems](#) (unsigned int items)
- void [SetSyngoDT](#) (unsigned int syngodt)
- void [SetValue](#) ([Value](#) const &vl)
- void [SetVM](#) (const [VM](#) &vm)
- void [SetVR](#) ([VR](#) const &vr)

Protected Types

- typedef [SmartPointer](#)< [Value](#) > [DataPtr](#)

Protected Attributes

- [DataPtr](#) [DataField](#)
- unsigned int [KeyField](#)
- std::string [NameField](#)
- unsigned int [NoOfItemsField](#)
- unsigned int [SyngoDTField](#)
- [VM](#) [ValueMultiplicityField](#)
- [VR](#) [VRField](#)

Friends

- `std::ostream & operator<<` (`std::ostream &os`, `const CSAElement &val`)

10.65.1 Detailed Description

Class to represent a CSA [Element](#).

See also

[CSAHeader](#)

Examples

[DumpCSA.cs](#), [DumpSiemensBase64.cxx](#), [MrProtocol.cxx](#), and [csa2img.cxx](#).

10.65.2 Member Typedef Documentation

10.65.2.1 DataPtr

```
typedef SmartPointer<Value> gdcm::CSAElement::DataPtr [protected]
```

10.65.3 Constructor & Destructor Documentation

10.65.3.1 CSAElement() [1/2]

```
gdcm::CSAElement::CSAElement (  
    unsigned int kf = 0) [inline]
```

References [KeyField](#), [NoOfItemsField](#), and [SyngoDTField](#).

Referenced by [CSAElement\(\)](#), [operator<\(\)](#), [operator<<](#), [operator=\(\)](#), and [operator==\(\)](#).

10.65.3.2 CSAElement() [2/2]

```
gdcm::CSAElement::CSAElement (  
    const CSAElement & _val) [inline]
```

References [CSAElement\(\)](#).

10.65.4 Member Function Documentation

10.65.4.1 GetByteValue()

```
const ByteValue * gdcM::CSAElement::GetByteValue () const [inline]
```

Return the [Value](#) of [CSAElement](#) as a [ByteValue](#) (if possible)

Warning

: You need to check for NULL return value

Examples

[DumpSiemensBase64.cxx](#), and [MrProtocol.cxx](#).

References [DataField](#).

10.65.4.2 GetKey()

```
unsigned int gdcM::CSAElement::GetKey () const [inline]
```

Set/Get Key.

References [KeyField](#).

Referenced by [operator<\(\)](#).

10.65.4.3 GetName()

```
const char * gdcM::CSAElement::GetName () const [inline]
```

Set/Get Name.

References [NameField](#).

10.65.4.4 GetNoOfItems()

```
unsigned int gdcM::CSAElement::GetNoOfItems () const [inline]
```

Set/Get NoOfItems.

References [NoOfItemsField](#).

10.65.4.5 GetSyngoDT()

```
unsigned int gdcm::CSAElement::GetSyngoDT () const [inline]
```

Set/Get SyngoDT.

References [SyngoDTField](#).

10.65.4.6 GetValue() [1/2]

```
Value & gdcm::CSAElement::GetValue () [inline]
```

References [DataField](#).

10.65.4.7 GetValue() [2/2]

```
Value const & gdcm::CSAElement::GetValue () const [inline]
```

Set/Get [Value](#) (bytes array, SQ of items, SQ of fragments):

Examples

[csa2img.cxx](#).

References [DataField](#).

10.65.4.8 GetVM()

```
const VM & gdcm::CSAElement::GetVM () const [inline]
```

Set/Get [VM](#).

References [ValueMultiplicityField](#).

10.65.4.9 GetVR()

```
VR const & gdcm::CSAElement::GetVR () const [inline]
```

Set/Get [VR](#).

References [VRField](#).

10.65.4.10 IsEmpty()

```
bool gdcm::CSAElement::IsEmpty () const [inline]
```

Check if CSA [Element](#) is empty.

Examples

[csa2img.cxx](#).

References [DataField](#).

10.65.4.11 operator<()

```
bool gdcm::CSAElement::operator< (  
    const CSAElement & de) const [inline]
```

References [CSAElement\(\)](#), and [GetKey\(\)](#).

10.65.4.12 operator=()

```
CSAElement & gdcm::CSAElement::operator= (  
    const CSAElement & de) [default]
```

References [CSAElement\(\)](#).

10.65.4.13 operator==()

```
bool gdcm::CSAElement::operator== (  
    const CSAElement & de) const [inline]
```

References [CSAElement\(\)](#), [KeyField](#), [NameField](#), [SyngoDTField](#), [ValueMultiplicityField](#), and [VRField](#).

10.65.4.14 SetByteValue()

```
void gdcm::CSAElement::SetByteValue (  
    const char * array,  
    VL length) [inline]
```

Set.

References [SetValue\(\)](#).

10.65.4.15 SetKey()

```
void gdcm::CSAElement::SetKey (
    unsigned int key) [inline]
```

References [KeyField](#).

10.65.4.16 SetName()

```
void gdcm::CSAElement::SetName (
    const char * name) [inline]
```

References [NameField](#).

10.65.4.17 SetNoOfItems()

```
void gdcm::CSAElement::SetNoOfItems (
    unsigned int items) [inline]
```

References [NoOfItemsField](#).

10.65.4.18 SetSyngoDT()

```
void gdcm::CSAElement::SetSyngoDT (
    unsigned int syngodt) [inline]
```

References [SyngoDTField](#).

10.65.4.19 SetValue()

```
void gdcm::CSAElement::SetValue (
    Value const & vl) [inline]
```

References [DataField](#).

Referenced by [SetByteValue\(\)](#).

10.65.4.20 SetVM()

```
void gdcm::CSAElement::SetVM (
    const VM & vm) [inline]
```

References [ValueMultiplicityField](#).

10.65.4.21 SetVR()

```
void gdcM::CSAElement::SetVR (
    VR const & vr) [inline]
```

References [VRField](#).

10.65.5 Friends And Related Symbol Documentation

10.65.5.1 operator<<

```
std::ostream & operator<< (
    std::ostream & os,
    const CSAElement & val) [friend]
```

References [CSAElement\(\)](#), [DataField](#), [gdcM_assert](#), [gdcM::ByteValue::GetLength\(\)](#), [gdcM::ByteValue::GetPointer\(\)](#), [KeyField](#), [NameField](#), [NoOfItemsField](#), [SyngoDTField](#), [ValueMultiplicityField](#), [gdcM::VM::VM1](#), and [VRField](#).

10.65.6 Member Data Documentation

10.65.6.1 DataField

```
DataPtr gdcM::CSAElement::DataField [protected]
```

Referenced by [GetByteValue\(\)](#), [GetValue\(\)](#), [GetValue\(\)](#), [IsEmpty\(\)](#), [operator<<](#), and [SetValue\(\)](#).

10.65.6.2 KeyField

```
unsigned int gdcM::CSAElement::KeyField [protected]
```

Referenced by [CSAElement\(\)](#), [GetKey\(\)](#), [operator<<](#), [operator==\(\)](#), and [SetKey\(\)](#).

10.65.6.3 NameField

```
std::string gdcM::CSAElement::NameField [protected]
```

Referenced by [GetName\(\)](#), [operator<<](#), [operator==\(\)](#), and [SetName\(\)](#).

10.65.6.4 NoOfItemsField

```
unsigned int gdcM::CSAElement::NoOfItemsField [protected]
```

Referenced by [CSAElement\(\)](#), [GetNoOfItems\(\)](#), [operator<<](#), and [SetNoOfItems\(\)](#).

10.65.6.5 SyngoDTField

```
unsigned int gdcm::CSAElement::SyngoDTField [protected]
```

Referenced by [CSAElement\(\)](#), [GetSyngoDT\(\)](#), [operator<<](#), [operator==\(\)](#), and [SetSyngoDT\(\)](#).

10.65.6.6 ValueMultiplicityField

```
VM gdcm::CSAElement::ValueMultiplicityField [protected]
```

Referenced by [GetVM\(\)](#), [operator<<](#), [operator==\(\)](#), and [SetVM\(\)](#).

10.65.6.7 VRField

```
VR gdcm::CSAElement::VRField [protected]
```

Referenced by [GetVR\(\)](#), [operator<<](#), [operator==\(\)](#), and [SetVR\(\)](#).

The documentation for this class was generated from the following file:

- [gdcmCSAElement.h](#)

10.66 gdcm::CSAHeader Class Reference

Class for [CSAHeader](#).

```
#include <gdcmCSAHeader.h>
```

Public Types

- enum [CSAHeaderType](#) {
 [UNKNOWN](#) = 0 ,
 [SV10](#) ,
 [NOMAGIC](#) ,
 [DATASET_FORMAT](#) ,
 [INTERFILE](#) ,
 [ZEROED_OUT](#) }

Diverse format of [CSAHeader](#) as found 'in the wild'.

Public Member Functions

- [CSAHeader](#) ()
- [~CSAHeader](#) ()=default
- bool [FindCSAElementByName](#) (const char *name)
- const [CSAElement](#) & [GetCSAElementByName](#) (const char *name)
- const [DataSet](#) & [GetDataSet](#) () const
Return the [DataSet](#) output (use only if Format == DATASET_FORMAT)
- [CSAHeaderType](#) [GetFormat](#) () const
- const char * [GetInterfile](#) () const
Return the string output (use only if Format == Interfile)
- bool [GetMrProtocol](#) (const [DataSet](#) &ds, [MrProtocol](#) &mrProtocol)
Retrieve the ASCII portion stored within the MrProtocol/MrPhoenixProtocol:
- bool [LoadFromDataElement](#) ([DataElement](#) const &de)
Decode the [CSAHeader](#) from element 'de'.
- void [Print](#) (std::ostream &os) const
Print the [CSAHeader](#) (use only if Format == SV10 or NOMAGIC)

Static Public Member Functions

- static const [PrivateTag](#) & [GetCSADataInfo](#) ()
- static const [PrivateTag](#) & [GetCSAImageHeaderInfoTag](#) ()
- static const [PrivateTag](#) & [GetCSASeriesHeaderInfoTag](#) ()

Protected Member Functions

- const [CSAElement](#) & [GetCSAEEnd](#) () const

Friends

- std::ostream & [operator<<](#) (std::ostream &_os, const [CSAHeader](#) &d)

10.66.1 Detailed Description

Class for [CSAHeader](#).

SIEMENS store private information in tag (0x0029,0x10,"SIEMENS CSA HEADER") this class is meant for user wishing to access values stored within this private attribute. There are basically two main 'format' for this attribute : SV10/↵ NOMAGIC and DATASET_FORMAT SV10 and NOMAGIC are from a user prospective identical, see CSAHeader.xml for possible name / value stored in this format. DATASET_FORMAT is in fact simply just another DICOM dataset (implicit) with -currently unknown- value. This can be only be printed for now.

Warning

Everything you do with this code is at your own risk, since decoding process was not written from specification documents.

the API of this class might change.

Todo MrEvaProtocol in 29,1020 contains ^M that would be nice to get rid of on UNIX system...

See also

[PDBHeader](#)

External references: 5.1.3.2.4.1 MEDCOM History Information and 5.1.4.3 CSA Non-Image [Module](#) in http://tamsinfo.toshiba.com/docrequest/pdf/E.Soft_v2.0.pdf

Examples

[DumpCSA.cs](#), [DumpSiemensBase64.cxx](#), [MrProtocol.cxx](#), and [csa2img.cxx](#).

10.66.2 Member Enumeration Documentation**10.66.2.1 CSAHeaderType**

```
enum gdcmm::CSAHeader::CSAHeaderType
```

Diverse format of [CSAHeader](#) as found 'in the wild'.

Enumerator

UNKNOWN	
SV10	
NOMAGIC	
DATASET_FORMAT	
INTERFILE	
ZEROED_OUT	

10.66.3 Constructor & Destructor Documentation**10.66.3.1 CSAHeader()**

```
gdcmm::CSAHeader::CSAHeader () [inline]
```

References [UNKNOWN](#).

Referenced by [operator<<](#).

10.66.3.2 ~CSAHeader()

```
gdcm::CSAHeader::~~CSAHeader () [default]
```

10.66.4 Member Function Documentation

10.66.4.1 FindCSAELEMENTByName()

```
bool gdcm::CSAHeader::FindCSAELEMENTByName (
    const char * name)
```

Return true if the CSA element matching 'name' is found or not

Warning

Case Sensitive

Examples

[DumpCSA.cs](#), [DumpSiemensBase64.cxx](#), [MrProtocol.cxx](#), and [csa2img.cxx](#).

10.66.4.2 GetCSADATAInfo()

```
const PrivateTag & gdcm::CSAHeader::GetCSADATAInfo () [static]
```

Return the private tag used by SIEMENS to store the CSA Data Info This is: [PrivateTag](#)(0x0029,0x10,"SIEMENS CSA NON-IMAGE");

10.66.4.3 GetCSAELEMENTEnd()

```
const CSAElement & gdcm::CSAHeader::GetCSAELEMENTEnd () const [protected]
```

10.66.4.4 GetCSAELEMENTByName()

```
const CSAElement & gdcm::CSAHeader::GetCSAELEMENTByName (
    const char * name)
```

Return the [CSAElement](#) corresponding to name 'name'

Warning

Case Sensitive

Examples

[DumpCSA.cs](#), [DumpSiemensBase64.cxx](#), [MrProtocol.cxx](#), and [csa2img.cxx](#).

10.66.4.5 GetCSAImageHeaderInfoTag()

```
const PrivateTag & gdcm::CSAHeader::GetCSAImageHeaderInfoTag () [static]
```

Return the private tag used by SIEMENS to store the CSA [Image](#) Header This is: [PrivateTag](#)(0x0029,0x10,"SIEMENS CSA HEADER");

Examples

[DumpCSA.cs](#), [DumpSiemensBase64.cxx](#), [PublicDict.cxx](#), and [csa2img.cxx](#).

10.66.4.6 GetCSASeriesHeaderInfoTag()

```
const PrivateTag & gdcm::CSAHeader::GetCSASeriesHeaderInfoTag () [static]
```

Return the private tag used by SIEMENS to store the CSA [Series](#) Header This is: [PrivateTag](#)(0x0029,0x20,"SIEMENS CSA HEADER");

Examples

[MrProtocol.cxx](#).

10.66.4.7 GetDataSet()

```
const DataSet & gdcm::CSAHeader::GetDataSet () const [inline]
```

Return the [DataSet](#) output (use only if Format == DATASET_FORMAT)

10.66.4.8 GetFormat()

```
CSAHeaderType gdcm::CSAHeader::GetFormat () const
```

return the format of the [CSAHeader](#) SV10 and NOMAGIC are equivalent.

10.66.4.9 GetInterfile()

```
const char * gdcm::CSAHeader::GetInterfile () const [inline]
```

Return the string output (use only if Format == Interfile)

10.66.4.10 GetMrProtocol()

```
bool gdcM::CSAHeader::GetMrProtocol (
    const DataSet & ds,
    MrProtocol & mrProtocol)
```

Retrieve the ASCII portion stored within the MrProtocol/MrPhoenixProtocol:

Examples

[MrProtocol.cxx](#).

10.66.4.11 LoadFromDataElement()

```
bool gdcM::CSAHeader::LoadFromDataElement (
    DataElement const & de)
```

Decode the [CSAHeader](#) from element 'de'.

Examples

[DumpCSA.cs](#), [DumpSiemensBase64.cxx](#), [MrProtocol.cxx](#), and [csa2img.cxx](#).

10.66.4.12 Print()

```
void gdcM::CSAHeader::Print (
    std::ostream & os) const
```

Print the [CSAHeader](#) (use only if Format == SV10 or NOMAGIC)

Examples

[csa2img.cxx](#).

Referenced by [operator<<](#).

10.66.5 Friends And Related Symbol Documentation

10.66.5.1 operator<<

```
std::ostream & operator<< (
    std::ostream & _os,
    const CSAHeader & d) [friend]
```

References [CSAHeader\(\)](#), and [Print\(\)](#).

The documentation for this class was generated from the following file:

- [gdcMCSAHeader.h](#)

10.67 gdcm::CSAHeaderDict Class Reference

Class to represent a map of [CSAHeaderDictEntry](#).

```
#include <gdcmCSAHeaderDict.h>
```

Public Types

- typedef MapCSAHeaderDictEntry::const_iterator [ConstIterator](#)
- typedef MapCSAHeaderDictEntry::iterator [Iterator](#)
- typedef std::set< [CSAHeaderDictEntry](#) > [MapCSAHeaderDictEntry](#)

Public Member Functions

- [CSAHeaderDict](#) ()
- [CSAHeaderDict](#) (const [CSAHeaderDict](#) &_val)=delete
- void [AddCSAHeaderDictEntry](#) (const [CSAHeaderDictEntry](#) &de)
- [ConstIterator](#) [Begin](#) () const
- [ConstIterator](#) [End](#) () const
- const [CSAHeaderDictEntry](#) & [GetCSAHeaderDictEntry](#) (const char *name) const
- bool [IsEmpty](#) () const
- [CSAHeaderDict](#) & [operator=](#) (const [CSAHeaderDict](#) &_val)=delete

Protected Member Functions

- void [LoadDefault](#) ()

Friends

- class [Dicts](#)
- std::ostream & [operator<<](#) (std::ostream &_os, const [CSAHeaderDict](#) &_val)

10.67.1 Detailed Description

Class to represent a map of [CSAHeaderDictEntry](#).

Examples

[MrProtocol.cxx](#).

10.67.2 Member Typedef Documentation

10.67.2.1 ConstIterator

```
typedef MapCSAHeaderDictEntry::const_iterator gdcm::CSAHeaderDict::ConstIterator
```

10.67.2.2 Iterator

```
typedef MapCSAHeaderDictEntry::iterator gdcm::CSAHeaderDict::Iterator
```

10.67.2.3 MapCSAHeaderDictEntry

```
typedef std::set<CSAHeaderDictEntry> gdcm::CSAHeaderDict::MapCSAHeaderDictEntry
```

10.67.3 Constructor & Destructor Documentation

10.67.3.1 CSAHeaderDict() [1/2]

```
gdcm::CSAHeaderDict::CSAHeaderDict () [inline]
```

References [gdcm_assert](#).

Referenced by [CSAHeaderDict\(\)](#), [operator<<](#), and [operator=\(\)](#).

10.67.3.2 CSAHeaderDict() [2/2]

```
gdcm::CSAHeaderDict::CSAHeaderDict (  
    const CSAHeaderDict & _val) [delete]
```

References [CSAHeaderDict\(\)](#), and [operator<<](#).

10.67.4 Member Function Documentation

10.67.4.1 AddCSAHeaderDictEntry()

```
void gdcm::CSAHeaderDict::AddCSAHeaderDictEntry (  
    const CSAHeaderDictEntry & de) [inline]
```

References [gdcm_assert](#).

10.67.4.2 Begin()

```
ConstIterator gdcm::CSAHeaderDict::Begin () const [inline]
```

10.67.4.3 End()

```
ConstIterator gdcm::CSAHeaderDict::End () const [inline]
```

10.67.4.4 GetCSAHeaderDictEntry()

```
const CSAHeaderDictEntry & gdcm::CSAHeaderDict::GetCSAHeaderDictEntry (  
    const char * name) const [inline]
```

Examples

[MrProtocol.cxx](#).

10.67.4.5 IsEmpty()

```
bool gdcm::CSAHeaderDict::IsEmpty () const [inline]
```

10.67.4.6 LoadDefault()

```
void gdcm::CSAHeaderDict::LoadDefault () [protected]
```

10.67.4.7 operator=()

```
CSAHeaderDict & gdcm::CSAHeaderDict::operator= (  
    const CSAHeaderDict & _val) [delete]
```

References [CSAHeaderDict\(\)](#).

10.67.5 Friends And Related Symbol Documentation

10.67.5.1 Dicts

```
friend class Dicts [friend]
```

References [Dicts](#).

Referenced by [Dicts](#).

10.67.5.2 operator<<

```
std::ostream & operator<< (  
    std::ostream & _os,  
    const CSAHeaderDict & _val) [friend]
```

References [CSAHeaderDict\(\)](#).

Referenced by [CSAHeaderDict\(\)](#).

The documentation for this class was generated from the following file:

- [gdcmCSAHeaderDict.h](#)

10.68 gdcm::CSAHeaderDictEntry Class Reference

Class to represent an Entry in the [Dict](#).

```
#include <gdcmCSAHeaderDictEntry.h>
```

Public Member Functions

- [CSAHeaderDictEntry](#) (const char *name="", [VR](#) const &vr=[VR::INVALID](#), [VM](#) const &vm=[VM::VM0](#), const char *desc="")
- const char * [GetDescription](#) () const
Set/Get Description.
- const char * [GetName](#) () const
Set/Get Name.
- const [VM](#) & [GetVM](#) () const
Set/Get VM.
- const [VR](#) & [GetVR](#) () const
Set/Get VR.
- bool [operator<](#) (const [CSAHeaderDictEntry](#) &entry) const
- void [SetDescription](#) (const char *desc)
- void [SetName](#) (const char *name)
- void [SetVM](#) ([VM](#) const &vm)
- void [SetVR](#) (const [VR](#) &vr)

Friends

- std::ostream & [operator<<](#) (std::ostream &_os, const [CSAHeaderDictEntry](#) &_val)

10.68.1 Detailed Description

Class to represent an Entry in the [Dict](#).

Does not really exist within the DICOM definition, just a way to minimize storage and have a mapping from [gdcm::Tag](#) to the needed information

Note

bla TODO FIXME: Need a PublicCSAHeaderDictEntry...indeed [CSAHeaderDictEntry](#) has a notion of retired which does not exist in PrivateCSAHeaderDictEntry...

See also

[gdcm::Dict](#)

Examples

[MrProtocol.cxx](#).

10.68.2 Constructor & Destructor Documentation

10.68.2.1 CSAHeaderDictEntry()

```
gdcm::CSAHeaderDictEntry::CSAHeaderDictEntry (  
    const char * name = "",  
    VR const & vr = VR::INVALID,  
    VM const & vm = VM::VM0,  
    const char * desc = "") [inline]
```

References [gdcm::VR::INVALID](#), and [gdcm::VM::VM0](#).

Referenced by [operator<\(\)](#), and [operator<<](#).

10.68.3 Member Function Documentation

10.68.3.1 GetDescription()

```
const char * gdcm::CSAHeaderDictEntry::GetDescription () const [inline]
```

Set/Get Description.

10.68.3.2 GetName()

```
const char * gdcm::CSAHeaderDictEntry::GetName () const [inline]
```

Set/Get Name.

Referenced by [operator<\(\)](#).

10.68.3.3 GetVM()

```
const VM & gdcm::CSAHeaderDictEntry::GetVM () const [inline]
```

Set/Get [VM](#).

10.68.3.4 GetVR()

```
const VR & gdcm::CSAHeaderDictEntry::GetVR () const [inline]
```

Set/Get [VR](#).

10.68.3.5 operator<()

```
bool gdcm::CSAHeaderDictEntry::operator< (
    const CSAHeaderDictEntry & entry) const [inline]
```

References [CSAHeaderDictEntry\(\)](#), and [GetName\(\)](#).

10.68.3.6 SetDescription()

```
void gdcm::CSAHeaderDictEntry::SetDescription (
    const char * desc) [inline]
```

10.68.3.7 SetName()

```
void gdcm::CSAHeaderDictEntry::SetName (
    const char * name) [inline]
```

10.68.3.8 SetVM()

```
void gdcm::CSAHeaderDictEntry::SetVM (
    VM const & vm) [inline]
```

10.68.3.9 SetVR()

```
void gdcm::CSAHeaderDictEntry::SetVR (
    const VR & vr) [inline]
```

10.68.4 Friends And Related Symbol Documentation

10.68.4.1 operator<<

```
std::ostream & operator<< (
    std::ostream & _os,
    const CSAHeaderDictEntry & _val) [friend]
```

References [CSAHeaderDictEntry\(\)](#).


The documentation for this class was generated from the following file:

- [gdcmCSAHeaderDictEntry.h](#)


10.69 gdcm::CSAHeaderDictException Class Reference

```
#include <gdcmCSAHeaderDict.h>
```

Inheritance diagram for gdcm::CSAHeaderDictException:



Collaboration diagram for gdcm::CSAHeaderDictException:



The documentation for this class was generated from the following file:


- [gdcmCSAHeaderDict.h](#)

10.70 gdcm::network::CStoreRQ Class Reference


[CStoreRQ](#).

```
#include <gdcmCStoreMessages.h>
```

Inheritance diagram for `gdcm::network::CStoreRQ`:



Collaboration diagram for `gdcm::network::CStoreRQ`:



Public Member Functions

- `std::vector< PresentationDataValue > ConstructPDV` (const [ULConnection](#) &inConnection, const [File](#) &file, bool writeDataSet=true)

Public Member Functions inherited from [gdcm::network::BaseCompositeMessage](#)

- virtual `~BaseCompositeMessage` ()=default

10.70.1 Detailed Description

[CStoreRQ](#).

this file defines the messages for the cecho action

10.70.2 Member Function Documentation

10.70.2.1 ConstructPDV()

```
std::vector< PresentationDataValue > gdcm::network::CStoreRQ::ConstructPDV (
    const ULConnection & inConnection,
    const File & file,
    bool writeDataSet = true)
```

The documentation for this class was generated from the following file:


- [gdcmCStoreMessages.h](#)

10.71 gdcm::network::CStoreRSP Class Reference


[CStoreRSP](#) this file defines the messages for the cecho action.

```
#include <gdcmCStoreMessages.h>
```

Inheritance diagram for gdcm::network::CStoreRSP:



Collaboration diagram for gdcm::network::CStoreRSP:



Public Member Functions

- `std::vector< PresentationDataValue > ConstructPDV` (const [DataSet](#) *inDataSet, const [BasePDU](#) *inPC)

Public Member Functions inherited from [gdcm::network::BaseCompositeMessage](#)

- virtual `~BaseCompositeMessage` ()=default

10.71.1 Detailed Description

[CStoreRSP](#) this file defines the messages for the cecho action.

10.71.2 Member Function Documentation

10.71.2.1 ConstructPDV()

```
std::vector< PresentationDataValue > gdcm::network::CStoreRSP::ConstructPDV (
    const DataSet * inDataSet,
    const BasePDU * inPC)
```

The documentation for this class was generated from the following file:


- [gdcmCStoreMessages.h](#)

10.72 gdcm::Curve Class Reference


[Curve](#) class to handle element 50xx,3000 [Curve](#) Data.

```
#include <gdcmCurve.h>
```

Inheritance diagram for `gdcm::Curve`:



Collaboration diagram for gdcm::Curve:



Public Member Functions

- [Curve](#) ()
- [Curve](#) ([Curve](#) const &ov)
- [~Curve](#) () override
- void [Decode](#) (std::istream &is, std::ostream &os)
- void [GetAsPoints](#) (float *array) const
- std::vector< unsigned short > const & [GetCurveDataDescriptor](#) () const
- unsigned short [GetDataValueRepresentation](#) () const
- unsigned short [GetDimensions](#) () const
- unsigned short [GetGroup](#) () const
- unsigned short [GetNumberOfPoints](#) () const
- const char * [GetTypeOfData](#) () const
- const char * [GetTypeOfDataDescription](#) () const
- bool [IsEmpty](#) () const
- void [Print](#) (std::ostream &) const override
- void [SetCoordinateStartValue](#) (unsigned short v)
- void [SetCoordinateStepValue](#) (unsigned short v)
- void [SetCurve](#) (const char *array, unsigned int length)
- void [SetCurveDataDescriptor](#) (const uint16_t *values, size_t num)
- void [SetCurveDescription](#) (const char *curvedescription)
- void [SetDataValueRepresentation](#) (unsigned short datavaluerepresentation)
- void [SetDimensions](#) (unsigned short dimensions)
- void [SetGroup](#) (unsigned short group)
- void [SetNumberOfPoints](#) (unsigned short numberofpoints)
- void [SetTypeOfData](#) (const char *typeofdata)
- void [Update](#) (const [DataElement](#) &de)

Public Member Functions inherited from [gdcm::Object](#)

- [Object](#) ()
- [Object](#) (const [Object](#) &)
- *Special requirement for copy/cstor, assignment operator.*
- virtual [~Object](#) ()
- void [operator=](#) (const [Object](#) &)

Static Public Member Functions

- static unsigned int [GetNumberOfCurves](#) ([DataSet](#) const &ds)

Additional Inherited Members

Protected Member Functions inherited from [gdcm::Object](#)

- void [Register](#) ()
- void [UnRegister](#) ()

10.72.1 Detailed Description

[Curve](#) class to handle element 50xx,3000 [Curve](#) Data.

WARNING: This is deprecated and lastly defined in PS 3.3 - 2004

Examples:

- GE_DLX-8-MONO2-Multiframe-Jpeg_Lossless.dcm
- GE_DLX-8-MONO2-Multiframe.dcm
- gdcmSampleData/Philips_Medical_Images/integris_HV_5000/xa_integris.dcm
- TOSHIBA-CurveData[1-3].dcm

10.72.2 Constructor & Destructor Documentation

10.72.2.1 [Curve\(\)](#) [1/2]

```
gdcm::Curve::Curve ()
```

Referenced by [Curve\(\)](#).

10.72.2.2 [~Curve\(\)](#)

```
gdcm::Curve::~~Curve () [override]
```

10.72.2.3 [Curve\(\)](#) [2/2]

```
gdcm::Curve::Curve (  
    Curve const & ov)
```

References [Curve\(\)](#).

10.72.3 Member Function Documentation

10.72.3.1 Decode()

```
void gdcm::Curve::Decode (
    std::istream & is,
    std::ostream & os)
```

10.72.3.2 GetAsPoints()

```
void gdcm::Curve::GetAsPoints (
    float * array) const
```

10.72.3.3 GetCurveDataDescriptor()

```
std::vector< unsigned short > const & gdcm::Curve::GetCurveDataDescriptor () const
```

10.72.3.4 GetDataValueRepresentation()

```
unsigned short gdcm::Curve::GetDataValueRepresentation () const
```

10.72.3.5 GetDimensions()

```
unsigned short gdcm::Curve::GetDimensions () const
```

10.72.3.6 GetGroup()

```
unsigned short gdcm::Curve::GetGroup () const
```

10.72.3.7 GetNumberOfCurves()

```
unsigned int gdcm::Curve::GetNumberOfCurves (
    DataSet const & ds) [static]
```

10.72.3.8 GetNumberOfPoints()

```
unsigned short gdcm::Curve::GetNumberOfPoints () const
```

10.72.3.9 GetTypeOfData()

```
const char * gdcm::Curve::GetTypeOfData () const
```

10.72.3.10 GetTypeOfDataDescription()

```
const char * gdcm::Curve::GetTypeOfDataDescription () const
```

10.72.3.11 IsEmpty()

```
bool gdcm::Curve::IsEmpty () const
```

10.72.3.12 Print()

```
void gdcm::Curve::Print (
    std::ostream & ) const [override], [virtual]
```

Reimplemented from [gdcm::Object](#).

10.72.3.13 SetCoordinateStartValue()

```
void gdcm::Curve::SetCoordinateStartValue (
    unsigned short v)
```

10.72.3.14 SetCoordinateStepValue()

```
void gdcm::Curve::SetCoordinateStepValue (
    unsigned short v)
```

10.72.3.15 SetCurve()

```
void gdcm::Curve::SetCurve (
    const char * array,
    unsigned int length)
```

10.72.3.16 SetCurveDataDescriptor()

```
void gdcm::Curve::SetCurveDataDescriptor (
    const uint16_t * values,
    size_t num)
```

10.72.3.17 SetCurveDescription()

```
void gdcm::Curve::SetCurveDescription (
    const char * curvedescription)
```

10.72.3.18 SetDataValueRepresentation()

```
void gdcm::Curve::SetDataValueRepresentation (
    unsigned short datavaluerepresentation)
```

10.72.3.19 SetDimensions()

```
void gdcm::Curve::SetDimensions (
    unsigned short dimensions)
```

10.72.3.20 SetGroup()

```
void gdcm::Curve::SetGroup (
    unsigned short group)
```

10.72.3.21 SetNumberOfPoints()

```
void gdcm::Curve::SetNumberOfPoints (
    unsigned short numberofpoints)
```

10.72.3.22 SetTypeOfData()

```
void gdcm::Curve::SetTypeOfData (
    const char * typeofdata)
```

10.72.3.23 Update()

```
void gdcm::Curve::Update (
    const DataElement & de)
```

The documentation for this class was generated from the following file:


- [gdcmCurve.h](#)

10.73 gdcm::DataElement Class Reference


Class to represent a Data [Element](#) either Implicit or Explicit.

```
#include <gdcmDataElement.h>
```

Inheritance diagram for gdcm::DataElement:



Collaboration diagram for gdcm::DataElement:



Public Member Functions

- [DataElement](#) (const [DataElement](#) &_val)
- [DataElement](#) (const [Tag](#) &t=[Tag](#)(0), const [VL](#) &vl=0, const [VR](#) &vr=[VR::INVALID](#))
- void [Clear](#) ()
 - Clear Data [Element](#) (make [Value](#) empty and invalidate [Tag](#) & [VR](#))*
- void [Empty](#) ()
 - Make Data [Element](#) empty (no [Value](#))*
- const [ByteValue](#) * [GetByteValue](#) () const
- template<typename TDE>
 - [VL](#) [GetLength](#) () const
- [SequenceOfFragments](#) * [GetSequenceOfFragments](#) ()
- const [SequenceOfFragments](#) * [GetSequenceOfFragments](#) () const
- [Tag](#) & [GetTag](#) ()
- const [Tag](#) & [GetTag](#) () const
 - Get [Tag](#).*
- [Value](#) & [GetValue](#) ()
- [Value](#) const & [GetValue](#) () const
 - Set/Get [Value](#) (bytes array, SQ of items, SQ of fragments):*
- [SmartPointer](#)< [SequenceOfItems](#) > [GetValueAsSQ](#) () const
- [VL](#) & [GetVL](#) ()
- const [VL](#) & [GetVL](#) () const
 - Get [VL](#).*
- [VR](#) const & [GetVR](#) () const
- bool [IsEmpty](#) () const
 - Check if Data [Element](#) is empty.*
- bool [IsUndefinedLength](#) () const
 - return if [Value](#) Length if of undefined length*
- bool [operator<](#) (const [DataElement](#) &de) const
- [DataElement](#) & [operator=](#) (const [DataElement](#) &)=default
- bool [operator==](#) (const [DataElement](#) &de) const
- template<typename TDE, typename TSwap>
 - std::istream & [Read](#) (std::istream &is)
- template<typename TDE, typename TSwap>
 - std::istream & [ReadOrSkip](#) (std::istream &is, std::set< [Tag](#) > const &skiptags)
- template<typename TDE, typename TSwap>
 - std::istream & [ReadPreValue](#) (std::istream &is, std::set< [Tag](#) > const &skiptags)
- template<typename TDE, typename TSwap>
 - std::istream & [ReadValue](#) (std::istream &is, std::set< [Tag](#) > const &skiptags)
- template<typename TDE, typename TSwap>
 - std::istream & [ReadValueWithLength](#) (std::istream &is, [VL](#) &length, std::set< [Tag](#) > const &skiptags)
- template<typename TDE, typename TSwap>
 - std::istream & [ReadWithLength](#) (std::istream &is, [VL](#) &length)
- void [SetByteValue](#) (const char *array, [VL](#) length)
- void [SetTag](#) (const [Tag](#) &t)
- void [SetValue](#) ([Value](#) const &vl)
- void [SetVL](#) (const [VL](#) &vl)
- void [SetVLToUndefined](#) ()
- void [SetVR](#) ([VR](#) const &vr)
- template<typename TDE, typename TSwap>
 - const std::ostream & [Write](#) (std::ostream &os) const

Protected Types

- typedef [SmartPointer](#)< [Value](#) > [ValuePtr](#)

Protected Member Functions

- void [SetValueFieldLength](#) ([VL](#) vl, bool readvalues)

Protected Attributes

- [Tag](#) TagField
- [ValuePtr](#) ValueField
- [VL](#) ValueLengthField
- [VR](#) VRField

Friends

- std::ostream & [operator<<](#) (std::ostream &_os, const [DataElement](#) &_val)

10.73.1 Detailed Description

Class to represent a Data [Element](#) either Implicit or Explicit.

DATA ELEMENT: A unit of information as defined by a single entry in the data dictionary. An encoded Information [Object](#) Definition (IOD) [Attribute](#) that is composed of, at a minimum, three fields: a Data [Element](#) [Tag](#), a [Value](#) Length, and a [Value](#) Field. For some specific Transfer Syntaxes, a Data [Element](#) also contains a [VR](#) Field where the [Value](#) Representation of that Data [Element](#) is specified explicitly.

Design:

- A [DataElement](#) in GDCM always store [VL](#) ([Value](#) Length) on a 32 bits integer even when [VL](#) is 16 bits
- A [DataElement](#) always store the [VR](#) even for Implicit TS, in which case [VR](#) is defaulted to [VR::INVALID](#)
- For [Item](#) start/end (See 0xfffe tags), [Value](#) is NULL

See also

[ExplicitDataElement](#) [ImplicitDataElement](#)

Examples

[BasicImageAnonymizer.cs](#), [ChangePrivateTags.cxx](#), [ChangeSequenceUltrasound.cxx](#), [CreateARGBImage.cxx](#), [CreateCMYKImage.cxx](#), [DecompressImage.cs](#), [DecompressImageMultiframe.cs](#), [DecompressJPEGFile.cs](#), [DiffFile.cxx](#), [DumpADAC.cxx](#), [DumpCSA.cs](#), [DumpExamCard.cxx](#), [DumpGEMSMovieGroup.cxx](#), [DumpImageHeaderInfo.cxx](#), [DumpPhilipsECHO.cxx](#), [DumpSiemensBase64.cxx](#), [DumpToshibaDT1.cxx](#), [DumpToshibaDTI2.cxx](#), [DumpVisusChange.cxx](#), [DuplicatePCDE.cxx](#), [ELSCINT1WaveToText.cxx](#), [ExtractEncapsulatedFile.cs](#), [ExtractEncryptedContent.cxx](#), [ExtractIconFromFile.cxx](#), [Extracting_All_Resolution.cxx](#), [Fake_Image_Using_Stream_Image_Writer.cxx](#), [FileChangeTS.cs](#), [FileChangeTSLossy.cs](#), [FixBrokenJ2K.cxx](#), [FixJAIBugJPEGLS.cxx](#), [GenAllVR.cxx](#), [GenFakeIdentifyFile.cxx](#), [GenFakeImage.cxx](#), [GenLongSeqs.cxx](#), [GenSeqs.cxx](#), [GetJPEGSamplePrecision.cxx](#), [GetSequenceUltrasound.cxx](#), [GetSubSequenceData.cxx](#), [LargeVRDSExplicit.cxx](#), [MpegVideoInfo.cs](#), [NewSequence.cs](#), [ReadAndDumpDICOMDIR.cxx](#), [ReadExplicitLengthSQIVR.cxx](#), [ReadGEMSSDO.cxx](#), [SimplePrint.cs](#), [StreamImageReaderTest.cxx](#), [csa2img.cxx](#), [gdcmrtnplan.cxx](#), [gdcmrtpplan.cxx](#), [iU22tomultisc.cxx](#), [pmsct_rgb1.cxx](#), and [rle2img.cxx](#).

10.73.2 Member Typedef Documentation

10.73.2.1 ValuePtr

```
typedef SmartPointer<Value> gdcm::DataElement::ValuePtr [protected]
```

10.73.3 Constructor & Destructor Documentation

10.73.3.1 DataElement() [1/2]

```
gdcm::DataElement::DataElement (  
    const Tag & t = Tag(0),  
    const VL & vl = 0,  
    const VR & vr = VR::INVALID) [inline]
```

References [gdcm::VR::INVALID](#), [TagField](#), [ValueField](#), [ValueLengthField](#), and [VRField](#).

Referenced by [DataElement\(\)](#), [gdcm::Fragment::Fragment\(\)](#), [gdcm::Item::Item\(\)](#), [gdcm::Item::Item\(\)](#), [gdcm::Item::GetDataElement\(\)](#), [gdcm::Item::InsertDataElement\(\)](#), [operator<\(\)](#), [operator<<\(\)](#), [operator=\(\)](#), and [operator==\(\)](#).

10.73.3.2 DataElement() [2/2]

```
gdcm::DataElement::DataElement (  
    const DataElement & _val) [inline]
```

References [DataElement\(\)](#).

10.73.4 Member Function Documentation

10.73.4.1 Clear()

```
void gdcm::DataElement::Clear () [inline]
```

Clear Data [Element](#) (make [Value](#) empty and invalidate [Tag](#) & [VR](#))

References [gdcm::VR::INVALID](#), [TagField](#), [ValueField](#), [ValueLengthField](#), and [VRField](#).

Referenced by [gdcm::Item::Clear\(\)](#).

10.73.4.2 Empty()

```
void gdcm::DataElement::Empty () [inline]
```

Make Data [Element](#) empty (no [Value](#))

References [ValueField](#), and [ValueLengthField](#).

10.73.4.3 GetByteValue()

```
const ByteValue * gdcm::DataElement::GetByteValue () const [inline]
```

Return the [Value](#) of [DataElement](#) as a [ByteValue](#) (if possible)

Warning

: You need to check for NULL return value

Examples

[DumpADAC.cxx](#), [DumpExamCard.cxx](#), [DumpGEMSMovieGroup.cxx](#), [DumpImageHeaderInfo.cxx](#), [DumpPhilipsECHO.cxx](#), [DumpToshibaDTI.cxx](#), [DumpToshibaDTI2.cxx](#), [DuplicatePCDE.cxx](#), [ELSCINT1WaveToText.cxx](#), [ExtractEncapsulatedFile.cs](#), [ExtractEncryptedContent.cxx](#), [ExtractIconFromFile.cxx](#), [FixBrokenJ2K.cxx](#), [FixJAI BugJPEGLS.cxx](#), [GetSubSequenceData.cxx](#), [PatchFile.cxx](#), [ReadExplicitLengthSQIVR.cxx](#), [ReadGEMSSDO.cxx](#), [pmsct_rgb1.cxx](#), and [rle2img.cxx](#).

References [ValueField](#).

Referenced by [IsEmpty\(\)](#), [gdcm::BasicOffsetTable::operator<<](#), [gdcm::Attribute< Group, Element, TVR, TVM >::SetFromDataElement\(\)](#), [gdcm::Attribute< Group, Element, TVR, VM::VM1 >::SetFromDataElement\(\)](#), [gdcm::Attribute< Group, Element, TVR, VM::VM1_n >::SetFromDataElement\(\)](#), [gdcm::Element< TVR, TVM >::SetFromDataElement\(\)](#), and [gdcm::Fragment::Write\(\)](#).

10.73.4.4 GetLength()

```
template<typename TDE>
VL gdcm::DataElement::GetLength () const [inline]
```

References [GetLength\(\)](#).

Referenced by [GetLength\(\)](#).

10.73.4.5 GetSequenceOfFragments() [1/2]

```
SequenceOfFragments * gdcm::DataElement::GetSequenceOfFragments ()
```

10.73.4.6 GetSequenceOfFragments() [2/2]

```
const SequenceOfFragments * gdcm::DataElement::GetSequenceOfFragments () const
```

Return the [Value](#) of [DataElement](#) as a Sequence Of Fragments (if possible)

Warning

: You need to check for NULL return value

Examples

[DecompressImage.cs](#), [FixBrokenJ2K.cxx](#), [FixJAI BugJPEGLS.cxx](#), and [GetJPEGSamplePrecision.cxx](#).

10.73.4.7 GetTag() [1/2]

```
Tag & gdcm::DataElement::GetTag () [inline]
```

References [TagField](#).

10.73.4.8 GetTag() [2/2]

```
const Tag & gdcm::DataElement::GetTag () const [inline]
```

Get [Tag](#).

Examples

[DumpGEMSMovieGroup.cxx](#), [DumpVisusChange.cxx](#), [DuplicatePCDE.cxx](#), [SimplePrint.cs](#), and [pmsct_rgb1.cxx](#).

References [TagField](#).

Referenced by [gdcm::CommandDataSet::Insert\(\)](#), [gdcm::DataSet::Insert\(\)](#), [gdcm::FileMetaInformation::Insert\(\)](#), [operator<\(\)](#), [gdcm::SequenceOfItems::Read\(\)](#), [gdcm::SequenceOfFragments::ReadValue\(\)](#), [gdcm::CommandDataSet::Replace\(\)](#), [gdcm::FileMetaInformation::Replace\(\)](#), [gdcm::Attribute< Group, Element, TVR, TVM >::SetFromDataElement\(\)](#), [gdcm::Attribute< Group, Element, TVR, VM::VM1 >::SetFromDataElement\(\)](#), and [gdcm::Attribute< Group, Element, TVR, VM::VM1_n >](#).

10.73.4.9 GetValue() [1/2]

```
Value & gdcm::DataElement::GetValue () [inline]
```

References [gdcmAssertAlwaysMacro](#), and [ValueField](#).

10.73.4.10 GetValue() [2/2]

```
Value const & gdcm::DataElement::GetValue () const [inline]
```

Set/Get [Value](#) (bytes array, SQ of items, SQ of fragments):

Examples

[ReadAndDumpDICOMDIR.cxx](#).

References [gdcmAssertAlwaysMacro](#), and [ValueField](#).

Referenced by [gdcm::DataSet::InsertDataElement\(\)](#), and [gdcm::Element< TVR, TVM >::SetFromDataElement\(\)](#).

10.73.4.11 GetValueAsSQ()

```
SmartPointer< SequenceOfItems > gdcM::DataElement::GetValueAsSQ () const
```

Interpret the [Value](#) stored in the [DataElement](#). This is more robust (but also more expensive) to call this function rather than the simplest form: [GetSequenceOfItems\(\)](#) It also return NULL when the [Value](#) is NOT of type [SequenceOfItems](#)

Warning

in case [GetSequenceOfItems\(\)](#) succeed the function return this value, otherwise it creates a new [SequenceOfItems](#), you should handle that in your case, for instance: `SmartPointer<SequenceOfItems> sqi = de.GetValueAsSQ();`

Examples

[ChangeSequenceUltrasound.cxx](#), [DumpExamCard.cxx](#), [DumpGEMSMovieGroup.cxx](#), [DumpPhilipsECHO.cxx](#), [DumpToshibaDTI.cxx](#), [DumpToshibaDTI2.cxx](#), [DumpVisusChange.cxx](#), [ExtractEncryptedContent.cxx](#), [GetSequenceUltrasound.cxx](#), [GetSubSequenceData.cxx](#), [LargeVRDSExplicit.cxx](#), [ReadAndDumpDICOMDIR.cxx](#), [SimplePrint.cs](#), [gdcMrtionplan.cxx](#), and [gdcMrtplan.cxx](#).

10.73.4.12 GetVL() [1/2]

```
VL & gdcM::DataElement::GetVL () [inline]
```

References [ValueLengthField](#).

10.73.4.13 GetVL() [2/2]

```
const VL & gdcM::DataElement::GetVL () const [inline]
```

Get [VL](#).

Examples

[SimplePrint.cs](#).

References [ValueLengthField](#).

Referenced by [gdcM::DataSet::InsertDataElement\(\)](#), [gdcM::SequenceOfItems::Read\(\)](#), and [gdcM::SequenceOfFragments::ReadValue\(\)](#).

10.73.4.14 GetVR()

```
VR const & gdcm::DataElement::GetVR () const [inline]
```

Get [VR](#) do not set [VR::SQ](#) on bytevalue data element

Examples

[DuplicatePCDE.cxx](#), and [GenFakeIdentifyFile.cxx](#).

References [VRField](#).

Referenced by [gdcm::Attribute< Group, Element, TVR, TVM >::GetAsDataElement\(\)](#), [gdcm::Attribute< Group, Element, TVR, VM::VM1 >::GetAsDataElement\(\)](#), [gdcm::Attribute< Group, Element, TVR, VM::VM1_n >::GetAsDataElement\(\)](#), [gdcm::Element< TVR, TVM >::GetAsDataElement\(\)](#), [gdcm::Attribute< Group, Element, TVR, TVM >::SetFromDataElement\(\)](#), [gdcm::Attribute< Group, Element, TVR, VM::VM1 >::SetFromDataElement\(\)](#), [gdcm::Attribute< Group, Element, TVR, VM::VM1_n >::SetFromDataElement\(\)](#), and [gdcm::Element< TVR, TVM >::SetFromDataElement\(\)](#).

10.73.4.15 IsEmpty()

```
bool gdcm::DataElement::IsEmpty () const [inline]
```

Check if Data [Element](#) is empty.

Examples

[DumpADAC.cxx](#), [DumpCSA.cs](#), [DumpExamCard.cxx](#), [DumpGEMSMovieGroup.cxx](#), [DumpImageHeaderInfo.cxx](#), [DumpToshibaDTI.cxx](#), [DumpToshibaDTI2.cxx](#), [ELSCINT1WaveToText.cxx](#), [FixJAIBugJPEGLS.cxx](#), [pmsct_rgb1.cxx](#), and [rle2img.cxx](#).

References [GetByteValue\(\)](#), and [ValueField](#).

Referenced by [gdcm::DataSet::InsertDataElement\(\)](#), [gdcm::Attribute< Group, Element, TVR, TVM >::SetFromDataElement\(\)](#), [gdcm::Attribute< Group, Element, TVR, VM::VM1 >::SetFromDataElement\(\)](#), [gdcm::Attribute< Group, Element, TVR, VM::VM1_n >::SetFromDataElement\(\)](#), and [gdcm::Fragment::Write\(\)](#).

10.73.4.16 IsUndefinedLength()

```
bool gdcm::DataElement::IsUndefinedLength () const [inline]
```

return if [Value](#) Length if of undefined length

References [ValueLengthField](#).

Referenced by [gdcm::Item::InsertDataElement\(\)](#).

10.73.4.17 operator<()

```
bool gdcm::DataElement::operator< (
    const DataElement & de) const [inline]
```

References [DataElement\(\)](#), and [GetTag\(\)](#).

10.73.4.18 operator=()

```
DataElement & gdcm::DataElement::operator= (
    const DataElement & ) [default]
```

References [DataElement\(\)](#).

10.73.4.19 operator==()

```
bool gdcm::DataElement::operator== (
    const DataElement & de) const [inline]
```

References [DataElement\(\)](#), [TagField](#), [ValueField](#), [ValueLengthField](#), and [VRField](#).

10.73.4.20 Read()

```
template<typename TDE, typename TSwap>
std::istream & gdcm::DataElement::Read (
    std::istream & is) [inline]
```

Examples

[DumpSiemensBase64.cxx](#).

References [Read\(\)](#).

Referenced by [Read\(\)](#), and [ReadOrSkip\(\)](#).

10.73.4.21 ReadOrSkip()

```
template<typename TDE, typename TSwap>
std::istream & gdcm::DataElement::ReadOrSkip (
    std::istream & is,
    std::set< Tag > const & skiptags) [inline]
```

References [Read\(\)](#).

10.73.4.22 ReadPreValue()

```
template<typename TDE, typename TSwap>
std::istream & gdcmm::DataElement::ReadPreValue (
    std::istream & is,
    std::set< Tag > const & skiptags) [inline]
```

References [ReadPreValue\(\)](#).

Referenced by [ReadPreValue\(\)](#).

10.73.4.23 ReadValue()

```
template<typename TDE, typename TSwap>
std::istream & gdcmm::DataElement::ReadValue (
    std::istream & is,
    std::set< Tag > const & skiptags) [inline]
```

References [ReadValue\(\)](#).

Referenced by [ReadValue\(\)](#).

10.73.4.24 ReadValueWithLength()

```
template<typename TDE, typename TSwap>
std::istream & gdcmm::DataElement::ReadValueWithLength (
    std::istream & is,
    VL & length,
    std::set< Tag > const & skiptags) [inline]
```

References [ReadValueWithLength\(\)](#).

Referenced by [ReadValueWithLength\(\)](#).

10.73.4.25 ReadWithLength()

```
template<typename TDE, typename TSwap>
std::istream & gdcmm::DataElement::ReadWithLength (
    std::istream & is,
    VL & length) [inline]
```

References [ReadWithLength\(\)](#).

Referenced by [gdcmm::Item::Read\(\)](#), and [ReadWithLength\(\)](#).

10.73.4.26 SetByteValue()

```
void gdcmm::DataElement::SetByteValue (
    const char * array,
    VL length) [inline]
```

Set the byte value

Warning

user need to read DICOM standard for an understanding of:

- even padding
- \0 vs space padding By default even padding is achieved using \0 regardless of the of [VR](#)

Examples

[BasicImageAnonymizer.cs](#), [ChangePrivateTags.cxx](#), [ChangeSequenceUltrasound.cxx](#), [CreateARGBImage.cxx](#), [CreateCMYKImage.cxx](#), [DecompressImage.cs](#), [DecompressImageMultiframe.cs](#), [DecompressJPEGFile.cs](#), [Fake_Image_Using_Stream_Image_Writer.cxx](#), [FileChangeTS.cs](#), [FileChangeTSLossy.cs](#), [FixBrokenJ2K.cxx](#), [FixJAIBugJPEGLS.cxx](#), [GenFakeIdentifyFile.cxx](#), [GenFakeImage.cxx](#), [GenLongSeqs.cxx](#), [GenSeqs.cxx](#), [GetSubSequenceData.cxx](#), [MpegVideoInfo.cs](#), [NewSequence.cs](#), [StreamImageReaderTest.cxx](#), [iU22tomultisc.cxx](#), and [rle2img.cxx](#).

References [SetValue\(\)](#).

Referenced by [gdcmm::Attribute< Group, Element, TVR, TVM >::GetAsDataElement\(\)](#), [gdcmm::Attribute< Group, Element, TVR, VM::VM1 gdcmm::Attribute< Group, Element, TVR, VM::VM1_n >::GetAsDataElement\(\)](#), and [gdcmm::Element< TVR, TVM >::GetAsDataElement\(\)](#).

10.73.4.27 SetTag()

```
void gdcmm::DataElement::SetTag (
    const Tag & t) [inline]
```

Set [Tag](#) Use with cautious (need to match Part 6)

Examples

[Extracting_All_Resolution.cxx](#), [Fake_Image_Using_Stream_Image_Writer.cxx](#), [GenFakeIdentifyFile.cxx](#), and [GetSubSequenceData.cxx](#).

References [TagField](#).

10.73.4.28 SetValue()

```
void gdcm::DataElement::SetValue (
    Value const & vl) [inline]
```

Warning

you need to set the ValueLengthField explicitly

Examples

[DecompressImageMultiframe.cs](#), [DecompressJPEGFile.cs](#), [DuplicatePCDE.cxx](#), [Fake_Image_Using_Stream_Image_Writer.cxx](#), [FixBrokenJ2K.cxx](#), [GenFakeIdentifyFile.cxx](#), [GenLongSeqs.cxx](#), [GenSeqs.cxx](#), [MpegVideoInfo.cs](#), and [NewSequence.cs](#).

References [gdcm::Value::GetLength\(\)](#), [ValueField](#), and [ValueLengthField](#).

Referenced by [SetByteValue\(\)](#).

10.73.4.29 SetValueFieldLength()

```
void gdcm::DataElement::SetValueFieldLength (
    VL vl,
    bool readvalues) [protected]
```

10.73.4.30 SetVL()

```
void gdcm::DataElement::SetVL (
    const VL & vl) [inline]
```

Set [VL](#) Use with cautious (need to match Part 6), advanced user only

See also

[SetByteValue](#)

References [ValueLengthField](#).

10.73.4.31 SetVLToUndefined()

```
void gdcm::DataElement::SetVLToUndefined ()
```

Examples

[Fake_Image_Using_Stream_Image_Writer.cxx](#), [GenAllVR.cxx](#), [GenFakeIdentifyFile.cxx](#), [GenLongSeqs.cxx](#), [GenSeqs.cxx](#), and [NewSequence.cs](#).

10.73.4.32 SetVR()

```
void gdcmm::DataElement::SetVR (
    VR const & vr) [inline]
```

Set [VR](#) Use with cautious (need to match Part 6), advanced user only

Precondition

vr is a [VR::VRALL](#) (not a dual one such as OB_OW)

Examples

[Fake_Image_Using_Stream_Image_Writer.cxx](#), [FixBrokenJ2K.cxx](#), [FixJAIBugJPEGLS.cxx](#), [GenFakeIdentifyFile.cxx](#), [GenLongSeqs.cxx](#), [GenSeqs.cxx](#), [GetSubSequenceData.cxx](#), [NewSequence.cs](#), [StreamImageReaderTest.cxx](#), [iU22tomultisc.cxx](#), and [rle2img.cxx](#).

References [gdcmm::VR::IsVRFile\(\)](#), and [VRField](#).

Referenced by [gdcmm::Attribute< Group, Element, TVR, TVM >::GetAsDataElement\(\)](#), [gdcmm::Attribute< Group, Element, TVR, VM::VM1 gdcmm::Attribute< Group, Element, TVR, VM::VM1_n >::GetAsDataElement\(\)](#), and [gdcmm::Element< TVR, TVM >::GetAsDataElement\(\)](#).

10.73.4.33 Write()

```
template<typename TDE, typename TSwap>
const std::ostream & gdcmm::DataElement::Write (
    std::ostream & os) const [inline]
```

References [Write\(\)](#).

Referenced by [Write\(\)](#).

10.73.5 Friends And Related Symbol Documentation

10.73.5.1 operator<<

```
std::ostream & operator<< (
    std::ostream & _os,
    const DataElement & _val) [friend]
```

References [DataElement\(\)](#), [operator<<](#), [gdcmm::Object::Print\(\)](#), [TagField](#), [ValueField](#), [ValueLengthField](#), and [VRField](#).

Referenced by [operator<<](#).

10.73.6 Member Data Documentation

10.73.6.1 TagField

`Tag` `gdcm::DataElement::TagField` [protected]

Referenced by [DataElement\(\)](#), [Clear\(\)](#), [GetTag\(\)](#), [GetTag\(\)](#), [operator<<](#), [gdcm::Fragment::operator<<](#), [gdcm::Item::operator<<](#), [operator==\(\)](#), [gdcm::BasicOffsetTable::Read\(\)](#), [gdcm::Item::Read\(\)](#), [gdcm::Fragment::ReadBacktrack\(\)](#), [gdcm::Fragment::ReadPreValue\(\)](#), [SetTag\(\)](#), [gdcm::Fragment::Write\(\)](#), and [gdcm::Item::Write\(\)](#).

10.73.6.2 ValueField

`ValuePtr` `gdcm::DataElement::ValueField` [protected]

Referenced by [DataElement\(\)](#), [Clear\(\)](#), [Empty\(\)](#), [GetByteValue\(\)](#), [GetValue\(\)](#), [GetValue\(\)](#), [IsEmpty\(\)](#), [gdcm::BasicOffsetTable::operator<<](#), [operator<<](#), [gdcm::Fragment::operator<<](#), [operator==\(\)](#), [gdcm::BasicOffsetTable::Read\(\)](#), [gdcm::Fragment::ReadBacktrack\(\)](#), [gdcm::Fragment::ReadValue\(\)](#), and [SetValue\(\)](#).

10.73.6.3 ValueLengthField

`VL` `gdcm::DataElement::ValueLengthField` [protected]

Referenced by [DataElement\(\)](#), [Clear\(\)](#), [Empty\(\)](#), [GetVL\(\)](#), [GetVL\(\)](#), [IsUndefinedLength\(\)](#), [gdcm::BasicOffsetTable::operator<<](#), [operator<<](#), [gdcm::Fragment::operator<<](#), [gdcm::Item::operator<<](#), [operator==\(\)](#), [gdcm::BasicOffsetTable::Read\(\)](#), [gdcm::Item::Read\(\)](#), [gdcm::Fragment::ReadBacktrack\(\)](#), [gdcm::Fragment::ReadPreValue\(\)](#), [gdcm::Fragment::ReadValue\(\)](#), [SetValue\(\)](#), [SetVL\(\)](#), [gdcm::Fragment::Write\(\)](#), and [gdcm::Item::Write\(\)](#).

10.73.6.4 VRField

`VR` `gdcm::DataElement::VRField` [protected]

Referenced by [DataElement\(\)](#), [Clear\(\)](#), [GetVR\(\)](#), [operator<<](#), [operator==\(\)](#), and [SetVR\(\)](#).


The documentation for this class was generated from the following file:

- [gdcmDataElement.h](#)


10.74 gdcm::DataElementException Class Reference

```
#include <gdcmDataSet.h>
```

Inheritance diagram for gdcm::DataElementException:



Collaboration diagram for gdcm::DataElementException:



The documentation for this class was generated from the following file:


- [gdcmDataSet.h](#)

10.75 gdcm::DataEvent Class Reference


[DataEvent](#).

```
#include <gdcmDataEvent.h>
```

Inheritance diagram for gdcm::DataEvent:



Collaboration diagram for gdcm::DataEvent:



Public Types

- typedef [DataEvent](#) Self
- typedef [AnyEvent](#) Superclass

Public Member Functions

- [DataEvent](#) (const char *bytes=nullptr, size_t len=0)

- [DataEvent](#) (const [Self](#) &s)
- [~DataEvent](#) () override=default
- bool [CheckEvent](#) (const [::gdcm::Event](#) *e) const override
- const char * [GetData](#) () const
- size_t [GetDataLength](#) () const
- const char * [GetEventName](#) () const override
- [::gdcm::Event](#) * [MakeObject](#) () const override
- void [operator=](#) (const [Self](#) &)=delete
- void [SetData](#) (const char *bytes, size_t len)

Public Member Functions inherited from [gdcm::Event](#)

- [Event](#) ()
- [Event](#) (const [Event](#) &)
- virtual [~Event](#) ()
- virtual bool [CheckEvent](#) (const [Event](#) *) const =0
- void [operator=](#) (const [Event](#) &)=delete
- virtual void [Print](#) (std::ostream &os) const

10.75.1 Detailed Description

[DataEvent](#).

10.75.2 Member Typedef Documentation

10.75.2.1 Self

```
typedef DataEvent gdcm::DataEvent::Self
```

10.75.2.2 Superclass

```
typedef AnyEvent gdcm::DataEvent::Superclass
```

10.75.3 Constructor & Destructor Documentation

10.75.3.1 [DataEvent](#)() [1/2]

```
gdcm::DataEvent::DataEvent (
    const char * bytes = nullptr,
    size_t len = 0) [inline]
```

10.75.3.2 ~DataEvent()

```
gdcm::DataEvent::~DataEvent () [override], [default]
```

10.75.3.3 DataEvent() [2/2]

```
gdcm::DataEvent::DataEvent (
    const Self & s) [inline]
```

10.75.4 Member Function Documentation

10.75.4.1 CheckEvent()

```
bool gdcm::DataEvent::CheckEvent (
    const ::gdcm::Event * e) const [inline], [override]
```

10.75.4.2 GetData()

```
const char * gdcm::DataEvent::GetData () const [inline]
```

10.75.4.3 GetDataLength()

```
size_t gdcm::DataEvent::GetDataLength () const [inline]
```

10.75.4.4 GetEventName()

```
const char * gdcm::DataEvent::GetEventName () const [inline], [override], [virtual]
```

Return the StringName associated with the event.

Implements [gdcm::Event](#).

10.75.4.5 MakeObject()

```
::gdcm::Event * gdcm::DataEvent::MakeObject () const [inline], [override], [virtual]
```

Create an [Event](#) of this type This method work as a Factory for creating events of each particular type.

Implements [gdcm::Event](#).

10.75.4.6 operator=()

```
void gdcM::DataEvent::operator= (
    const Self & ) [delete]
```

10.75.4.7 SetData()

```
void gdcM::DataEvent::SetData (
    const char * bytes,
    size_t len) [inline]
```

The documentation for this class was generated from the following file:


- [gdcMDataEvent.h](#)

10.76 gdcM::DataSet Class Reference

Class to represent a Data Set (which contains Data Elements)

```
#include <gdcMDataSet.h>
```

Inheritance diagram for gdcM::DataSet:



Public Types

- typedef DataElementSet::const_iterator [ConstIterator](#)
- typedef std::set< [DataElement](#) > [DataElementSet](#)
- typedef DataElementSet::iterator [Iterator](#)
- typedef DataElementSet::size_type [SizeType](#)

Public Member Functions

- [Iterator Begin](#) ()
- [ConstIterator Begin](#) () const
- void [Clear](#) ()
- template<typename TDE>
unsigned int [ComputeGroupLength](#) ([Tag](#) const &tag) const
- [Iterator End](#) ()
- [ConstIterator End](#) () const
- bool [FindDataElement](#) (const [PrivateTag](#) &t) const
Look up if private tag 't' is present in the dataset:
- bool [FindDataElement](#) (const [Tag](#) &t) const
- const [DataElement](#) & [FindNextDataElement](#) (const [Tag](#) &t) const
- const [DataElement](#) & [GetDataElement](#) (const [PrivateTag](#) &t) const
Return the dataelement.
- const [DataElement](#) & [GetDataElement](#) (const [Tag](#) &t) const
- [DataElementSet](#) & [GetDES](#) ()
- const [DataElementSet](#) & [GetDES](#) () const
- template<typename TDE>
[VL](#) [GetLength](#) () const
- [MediaStorage](#) [GetMediaStorage](#) () const
- std::string [GetPrivateCreator](#) (const [Tag](#) &t) const
- [PrivateTag](#) [GetPrivateTag](#) (const [Tag](#) &t) const
Return the private tag of the private tag 't', private creator will be set to empty if not found.
- void [Insert](#) (const [DataElement](#) &de)
- bool [IsEmpty](#) () const
Returns if the dataset is empty.
- const [DataElement](#) & [operator\(\)](#) (uint16_t group, uint16_t element) const
- [DataSet](#) & [operator=](#) ([DataSet](#) const &)=default
- const [DataElement](#) & [operator\[\]](#) (const [Tag](#) &t) const
- void [Print](#) (std::ostream &os, std::string const &indent="") const
- template<typename TDE, typename TSwap>
std::istream & [Read](#) (std::istream &is)
- template<typename TDE, typename TSwap>
std::istream & [ReadNested](#) (std::istream &is)
- template<typename TDE, typename TSwap>
std::istream & [ReadSelectedPrivateTags](#) (std::istream &is, const std::set< [PrivateTag](#) > &tags, bool readvalues=true)
- template<typename TDE, typename TSwap>
std::istream & [ReadSelectedPrivateTagsWithLength](#) (std::istream &is, const std::set< [PrivateTag](#) > &tags, [VL](#) &length, bool readvalues=true)
- template<typename TDE, typename TSwap>
std::istream & [ReadSelectedTags](#) (std::istream &is, const std::set< [Tag](#) > &tags, bool readvalues=true)
- template<typename TDE, typename TSwap>
std::istream & [ReadSelectedTagsWithLength](#) (std::istream &is, const std::set< [Tag](#) > &tags, [VL](#) &length, bool readvalues=true)
- template<typename TDE, typename TSwap>
std::istream & [ReadUpToTag](#) (std::istream &is, const [Tag](#) &t, std::set< [Tag](#) > const &skiptags)
- template<typename TDE, typename TSwap>
std::istream & [ReadUpToTagWithLength](#) (std::istream &is, const [Tag](#) &t, std::set< [Tag](#) > const &skiptags, [VL](#) &length)

- `template<typename TDE, typename TSwap>`
`std::istream & ReadWithLength (std::istream &is, VL &length)`
- `SizeType Remove` (const `Tag` &tag)
Completely remove a dataelement from the dataset.
- `void Replace` (const `DataElement` &de)
Replace a dataelement with another one.
- `void ReplaceEmpty` (const `DataElement` &de)
Only replace a DICOM attribute when it is missing or empty.
- `SizeType Size` () const
- `template<typename TDE, typename TSwap>`
`std::ostream const & Write (std::ostream &os) const`

Protected Member Functions

- `Tag ComputeDataElement` (const `PrivateTag` &t) const
- const `DataElement` & `GetDEEnd` () const
- `void InsertDataElement` (const `DataElement` &de)

Friends

- class `CSAHeader`
- `std::ostream & operator<<` (std::ostream &_os, const `DataSet` &val)

10.76.1 Detailed Description

Class to represent a Data Set (which contains Data Elements)

A Data Set represents an instance of a real world Information [Object](#)

Note

DATA SET: Exchanged information consisting of a structured set of [Attribute](#) values directly or indirectly related to Information Objects. The value of each [Attribute](#) in a Data Set is expressed as a Data [Element](#). A collection of Data Elements ordered by increasing Data [Element Tag](#) number that is an encoding of the values of Attributes of a real world object.

Implementation note. If one do: `DataSet ds; ds.SetLength(0); ds.Read(is);` setting length to 0 actually means try to read is as if it was a root [DataSet](#). Other value are undefined (nested dataset with undefined length) or defined length (different from 0) means nested dataset with defined length.

Warning

a [DataSet](#) does not have a Transfer Syntax type, only a [File](#) does.

Examples

[ChangePrivateTags.cxx](#), [ChangeSequenceUltrasound.cxx](#), [CompressLossyJPEG.cs](#), [CreateFakeRTDOSE.cxx](#), [CreateJPIPDataSet.cxx](#), [DeriveSeries.cxx](#), [DiffFile.cxx](#), [DumpADAC.cxx](#), [DumpCSA.cs](#), [DumpExamCard.cxx](#), [DumpGEMSMovieGroup.cxx](#), [DumpImageHeaderInfo.cxx](#), [DumpPhilipsECHO.cxx](#), [DumpSiemensBase64.cxx](#), [DumpToshibaDTI.cxx](#), [DumpToshibaDTI2.cxx](#), [DumpVisusChange.cxx](#), [DuplicatePCDE.cxx](#), [ELSCINT1WaveToText.cxx](#), [ExtractEncapsulatedFile.cs](#), [ExtractEncryptedContent.cxx](#), [Extracting_All_Resolution.cxx](#), [Fake_Image_Using_Stream_Image_Write.cxx](#), [FileChangeTS.cs](#), [FileChangeTSLossy.cs](#), [FixOrientation.cxx](#), [GenAllVR.cxx](#), [GenFakeIdentifyFile.cxx](#), [GenLongSeqs.cxx](#), [GenSeqs.cxx](#), [GetJPEGSamplePrecision.cxx](#), [GetSequenceUltrasound.cxx](#), [GetSubSequenceData.cxx](#), [HelloWorld.cxx](#), [LargeVRDSExplicit.cxx](#), [MergeTwoFiles.cxx](#), [MrProtocol.cxx](#), [NewSequence.cs](#), [PatchFile.cxx](#), [ReadAndDumpDICOMDIR.cxx](#), [ReadAndPrintAttributes.cxx](#), [ReadExplicitLengthSQIVR.cxx](#), [ReadGEMSSDO.cxx](#), [SimplePrint.cs](#), [SortImage.cxx](#), [SortImage2.cs](#), [StreamImageReaderTest.cxx](#), [TemplateEmptyImage.cxx](#), [VolumeSorter.cxx](#), [csa2img.cxx](#), [gdcmrtionplan.cxx](#), [gdcmrtplan.cxx](#), [iU22tomultisc.cxx](#), [pmsct_rgb1.cxx](#), and [rle2img.cxx](#).

10.76.2 Member Typedef Documentation

10.76.2.1 ConstIterator

```
typedef DataSet::const_iterator gdcm::DataSet::ConstIterator
```

Examples

[DiffFile.cxx](#), [DumpGEMSMovieGroup.cxx](#), [DumpVisusChange.cxx](#), and [DuplicatePCDE.cxx](#).

10.76.2.2 DataSet

```
typedef std::set<DataElement> gdcm::DataSet::DataSet
```

10.76.2.3 Iterator

```
typedef DataSet::iterator gdcm::DataSet::Iterator
```

10.76.2.4 SizeType

```
typedef DataSet::size_type gdcm::DataSet::SizeType
```

10.76.3 Member Function Documentation

10.76.3.1 Begin() [1/2]

`Iterator` `gdcM::DataSet::Begin ()` `[inline]`

10.76.3.2 Begin() [2/2]

`ConstIterator` `gdcM::DataSet::Begin () const` `[inline]`

Examples

[DiffFile.cxx](#), [DumpGEMSMovieGroup.cxx](#), [DumpVisusChange.cxx](#), and [DuplicatePCDE.cxx](#).

10.76.3.3 Clear()

`void` `gdcM::DataSet::Clear ()` `[inline]`

References [gdcM_assert](#).

Referenced by [gdcM::Item::Read\(\)](#).

10.76.3.4 ComputeDataElement()

`Tag` `gdcM::DataSet::ComputeDataElement (`
 `const PrivateTag & t) const` `[protected]`

References [operator<<](#).

10.76.3.5 ComputeGroupLength()

```
template<typename TDE>
unsigned int gdcM::DataSet::ComputeGroupLength (
    Tag const & tag) const [inline]
```

References [gdcM_assert](#), [gdcM::Tag::GetElement\(\)](#), and [gdcM::Tag::GetGroup\(\)](#).

10.76.3.6 End() [1/2]

`Iterator` `gdcM::DataSet::End ()` `[inline]`

10.76.3.7 End() [2/2]

```
ConstIterator gdcm::DataSet::End () const [inline]
```

Examples

[DiffFile.cxx](#), [DumpGEMSMovieGroup.cxx](#), [DumpVisusChange.cxx](#), and [DuplicatePCDE.cxx](#).

10.76.3.8 FindDataElement() [1/2]

```
bool gdcm::DataSet::FindDataElement (
    const PrivateTag & t) const
```

Look up if private tag 't' is present in the dataset:

Examples

[ChangePrivateTags.cxx](#), [ChangeSequenceUltrasound.cxx](#), [DumpADAC.cxx](#), [DumpCSA.cs](#), [DumpExamCard.cxx](#), [DumpGEMSMovieGroup.cxx](#), [DumpImageHeaderInfo.cxx](#), [DumpPhilipsECHO.cxx](#), [DumpSiemensBase64.cxx](#), [DumpToshibaDTI.cxx](#), [DumpToshibaDTI2.cxx](#), [DumpVisusChange.cxx](#), [ELSCINT1WaveToText.cxx](#), [ExtractEncapsulatedFile.cs](#), [ExtractEncryptedContent.cxx](#), [GetSequenceUltrasound.cxx](#), [GetSubSequenceData.cxx](#), [LargeVRDSExplicit.cxx](#), [MrProtocol.cxx](#), [ReadAndDumpDICOMDIR.cxx](#), [ReadAndPrintAttributes.cxx](#), [ReadGEMSSDO.cxx](#), [csa2img.cxx](#), [gdcmrtionplan.cxx](#), [gdcmrtplan.cxx](#), [pmsct_rgb1.cxx](#), and [rle2img.cxx](#).

Referenced by [gdcm::Attribute< Group, Element, TVR, TVM >::SetFromDataSet\(\)](#), [gdcm::Attribute< Group, Element, TVR, VM::VM1 >::SetFromDataSet\(\)](#), and [gdcm::Attribute< Group, Element, TVR, VM::VM1_n >::SetFromDataSet\(\)](#).

10.76.3.9 FindDataElement() [2/2]

```
bool gdcm::DataSet::FindDataElement (
    const Tag & t) const [inline]
```

References [GetDataElement\(\)](#), and [GetDEEnd\(\)](#).

10.76.3.10 FindNextDataElement()

```
const DataElement & gdcm::DataSet::FindNextDataElement (
    const Tag & t) const [inline]
```

Examples

[DuplicatePCDE.cxx](#).

References [GetDEEnd\(\)](#).

10.76.3.11 GetDataElement() [1/2]

```
const DataElement & gdcM::DataSet::GetDataElement (
    const PrivateTag & t) const
```

Return the dataelement.

10.76.3.12 GetDataElement() [2/2]

```
const DataElement & gdcM::DataSet::GetDataElement (
    const Tag & t) const [inline]
```

Return the [DataElement](#) with [Tag](#) 't'

Warning

: This only search at the 'root level' of the [DataSet](#)

Examples

[ChangePrivateTags.cxx](#), [ChangeSequenceUltrasound.cxx](#), [DecompressImage.cs](#), [DeriveSeries.cxx](#), [DumpADAC.cxx](#), [DumpCSA.cs](#), [DumpExamCard.cxx](#), [DumpGEMSMovieGroup.cxx](#), [DumpImageHeaderInfo.cxx](#), [DumpPhilipsECHO.cxx](#), [DumpSiemensBase64.cxx](#), [DumpToshibaDTI.cxx](#), [DumpToshibaDTI2.cxx](#), [DumpVisusChange.cxx](#), [ELSCINT1WaveToText.cxx](#), [ExtractEncapsulatedFile.cs](#), [ExtractEncryptedContent.cxx](#), [FixBrokenJ2K.cxx](#), [FixJAIBugJPEGLS.cxx](#), [GetJPEGSamplePrecision.cxx](#), [GetSequenceUltrasound.cxx](#), [GetSubSequenceData.cxx](#), [LargeVRDSExplicit.cxx](#), [MrProtocol.cxx](#), [PatchFile.cxx](#), [ReadAndDumpDICOMDIR.cxx](#), [ReadExplicitLengthSQIVR.cxx](#), [ReadGEMSSDO.cxx](#), [csa2img.cxx](#), [gdcMrtionplan.cxx](#), [gdcMrtplan.cxx](#), [iU22tomultisc.cxx](#), [pmsct_rgb1.cxx](#), and [rle2img.cxx](#).

References [GetDEEnd\(\)](#).

Referenced by [FindDataElement\(\)](#), [operator\(\)\(\)](#), [operator\[\]\(\)](#), [gdcM::Attribute< Group, Element, TVR, TVM >::Set\(\)](#), [gdcM::Attribute< Group, Element, TVR, VM::VM1 >::Set\(\)](#), [gdcM::Attribute< Group, Element, TVR, VM::VM1_n >::Set\(\)](#), [gdcM::Attribute< Group, Element, TVR, TVM >::SetFromDataSet\(\)](#), [gdcM::Attribute< Group, Element, TVR, VM::VM1 >::SetFromDataSet\(\)](#) and [gdcM::Attribute< Group, Element, TVR, VM::VM1_n >::SetFromDataSet\(\)](#).

10.76.3.13 GetDEEnd()

```
const DataElement & gdcM::DataSet::GetDEEnd () const [protected]
```

Referenced by [FindDataElement\(\)](#), [FindNextDataElement\(\)](#), and [GetDataElement\(\)](#).

10.76.3.14 GetDES() [1/2]

```
DataElementSet & gdcM::DataSet::GetDES () [inline]
```

10.76.3.15 GetDES() [2/2]

```
const DataElementSet & gdcm::DataSet::GetDES () const [inline]
```

Examples

[ReadAndDumpDICOMDIR.cxx](#).

10.76.3.16 GetLength()

```
template<typename TDE>  
VL gdcm::DataSet::GetLength () const [inline]
```

References [gdcm_assert](#).

Referenced by [gdcm::FileMetaInformation::GetFullLength\(\)](#).

10.76.3.17 GetMediaStorage()

```
MediaStorage gdcm::DataSet::GetMediaStorage () const
```

10.76.3.18 GetPrivateCreator()

```
std::string gdcm::DataSet::GetPrivateCreator (  
    const Tag & t) const
```

Return the private creator of the private tag 't': or an empty string when not found

Examples

[DuplicatePCDE.cxx](#).

10.76.3.19 GetPrivateTag()

```
PrivateTag gdcm::DataSet::GetPrivateTag (  
    const Tag & t) const
```

Return the private tag of the private tag 't', private creator will be set to empty if not found.

10.76.3.20 Insert()

```
void gdcm::DataSet::Insert (
    const DataElement & de) [inline]
```

Insert a [DataElement](#) in the [DataSet](#).

Warning

: [Tag](#) need to be $\geq 0x8$ to be considered valid data element

Examples

[CreateJPIPDataSet.cxx](#), [DumpSiemensBase64.cxx](#), [DuplicatePCDE.cxx](#), [Extracting_All_Resolution.cxx](#), [Fake_Image_Using_Stream_Image_Writer.cxx](#), [FileChangeTS.cs](#), [FileChangeTSLossy.cs](#), [GenAllVR.cxx](#), [GenFakeIdentifyFile.cxx](#), [GenLongSeqs.cxx](#), [GenSeqs.cxx](#), [NewSequence.cs](#), [StreamImageReaderTest.cxx](#), and [TemplateEmptyImage.cxx](#).

References [gdcmErrorMacro](#), [gdcm::Tag::GetGroup\(\)](#), [gdcm::DataElement::GetTag\(\)](#), and [InsertDataElement\(\)](#).

10.76.3.21 InsertDataElement()

```
void gdcm::DataSet::InsertDataElement (
    const DataElement & de) [inline], [protected]
```

References [gdcm_assert](#), [gdcmWarningMacro](#), [gdcm::Value::GetLength\(\)](#), [gdcm::DataElement::GetValue\(\)](#), [gdcm::DataElement::GetVL\(\)](#) and [gdcm::DataElement::IsEmpty\(\)](#).

Referenced by [gdcm::CommandDataSet::Insert\(\)](#), [Insert\(\)](#), and [gdcm::FileMetaInformation::Insert\(\)](#).

10.76.3.22 IsEmpty()

```
bool gdcm::DataSet::IsEmpty () const [inline]
```

Returns if the dataset is empty.

Referenced by [gdcm::Item::Read\(\)](#).

10.76.3.23 operator>()()

```
const DataElement & gdcm::DataSet::operator() (
    uint16_t group,
    uint16_t element) const [inline]
```

References [GetDataElement\(\)](#).

10.76.3.24 operator=()

```
DataSet & gdcm::DataSet::operator= (
    DataSet const & ) [default]
```

10.76.3.25 operator[]()

```
const DataElement & gdcm::DataSet::operator[] (
    const Tag & t) const [inline]
```

References [GetDataElement\(\)](#).

10.76.3.26 Print()

```
void gdcm::DataSet::Print (
    std::ostream & os,
    std::string const & indent = "") const [inline]
```

Referenced by [gdcm::CommandDataSet::operator<<](#), [operator<<](#), [gdcm::FileMetaInformation::operator<<](#), and [gdcm::Item::operator<<](#).

10.76.3.27 Read()

```
template<typename TDE, typename TSwap>
std::istream & gdcm::DataSet::Read (
    std::istream & is)
```

Examples

[DumpToshibaDTI.cxx](#), and [DumpToshibaDTI2.cxx](#).

10.76.3.28 ReadNested()

```
template<typename TDE, typename TSwap>
std::istream & gdcm::DataSet::ReadNested (
    std::istream & is)
```

10.76.3.29 ReadSelectedPrivateTags()

```
template<typename TDE, typename TSwap>
std::istream & gdcm::DataSet::ReadSelectedPrivateTags (
    std::istream & is,
    const std::set< PrivateTag > & tags,
    bool readvalues = true)
```

10.76.3.30 ReadSelectedPrivateTagsWithLength()

```
template<typename TDE, typename TSwap>
std::istream & gdcm::DataSet::ReadSelectedPrivateTagsWithLength (
    std::istream & is,
    const std::set< PrivateTag > & tags,
    VL & length,
    bool readvalues = true)
```

10.76.3.31 ReadSelectedTags()

```
template<typename TDE, typename TSwap>
std::istream & gdcm::DataSet::ReadSelectedTags (
    std::istream & is,
    const std::set< Tag > & tags,
    bool readvalues = true)
```

10.76.3.32 ReadSelectedTagsWithLength()

```
template<typename TDE, typename TSwap>
std::istream & gdcm::DataSet::ReadSelectedTagsWithLength (
    std::istream & is,
    const std::set< Tag > & tags,
    VL & length,
    bool readvalues = true)
```

10.76.3.33 ReadUpToTag()

```
template<typename TDE, typename TSwap>
std::istream & gdcm::DataSet::ReadUpToTag (
    std::istream & is,
    const Tag & t,
    std::set< Tag > const & skiptags)
```

10.76.3.34 ReadUpToTagWithLength()

```
template<typename TDE, typename TSwap>
std::istream & gdcm::DataSet::ReadUpToTagWithLength (
    std::istream & is,
    const Tag & t,
    std::set< Tag > const & skiptags,
    VL & length)
```


10.76.3.35 ReadWithLength()

```
template<typename TDE, typename TSwap>
std::istream & gdcm::DataSet::ReadWithLength (
    std::istream & is,
    VL & length)
```

10.76.3.36 Remove()

```
SizeType gdcm::DataSet::Remove (
    const Tag & tag) [inline]
```

Completely remove a dataelement from the dataset.

Examples

[ClinicalTrialIdentificationWorkflow.cs](#), [GenFakeIdentifyFile.cxx](#), [LargeVRDSExplicit.cxx](#), [MergeTwoFiles.cxx](#), [ReformatFile.cs](#), [StandardizeFiles.cs](#), [pmsct_rgb1.cxx](#), and [rle2img.cxx](#).

References [gdcm_assert](#).

Referenced by [gdcm::CommandDataSet::Replace\(\)](#), and [gdcm::FileMetaInformation::Replace\(\)](#).

10.76.3.37 Replace()

```
void gdcm::DataSet::Replace (
    const DataElement & de) [inline]
```

Replace a dataelement with another one.

Examples

[ChangePrivateTags.cxx](#), [ChangeSequenceUltrasound.cxx](#), [CreateFakeRTDOSE.cxx](#), [DeriveSeries.cxx](#), [FixBrokenJ2K.cxx](#), [FixJAIBugJPEGLS.cxx](#), [FixOrientation.cxx](#), [GenFakeIdentifyFile.cxx](#), [GetSubSequenceData.cxx](#), [HelloWorld.cxx](#), [LargeVRDSExplicit.cxx](#), [PatchFile.cxx](#), [iU22tomultisc.cxx](#), [pmsct_rgb1.cxx](#), and [rle2img.cxx](#).

References [gdcmAssertAlwaysMacro](#).

10.76.3.38 ReplaceEmpty()

```
void gdcm::DataSet::ReplaceEmpty (
    const DataElement & de) [inline]
```

Only replace a DICOM attribute when it is missing or empty.

Examples

[rle2img.cxx](#).

References [gdcmAssertAlwaysMacro](#).

10.76.3.39 Size()

```
SizeType gdcM::DataSet::Size () const [inline]
```

Examples

[DumpGEMSMovieGroup.cxx](#).

Referenced by [gdcM::SequenceOfItems::Read\(\)](#).

10.76.3.40 Write()

```
template<typename TDE, typename TSwap>
std::ostream const & gdcM::DataSet::Write (
    std::ostream & os) const
```

10.76.4 Friends And Related Symbol Documentation

10.76.4.1 CSAHeader

```
friend class CSAHeader [friend]
```

References [CSAHeader](#).

Referenced by [CSAHeader](#).

10.76.4.2 operator<<

```
std::ostream & operator<< (
    std::ostream & _os,
    const DataSet & val) [friend]
```

References [operator<<](#), and [Print\(\)](#).

Referenced by [ComputeDataElement\(\)](#), and [operator<<](#).

The documentation for this class was generated from the following file:


- [gdcMDataSet.h](#)

10.77 gdcm::DataSetEvent Class Reference


[DataSetEvent](#).

```
#include <gdcmDataSetEvent.h>
```

Inheritance diagram for gdcm::DataSetEvent:



Collaboration diagram for gdcm::DataSetEvent:



Public Types

- typedef [DataSetEvent](#) Self
- typedef [AnyEvent](#) Superclass

Public Member Functions

- [DataSetEvent](#) (const [Self](#) &s)
- [DataSetEvent](#) ([DataSet](#) const *ds=nullptr)
- [~DataSetEvent](#) () override=default
- bool [CheckEvent](#) (const [::gdcm::Event](#) *e) const override
- [DataSet](#) const & [GetDataSet](#) () const
- const char * [GetEventName](#) () const override
- [::gdcm::Event](#) * [MakeObject](#) () const override
- void [operator=](#) (const [Self](#) &)=delete

Public Member Functions inherited from [gdcm::Event](#)

- [Event](#) ()
- [Event](#) (const [Event](#) &)
- virtual [~Event](#) ()
- virtual bool [CheckEvent](#) (const [Event](#) *) const =0
- void [operator=](#) (const [Event](#) &)=delete
- virtual void [Print](#) (std::ostream &os) const

Public Attributes

- const [DataSet](#) * [m_DataSet](#)

10.77.1 Detailed Description

[DataSetEvent](#).

Special type of event triggered during the [DataSet](#) store/move process

10.77.2 Member Typedef Documentation

10.77.2.1 Self

```
typedef DataSetEvent gdcm::DataSetEvent::Self
```

10.77.2.2 Superclass

```
typedef AnyEvent gdcm::DataSetEvent::Superclass
```

10.77.3 Constructor & Destructor Documentation

10.77.3.1 DataSetEvent() [1/2]

```
gdcm::DataSetEvent::DataSetEvent (
    DataSet const * ds = nullptr) [inline]
```

References [m_DataSet](#).

10.77.3.2 ~DataSetEvent()

```
gdcm::DataSetEvent::~~DataSetEvent () [override], [default]
```

10.77.3.3 DataSetEvent() [2/2]

```
gdcm::DataSetEvent::DataSetEvent (
    const Self & s) [inline]
```

10.77.4 Member Function Documentation

10.77.4.1 CheckEvent()

```
bool gdcm::DataSetEvent::CheckEvent (
    const ::gdcm::Event * e) const [inline], [override]
```

10.77.4.2 GetDataSet()

```
DataSet const & gdcm::DataSetEvent::GetDataSet () const [inline]
```

References [m_DataSet](#).

10.77.4.3 GetEventName()

```
const char * gdcm::DataSetEvent::GetEventName () const [inline], [override], [virtual]
```

Return the StringName associated with the event.

Implements [gdcm::Event](#).

10.77.4.4 MakeObject()

```
::gdcM::Event * gdcM::DataSetEvent::MakeObject () const [inline], [override], [virtual]
```

Create an [Event](#) of this type This method work as a Factory for creating events of each particular type.

Implements [gdcM::Event](#).

10.77.4.5 operator=()

```
void gdcM::DataSetEvent::operator= (
    const Self & ) [delete]
```

10.77.5 Member Data Documentation

10.77.5.1 m_DataSet

```
const DataSet* gdcM::DataSetEvent::m_DataSet
```

Referenced by [DataSetEvent\(\)](#), and [GetDataSet\(\)](#).

The documentation for this class was generated from the following file:

- [gdcMDataSetEvent.h](#)

10.78 gdcm::DataSetHelper Class Reference

[DataSetHelper](#) (internal class, not intended for user level)

```
#include <gdcmDataSetHelper.h>
```

Static Public Member Functions

- static [VR ComputeVR](#) ([File](#) const &file, [DataSet](#) const &ds, const [Tag](#) &tag)

10.78.1 Detailed Description

[DataSetHelper](#) (internal class, not intended for user level)

Examples

[SimplePrint.cs](#).

Public Member Functions

- virtual [~Decoder](#) ()=default
- virtual bool [CanDecode](#) ([TransferSyntax](#) const &) const =0
Return whether this decoder support this transfer syntax (can decode it)
- virtual bool [Decode](#) ([DataElement](#) const &, [DataElement](#) &)
Decode.

Protected Member Functions

- virtual bool [DecodeByStreams](#) (std::istream &, std::ostream &)

10.79.1 Detailed Description

[Decoder](#).

10.79.2 Constructor & Destructor Documentation

10.79.2.1 ~Decoder()

```
virtual gdcm::Decoder::~Decoder () [virtual], [default]
```

10.79.3 Member Function Documentation

10.79.3.1 CanDecode()

```
virtual bool gdcm::Decoder::CanDecode (
    TransferSyntax const & ) const [pure virtual]
```

Return whether this decoder support this transfer syntax (can decode it)

Implemented in [gdcm::AudioCodec](#), [gdcm::ImageCodec](#), [gdcm::JPEG2000Codec](#), [gdcm::JPEGCodec](#), [gdcm::JPEGLSCodec](#), [gdcm::KAKADUCodec](#), [gdcm::PDFCodec](#), [gdcm::PGXCodec](#), [gdcm::PNMCodec](#), [gdcm::PVRGCodec](#), [gdcm::RAWCodec](#), and [gdcm::RLECodec](#).

10.79.3.2 Decode()

```
virtual bool gdcm::Decoder::Decode (
    DataElement const & ,
    DataElement & ) [inline], [virtual]
```

Decode.

Reimplemented in [gdcm::AudioCodec](#), [gdcm::DeltaEncodingCodec](#), [gdcm::ImageCodec](#), [gdcm::JPEG2000Codec](#), [gdcm::JPEGCodec](#), [gdcm::JPEGLSCodec](#), [gdcm::KAKADUCodec](#), [gdcm::PDFCodec](#), [gdcm::PVRGCodec](#), [gdcm::RAWCodec](#), and [gdcm::RLECodec](#).

10.79.3.3 DecodeByStreams()

```
virtual bool gdcm::Decoder::DecodeByStreams (
    std::istream & ,
    std::ostream & ) [inline], [protected], [virtual]
```

Reimplemented in [gdcm::ImageCodec](#), [gdcm::JPEG12Codec](#), [gdcm::JPEG16Codec](#), [gdcm::JPEG2000Codec](#), [gdcm::JPEG8Codec](#), [gdcm::JPEGCodec](#), [gdcm::RAWCodec](#), and [gdcm::RLECodec](#).

The documentation for this class was generated from the following file:

- [gdcmDecoder.h](#)

10.80 gdcm::DefinedTerms Class Reference

Defined Terms are used when the specified explicit Values may be extended by implementors to include additional new Values. These new Values shall be specified in the Conformance Statement (see PS 3.2) and shall not have the same meaning as currently defined Values in this standard. A Data [Element](#) with Defined Terms that does not contain a [Value](#) equivalent to one of the Values currently specified in this standard shall not be considered to have an invalid value. Note: Interpretation [Type](#) ID (4008,0210) is an example of a Data [Element](#) having Defined Terms. It is defined to have a [Value](#) that may be one of the set of standard Values; REPORT or AMENDMENT (see PS 3.3). Because this Data [Element](#) has Defined Terms other Interpretation [Type](#) IDs may be defined by the implementor.

```
#include <gdcmDefinedTerms.h>
```

Public Member Functions

- [DefinedTerms](#) ()=default

10.80.1 Detailed Description

Defined Terms are used when the specified explicit Values may be extended by implementors to include additional new Values. These new Values shall be specified in the Conformance Statement (see PS 3.2) and shall not have the same meaning as currently defined Values in this standard. A Data [Element](#) with Defined Terms that does not contain a [Value](#) equivalent to one of the Values currently specified in this standard shall not be considered to have an invalid value. Note: Interpretation [Type](#) ID (4008,0210) is an example of a Data [Element](#) having Defined Terms. It is defined to have a [Value](#) that may be one of the set of standard Values; REPORT or AMENDMENT (see PS 3.3). Because this Data [Element](#) has Defined Terms other Interpretation [Type](#) IDs may be defined by the implementor.

10.80.2 Constructor & Destructor Documentation

10.80.2.1 DefinedTerms()

```
gdcm::DefinedTerms::DefinedTerms () [default]
```

The documentation for this class was generated from the following file:

- [gdcmDefinedTerms.h](#)

10.81 gdcM::Defs Class Reference

FIXME I do not like the name 'Defs'.

```
#include <gdcMDefs.h>
```

Public Member Functions

- [Defs](#) ()
- [Defs](#) (const [Defs](#) &val)=delete
- [~Defs](#) ()
- const [IOD](#) & [GetIODFromFile](#) (const [File](#) &file) const
- [IODs](#) & [GetIODs](#) ()
- const [IODs](#) & [GetIODs](#) () const
- [Macros](#) & [GetMacros](#) ()
- const [Macros](#) & [GetMacros](#) () const
- [Modules](#) & [GetModules](#) ()
- const [Modules](#) & [GetModules](#) () const
- [Type](#) [GetTypeFromTag](#) (const [File](#) &file, const [Tag](#) &tag) const
- bool [IsEmpty](#) () const
- [Defs](#) & [operator=](#) (const [Defs](#) &val)=delete
- bool [Verify](#) (const [DataSet](#) &ds) const
- bool [Verify](#) (const [File](#) &file) const

Static Public Member Functions

- static const char * [GetIODNameFromMediaStorage](#) ([MediaStorage](#) const &ms)

Protected Member Functions

- void [LoadDefaults](#) ()
- void [LoadFromFile](#) (const char *filename)

Friends

- class [Global](#)

10.81.1 Detailed Description

FIXME I do not like the name 'Defs'.

Note

bla

Examples

[GenerateStandardSOPClasses.cxx](#), and [TraverseModules.cxx](#).

10.81.2 Constructor & Destructor Documentation

10.81.2.1 Defs() [1/2]

```
gdcm::Defs::Defs ()
```

Referenced by [Defs\(\)](#), and [operator=\(\)](#).

10.81.2.2 ~Defs()

```
gdcm::Defs::~~Defs ()
```

10.81.2.3 Defs() [2/2]

```
gdcm::Defs::Defs (  
    const Defs & val) [delete]
```

References [Defs\(\)](#).

10.81.3 Member Function Documentation

10.81.3.1 GetIODFromFile()

```
const IOD & gdcm::Defs::GetIODFromFile (  
    const File & file) const
```

10.81.3.2 GetIODNameFromMediaStorage()

```
const char * gdcm::Defs::GetIODNameFromMediaStorage (  
    MediaStorage const & ms) [static]
```

Examples

[GenerateStandardSOPClasses.cxx](#).

10.81.3.3 GetIODs() [1/2]

```
IODs & gdcm::Defs::GetIODs () [inline]
```

10.81.3.4 GetIODs() [2/2]

```
const IODs & gdcm::Defs::GetIODs () const [inline]
```

Examples

[TraverseModules.cxx](#).

10.81.3.5 GetMacros() [1/2]

```
Macros & gdcm::Defs::GetMacros () [inline]
```

10.81.3.6 GetMacros() [2/2]

```
const Macros & gdcm::Defs::GetMacros () const [inline]
```

Users should not directly use [Macro](#). [Macro](#) are simply a way for DICOM WG to re-use Tables. [Macros](#) are conveniently wrapped within [Modules](#). See [gdcm::Module](#) API directly

Examples

[TraverseModules.cxx](#).

10.81.3.7 GetModules() [1/2]

```
Modules & gdcm::Defs::GetModules () [inline]
```

10.81.3.8 GetModules() [2/2]

```
const Modules & gdcm::Defs::GetModules () const [inline]
```

Examples

[TraverseModules.cxx](#).

Referenced by [IsEmpty\(\)](#).

10.81.3.9 GetTypeFromTag()

```
Type gdcm::Defs::GetTypeFromTag (  
    const File & file,  
    const Tag & tag) const
```

10.81.3.10 IsEmpty()

```
bool gdcmm::Defs::IsEmpty () const [inline]
```

References [GetModules\(\)](#).

10.81.3.11 LoadDefaults()

```
void gdcmm::Defs::LoadDefaults () [protected]
```

10.81.3.12 LoadFromFile()

```
void gdcmm::Defs::LoadFromFile (  
    const char * filename) [protected]
```

10.81.3.13 operator=()

```
Defs & gdcmm::Defs::operator= (  
    const Defs & val) [delete]
```

References [Defs\(\)](#).

10.81.3.14 Verify() [1/2]

```
bool gdcmm::Defs::Verify (  
    const DataSet & ds) const
```

10.81.3.15 Verify() [2/2]

```
bool gdcmm::Defs::Verify (  
    const File & file) const
```

10.81.4 Friends And Related Symbol Documentation

10.81.4.1 Global

```
friend class Global [friend]
```

References [Global](#).

Referenced by [Global](#).

The documentation for this class was generated from the following file:


- [gdcmmDefs.h](#)

10.82 gdcm::DeltaEncodingCodec Class Reference


[DeltaEncodingCodec](#) compression used by some private vendor.

```
#include <gdcmDeltaEncodingCodec.h>
```

Inheritance diagram for `gdcm::DeltaEncodingCodec`:



Collaboration diagram for `gdcm::DeltaEncodingCodec`:



Public Member Functions

- [DeltaEncodingCodec](#) ()
- [~DeltaEncodingCodec](#) ()
- bool [CanDecode](#) ([TransferSyntax](#) const &ts)
- bool [Decode](#) ([DataElement](#) const &is, [DataElement](#) &os)

Decode.

Public Member Functions inherited from [gdcm::ImageCodec](#)

- [ImageCodec](#) ()
- [~ImageCodec](#) () override
- bool [CanCode](#) ([TransferSyntax](#) const &) const override
Return whether this coder support this transfer syntax (can code it)
- bool [CanDecode](#) ([TransferSyntax](#) const &) const override
Return whether this decoder support this transfer syntax (can decode it)
- bool [CleanupUnusedBits](#) (char *data, size_t datalen)
- virtual [ImageCodec](#) * [Clone](#) () const =0
- bool [Decode](#) ([DataElement](#) const &is_, [DataElement](#) &os) override
Decode.
- const unsigned int * [GetDimensions](#) () const
- virtual bool [GetHeaderInfo](#) (std::istream &is_, [TransferSyntax](#) &ts)
- bool [GetLossyFlag](#) () const
- const [LookupTable](#) & [GetLUT](#) () const
- bool [GetNeedByteSwap](#) () const
- unsigned int [GetNumberOfDimensions](#) () const
- const [PhotometricInterpretation](#) & [GetPhotometricInterpretation](#) () const
- [PixelFormat](#) & [GetPixelFormat](#) ()
- const [PixelFormat](#) & [GetPixelFormat](#) () const
- unsigned int [GetPlanarConfiguration](#) () const
- bool [IsLossy](#) () const
- void [SetDimensions](#) (const std::vector< unsigned int > &d)
- void [SetDimensions](#) (const unsigned int d[3])
- void [SetLossyFlag](#) (bool l)
- void [SetLUT](#) ([LookupTable](#) const &lut)
- void [SetNeedByteSwap](#) (bool b)
- void [SetNeedOverlayCleanup](#) (bool b)
- void [SetNumberOfDimensions](#) (unsigned int dim)
- void [SetPhotometricInterpretation](#) ([PhotometricInterpretation](#) const &pi)
- virtual void [SetPixelFormat](#) ([PixelFormat](#) const &pf)
- void [SetPlanarConfiguration](#) (unsigned int pc)

Public Member Functions inherited from [gdcm::Coder](#)

- virtual [~Coder](#) ()=default
- virtual bool [Code](#) ([DataElement](#) const &in_, [DataElement](#) &out_)
Code.

Public Member Functions inherited from [gdcm::Decoder](#)

- virtual [~Decoder](#) ()=default

Protected Member Functions

- bool [Decode](#) (std::istream &is, std::ostream &os)

Protected Member Functions inherited from [gdcm::ImageCodec](#)

- virtual bool [AppendFrameEncode](#) (std::ostream &out, const char *data, size_t datalen)
- virtual bool [AppendRowEncode](#) (std::ostream &out, const char *data, size_t datalen)
- bool [DecodeByStreams](#) (std::istream &is_, std::ostream &os) override
- bool [DoByteSwap](#) (std::istream &is_, std::ostream &os)
- bool [DoInvertMonochrome](#) (std::istream &is_, std::ostream &os)
- bool [DoOverlayCleanup](#) (std::istream &is_, std::ostream &os)
- bool [DoPaddedCompositePixelCode](#) (std::istream &is_, std::ostream &os)
- bool [DoPlanarConfiguration](#) (std::istream &is_, std::ostream &os)
- bool [DoSimpleCopy](#) (std::istream &is_, std::ostream &os)
- bool [DoYBR](#) (std::istream &is_, std::ostream &os)
- bool [DoYBRFull422](#) (std::istream &is_, std::ostream &os)
- virtual bool [IsFrameEncoder](#) ()
- virtual bool [IsRowEncoder](#) ()
- virtual bool [IsValid](#) ([PhotometricInterpretation](#) const &pi)
- virtual bool [StartEncode](#) (std::ostream &os)
- virtual bool [StopEncode](#) (std::ostream &os)

Protected Member Functions inherited from [gdcm::Coder](#)

- virtual bool [InternalCode](#) (const char *bv, unsigned long len, std::ostream &os)

Additional Inherited Members

Protected Types inherited from [gdcm::ImageCodec](#)

- typedef [SmartPointer](#)< [LookupTable](#) > [LUTPtr](#)

Protected Attributes inherited from [gdcm::ImageCodec](#)

- unsigned int [Dimensions](#) [3]
- bool [LossyFlag](#)
- [LUTPtr](#) [LUT](#)
- bool [NeedByteSwap](#)
- bool [NeedOverlayCleanup](#)
- unsigned int [NumberOfDimensions](#)
- [PixelFormat](#) [PF](#)
- [PhotometricInterpretation](#) [PI](#)
- unsigned int [PlanarConfiguration](#)
- bool [RequestPaddedCompositePixelCode](#)
- bool [RequestPlanarConfiguration](#)

10.82.1 Detailed Description

[DeltaEncodingCodec](#) compression used by some private vendor.

10.82.2 Constructor & Destructor Documentation

10.82.2.1 DeltaEncodingCodec()

```
gdcm::DeltaEncodingCodec::DeltaEncodingCodec ()
```

10.82.2.2 ~DeltaEncodingCodec()

```
gdcm::DeltaEncodingCodec::~~DeltaEncodingCodec ()
```

10.82.3 Member Function Documentation

10.82.3.1 CanDecode()

```
bool gdcm::DeltaEncodingCodec::CanDecode (
    TransferSyntax const & ts)
```

10.82.3.2 Decode() [1/2]

```
bool gdcm::DeltaEncodingCodec::Decode (
    DataElement const & ,
    DataElement & ) [virtual]
```

Decode.

Reimplemented from [gdcm::Decoder](#).

10.82.3.3 Decode() [2/2]

```
bool gdcm::DeltaEncodingCodec::Decode (
    std::istream & is,
    std::ostream & os) [protected]
```

The documentation for this class was generated from the following file:

- [gdcmDeltaEncodingCodec.h](#)

10.83 gdcm::DICOMDIR Class Reference

[DICOMDIR](#) class.

```
#include <gdcmDICOMDIR.h>
```

Public Member Functions

- [DICOMDIR](#) ()=default
- [DICOMDIR](#) ([FileSet](#) fs)

10.83.1 Detailed Description

[DICOMDIR](#) class.

Structured for handling [DICOMDIR](#)

10.83.2 Constructor & Destructor Documentation

10.83.2.1 DICOMDIR() [1/2]

```
gdcm::DICOMDIR::DICOMDIR () [default]
```

10.83.2.2 DICOMDIR() [2/2]

```
gdcm::DICOMDIR::DICOMDIR (  
    FileSet fs) [inline]
```

The documentation for this class was generated from the following file:

- [gdcmDICOMDIR.h](#)

10.84 gdcm::DICOMDIRGenerator Class Reference

[DICOMDIRGenerator](#) class.

```
#include <gdcmDICOMDIRGenerator.h>
```

Public Types

- typedef [Directory::FileNamesType](#) FileNamesType
- typedef [Directory::FilenameType](#) FilenameType

Public Member Functions

- [DICOMDIRGenerator](#) ()
- [~DICOMDIRGenerator](#) ()
- bool [Generate](#) ()
Main function to generate the [DICOMDIR](#).
- [File](#) & [GetFile](#) ()
- void [SetDescriptor](#) (const char *d)
- void [SetFile](#) (const [File](#) &f)
Set/Get file. The [DICOMDIR](#) file will be valid once a call to Generate has been done.
- void [SetFilenames](#) ([FilenamesType](#) const &fns)
Set the list of filenames from which the [DICOMDIR](#) should be generated from.
- void [SetRootDirectory](#) ([FilenameType](#) const &root)
Set the root directory from which the filenames should be considered.

Protected Member Functions

- bool [AddImageDirectoryRecord](#) ()
- bool [AddPatientDirectoryRecord](#) ()
- bool [AddSeriesDirectoryRecord](#) ()
- bool [AddStudyDirectoryRecord](#) ()
- [Scanner](#) & [GetScanner](#) ()

10.84.1 Detailed Description

[DICOMDIRGenerator](#) class.

This is a STD-GEN-CD [DICOMDIR](#) generator. ref: PS 3.11-2008 Annex D (Normative) - General Purpose CD-R and DVD Interchange Profiles

Note

PS 3.11 - 2008 / D.3.2 Physical Medium And Medium Format The STD-GEN-CD and STD-GEN-SEC-CD application profiles require the 120 mm CD-R physical medium with the ISO/IEC 9660 Media Format, as defined in PS3.12. See also PS 3.12 - 2008 / Annex F 120mm CD-R Medium (Normative) and PS 3.10 - 2008 / 8 DICOM [File](#) Service / 8.1 FILE-SET

Warning

: PS 3.11 - 2008 / D.3.1 SOP Classes and Transfer Syntaxes Composite [Image](#) & Stand-alone Storage are required to be stored as Explicit [VR](#) Little Endian Uncompressed (1.2.840.10008.1.2.1). When a DICOM file is found using another Transfer Syntax the generator will simply stops.

- Input files should be Explicit [VR](#) Little Endian
- filenames should be valid [VR::CS](#) value (16 bytes, upper case ...)

Bug : There is a current limitation of not handling Referenced SOP Class UID / Referenced SOP Instance UID simply because the [Scanner](#) does not allow us See PS 3.11 / [Table](#) D.3-2 STD-GEN Additional [DICOMDIR](#) Keys

Examples

[GenerateDICOMDIR.cs](#).

10.84.2 Member Typedef Documentation

10.84.2.1 FilenamesType

```
typedef Directory::FilenamesType gdcm::DICOMDIRGenerator::FilenamesType
```

10.84.2.2 FilenameType

```
typedef Directory::FilenameType gdcm::DICOMDIRGenerator::FilenameType
```

10.84.3 Constructor & Destructor Documentation

10.84.3.1 DICOMDIRGenerator()

```
gdcm::DICOMDIRGenerator::DICOMDIRGenerator ()
```

10.84.3.2 ~DICOMDIRGenerator()

```
gdcm::DICOMDIRGenerator::~~DICOMDIRGenerator ()
```

10.84.4 Member Function Documentation

10.84.4.1 AddImageDirectoryRecord()

```
bool gdcm::DICOMDIRGenerator::AddImageDirectoryRecord () [protected]
```

10.84.4.2 AddPatientDirectoryRecord()

```
bool gdcm::DICOMDIRGenerator::AddPatientDirectoryRecord () [protected]
```

10.84.4.3 AddSeriesDirectoryRecord()

```
bool gdcm::DICOMDIRGenerator::AddSeriesDirectoryRecord () [protected]
```

10.84.4.4 AddStudyDirectoryRecord()

```
bool gdcm::DICOMDIRGenerator::AddStudyDirectoryRecord () [protected]
```

10.84.4.5 Generate()

```
bool gdcm::DICOMDIRGenerator::Generate ()
```

Main function to generate the [DICOMDIR](#).

Examples

[GenerateDICOMDIR.cs](#).

10.84.4.6 GetFile()

```
File & gdcm::DICOMDIRGenerator::GetFile ()
```

Examples

[GenerateDICOMDIR.cs](#).

10.84.4.7 GetScanner()

```
Scanner & gdcm::DICOMDIRGenerator::GetScanner () [protected]
```

10.84.4.8 SetDescriptor()

```
void gdcm::DICOMDIRGenerator::SetDescriptor (  
    const char * d)
```

Set the [File](#) Set ID.

Warning

this need to be a valid [VR::CS](#) value

Examples

[GenerateDICOMDIR.cs](#).

10.84.4.9 SetFile()

```
void gdcm::DICOMDIRGenerator::SetFile (  
    const File & f)
```

Set/Get file. The [DICOMDIR](#) file will be valid once a call to Generate has been done.

10.84.4.10 SetFileNames()

```
void gdcmm::DICOMDIRGenerator::SetFileNames (
    FilenamesType const & fns)
```

Set the list of filenames from which the [DICOMDIR](#) should be generated from.

Examples

[GenerateDICOMDIR.cs.](#)

10.84.4.11 SetRootDirectory()

```
void gdcmm::DICOMDIRGenerator::SetRootDirectory (
    FilenameType const & root)
```

Set the root directory from which the filenames should be considered.

The documentation for this class was generated from the following file:

- [gdcmmDICOMDIRGenerator.h](#)

10.85 gdcmm::Dict Class Reference

Class to represent a map of [DictEntry](#).

```
#include <gdcmmDict.h>
```

Public Types

- typedef MapDictEntry::const_iterator [ConstIterator](#)
- typedef MapDictEntry::iterator [Iterator](#)
- typedef std::map< [Tag](#), [DictEntry](#) > [MapDictEntry](#)

Public Member Functions

- [Dict](#) ()
 - [Dict](#) (const [Dict](#) & _val)=delete
 - void [AddDictEntry](#) (const [Tag](#) &tag, const [DictEntry](#) &de)
 - [ConstIterator](#) [Begin](#) () const
 - [ConstIterator](#) [End](#) () const
 - const [DictEntry](#) & [GetDictEntry](#) (const [Tag](#) &tag) const
 - const [DictEntry](#) & [GetDictEntryByKeyword](#) (const char *keyword, [Tag](#) &tag) const
 - const [DictEntry](#) & [GetDictEntryByName](#) (const char *name, [Tag](#) &tag) const
 - const char * [GetKeywordFromTag](#) ([Tag](#) const &tag) const
- Function to return the Keyword from a [Tag](#).*
- bool [IsEmpty](#) () const
 - [Dict](#) & [operator=](#) (const [Dict](#) & _val)=delete

Protected Member Functions

- void [LoadDefault](#) ()

Friends

- class [Dicts](#)
- std::ostream & [operator<<](#) (std::ostream &_os, const [Dict](#) &_val)

10.85.1 Detailed Description

Class to represent a map of [DictEntry](#).

Note

bla TODO FIXME: For [Element](#) == 0x0 need to return Name = Group Length ValueRepresentation = UL Value↵
Multiplicity = 1

Examples

[GenAllVR.cxx](#), [GenFakeIdentifyFile.cxx](#), [PublicDict.cxx](#), and [ReadAndPrintAttributes.cxx](#).

10.85.2 Member Typedef Documentation

10.85.2.1 ConstIterator

```
typedef MapDictEntry::const_iterator gdcm::Dict::ConstIterator
```

10.85.2.2 Iterator

```
typedef MapDictEntry::iterator gdcm::Dict::Iterator
```

10.85.2.3 MapDictEntry

```
typedef std::map<Tag, DictEntry> gdcm::Dict::MapDictEntry
```

10.85.3 Constructor & Destructor Documentation

10.85.3.1 Dict() [1/2]

```
gdcm::Dict::Dict () [inline]
```

References [gdcm_assert](#).

Referenced by [Dict\(\)](#), [operator<<](#), and [operator=\(\)](#).

10.85.3.2 Dict() [2/2]

```
gdcmm::Dict::Dict (
    const Dict & _val) [delete]
```

References [Dict\(\)](#), and [operator<<](#).

10.85.4 Member Function Documentation

10.85.4.1 AddDictEntry()

```
void gdcmm::Dict::AddDictEntry (
    const Tag & tag,
    const DictEntry & de) [inline]
```

References [gdcmm_assert](#).

10.85.4.2 Begin()

```
ConstIterator gdcmm::Dict::Begin () const [inline]
```

Examples

[GenAllVR.cxx](#), and [GenFakeIdentifyFile.cxx](#).

10.85.4.3 End()

```
ConstIterator gdcmm::Dict::End () const [inline]
```

Examples

[GenAllVR.cxx](#), and [GenFakeIdentifyFile.cxx](#).

10.85.4.4 GetDictEntry()

```
const DictEntry & gdcmm::Dict::GetDictEntry (
    const Tag & tag) const [inline]
```

Examples

[GenFakeIdentifyFile.cxx](#), and [PublicDict.cxx](#).

References [gdcmm_assert](#).

10.85.4.5 GetDictEntryByKeyword()

```
const DictEntry & gdcm::Dict::GetDictEntryByKeyword (
    const char * keyword,
    Tag & tag) const [inline]
```

Lookup [DictEntry](#) by keyword. Even if DICOM standard defines keyword as being unique. The lookup table is built on [Tag](#). Therefore looking up a [DictEntry](#) by Keyword is more inefficient than looking up by [Tag](#).

References [gdcm_assert](#).

10.85.4.6 GetDictEntryByName()

```
const DictEntry & gdcm::Dict::GetDictEntryByName (
    const char * name,
    Tag & tag) const [inline]
```

Inefficient way of looking up tag by name. Technically DICOM does not guarantee uniqueness (and [Curve](#) / [Overlay](#) are there to prove it). But most of the time name is in fact uniq and can be uniquely link to a tag

Examples

[ReadAndPrintAttributes.cxx](#).

References [gdcm_assert](#).

10.85.4.7 GetKeywordFromTag()

```
const char * gdcm::Dict::GetKeywordFromTag (
    Tag const & tag) const [inline]
```

Function to return the Keyword from a [Tag](#).

References [gdcm_assert](#).

10.85.4.8 IsEmpty()

```
bool gdcm::Dict::IsEmpty () const [inline]
```

10.85.4.9 LoadDefault()

```
void gdcm::Dict::LoadDefault () [protected]
```

10.85.4.10 operator=()

```
Dict & gdcmm::Dict::operator= (
    const Dict & _val) [delete]
```

References [Dict\(\)](#).

10.85.5 Friends And Related Symbol Documentation

10.85.5.1 Dicts

```
friend class Dicts [friend]
```

References [Dicts](#).

Referenced by [Dicts](#).

10.85.5.2 operator<<

```
std::ostream & operator<< (
    std::ostream & _os,
    const Dict & _val) [friend]
```

References [Dict\(\)](#).

Referenced by [Dict\(\)](#).

The documentation for this class was generated from the following file:

- [gdcmmDict.h](#)

10.86 gdcmm::DictConverter Class Reference

Class to convert a .dic file into something else:

```
#include <gdcmmDictConverter.h>
```

Public Types

- enum [OutputTypes](#) {
 [DICT_DEFAULT](#) = 0 ,
 [DICT_DEBUG](#) ,
 [DICT_XML](#) }

Public Member Functions

- [DictConverter](#) ()
- [~DictConverter](#) ()
- void [Convert](#) ()
- const std::string & [GetDictName](#) () const
- const std::string & [GetInputFilename](#) () const
- const std::string & [GetOutputFilename](#) () const
- int [GetOutputType](#) () const
- void [SetDictName](#) (const char *name)
- void [SetInputFileName](#) (const char *filename)
- void [SetOutputFileName](#) (const char *filename)
- void [SetOutputType](#) (int type)

Static Public Member Functions

- static bool [Readuint16](#) (const char *raw, uint16_t &ov)
- static bool [ReadVM](#) (const char *raw, [VM::VMType](#) &type)
- static bool [ReadVR](#) (const char *raw, [VR::VRType](#) &type)

Protected Member Functions

- void [AddGroupLength](#) ()
- bool [ConvertToCXX](#) (const char *raw, std::string &cxx)
- bool [ConvertToXML](#) (const char *raw, std::string &cxx)
- void [WriteFooter](#) ()
- void [WriteHeader](#) ()

10.86.1 Detailed Description

Class to convert a .dic file into something else:

- CXX code : embed dict into shared lib (DICT_DEFAULT)
- Debug mode (DICT_DEBUG)
- XML dict (DICT_XML)

Note

10.86.2 Member Enumeration Documentation

10.86.2.1 OutputTypes

enum [gdcm::DictConverter::OutputTypes](#)

Enumerator

DICT_DEFAULT	
DICT_DEBUG	
DICT_XML	

10.86.3 Constructor & Destructor Documentation**10.86.3.1 DictConverter()**

```
gdcM::DictConverter::DictConverter ()
```

10.86.3.2 ~DictConverter()

```
gdcM::DictConverter::~~DictConverter ()
```

10.86.4 Member Function Documentation**10.86.4.1 AddGroupLength()**

```
void gdcM::DictConverter::AddGroupLength () [protected]
```

10.86.4.2 Convert()

```
void gdcM::DictConverter::Convert ()
```

10.86.4.3 ConvertToCXX()

```
bool gdcM::DictConverter::ConvertToCXX (
    const char * raw,
    std::string & cxx) [protected]
```

10.86.4.4 ConvertToXML()

```
bool gdcM::DictConverter::ConvertToXML (
    const char * raw,
    std::string & cxx) [protected]
```

10.86.4.5 GetDictName()

```
const std::string & gdcm::DictConverter::GetDictName () const
```

10.86.4.6 GetInputFilename()

```
const std::string & gdcm::DictConverter::GetInputFilename () const
```

10.86.4.7 GetOutputFilename()

```
const std::string & gdcm::DictConverter::GetOutputFilename () const
```

10.86.4.8 GetOutputType()

```
int gdcm::DictConverter::GetOutputType () const [inline]
```

10.86.4.9 Readuint16()

```
bool gdcm::DictConverter::Readuint16 (
    const char * raw,
    uint16_t & ov) [static]
```

10.86.4.10 ReadVM()

```
bool gdcm::DictConverter::ReadVM (
    const char * raw,
    VM::VMType & type) [static]
```

10.86.4.11 ReadVR()

```
bool gdcm::DictConverter::ReadVR (
    const char * raw,
    VR::VRType & type) [static]
```

10.86.4.12 SetDictName()

```
void gdcm::DictConverter::SetDictName (
    const char * name)
```

10.86.4.13 SetInputFileName()

```
void gdcm::DictConverter::SetInputFileName (
    const char * filename)
```

10.86.4.14 SetOutputFileName()

```
void gdcm::DictConverter::SetOutputFileName (
    const char * filename)
```

10.86.4.15 SetOutputType()

```
void gdcm::DictConverter::SetOutputType (
    int type) [inline]
```

10.86.4.16 WriteFooter()

```
void gdcm::DictConverter::WriteFooter () [protected]
```

10.86.4.17 WriteHeader()

```
void gdcm::DictConverter::WriteHeader () [protected]
```

The documentation for this class was generated from the following file:

- [gdcmDictConverter.h](#)

10.87 gdcm::DictEntry Class Reference

Class to represent an Entry in the [Dict](#).

```
#include <gdcmDictEntry.h>
```

Public Member Functions

- [DictEntry](#) (const char *name="", const char *keyword="", [VR](#) const &vr=[VR::INVALID](#), [VM](#) const &vm=[VM::VM0](#), bool ret=false)
- const char * [GetKeyword](#) () const
same as GetName but without spaces...
- const char * [GetName](#) () const
Set/Get Name.
- bool [GetRetired](#) () const
Set/Get Retired flag.
- const [VM](#) & [GetVM](#) () const
Set/Get VM.
- const [VR](#) & [GetVR](#) () const
Set/Get VR.
- bool [IsUnique](#) () const
- void [SetElementXX](#) (bool v)
Set whether element is shared in multiple elements (Source [Image](#) IDs typically)
- void [SetGroupXX](#) (bool v)
Set whether element is shared in multiple groups (Curve/Overlay typically)
- void [SetKeyword](#) (const char *keyword)
- void [SetName](#) (const char *name)
- void [SetRetired](#) (bool retired)
- void [SetVM](#) ([VM](#) const &vm)
- void [SetVR](#) (const [VR](#) &vr)

Friends

- class [Dict](#)
- std::ostream & [operator<<](#) (std::ostream &_os, const [DictEntry](#) &_val)

10.87.1 Detailed Description

Class to represent an Entry in the [Dict](#).

Does not really exist within the DICOM definition, just a way to minimize storage and have a mapping from [gdcm::Tag](#) to the needed information

Note

bla TODO FIXME: Need a PublicDictEntry...indeed [DictEntry](#) has a notion of retired which does not exist in PrivateDictEntry...

See also

[gdcm::Dict](#)

Examples

[GenAllVR.cxx](#), [GenFakeIdentifyFile.cxx](#), [PublicDict.cxx](#), and [TraverseModules.cxx](#).

10.87.2 Constructor & Destructor Documentation

10.87.2.1 DictEntry()

```
gdcM::DictEntry::DictEntry (  
    const char * name = "",  
    const char * keyword = "",  
    VR const & vr = VR::INVALID,  
    VM const & vm = VM::VM0,  
    bool ret = false) [inline]
```

References [gdcM::VR::INVALID](#), and [gdcM::VM::VM0](#).

Referenced by [operator<<](#).

10.87.3 Member Function Documentation

10.87.3.1 GetKeyword()

```
const char * gdcM::DictEntry::GetKeyword () const [inline]
```

same as GetName but without spaces...

10.87.3.2 GetName()

```
const char * gdcM::DictEntry::GetName () const [inline]
```

Set/Get Name.

Referenced by [gdcM::PrivateDict::PrintXML\(\)](#).

10.87.3.3 GetRetired()

```
bool gdcM::DictEntry::GetRetired () const [inline]
```

Set/Get Retired flag.

Examples

[GenAllVR.cxx](#).

10.87.3.4 GetVM()

```
const VM & gdcM::DictEntry::GetVM () const [inline]
```

Set/Get VM.

Referenced by [gdcM::PrivateDict::AddDictEntry\(\)](#), and [gdcM::PrivateDict::PrintXML\(\)](#).

10.87.3.5 GetVR()

```
const VR & gdcmm::DictEntry::GetVR () const [inline]
```

Set/Get [VR](#).

Examples

[GenAllVR.cxx](#), and [GenFakeIdentifyFile.cxx](#).

Referenced by [gdcmm::PrivateDict::AddDictEntry\(\)](#), and [gdcmm::PrivateDict::PrintXML\(\)](#).

10.87.3.6 IsUnique()

```
bool gdcmm::DictEntry::IsUnique () const [inline]
```

Return whether the name of the [DataElement](#) can be considered to be unique. As of 2008 all elements name were unique (except the explicitly 'XX' ones)

10.87.3.7 SetElementXX()

```
void gdcmm::DictEntry::SetElementXX (  
    bool v) [inline]
```

Set whether element is shared in multiple elements (Source [Image](#) IDs typically)

10.87.3.8 SetGroupXX()

```
void gdcmm::DictEntry::SetGroupXX (  
    bool v) [inline]
```

Set whether element is shared in multiple groups (Curve/Overlay typically)

10.87.3.9 SetKeyword()

```
void gdcmm::DictEntry::SetKeyword (  
    const char * keyword) [inline]
```

10.87.3.10 SetName()

```
void gdcmm::DictEntry::SetName (  
    const char * name) [inline]
```

10.87.3.11 SetRetired()

```
void gdcM::DictEntry::SetRetired (
    bool retired) [inline]
```

10.87.3.12 SetVM()

```
void gdcM::DictEntry::SetVM (
    VM const & vm) [inline]
```

Referenced by [gdcM::PrivateDict::AddDictEntry\(\)](#).

10.87.3.13 SetVR()

```
void gdcM::DictEntry::SetVR (
    const VR & vr) [inline]
```

Referenced by [gdcM::PrivateDict::AddDictEntry\(\)](#).

10.87.4 Friends And Related Symbol Documentation

10.87.4.1 Dict

```
friend class Dict [friend]
```

References [Dict](#).

Referenced by [Dict](#).

10.87.4.2 operator<<

```
std::ostream & operator<< (
    std::ostream & _os,
    const DictEntry & _val) [friend]
```

References [DictEntry\(\)](#).

The documentation for this class was generated from the following file:


- [gdcMDictEntry.h](#)

10.88 gdcm::DictPrinter Class Reference


[DictPrinter](#) class.

```
#include <gdcmDictPrinter.h>
```

Inheritance diagram for gdcm::DictPrinter:



Collaboration diagram for gdcm::DictPrinter:



Public Member Functions

- [DictPrinter](#) ()
- [~DictPrinter](#) ()=default
- void [Print](#) (std::ostream &os)

Public Member Functions inherited from [gdcm::Printer](#)

- [Printer](#) ()
- [~Printer](#) ()=default
- [PrintStyles GetPrintStyle](#) () const
Get PrintStyle value.
- void [Print](#) (std::ostream &os)
Print.
- void [PrintDataSet](#) (const [DataSet](#) &ds, std::ostream &os, const std::string &s="")
Print an individual dataset.
- void [SetColor](#) (bool c)
Set color mode or not.
- void [SetFile](#) ([File](#) const &f)
Set file.
- void [SetStyle](#) ([PrintStyles](#) ps)
Set PrintStyle value.

Protected Member Functions

- void [PrintDataElement2](#) (std::ostream &os, const [DataSet](#) &ds, const [DataElement](#) &ide)
- void [PrintDataSet2](#) (std::ostream &os, const [DataSet](#) &ds)

Protected Member Functions inherited from [gdcm::Printer](#)

- [VR PrintDataElement](#) (std::ostringstream &os, const [Dicts](#) &dicts, const [DataSet](#) &ds, const [DataElement](#) &de, std::ostream &out, std::string const &indent)
- void [PrintSQ](#) (const [SequenceOfItems](#) *sqi, std::ostream &os, std::string const &indent)

Additional Inherited Members

Public Types inherited from [gdcm::Printer](#)

- enum [PrintStyles](#) {
 [VERBOSE_STYLE](#) = 0 ,
 [CONDENSED_STYLE](#) ,
 [XML](#) ,
 [CXX](#) }

Protected Attributes inherited from [gdcm::Printer](#)

- const [File](#) * [F](#)
- [VL](#) [MaxPrintLength](#)
- [PrintStyles](#) [PrintStyle](#)

10.88.1 Detailed Description

[DictPrinter](#) class.

10.88.2 Constructor & Destructor Documentation

10.88.2.1 DictPrinter()

```
gdcm::DictPrinter::DictPrinter ()
```

10.88.2.2 ~DictPrinter()

```
gdcm::DictPrinter::~~DictPrinter () [default]
```

10.88.3 Member Function Documentation

10.88.3.1 Print()

```
void gdcm::DictPrinter::Print (  
    std::ostream & os)
```

10.88.3.2 PrintDataElement2()

```
void gdcm::DictPrinter::PrintDataElement2 (  
    std::ostream & os,  
    const DataSet & ds,  
    const DataElement & ide) [protected]
```

10.88.3.3 PrintDataSet2()

```
void gdcm::DictPrinter::PrintDataSet2 (  
    std::ostream & os,  
    const DataSet & ds) [protected]
```

The documentation for this class was generated from the following file:

- [gdcmDictPrinter.h](#)

10.89 gdcmmDicts Class Reference

Class to manipulate the sum of knowledge (all the dict user load)

```
#include <gdcmmDicts.h>
```

Public Member Functions

- [Dicts](#) ()
- [Dicts](#) (const [Dicts](#) &_val)=delete
- [~Dicts](#) ()
- const [CSAHeaderDict](#) & [GetCSAHeaderDict](#) () const
- const [DictEntry](#) & [GetDictEntry](#) (const [PrivateTag](#) &tag) const
- const [DictEntry](#) & [GetDictEntry](#) (const [Tag](#) &tag, const char *owner=nullptr) const
THREAD SAFE.
- [PrivateDict](#) & [GetPrivateDict](#) ()
- const [PrivateDict](#) & [GetPrivateDict](#) () const
- const [Dict](#) & [GetPublicDict](#) () const
- bool [IsEmpty](#) () const
- [Dicts](#) & [operator=](#) (const [Dicts](#) &_val)=delete

Protected Types

- enum [ConstructorType](#) {
 [PHILIPS](#) ,
 [GEMS](#) ,
 [SIEMENS](#) }

Protected Member Functions

- void [LoadDefaults](#) ()

Static Protected Member Functions

- static const char * [GetConstructorString](#) ([ConstructorType](#) type)

Friends

- class [Global](#)
- std::ostream & [operator<<](#) (std::ostream &_os, const [Dicts](#) &d)

10.89.1 Detailed Description

Class to manipulate the sum of knowledge (all the dict user load)

Note

bla

Examples

[GenAllVR.cxx](#), [GenFakeIdentifyFile.cxx](#), [PublicDict.cxx](#), [ReadAndPrintAttributes.cxx](#), and [TraverseModules.cxx](#).

10.89.2 Member Enumeration Documentation

10.89.2.1 ConstructorType

```
enum gdcmm::Dicts::ConstructorType [protected]
```

Enumerator

PHILIPS	
GEMS	
SIEMENS	

10.89.3 Constructor & Destructor Documentation

10.89.3.1 Dicts() [1/2]

```
gdcmm::Dicts::Dicts ()
```

Referenced by [Dicts\(\)](#), [operator<<](#), and [operator=\(\)](#).

10.89.3.2 ~Dicts()

```
gdcmm::Dicts::~~Dicts ()
```

10.89.3.3 Dicts() [2/2]

```
gdcmm::Dicts::Dicts (  
    const Dicts & _val) [delete]
```

References [Dicts\(\)](#).

10.89.4 Member Function Documentation

10.89.4.1 GetConstructorString()

```
const char * gdcmm::Dicts::GetConstructorString (  
    ConstructorType type) [static], [protected]
```

10.89.4.2 GetCSAHeaderDict()

```
const CSAHeaderDict & gdcmm::Dicts::GetCSAHeaderDict () const
```

Examples

[MrProtocol.cxx](#).

10.89.4.3 GetDictEntry() [1/2]

```
const DictEntry & gdcmm::Dicts::GetDictEntry (  
    const PrivateTag & tag) const
```

10.89.4.4 GetDictEntry() [2/2]

```
const DictEntry & gdcmm::Dicts::GetDictEntry (  
    const Tag & tag,  
    const char * owner = nullptr) const
```

THREAD SAFE.

works for both public and private dicts: owner is null for public dict

Warning

owner need to be set to appropriate owner for call to work. see

Examples

[PublicDict.cxx](#), and [TraverseModules.cxx](#).

10.89.4.5 GetPrivateDict() [1/2]

```
PrivateDict & gdcmm::Dicts::GetPrivateDict ()
```


10.89.4.6 GetPrivateDict() [2/2]

```
const PrivateDict & gdcm::Dicts::GetPrivateDict () const
```

10.89.4.7 GetPublicDict()

```
const Dict & gdcm::Dicts::GetPublicDict () const
```

Examples

[GenAllVR.cxx](#), [GenFakeIdentifyFile.cxx](#), [PublicDict.cxx](#), and [ReadAndPrintAttributes.cxx](#).

Referenced by [IsEmpty\(\)](#).

10.89.4.8 IsEmpty()

```
bool gdcm::Dicts::IsEmpty () const [inline]
```

References [GetPublicDict\(\)](#).

10.89.4.9 LoadDefaults()

```
void gdcm::Dicts::LoadDefaults () [protected]
```

10.89.4.10 operator=()

```
Dicts & gdcm::Dicts::operator= (  
    const Dicts & _val) [delete]
```

References [Dicts\(\)](#).

10.89.5 Friends And Related Symbol Documentation

10.89.5.1 Global

```
friend class Global [friend]
```

References [Global](#).

Referenced by [Global](#).

10.89.5.2 operator<<

```
std::ostream & operator<< (
    std::ostream & _os,
    const Dicts & d) [friend]
```

References [Dicts\(\)](#).

The documentation for this class was generated from the following file:

- [gdcmDicts.h](#)

10.90 gdcm::network::DIMSE Class Reference

[DIMSE](#).

```
#include <gdcmDIMSE.h>
```

Public Types

- enum [CommandTypes](#) {
 - [C_STORE_RQ](#) = 0x0001 ,
 - [C_STORE_RSP](#) = 0x8001 ,
 - [C_GET_RQ](#) = 0x0010 ,
 - [C_GET_RSP](#) = 0x8010 ,
 - [C_FIND_RQ](#) = 0x0020 ,
 - [C_FIND_RSP](#) = 0x8020 ,
 - [C_MOVE_RQ](#) = 0x0021 ,
 - [C_MOVE_RSP](#) = 0x8021 ,
 - [C_ECHO_RQ](#) = 0x0030 ,
 - [C_ECHO_RSP](#) = 0x8030 ,
 - [N_EVENT_REPORT_RQ](#) = 0x0100 ,
 - [N_EVENT_REPORT_RSP](#) = 0x8100 ,
 - [N_GET_RQ](#) = 0x0110 ,
 - [N_GET_RSP](#) = 0x8110 ,
 - [N_SET_RQ](#) = 0x0120 ,
 - [N_SET_RSP](#) = 0x8120 ,
 - [N_ACTION_RQ](#) = 0x0130 ,
 - [N_ACTION_RSP](#) = 0x8130 ,
 - [N_CREATE_RQ](#) = 0x0140 ,
 - [N_CREATE_RSP](#) = 0x8140 ,
 - [N_DELETE_RQ](#) = 0x0150 ,
 - [N_DELETE_RSP](#) = 0x8150 ,
 - [C_CANCEL_RQ](#) = 0x0FFF }

10.90.1 Detailed Description

[DIMSE](#).

PS 3.7 - 2009 Annex E [Command](#) Dictionary (Normative) E.1 REGISTRY OF DICOM COMMAND ELEMENTS [Table E.1-1 COMMAND FIELDS \(PART 1\)](#)

10.90.2 Member Enumeration Documentation

10.90.2.1 CommandTypes

enum [gdcm::network::DIMSE::CommandTypes](#)

Enumerator

C_STORE_RQ	
C_STORE_RSP	
C_GET_RQ	
C_GET_RSP	
C_FIND_RQ	
C_FIND_RSP	
C_MOVE_RQ	
C_MOVE_RSP	
C_ECHO_RQ	
C_ECHO_RSP	
N_EVENT_REPORT_RQ	
N_EVENT_REPORT_RSP	
N_GET_RQ	
N_GET_RSP	
N_SET_RQ	
N_SET_RSP	
N_ACTION_RQ	
N_ACTION_RSP	
N_CREATE_RQ	
N_CREATE_RSP	
N_DELETE_RQ	
N_DELETE_RSP	
C_CANCEL_RQ	

The documentation for this class was generated from the following file:

- [gdcmDIMSE.h](#)

10.91 gdcm::DirectionCosines Class Reference

class to handle [DirectionCosines](#)

```
#include <gdcmDirectionCosines.h>
```

Public Member Functions

- [DirectionCosines](#) ()
- [DirectionCosines](#) (const double dircos[6])
- [~DirectionCosines](#) ()=default
- double [ComputeDistAlongNormal](#) (const double ipp[3]) const
Compute the distance along the normal.
- void [Cross](#) (double z[3]) const
Compute Cross product.
- double [CrossDot](#) ([DirectionCosines](#) const &dc) const
Compute the Dot product of the two cross vector of both [DirectionCosines](#) object.
- double [Dot](#) () const
Compute Dot.
- bool [IsValid](#) () const
Return whether or not this is a valid direction cosines.
- void [Normalize](#) ()
Normalize in-place.
- [operator const double *](#) () const
*Make the class behave like a const double *.*
- void [Print](#) (std::ostream &) const
Print.
- bool [SetFromString](#) (const char *str)

Static Public Member Functions

- static double [Dot](#) (const double x[3], const double y[3])
Compute Dot.
- static double [Norm](#) (const double v[3])
Return norm of the vector.
- static void [Normalize](#) (double v[3])
Normalize in-place.

10.91.1 Detailed Description

class to handle [DirectionCosines](#)

Examples

[DiscriminateVolume.cxx](#).

10.91.2 Constructor & Destructor Documentation

10.91.2.1 [DirectionCosines](#)() [1/2]

```
gdcm::DirectionCosines::DirectionCosines ()
```

Referenced by [CrossDot](#)().

10.91.2.2 DirectionCosines() [2/2]

```
gdcmm::DirectionCosines::DirectionCosines (
    const double dircos[6])
```

10.91.2.3 ~DirectionCosines()

```
gdcmm::DirectionCosines::~~DirectionCosines () [default]
```

10.91.3 Member Function Documentation

10.91.3.1 ComputeDistAlongNormal()

```
double gdcmm::DirectionCosines::ComputeDistAlongNormal (
    const double ipp[3]) const
```

Compute the distance along the normal.

10.91.3.2 Cross()

```
void gdcmm::DirectionCosines::Cross (
    double z[3]) const
```

Compute Cross product.

10.91.3.3 CrossDot()

```
double gdcmm::DirectionCosines::CrossDot (
    DirectionCosines const & dc) const
```

Compute the Dot product of the two cross vector of both [DirectionCosines](#) object.

Examples

[DiscriminateVolume.cxx](#).

References [DirectionCosines\(\)](#).

10.91.3.4 Dot() [1/2]

```
double gdcmm::DirectionCosines::Dot () const
```

Compute Dot.

10.91.3.5 Dot() [2/2]

```
double gdcM::DirectionCosines::Dot (  
    const double x[3],  
    const double y[3]) [static]
```

Compute Dot.

10.91.3.6 IsValid()

```
bool gdcM::DirectionCosines::IsValid () const
```

Return whether or not this is a valid direction cosines.

10.91.3.7 Norm()

```
double gdcM::DirectionCosines::Norm (  
    const double v[3]) [static]
```

Return norm of the vector.

10.91.3.8 Normalize() [1/2]

```
void gdcM::DirectionCosines::Normalize ()
```

Normalize in-place.

10.91.3.9 Normalize() [2/2]

```
void gdcM::DirectionCosines::Normalize (  
    double v[3]) [static]
```

Normalize in-place.

10.91.3.10 operator const double *()

```
gdcM::DirectionCosines::operator const double * () const [inline]
```

Make the class behave like a const double *.

10.91.3.11 Print()

```
void gdcM::DirectionCosines::Print (  
    std::ostream & ) const
```

Print.

10.91.3.12 SetFromString()

```
bool gdcm::DirectionCosines::SetFromString (
    const char * str)
```

Initialize from string str. It requires 6 floating point separated by a backslash character.

Examples

[DiscriminateVolume.cxx](#).

The documentation for this class was generated from the following file:

- [gdcmDirectionCosines.h](#)

10.92 gdcm::Directory Class Reference

Class for manipulation directories.

```
#include <gdcmDirectory.h>
```

Public Types

- typedef std::vector< [FilenameType](#) > [FileNamesType](#)
- typedef std::string [FilenameType](#)

Public Member Functions

- [Directory](#) ()=default
- [~Directory](#) ()=default
- [FileNamesType](#) const & [GetDirectories](#) () const
Return the Directories traversed.
- [FileNamesType](#) const & [GetFileNames](#) () const
Set/Get the file names within the directory.
- [FilenameType](#) const & [GetToplevel](#) () const
Get the name of the toplevel directory.
- unsigned int [Load](#) ([FilenameType](#) const &name, bool recursive=false)
- void [Print](#) (std::ostream &os=std::cout) const
Print.

Protected Member Functions

- unsigned int [Explore](#) ([FilenameType](#) const &name, bool recursive)
Return number of file found when 'recursive'ly exploring directory name

Friends

- `std::ostream & operator<< (std::ostream &_os, const Directory &d)`

10.92.1 Detailed Description

Class for manipulation directories.

Note

This implementation provide a cross platform implementation for manipulating directories: basically traversing directories and harvesting files

will not take into account unix type hidden file recursive option will not look into UNIX type hidden directory (those starting with a '.')

Since python or C# provide there own equivalent implementation, in which case `gdcmm::Directory` does not make much sense.

Examples

`DecompressImageMultiframe.cs`, `DiscriminateVolume.cxx`, `DumpToSQLITE3.cxx`, `DumpVisusChange.cxx`, `ExplicitLittleEndian.cs`, `GenerateDICOMDIR.cs`, `GenerateRTSTRUCT.cxx`, `ReadUTF8QtDir.cxx`, `ScanDirectory.cs`, `SortImage.cxx`, `StandardizeFiles.cs`, `VolumeSorter.cxx`, `gdcmmorphoplanes.cxx`, and `threadgdcmm.cxx`.

10.92.2 Member Typedef Documentation

10.92.2.1 FilenamesType

```
typedef std::vector<FilenameType> gdcmm::Directory::FilenamesType
```

Examples

`CStoreQtProgress.cxx`, `DumpVisusChange.cxx`, `GenerateRTSTRUCT.cxx`, `ReadUTF8QtDir.cxx`, `SimpleScanner.cxx`, `VolumeSorter.cxx`, `gdcmmorphoplanes.cxx`, `reslicesphere.cxx`, and `threadgdcmm.cxx`.

10.92.2.2 FilenameType

```
typedef std::string gdcmm::Directory::FilenameType
```

10.92.3 Constructor & Destructor Documentation

10.92.3.1 Directory()

```
gdcmm::Directory::Directory () [default]
```

Referenced by `operator<<`.

10.92.3.2 ~Directory()

```
gdcm::Directory::~~Directory () [default]
```

10.92.4 Member Function Documentation

10.92.4.1 Explore()

```
unsigned int gdcm::Directory::Explore (
    FilenameType const & name,
    bool recursive) [protected]
```

Return number of file found when 'recursive'ly exploring directory name

10.92.4.2 GetDirectories()

```
FilenameType const & gdcm::Directory::GetDirectories () const [inline]
```

Return the Directories traversed.

10.92.4.3 GetFileNames()

```
FilenameType const & gdcm::Directory::GetFileNames () const [inline]
```

Set/Get the file names within the directory.

Examples

[ClinicalTrialIdentificationWorkflow.cs](#), [DecompressImageMultiframe.cs](#), [DiscriminateVolume.cxx](#), [DumpToSQLITE3.cxx](#), [DumpVisusChange.cxx](#), [ExplicitLittleEndian.cs](#), [GenerateDICOMDIR.cs](#), [GenerateRTSTRUCT.cxx](#), [ReadUTF8QtDir.cxx](#), [ScanDirectory.cs](#), [SortImage.cxx](#), [StandardizeFiles.cs](#), [VolumeSorter.cxx](#), [gdcmorthoplanes.cxx](#), [reslicesphere.cxx](#), and [threadgdcm.cxx](#).

References [gdcm_assert](#).

10.92.4.4 GetToplevel()

```
FilenameType const & gdcm::Directory::GetToplevel () const [inline]
```

Get the name of the toplevel directory.

10.92.4.5 Load()

```
unsigned int gdcM::Directory::Load (  
    FilenameType const & name,  
    bool recursive = false)
```

construct a list of filenames and subdirectory beneath directory: name

Warning

: hidden file and hidden directory are not loaded.

Examples

[ClinicalTrialIdentificationWorkflow.cs](#), [DecompressImageMultiframe.cs](#), [DiscriminateVolume.cxx](#), [DumpToSQLITE3.cxx](#), [DumpVisusChange.cxx](#), [ExplicitLittleEndian.cs](#), [GenerateDICOMDIR.cs](#), [GenerateRTSTRUCT.cxx](#), [ReadUTF8QtDir.cxx](#), [ScanDirectory.cs](#), [SortImage.cxx](#), [StandardizeFiles.cs](#), [VolumeSorter.cxx](#), [gdcMOrthoplanes.cxx](#), [reslicesphere.cxx](#), and [threadgdcM.cxx](#).

10.92.4.6 Print()

```
void gdcM::Directory::Print (  
    std::ostream & os = std::cout) const
```

Print.

Examples

[SortImage.cxx](#).

Referenced by [operator<<](#).

10.92.5 Friends And Related Symbol Documentation

10.92.5.1 operator<<

```
std::ostream & operator<< (  
    std::ostream & _os,  
    const Directory & d) [friend]
```

References [Directory\(\)](#), and [Print\(\)](#).

The documentation for this class was generated from the following file:

- [gdcMDirectory.h](#)

10.93 gdcm::DirectoryHelper Class Reference

[DirectoryHelper](#).

```
#include <gdcmDirectoryHelper.h>
```

Static Public Member Functions

- static [Directory::FilenamesType GetCTImageSeriesUIDs](#) (const std::string &inDirectory)
- static [Directory::FilenamesType GetFileNamesFromSeriesUIDs](#) (const std::string &inDirectory, const std::string &inSeriesUID)
- static std::string [GetFrameOfReference](#) (const std::vector< [DataSet](#) > &inDS)
- static [Directory::FilenamesType GetMRImageSeriesUIDs](#) (const std::string &inDirectory)
- static [Directory::FilenamesType GetRTStructSeriesUIDs](#) (const std::string &inDirectory)
- static [Directory::FilenamesType GetSeriesUIDsBySOPClassUID](#) (const std::string &inDirectory, const std::string &inSOPClassUID)
- static std::string [GetSOPClassUID](#) (const std::vector< [DataSet](#) > &inDS)
- static std::string [GetStringValueFromTag](#) (const [Tag](#) &t, const [DataSet](#) &ds)
- static std::vector< [DataSet](#) > [LoadImageFromFiles](#) (const std::string &inDirectory, const std::string &inSeriesUID)
- static std::string [RetrieveSOPInstanceUIDFromIndex](#) (int inIndex, const std::vector< [DataSet](#) > &inDS)
- static std::string [RetrieveSOPInstanceUIDFromZPosition](#) (double inZPos, const std::vector< [DataSet](#) > &inDS)

10.93.1 Detailed Description

[DirectoryHelper](#).

this class is designed to help mitigate some of the commonly performed operations on directories. namely: 1) the ability to determine the number of series in a directory by what type of series is present 2) the ability to find all ct series in a directory 3) the ability to find all mr series in a directory 4) to load a set of DataSets from a series that's already been sorted by the IPP sorter 5) For rtstruct stuff, you need to know the sopinstanceuid of each z plane, so there's a retrieval function for that 6) then a few other functions for rtstruct writeouts

10.93.2 Member Function Documentation

10.93.2.1 GetCTImageSeriesUIDs()

```
Directory::FilenamesType gdcm::DirectoryHelper::GetCTImageSeriesUIDs (
    const std::string & inDirectory) [static]
```

10.93.2.2 GetFileNamesFromSeriesUIDs()

```
Directory::FilenamesType gdcm::DirectoryHelper::GetFileNamesFromSeriesUIDs (
    const std::string & inDirectory,
    const std::string & inSeriesUID) [static]
```

Examples

[GenerateRTSTRUCT.cxx](#).

10.93.2.3 GetFrameOfReference()

```
std::string gdcm::DirectoryHelper::GetFrameOfReference (
    const std::vector< DataSet > & inDS) [static]
```

10.93.2.4 GetMRImageSeriesUIDs()

```
Directory::FilenamesType gdcm::DirectoryHelper::GetMRImageSeriesUIDs (
    const std::string & inDirectory) [static]
```

10.93.2.5 GetRTStructSeriesUIDs()

```
Directory::FilenamesType gdcm::DirectoryHelper::GetRTStructSeriesUIDs (
    const std::string & inDirectory) [static]
```

Examples

[GenerateRTSTRUCT.cxx.](#)

10.93.2.6 GetSeriesUIDsBySOPClassUID()

```
Directory::FilenamesType gdcm::DirectoryHelper::GetSeriesUIDsBySOPClassUID (
    const std::string & inDirectory,
    const std::string & inSOPClassUID) [static]
```

10.93.2.7 GetSOPClassUID()

```
std::string gdcm::DirectoryHelper::GetSOPClassUID (
    const std::vector< DataSet > & inDS) [static]
```

10.93.2.8 GetStringValueFromTag()

```
std::string gdcm::DirectoryHelper::GetStringValueFromTag (
    const Tag & t,
    const DataSet & ds) [static]
```

10.93.2.9 LoadImageFromFiles()

```
std::vector< DataSet > gdcm::DirectoryHelper::LoadImageFromFiles (
    const std::string & inDirectory,
    const std::string & inSeriesUID) [static]
```

10.93.2.10 RetrieveSOPInstanceUIDFromIndex()

```
std::string gdcm::DirectoryHelper::RetrieveSOPInstanceUIDFromIndex (
    int inIndex,
    const std::vector< DataSet > & inDS) [static]
```

10.93.2.11 RetrieveSOPInstanceUIDFromZPosition()

```
std::string gdcm::DirectoryHelper::RetrieveSOPInstanceUIDFromZPosition (
    double inZPos,
    const std::vector< DataSet > & inDS) [static]
```

The documentation for this class was generated from the following file:

- [gdcmDirectoryHelper.h](#)

10.94 gdcm::DPath Class Reference

class to handle a DICOM path While supp 118 did introduced a notion of XPath for XML Native model this convention is too XML-centric. Instead prefer DCMTK style notation <https://groups.google.com/g/comp.protocols.dicom/c/IyIH0IOBMPA>

```
#include <gdcmDPath.h>
```

Public Member Functions

- [DPath](#) ()
- [~DPath](#) ()
- bool [ConstructFromString](#) (const char *path)
- bool [Match](#) ([DPath](#) const &other) const
Return whether or not 'other' match the template [DPath](#).
- bool [operator<](#) (const [DPath](#) &rhs) const
- void [Print](#) (std::ostream &) const

Static Public Member Functions

- static bool [IsValid](#) (const char *path)
Return if path is valid or not.

Friends

- std::ostream & [operator<<](#) (std::ostream &_os, const [DPath](#) &_val)

10.94.1 Detailed Description

class to handle a DICOM path While supp 118 did introduced a notion of XPath for XML Native model this convention is too XML-centric. Instead prefer DCMTK style notation [https://groups.google.com/g/comp.↵protocols.dicom/c/IyIH0IOBMPA](https://groups.google.com/g/comp.protocols.dicom/c/IyIH0IOBMPA)

10.94.2 Constructor & Destructor Documentation

10.94.2.1 DPath()

```
gdcm::DPath::DPath ()
```

Referenced by [Match\(\)](#), [operator<\(\)](#), and [operator<<](#).

10.94.2.2 ~DPath()

```
gdcm::DPath::~~DPath ()
```

10.94.3 Member Function Documentation

10.94.3.1 ConstructFromString()

```
bool gdcm::DPath::ConstructFromString (
    const char * path)
```

Examples

[Cleaner.cs](#).

10.94.3.2 IsValid()

```
bool gdcm::DPath::IsValid (
    const char * path) [static]
```

Return if path is valid or not.

10.94.3.3 Match()

```
bool gdcm::DPath::Match (
    DPath const & other) const
```

Return whether or not 'other' match the template [DPath](#).

References [DPath\(\)](#).

10.94.3.4 operator<()

```
bool gdcm::DPath::operator< (
    const DPath & rhs) const
```

References [DPath\(\)](#).

10.94.3.5 Print()

```
void gdcm::DPath::Print (
    std::ostream & ) const
```

10.94.4 Friends And Related Symbol Documentation

10.94.4.1 operator<<

```
std::ostream & operator<< (
    std::ostream & _os,
    const DPath & _val) [friend]
```

References [DPath\(\)](#).

The documentation for this class was generated from the following file:

- [gdcmDPath.h](#)

10.95 gdcm::DummyValueGenerator Class Reference

Class for generating dummy value.

```
#include <gdcmDummyValueGenerator.h>
```

Static Public Member Functions

- static const char * [Generate](#) (const char *input)

10.95.1 Detailed Description

Class for generating dummy value.

See also

[Anonymizer](#)

10.95.2 Member Function Documentation

10.95.2.1 Generate()

```
const char * gdcm::DummyValueGenerator::Generate (  
    const char * input)    [static]
```

Generate a dummy value from an input value. This is guarantee to always return the same output value when input is identical. Return an array of bytes that can be used for anonymization purpose, return NULL on error NOT THREAD SAFE

The documentation for this class was generated from the following file:


- [gdcmDummyValueGenerator.h](#)

10.96 gdcm::Dumper Class Reference


[Codec](#) class.

```
#include <gdcmDumper.h>
```

Inheritance diagram for gdcm::Dumper:



Collaboration diagram for gdcmm::Dumper:



Public Member Functions

- [Dumper](#) ()
- [~Dumper](#) ()=default

Public Member Functions inherited from [gdcmm::Printer](#)

- [Printer](#) ()
- [~Printer](#) ()=default
- [PrintStyles GetPrintStyle](#) () const
Get PrintStyle value.
- void [Print](#) (std::ostream &os)
Print.
- void [PrintDataSet](#) (const [DataSet](#) &ds, std::ostream &os, const std::string &s="")
Print an individual dataset.
- void [SetColor](#) (bool c)
Set color mode or not.
- void [SetFile](#) ([File](#) const &f)
Set file.
- void [SetStyle](#) ([PrintStyles](#) ps)
Set PrintStyle value.

Additional Inherited Members

Public Types inherited from [gdcm::Printer](#)

- enum [PrintStyles](#) {
[VERBOSE_STYLE](#) = 0 ,
[CONDENSED_STYLE](#) ,
[XML](#) ,
[CXX](#) }

Protected Member Functions inherited from [gdcm::Printer](#)

- [VR PrintDataElement](#) (std::ostream &os, const [Dicts](#) &dicts, const [DataSet](#) &ds, const [DataElement](#) &de, std::ostream &out, std::string const &indent)
- void [PrintSQ](#) (const [SequenceOfItems](#) *sqi, std::ostream &os, std::string const &indent)

Protected Attributes inherited from [gdcm::Printer](#)

- const [File](#) * [F](#)
- [VL MaxPrintLength](#)
- [PrintStyles](#) [PrintStyle](#)

10.96.1 Detailed Description

[Codec](#) class.

Note

Use it to simply dump value read from the file. No interpretation is done. But it is real fast ! Almost no overhead

10.96.2 Constructor & Destructor Documentation

10.96.2.1 [Dumper\(\)](#)

```
gdcm::Dumper::Dumper () [inline]
```

References [gdcm::Printer::CONDENSED_STYLE](#), and [gdcm::Printer::PrintStyle](#).

10.96.2.2 [~Dumper\(\)](#)

```
gdcm::Dumper::~Dumper () [default]
```

The documentation for this class was generated from the following file:


- [gdcmDumper.h](#)

10.97 gdcmm::Element< TVR, TVM > Class Template Reference


[Element](#) class.

```
#include <gdcmmElement.h>
```

Inheritance diagram for gdcmm::Element< TVR, TVM >:



Collaboration diagram for `gdcm::Element< TVR, TVM >`:



Public Types

- typedef `VRTToType< TVR >::Type` `Type`

Public Member Functions

- `DataElement GetAsDataElement ()` const
- unsigned long `GetLength ()` const
- `VRTToType< TVR >::Type & GetValue` (unsigned int idx=0)
- const `VRTToType< TVR >::Type & GetValue` (unsigned int idx=0) const
- const `VRTToType< TVR >::Type * GetValues ()` const
- `VRTToType< TVR >::Type operator[]` (unsigned int idx) const
- void `Print` (std::ostream &_os) const
- void `Read` (std::istream &_is)
- void `Set` (Value const &v)
- void `SetFromDataElement` (DataElement const &de)
- void `SetValue` (typename `VRTToType< TVR >::Type` v, unsigned int idx=0)
- void `Write` (std::ostream &_os) const

Static Public Member Functions

- static `VM GetVM ()`
- static `VR GetVR ()`

Public Attributes

- [VRToType](#)< TVR >::Type [Internal](#) [[VMToLength](#)< TVM >::Length]

Protected Member Functions

- void [SetNoSwap](#) ([Value](#) const &v)

10.97.1 Detailed Description

```
template<long long TVR, int TVM>
class gdcm::Element< TVR, TVM >
```

[Element](#) class.

Note

TODO

Examples

[DumpADAC.cxx](#), [DumpExamCard.cxx](#), [DumpGEMSMovieGroup.cxx](#), [DumpPhilipsECHO.cxx](#), [Extracting_All_Resolution.cxx](#), [Fake_Image_Using_Stream_Image_Writer.cxx](#), [GetSubSequenceData.cxx](#), [csa2img.cxx](#), and [iU22tomultisc.cxx](#).

10.97.2 Member Typedef Documentation

10.97.2.1 Type

```
template<long long TVR, int TVM>
typedef VRToType<TVR>::Type gdcm::Element< TVR, TVM >::Type
```

10.97.3 Member Function Documentation

10.97.3.1 GetAsDataElement()

```
template<long long TVR, int TVM>
DataElement gdcm::Element< TVR, TVM >::GetAsDataElement () const [inline]
```

Examples

[Extracting_All_Resolution.cxx](#), and [Fake_Image_Using_Stream_Image_Writer.cxx](#).

References [gdcm_assert](#), [GetLength\(\)](#), [gdcm::DataElement::GetVR\(\)](#), [GetVR\(\)](#), [Internal](#), [gdcm::DataElement::SetByteValue\(\)](#), [gdcm::DataElement::SetVR\(\)](#), [gdcm::VR::SQ](#), [gdcm::VR::UI](#), [gdcm::VR::VRASCII](#), and [Write\(\)](#).

10.97.3.2 GetLength()

```
template<long long TVR, int TVM>
unsigned long gdc<::Element< TVR, TVM >::GetLength () const [inline]
```

Examples

[DumpGEMSMovieGroup.cxx](#), and [GetSubSequenceData.cxx](#).

Referenced by [GetAsDataElement\(\)](#), [Read\(\)](#), [Set\(\)](#), [SetNoSwap\(\)](#), and [Write\(\)](#).

10.97.3.3 GetValue() [1/2]

```
template<long long TVR, int TVM>
VRToType< TVR >::Type & gdc<::Element< TVR, TVM >::GetValue (
    unsigned int idx = 0) [inline]
```

References [gdc<::assert](#), and [Internal](#).

10.97.3.4 GetValue() [2/2]

```
template<long long TVR, int TVM>
const VRToType< TVR >::Type & gdc<::Element< TVR, TVM >::GetValue (
    unsigned int idx = 0) const [inline]
```

Examples

[DumpADAC.cxx](#), [DumpExamCard.cxx](#), [DumpGEMSMovieGroup.cxx](#), [DumpPhilipsECHO.cxx](#), [GetSubSequenceData.cxx](#), and [csa2img.cxx](#).

References [gdc<::assert](#), and [Internal](#).

Referenced by [operator\[\]\(\)](#).

10.97.3.5 GetValues()

```
template<long long TVR, int TVM>
const VRToType< TVR >::Type * gdc<::Element< TVR, TVM >::GetValues () const [inline]
```

References [Internal](#).

10.97.3.6 GetVM()

```
template<long long TVR, int TVM>
VM gdc<::Element< TVR, TVM >::GetVM () [inline], [static]
```

10.97.3.7 GetVR()

```
template<long long TVR, int TVM>
VR gdcmm::Element< TVR, TVM >::GetVR () [inline], [static]
```

Referenced by [GetAsDataElement\(\)](#).

10.97.3.8 operator[]()

```
template<long long TVR, int TVM>
VRToType< TVR >::Type gdcmm::Element< TVR, TVM >::operator[] (
    unsigned int idx) const [inline]
```

References [GetValue\(\)](#).

10.97.3.9 Print()

```
template<long long TVR, int TVM>
void gdcmm::Element< TVR, TVM >::Print (
    std::ostream & _os) const [inline]
```

Examples

[DumpGEMSMovieGroup.cxx](#).

References [Internal](#).

10.97.3.10 Read()

```
template<long long TVR, int TVM>
void gdcmm::Element< TVR, TVM >::Read (
    std::istream & _is) [inline]
```

References [GetLength\(\)](#), [Internal](#), and [Read\(\)](#).

Referenced by [Read\(\)](#), and [Set\(\)](#).

10.97.3.11 Set()

```
template<long long TVR, int TVM>
void gdcmm::Element< TVR, TVM >::Set (
    Value const & v) [inline]
```

Examples

[csa2img.cxx](#).

References [gdcmm::ByteValue::GetLength\(\)](#), [GetLength\(\)](#), [gdcmm::ByteValue::GetPointer\(\)](#), [Internal](#), and [Read\(\)](#).

Referenced by [SetFromDataElement\(\)](#).

10.97.3.12 SetFromDataElement()

```
template<long long TVR, int TVM>
void gdcm::Element< TVR, TVM >::SetFromDataElement (
    DataElement< TVR, TVM > const & de) [inline]
```

Examples

[DumpADAC.cxx](#), [DumpExamCard.cxx](#), [DumpGEMSMovieGroup.cxx](#), [DumpPhilipsECHO.cxx](#), [GetSubSequenceData.cxx](#), and [iU22tomultisc.cxx](#).

References [gdcm::DataElement::GetByteValue\(\)](#), [gdcm::DataElement::GetValue\(\)](#), [gdcm::DataElement::GetVR\(\)](#), [gdcm::VR::INVALID](#), [Set\(\)](#), [SetNoSwap\(\)](#), and [gdcm::VR::UN](#).

10.97.3.13 SetNoSwap()

```
template<long long TVR, int TVM>
void gdcm::Element< TVR, TVM >::SetNoSwap (
    Value const & v) [inline], [protected]
```

References [gdcm_assert](#), [gdcm::ByteValue::GetLength\(\)](#), [GetLength\(\)](#), [gdcm::ByteValue::GetPointer\(\)](#), and [Internal](#).

Referenced by [SetFromDataElement\(\)](#).

10.97.3.14 SetValue()

```
template<long long TVR, int TVM>
void gdcm::Element< TVR, TVM >::SetValue (
    typename VRToType< TVR >::Type v,
    unsigned int idx = 0) [inline]
```

Examples

[Extracting_All_Resolution.cxx](#), and [Fake_Image_Using_Stream_Image_Writer.cxx](#).

References [gdcm_assert](#), and [Internal](#).

10.97.3.15 Write()

```
template<long long TVR, int TVM>
void gdcm::Element< TVR, TVM >::Write (
    std::ostream & _os) const [inline]
```

References [GetLength\(\)](#), [Internal](#), and [Write\(\)](#).

Referenced by [GetAsDataElement\(\)](#), and [Write\(\)](#).

10.97.4 Member Data Documentation

10.97.4.1 Internal

```
template<long long TVR, int TVM>  
VRToType<TVR>::Type gdcm::Element< TVR, TVM >::Internal[VMToLength< TVM >::Length]
```

Referenced by [GetAsDataElement\(\)](#), [GetValue\(\)](#), [GetValue\(\)](#), [GetValues\(\)](#), [Print\(\)](#), [Read\(\)](#), [Set\(\)](#), [SetNoSwap\(\)](#), [SetValue\(\)](#), and [Write\(\)](#).


The documentation for this class was generated from the following file:

- [gdcmElement.h](#)


10.98 gdcm::Element< TVR, VM::VM1_2 > Class Template Reference

```
#include <gdcmElement.h>
```

Inheritance diagram for gdcm::Element< TVR, VM::VM1_2 >:



Collaboration diagram for `gdcm::Element< TVR, VM::VM1_2 >`:



Public Types

- typedef `Element< TVR, VM::VM1_n >` `Parent`
- typedef `VRTToType< TVR >::Type` `Type`

Public Types inherited from `gdcm::Element< TVR, TVM >`

- typedef `VRTToType< TVR >::Type` `Type`

Public Member Functions

- `DataElement GetAsDataElement ()` const
- unsigned long `GetLength ()` const
- const `VRTToType< TVR >::Type & GetValue` (unsigned int idx=0) const
- const `VRTToType< TVR >::Type * GetValues ()` const
- `VRTToType< TVR >::Type operator[]` (unsigned int idx) const
- void `Print` (std::ostream &_os) const
- void `Read` (std::istream &_is)

- void [Set](#) ([Value](#) const &v)
- void [SetFromDataElement](#) ([DataElement](#) const &de)
- void [SetLength](#) (int len)
- void [SetValue](#) (typename [VRToType](#)< TVR >::Type v, unsigned int idx=0)
- void [Write](#) (std::ostream &_os) const

Public Member Functions inherited from [gdcm::Element](#)< TVR, TVM >

- [DataElement](#) [GetAsDataElement](#) () const
- unsigned long [GetLength](#) () const
- [VRToType](#)< TVR >::Type & [GetValue](#) (unsigned int idx=0)
- const [VRToType](#)< TVR >::Type & [GetValue](#) (unsigned int idx=0) const
- const [VRToType](#)< TVR >::Type * [GetValues](#) () const
- [VRToType](#)< TVR >::Type [operator\[\]](#) (unsigned int idx) const
- void [Print](#) (std::ostream &_os) const
- void [Read](#) (std::istream &_is)
- void [Set](#) ([Value](#) const &v)
- void [SetFromDataElement](#) ([DataElement](#) const &de)
- void [SetValue](#) (typename [VRToType](#)< TVR >::Type v, unsigned int idx=0)
- void [Write](#) (std::ostream &_os) const

Static Public Member Functions

- static [VM](#) [GetVM](#) ()
- static [VR](#) [GetVR](#) ()

Static Public Member Functions inherited from [gdcm::Element](#)< TVR, TVM >

- static [VM](#) [GetVM](#) ()
- static [VR](#) [GetVR](#) ()

Public Attributes

- [VRToType](#)< TVR >::Type [Internal](#) [[VMToLength](#)< TVM >::Length]

Public Attributes inherited from [gdcm::Element](#)< TVR, TVM >

- [VRToType](#)< TVR >::Type [Internal](#) [[VMToLength](#)< TVM >::Length]

Protected Member Functions

- void [SetNoSwap](#) ([Value](#) const &v)

Protected Member Functions inherited from [gdcm::Element< TVR, TVM >](#)

- void [SetNoSwap](#) (Value const &v)

10.98.1 Member Typedef Documentation

10.98.1.1 Parent

```
template<long long TVR>
typedef Element<TVR, VM::VM1_n> gdcm::Element< TVR, VM::VM1_2 >::Parent
```

10.98.1.2 Type

```
typedef VRToType<TVR>::Type gdcm::Element< TVR, TVM >::Type
```

10.98.2 Member Function Documentation

10.98.2.1 GetAsDataElement()

```
DataElement gdcm::Element< TVR, TVM >::GetAsDataElement () const [inline]
```

10.98.2.2 GetLength()

```
unsigned long gdcm::Element< TVR, TVM >::GetLength () const [inline]
```

10.98.2.3 GetValue()

```
const VRToType< TVR >::Type & gdcm::Element< TVR, TVM >::GetValue (
    unsigned int idx = 0) const [inline]
```

10.98.2.4 GetValues()

```
const VRToType< TVR >::Type * gdcm::Element< TVR, TVM >::GetValues () const [inline]
```

10.98.2.5 GetVM()

```
VM gdcm::Element< TVR, TVM >::GetVM () [inline], [static]
```

10.98.2.6 GetVR()

```
VR gdcmm::Element< TVR, TVM >::GetVR () [inline], [static]
```

10.98.2.7 operator[]()

```
VRToType< TVR >::Type gdcmm::Element< TVR, TVM >::operator[] (
    unsigned int idx) const [inline]
```

10.98.2.8 Print()

```
void gdcmm::Element< TVR, TVM >::Print (
    std::ostream & _os) const [inline]
```

10.98.2.9 Read()

```
void gdcmm::Element< TVR, TVM >::Read (
    std::istream & _is) [inline]
```

10.98.2.10 Set()

```
void gdcmm::Element< TVR, TVM >::Set (
    Value const & v) [inline]
```

10.98.2.11 SetFromDataElement()

```
void gdcmm::Element< TVR, TVM >::SetFromDataElement (
    DataElement< TVR, VM::VM1_2 > const & de) [inline]
```

10.98.2.12 SetLength()

```
template<long long TVR>
void gdcmm::Element< TVR, VM::VM1_2 >::SetLength (
    int len) [inline]
```

10.98.2.13 SetNoSwap()

```
void gdcmm::Element< TVR, TVM >::SetNoSwap (
    Value const & v) [inline], [protected]
```

10.98.2.14 SetValue()

```
void gdcM::Element< TVR, TVM >::SetValue (
    typename VRToType< TVR >::Type v,
    unsigned int idx = 0) [inline]
```

10.98.2.15 Write()

```
void gdcM::Element< TVR, TVM >::Write (
    std::ostream & _os) const [inline]
```

10.98.3 Member Data Documentation

10.98.3.1 Internal

```
VRToType<TVR>::Type gdcM::Element< TVR, TVM >::Internal[VMToLength< TVM >::Length]
```


The documentation for this class was generated from the following file:

- [gdcMElement.h](#)


10.99 gdcM::Element< TVR, VM::VM2_2n > Class Template Reference

```
#include <gdcMElement.h>
```

Inheritance diagram for gdcM::Element< TVR, VM::VM2_2n >:



Collaboration diagram for gdcm::Element< TVR, VM::VM2_2n >:



Public Types

- typedef `Element< TVR, VM::VM2_n > Parent`
- typedef `VRTToType< TVR >::Type Type`

Public Types inherited from `gdcm::Element< TVR, TVM >`

- typedef `VRTToType< TVR >::Type Type`

Public Member Functions

- `DataElement GetAsDataElement () const`
- `unsigned long GetLength () const`
- `const VRTToType< TVR >::Type & GetValue (unsigned int idx=0) const`
- `const VRTToType< TVR >::Type * GetValues () const`
- `VRTToType< TVR >::Type operator[] (unsigned int idx) const`
- `void Print (std::ostream &_os) const`
- `void Read (std::istream &_is)`

- void [Set](#) ([Value](#) const &v)
- void [SetFromDataElement](#) ([DataElement](#) const &de)
- void [SetLength](#) (int len)
- void [SetValue](#) (typename [VRToType](#)< TVR >::Type v, unsigned int idx=0)
- void [Write](#) (std::ostream &_os) const

Public Member Functions inherited from [gdcm::Element](#)< TVR, TVM >

- [DataElement](#) [GetAsDataElement](#) () const
- unsigned long [GetLength](#) () const
- [VRToType](#)< TVR >::Type & [GetValue](#) (unsigned int idx=0)
- const [VRToType](#)< TVR >::Type & [GetValue](#) (unsigned int idx=0) const
- const [VRToType](#)< TVR >::Type * [GetValues](#) () const
- [VRToType](#)< TVR >::Type [operator\[\]](#) (unsigned int idx) const
- void [Print](#) (std::ostream &_os) const
- void [Read](#) (std::istream &_is)
- void [Set](#) ([Value](#) const &v)
- void [SetFromDataElement](#) ([DataElement](#) const &de)
- void [SetValue](#) (typename [VRToType](#)< TVR >::Type v, unsigned int idx=0)
- void [Write](#) (std::ostream &_os) const

Static Public Member Functions

- static [VM](#) [GetVM](#) ()
- static [VR](#) [GetVR](#) ()

Static Public Member Functions inherited from [gdcm::Element](#)< TVR, TVM >

- static [VM](#) [GetVM](#) ()
- static [VR](#) [GetVR](#) ()

Public Attributes

- [VRToType](#)< TVR >::Type [Internal](#) [[VMToLength](#)< TVM >::Length]

Public Attributes inherited from [gdcm::Element](#)< TVR, TVM >

- [VRToType](#)< TVR >::Type [Internal](#) [[VMToLength](#)< TVM >::Length]

Protected Member Functions

- void [SetNoSwap](#) ([Value](#) const &v)

Protected Member Functions inherited from [gdcmm::Element< TVR, TVM >](#)

- void [SetNoSwap](#) (Value const &v)

10.99.1 Member Typedef Documentation**10.99.1.1 Parent**

```
template<long long TVR>
typedef Element<TVR, VM::VM2_n> gdcmm::Element< TVR, VM::VM2_2n >::Parent
```

10.99.1.2 Type

```
typedef VRToType<TVR>::Type gdcmm::Element< TVR, TVM >::Type
```

10.99.2 Member Function Documentation**10.99.2.1 GetAsDataElement()**

```
DataElement gdcmm::Element< TVR, TVM >::GetAsDataElement () const [inline]
```

10.99.2.2 GetLength()

```
unsigned long gdcmm::Element< TVR, TVM >::GetLength () const [inline]
```

10.99.2.3 GetValue()

```
const VRToType< TVR >::Type & gdcmm::Element< TVR, TVM >::GetValue (
    unsigned int idx = 0) const [inline]
```

10.99.2.4 GetValues()

```
const VRToType< TVR >::Type * gdcmm::Element< TVR, TVM >::GetValues () const [inline]
```

10.99.2.5 GetVM()

```
VM gdcmm::Element< TVR, TVM >::GetVM () [inline], [static]
```

10.99.2.6 GetVR()

```
VR gdcmm::Element< TVR, TVM >::GetVR () [inline], [static]
```

10.99.2.7 operator[]()

```
VRToType< TVR >::Type gdcmm::Element< TVR, TVM >::operator[] (
    unsigned int idx) const [inline]
```

10.99.2.8 Print()

```
void gdcmm::Element< TVR, TVM >::Print (
    std::ostream & _os) const [inline]
```

10.99.2.9 Read()

```
void gdcmm::Element< TVR, TVM >::Read (
    std::istream & _is) [inline]
```

10.99.2.10 Set()

```
void gdcmm::Element< TVR, TVM >::Set (
    Value const & v) [inline]
```

10.99.2.11 SetFromDataElement()

```
void gdcmm::Element< TVR, TVM >::SetFromDataElement (
    DataElement< TVR, VM::VM2_2n > const & de) [inline]
```

10.99.2.12 SetLength()

```
template<long long TVR>
void gdcmm::Element< TVR, VM::VM2_2n >::SetLength (
    int len) [inline]
```

10.99.2.13 SetNoSwap()

```
void gdcmm::Element< TVR, TVM >::SetNoSwap (
    Value const & v) [inline], [protected]
```

10.99.2.14 SetValue()

```
void gdcmm::Element< TVR, TVM >::SetValue (
    typename VRToType< TVR >::Type v,
    unsigned int idx = 0) [inline]
```

10.99.2.15 Write()

```
void gdcmm::Element< TVR, TVM >::Write (
    std::ostream & _os) const [inline]
```

10.99.3 Member Data Documentation**10.99.3.1 Internal**

```
VRToType<TVR>::Type gdcmm::Element< TVR, TVM >::Internal[VMToLength< TVM >::Length]
```


The documentation for this class was generated from the following file:

- [gdcmmElement.h](#)


10.100 gdcmm::Element< TVR, VM::VM3_3n > Class Template Reference

```
#include <gdcmmElement.h>
```

Inheritance diagram for gdcmm::Element< TVR, VM::VM3_3n >:



Collaboration diagram for `gdcm::Element< TVR, VM::VM3_3n >`:



Public Types

- typedef `Element< TVR, VM::VM3_n >` `Parent`
- typedef `VRTToType< TVR >::Type` `Type`

Public Types inherited from `gdcm::Element< TVR, TVM >`

- typedef `VRTToType< TVR >::Type` `Type`

Public Member Functions

- `DataElement GetAsDataElement ()` const
- unsigned long `GetLength ()` const
- const `VRTToType< TVR >::Type` & `GetValue` (unsigned int idx=0) const
- const `VRTToType< TVR >::Type` * `GetValues ()` const
- `VRTToType< TVR >::Type` `operator[]` (unsigned int idx) const
- void `Print` (std::ostream &_os) const
- void `Read` (std::istream &_is)

- void [Set](#) ([Value](#) const &v)
- void [SetFromDataElement](#) ([DataElement](#) const &de)
- void [SetLength](#) (int len)
- void [SetValue](#) (typename [VRToType](#)< TVR >::Type v, unsigned int idx=0)
- void [Write](#) (std::ostream &_os) const

Public Member Functions inherited from [gdcm::Element< TVR, TVM >](#)

- [DataElement](#) [GetAsDataElement](#) () const
- unsigned long [GetLength](#) () const
- [VRToType](#)< TVR >::Type & [GetValue](#) (unsigned int idx=0)
- const [VRToType](#)< TVR >::Type & [GetValue](#) (unsigned int idx=0) const
- const [VRToType](#)< TVR >::Type * [GetValues](#) () const
- [VRToType](#)< TVR >::Type [operator\[\]](#) (unsigned int idx) const
- void [Print](#) (std::ostream &_os) const
- void [Read](#) (std::istream &_is)
- void [Set](#) ([Value](#) const &v)
- void [SetFromDataElement](#) ([DataElement](#) const &de)
- void [SetValue](#) (typename [VRToType](#)< TVR >::Type v, unsigned int idx=0)
- void [Write](#) (std::ostream &_os) const

Static Public Member Functions

- static [VM](#) [GetVM](#) ()
- static [VR](#) [GetVR](#) ()

Static Public Member Functions inherited from [gdcm::Element< TVR, TVM >](#)

- static [VM](#) [GetVM](#) ()
- static [VR](#) [GetVR](#) ()

Public Attributes

- [VRToType](#)< TVR >::Type [Internal](#) [[VMToLength](#)< TVM >::Length]

Public Attributes inherited from [gdcm::Element< TVR, TVM >](#)

- [VRToType](#)< TVR >::Type [Internal](#) [[VMToLength](#)< TVM >::Length]

Protected Member Functions

- void [SetNoSwap](#) ([Value](#) const &v)

Protected Member Functions inherited from [gdcm::Element< TVR, TVM >](#)

- void [SetNoSwap](#) (Value const &v)

10.100.1 Member Typedef Documentation

10.100.1.1 Parent

```
template<long long TVR>
typedef Element<TVR, VM::VM3\_n> gdcm::Element< TVR, VM::VM3\_3n >::Parent
```

10.100.1.2 Type

```
typedef VRToType<TVR>::Type gdcm::Element< TVR, TVM >::Type
```

10.100.2 Member Function Documentation

10.100.2.1 GetAsDataElement()

```
DataElement gdcm::Element< TVR, TVM >::GetAsDataElement () const [inline]
```

10.100.2.2 GetLength()

```
unsigned long gdcm::Element< TVR, TVM >::GetLength () const [inline]
```

10.100.2.3 GetValue()

```
const VRToType< TVR >::Type & gdcm::Element< TVR, TVM >::GetValue (
    unsigned int idx = 0) const [inline]
```

10.100.2.4 GetValues()

```
const VRToType< TVR >::Type * gdcm::Element< TVR, TVM >::GetValues () const [inline]
```

10.100.2.5 GetVM()

```
VM gdcm::Element< TVR, TVM >::GetVM () [inline], [static]
```

10.100.2.6 GetVR()

```
VR gdcmm::Element< TVR, TVM >::GetVR () [inline], [static]
```

10.100.2.7 operator[]()

```
VRToType< TVR >::Type gdcmm::Element< TVR, TVM >::operator[] (
    unsigned int idx) const [inline]
```

10.100.2.8 Print()

```
void gdcmm::Element< TVR, TVM >::Print (
    std::ostream & _os) const [inline]
```

10.100.2.9 Read()

```
void gdcmm::Element< TVR, TVM >::Read (
    std::istream & _is) [inline]
```

10.100.2.10 Set()

```
void gdcmm::Element< TVR, TVM >::Set (
    Value const & v) [inline]
```

10.100.2.11 SetFromDataElement()

```
void gdcmm::Element< TVR, TVM >::SetFromDataElement (
    DataElement< TVR, VM::VM3_3n > const & de) [inline]
```

10.100.2.12 SetLength()

```
template<long long TVR>
void gdcmm::Element< TVR, VM::VM3_3n >::SetLength (
    int len) [inline]
```

10.100.2.13 SetNoSwap()

```
void gdcmm::Element< TVR, TVM >::SetNoSwap (
    Value const & v) [inline], [protected]
```

10.100.2.14 SetValue()

```
void gdcM::Element< TVR, TVM >::SetValue (
    typename VRToType< TVR >::Type v,
    unsigned int idx = 0) [inline]
```

10.100.2.15 Write()

```
void gdcM::Element< TVR, TVM >::Write (
    std::ostream & _os) const [inline]
```

10.100.3 Member Data Documentation

10.100.3.1 Internal

```
VRToType<TVR>::Type gdcM::Element< TVR, TVM >::Internal[VMToLength< TVM >::Length]
```


The documentation for this class was generated from the following file:

- [gdcMElement.h](#)


10.101 gdcM::Element< TVR, VM::VM3_4 > Class Template Reference

```
#include <gdcMElement.h>
```

Inheritance diagram for gdcM::Element< TVR, VM::VM3_4 >:



Collaboration diagram for gdcm::Element< TVR, VM::VM3_4 >:



Public Types

- typedef `Element< TVR, VM::VM1_n > Parent`
- typedef `VRTToType< TVR >::Type Type`

Public Types inherited from `gdcm::Element< TVR, TVM >`

- typedef `VRTToType< TVR >::Type Type`

Public Member Functions

- `DataElement GetAsDataElement () const`
- `unsigned long GetLength () const`
- `const VRTToType< TVR >::Type & GetValue (unsigned int idx=0) const`
- `const VRTToType< TVR >::Type * GetValues () const`
- `VRTToType< TVR >::Type operator[] (unsigned int idx) const`
- `void Print (std::ostream &_os) const`
- `void Read (std::istream &_is)`

- void [Set](#) ([Value](#) const &v)
- void [SetFromDataElement](#) ([DataElement](#) const &de)
- void [SetLength](#) (int len)
- void [SetValue](#) (typename [VRToType](#)< TVR >::Type v, unsigned int idx=0)
- void [Write](#) (std::ostream &_os) const

Public Member Functions inherited from [gdcm::Element](#)< TVR, TVM >

- [DataElement](#) [GetAsDataElement](#) () const
- unsigned long [GetLength](#) () const
- [VRToType](#)< TVR >::Type & [GetValue](#) (unsigned int idx=0)
- const [VRToType](#)< TVR >::Type & [GetValue](#) (unsigned int idx=0) const
- const [VRToType](#)< TVR >::Type * [GetValues](#) () const
- [VRToType](#)< TVR >::Type [operator\[\]](#) (unsigned int idx) const
- void [Print](#) (std::ostream &_os) const
- void [Read](#) (std::istream &_is)
- void [Set](#) ([Value](#) const &v)
- void [SetFromDataElement](#) ([DataElement](#) const &de)
- void [SetValue](#) (typename [VRToType](#)< TVR >::Type v, unsigned int idx=0)
- void [Write](#) (std::ostream &_os) const

Static Public Member Functions

- static [VM](#) [GetVM](#) ()
- static [VR](#) [GetVR](#) ()

Static Public Member Functions inherited from [gdcm::Element](#)< TVR, TVM >

- static [VM](#) [GetVM](#) ()
- static [VR](#) [GetVR](#) ()

Public Attributes

- [VRToType](#)< TVR >::Type [Internal](#) [[VMToLength](#)< TVM >::Length]

Public Attributes inherited from [gdcm::Element](#)< TVR, TVM >

- [VRToType](#)< TVR >::Type [Internal](#) [[VMToLength](#)< TVM >::Length]

Protected Member Functions

- void [SetNoSwap](#) ([Value](#) const &v)

Protected Member Functions inherited from [gdcm::Element< TVR, TVM >](#)

- void [SetNoSwap](#) (Value const &v)

10.101.1 Member Typedef Documentation

10.101.1.1 Parent

```
template<long long TVR>
typedef Element<TVR, VM::VM1\_n> gdcm::Element< TVR, VM::VM3\_4 >::Parent
```

10.101.1.2 Type

```
typedef VRToType<TVR>::Type gdcm::Element< TVR, TVM >::Type
```

10.101.2 Member Function Documentation

10.101.2.1 GetAsDataElement()

```
DataElement gdcm::Element< TVR, TVM >::GetAsDataElement () const [inline]
```

10.101.2.2 GetLength()

```
unsigned long gdcm::Element< TVR, TVM >::GetLength () const [inline]
```

10.101.2.3 GetValue()

```
const VRToType< TVR >::Type & gdcm::Element< TVR, TVM >::GetValue (
    unsigned int idx = 0) const [inline]
```

10.101.2.4 GetValues()

```
const VRToType< TVR >::Type * gdcm::Element< TVR, TVM >::GetValues () const [inline]
```

10.101.2.5 GetVM()

```
VM gdcm::Element< TVR, TVM >::GetVM () [inline], [static]
```

10.101.2.6 GetVR()

```
VR gdcmm::Element< TVR, TVM >::GetVR () [inline], [static]
```

10.101.2.7 operator[]()

```
VRToType< TVR >::Type gdcmm::Element< TVR, TVM >::operator[] (
    unsigned int idx) const [inline]
```

10.101.2.8 Print()

```
void gdcmm::Element< TVR, TVM >::Print (
    std::ostream & _os) const [inline]
```

10.101.2.9 Read()

```
void gdcmm::Element< TVR, TVM >::Read (
    std::istream & _is) [inline]
```

10.101.2.10 Set()

```
void gdcmm::Element< TVR, TVM >::Set (
    Value const & v) [inline]
```

10.101.2.11 SetFromDataElement()

```
void gdcmm::Element< TVR, TVM >::SetFromDataElement (
    DataElement< TVR, VM::VM3_4 > const & de) [inline]
```

10.101.2.12 SetLength()

```
template<long long TVR>
void gdcmm::Element< TVR, VM::VM3_4 >::SetLength (
    int len) [inline]
```

10.101.2.13 SetNoSwap()

```
void gdcmm::Element< TVR, TVM >::SetNoSwap (
    Value const & v) [inline], [protected]
```

10.101.2.14 SetValue()

```
void gdcm::Element< TVR, TVM >::SetValue (
    typename VRToType< TVR >::Type v,
    unsigned int idx = 0) [inline]
```

10.101.2.15 Write()

```
void gdcm::Element< TVR, TVM >::Write (
    std::ostream & _os) const [inline]
```

10.101.3 Member Data Documentation**10.101.3.1 Internal**

```
VRToType<TVR>::Type gdcm::Element< TVR, TVM >::Internal[VMToLength< TVM >::Length]
```


The documentation for this class was generated from the following file:

- [gdcmElement.h](#)


10.102 gdcm::Element< VR::AS, VM::VM5 > Class Reference

```
#include <gdcmElement.h>
```

Inheritance diagram for gdcm::Element< VR::AS, VM::VM5 >:



Collaboration diagram for `gdcm::Element< VR::AS, VM::VM5 >`:



Public Types

- typedef `VRToType< TVR >::Type` `Type`

Public Member Functions

- `DataElement GetAsDataElement ()` const
- unsigned long `GetLength ()` const
- const `VRToType< TVR >::Type & GetValue (unsigned int idx=0)` const
- const `VRToType< TVR >::Type * GetValues ()` const
- `VRToType< TVR >::Type operator[] (unsigned int idx)` const
- void `Print (std::ostream &_os)` const
- void `Read (std::istream &_is)`
- void `Set (Value const &v)`
- void `SetFromDataElement (DataElement const &de)`
- void `SetValue (typename VRToType< TVR >::Type v, unsigned int idx=0)`
- void `Write (std::ostream &_os)` const

Static Public Member Functions

- static [VM GetVM](#) ()
- static [VR GetVR](#) ()

Public Attributes

- char [Internal](#) [[VMToLength](#)< [VM::VM5](#) >::Length *sizeof([VRToType](#)< [VR::AS](#) >::Type)]

Protected Member Functions

- void [SetNoSwap](#) ([Value](#) const &v)

10.102.1 Member Typedef Documentation

10.102.1.1 Type

```
typedef VRToType<TVR>::Type gdcm::Element< TVR, TVM >::Type
```

10.102.2 Member Function Documentation

10.102.2.1 GetAsDataElement()

```
DataElement gdcm::Element< TVR, TVM >::GetAsDataElement () const [inline]
```

10.102.2.2 GetLength()

```
unsigned long gdcm::Element< VR::AS, VM::VM5 >::GetLength () const [inline]
```

10.102.2.3 GetValue()

```
const VRToType< TVR >::Type & gdcm::Element< TVR, TVM >::GetValue (  
    unsigned int idx = 0) const [inline]
```

10.102.2.4 GetValues()

```
const VRToType< TVR >::Type * gdcm::Element< TVR, TVM >::GetValues () const [inline]
```

10.102.2.5 GetVM()

```
VM gdcmm::Element< TVR, TVM >::GetVM () [inline], [static]
```

10.102.2.6 GetVR()

```
VR gdcmm::Element< TVR, TVM >::GetVR () [inline], [static]
```

10.102.2.7 operator[]()

```
VRToType< TVR >::Type gdcmm::Element< TVR, TVM >::operator[] (
    unsigned int idx) const [inline]
```

10.102.2.8 Print()

```
void gdcmm::Element< VR::AS, VM::VM5 >::Print (
    std::ostream & _os) const [inline]
```

References [Internal](#).

10.102.2.9 Read()

```
void gdcmm::Element< TVR, TVM >::Read (
    std::istream & _is) [inline]
```

10.102.2.10 Set()

```
void gdcmm::Element< TVR, TVM >::Set (
    Value const & v) [inline]
```

10.102.2.11 SetFromDataElement()

```
void gdcmm::Element< TVR, TVM >::SetFromDataElement (
    DataElement< VR::AS, VM::VM5 > const & de) [inline]
```

10.102.2.12 SetNoSwap()

```
void gdcmm::Element< TVR, TVM >::SetNoSwap (
    Value const & v) [inline], [protected]
```


10.102.2.13 SetValue()

```
void gdcm::Element< TVR, TVM >::SetValue (
    typename VRToType< TVR >::Type v,
    unsigned int idx = 0) [inline]
```

10.102.2.14 Write()

```
void gdcm::Element< TVR, TVM >::Write (
    std::ostream & _os) const [inline]
```

10.102.3 Member Data Documentation**10.102.3.1 Internal**

```
char gdcm::Element< VR::AS, VM::VM5 >::Internal[VMToLength< VM::VM5 >::Length *sizeof(VRToType<
VR::AS >::Type)]
```

Referenced by [Print\(\)](#).


The documentation for this class was generated from the following file:

- [gdcmElement.h](#)


10.103 gdcm::Element< VR::OB, VM::VM1 > Class Reference

```
#include <gdcmElement.h>
```

Inheritance diagram for gdcm::Element< VR::OB, VM::VM1 >:



Collaboration diagram for `gdcM::Element< VR::OB, VM::VM1 >`:



Public Types

- typedef `VRToType< TVR >::Type` `Type`

Public Types inherited from `gdcM::Element< VR::OB, VM::VM1_n >`

- typedef `VRToType< TVR >::Type` `Type`

Public Member Functions

- `DataElement GetAsDataElement ()` const
- unsigned long `GetLength ()` const
- const `VRToType< TVR >::Type` & `GetValue` (unsigned int idx=0) const
- const `VRToType< TVR >::Type` * `GetValues ()` const
- `VRToType< TVR >::Type` `operator[]` (unsigned int idx) const

- void [Print](#) (std::ostream &_os) const
- void [Read](#) (std::istream &_is)
- void [Set](#) ([Value](#) const &v)
- void [SetFromDataElement](#) ([DataElement](#) const &de)
- void [SetValue](#) (typename [VRToType](#)< TVR >::Type v, unsigned int idx=0)
- void [Write](#) (std::ostream &_os) const

Public Member Functions inherited from [gdcm::Element< VR::OB, VM::VM1_n >](#)

- [DataElement](#) [GetAsDataElement](#) () const
- unsigned long [GetLength](#) () const
- const [VRToType](#)< TVR >::Type & [GetValue](#) (unsigned int idx=0) const
- const [VRToType](#)< TVR >::Type * [GetValues](#) () const
- [VRToType](#)< TVR >::Type [operator\[\]](#) (unsigned int idx) const
- void [Print](#) (std::ostream &_os) const
- void [Read](#) (std::istream &_is)
- void [Set](#) ([Value](#) const &v)
- void [SetFromDataElement](#) ([DataElement](#) const &de)
- void [SetValue](#) (typename [VRToType](#)< TVR >::Type v, unsigned int idx=0)
- void [Write](#) (std::ostream &_os) const

Static Public Member Functions

- static [VM](#) [GetVM](#) ()
- static [VR](#) [GetVR](#) ()

Static Public Member Functions inherited from [gdcm::Element< VR::OB, VM::VM1_n >](#)

- static [VM](#) [GetVM](#) ()
- static [VR](#) [GetVR](#) ()

Public Attributes

- [VRToType](#)< TVR >::Type [Internal](#) [[VMToLength](#)< TVM >::Length]

Public Attributes inherited from [gdcm::Element< VR::OB, VM::VM1_n >](#)

- [VRToType](#)< TVR >::Type [Internal](#) [[VMToLength](#)< TVM >::Length]

Protected Member Functions

- void [SetNoSwap](#) ([Value](#) const &v)

Protected Member Functions inherited from [gdcm::Element< VR::OB, VM::VM1_n >](#)

- void [SetNoSwap](#) (Value const &v)

10.103.1 Member Typedef Documentation

10.103.1.1 Type

```
typedef VRToType<TVR>::Type gdcm::Element< TVR, TVM >::Type
```

10.103.2 Member Function Documentation

10.103.2.1 GetAsDataElement()

```
DataElement gdcm::Element< TVR, TVM >::GetAsDataElement () const [inline]
```

10.103.2.2 GetLength()

```
unsigned long gdcm::Element< TVR, TVM >::GetLength () const [inline]
```

10.103.2.3 GetValue()

```
const VRToType< TVR >::Type & gdcm::Element< TVR, TVM >::GetValue (
    unsigned int idx = 0) const [inline]
```

10.103.2.4 GetValues()

```
const VRToType< TVR >::Type * gdcm::Element< TVR, TVM >::GetValues () const [inline]
```

10.103.2.5 GetVM()

```
VM gdcm::Element< TVR, TVM >::GetVM () [inline], [static]
```

10.103.2.6 GetVR()

```
VR gdcm::Element< TVR, TVM >::GetVR () [inline], [static]
```

10.103.2.7 operator[]()

```
VRToType< TVR >::Type gdcm::Element< TVR, TVM >::operator[] (
    unsigned int idx) const [inline]
```

10.103.2.8 Print()

```
void gdcm::Element< TVR, TVM >::Print (
    std::ostream & _os) const [inline]
```

10.103.2.9 Read()

```
void gdcm::Element< TVR, TVM >::Read (
    std::istream & _is) [inline]
```

10.103.2.10 Set()

```
void gdcm::Element< TVR, TVM >::Set (
    Value const & v) [inline]
```

10.103.2.11 SetFromDataElement()

```
void gdcm::Element< TVR, TVM >::SetFromDataElement (
    DataElement< VR::OB, VM::VM1 > const & de) [inline]
```

10.103.2.12 SetNoSwap()

```
void gdcm::Element< TVR, TVM >::SetNoSwap (
    Value const & v) [inline], [protected]
```

10.103.2.13 SetValue()

```
void gdcm::Element< TVR, TVM >::SetValue (
    typename VRToType< TVR >::Type v,
    unsigned int idx = 0) [inline]
```

10.103.2.14 Write()

```
void gdcm::Element< TVR, TVM >::Write (
    std::ostream & _os) const [inline]
```

10.103.3 Member Data Documentation

10.103.3.1 Internal

```
VRToType<TVR>::Type gdcM::Element< TVR, TVM >::Internal[VMToLength< TVM >::Length]
```


The documentation for this class was generated from the following file:

- [gdcMElement.h](#)


10.104 gdcM::Element< VR::OW, VM::VM1 > Class Reference

```
#include <gdcMElement.h>
```

Inheritance diagram for gdcM::Element< VR::OW, VM::VM1 >:



Collaboration diagram for gdcm::Element< VR::OW, VM::VM1 >:



Public Types

- typedef `VRTToType< TVR >::Type` `Type`

Public Types inherited from `gdcm::Element< VR::OW, VM::VM1_n >`

- typedef `VRTToType< TVR >::Type` `Type`

Public Member Functions

- `DataElement GetAsDataElement ()` const
- unsigned long `GetLength ()` const
- const `VRTToType< TVR >::Type & GetValue (unsigned int idx=0)` const
- const `VRTToType< TVR >::Type * GetValues ()` const
- `VRTToType< TVR >::Type operator[] (unsigned int idx)` const
- void `Print (std::ostream &_os)` const

- void [Read](#) (std::istream &_is)
- void [Set](#) ([Value](#) const &v)
- void [SetFromDataElement](#) ([DataElement](#) const &de)
- void [SetValue](#) (typename [VRToType](#)< TVR >::Type v, unsigned int idx=0)
- void [Write](#) (std::ostream &_os) const

Public Member Functions inherited from [gdcm::Element](#)< [VR::OW](#), [VM::VM1_n](#) >

- [DataElement](#) [GetAsDataElement](#) () const
- unsigned long [GetLength](#) () const
- const [VRToType](#)< TVR >::Type & [GetValue](#) (unsigned int idx=0) const
- const [VRToType](#)< TVR >::Type * [GetValues](#) () const
- [VRToType](#)< TVR >::Type [operator\[\]](#) (unsigned int idx) const
- void [Print](#) (std::ostream &_os) const
- void [Read](#) (std::istream &_is)
- void [Set](#) ([Value](#) const &v)
- void [SetFromDataElement](#) ([DataElement](#) const &de)
- void [SetValue](#) (typename [VRToType](#)< TVR >::Type v, unsigned int idx=0)
- void [Write](#) (std::ostream &_os) const

Static Public Member Functions

- static [VM](#) [GetVM](#) ()
- static [VR](#) [GetVR](#) ()

Static Public Member Functions inherited from [gdcm::Element](#)< [VR::OW](#), [VM::VM1_n](#) >

- static [VM](#) [GetVM](#) ()
- static [VR](#) [GetVR](#) ()

Public Attributes

- [VRToType](#)< TVR >::Type [Internal](#) [[VMToLength](#)< TVM >::Length]

Public Attributes inherited from [gdcm::Element](#)< [VR::OW](#), [VM::VM1_n](#) >

- [VRToType](#)< TVR >::Type [Internal](#) [[VMToLength](#)< TVM >::Length]

Protected Member Functions

- void [SetNoSwap](#) ([Value](#) const &v)

Protected Member Functions inherited from [gdcm::Element< VR::OW, VM::VM1_n >](#)

- void [SetNoSwap](#) (Value const &v)

10.104.1 Member Typedef Documentation**10.104.1.1 Type**

```
typedef VRToType<TVR>::Type gdcm::Element< TVR, TVM >::Type
```

10.104.2 Member Function Documentation**10.104.2.1 GetAsDataElement()**

```
DataElement gdcm::Element< TVR, TVM >::GetAsDataElement () const [inline]
```

10.104.2.2 GetLength()

```
unsigned long gdcm::Element< TVR, TVM >::GetLength () const [inline]
```

10.104.2.3 GetValue()

```
const VRToType< TVR >::Type & gdcm::Element< TVR, TVM >::GetValue (
    unsigned int idx = 0) const [inline]
```

10.104.2.4 GetValues()

```
const VRToType< TVR >::Type * gdcm::Element< TVR, TVM >::GetValues () const [inline]
```

10.104.2.5 GetVM()

```
VM gdcm::Element< TVR, TVM >::GetVM () [inline], [static]
```

10.104.2.6 GetVR()

```
VR gdcm::Element< TVR, TVM >::GetVR () [inline], [static]
```

10.104.2.7 operator[]()

```
VRToType< TVR >::Type gdcM::Element< TVR, TVM >::operator[] (
    unsigned int idx) const [inline]
```

10.104.2.8 Print()

```
void gdcM::Element< TVR, TVM >::Print (
    std::ostream & _os) const [inline]
```

10.104.2.9 Read()

```
void gdcM::Element< TVR, TVM >::Read (
    std::istream & _is) [inline]
```

10.104.2.10 Set()

```
void gdcM::Element< TVR, TVM >::Set (
    Value const & v) [inline]
```

10.104.2.11 SetFromDataElement()

```
void gdcM::Element< TVR, TVM >::SetFromDataElement (
    DataElement< VR::OW, VM::VM1 > const & de) [inline]
```

10.104.2.12 SetNoSwap()

```
void gdcM::Element< TVR, TVM >::SetNoSwap (
    Value const & v) [inline], [protected]
```

10.104.2.13 SetValue()

```
void gdcM::Element< TVR, TVM >::SetValue (
    typename VRTToType< TVR >::Type v,
    unsigned int idx = 0) [inline]
```

10.104.2.14 Write()

```
void gdcM::Element< TVR, TVM >::Write (
    std::ostream & _os) const [inline]
```

10.104.3 Member Data Documentation

10.104.3.1 Internal

```
VRToType<TVR>::Type gdcm::Element< TVR, TVM >::Internal[VMToLength< TVM >::Length]
```

The documentation for this class was generated from the following file:

- [gdcmElement.h](#)

10.105 gdcm::ElementDisableCombinations< TVR, TVM > Class Template Reference

A class which is used to produce compile errors for an invalid combination of template parameters.

```
#include <gdcmElement.h>
```

Inheritance diagram for gdcm::ElementDisableCombinations< TVR, TVM >:



10.105.1 Detailed Description

```
template<long long TVR, int TVM>
class gdcm::ElementDisableCombinations< TVR, TVM >
```

A class which is used to produce compile errors for an invalid combination of template parameters.

Invalid combinations have specialized declarations with no definition.


The documentation for this class was generated from the following file:

- [gdcmElement.h](#)


10.106 gdcmm::ElementDisableCombinations< VR::OB, VM::VM1_n > Class Reference

```
#include <gdcmmElement.h>
```

Inheritance diagram for gdcmm::ElementDisableCombinations< VR::OB, VM::VM1_n >:



Collaboration diagram for gdcmm::ElementDisableCombinations< VR::OB, VM::VM1_n >:




The documentation for this class was generated from the following file:

- [gdcmmElement.h](#)


10.107 gdcm::ElementDisableCombinations< VR::OW, VM::VM1_n > Class Reference

```
#include <gdcmElement.h>
```

Inheritance diagram for gdcm::ElementDisableCombinations< VR::OW, VM::VM1_n >:



Collaboration diagram for gdcm::ElementDisableCombinations< VR::OW, VM::VM1_n >:



The documentation for this class was generated from the following file:

- [gdcmElement.h](#)

10.108 gdcm::EmptyMaskGenerator Class Reference

EmptyMaskGenerator Main class to generate a Empty Mask [Series](#) from an input [Series](#). This class takes an input folder and generates a series of DICOM files in the specified output directory. This class handles multiples DICOM [Series](#) within the same input directory.

```
#include <gdcmEmptyMaskGenerator.h>
```

Public Types

- enum [SOPClassUIDMode](#) {
[UseOriginalSOPClassUID](#) = 0 ,
[UseGrayscaleSecondaryImageStorage](#) }

Public Member Functions

- [EmptyMaskGenerator](#) ()
- [~EmptyMaskGenerator](#) ()
- bool [Execute](#) ()
Main loop.
- void [SetInputDirectory](#) (const char *dirname)
Specify input directory.
- void [SetOutputDirectory](#) (const char *dirname)
Specify output directory.
- void [SetSOPClassUIDMode](#) ([SOPClassUIDMode](#) mode)

10.108.1 Detailed Description

EmptyMaskGenerator Main class to generate a Empty Mask [Series](#) from an input [Series](#). This class takes an input folder and generates a series of DICOM files in the specified output directory. This class handles multiples DICOM [Series](#) within the same input directory.

The class allow two mode of operations:

- [UseOriginalSOPClassUID](#)
- [UseGrayscaleSecondaryImageStorage](#)

[UseOriginalSOPClassUID](#) is the mode where original attributes are copied from the original DICOM instance.

[UseGrayscaleSecondaryImageStorage](#) is the mode where attributes are generated so as to create a MultiframeGrayscaleByteSecondaryCaptureImageStorage (MultiframeGrayscaleWordSecondaryCaptureImageStorage) instance.

In both mode:

- the [Study](#) references (StudyInstanceUID and StudyID) are preserved.
- the PatientID reference is preserved.
- the [Image Type](#) attribute will be setup so that the fourth element is set to 'MASK'.
- a new [Series](#) Instance UID is generated. It is thus required to run the process over all files using the same input [Series](#) Instance UID so that a proper mapping from the old [Series](#) UID is done to the new one. Since a new [Series](#) Instance UID is generated, there is no sense to preserve the original Frame of Reference UID, although it would have made sense here.

Examples

[EmptyMask.cxx](#).

10.108.2 Member Enumeration Documentation

10.108.2.1 SOPClassUIDMode

enum `gdcm::EmptyMaskGenerator::SOPClassUIDMode`

Enumerator

UseOriginalSOPClassUID	
UseGrayscaleSecondaryImageStorage	

10.108.3 Constructor & Destructor Documentation

10.108.3.1 EmptyMaskGenerator()

`gdcm::EmptyMaskGenerator::EmptyMaskGenerator ()`

10.108.3.2 ~EmptyMaskGenerator()

`gdcm::EmptyMaskGenerator::~~EmptyMaskGenerator ()`

10.108.4 Member Function Documentation

10.108.4.1 Execute()

`bool gdcm::EmptyMaskGenerator::Execute ()`

Main loop.

Examples

[EmptyMask.cxx](#).

10.108.4.2 SetInputDirectory()

`void gdcm::EmptyMaskGenerator::SetInputDirectory (
 const char * dirname)`

Specify input directory.

Examples

[EmptyMask.cxx](#).

10.108.4.3 SetOutputDirectory()

```
void gdcM::EmptyMaskGenerator::SetOutputDirectory (
    const char * dirname)
```

Specify output directory.

Examples

[EmptyMask.cxx](#).

10.108.4.4 SetSOPClassUIDMode()

```
void gdcM::EmptyMaskGenerator::SetSOPClassUIDMode (
    SOPClassUIDMode mode)
```

Select generation of SOP Class UID method: Default is UseOriginalSOPClassUID

Examples

[EmptyMask.cxx](#).

The documentation for this class was generated from the following file:

- [gdcMEmptyMaskGenerator.h](#)

10.109 gdcM::EncapsulatedDocument Class Reference

[EncapsulatedDocument](#).

```
#include <gdcMEncapsulatedDocument.h>
```

Public Member Functions

- [EncapsulatedDocument](#) ()=default

10.109.1 Detailed Description

[EncapsulatedDocument](#).

10.109.2 Constructor & Destructor Documentation

10.109.2.1 EncapsulatedDocument()

```
gdcm::EncapsulatedDocument::EncapsulatedDocument () [default]
```

The documentation for this class was generated from the following file:

- [gdcmEncapsulatedDocument.h](#)

10.110 gdcm::EncodingImplementation< T > Class Template Reference

[EncodingImplementation.](#)

Inheritance diagram for gdcm::EncodingImplementation< T >:



10.110.1 Detailed Description

```
template<long long T>
class gdcm::EncodingImplementation< T >
```

[EncodingImplementation.](#)

Note

TODO


The documentation for this class was generated from the following file:

- [gdcmElement.h](#)


10.111 gdcm::EncodingImplementation< VR::VRASCII > Class Reference

```
#include <gdcmElement.h>
```

Inheritance diagram for gdcm::EncodingImplementation< VR::VRASCII >:



Collaboration diagram for gdcm::EncodingImplementation< VR::VRASCII >:



Public Member Functions

- template<> void [Write](#) (const double *data, unsigned long length, std::ostream &_os)

Static Public Member Functions

- template<typename T>
static void [Read](#) (T *data, unsigned long length, std::istream &_is)
- template<typename T>
static void [ReadComputeLength](#) (T *data, unsigned int &length, std::istream &_is)
- template<typename T>
static void [ReadNoSwap](#) (T *data, unsigned long length, std::istream &_is)
- template<typename T>
static void [Write](#) (const T *data, unsigned long length, std::ostream &_os)

10.111.1 Member Function Documentation

10.111.1.1 Read()

```
template<typename T>
void gdcm::EncodingImplementation< VR::VRASCII >::Read (
    T * data,
    unsigned long length,
    std::istream & _is) [inline], [static]
```

References [gdcm_assert](#).

Referenced by [ReadNoSwap\(\)](#).

10.111.1.2 ReadComputeLength()

```
template<typename T>
void gdcm::EncodingImplementation< VR::VRASCII >::ReadComputeLength (
    T * data,
    unsigned int & length,
    std::istream & _is) [inline], [static]
```

References [gdcm::backslash\(\)](#), and [gdcm_assert](#).

10.111.1.3 ReadNoSwap()

```
template<typename T>
void gdcm::EncodingImplementation< VR::VRASCII >::ReadNoSwap (
    T * data,
    unsigned long length,
    std::istream & _is) [inline], [static]
```

References [Read\(\)](#).

10.111.1.4 Write() [1/2]

```
template<>
void gdcM::EncodingImplementation< VR::VRASCII >::Write (
    const double * data,
    unsigned long length,
    std::ostream & _os) [inline]
```

References [gdcM_assert](#), and [gdcM::x16printf\(\)](#).

10.111.1.5 Write() [2/2]

```
template<typename T>
void gdcM::EncodingImplementation< VR::VRASCII >::Write (
    const T * data,
    unsigned long length,
    std::ostream & _os) [inline], [static]
```

References [gdcM_assert](#).


The documentation for this class was generated from the following file:

- [gdcMElement.h](#)


10.112 gdcM::EncodingImplementation< VR::VRBINARY > Class Reference

```
#include <gdcMElement.h>
```

Inheritance diagram for gdcM::EncodingImplementation< VR::VRBINARY >:



Collaboration diagram for gdcm::EncodingImplementation< VR::VRBINARY >:



Static Public Member Functions

- `template<typename T>`
static void [Read](#) (T *data, unsigned long length, std::istream &_is)
- `template<typename T>`
static void [ReadComputeLength](#) (T *data, unsigned int &length, std::istream &_is)
- `template<typename T>`
static void [ReadNoSwap](#) (T *data, unsigned long length, std::istream &_is)
- `template<typename T>`
static void [Write](#) (const T *data, unsigned long length, std::ostream &_os)

10.112.1 Member Function Documentation

10.112.1.1 Read()

```

template<typename T>
void gdcm::EncodingImplementation< VR::VRBINARY >::Read (
    T * data,
    unsigned long length,
    std::istream & _is) [inline], [static]
  
```

References [gdcm_assert](#), and [gdcm::SwapperNoOp::SwapArray\(\)](#).

10.112.1.2 ReadComputeLength()

```

template<typename T>
void gdcm::EncodingImplementation< VR::VRBINARY >::ReadComputeLength (
    T * data,
    unsigned int & length,
    std::istream & _is) [inline], [static]
  
```

References [gdcm_assert](#).

10.112.1.3 ReadNoSwap()

```
template<typename T>
void gdcM::EncodingImplementation< VR::VRBINARY >::ReadNoSwap (
    T * data,
    unsigned long length,
    std::istream & _is) [inline], [static]
```

References [gdcM_assert](#).

10.112.1.4 Write()

```
template<typename T>
void gdcM::EncodingImplementation< VR::VRBINARY >::Write (
    const T * data,
    unsigned long length,
    std::ostream & _os) [inline], [static]
```

References [gdcM_assert](#), and [gdcM::SwapperNoOp::Swap\(\)](#).


The documentation for this class was generated from the following file:

- [gdcMElement.h](#)


10.113 gdcM::EndEvent Class Reference

```
#include <gdcMEvent.h>
```

Inheritance diagram for gdcM::EndEvent:



Collaboration diagram for gdcm::EndEvent:



Additional Inherited Members

Public Member Functions inherited from [gdcm::Event](#)

- [Event](#) ()
- [Event](#) (const [Event](#) &)
- virtual [~Event](#) ()
- virtual bool [CheckEvent](#) (const [Event](#) *) const =0
- virtual const char * [GetEventName](#) () const =0
- virtual [Event](#) * [MakeObject](#) () const =0
- void [operator=](#) (const [Event](#) &)=delete
- virtual void [Print](#) (std::ostream &os) const

The documentation for this class was generated from the following file:

- [gdcmEvent.h](#)

10.114 gdcm::EnumeratedValues Class Reference

Element. A Data [Element](#) with Enumerated Values that does not have a [Value](#) equivalent to one of the Values specified in this standard has an invalid value within the scope of a specific Information Object/SOP Class definition. Note:

```
#include <gdcmEnumeratedValues.h>
```

Public Member Functions

- [EnumeratedValues](#) ()=default

10.114.1 Detailed Description

Element. A Data [Element](#) with Enumerated Values that does not have a [Value](#) equivalent to one of the Values specified in this standard has an invalid value within the scope of a specific Information Object/SOP Class definition. Note:

1. [Patient](#) Sex (0010, 0040) is an example of a Data [Element](#) having Enumerated Values. It is defined to have a [Value](#) that is either "M", "F", or "O" (see PS 3.3). No other [Value](#) shall be given to this Data [Element](#).
2. Future modifications of this standard may add to the set of allowed values for Data Elements with Enumerated Values. Such additions by themselves may or may not require a change in SOP Class [UIDs](#), depending on the semantics of the Data [Element](#).

10.114.2 Constructor & Destructor Documentation

10.114.2.1 EnumeratedValues()

```
gdcm::EnumeratedValues::EnumeratedValues () [default]
```

The documentation for this class was generated from the following file:

- [gdcmEnumeratedValues.h](#)

10.115 gdcm::EquipmentManufacturer Class Reference

```
#include <gdcmEquipmentManufacturer.h>
```

Public Types

- enum [Type](#) {
[UNKNOWN](#) = 0 ,
[AGFA](#) ,
[FUJI](#) ,
[GEMS](#) ,
[HITACHI](#) ,
[KODAK](#) ,
[MARCONI](#) ,
[PMS](#) ,
[SAMSUNG](#) ,
[SIEMENS](#) ,
[TOSHIBA](#) ,
[UIH](#) }

Static Public Member Functions

- static [Type](#) [Compute](#) ([DataSet](#) const &ds)
- static const char * [TypeToString](#) ([Type](#) type)

10.115.1 Detailed Description

The intent is for private tags handling. This class is not meant to handle all possible vendors in the world, simply those well known where we intend to read private tags afterwards (typically SIEMENS+CSA, GEMS+PDB ...)

10.115.2 Member Enumeration Documentation

10.115.2.1 Type

```
enum gdcm::EquipmentManufacturer::Type
```

Enumerator

UNKNOWN	
AGFA	
FUJI	
GEMS	
HITACHI	
KODAK	
MARCONI	
PMS	
SAMSUNG	
SIEMENS	
TOSHIBA	
UIH	

10.115.3 Member Function Documentation

10.115.3.1 Compute()

```
Type gdcm::EquipmentManufacturer::Compute (  
    DataSet const & ds) [static]
```

10.115.3.2 TypeToString()

```
const char * gdcm::EquipmentManufacturer::TypeToString (  
    Type type) [static]
```

The documentation for this class was generated from the following file:


- [gdcmEquipmentManufacturer.h](#)

10.116 gdcm::Event Class Reference

superclass for callback/observer methods

```
#include <gdcmEvent.h>
```

Inheritance diagram for gdcm::Event:



Public Member Functions

- [Event](#) ()
- [Event](#) (const [Event](#) &)
- virtual [~Event](#) ()

- virtual bool [CheckEvent](#) (const [Event](#) *) const =0
- virtual const char * [GetEventName](#) () const =0
- virtual [Event](#) * [MakeObject](#) () const =0
- void [operator=](#) (const [Event](#) &)=delete
- virtual void [Print](#) (std::ostream &os) const

10.116.1 Detailed Description

superclass for callback/observer methods

See also

[Command Subject](#)

Examples

[BasicAnonymizer.cs](#), [Cleaner.cs](#), [ClinicalTrialIdentificationWorkflow.cs](#), [ScanDirectory.cs](#), and [SimpleScanner.cxx](#).

10.116.2 Constructor & Destructor Documentation

10.116.2.1 Event() [1/2]

```
gdcm::Event::Event ()
```

Referenced by [Event\(\)](#), [CheckEvent\(\)](#), [MakeObject\(\)](#), and [operator=\(\)](#).

10.116.2.2 ~Event()

```
virtual gdcm::Event::~~Event () [virtual]
```

10.116.2.3 Event() [2/2]

```
gdcm::Event::Event (  
    const Event & )
```

References [Event\(\)](#).

10.116.3 Member Function Documentation

10.116.3.1 CheckEvent()

```
virtual bool gdcm::Event::CheckEvent (  
    const Event * ) const [pure virtual]
```

Check if given event matches or derives from this event.

References [Event\(\)](#).

10.116.3.2 GetEventName()

```
virtual const char * gdcm::Event::GetEventName () const [pure virtual]
```

Return the StringName associated with the event.

Implemented in [gdcm::AnonymizeEvent](#), [gdcm::DataEvent](#), [gdcm::DataSetEvent](#), [gdcm::FileNameEvent](#), and [gdcm::ProgressEvent](#).

Examples

[BasicAnonymizer.cs](#), [Cleaner.cs](#), [ClinicalTrialIdentificationWorkflow.cs](#), and [ScanDirectory.cs](#).

10.116.3.3 MakeObject()

```
virtual Event * gdcm::Event::MakeObject () const [pure virtual]
```

Create an [Event](#) of this type This method work as a Factory for creating events of each particular type.

Implemented in [gdcm::AnonymizeEvent](#), [gdcm::DataEvent](#), [gdcm::DataSetEvent](#), [gdcm::FileNameEvent](#), and [gdcm::ProgressEvent](#).

References [Event\(\)](#).

10.116.3.4 operator=()

```
void gdcm::Event::operator= (  
    const Event & ) [delete]
```

References [Event\(\)](#).

10.116.3.5 Print()

```
virtual void gdcm::Event::Print (  
    std::ostream & os) const [virtual]
```

Print [Event](#) information. This method can be overridden by specific [Event](#) subtypes. The default is to print out the type of the event.

Referenced by [gdcm::operator<<\(\)](#).

The documentation for this class was generated from the following file:


- [gdcmEvent.h](#)

10.117 gdcm::Exception Class Reference


[Exception](#).

```
#include <gdcmException.h>
```

Inheritance diagram for gdcm::Exception:



Collaboration diagram for gdcm::Exception:



Public Member Functions

- [Exception](#) (const char *desc="None", const char *file=__FILE__, unsigned int lineNumber=__LINE__, const char *func="")
- [~Exception](#) () override throw ()
- const char * [GetDescription](#) () const
Return the Description.
- const char * [what](#) () const override throw ()
what implementation

10.117.1 Detailed Description

[Exception](#).

Standard exception handling object.

Note

Its copy-constructor and assignment operator are generated by the compiler.

Examples

[ExtractImageRegion.cs](#), [ExtractImageRegionWithLUT.cs](#), [ExtractOneFrame.cs](#), [FileChangeTS.cs](#), and [FileChangeTSLossy.cs](#).

10.117.2 Constructor & Destructor Documentation

10.117.2.1 Exception()

```
gdcM::Exception::Exception (
    const char * desc = "None",
    const char * file = __FILE__,
    unsigned int lineNumber = __LINE__,
    const char * func = "") [inline], [explicit]
```

Explicit constructor, initializing the description and the text returned by [what\(\)](#).

Note

The last parameter is ignored for the time being. It may be used to specify the function where the exception was thrown.

Referenced by [gdcM::ParseException::ParseException\(\)](#).

10.117.2.2 ~Exception()

```
gdcM::Exception::~~Exception () throw ( ) [inline], [override]
```

10.117.3 Member Function Documentation

10.117.3.1 GetDescription()

```
const char * gdcM::Exception::GetDescription () const [inline]
```

Return the Description.

Referenced by [gdcM::SequenceOfItems::Read\(\)](#).

10.117.3.2 what()

```
const char * gdcm::Exception::what () const throw ( )    [inline], [override]
```

what implementation

Referenced by [gdcm::SequenceOfFragments::ReadValue\(\)](#).


The documentation for this class was generated from the following file:

- [gdcmException.h](#)


10.118 gdcm::ExitEvent Class Reference

```
#include <gdcmEvent.h>
```

Inheritance diagram for gdcm::ExitEvent:



Collaboration diagram for `gdcm::ExitEvent`:



Additional Inherited Members

Public Member Functions inherited from [gdcm::Event](#)

- [Event](#) ()
- [Event](#) (const [Event](#) &)
- virtual [~Event](#) ()
- virtual bool [CheckEvent](#) (const [Event](#) *) const =0
- virtual const char * [GetEventName](#) () const =0
- virtual [Event](#) * [MakeObject](#) () const =0
- void [operator=](#) (const [Event](#) &)=delete
- virtual void [Print](#) (std::ostream &os) const

The documentation for this class was generated from the following file:


- [gdcmEvent.h](#)

10.119 `gdcm::ExplicitDataElement` Class Reference


Class to read/write a [DataElement](#) as Explicit Data [Element](#).

```
#include <gdcmExplicitDataElement.h>
```


Inheritance diagram for gdcmm::ExplicitDataElement:



Collaboration diagram for gdcmm::ExplicitDataElement:



Public Member Functions

- [VL GetLength](#) () const
- template<typename TSwap>
std::istream & [Read](#) (std::istream &is)
- template<typename TSwap>
std::istream & [ReadPreValue](#) (std::istream &is)
- template<typename TSwap>
std::istream & [ReadValue](#) (std::istream &is, bool readvalues=true)
- template<typename TSwap>
std::istream & [ReadWithLength](#) (std::istream &is, [VL](#) &length)
- template<typename TSwap>
const std::ostream & [Write](#) (std::ostream &os) const

Public Member Functions inherited from `gdcm::DataElement`

- `DataElement` (const `DataElement` &_val)
- `DataElement` (const `Tag` &t=`Tag`(0), const `VL` &vl=0, const `VR` &vr=`VR::INVALID`)
- void `Clear` ()
 - Clear Data `Element` (make `Value` empty and invalidate `Tag` & `VR`)*
- void `Empty` ()
 - Make Data `Element` empty (no `Value`)*
- const `ByteValue` * `GetByteValue` () const
- template<typename TDE>
 - `VL` `GetLength` () const
- `SequenceOfFragments` * `GetSequenceOfFragments` ()
- const `SequenceOfFragments` * `GetSequenceOfFragments` () const
- `Tag` & `GetTag` ()
- const `Tag` & `GetTag` () const
 - Get `Tag`.*
- `Value` & `GetValue` ()
- `Value` const & `GetValue` () const
 - Set/Get `Value` (bytes array, SQ of items, SQ of fragments):*
- `SmartPointer`< `SequenceOfItems` > `GetValueAsSQ` () const
- `VL` & `GetVL` ()
- const `VL` & `GetVL` () const
 - Get `VL`.*
- `VR` const & `GetVR` () const
- bool `IsEmpty` () const
 - Check if Data `Element` is empty.*
- bool `IsUndefinedLength` () const
 - return if `Value` Length if of undefined length*
- bool `operator`< (const `DataElement` &de) const
- `DataElement` & `operator`= (const `DataElement` &)=default
- bool `operator`== (const `DataElement` &de) const
- template<typename TDE, typename TSwap>
 - `std::istream` & `Read` (`std::istream` &is)
- template<typename TDE, typename TSwap>
 - `std::istream` & `ReadOrSkip` (`std::istream` &is, `std::set`< `Tag` > const &skiptags)
- template<typename TDE, typename TSwap>
 - `std::istream` & `ReadPreValue` (`std::istream` &is, `std::set`< `Tag` > const &skiptags)
- template<typename TDE, typename TSwap>
 - `std::istream` & `ReadValue` (`std::istream` &is, `std::set`< `Tag` > const &skiptags)
- template<typename TDE, typename TSwap>
 - `std::istream` & `ReadValueWithLength` (`std::istream` &is, `VL` &length, `std::set`< `Tag` > const &skiptags)
- template<typename TDE, typename TSwap>
 - `std::istream` & `ReadWithLength` (`std::istream` &is, `VL` &length)
- void `SetByteValue` (const char *array, `VL` length)
- void `SetTag` (const `Tag` &t)
- void `SetValue` (`Value` const &vl)
- void `SetVL` (const `VL` &vl)
- void `SetVLToUndefined` ()
- void `SetVR` (`VR` const &vr)
- template<typename TDE, typename TSwap>
 - const `std::ostream` & `Write` (`std::ostream` &os) const

Additional Inherited Members

Protected Types inherited from [gdcm::DataElement](#)

- typedef [SmartPointer](#)< [Value](#) > [ValuePtr](#)

Protected Member Functions inherited from [gdcm::DataElement](#)

- void [SetValueFieldLength](#) ([VL](#) vl, bool readvalues)

Protected Attributes inherited from [gdcm::DataElement](#)

- [Tag](#) [TagField](#)
- [ValuePtr](#) [ValueField](#)
- [VL](#) [ValueLengthField](#)
- [VR](#) [VRField](#)

10.119.1 Detailed Description

Class to read/write a [DataElement](#) as Explicit Data [Element](#).

Note

bla

Examples

[DumpSiemensBase64.cxx](#), [DumpToshibaDTI.cxx](#), [DumpToshibaDTI2.cxx](#), and [ReadAndDumpDICOMDIR2.cxx](#).

10.119.2 Member Function Documentation

10.119.2.1 GetLength()

```
VL gdcm::ExplicitDataElement::GetLength () const
```

10.119.2.2 Read()

```
template<typename TSwap>
std::istream & gdcm::ExplicitDataElement::Read (
    std::istream & is)
```

10.119.2.3 ReadPreValue()

```
template<typename TSwap>
std::istream & gdcM::ExplicitDataElement::ReadPreValue (
    std::istream & is)
```

10.119.2.4 ReadValue()

```
template<typename TSwap>
std::istream & gdcM::ExplicitDataElement::ReadValue (
    std::istream & is,
    bool readvalues = true)
```

10.119.2.5 ReadWithLength()

```
template<typename TSwap>
std::istream & gdcM::ExplicitDataElement::ReadWithLength (
    std::istream & is,
    VL & length)
```

10.119.2.6 Write()

```
template<typename TSwap>
const std::ostream & gdcM::ExplicitDataElement::Write (
    std::ostream & os) const
```

The documentation for this class was generated from the following file:


- [gdcMExplicitDataElement.h](#)

10.120 gdcM::ExplicitImplicitDataElement Class Reference


Class to read/write a [DataElement](#) as ExplicitImplicit Data [Element](#).

```
#include <gdcMExplicitImplicitDataElement.h>
```

Inheritance diagram for gdcM::ExplicitImplicitDataElement:



Collaboration diagram for gdcM::ExplicitImplicitDataElement:



Public Member Functions

- [VL GetLength](#) () const
- template<typename TSwap>
std::istream & [Read](#) (std::istream &is)
- template<typename TSwap>
std::istream & [ReadPreValue](#) (std::istream &is)
- template<typename TSwap>
std::istream & [ReadValue](#) (std::istream &is, bool readvalues=true)
- template<typename TSwap>
std::istream & [ReadWithLength](#) (std::istream &is, [VL](#) &length)

Public Member Functions inherited from `gdcm::DataElement`

- `DataElement` (const `DataElement` &_val)
- `DataElement` (const `Tag` &t=`Tag`(0), const `VL` &vl=0, const `VR` &vr=`VR::INVALID`)
- void `Clear` ()
 - Clear Data `Element` (make `Value` empty and invalidate `Tag` & `VR`)*
- void `Empty` ()
 - Make Data `Element` empty (no `Value`)*
- const `ByteValue` * `GetByteValue` () const
- template<typename TDE>
 - `VL` `GetLength` () const
- `SequenceOfFragments` * `GetSequenceOfFragments` ()
- const `SequenceOfFragments` * `GetSequenceOfFragments` () const
- `Tag` & `GetTag` ()
- const `Tag` & `GetTag` () const
 - Get `Tag`.*
- `Value` & `GetValue` ()
- `Value` const & `GetValue` () const
 - Set/Get `Value` (bytes array, SQ of items, SQ of fragments):*
- `SmartPointer`< `SequenceOfItems` > `GetValueAsSQ` () const
- `VL` & `GetVL` ()
- const `VL` & `GetVL` () const
 - Get `VL`.*
- `VR` const & `GetVR` () const
- bool `IsEmpty` () const
 - Check if Data `Element` is empty.*
- bool `IsUndefinedLength` () const
 - return if `Value` Length if of undefined length*
- bool `operator`< (const `DataElement` &de) const
- `DataElement` & `operator`= (const `DataElement` &)=default
- bool `operator`== (const `DataElement` &de) const
- template<typename TDE, typename TSwap>
 - `std::istream` & `Read` (`std::istream` &is)
- template<typename TDE, typename TSwap>
 - `std::istream` & `ReadOrSkip` (`std::istream` &is, `std::set`< `Tag` > const &skiptags)
- template<typename TDE, typename TSwap>
 - `std::istream` & `ReadPreValue` (`std::istream` &is, `std::set`< `Tag` > const &skiptags)
- template<typename TDE, typename TSwap>
 - `std::istream` & `ReadValue` (`std::istream` &is, `std::set`< `Tag` > const &skiptags)
- template<typename TDE, typename TSwap>
 - `std::istream` & `ReadValueWithLength` (`std::istream` &is, `VL` &length, `std::set`< `Tag` > const &skiptags)
- template<typename TDE, typename TSwap>
 - `std::istream` & `ReadWithLength` (`std::istream` &is, `VL` &length)
- void `SetByteValue` (const char *array, `VL` length)
- void `SetTag` (const `Tag` &t)
- void `SetValue` (`Value` const &vl)
- void `SetVL` (const `VL` &vl)
- void `SetVLToUndefined` ()
- void `SetVR` (`VR` const &vr)
- template<typename TDE, typename TSwap>
 - const `std::ostream` & `Write` (`std::ostream` &os) const

Additional Inherited Members

Protected Types inherited from [gdcm::DataElement](#)

- typedef [SmartPointer](#)< [Value](#) > [ValuePtr](#)

Protected Member Functions inherited from [gdcm::DataElement](#)

- void [SetValueFieldLength](#) ([VL](#) vl, bool readvalues)

Protected Attributes inherited from [gdcm::DataElement](#)

- [Tag](#) [TagField](#)
- [ValuePtr](#) [ValueField](#)
- [VL](#) [ValueLengthField](#)
- [VR](#) [VRField](#)

10.120.1 Detailed Description

Class to read/write a [DataElement](#) as ExplicitImplicit Data [Element](#).

Note

This only happen for some Philips images Should I derive from [ExplicitDataElement](#) instead ? This is the class that is the closest the GDCM1.x parser. At each element we try first to read it as explicit, if this fails, then we try again as an implicit element.

10.120.2 Member Function Documentation

10.120.2.1 GetLength()

```
VL gdcm::ExplicitImplicitDataElement::GetLength () const
```

10.120.2.2 Read()

```
template<typename TSwap>
std::istream & gdcm::ExplicitImplicitDataElement::Read (
    std::istream & is)
```

Referenced by [ReadWithLength\(\)](#).

10.120.2.3 ReadPreValue()

```
template<typename TSwap>
std::istream & gdcmm::ExplicitImplicitDataElement::ReadPreValue (
    std::istream & is)
```

10.120.2.4 ReadValue()

```
template<typename TSwap>
std::istream & gdcmm::ExplicitImplicitDataElement::ReadValue (
    std::istream & is,
    bool readvalues = true)
```

10.120.2.5 ReadWithLength()

```
template<typename TSwap>
std::istream & gdcmm::ExplicitImplicitDataElement::ReadWithLength (
    std::istream & is,
    VL & length) [inline]
```

References [Read\(\)](#).

The documentation for this class was generated from the following file:

- [gdcmmExplicitImplicitDataElement.h](#)

10.121 gdcmm::Fiducials Class Reference

[Fiducials](#).

```
#include <gdcmmFiducials.h>
```

Public Member Functions

- [Fiducials](#) ()=default

10.121.1 Detailed Description

[Fiducials](#).

10.121.2 Constructor & Destructor Documentation

10.121.2.1 Fiducials()

```
gdcm::Fiducials::Fiducials () [default]
```

The documentation for this class was generated from the following file:


- [gdcmFiducials.h](#)

10.122 gdcm::File Class Reference


a DICOM [File](#)

```
#include <gdcmFile.h>
```

Inheritance diagram for gdcm::File:



Collaboration diagram for gdcm::File:



Public Member Functions

- [File](#) ()
- [~File](#) () override
- [DataSet](#) & [GetDataSet](#) ()
Get Data Set.
- const [DataSet](#) & [GetDataSet](#) () const
Get Data Set.
- [FileMetaInformation](#) & [GetHeader](#) ()
Get [File](#) Meta Information.
- const [FileMetaInformation](#) & [GetHeader](#) () const
Get [File](#) Meta Information.
- std::istream & [Read](#) (std::istream &is)
Read.
- void [SetDataSet](#) (const [DataSet](#) &ds)
Set Data Set.
- void [SetHeader](#) (const [FileMetaInformation](#) &fmi)
Set [File](#) Meta Information.
- std::ostream const & [Write](#) (std::ostream &os) const
Write.

Public Member Functions inherited from [gdcm::Object](#)

- [Object](#) ()
- [Object](#) (const [Object](#) &)
Special requirement for copy/cstor, assignment operator.
- virtual [~Object](#) ()
- void [operator=](#) (const [Object](#) &)
- virtual void [Print](#) (std::ostream &) const

Friends

- std::ostream & [operator<<](#) (std::ostream &os, const [File](#) &val)

Additional Inherited Members

Protected Member Functions inherited from [gdcm::Object](#)

- void [Register](#) ()
- void [UnRegister](#) ()

10.122.1 Detailed Description

a DICOM [File](#)

See PS 3.10 [File](#): A [File](#) is an ordered string of zero or more bytes, where the first byte is at the beginning of the file and the last byte at the end of the [File](#). Files are identified by a unique [File](#) ID and may be written, read and/or deleted.

See also

[Reader Writer](#)

Examples

[ChangePrivateTags.cxx](#), [ChangeSequenceUltrasound.cxx](#), [CompressLossyJPEG.cs](#), [CreateFakeRTDOSE.cxx](#), [CreateJPIPDataSet.cxx](#), [DeriveSeries.cxx](#), [DiffFile.cxx](#), [DumpCSA.cs](#), [DumpGEMSMovieGroup.cxx](#), [DumpPhilipsECHO.cxx](#), [DumpSiemensBase64.cxx](#), [DumpToshibaDTI.cxx](#), [DumpToshibaDTI2.cxx](#), [DumpVisusChange.cxx](#), [DuplicatePCDE.cxx](#), [EncapsulateFileInRawData.cxx](#), [ExtractEncapsulatedFile.cs](#), [ExtractEncryptedContent.cxx](#), [ExtractImageRegion.cs](#), [ExtractImageRegionWithLUT.cs](#), [ExtractOneFrame.cs](#), [Extracting_All_Resolution.cxx](#), [Fake_Image_Using_Stream_Image_Writer.cxx](#), [FileChangeTS.cs](#), [FileChangeTSLossy.cs](#), [FixBrokenJ2K.cxx](#), [FixOrientation.cxx](#), [GenAllVR.cxx](#), [GenFakeIdentifyFile.cxx](#), [GenFakeImage.cxx](#), [GenLongSeqs.cxx](#), [GenSeqs.cxx](#), [GetJPEGSamplePrecision.cxx](#), [GetSequenceUltrasound.cxx](#), [GetSubSequenceData.cxx](#), [HelloWorld.cxx](#), [LargeVRDSExplicit.cxx](#), [MakeTemplate.cxx](#), [MpegVideoInfo.cs](#), [NewSequence.cs](#), [PatchFile.cxx](#), [QIDO-RS.cxx](#), [ReadAndDumpDICOMDIR.cxx](#), [ReadAndPrintAttributes.cxx](#), [ReadGEMSSDO.cxx](#), [SimplePrint.cs](#), [SimplePrintPatientName.cs](#), [StreamImageReaderTest.cxx](#), [TemplateEmptyImage.cxx](#), and [iU22tomultisc.cxx](#).

10.122.2 Constructor & Destructor Documentation

10.122.2.1 File()

```
gdcm::File::File ()
```

Referenced by [gdcm::FileWithName::FileWithName\(\)](#), [~File\(\)](#), and [operator<<](#).

10.122.2.2 ~File()

```
gdcm::File::~File () [override]
```

References [File\(\)](#), and [operator<<](#).

10.122.3 Member Function Documentation

10.122.3.1 GetDataSet() [1/2]

```
DataSet & gdcm::File::GetDataSet () [inline]
```

Get Data Set.

10.122.3.2 GetDataSet() [2/2]

```
const DataSet & gdcm::File::GetDataSet () const [inline]
```

Get Data Set.

Examples

[ChangePrivateTags.cxx](#), [ChangeSequenceUltrasound.cxx](#), [CompressLossyJPEG.cs](#), [CreateFakeRTDOSE.cxx](#), [CreateJPIPDataSet.cxx](#), [DecompressImage.cs](#), [DeriveSeries.cxx](#), [DiffFile.cxx](#), [DumpADAC.cxx](#), [DumpCSA.cs](#), [DumpExamCard.cxx](#), [DumpGEMSMovieGroup.cxx](#), [DumpImageHeaderInfo.cxx](#), [DumpPhilipsECHO.cxx](#), [DumpSiemensBase64.cxx](#), [DumpToshibaDTI.cxx](#), [DumpToshibaDTI2.cxx](#), [DumpVisusChange.cxx](#), [DuplicatePCDE.cxx](#), [ELSCINT1WaveToText.cxx](#), [ExtractEncapsulatedFile.cs](#), [ExtractEncryptedContent.cxx](#), [Extracting_All_Resolution.cxx](#), [Fake_Image_Using_Stream_Image_Writer.cxx](#), [FileChangeTS.cs](#), [FileChangeTSLossy.cs](#), [FixBrokenJ2K.cxx](#), [FixJAIBugJPEGLS.cxx](#), [FixOrientation.cxx](#), [GenAllVR.cxx](#), [GenFakeIdentifyFile.cxx](#), [GenLongSeqs.cxx](#), [GenSeqs.cxx](#), [GetJPEGSamplePrecision.cxx](#), [GetSequenceUltrasound.cxx](#), [GetSubSequenceData.cxx](#), [HelloWorld.cxx](#), [LargeVRDSExplicit.cxx](#), [MergeTwoFiles.cxx](#), [MrProtocol.cxx](#), [NewSequence.cs](#), [PatchFile.cxx](#), [QIDO-RS.cxx](#), [ReadAndDumpDICOMDIR.cxx](#), [ReadAndDumpDICOMDIR2.cxx](#), [ReadAndPrintAttributes.cxx](#), [ReadExplicitLengthSQIVR.cxx](#), [ReadGEMSSDO.cxx](#), [SimplePrint.cs](#), [StreamImageReaderTest.cxx](#), [TemplateEmptyImage.cxx](#), [csa2img.cxx](#), [gdcmrtionplan.cxx](#), [gdcmrtplan.cxx](#), [iU22tomultisc.cxx](#), [pmsct_rgb1.cxx](#), and [rle2img.cxx](#).

10.122.3.3 GetHeader() [1/2]

```
FileMetaInformation & gdcm::File::GetHeader () [inline]
```

Get [File](#) Meta Information.

10.122.3.4 GetHeader() [2/2]

```
const FileMetaInformation & gdcm::File::GetHeader () const [inline]
```

Get [File](#) Meta Information.

Examples

[CreateJPIPDataSet.cxx](#), [DumpToshibaDTI.cxx](#), [DumpToshibaDTI2.cxx](#), [EncapsulateFileInRawData.cxx](#), [Extracting_All_Resolution.cxx](#), [Fake_Image_Using_Stream_Image_Writer.cxx](#), [FixJAIBugJPEGLS.cxx](#), [GenAllVR.cxx](#), [GenFakeIdentifyFile.cxx](#), [GetJPEGSamplePrecision.cxx](#), [LargeVRDSExplicit.cxx](#), [MakeTemplate.cxx](#), [MergeTwoFiles.cxx](#), [MpegVideoInfo.cs](#), [QIDO-RS.cxx](#), [ReadAndDumpDICOMDIR.cxx](#), [ReformatFile.cs](#), [StandardizeFiles.cs](#), [StreamImageReaderTest.cxx](#), [pmsct_rgb1.cxx](#), and [rle2img.cxx](#).

Referenced by [operator<<](#).

10.122.3.5 Read()

```
std::istream & gdcm::File::Read (
    std::istream & is)
```

Read.

10.122.3.6 SetDataSet()

```
void gdcm::File::SetDataSet (
    const DataSet & ds) [inline]
```

Set Data Set.

10.122.3.7 SetHeader()

```
void gdcm::File::SetHeader (
    const FileMetaInformation & fmi) [inline]
```

Set File Meta Information.

10.122.3.8 Write()

```
std::ostream const & gdcm::File::Write (
    std::ostream & os) const
```

Write.

10.122.4 Friends And Related Symbol Documentation

10.122.4.1 operator<<

```
std::ostream & operator<< (
    std::ostream & os,
    const File & val) [friend]
```

References [File\(\)](#), [gdcm_assert](#), [GetHeader\(\)](#), and [operator<<](#).

Referenced by [~File\(\)](#), and [operator<<](#).

The documentation for this class was generated from the following file:


- [gdcmFile.h](#)

10.123 gdcm::FileAnonymizer Class Reference


[FileAnonymizer.](#)

```
#include <gdcmFileAnonymizer.h>
```

Inheritance diagram for gdcm::FileAnonymizer:



Collaboration diagram for gdcm::FileAnonymizer:



Public Member Functions

- [FileAnonymizer](#) ()
- [~FileAnonymizer](#) () override
- void [Empty](#) ([Tag](#) const &t)
- void [Remove](#) ([Tag](#) const &t)
remove a tag (even a SQ can be removed)
- void [Replace](#) ([Tag](#) const &t, const char *value_data, [VL](#) const &vl)
- void [Replace](#) ([Tag](#) const &t, const char *value_str)
- void [SetInputFileName](#) (const char *filename_native)
Set input filename.
- void [SetOutputFileName](#) (const char *filename_native)
Set output filename.
- bool [Write](#) ()
Write the output file.

Public Member Functions inherited from [gdcm::Subject](#)

- [Subject](#) ()
- [~Subject](#) () override
- unsigned long [AddObserver](#) (const [Event](#) &event, [Command](#) *)
- unsigned long [AddObserver](#) (const [Event](#) &event, [Command](#) *) const
- [Command](#) * [GetCommand](#) (unsigned long tag)
- bool [HasObserver](#) (const [Event](#) &event) const
- void [InvokeEvent](#) (const [Event](#) &)
- void [InvokeEvent](#) (const [Event](#) &) const
- void [RemoveAllObservers](#) ()
- void [RemoveObserver](#) (unsigned long tag)

Public Member Functions inherited from [gdcm::Object](#)

- [Object](#) ()
- [Object](#) (const [Object](#) &)
Special requirement for copy/cstor, assignment operator.
- virtual [~Object](#) ()
- void [operator=](#) (const [Object](#) &)
- virtual void [Print](#) (std::ostream &) const

Additional Inherited Members**Protected Member Functions inherited from [gdcm::Object](#)**

- void [Register](#) ()
- void [UnRegister](#) ()

10.123.1 Detailed Description

[FileAnonymizer](#).

This [Anonymizer](#) is a file-based [Anonymizer](#). It requires a valid DICOM file and will use the [Value](#) Length to skip over any information.

It will not load the DICOM dataset taken from [SetInputFileName\(\)](#) into memory and should consume much less memory than [Anonymizer](#).

Warning

: Each time you call [Replace\(\)](#) with a value. This value will be copied, and stored in memory. The behavior is not ideal for extremely large data (larger than memory size). This class is really meant to take a large DICOM input file and then only change some small attribute.

caveats:

- This class will NOT work with unordered attributes in a DICOM [File](#),
- This class does neither recompute nor update the Group Length element,
- This class currently does not update the [File](#) Meta Information header.
- Only strict inplace Replace operation is supported when input and output file are the same.

Examples

[FileAnonymize.cs](#), and [MakeTemplate.cxx](#).

10.123.2 Constructor & Destructor Documentation

10.123.2.1 FileAnonymizer()

```
gdcm::FileAnonymizer::FileAnonymizer ()
```

10.123.2.2 ~FileAnonymizer()

```
gdcm::FileAnonymizer::~~FileAnonymizer () [override]
```

10.123.3 Member Function Documentation

10.123.3.1 Empty()

```
void gdcm::FileAnonymizer::Empty (  
    Tag const & t)
```

Make [Tag](#) t empty Warning: does not handle SQ element

Examples

[FileAnonymize.cs](#), and [MakeTemplate.cxx](#).

10.123.3.2 Remove()

```
void gdcM::FileAnonymizer::Remove (  
    Tag const & t)
```

remove a tag (even a SQ can be removed)

Examples

[FileAnonymize.cs](#).

10.123.3.3 Replace() [1/2]

```
void gdcM::FileAnonymizer::Replace (  
    Tag const & t,  
    const char * value_data,  
    VL const & vl)
```

when the value contains \0, it is a good idea to specify the length. This function is required when dealing with VRBINARY tag

10.123.3.4 Replace() [2/2]

```
void gdcM::FileAnonymizer::Replace (  
    Tag const & t,  
    const char * value_str)
```

Replace tag with another value, if tag is not found it will be created: WARNING: this function can only execute if tag is a VRASCII WARNING: Do not ever try to write a value in a SQ Data [Element](#) !

Examples

[FileAnonymize.cs](#).

10.123.3.5 SetInputFileName()

```
void gdcM::FileAnonymizer::SetInputFileName (  
    const char * filename_native)
```

Set input filename.

Examples

[FileAnonymize.cs](#), and [MakeTemplate.cxx](#).

10.123.3.6 SetOutputFileName()

```
void gdcM::FileAnonymizer::SetOutputFileName (  
    const char * filename_native)
```

Set output filename.

Examples

[FileAnonymize.cs](#), and [MakeTemplate.cxx](#).

10.123.3.7 Write()

```
bool gdcM::FileAnonymizer::Write ()
```

Write the output file.

Examples

[FileAnonymize.cs](#), and [MakeTemplate.cxx](#).

The documentation for this class was generated from the following file:


- [gdcMFileAnonymizer.h](#)

10.124 gdcM::FileChangeTransferSyntax Class Reference


[FileChangeTransferSyntax](#).

```
#include <gdcMFileChangeTransferSyntax.h>
```

Inheritance diagram for gdcM::FileChangeTransferSyntax:



Collaboration diagram for gdcm::FileChangeTransferSyntax:



Public Member Functions

- [FileChangeTransferSyntax](#) ()
- [~FileChangeTransferSyntax](#) () override
- bool [Change](#) ()
Change the transfer syntax.
- [ImageCodec](#) * [GetCodec](#) ()
- void [SetInputFileName](#) (const char *filename_native)
Set input filename (raw DICOM)
- void [SetOutputFileName](#) (const char *filename_native)
Set output filename (target compressed DICOM)
- void [SetTransferSyntax](#) ([TransferSyntax](#) const &ts)
Specify the Target Transfer Syntax.

Public Member Functions inherited from [gdcm::Subject](#)

- [Subject](#) ()
- [~Subject](#) () override
- unsigned long [AddObserver](#) (const [Event](#) &event, [Command](#) *)
- unsigned long [AddObserver](#) (const [Event](#) &event, [Command](#) *) const
- [Command](#) * [GetCommand](#) (unsigned long tag)
- bool [HasObserver](#) (const [Event](#) &event) const
- void [InvokeEvent](#) (const [Event](#) &)
- void [InvokeEvent](#) (const [Event](#) &) const
- void [RemoveAllObservers](#) ()
- void [RemoveObserver](#) (unsigned long tag)

Public Member Functions inherited from [gdcm::Object](#)

- [Object](#) ()
- [Object](#) (const [Object](#) &)
Special requirement for copy/cstor, assignment operator.
- virtual [~Object](#) ()
- void [operator=](#) (const [Object](#) &)
- virtual void [Print](#) (std::ostream &) const

Static Public Member Functions

- static [SmartPointer](#)< [FileChangeTransferSyntax](#) > [New](#) ()
for wrapped language: instantiate a reference counted object

Additional Inherited Members

Protected Member Functions inherited from [gdcm::Object](#)

- void [Register](#) ()
- void [UnRegister](#) ()

10.124.1 Detailed Description

[FileChangeTransferSyntax](#).

This class is a file-based (limited) replacement of the in-memory [ImageChangeTransferSyntax](#).

This class provide a file-based compression-only mechanism. It will take in an uncompressed DICOM image file (Pixel Data element). Then produced as output a compressed DICOM file (Transfer Syntax will be updated).

Currently it supports the following transfer syntax:

- [JPEGLosslessProcess14_1](#)

Examples

[FileChangeTS.cs](#), and [FileChangeTSLossy.cs](#).

10.124.2 Constructor & Destructor Documentation

10.124.2.1 [FileChangeTransferSyntax](#)()

```
gdcm::FileChangeTransferSyntax::FileChangeTransferSyntax ()
```

Referenced by [New\(\)](#).

10.124.2.2 ~FileChangeTransferSyntax()

```
gdcm::FileChangeTransferSyntax::~FileChangeTransferSyntax () [override]
```

10.124.3 Member Function Documentation

10.124.3.1 Change()

```
bool gdcm::FileChangeTransferSyntax::Change ()
```

Change the transfer syntax.

Examples

[FileChangeTS.cs](#), and [FileChangeTSLossy.cs](#).

10.124.3.2 GetCodec()

```
ImageCodec * gdcm::FileChangeTransferSyntax::GetCodec ()
```

Retrieve the actual codec (valid after calling SetTransferSyntax) Only advanced users should call this function.

Examples

[FileChangeTSLossy.cs](#).

10.124.3.3 New()

```
SmartPointer< FileChangeTransferSyntax > gdcm::FileChangeTransferSyntax::New () [inline], [static]
```

for wrapped language: instantiate a reference counted object

Examples

[FileChangeTS.cs](#), and [FileChangeTSLossy.cs](#).

References [FileChangeTransferSyntax\(\)](#).

10.124.3.4 SetInputFileName()

```
void gdcm::FileChangeTransferSyntax::SetInputFileName (  
    const char * filename_native)
```

Set input filename (raw DICOM)

Examples

[FileChangeTS.cs](#), and [FileChangeTSLossy.cs](#).

10.124.3.5 SetOutputFileName()

```
void gdcM::FileChangeTransferSyntax::SetOutputFileName (
    const char * filename_native)
```

Set output filename (target compressed DICOM)

Examples

[FileChangeTS.cs](#), and [FileChangeTSLossy.cs](#).

10.124.3.6 SetTransferSyntax()

```
void gdcM::FileChangeTransferSyntax::SetTransferSyntax (
    TransferSyntax const & ts)
```

Specify the Target Transfer Syntax.

Examples

[FileChangeTS.cs](#), and [FileChangeTSLossy.cs](#).

The documentation for this class was generated from the following file:


- [gdcMFileChangeTransferSyntax.h](#)

10.125 gdcM::FileDecompressLookupTable Class Reference


[FileDecompressLookupTable](#) class.

```
#include <gdcMFileDecompressLookupTable.h>
```

Inheritance diagram for gdcM::FileDecompressLookupTable:



Collaboration diagram for gdcm::FileDecompressLookupTable:



Public Member Functions

- `FileDecompressLookupTable ()`=default
- `~FileDecompressLookupTable ()` override=default
- `bool Change ()`
Decompress.
- `File & GetFile ()`
- `Pixmap & GetPixmap ()`
- `const Pixmap & GetPixmap () const`
- `void SetFile (const File &f)`
Set/Get File.
- `void SetPixmap (Pixmap const &img)`

Public Member Functions inherited from `gdcm::Subject`

- `Subject ()`
- `~Subject ()` override
- `unsigned long AddObserver (const Event &event, Command *)`
- `unsigned long AddObserver (const Event &event, Command *) const`
- `Command * GetCommand (unsigned long tag)`
- `bool HasObserver (const Event &event) const`
- `void InvokeEvent (const Event &)`
- `void InvokeEvent (const Event &) const`
- `void RemoveAllObservers ()`
- `void RemoveObserver (unsigned long tag)`

Public Member Functions inherited from [gdcm::Object](#)

- [Object](#) ()
- [Object](#) (const [Object](#) &)
Special requirement for copy/cstor, assignment operator.
- virtual [~Object](#) ()
- void [operator=](#) (const [Object](#) &)
- virtual void [Print](#) (std::ostream &) const

Additional Inherited Members

Protected Member Functions inherited from [gdcm::Object](#)

- void [Register](#) ()
- void [UnRegister](#) ()

10.125.1 Detailed Description

[FileDecompressLookupTable](#) class.

It decompress the segmented LUT into linearized one (only PALETTE_COLOR images) Output will be a [PhotometricInterpretation](#)=RGB image

10.125.2 Constructor & Destructor Documentation

10.125.2.1 [FileDecompressLookupTable](#)()

```
gdcm::FileDecompressLookupTable::FileDecompressLookupTable () [default]
```

10.125.2.2 [~FileDecompressLookupTable](#)()

```
gdcm::FileDecompressLookupTable::~~FileDecompressLookupTable () [override], [default]
```

10.125.3 Member Function Documentation

10.125.3.1 [Change](#)()

```
bool gdcm::FileDecompressLookupTable::Change ()
```

Decompress.

10.125.3.2 GetFile()

```
File & gdcm::FileDecompressLookupTable::GetFile () [inline]
```

10.125.3.3 GetPixmap() [1/2]

```
Pixmap & gdcm::FileDecompressLookupTable::GetPixmap () [inline]
```

10.125.3.4 GetPixmap() [2/2]

```
const Pixmap & gdcm::FileDecompressLookupTable::GetPixmap () const [inline]
```

10.125.3.5 SetFile()

```
void gdcm::FileDecompressLookupTable::SetFile (  
    const File & f) [inline]
```

Set/Get [File](#).

10.125.3.6 SetPixmap()

```
void gdcm::FileDecompressLookupTable::SetPixmap (  
    Pixmap const & img) [inline]
```

The documentation for this class was generated from the following file:

- [gdcmFileDecompressLookupTable.h](#)

10.126 gdcm::FileDerivation Class Reference

[FileDerivation](#) class.

```
#include <gdcmFileDerivation.h>
```

Public Member Functions

- [FileDerivation](#) ()
- [~FileDerivation](#) ()
- bool [AddReference](#) (const char *referencedsopclassuid, const char *referencedsopinstanceuid)
- bool [Derive](#) ()
 - Change.*
- [File](#) & [GetFile](#) ()
- const [File](#) & [GetFile](#) () const
- void [SetAppendDerivationHistory](#) (bool b)
- void [SetDerivationCodeSequenceCodeValue](#) (unsigned int codevalue)
 - Specify the Derivation Code Sequence Code [Value](#). Eg 113040.*
- void [SetDerivationDescription](#) (const char *dd)
 - Specify the Derivation Description. Eg "lossy conversion".*
- void [SetFile](#) (const [File](#) &f)
 - Set/Get [File](#).*
- void [SetPurposeOfReferenceCodeSequenceCodeValue](#) (unsigned int codevalue)
 - Specify the Purpose Of Reference Code [Value](#). Eg. 121320.*

Protected Member Functions

- bool [AddDerivationDescription](#) ()
- bool [AddPurposeOfReferenceCodeSequence](#) ([DataSet](#) &ds)
- bool [AddSourceImageSequence](#) ()

10.126.1 Detailed Description

[FileDerivation](#) class.

See PS 3.16 - 2008 For the list of Code [Value](#) that can be used for in Derivation Code Sequence

URL: http://medical.nema.org/medical/dicom/2008/08_16pu.pdf

DICOM Part 16 has two Context Groups CID 7202 and CID 7203 which contain a set of codes defining reason for a source image reference (ie. reason code for referenced image sequence) and a coded description of the derivation applied to the new image data from the original. Both these context groups are extensible.

[File](#) Derivation is compulsory when creating a lossy derived image.

Examples

[DeriveSeries.cxx](#), [GenFakelImage.cxx](#), and [ReformatFile.cs](#).

10.126.2 Constructor & Destructor Documentation

10.126.2.1 FileDerivation()

```
gdcm::FileDerivation::FileDerivation ()
```

10.126.2.2 ~FileDerivation()

```
gdcm::FileDerivation::~~FileDerivation ()
```

10.126.3 Member Function Documentation

10.126.3.1 AddDerivationDescription()

```
bool gdcm::FileDerivation::AddDerivationDescription () [protected]
```

10.126.3.2 AddPurposeOfReferenceCodeSequence()

```
bool gdcm::FileDerivation::AddPurposeOfReferenceCodeSequence (  
    DataSet & ds) [protected]
```

10.126.3.3 AddReference()

```
bool gdcm::FileDerivation::AddReference (  
    const char * referencedsopclassuid,  
    const char * referencedsopinstanceuid)
```

Create the proper reference. Need to pass the original SOP Class UID and the original SOP Instance UID, so that those value can be used as Reference.

Warning

referencedsopclassuid and referencedsopinstanceuid needs to be \0 padded. This is not compatible with how ByteValue->GetPointer works.

Examples

[DeriveSeries.cxx](#), [GenFakelImage.cxx](#), and [ReformatFile.cs](#).

10.126.3.4 AddSourceImageSequence()

```
bool gdcm::FileDerivation::AddSourceImageSequence () [protected]
```

10.126.3.5 Derive()

```
bool gdcm::FileDerivation::Derive ()
```

Change.

Examples

[DeriveSeries.cxx](#), [GenFakelImage.cxx](#), and [ReformatFile.cs](#).

10.126.3.6 GetFile() [1/2]

```
File & gdcm::FileDerivation::GetFile () [inline]
```

Examples

[GenFakelImage.cxx](#), and [ReformatFile.cs](#).

10.126.3.7 GetFile() [2/2]

```
const File & gdcm::FileDerivation::GetFile () const [inline]
```

10.126.3.8 SetAppendDerivationHistory()

```
void gdcm::FileDerivation::SetAppendDerivationHistory (  
    bool b)
```

Specify if Derivation history should be appended (default false) When false, this is an error if input already has a derivation history When true, both Purpose of Reference Code [Value](#) and Derivation Code Sequence Code [Value](#) can have their history appended.

10.126.3.9 SetDerivationCodeSequenceCodeValue()

```
void gdcm::FileDerivation::SetDerivationCodeSequenceCodeValue (  
    unsigned int codevalue)
```

Specify the Derivation Code Sequence Code [Value](#). Eg 113040.

Examples

[DeriveSeries.cxx](#), [GenFakelImage.cxx](#), and [ReformatFile.cs](#).

10.126.3.10 SetDerivationDescription()

```
void gdcm::FileDerivation::SetDerivationDescription (  
    const char * dd)
```

Specify the Derivation Description. Eg "lossy conversion".

10.126.3.11 SetFile()

```
void gdcm::FileDerivation::SetFile (
    const File & f) [inline]
```

Set/Get [File](#).

Examples

[DeriveSeries.cxx](#), [GenFakelImage.cxx](#), and [ReformatFile.cs](#).

10.126.3.12 SetPurposeOfReferenceCodeSequenceCodeValue()

```
void gdcm::FileDerivation::SetPurposeOfReferenceCodeSequenceCodeValue (
    unsigned int codevalue)
```

Specify the Purpose Of Reference Code [Value](#). Eg. 121320.

Examples

[DeriveSeries.cxx](#), [GenFakelImage.cxx](#), and [ReformatFile.cs](#).

The documentation for this class was generated from the following file:

- [gdcmFileDerivation.h](#)

10.127 gdcm::FileExplicitFilter Class Reference

[FileExplicitFilter](#) class.

```
#include <gdcmFileExplicitFilter.h>
```

Public Member Functions

- [FileExplicitFilter](#) ()
- [~FileExplicitFilter](#) ()=default
- bool [Change](#) ()
Set FMI Transfer Syntax.
- [File](#) & [GetFile](#) ()
- void [SetChangePrivateTags](#) (bool b)
Decide whether or not to [VR](#)ify private tags.
- void [SetFile](#) (const [File](#) &f)
Set/Get [File](#).
- void [SetRecomputeItemLength](#) (bool b)
By default set Sequence & [Item](#) length to Undefined to avoid recomputing length:
- void [SetRecomputeSequenceLength](#) (bool b)
- void [SetUseVRUN](#) (bool b)
When [VR](#)=16bits in explicit but Implicit has a 32bits length, use [VR](#)=UN.

Protected Member Functions

- bool [ChangeFMI](#) ()
- bool [ProcessDataSet](#) ([DataSet](#) &ds, [Dicts](#) const &dicts)

10.127.1 Detailed Description

[FileExplicitFilter](#) class.

After changing a file from Implicit to Explicit representation (see [ImageChangeTransferSyntax](#)) one operation is to make sure the [VR](#) of each DICOM attribute are accurate and do match the one from PS 3.6. Indeed when a file is written in Implicit representation, the [VR](#) is not stored directly in the file.

Warning

changing an implicit dataset to an explicit dataset is NOT a trivial task of simply changing the [VR](#) to the dict one:

- One has to make sure SQ is properly set
- One has to recompute the explicit length SQ
- One has to make sure that [VR](#) is valid for the encoding
- One has to make sure that [VR](#) 16bits can store the original value length

Examples

[ExplicitLittleEndian.cs](#), [GenAllVR.cxx](#), and [LargeVRDSExplicit.cxx](#).

10.127.2 Constructor & Destructor Documentation

10.127.2.1 FileExplicitFilter()

```
gdcm::FileExplicitFilter::FileExplicitFilter () [inline]
```

10.127.2.2 ~FileExplicitFilter()

```
gdcm::FileExplicitFilter::~FileExplicitFilter () [default]
```

10.127.3 Member Function Documentation

10.127.3.1 Change()

```
bool gdcm::FileExplicitFilter::Change ()
```

Set FMI Transfer Syntax.

Change

Examples

[ExplicitLittleEndian.cs](#), [GenAllVR.cxx](#), and [LargeVRDSExplicit.cxx](#).

10.127.3.2 ChangeFMI()

```
bool gdcm::FileExplicitFilter::ChangeFMI () [protected]
```

10.127.3.3 GetFile()

```
File & gdcm::FileExplicitFilter::GetFile () [inline]
```

Examples

[ExplicitLittleEndian.cs](#).

10.127.3.4 ProcessDataSet()

```
bool gdcm::FileExplicitFilter::ProcessDataSet (  
    DataSet & ds,  
    Dicts const & dicts) [protected]
```

10.127.3.5 SetChangePrivateTags()

```
void gdcm::FileExplicitFilter::SetChangePrivateTags (  
    bool b) [inline]
```

Decide whether or not to [VR](#)ify private tags.

Examples

[ExplicitLittleEndian.cs](#).

10.127.3.6 SetFile()

```
void gdcm::FileExplicitFilter::SetFile (  
    const File & f) [inline]
```

Set/Get [File](#).

Examples

[ExplicitLittleEndian.cs](#), [GenAllVR.cxx](#), and [LargeVRDSExplicit.cxx](#).

10.127.3.7 SetRecomputeItemLength()

```
void gdcM::FileExplicitFilter::SetRecomputeItemLength (
    bool b)
```

By default set Sequence & Item length to Undefined to avoid recomputing length:

10.127.3.8 SetRecomputeSequenceLength()

```
void gdcM::FileExplicitFilter::SetRecomputeSequenceLength (
    bool b)
```

10.127.3.9 SetUseVRUN()

```
void gdcM::FileExplicitFilter::SetUseVRUN (
    bool b) [inline]
```

When VR=16bits in explicit but Implicit has a 32bits length, use VR=UN.

The documentation for this class was generated from the following file:


- [gdcMFileExplicitFilter.h](#)

10.128 gdcM::FileMetaInformation Class Reference


Class to represent a File Meta Information.

```
#include <gdcMFileMetaInformation.h>
```

Inheritance diagram for gdcM::FileMetaInformation:



Collaboration diagram for gdcm::FileMetaInformation:



Public Member Functions

- [FileMetaInformation](#) ()
- [FileMetaInformation](#) ([FileMetaInformation](#) const &fmi)=default
- [~FileMetaInformation](#) ()
- void [FillFromDataSet](#) ([DataSet](#) const &ds)
 - Construct a [FileMetaInformation](#) from an already existing [DataSet](#):*
- const [TransferSyntax](#) & [GetDataSetTransferSyntax](#) () const
- [VL](#) [GetFullLength](#) () const
- [MediaStorage](#) [GetMediaStorage](#) () const
- std::string [GetMediaStorageAsString](#) () const
- [TransferSyntax::NegociatedType](#) [GetMetaInformationTS](#) () const
- [Preamble](#) & [GetPreamble](#) ()
- const [Preamble](#) & [GetPreamble](#) () const
 - Get [Preamble](#).*
- void [Insert](#) (const [DataElement](#) &de)
- bool [IsValid](#) () const
- [FileMetaInformation](#) & [operator=](#) (const [FileMetaInformation](#) &fmi)=default
- std::istream & [Read](#) (std::istream &is)
 - Read.*
- std::istream & [ReadCompat](#) (std::istream &is)
- void [Replace](#) (const [DataElement](#) &de)
- void [SetDataSetTransferSyntax](#) (const [TransferSyntax](#) &ts)
- void [SetPreamble](#) (const [Preamble](#) &p)
- std::ostream & [Write](#) (std::ostream &os) const
 - Write.*

Public Member Functions inherited from `gdcm::DataSet`

- `Iterator Begin ()`
- `ConstIterator Begin () const`
- `void Clear ()`
- `template<typename TDE>`
`unsigned int ComputeGroupLength (Tag const &tag) const`
- `Iterator End ()`
- `ConstIterator End () const`
- `bool FindDataElement (const PrivateTag &t) const`
Look up if private tag 't' is present in the dataset:
- `bool FindDataElement (const Tag &t) const`
- `const DataElement & FindNextDataElement (const Tag &t) const`
- `const DataElement & GetDataElement (const PrivateTag &t) const`
Return the dataelement.
- `const DataElement & GetDataElement (const Tag &t) const`
- `DataElementSet & GetDES ()`
- `const DataElementSet & GetDES () const`
- `template<typename TDE>`
`VL GetLength () const`
- `MediaStorage GetMediaStorage () const`
- `std::string GetPrivateCreator (const Tag &t) const`
- `PrivateTag GetPrivateTag (const Tag &t) const`
Return the private tag of the private tag 't', private creator will be set to empty if not found.
- `void Insert (const DataElement &de)`
- `bool IsEmpty () const`
Returns if the dataset is empty.
- `const DataElement & operator() (uint16_t group, uint16_t element) const`
- `DataSet & operator= (DataSet const &)=default`
- `const DataElement & operator[] (const Tag &t) const`
- `void Print (std::ostream &os, std::string const &indent="") const`
- `template<typename TDE, typename TSwap>`
`std::istream & Read (std::istream &is)`
- `template<typename TDE, typename TSwap>`
`std::istream & ReadNested (std::istream &is)`
- `template<typename TDE, typename TSwap>`
`std::istream & ReadSelectedPrivateTags (std::istream &is, const std::set< PrivateTag > &tags, bool readvalues=true)`
- `template<typename TDE, typename TSwap>`
`std::istream & ReadSelectedPrivateTagsWithLength (std::istream &is, const std::set< PrivateTag > &tags, VL &length, bool readvalues=true)`
- `template<typename TDE, typename TSwap>`
`std::istream & ReadSelectedTags (std::istream &is, const std::set< Tag > &tags, bool readvalues=true)`
- `template<typename TDE, typename TSwap>`
`std::istream & ReadSelectedTagsWithLength (std::istream &is, const std::set< Tag > &tags, VL &length, bool readvalues=true)`
- `template<typename TDE, typename TSwap>`
`std::istream & ReadUpToTag (std::istream &is, const Tag &t, std::set< Tag > const &skiptags)`
- `template<typename TDE, typename TSwap>`
`std::istream & ReadUpToTagWithLength (std::istream &is, const Tag &t, std::set< Tag > const &skiptags, VL &length)`

- template<typename TDE, typename TSwap>
std::istream & [ReadWithLength](#) (std::istream &is, [VL](#) &length)
- [SizeType Remove](#) (const [Tag](#) &tag)
Completely remove a dataelement from the dataset.
- void [Replace](#) (const [DataElement](#) &de)
Replace a dataelement with another one.
- void [ReplaceEmpty](#) (const [DataElement](#) &de)
Only replace a DICOM attribute when it is missing or empty.
- [SizeType Size](#) () const
- template<typename TDE, typename TSwap>
std::ostream const & [Write](#) (std::ostream &os) const

Static Public Member Functions

- static void [AppendImplementationClassUID](#) (const char *imp)
- static const char * [GetImplementationClassUID](#) ()
- static const char * [GetImplementationVersionName](#) ()
- static const char * [GetSourceApplicationEntityTitle](#) ()
- static void [SetImplementationClassUID](#) (const char *imp)
Override the GDCM default values:
- static void [SetImplementationVersionName](#) (const char *version)
- static void [SetSourceApplicationEntityTitle](#) (const char *title)

Protected Member Functions

- void [ComputeDataSetMediaStorageSOPClass](#) ()
- void [ComputeDataSetTransferSyntax](#) ()
- void [Default](#) ()
- template<typename TSwap>
std::istream & [ReadCompatInternal](#) (std::istream &is)

Protected Member Functions inherited from [gdcm::DataSet](#)

- [Tag ComputeDataElement](#) (const [PrivateTag](#) &t) const
- const [DataElement](#) & [GetDEEnd](#) () const
- void [InsertDataElement](#) (const [DataElement](#) &de)

Static Protected Member Functions

- static const char * [GetFileMetaInformationVersion](#) ()
- static const char * [GetGDCMImplementationClassUID](#) ()
- static const char * [GetGDCMImplementationVersionName](#) ()
- static const char * [GetGDCMSourceApplicationEntityTitle](#) ()

Protected Attributes

- [MediaStorage::MSType DataSetMS](#)
- [TransferSyntax DataSetTS](#)
- [TransferSyntax::NegociatedType MetaInformationTS](#)

Friends

- `std::ostream & operator<< (std::ostream &_os, const FileMetaInformation &_val)`

Additional Inherited Members**Public Types inherited from [gdcm::DataSet](#)**

- `typedef DataSet::const_iterator ConstIterator`
- `typedef std::set< DataElement > DataElementSet`
- `typedef DataSet::iterator Iterator`
- `typedef DataSet::size_type SizeType`

10.128.1 Detailed Description

Class to represent a [File](#) Meta Information.

[FileMetaInformation](#) is a Explicit Structured Set. Whenever the file contains an [ImplicitDataElement DataSet](#), a conversion will take place.

Definition: The [File](#) Meta Information includes identifying information on the encapsulated Data Set. This header consists of a 128 byte [File Preamble](#), followed by a 4 byte DICOM prefix, followed by the [File](#) Meta Elements shown in [Table 7.1-1](#). This header shall be present in every DICOM file.

See also

[Writer Reader](#)

Examples

[DumpToshibaDTI.cxx](#), [DumpToshibaDTI2.cxx](#), [GenAllVR.cxx](#), [GenFakeIdentifyFile.cxx](#), [LargeVRDSExplicit.cxx](#), [MakeTemplate.cxx](#), [ReadAndDumpDICOMDIR.cxx](#), [ReformatFile.cs](#), and [StandardizeFiles.cs](#).

10.128.2 Constructor & Destructor Documentation**10.128.2.1 [FileMetaInformation\(\)](#) [1/2]**

```
gdcm::FileMetaInformation::FileMetaInformation ()
```

Referenced by [FileMetaInformation\(\)](#), [~FileMetaInformation\(\)](#), [operator<<](#), and [operator=\(\)](#).

10.128.2.2 ~FileMetaInformation()

```
gdcm::FileMetaInformation::~~FileMetaInformation ()
```

References [FileMetaInformation\(\)](#), and [operator<<](#).

10.128.2.3 FileMetaInformation() [2/2]

```
gdcm::FileMetaInformation::FileMetaInformation (  
    FileMetaInformation const & fmi) [default]
```

References [FileMetaInformation\(\)](#).

10.128.3 Member Function Documentation

10.128.3.1 AppendImplementationClassUID()

```
void gdcm::FileMetaInformation::AppendImplementationClassUID (  
    const char * imp) [static]
```

10.128.3.2 ComputeDataSetMediaStorageSOPClass()

```
void gdcm::FileMetaInformation::ComputeDataSetMediaStorageSOPClass () [protected]
```

10.128.3.3 ComputeDataSetTransferSyntax()

```
void gdcm::FileMetaInformation::ComputeDataSetTransferSyntax () [protected]
```

10.128.3.4 Default()

```
void gdcm::FileMetaInformation::Default () [protected]
```

10.128.3.5 FillFromDataSet()

```
void gdcm::FileMetaInformation::FillFromDataSet (  
    DataSet const & ds)
```

Construct a [FileMetaInformation](#) from an already existing [DataSet](#):

10.128.3.6 GetDataSetTransferSyntax()

```
const TransferSyntax & gdcm::FileMetaInformation::GetDataSetTransferSyntax () const [inline]
```

Examples

[GetJPEGSamplePrecision.cxx](#), and [MergeTwoFiles.cxx](#).

References [DataSetTS](#).

10.128.3.7 GetFileMetaInformationVersion()

```
const char * gdcm::FileMetaInformation::GetFileMetaInformationVersion () [static], [protected]
```

10.128.3.8 GetFullLength()

```
VL gdcm::FileMetaInformation::GetFullLength () const [inline]
```

References [gdcm::DataSet::GetLength\(\)](#), and [gdcm::VL::GetLength\(\)](#).

10.128.3.9 GetGDCMImplementationClassUID()

```
const char * gdcm::FileMetaInformation::GetGDCMImplementationClassUID () [static], [protected]
```

10.128.3.10 GetGDCMImplementationVersionName()

```
const char * gdcm::FileMetaInformation::GetGDCMImplementationVersionName () [static], [protected]
```

10.128.3.11 GetGDCMSourceApplicationEntityTitle()

```
const char * gdcm::FileMetaInformation::GetGDCMSourceApplicationEntityTitle () [static], [protected]
```

10.128.3.12 GetImplementationClassUID()

```
const char * gdcm::FileMetaInformation::GetImplementationClassUID () [static]
```

10.128.3.13 GetImplementationVersionName()

```
const char * gdcm::FileMetaInformation::GetImplementationVersionName () [static]
```

10.128.3.14 GetMediaStorage()

```
MediaStorage gdcm::FileMetaInformation::GetMediaStorage () const
```

10.128.3.15 GetMediaStorageAsString()

```
std::string gdcm::FileMetaInformation::GetMediaStorageAsString () const
```

10.128.3.16 GetMetaInformationTS()

```
TransferSyntax::NegociatedType gdcm::FileMetaInformation::GetMetaInformationTS () const [inline]
```

References [MetaInformationTS](#).

10.128.3.17 GetPreamble() [1/2]

```
Preamble & gdcm::FileMetaInformation::GetPreamble () [inline]
```

10.128.3.18 GetPreamble() [2/2]

```
const Preamble & gdcm::FileMetaInformation::GetPreamble () const [inline]
```

Get [Preamble](#).

Referenced by [operator<<](#).

10.128.3.19 GetSourceApplicationEntityTitle()

```
const char * gdcm::FileMetaInformation::GetSourceApplicationEntityTitle () [static]
```

10.128.3.20 Insert()

```
void gdcm::FileMetaInformation::Insert (  
    const DataElement & de) [inline]
```

References [gdcmErrorMacro](#), [gdcm::Tag::GetGroup\(\)](#), [gdcm::DataElement::GetTag\(\)](#), and [gdcm::DataSet::InsertDataElement\(\)](#).

Referenced by [Replace\(\)](#).

10.128.3.21 IsValid()

```
bool gdcm::FileMetaInformation::IsValid () const [inline]
```

10.128.3.22 operator=()

```
FileMetaInformation & gdcM::FileMetaInformation::operator= (
    const FileMetaInformation & fmi) [default]
```

References [FileMetaInformation\(\)](#).

10.128.3.23 Read()

```
std::istream & gdcM::FileMetaInformation::Read (
    std::istream & is)
```

Read.

10.128.3.24 ReadCompat()

```
std::istream & gdcM::FileMetaInformation::ReadCompat (
    std::istream & is)
```

10.128.3.25 ReadCompatInternal()

```
template<typename TSwap>
std::istream & gdcM::FileMetaInformation::ReadCompatInternal (
    std::istream & is) [protected]
```

10.128.3.26 Replace()

```
void gdcM::FileMetaInformation::Replace (
    const DataElement & de) [inline]
```

Examples

[LargeVRDSExplicit.cxx](#).

References [gdcM::DataElement::GetTag\(\)](#), [Insert\(\)](#), and [gdcM::DataSet::Remove\(\)](#).

10.128.3.27 SetDataSetTransferSyntax()

```
void gdcM::FileMetaInformation::SetDataSetTransferSyntax (
    const TransferSyntax & ts)
```

Examples

[CreateJPIPDataSet.cxx](#), [DumpToshibaDTI.cxx](#), [DumpToshibaDTI2.cxx](#), [EncapsulateFileInRawData.cxx](#), [Extracting_All_Resolution.cxx](#), [Fake_Image_Using_Stream_Image_Writer.cxx](#), [FixJAIBugJPEGLS.cxx](#), [GenAllVR.cxx](#), [GenFakeIdentifyFile.cxx](#), [LargeVRDSExplicit.cxx](#), [MakeTemplate.cxx](#), [MpegVideoInfo.cs](#), [QIDO-RS.cxx](#), [StreamImageReaderTest.cxx](#), [pmsct_rgb1.cxx](#), and [rle2img.cxx](#).

10.128.3.28 SetImplementationClassUID()

```
void gdcm::FileMetaInformation::SetImplementationClassUID (
    const char * imp) [static]
```

Override the GDCM default values:

10.128.3.29 SetImplementationVersionName()

```
void gdcm::FileMetaInformation::SetImplementationVersionName (
    const char * version) [static]
```

10.128.3.30 SetPreamble()

```
void gdcm::FileMetaInformation::SetPreamble (
    const Preamble & p) [inline]
```

10.128.3.31 SetSourceApplicationEntityTitle()

```
void gdcm::FileMetaInformation::SetSourceApplicationEntityTitle (
    const char * title) [static]
```

Examples

[ExplicitLittleEndian.cs](#), [FixJAIBugJPEGLS.cxx](#), [GenerateDICOMDIR.cs](#), [ReformatFile.cs](#), and [StandardizeFiles.cs](#).

10.128.3.32 Write()

```
std::ostream & gdcm::FileMetaInformation::Write (
    std::ostream & os) const
```

Write.

10.128.4 Friends And Related Symbol Documentation

10.128.4.1 operator<<

```
std::ostream & operator<< (
    std::ostream & _os,
    const FileMetaInformation & _val) [friend]
```

References [FileMetaInformation\(\)](#), [GetPreamble\(\)](#), [operator<<](#), and [gdcm::DataSet::Print\(\)](#).

Referenced by [~FileMetaInformation\(\)](#), and [operator<<](#).

10.128.5 Member Data Documentation

10.128.5.1 DataSetMS

[MediaStorage::MSType](#) `gdcm::FileMetaInformation::DataSetMS` [protected]

10.128.5.2 DataSetTS

[TransferSyntax](#) `gdcm::FileMetaInformation::DataSetTS` [protected]

Referenced by [GetDataSetTransferSyntax\(\)](#).

10.128.5.3 MetaInformationTS

[TransferSyntax::NegociatedType](#) `gdcm::FileMetaInformation::MetaInformationTS` [protected]

Referenced by [GetMetaInformationTS\(\)](#).

The documentation for this class was generated from the following file:

- [gdcmFileMetaInformation.h](#)

10.129 gdcm::Filename Class Reference

Class to manipulate file name's.

```
#include <gdcmFilename.h>
```

Public Member Functions

- [Filename](#) (const char *filename="")
- bool [EndWith](#) (const char ending[]) const
Does the filename ends with a particular string ?
- const char * [GetExtension](#) ()
return only the extension part of a filename
- const char * [GetFileName](#) () const
Return the full filename.
- const char * [GetName](#) ()
return only the name part of a filename
- const char * [GetPath](#) ()
Return only the path component of a filename.
- bool [IsEmpty](#) () const
return whether the filename is empty
- bool [IsIdentical](#) ([Filename](#) const &fn) const
- [operator const char *](#) () const
- const char * [ToUnixSlashes](#) ()
Convert backslash (windows style) to UNIX style slash.
- const char * [ToWindowsSlashes](#) ()
Convert forward slash (UNIX style) to windows style slash.

Static Public Member Functions

- static const char * [Join](#) (const char *path, const char *filename)

10.129.1 Detailed Description

Class to manipulate file name's.

Note

OS independent representation of a filename (to query path, name and extension from a filename)

10.129.2 Constructor & Destructor Documentation

10.129.2.1 Filename()

```
gdcm::Filename::Filename (  
    const char * filename = "") [inline]
```

Referenced by [IsIdentical\(\)](#).

10.129.3 Member Function Documentation

10.129.3.1 EndWith()

```
bool gdcm::Filename::EndWith (  
    const char ending[]) const
```

Does the filename ends with a particular string ?

10.129.3.2 GetExtension()

```
const char * gdcm::Filename::GetExtension ()
```

return only the extension part of a filename

10.129.3.3 GetFileName()

```
const char * gdcm::Filename::GetFileName () const [inline]
```

Return the full filename.

Referenced by [operator const char *\(\)](#).

10.129.3.4 GetName()

```
const char * gdcM::Filename::GetName ()
```

return only the name part of a filename

10.129.3.5 GetPath()

```
const char * gdcM::Filename::GetPath ()
```

Return only the path component of a filename.

Examples

[ClinicalTrialIdentificationWorkflow.cs](#).

10.129.3.6 IsEmpty()

```
bool gdcM::Filename::IsEmpty () const [inline]
```

return whether the filename is empty

10.129.3.7 IsIdentical()

```
bool gdcM::Filename::IsIdentical (  
    Filename const & fn) const
```

References [Filename\(\)](#).

10.129.3.8 Join()

```
const char * gdcM::Filename::Join (  
    const char * path,  
    const char * filename) [static]
```

Join two paths NOT THREAD SAFE

10.129.3.9 operator const char *()

```
gdcM::Filename::operator const char * () const [inline]
```

Simple operator to allow [Filename](#) myfilename("..."); const char * s = myfilename;

References [GetFileName\(\)](#).

10.129.3.10 ToUnixSlashes()

```
const char * gdcm::Filename::ToUnixSlashes ()
```

Convert backslash (windows style) to UNIX style slash.

10.129.3.11 ToWindowsSlashes()

```
const char * gdcm::Filename::ToWindowsSlashes ()
```

Convert forward slash (UNIX style) to windows style slash.

The documentation for this class was generated from the following file:


- [gdcmFilename.h](#)

10.130 gdcm::FileNameEvent Class Reference


[FileNameEvent](#).

```
#include <gdcmFileNameEvent.h>
```

Inheritance diagram for gdcm::FileNameEvent:



Collaboration diagram for `gdcm::FileNameEvent`:



Public Types

- typedef [FileNameEvent](#) `Self`
- typedef [AnyEvent](#) `Superclass`

Public Member Functions

- [FileNameEvent](#) (`const char *s=""`)
- [FileNameEvent](#) (`const Self &s`)
- [~FileNameEvent](#) () `override=default`
- `bool` [CheckEvent](#) (`const ::gdcm::Event *e`) `const override`
- `const char *` [GetEventName](#) () `const override`
- `const char *` [GetFileName](#) () `const`
- `::gdcm::Event *` [MakeObject](#) () `const override`
- `void` [operator=](#) (`const Self &`) `=delete`
- `void` [SetFileName](#) (`const char *f`)

Public Member Functions inherited from [gdcm::Event](#)

- [Event](#) ()
- [Event](#) (`const Event &`)
- `virtual` [~Event](#) ()
- `virtual bool` [CheckEvent](#) (`const Event *`) `const =0`
- `void` [operator=](#) (`const Event &`) `=delete`
- `virtual void` [Print](#) (`std::ostream &os`) `const`

10.130.1 Detailed Description

[FileNameEvent](#).

Special type of event triggered during processing of [FileSet](#)

See also

[AnyEvent](#)

Examples

[ScanDirectory.cs](#), and [SimpleScanner.cxx](#).

10.130.2 Member Typedef Documentation

10.130.2.1 Self

```
typedef FileNameEvent gdcm::FileNameEvent::Self
```

10.130.2.2 Superclass

```
typedef AnyEvent gdcm::FileNameEvent::Superclass
```

10.130.3 Constructor & Destructor Documentation

10.130.3.1 [FileNameEvent\(\)](#) [1/2]

```
gdcm::FileNameEvent::FileNameEvent (  
    const char * s = "") [inline]
```

10.130.3.2 [~FileNameEvent\(\)](#)

```
gdcm::FileNameEvent::~~FileNameEvent () [override], [default]
```

10.130.3.3 [FileNameEvent\(\)](#) [2/2]

```
gdcm::FileNameEvent::FileNameEvent (  
    const Self & s) [inline]
```

10.130.4 Member Function Documentation

10.130.4.1 CheckEvent()

```
bool gdcm::FileNameEvent::CheckEvent (
    const ::gdcm::Event * e) const [inline], [override]
```

10.130.4.2 GetEventName()

```
const char * gdcm::FileNameEvent::GetEventName () const [inline], [override], [virtual]
```

Return the StringName associated with the event.

Implements [gdcm::Event](#).

10.130.4.3 GetFileName()

```
const char * gdcm::FileNameEvent::GetFileName () const [inline]
```

Examples

[ScanDirectory.cs](#), and [SimpleScanner.cxx](#).

10.130.4.4 MakeObject()

```
::gdcm::Event * gdcm::FileNameEvent::MakeObject () const [inline], [override], [virtual]
```

Create an [Event](#) of this type This method work as a Factory for creating events of each particular type.

Implements [gdcm::Event](#).

10.130.4.5 operator=()

```
void gdcm::FileNameEvent::operator= (
    const Self & ) [delete]
```

10.130.4.6 SetFileName()

```
void gdcm::FileNameEvent::SetFileName (
    const char * f) [inline]
```

The documentation for this class was generated from the following file:

- [gdcmFileNameEvent.h](#)

10.131 gdcm::FilenameGenerator Class Reference

[FilenameGenerator](#).

```
#include <gdcmFilenameGenerator.h>
```

Public Types

- typedef std::vector< [FilenameType](#) > [FilenamesType](#)
- typedef std::string [FilenameType](#)
- typedef [FilenamesType](#)::size_type [SizeType](#)

Public Member Functions

- [FilenameGenerator](#) ()
- [~FilenameGenerator](#) ()=default
- bool [Generate](#) ()
Generate (return success)
- const char * [GetFilename](#) ([SizeType](#) n) const
Get a particular filename (call after Generate)
- [FilenamesType](#) const & [GetFilenames](#) () const
Return all filenames.
- [SizeType](#) [GetNumberOfFilenames](#) () const
- const char * [GetPattern](#) () const
- const char * [GetPrefix](#) () const
- void [SetNumberOfFilenames](#) ([SizeType](#) nfiles)
Set/Get the number of filenames to generate.
- void [SetPattern](#) (const char *pattern)
Set/Get pattern.
- void [SetPrefix](#) (const char *prefix)
Set/Get prefix.

10.131.1 Detailed Description

[FilenameGenerator](#).

class to generate filenames based on a pattern (C-style)

Output will be:

for i = 0, number of filenames: outfilename[i] = prefix + (pattern % i)

where pattern % i means C-style sprintf of Pattern using value 'i'

Examples

[ConvertMultiFrameToSingleFrame.cxx](#), and [CreateFakePET.cxx](#).

10.131.2 Member Typedef Documentation

10.131.2.1 FilenamesType

```
typedef std::vector<FilenameType> gdcm::FilenameGenerator::FilenamesType
```

10.131.2.2 FilenameType

```
typedef std::string gdcm::FilenameGenerator::FilenameType
```

10.131.2.3 SizeType

```
typedef FilenamesType::size_type gdcm::FilenameGenerator::SizeType
```

10.131.3 Constructor & Destructor Documentation

10.131.3.1 FilenameGenerator()

```
gdcm::FilenameGenerator::FilenameGenerator () [inline]
```

10.131.3.2 ~FilenameGenerator()

```
gdcm::FilenameGenerator::~~FilenameGenerator () [default]
```

10.131.4 Member Function Documentation

10.131.4.1 Generate()

```
bool gdcm::FilenameGenerator::Generate ()
```

Generate (return success)

Examples

[ConvertMultiFrameToSingleFrame.cxx](#), and [CreateFakePET.cxx](#).

10.131.4.2 GetFilename()

```
const char * gdcm::FilenameGenerator::GetFilename (
    SizeType n) const
```

Get a particular filename (call after Generate)

Examples

[ConvertMultiFrameToSingleFrame.cxx](#), and [CreateFakePET.cxx](#).

10.131.4.3 GetFileNames()

```
FileNamesType const & gdcm::FilenameGenerator::GetFileNames () const [inline]
```

Return all filenames.

References [gdcm_assert](#).

10.131.4.4 GetNumberOfFileNames()

```
SizeType gdcm::FilenameGenerator::GetNumberOfFileNames () const
```

Examples

[ConvertMultiFrameToSingleFrame.cxx](#), and [CreateFakePET.cxx](#).

10.131.4.5 GetPattern()

```
const char * gdcm::FilenameGenerator::GetPattern () const [inline]
```

10.131.4.6 GetPrefix()

```
const char * gdcm::FilenameGenerator::GetPrefix () const [inline]
```

10.131.4.7 SetNumberOfFileNames()

```
void gdcm::FilenameGenerator::SetNumberOfFileNames (
    SizeType nfiles)
```

Set/Get the number of filenames to generate.

Examples

[ConvertMultiFrameToSingleFrame.cxx](#), and [CreateFakePET.cxx](#).

10.131.4.8 SetPattern()

```
void gdcM::FilenameGenerator::SetPattern (
    const char * pattern) [inline]
```

Set/Get pattern.

Examples

[ConvertMultiFrameToSingleFrame.cxx](#), and [CreateFakePET.cxx](#).

10.131.4.9 SetPrefix()

```
void gdcM::FilenameGenerator::SetPrefix (
    const char * prefix) [inline]
```

Set/Get prefix.

The documentation for this class was generated from the following file:

- [gdcMFilenameGenerator.h](#)

10.132 gdcM::FileSet Class Reference

```
#include <gdcMFileSet.h>
```

Public Types

- typedef std::vector< [FileType](#) > [FilesType](#)
- typedef std::string [FileType](#)

Public Member Functions

- [FileSet](#) ()
- bool [AddFile](#) (const char *filename)
- void [AddFile](#) ([File](#) const &)
- [FilesType](#) const & [GetFiles](#) () const
- void [SetFiles](#) ([FilesType](#) const &files)

Friends

- std::ostream & [operator<<](#) (std::ostream &_os, const [FileSet](#) &d)

10.132.1 Detailed Description

File-set: A File-set is a collection of DICOM Files (and possibly non-DICOM Files) that share a common naming space within which [File](#) IDs are unique.

10.132.2 Member Typedef Documentation

10.132.2.1 FileType

```
typedef std::vector<FileType> gdcm::FileSet::FileType
```

10.132.2.2 FileType

```
typedef std::string gdcm::FileSet::FileType
```

10.132.3 Constructor & Destructor Documentation

10.132.3.1 FileSet()

```
gdcm::FileSet::FileSet () [inline]
```

Referenced by [operator<<](#).

10.132.4 Member Function Documentation

10.132.4.1 AddFile() [1/2]

```
bool gdcm::FileSet::AddFile (  
    const char * filename)
```

Add a file 'filename' to the list of files. Return true on success, false in case filename could not be found on system.

10.132.4.2 AddFile() [2/2]

```
void gdcm::FileSet::AddFile (  
    File const & ) [inline]
```

Deprecated . Does nothing

10.132.4.3 GetFiles()

```
FileType const & gdcM::FileSet::GetFiles () const [inline]
```

10.132.4.4 SetFiles()

```
void gdcM::FileSet::SetFiles (
    FileType const & files)
```

10.132.5 Friends And Related Symbol Documentation

10.132.5.1 operator<<

```
std::ostream & operator<< (
    std::ostream & _os,
    const FileSet & d) [friend]
```

References [FileSet\(\)](#).

The documentation for this class was generated from the following file:


- [gdcMFileSet.h](#)

10.133 gdcM::FileStreamer Class Reference


[FileStreamer](#).

```
#include <gdcMFileStreamer.h>
```

Inheritance diagram for gdcM::FileStreamer:



Collaboration diagram for gdcm::FileStreamer:



Public Member Functions

- [FileStreamer](#) ()
- [~FileStreamer](#) () override
- bool [AppendToDataElement](#) (const [Tag](#) &t, const char *array, size_t len)
Append to previously started [Tag](#) t.
- bool [AppendToGroupDataElement](#) (const [PrivateTag](#) &pt, const char *array, size_t len)
Append to previously started private creator.
- bool [CheckDataElement](#) (const [Tag](#) &t)
- void [CheckTemplateFileName](#) (bool check)
- bool [ReserveDataElement](#) (size_t len)
- bool [ReserveGroupDataElement](#) (unsigned short ndataelement)
- void [SetOutputFileName](#) (const char *filename_native)
Set output filename (target file)
- void [SetTemplateFileName](#) (const char *filename_native)
Set input DICOM template filename.
- bool [StartDataElement](#) (const [Tag](#) &t)
- bool [StartGroupDataElement](#) (const [PrivateTag](#) &pt, size_t maxsize=0, uint8_t startoffset=0)
- bool [StopDataElement](#) (const [Tag](#) &t)
Stop appending to tag t. This will compute the proper attribute length.
- bool [StopGroupDataElement](#) (const [PrivateTag](#) &pt)
Stop appending to private creator.

Public Member Functions inherited from [gdcm::Subject](#)

- [Subject](#) ()
- [~Subject](#) () override
- unsigned long [AddObserver](#) (const [Event](#) &event, [Command](#) *)

- unsigned long [AddObserver](#) (const [Event](#) &event, [Command](#) *) const
- [Command](#) * [GetCommand](#) (unsigned long tag)
- bool [HasObserver](#) (const [Event](#) &event) const
- void [InvokeEvent](#) (const [Event](#) &)
- void [InvokeEvent](#) (const [Event](#) &) const
- void [RemoveAllObservers](#) ()
- void [RemoveObserver](#) (unsigned long tag)

Public Member Functions inherited from [gdcm::Object](#)

- [Object](#) ()
- [Object](#) (const [Object](#) &)
Special requirement for copy/cstor, assignment operator.
- virtual [~Object](#) ()
- void [operator=](#) (const [Object](#) &)
- virtual void [Print](#) (std::ostream &) const

Static Public Member Functions

- static [SmartPointer](#)< [FileStreamer](#) > [New](#) ()
for wrapped language: instantiate a reference counted object

Additional Inherited Members

Protected Member Functions inherited from [gdcm::Object](#)

- void [Register](#) ()
- void [UnRegister](#) ()

10.133.1 Detailed Description

[FileStreamer](#).

This class let a user create a massive DICOM [DataSet](#) from a template DICOM file, by appending chunks of data.

This class support two mode of operation:

1. Creating a single [DataElement](#) by appending chunk after chunk of data.
2. Creating a set of [DataElement](#) within the same group, using a private creator for start. New [DataElement](#) are added any time the user defined maximum size for data element is reached.

Warning

any existing [DataElement](#) is removed, pick carefully which [DataElement](#) to add.

Examples

[FileStreaming.cs](#).

10.133.2 Constructor & Destructor Documentation

10.133.2.1 FileStreamer()

```
gdcm::FileStreamer::FileStreamer ()
```

Referenced by [New\(\)](#).

10.133.2.2 ~FileStreamer()

```
gdcm::FileStreamer::~~FileStreamer () [override]
```

10.133.3 Member Function Documentation

10.133.3.1 AppendToDataElement()

```
bool gdcm::FileStreamer::AppendToDataElement (
    const Tag & t,
    const char * array,
    size_t len)
```

Append to previously started [Tag](#) t.

10.133.3.2 AppendToGroupDataElement()

```
bool gdcm::FileStreamer::AppendToGroupDataElement (
    const PrivateTag & pt,
    const char * array,
    size_t len)
```

Append to previously started private creator.

Examples

[FileStreaming.cs](#).

10.133.3.3 CheckDataElement()

```
bool gdcm::FileStreamer::CheckDataElement (
    const Tag & t)
```

Decide to check the Data [Element](#) to be written (default: off) The implementation has default strategy for checking validity of [DataElement](#). Currently it only support checking for the following tags:

- (7fe0,0010) Pixel Data

10.133.3.4 CheckTemplateFileName()

```
void gdcm::FileStreamer::CheckTemplateFileName (
    bool check)
```

Instead of simply blindly copying the input DICOM Template file, GDCM will be used to check the input file, and correct any issues recognized within the file. Only use if you do not have control over the input template file.

10.133.3.5 New()

```
SmartPointer< FileStreamer > gdcm::FileStreamer::New () [inline], [static]
```

for wrapped language: instantiate a reference counted object

References [FileStreamer\(\)](#).

10.133.3.6 ReserveDataElement()

```
bool gdcm::FileStreamer::ReserveDataElement (
    size_t len)
```

Add a hint on the final size of the dataelement. When optimally chosen, this reduce the number of file in-place copying. Should be called before StartDataElement

10.133.3.7 ReserveGroupDataElement()

```
bool gdcm::FileStreamer::ReserveGroupDataElement (
    unsigned short ndataelement)
```

Optimisation: pre-allocate the number of dataelement within the private group (ndataelement <= 256). Should be called before StartGroupDataElement

10.133.3.8 SetOutputFileName()

```
void gdcm::FileStreamer::SetOutputFileName (
    const char * filename_native)
```

Set output filename (target file)

Examples

[FileStreaming.cs](#).

10.133.3.9 SetTemplateFileName()

```
void gdcm::FileStreamer::SetTemplateFileName (
    const char * filename_native)
```

Set input DICOM template filename.

Examples

[FileStreaming.cs](#).

10.133.3.10 StartDataElement()

```
bool gdcm::FileStreamer::StartDataElement (
    const Tag & t)
```

Start Single Data [Element](#) Operation This will delete any existing [Tag](#) t. Need to call it only once.

10.133.3.11 StartGroupDataElement()

```
bool gdcm::FileStreamer::StartGroupDataElement (
    const PrivateTag & pt,
    size_t maxsize = 0,
    uint8_t startoffset = 0)
```

Start Private Group (multiple [DataElement](#)) Operation. Each newly added [DataElement](#) will have a length lower than

Parameters

<i>maxsize</i>	. When not specified, maxsize is set to maximum size allowed by DICOM ($= 2^{32}$). startoffset can be used to specify the very first element you want to start with (instead of the first possible). Value should be in [0x0, 0xff] This will find the first available private creator.
----------------	--

Bug maxsize should be a value lower than the actual total size of the buffer to be copied

Examples

[FileStreaming.cs](#).

10.133.3.12 StopDataElement()

```
bool gdcm::FileStreamer::StopDataElement (
    const Tag & t)
```

Stop appending to tag t. This will compute the proper attribute length.

10.133.3.13 StopGroupDataElement()

```
bool gdcM::FileStreamer::StopGroupDataElement (
    const PrivateTag & pt)
```

Stop appending to private creator.

Examples

[FileStreaming.cs](#).

The documentation for this class was generated from the following file:


- [gdcMFileStreamer.h](#)

10.134 gdcM::FileWithName Class Reference


[FileWithName](#).

```
#include <gdcMSerieHelper.h>
```

Inheritance diagram for gdcM::FileWithName:



Collaboration diagram for gdcm::FileWithName:



Public Member Functions

- [FileWithName](#) ([File](#) &f)

Public Member Functions inherited from [gdcm::File](#)

- [File](#) ()
- [~File](#) () override
- [DataSet](#) & [GetDataSet](#) ()
Get Data Set.
- const [DataSet](#) & [GetDataSet](#) () const
Get Data Set.
- [FileMetaInformation](#) & [GetHeader](#) ()
Get [File](#) Meta Information.
- const [FileMetaInformation](#) & [GetHeader](#) () const
Get [File](#) Meta Information.
- std::istream & [Read](#) (std::istream &is)
Read.
- void [SetDataSet](#) (const [DataSet](#) &ds)
Set Data Set.
- void [SetHeader](#) (const [FileMetaInformation](#) &fmi)
Set [File](#) Meta Information.
- std::ostream const & [Write](#) (std::ostream &os) const
Write.

Public Member Functions inherited from [gdcm::Object](#)

- [Object](#) ()
- [Object](#) (const [Object](#) &)
Special requirement for copy/cstor, assignment operator.
- virtual [~Object](#) ()
- void [operator=](#) (const [Object](#) &)
- virtual void [Print](#) (std::ostream &) const

Public Attributes

- std::string [filename](#)

Additional Inherited Members

Protected Member Functions inherited from [gdcm::Object](#)

- void [Register](#) ()
- void [UnRegister](#) ()

10.134.1 Detailed Description

[FileWithName](#).

Backward only class do not use in newer code

10.134.2 Constructor & Destructor Documentation

10.134.2.1 FileWithName()

```
gdcm::FileWithName::FileWithName (
    File & f) [inline]
```

References [gdcm::File::File\(\)](#), and [filename](#).

10.134.3 Member Data Documentation

10.134.3.1 filename

```
std::string gdcm::FileWithName::filename
```

Referenced by [FileWithName\(\)](#).

The documentation for this class was generated from the following file:


- [gdcmSerieHelper.h](#)

10.135 gdcm::FindPatientRootQuery Class Reference


PatientRootQuery.

```
#include <gdcmFindPatientRootQuery.h>
```

Inheritance diagram for gdcm::FindPatientRootQuery:



Collaboration diagram for gdcm::FindPatientRootQuery:



Public Member Functions

- `FindPatientRootQuery ()`
- `UIDs::TSName GetAbstractSyntaxUID ()` const override
- `std::vector< Tag > GetTagListByLevel (const EQueryLevel &inQueryLevel)` override
- `void InitializeDataSet (const EQueryLevel &inQueryLevel)` override
- `bool ValidateQuery (bool inStrict=true)` const override

Public Member Functions inherited from [gdcm::BaseRootQuery](#)

- [~BaseRootQuery](#) () override=default
- [EQueryLevel](#) [GetQueryLevelFromQueryRoot](#) ([ERootType](#) roottype)

Public Member Functions inherited from [gdcm::BaseQuery](#)

- [~BaseQuery](#) () override
 - void [AddQueryDataSet](#) (const [DataSet](#) &ds)
 - [DataSet](#) & [GetQueryDataSet](#) ()
 - [DataSet](#) const & [GetQueryDataSet](#) () const
- Set/Get the internal representation of the query as a [DataSet](#).*
- std::string [GetSOPInstanceUID](#) () const
 - void [Print](#) (std::ostream &os) const override
 - void [SetSearchParameter](#) (const std::string &inKeyword, const std::string &inValue)
 - void [SetSearchParameter](#) (const [Tag](#) &inTag, const std::string &inValue)
 - void [SetSOPInstanceUID](#) (const std::string &iSopInstanceUID)
 - const std::ostream & [WriteHelpFile](#) (std::ostream &os)
 - bool [WriteQuery](#) (const std::string &inFileName)

Public Member Functions inherited from [gdcm::Object](#)

- [Object](#) ()
 - [Object](#) (const [Object](#) &)
- Special requirement for copy/cstor, assignment operator.*
- virtual [~Object](#) ()
 - void [operator=](#) (const [Object](#) &)

Friends

- class [QueryFactory](#)

Additional Inherited Members

Static Public Member Functions inherited from [gdcm::BaseRootQuery](#)

- static [QueryBase](#) * [Construct](#) ([ERootType](#) inRootType, [EQueryLevel](#) qllevel)
- static int [GetQueryLevelFromString](#) (const char *str)
- static const char * [GetQueryLevelString](#) ([EQueryLevel](#) ql)

Protected Member Functions inherited from [gdcm::BaseRootQuery](#)

- [BaseRootQuery](#) ()

Protected Member Functions inherited from [gdcm::BaseQuery](#)

- [BaseQuery](#) ()
- void [SetSearchParameter](#) (const [Tag](#) &inTag, const [DictEntry](#) &inDictEntry, const std::string &inValue)
- bool [ValidDataSet](#) (const [DataSet](#) &dataSetToValid, const [DataSet](#) &dataSetReference) const

Protected Member Functions inherited from [gdcm::Object](#)

- void [Register](#) ()
- void [UnRegister](#) ()

Protected Attributes inherited from [gdcm::BaseRootQuery](#)

- std::string [mHelpDescription](#)
- [QueryImage](#) [mImage](#)
- [QueryPatient](#) [mPatient](#)
- [ERootType](#) [mRootType](#)
- [QuerySeries](#) [mSeries](#)
- [QueryStudy](#) [mStudy](#)

Protected Attributes inherited from [gdcm::BaseQuery](#)

- [DataSet](#) [mDataSet](#)
- std::string [mSopInstanceUID](#)

10.135.1 Detailed Description

PatientRootQuery.

contains: the class which will produce a dataset for c-find with patient root

10.135.2 Constructor & Destructor Documentation**10.135.2.1 FindPatientRootQuery()**

```
gdcm::FindPatientRootQuery::FindPatientRootQuery ()
```

10.135.3 Member Function Documentation**10.135.3.1 GetAbstractSyntaxUID()**

```
UIDs::TSName gdcm::FindPatientRootQuery::GetAbstractSyntaxUID () const [override], [virtual]
```

Implements [gdcm::BaseQuery](#).

10.135.3.2 GetTagListByLevel()

```
std::vector< Tag > gdcmm::FindPatientRootQuery::GetTagListByLevel (
    const EQueryLevel & inQueryLevel) [override], [virtual]
```

this function will return all tags at a given query level, so that they maybe selected for searching. The boolean forFind is true if the query is a find query, or false for a move query.

Implements [gdcmm::BaseRootQuery](#).

10.135.3.3 InitializeDataSet()

```
void gdcmm::FindPatientRootQuery::InitializeDataSet (
    const EQueryLevel & inQueryLevel) [override], [virtual]
```

this function sets tag 8,52 to the appropriate value based on query level also fills in the right unique tags, as per the standard's requirements should allow for connection with dcm4tk

Implements [gdcmm::BaseRootQuery](#).

10.135.3.4 ValidateQuery()

```
bool gdcmm::FindPatientRootQuery::ValidateQuery (
    bool inStrict = true) const [override], [virtual]
```

have to be able to ensure that 0x8,0x52 is set (which will be true if InitializeDataSet is called...) that the level is appropriate (ie, not setting PATIENT for a study query that the tags in the query match the right level (either required, unique, optional) by default, this function checks to see if the query is for finding, which is more permissive than for moving. For moving, only the unique tags are allowed. 10 Jan 2011: adding in the 'strict' mode. according to the standard (at least, how I've read it), only tags for a particular level should be allowed in a particular query (ie, just series level tags in a series level query). However, it seems that dcm4chee doesn't share that interpretation. So, if 'inStrict' is false, then tags from the current level and all higher levels are now considered valid. So, if you're doing a non-strict series-level query, tags from the patient and study level can be passed along as well.

Implements [gdcmm::BaseRootQuery](#).

10.135.4 Friends And Related Symbol Documentation

10.135.4.1 QueryFactory

```
friend class QueryFactory [friend]
```

References [QueryFactory](#).

Referenced by [QueryFactory](#).

The documentation for this class was generated from the following file:


- [gdcmmFindPatientRootQuery.h](#)

10.136 gdcm::FindStudyRootQuery Class Reference


[FindStudyRootQuery](#).

```
#include <gdcmFindStudyRootQuery.h>
```

Inheritance diagram for gdcm::FindStudyRootQuery:



Collaboration diagram for gdcm::FindStudyRootQuery:



Public Member Functions

- [FindStudyRootQuery](#) ()
- `UIDs::TSName GetAbstractSyntaxUID` () const override
- `std::vector< Tag > GetTagListByLevel` (const [EQueryLevel](#) &inQueryLevel) override
- void `InitializeDataSet` (const [EQueryLevel](#) &inQueryLevel) override
- bool `ValidateQuery` (bool inStrict=true) const override

Public Member Functions inherited from [gdcm::BaseRootQuery](#)

- [~BaseRootQuery](#) () override=default
- [EQueryLevel GetQueryLevelFromQueryRoot](#) (ERootType roottype)

Public Member Functions inherited from [gdcm::BaseQuery](#)

- [~BaseQuery](#) () override
 - void [AddQueryDataSet](#) (const [DataSet](#) &ds)
 - [DataSet](#) & [GetQueryDataSet](#) ()
 - [DataSet](#) const & [GetQueryDataSet](#) () const
- Set/Get the internal representation of the query as a [DataSet](#).*
- std::string [GetSOPInstanceUID](#) () const
 - void [Print](#) (std::ostream &os) const override
 - void [SetSearchParameter](#) (const std::string &inKeyword, const std::string &inValue)
 - void [SetSearchParameter](#) (const [Tag](#) &inTag, const std::string &inValue)
 - void [SetSOPInstanceUID](#) (const std::string &iSopInstanceUID)
 - const std::ostream & [WriteHelpFile](#) (std::ostream &os)
 - bool [WriteQuery](#) (const std::string &inFileName)

Public Member Functions inherited from [gdcm::Object](#)

- [Object](#) ()
 - [Object](#) (const [Object](#) &)
- Special requirement for copy/cstor, assignment operator.*
- virtual [~Object](#) ()
 - void [operator=](#) (const [Object](#) &)

Friends

- class [QueryFactory](#)

Additional Inherited Members

Static Public Member Functions inherited from [gdcm::BaseRootQuery](#)

- static [QueryBase](#) * [Construct](#) (ERootType inRootType, [EQueryLevel](#) qllevel)
- static int [GetQueryLevelFromString](#) (const char *str)
- static const char * [GetQueryLevelString](#) ([EQueryLevel](#) ql)

Protected Member Functions inherited from [gdcm::BaseRootQuery](#)

- [BaseRootQuery](#) ()

Protected Member Functions inherited from [gdcm::BaseQuery](#)

- [BaseQuery](#) ()
- void [SetSearchParameter](#) (const [Tag](#) &inTag, const [DictEntry](#) &inDictEntry, const std::string &inValue)
- bool [ValidDataSet](#) (const [DataSet](#) &dataSetToValid, const [DataSet](#) &dataSetReference) const

Protected Member Functions inherited from [gdcm::Object](#)

- void [Register](#) ()
- void [UnRegister](#) ()

Protected Attributes inherited from [gdcm::BaseRootQuery](#)

- std::string [mHelpDescription](#)
- [QueryImage](#) [mImage](#)
- [QueryPatient](#) [mPatient](#)
- [ERootType](#) [mRootType](#)
- [QuerySeries](#) [mSeries](#)
- [QueryStudy](#) [mStudy](#)

Protected Attributes inherited from [gdcm::BaseQuery](#)

- [DataSet](#) [mDataSet](#)
- std::string [mSopInstanceUID](#)

10.136.1 Detailed Description

[FindStudyRootQuery](#).

contains: the class which will produce a dataset for C-FIND with study root

10.136.2 Constructor & Destructor Documentation**10.136.2.1 FindStudyRootQuery()**

```
gdcm::FindStudyRootQuery::FindStudyRootQuery ()
```

10.136.3 Member Function Documentation**10.136.3.1 GetAbstractSyntaxUID()**

```
UIDs::TSName gdcm::FindStudyRootQuery::GetAbstractSyntaxUID () const [override], [virtual]
```

Implements [gdcm::BaseQuery](#).

10.136.3.2 GetTagListByLevel()

```
std::vector< Tag > gdcm::FindStudyRootQuery::GetTagListByLevel (
    const EQueryLevel & inQueryLevel) [override], [virtual]
```

this function will return all tags at a given query level, so that they maybe selected for searching. The boolean forFind is true if the query is a find query, or false for a move query.

Implements [gdcm::BaseRootQuery](#).

10.136.3.3 InitializeDataSet()

```
void gdcm::FindStudyRootQuery::InitializeDataSet (
    const EQueryLevel & inQueryLevel) [override], [virtual]
```

this function sets tag 8,52 to the appropriate value based on query level also fills in the right unique tags, as per the standard's requirements should allow for connection with dcmTk

Implements [gdcm::BaseRootQuery](#).

10.136.3.4 ValidateQuery()

```
bool gdcm::FindStudyRootQuery::ValidateQuery (
    bool inStrict = true) const [override], [virtual]
```

have to be able to ensure that (0008,0052) is set that the level is appropriate (ie, not setting PATIENT for a study query that the tags in the query match the right level (either required, unique, optional)

Implements [gdcm::BaseRootQuery](#).

10.136.4 Friends And Related Symbol Documentation

10.136.4.1 QueryFactory

```
friend class QueryFactory [friend]
```

References [QueryFactory](#).

Referenced by [QueryFactory](#).

The documentation for this class was generated from the following file:


- [gdcmFindStudyRootQuery.h](#)

10.137 gdcm::Fragment Class Reference


Class to represent a [Fragment](#).

```
#include <gdcmFragment.h>
```

Inheritance diagram for gdcm::Fragment:



Collaboration diagram for gdcm::Fragment:



Public Member Functions

- [Fragment](#) ()
- [VL ComputeLength](#) () const
- [VL GetLength](#) () const
- template<typename TSwap>
std::istream & [Read](#) (std::istream &is)
- template<typename TSwap>
std::istream & [ReadBacktrack](#) (std::istream &is)
- template<typename TSwap>
std::istream & [ReadPreValue](#) (std::istream &is)
- template<typename TSwap>
std::istream & [ReadValue](#) (std::istream &is)
- template<typename TSwap>
std::ostream & [Write](#) (std::ostream &os) const

Public Member Functions inherited from [gdcm::DataElement](#)

- [DataElement](#) (const [DataElement](#) &_val)
- [DataElement](#) (const [Tag](#) &t=[Tag](#)(0), const [VL](#) &vl=0, const [VR](#) &vr=[VR::INVALID](#))
- void [Clear](#) ()
Clear Data [Element](#) (make [Value](#) empty and invalidate [Tag](#) & [VR](#))
- void [Empty](#) ()
Make Data [Element](#) empty (no [Value](#))
- const [ByteValue](#) * [GetByteValue](#) () const
- template<typename TDE>
[VL GetLength](#) () const
- [SequenceOfFragments](#) * [GetSequenceOfFragments](#) ()
- const [SequenceOfFragments](#) * [GetSequenceOfFragments](#) () const
- [Tag](#) & [GetTag](#) ()
- const [Tag](#) & [GetTag](#) () const
Get [Tag](#).
- [Value](#) & [GetValue](#) ()
- [Value](#) const & [GetValue](#) () const
Set/Get [Value](#) (bytes array, SQ of items, SQ of fragments):
- [SmartPointer](#)< [SequenceOfItems](#) > [GetValueAsSQ](#) () const
- [VL](#) & [GetVL](#) ()
- const [VL](#) & [GetVL](#) () const
Get [VL](#).
- [VR](#) const & [GetVR](#) () const
- bool [IsEmpty](#) () const
Check if Data [Element](#) is empty.
- bool [IsUndefinedLength](#) () const
return if [Value](#) Length if of undefined length
- bool [operator<](#) (const [DataElement](#) &de) const
- [DataElement](#) & [operator=](#) (const [DataElement](#) &)=default
- bool [operator==](#) (const [DataElement](#) &de) const
- template<typename TDE, typename TSwap>
std::istream & [Read](#) (std::istream &is)

- template<typename TDE, typename TSwap>
std::istream & [ReadOrSkip](#) (std::istream &is, std::set< [Tag](#) > const &skiptags)
- template<typename TDE, typename TSwap>
std::istream & [ReadPreValue](#) (std::istream &is, std::set< [Tag](#) > const &skiptags)
- template<typename TDE, typename TSwap>
std::istream & [ReadValue](#) (std::istream &is, std::set< [Tag](#) > const &skiptags)
- template<typename TDE, typename TSwap>
std::istream & [ReadValueWithLength](#) (std::istream &is, [VL](#) &length, std::set< [Tag](#) > const &skiptags)
- template<typename TDE, typename TSwap>
std::istream & [ReadWithLength](#) (std::istream &is, [VL](#) &length)
- void [SetByteValue](#) (const char *array, [VL](#) length)
- void [SetTag](#) (const [Tag](#) &t)
- void [SetValue](#) ([Value](#) const &vl)
- void [SetVL](#) (const [VL](#) &vl)
- void [SetVLToUndefined](#) ()
- void [SetVR](#) ([VR](#) const &vr)
- template<typename TDE, typename TSwap>
const std::ostream & [Write](#) (std::ostream &os) const

Friends

- std::ostream & [operator<<](#) (std::ostream &os, const [Fragment](#) &val)

Additional Inherited Members

Protected Types inherited from [gdcm::DataElement](#)

- typedef [SmartPointer](#)< [Value](#) > [ValuePtr](#)

Protected Member Functions inherited from [gdcm::DataElement](#)

- void [SetValueFieldLength](#) ([VL](#) vl, bool readvalues)

Protected Attributes inherited from [gdcm::DataElement](#)

- [Tag](#) TagField
- [ValuePtr](#) ValueField
- [VL](#) ValueLengthField
- [VR](#) VRField

10.137.1 Detailed Description

Class to represent a [Fragment](#).

Examples

[DecompressImageMultiframe.cs](#), [DecompressJPEGFile.cs](#), [FixBrokenJ2K.cxx](#), [FixJAIBugJPEGLS.cxx](#), and [MpegVideoInfo.cs](#).

10.137.2 Constructor & Destructor Documentation

10.137.2.1 Fragment()

```
gdcmm::Fragment::Fragment () [inline]
```

References [gdcmm::DataElement::DataElement\(\)](#).

Referenced by [gdcmm::BasicOffsetTable::BasicOffsetTable\(\)](#), and [operator<<](#).

10.137.3 Member Function Documentation

10.137.3.1 ComputeLength()

```
VL gdcmm::Fragment::ComputeLength () const
```

10.137.3.2 GetLength()

```
VL gdcmm::Fragment::GetLength () const
```

10.137.3.3 Read()

```
template<typename TSwap>
std::istream & gdcmm::Fragment::Read (
    std::istream & is) [inline]
```

References [ReadPreValue\(\)](#), and [ReadValue\(\)](#).

Referenced by [gdcmm::SequenceOfFragments::ReadValue\(\)](#).

10.137.3.4 ReadBacktrack()

```
template<typename TSwap>
std::istream & gdcmm::Fragment::ReadBacktrack (
    std::istream & is) [inline]
```

References [gdcmm_assert](#), [gdcmmErrorMacro](#), [gdcmmWarningMacro](#), [gdcmm::ParseException::SetLastElement\(\)](#), [gdcmm::DataElement::TagField](#), [gdcmm::DataElement::ValueField](#), and [gdcmm::DataElement::ValueLengthField](#).

Referenced by [gdcmm::SequenceOfFragments::ReadValue\(\)](#).

10.137.3.5 ReadPreValue()

```
template<typename TSwap>
std::istream & gdcm::Fragment::ReadPreValue (
    std::istream & is) [inline]
```

References [gdcm::DataElement::TagField](#), and [gdcm::DataElement::ValueLengthField](#).

Referenced by [Read\(\)](#).

10.137.3.6 ReadValue()

```
template<typename TSwap>
std::istream & gdcm::Fragment::ReadValue (
    std::istream & is) [inline]
```

References [gdcmWarningMacro](#), [gdcm::ParseException::SetLastElement\(\)](#), [gdcm::DataElement::ValueField](#), and [gdcm::DataElement::ValueLengthField](#).

Referenced by [Read\(\)](#).

10.137.3.7 Write()

```
template<typename TSwap>
std::ostream & gdcm::Fragment::Write (
    std::ostream & os) const [inline]
```

References [gdcm::ByteValue::ComputeLength\(\)](#), [gdcm_assert](#), [gdcm::DataElement::GetByteValue\(\)](#), [gdcm::ByteValue::GetLength\(\)](#), [gdcm::DataElement::IsEmpty\(\)](#), [gdcm::DataElement::TagField](#), [gdcm::DataElement::ValueLengthField](#), [gdcm::ByteValue::Write\(\)](#), and [gdcm::VL::Write\(\)](#).

10.137.4 Friends And Related Symbol Documentation

10.137.4.1 operator<<

```
std::ostream & operator<< (
    std::ostream & os,
    const Fragment & val) [friend]
```

References [Fragment\(\)](#), [operator<<](#), [gdcm::DataElement::TagField](#), [gdcm::DataElement::ValueField](#), and [gdcm::DataElement::ValueLengthField](#).

Referenced by [operator<<](#).

The documentation for this class was generated from the following file:

- [gdcmFragment.h](#)

10.138 gdcm::Global Class Reference

[Global](#).

```
#include <gdcmGlobal.h>
```

Public Member Functions

- [Global](#) ()
- [Global](#) (const [Global](#) &_val)=delete
- [~Global](#) ()
- bool [Append](#) (const char *path)
- [Defs](#) const & [GetDefs](#) () const
- [Dicts](#) & [GetDicts](#) ()
- [Dicts](#) const & [GetDicts](#) () const
- bool [LoadResourcesFiles](#) ()
- [Global](#) & [operator=](#) (const [Global](#) &_val)=delete
- bool [Prepend](#) (const char *path)

Static Public Member Functions

- static [Global](#) & [GetInstance](#) ()
return the singleton instance

Protected Member Functions

- const char * [Locate](#) (const char *resfile) const
Locate a resource file.

Friends

- std::ostream & [operator<<](#) (std::ostream &_os, const [Global](#) &g)

10.138.1 Detailed Description

[Global](#).

Note

[Global](#) should be included in any translation unit that will use [Dict](#) or that implements the singleton pattern. It makes sure that the [Dict](#) singleton is created before and destroyed after all other singletons in GDCM.

Examples

[BasicAnonymizer.cs](#), [Cleaner.cs](#), [GenAllVR.cxx](#), [GenFakeIdentifyFile.cxx](#), [GenerateStandardSOPClasses.cxx](#), [PublicDict.cxx](#), [ReadAndPrintAttributes.cxx](#), and [TraverseModules.cxx](#).

10.138.2 Constructor & Destructor Documentation

10.138.2.1 Global() [1/2]

```
gdcm::Global::Global ()
```

Referenced by [Global\(\)](#), [GetInstance\(\)](#), [operator<<](#), and [operator=\(\)](#).

10.138.2.2 ~Global()

```
gdcm::Global::~~Global ()
```

10.138.2.3 Global() [2/2]

```
gdcm::Global::Global (  
    const Global & _val) [delete]
```

References [Global\(\)](#).

10.138.3 Member Function Documentation

10.138.3.1 Append()

```
bool gdcm::Global::Append (  
    const char * path)
```

Append path at the end of the path list

Warning

not thread safe !

10.138.3.2 GetDefs()

```
Defs const & gdcm::Global::GetDefs () const
```

retrieve the default/internal (Part 3) You need to explicitly call LoadResourcesFiles before

Examples

[GenerateStandardSOPClasses.cxx](#), and [TraverseModules.cxx](#).

10.138.3.3 GetDicts() [1/2]

```
Dicts & gdcm::Global::GetDicts ()
```

10.138.3.4 GetDicts() [2/2]

```
Dicts const & gdcm::Global::GetDicts () const
```

retrieve the default/internal dicts (Part 6) This dict is filled up at load time

Examples

[GenAllVR.cxx](#), [GenFakeIdentifyFile.cxx](#), [MrProtocol.cxx](#), [PublicDict.cxx](#), [ReadAndPrintAttributes.cxx](#), and [TraverseModules.cxx](#).

10.138.3.5 GetInstance()

```
Global & gdcm::Global::GetInstance () [static]
```

return the singleton instance

Examples

[BasicAnonymizer.cs](#), [Cleaner.cs](#), [GenAllVR.cxx](#), [GenFakeIdentifyFile.cxx](#), [GenerateStandardSOPClasses.cxx](#), [MrProtocol.cxx](#), [PublicDict.cxx](#), [ReadAndPrintAttributes.cxx](#), and [TraverseModules.cxx](#).

References [Global\(\)](#).

10.138.3.6 LoadResourcesFiles()

```
bool gdcm::Global::LoadResourcesFiles ()
```

Load all internal XML files, resource path need to have been set before calling this member function (see [Append/↔](#) Prepend members func)

Warning

not thread safe !

Examples

[BasicAnonymizer.cs](#), [Cleaner.cs](#), [ClinicalTrialIdentificationWorkflow.cs](#), [GenerateStandardSOPClasses.cxx](#), and [TraverseModules.cxx](#).

10.138.3.7 Locate()

```
const char * gdcm::Global::Locate (  
    const char * resfile) const [protected]
```

Locate a resource file.

10.138.3.8 operator=()

```
Global & gdcm::Global::operator= (  
    const Global & _val) [delete]
```

References [Global\(\)](#).

10.138.3.9 Prepend()

```
bool gdcm::Global::Prepend (  
    const char * path)
```

Prepend path at the beginning of the path list

Warning

not thread safe !

10.138.4 Friends And Related Symbol Documentation

10.138.4.1 operator<<

```
std::ostream & operator<< (  
    std::ostream & _os,  
    const Global & g) [friend]
```

References [Global\(\)](#).

The documentation for this class was generated from the following file:

- [gdcmGlobal.h](#)

10.139 gdcm::GroupDict Class Reference

Class to represent the mapping from group number to its abbreviation and name.

```
#include <gdcmGroupDict.h>
```

Public Types

- typedef std::vector< std::string > [GroupStringVector](#)

Public Member Functions

- [GroupDict](#) ()
- [~GroupDict](#) ()=default
- std::string const & [GetAbbreviation](#) (uint16_t num) const
- std::string const & [GetName](#) (uint16_t num) const
- size_t [Size](#) () const

Protected Member Functions

- void [Add](#) (std::string const &abbreviation, std::string const &name)
- void [Insert](#) (uint16_t num, std::string const &abbreviation, std::string const &name)

Friends

- std::ostream & [operator<<](#) (std::ostream &_os, const [GroupDict](#) &_val)

10.139.1 Detailed Description

Class to represent the mapping from group number to its abbreviation and name.

Note

Should I rewrite this class to use a std::map instead of std::vector for problem of memory consumption ?

10.139.2 Member Typedef Documentation

10.139.2.1 GroupStringVector

```
typedef std::vector<std::string> gdc::GroupDict::GroupStringVector
```

10.139.3 Constructor & Destructor Documentation

10.139.3.1 GroupDict()

```
gdc::GroupDict::GroupDict () [inline]
```

Referenced by [~GroupDict\(\)](#), [Insert\(\)](#), and [operator<<](#).

10.139.3.2 ~GroupDict()

```
gdcm::GroupDict::~~GroupDict () [default]
```

References [GroupDict\(\)](#), and [operator<<](#).

10.139.4 Member Function Documentation

10.139.4.1 Add()

```
void gdcm::GroupDict::Add (  
    std::string const & abbreviation,  
    std::string const & name) [protected]
```

10.139.4.2 GetAbbreviation()

```
std::string const & gdcm::GroupDict::GetAbbreviation (  
    uint16_t num) const
```

Referenced by [operator<<](#).

10.139.4.3 GetName()

```
std::string const & gdcm::GroupDict::GetName (  
    uint16_t num) const
```

Referenced by [operator<<](#).

10.139.4.4 Insert()

```
void gdcm::GroupDict::Insert (  
    uint16_t num,  
    std::string const & abbreviation,  
    std::string const & name) [protected]
```

References [GroupDict\(\)](#).

10.139.4.5 Size()

```
size_t gdcm::GroupDict::Size () const [inline]
```

References [gdcm_assert](#).

Referenced by [operator<<](#).

10.139.5 Friends And Related Symbol Documentation

10.139.5.1 operator<<

```
std::ostream & operator<< (
    std::ostream & _os,
    const GroupDict & _val) [friend]
```

References [GroupDict\(\)](#), [GetAbbreviation\(\)](#), [GetName\(\)](#), and [Size\(\)](#).

Referenced by [~GroupDict\(\)](#).

The documentation for this class was generated from the following file:

- [gdcmGroupDict.h](#)

10.140 gdcm::IconImageFilter Class Reference

[IconImageFilter](#).

```
#include <gdcmIconImageFilter.h>
```

Public Member Functions

- [IconImageFilter](#) ()
- [~IconImageFilter](#) ()
- bool [Extract](#) ()
Extract all Icon found in [File](#).
- [File](#) & [GetFile](#) ()
- const [File](#) & [GetFile](#) () const
- [IconImage](#) & [GetIconImage](#) (unsigned int i) const
- unsigned int [GetNumberOfIconImages](#) () const
Retrieve extract [IconImage](#) (need to call [Extract](#) first)
- void [SetFile](#) (const [File](#) &f)
Set/Get [File](#).

Protected Member Functions

- void [ExtractIconImages](#) ()
- void [ExtractVeprolIconImages](#) ()

10.140.1 Detailed Description

[IconImageFilter](#).

This filter will extract icons from a [File](#) This filter will loop over all known sequence (public and private) that may contains an [IconImage](#) and retrieve them. The filter will fails with a value of false if no icon can be found Since it handle both public and private icon type, one should not assume the icon is in uncompress form, some private vendor store private icon in JPEG8/JPEG12

Implementation details: This filter supports the following Icons:

- (0088,0200) Icon [Image](#) Sequence
- (0009,10,GEIIS) GE IIS Thumbnail Sequence
- (6003,10,GEMS_Ultrasound_ImageGroup_001) GEMS [Image](#) Thumbnail Sequence
- (0055,30,VEPRO VIF 3.0 DATA) Icon Data
- (0055,30,VEPRO VIM 5.0 DATA) ICONDATA2

Warning

the icon stored in those private attribute do not conform to definition of Icon [Image](#) Sequence (do not simply copy/paste). For example some private icon can be expressed as 12bits pixel, while the DICOM standard only allow 8bits icons.

See also

[ImageReader](#)

Examples

[ExtractIconFromFile.cxx](#).

10.140.2 Constructor & Destructor Documentation

10.140.2.1 IconImageFilter()

```
gdcm::IconImageFilter::IconImageFilter ()
```

10.140.2.2 ~IconImageFilter()

```
gdcm::IconImageFilter::~~IconImageFilter ()
```

10.140.3 Member Function Documentation

10.140.3.1 Extract()

```
bool gdcm::IconImageFilter::Extract ()
```

Extract all Icon found in [File](#).

Examples

[ExtractIconFromFile.cxx](#).

10.140.3.2 ExtractIconImages()

```
void gdcm::IconImageFilter::ExtractIconImages () [protected]
```

10.140.3.3 ExtractVeprolIconImages()

```
void gdcm::IconImageFilter::ExtractVeproIconImages () [protected]
```

10.140.3.4 GetFile() [1/2]

```
File & gdcm::IconImageFilter::GetFile () [inline]
```

10.140.3.5 GetFile() [2/2]

```
const File & gdcm::IconImageFilter::GetFile () const [inline]
```

10.140.3.6 GetIconImage()

```
IconImage & gdcm::IconImageFilter::GetIconImage (  
    unsigned int i) const
```

Examples

[ExtractIconFromFile.cxx](#).

10.140.3.7 GetNumberOfIconImages()

```
unsigned int gdcm::IconImageFilter::GetNumberOfIconImages () const
```

Retrieve extract [IconImage](#) (need to call Extract first)

Examples

[ExtractIconFromFile.cxx](#).

10.140.3.8 SetFile()

```
void gdcm::IconImageFilter::SetFile (
    const File & f) [inline]
```

Set/Get [File](#).

Examples

[ExtractIconFromFile.cxx](#).

The documentation for this class was generated from the following file:

- [gdcmIconImageFilter.h](#)

10.141 gdcm::IconImageGenerator Class Reference

[IconImageGenerator](#).

```
#include <gdcmIconImageGenerator.h>
```

Public Member Functions

- [IconImageGenerator](#) ()
- [~IconImageGenerator](#) ()
- void [AutoPixelMinMax](#) (bool b)
- void [ConvertRGBToPaletteColor](#) (bool b)
- bool [Generate](#) ()
 - Generate Icon.*
- const [IconImage](#) & [GetIconImage](#) () const
 - Retrieve generated Icon.*
- [Pixmap](#) & [GetPixmap](#) ()
- const [Pixmap](#) & [GetPixmap](#) () const
- void [SetOutputDimensions](#) (const unsigned int dims[2])
 - Set Target dimension of output Icon.*
- void [SetOutsideValuePixel](#) (double v)
- void [SetPixelMinMax](#) (double min, double max)
- void [SetPixmap](#) (const [Pixmap](#) &p)
 - Set/Get File.*

10.141.1 Detailed Description

[IconImageGenerator](#).

This filter will generate a valid Icon from the Pixel Data element (an instance of [Pixmap](#)). To generate a valid Icon, one is only allowed the following Photometric Interpretation:

- MONOCHROME1
- MONOCHROME2
- PALETTE_COLOR

The Pixel Bits Allocated is restricted to 8bits, therefore 16 bits image needs to be rescaled. By default the filter will use the full scalar range of 16bits image to rescale to unsigned 8bits. This may not be ideal for some situation, in which case the API `SetPixelMinMax` can be used to overwrite the default min,max interval used.

See also

[ImageReader](#)

Examples

[ExtractIconFromFile.cxx](#).

10.141.2 Constructor & Destructor Documentation

10.141.2.1 IconImageGenerator()

```
gdcm::IconImageGenerator::IconImageGenerator ()
```

10.141.2.2 ~IconImageGenerator()

```
gdcm::IconImageGenerator::~~IconImageGenerator ()
```

10.141.3 Member Function Documentation

10.141.3.1 AutoPixelMinMax()

```
void gdcm::IconImageGenerator::AutoPixelMinMax (  
    bool b)
```

Instead of explicitly specifying the min/max value for the rescale operation, let the internal mechanism compute the min/max of icon and rescale to best appropriate.

Examples

[ExtractIconFromFile.cxx](#).

10.141.3.2 ConvertRGBToPaletteColor()

```
void gdcm::IconImageGenerator::ConvertRGBToPaletteColor (
    bool b)
```

Converting from RGB to PALETTE_COLOR can be a slow operation. However DICOM standard requires that color icon be described as palette. Set this boolean to false only if you understand the consequences. default value is true, false generates invalid Icon [Image](#) Sequence

10.141.3.3 Generate()

```
bool gdcm::IconImageGenerator::Generate ()
```

Generate Icon.

Examples

[ExtractIconFromFile.cxx](#).

10.141.3.4 GetIconImage()

```
const IconImage & gdcm::IconImageGenerator::GetIconImage () const [inline]
```

Retrieve generated Icon.

Examples

[ExtractIconFromFile.cxx](#).

10.141.3.5 GetPixmap() [1/2]

```
Pixmap & gdcm::IconImageGenerator::GetPixmap () [inline]
```

10.141.3.6 GetPixmap() [2/2]

```
const Pixmap & gdcm::IconImageGenerator::GetPixmap () const [inline]
```

10.141.3.7 SetOutputDimensions()

```
void gdcm::IconImageGenerator::SetOutputDimensions (
    const unsigned int dims[2])
```

Set Target dimension of output Icon.

Examples

[ExtractIconFromFile.cxx](#).

10.141.3.8 SetOutsideValuePixel()

```
void gdcmm::IconImageGenerator::SetOutsideValuePixel (
    double v)
```

Set a pixel value that should be discarded. This happens typically for CT image, where a pixel has been used to pad outside the image (see Pixel Padding [Value](#)). Requires `AutoPixelMinMax(true)`

10.141.3.9 SetPixelMinMax()

```
void gdcmm::IconImageGenerator::SetPixelMinMax (
    double min,
    double max)
```

Override default min/max to compute best rescale for 16bits -> 8bits downscale. Typically those values can be read from the `SmallestImagePixelValue` `LargestImagePixelValue` DICOM attribute.

10.141.3.10 SetPixmap()

```
void gdcmm::IconImageGenerator::SetPixmap (
    const Pixmap & p) [inline]
```

Set/Get [File](#).

Examples

[ExtractIconFromFile.cxx](#).

The documentation for this class was generated from the following file:

- [gdcmmIconImageGenerator.h](#)

10.142 gdcmm::ignore_char Struct Reference

```
#include <gdcmmElement.h>
```

Public Member Functions

- [ignore_char](#) (char c)

Public Attributes

- char [m_char](#)

10.142.1 Constructor & Destructor Documentation

10.142.1.1 ignore_char()

```
gdcm::ignore_char::ignore_char (  
    char c) [inline]
```

References [m_char](#).

10.142.2 Member Data Documentation

10.142.2.1 m_char

```
char gdcm::ignore_char::m_char
```

Referenced by [ignore_char\(\)](#), and [gdcm::operator>>\(\)](#).

The documentation for this struct was generated from the following file:


- [gdcmElement.h](#)

10.143 gdcm::Image Class Reference

[Image](#).

```
#include <gdcmImage.h>
```

Inheritance diagram for gdcm::Image:



Public Member Functions inherited from [gdcm::Pixmap](#)

- [Pixmap](#) ()
- [~Pixmap](#) () override
- bool [AreOverlaysInPixelData](#) () const override
returns if Overlays are stored in the unused bit of the pixel data:
- [Curve](#) & [GetCurve](#) (size_t i=0)
Curve: group 50xx.
- const [Curve](#) & [GetCurve](#) (size_t i=0) const
- [IconImage](#) & [GetIconImage](#) ()
- const [IconImage](#) & [GetIconImage](#) () const
Set/Get Icon Image.
- size_t [GetNumberOfCurves](#) () const
- size_t [GetNumberOfOverlays](#) () const
- [Overlay](#) & [GetOverlay](#) (size_t i=0)
Overlay: group 60xx.
- const [Overlay](#) & [GetOverlay](#) (size_t i=0) const
- void [Print](#) (std::ostream &) const override
- void [RemoveOverlay](#) (size_t i)
- void [SetIconImage](#) ([IconImage](#) const &ii)
- void [SetNumberOfCurves](#) (size_t n)
- void [SetNumberOfOverlays](#) (size_t n)
- bool [UnusedBitsPresentInPixelData](#) () const override
returns if there are unused bits in the pixel data

Public Member Functions inherited from [gdcm::Bitmap](#)

- [Bitmap](#) ()
- [~Bitmap](#) () override
- void [Clear](#) ()
- bool [GetBuffer](#) (char *buffer) const
Access the raw data.
- unsigned long [GetBufferLength](#) () const
- unsigned int [GetColumns](#) () const
- [DataElement](#) & [GetDataElement](#) ()
- const [DataElement](#) & [GetDataElement](#) () const
- unsigned int [GetDimension](#) (unsigned int idx) const
- const unsigned int * [GetDimensions](#) () const
Return the dimension of the pixel data, first dimension (x), then 2nd (y), then 3rd (z)...
- [LookupTable](#) & [GetLUT](#) ()
- const [LookupTable](#) & [GetLUT](#) () const
- bool [GetNeedByteSwap](#) () const
INTERNAL do not use.
- unsigned int [GetNumberOfDimensions](#) () const
Return the number of dimension of the pixel data bytes; for example 2 for a 2D matrices of values.
- const [PhotometricInterpretation](#) & [GetPhotometricInterpretation](#) () const
return the photometric interpretation
- [PixelFormat](#) & [GetPixelFormat](#) ()

- const [PixelFormat](#) & [GetPixelFormat](#) () const
Get/Set [PixelFormat](#).
- unsigned int [GetPlanarConfiguration](#) () const
return the planar configuration
- unsigned int [GetRows](#) () const
- const [TransferSyntax](#) & [GetTransferSyntax](#) () const
- bool [IsEmpty](#) () const
- bool [IsLossy](#) () const
Return whether or not the image was compressed using a lossy compressor or not.
- bool [IsTransferSyntaxCompatible](#) ([TransferSyntax](#) const &ts) const
- void [SetColumns](#) (unsigned int col)
- void [SetDataElement](#) ([DataElement](#) const &de)
- void [SetDimension](#) (unsigned int idx, unsigned int dim)
- void [SetDimensions](#) (const unsigned int dims[3])
- void [SetLossyFlag](#) (bool f)
Specifically set that the image was compressed using a lossy compression mechanism.
- void [SetLUT](#) ([LookupTable](#) const &lut)
Set/Get LUT.
- void [SetNeedByteSwap](#) (bool b)
- void [SetNumberOfDimensions](#) (unsigned int dim)
- void [SetPhotometricInterpretation](#) ([PhotometricInterpretation](#) const &pi)
- void [SetPixelFormat](#) ([PixelFormat](#) const &pf)
- void [SetPlanarConfiguration](#) (unsigned int pc)
- void [SetRows](#) (unsigned int rows)
- void [SetTransferSyntax](#) ([TransferSyntax](#) const &ts)
Transfer syntax.

Public Member Functions inherited from [gdcm::Object](#)

- [Object](#) ()
- [Object](#) (const [Object](#) &)
Special requirement for copy/cstor, assignment operator.
- virtual [~Object](#) ()
- void [operator=](#) (const [Object](#) &)

Additional Inherited Members

Protected Types inherited from [gdcm::Bitmap](#)

- typedef [SmartPointer](#)< [LookupTable](#) > [LUTPtr](#)

Protected Member Functions inherited from [gdcm::Bitmap](#)

- bool [ComputeLossyFlag](#) ()
- bool [GetBuffer2](#) (std::ostream &os) const
- bool [TryJPEG2000Codec](#) (char *buffer, bool &lossyflag) const
- bool [TryJPEG2000Codec2](#) (std::ostream &os) const
- bool [TryJPEGCodec](#) (char *buffer, bool &lossyflag) const
- bool [TryJPEGCodec2](#) (std::ostream &os) const
- bool [TryJPEGLSCodec](#) (char *buffer, bool &lossyflag) const
- bool [TryKAKADUCodec](#) (char *buffer, bool &lossyflag) const
- bool [TryPVRGCodec](#) (char *buffer, bool &lossyflag) const
- bool [TryRAWCodec](#) (char *buffer, bool &lossyflag) const
- bool [TryRLECodec](#) (char *buffer, bool &lossyflag) const

Protected Member Functions inherited from [gdcm::Object](#)

- void [Register](#) ()
- void [UnRegister](#) ()

Protected Attributes inherited from [gdcm::Pixmap](#)

- std::vector< [Curve](#) > [Curves](#)
- [SmartPointer](#)< [IconImage](#) > [Icon](#)
- std::vector< [Overlay](#) > [Overlays](#)

Protected Attributes inherited from [gdcm::Bitmap](#)

- std::vector< unsigned int > [Dimensions](#)
- bool [LossyFlag](#)
- [LUTPtr](#) [LUT](#)
- bool [NeedByteSwap](#)
- unsigned int [NumberOfDimensions](#)
- [PixelFormat](#) [PF](#)
- [PhotometricInterpretation](#) [PI](#)
- [DataElement](#) [PixelData](#)
- unsigned int [PlanarConfiguration](#)
- [TransferSyntax](#) [TS](#)

10.143.1 Detailed Description

[Image](#).

This is the container for an [Image](#) in the general sense. From this container you should be able to request information like:

- Origin
- Dimension
- [PixelFormat](#) ... But also to retrieve the image as a raw buffer (char *) Since we have to deal with both RAW data and JPEG stream (which internally encode all the above information) this API might seems redundant. One way to solve that would be to subclass [Image](#) with [JPEGImage](#) which would from the stream extract the header info and fill it to please [Image](#)...well except origin for instance

Basically you can see it as a storage for the Pixel Data element (7fe0,0010).

Warning

This class does some heuristics to guess the [Spacing](#) but is not compatible with DICOM CP-586. In case of doubt use [PixmapReader](#) instead

See also

[ImageReader](#) [PixmapReader](#)

Examples

[BasicImageAnonymizer.cs](#), [CompressImage.cxx](#), [CompressLossyJPEG.cs](#), [ConvertToQImage.cxx](#), [CreateARGBImage.cxx](#), [CreateCMYKImage.cxx](#), [DecompressImage.cs](#), [DecompressImageMultiframe.cs](#), [DecompressJPEGFile.cs](#), [ExtractIconFromFile.cxx](#), [FixJAIBugJPEGLS.cxx](#), [GenFakeImage.cxx](#), [GetArray.cs](#), [GetJPEGSamplePrecision.cxx](#), [GetSubSequenceData.cxx](#), [HelloVizWorld.cxx](#), [MpegVideoInfo.cs](#), [PatchFile.cxx](#), [PrintLUT.cxx](#), [ReadMultiTimesException.cxx](#), [RescaleImage.cs](#), [TemplateEmptyImage.cxx](#), [csa2img.cxx](#), [iU22tomultisc.cxx](#), and [threadgdcm.cxx](#).

10.143.2 Constructor & Destructor Documentation

10.143.2.1 Image()

```
gdcm::Image::Image () [inline]
```

10.143.2.2 ~Image()

```
gdcm::Image::~Image () [override], [default]
```

10.143.3 Member Function Documentation

10.143.3.1 GetDirectionCosines() [1/2]

```
const double * gdcm::Image::GetDirectionCosines () const
```

Return a 6-tuples specifying the direction cosines A default value of (1,0,0,0,1,0) will be return when the direction cosines was not specified.

10.143.3.2 GetDirectionCosines() [2/2]

```
double gdcm::Image::GetDirectionCosines (
    unsigned int idx) const
```

10.143.3.3 GetIntercept()

```
double gdcm::Image::GetIntercept () const [inline]
```

10.143.3.4 GetOrigin() [1/2]

```
const double * gdcm::Image::GetOrigin () const
```

Return a 3-tuples specifying the origin Will return (0,0,0) if the origin was not specified.

Examples

[HelloVizWorld.cxx](#).

10.143.3.5 GetOrigin() [2/2]

```
double gdcm::Image::GetOrigin (
    unsigned int idx) const
```

10.143.3.6 GetSlope()

```
double gdcm::Image::GetSlope () const [inline]
```

10.143.3.7 GetSpacing() [1/2]

```
const double * gdcm::Image::GetSpacing () const
```

Return a 3-tuples specifying the spacing NOTE: 3rd value can be an arbitrary 1 value when the spacing was not specified (ex. 2D image). WARNING: when the spacing is not specifier, a default value of 1 will be returned

10.143.3.8 GetSpacing() [2/2]

```
double gdcM::Image::GetSpacing (
    unsigned int idx) const
```

10.143.3.9 Print()

```
void gdcM::Image::Print (
    std::ostream & os) const [override], [virtual]
```

print

Reimplemented from [gdcM::Bitmap](#).

Examples

[CompressImage.cxx](#), and [PatchFile.cxx](#).

10.143.3.10 SetDirectionCosines() [1/3]

```
void gdcM::Image::SetDirectionCosines (
    const double dircos[6])
```

10.143.3.11 SetDirectionCosines() [2/3]

```
void gdcM::Image::SetDirectionCosines (
    const float dircos[6])
```

10.143.3.12 SetDirectionCosines() [3/3]

```
void gdcM::Image::SetDirectionCosines (
    unsigned int idx,
    double dircos)
```

10.143.3.13 SetIntercept()

```
void gdcM::Image::SetIntercept (
    double intercept) [inline]
```

intercept

Examples

[TemplateEmptyImage.cxx](#).

10.143.3.14 SetOrigin() [1/3]

```
void gdcm::Image::SetOrigin (
    const double origin[3])
```

10.143.3.15 SetOrigin() [2/3]

```
void gdcm::Image::SetOrigin (
    const float origin[3])
```

10.143.3.16 SetOrigin() [3/3]

```
void gdcm::Image::SetOrigin (
    unsigned int idx,
    double ori)
```

10.143.3.17 SetSlope()

```
void gdcm::Image::SetSlope (
    double slope) [inline]
```

slope

Examples

[TemplateEmptyImage.cxx](#).

10.143.3.18 SetSpacing() [1/2]

```
void gdcm::Image::SetSpacing (
    const double spacing[3])
```

Examples

[csa2img.cxx](#), and [iU22tomultisc.cxx](#).

10.143.3.19 SetSpacing() [2/2]

```
void gdcm::Image::SetSpacing (
    unsigned int idx,
    double spacing)
```

The documentation for this class was generated from the following file:


- [gdcmImage.h](#)

10.144 gdcm::ImageApplyLookupTable Class Reference


[ImageApplyLookupTable](#) class.

```
#include <gdcmImageApplyLookupTable.h>
```

Inheritance diagram for gdcm::ImageApplyLookupTable:



Collaboration diagram for gdcm::ImageApplyLookupTable:



Public Member Functions

- [ImageApplyLookupTable](#) ()
- [~ImageApplyLookupTable](#) ()
- bool [Apply](#) ()
 - Apply.*
- void [SetRGB8](#) (bool b)
 - RGB8 ?*

Public Member Functions inherited from [gdcm::ImageToImageFilter](#)

- [ImageToImageFilter](#) ()
- [~ImageToImageFilter](#) ()=default
- [Image](#) & [GetInput](#) ()
- const [Image](#) & [GetOutput](#) () const

Get Output image.

Public Member Functions inherited from [gdcm::PixmapToPixmapFilter](#)

- [PixmapToPixmapFilter](#) ()
 - [~PixmapToPixmapFilter](#) ()=default
 - [Pixmap](#) & [GetInput](#) ()
 - const [Pixmap](#) & [GetOutput](#) () const
- Get Output image.*
- const [Pixmap](#) & [GetOutputAsPixmap](#) () const

Public Member Functions inherited from [gdcm::BitmapToBitmapFilter](#)

- [BitmapToBitmapFilter](#) ()
 - [~BitmapToBitmapFilter](#) ()=default
 - const [Bitmap](#) & [GetOutput](#) () const
- Get Output image.*
- const [Bitmap](#) & [GetOutputAsBitmap](#) () const
 - void [SetInput](#) (const [Bitmap](#) &image)
- Set input image.*

Additional Inherited Members

Protected Attributes inherited from [gdcm::BitmapToBitmapFilter](#)

- [SmartPointer](#)< [Bitmap](#) > [Input](#)
- [SmartPointer](#)< [Bitmap](#) > [Output](#)

10.144.1 Detailed Description

[ImageApplyLookupTable](#) class.

It applies the LUT the PixelData (only PALETTE_COLOR images) Output will be a [PhotometricInterpretation](#)=RGB image

10.144.2 Constructor & Destructor Documentation

10.144.2.1 ImageApplyLookupTable()

```
gdcm::ImageApplyLookupTable::ImageApplyLookupTable ()
```

10.144.2.2 ~ImageApplyLookupTable()

```
gdcm::ImageApplyLookupTable::~ImageApplyLookupTable ()
```

10.144.3 Member Function Documentation

10.144.3.1 Apply()

```
bool gdcm::ImageApplyLookupTable::Apply ()
```

Apply.

10.144.3.2 SetRGB8()

```
void gdcm::ImageApplyLookupTable::SetRGB8 (  
    bool b)
```

RGB8 ?

The documentation for this class was generated from the following file:


- [gdcmImageApplyLookupTable.h](#)

10.145 gdcm::ImageChangePhotometricInterpretation Class Reference


[ImageChangePhotometricInterpretation](#) class.

```
#include <gdcmImageChangePhotometricInterpretation.h>
```

Inheritance diagram for gdcm::ImageChangePhotometricInterpretation:



Collaboration diagram for `gdcm::ImageChangePhotometricInterpretation`:



Public Member Functions

- `ImageChangePhotometricInterpretation ()`
- `~ImageChangePhotometricInterpretation ()=default`
- `bool Change ()`
Change.
- `const PhotometricInterpretation & GetPhotometricInterpretation () const`
- `void SetPhotometricInterpretation (PhotometricInterpretation const &pi)`
Set/Get requested PhotometricInterpretation.

Public Member Functions inherited from [gdcm::ImageToImageFilter](#)

- [ImageToImageFilter](#) ()
- [~ImageToImageFilter](#) ()=default
- [Image](#) & [GetInput](#) ()
- const [Image](#) & [GetOutput](#) () const

Get Output image.

Public Member Functions inherited from [gdcm::PixmapToPixmapFilter](#)

- [PixmapToPixmapFilter](#) ()
- [~PixmapToPixmapFilter](#) ()=default
- [Pixmap](#) & [GetInput](#) ()
- const [Pixmap](#) & [GetOutput](#) () const
- const [Pixmap](#) & [GetOutputAsPixmap](#) () const

Get Output image.

Public Member Functions inherited from [gdcm::BitmapToBitmapFilter](#)

- [BitmapToBitmapFilter](#) ()
- [~BitmapToBitmapFilter](#) ()=default
- const [Bitmap](#) & [GetOutput](#) () const
- const [Bitmap](#) & [GetOutputAsBitmap](#) () const
- void [SetInput](#) (const [Bitmap](#) &image)

Get Output image.

Set input image.

Static Public Member Functions

- template<typename T>
static void [RGB2YBR](#) (T ybr[3], const T rgb[3], unsigned short storedbits=8)
- template<typename T>
static void [YBR2RGB](#) (T rgb[3], const T ybr[3], unsigned short storedbits=8)

Protected Member Functions

- bool [ChangeMonochrome](#) ()
- bool [ChangeRGB2YBR](#) ()
- bool [ChangeYBR2RGB](#) ()

Additional Inherited Members**Protected Attributes inherited from [gdcm::BitmapToBitmapFilter](#)**

- [SmartPointer](#)< [Bitmap](#) > [Input](#)
- [SmartPointer](#)< [Bitmap](#) > [Output](#)

10.145.1 Detailed Description

[ImageChangePhotometricInterpretation](#) class.

Class to change the Photometric Interpretation of an input DICOM

10.145.2 Constructor & Destructor Documentation

10.145.2.1 ImageChangePhotometricInterpretation()

```
gdcm::ImageChangePhotometricInterpretation::ImageChangePhotometricInterpretation () [inline]
```

10.145.2.2 ~ImageChangePhotometricInterpretation()

```
gdcm::ImageChangePhotometricInterpretation::~~ImageChangePhotometricInterpretation () [default]
```

10.145.3 Member Function Documentation

10.145.3.1 Change()

```
bool gdcm::ImageChangePhotometricInterpretation::Change ()
```

Change.

References [RGB2YBR\(\)](#), and [YBR2RGB\(\)](#).

10.145.3.2 ChangeMonochrome()

```
bool gdcm::ImageChangePhotometricInterpretation::ChangeMonochrome () [protected]
```

10.145.3.3 ChangeRGB2YBR()

```
bool gdcm::ImageChangePhotometricInterpretation::ChangeRGB2YBR () [protected]
```

10.145.3.4 ChangeYBR2RGB()

```
bool gdcm::ImageChangePhotometricInterpretation::ChangeYBR2RGB () [protected]
```


10.145.3.5 GetPhotometricInterpretation()

```
const PhotometricInterpretation & gdcm::ImageChangePhotometricInterpretation::GetPhotometricInterpretation () const [inline]
```

10.145.3.6 RGB2YBR()

```
template<typename T>
void gdcm::ImageChangePhotometricInterpretation::RGB2YBR (
    T ybr[3],
    const T rgb[3],
    unsigned short storedbits = 8) [static]
```

colorspace conversion (based on CCIR Recommendation 601-2) -> T.871

References [gdcm::Clamp\(\)](#), [gdcm_assert](#), and [gdcm::Round\(\)](#).

Referenced by [Change\(\)](#).

10.145.3.7 SetPhotometricInterpretation()

```
void gdcm::ImageChangePhotometricInterpretation::SetPhotometricInterpretation (
    PhotometricInterpretation const & pi) [inline]
```

Set/Get requested [PhotometricInterpretation](#).

10.145.3.8 YBR2RGB()

```
template<typename T>
void gdcm::ImageChangePhotometricInterpretation::YBR2RGB (
    T rgb[3],
    const T ybr[3],
    unsigned short storedbits = 8) [static]
```

References [gdcm::Clamp\(\)](#), [gdcm_assert](#), and [gdcm::Round\(\)](#).

Referenced by [Change\(\)](#).

The documentation for this class was generated from the following file:


- [gdcmImageChangePhotometricInterpretation.h](#)

10.146 gdcm::ImageChangePlanarConfiguration Class Reference


[ImageChangePlanarConfiguration](#) class.

```
#include <gdcmImageChangePlanarConfiguration.h>
```

Inheritance diagram for `gdcm::ImageChangePlanarConfiguration`:



Collaboration diagram for gdcm::ImageChangePlanarConfiguration:



Public Member Functions

- [ImageChangePlanarConfiguration](#) ()
- [~ImageChangePlanarConfiguration](#) ()=default
- bool [Change](#) ()
Change.
- unsigned int [GetPlanarConfiguration](#) () const
- void [SetPlanarConfiguration](#) (unsigned int pc)
Set/Get requested PlanarConfiguration.

Public Member Functions inherited from [gdcm::ImageToImageFilter](#)

- [ImageToImageFilter](#) ()
- [~ImageToImageFilter](#) ()=default
- [Image](#) & [GetInput](#) ()
- const [Image](#) & [GetOutput](#) () const

Get Output image.

Public Member Functions inherited from [gdcm::PixmapToPixmapFilter](#)

- [PixmapToPixmapFilter](#) ()
 - [~PixmapToPixmapFilter](#) ()=default
 - [Pixmap](#) & [GetInput](#) ()
 - const [Pixmap](#) & [GetOutput](#) () const
- Get Output image.*
- const [Pixmap](#) & [GetOutputAsPixmap](#) () const

Public Member Functions inherited from [gdcm::BitmapToBitmapFilter](#)

- [BitmapToBitmapFilter](#) ()
 - [~BitmapToBitmapFilter](#) ()=default
 - const [Bitmap](#) & [GetOutput](#) () const
- Get Output image.*
- const [Bitmap](#) & [GetOutputAsBitmap](#) () const
 - void [SetInput](#) (const [Bitmap](#) &image)

Set input image.

Static Public Member Functions

- template<typename T>
static size_t [RGBPixelsToRGBPlanes](#) (T *r, T *g, T *b, const T *rgb, size_t s)
- template<typename T>
static size_t [RGBPlanesToRGBPixels](#) (T *out, const T *r, const T *g, const T *b, size_t s)

Additional Inherited Members

Protected Attributes inherited from [gdcm::BitmapToBitmapFilter](#)

- [SmartPointer](#)< [Bitmap](#) > [Input](#)
- [SmartPointer](#)< [Bitmap](#) > [Output](#)

10.146.1 Detailed Description

[ImageChangePlanarConfiguration](#) class.

Class to change the Planar configuration of an input DICOM By default it will change into the more usual representation: PlanarConfiguration = 0

10.146.2 Constructor & Destructor Documentation

10.146.2.1 ImageChangePlanarConfiguration()

```
gdcm::ImageChangePlanarConfiguration::ImageChangePlanarConfiguration () [inline]
```

10.146.2.2 ~ImageChangePlanarConfiguration()

```
gdcm::ImageChangePlanarConfiguration::~~ImageChangePlanarConfiguration () [default]
```

10.146.3 Member Function Documentation

10.146.3.1 Change()

```
bool gdcm::ImageChangePlanarConfiguration::Change ()
```

Change.

10.146.3.2 GetPlanarConfiguration()

```
unsigned int gdcm::ImageChangePlanarConfiguration::GetPlanarConfiguration () const [inline]
```

10.146.3.3 RGBPixelsToRGBPlanes()

```
template<typename T>
size_t gdcm::ImageChangePlanarConfiguration::RGBPixelsToRGBPlanes (
    T * r,
    T * g,
    T * b,
    const T * rgb,
    size_t s) [static]
```

Convert a regular RGB pixel image (R,G,B,R,G,B...) into a planar R,G,B image (R,R...,G,G...,B,B)

Warning

this works on a frame basis, you need to loop over all frames in multiple frames image to apply this function

References [gdcm_assert](#).

10.146.3.4 RGBPlanesToRGBPixels()

```
template<typename T>
size_t gdcM::ImageChangePlanarConfiguration::RGBPlanesToRGBPixels (
    T * out,
    const T * r,
    const T * g,
    const T * b,
    size_t s) [static]
```

s is the size of one plane (r,g or b). Thus the output buffer needs to be at least 3*s bytes long s can be seen as the number of RGB pixels in the output

References [gdcM_assert](#).

10.146.3.5 SetPlanarConfiguration()

```
void gdcM::ImageChangePlanarConfiguration::SetPlanarConfiguration (
    unsigned int pc) [inline]
```

Set/Get requested PlanarConfiguration.

The documentation for this class was generated from the following file:


- [gdcMImageChangePlanarConfiguration.h](#)

10.147 gdcM::ImageChangeTransferSyntax Class Reference


[ImageChangeTransferSyntax](#) class.

```
#include <gdcMImageChangeTransferSyntax.h>
```

Inheritance diagram for gdcm::ImageChangeTransferSyntax:



Collaboration diagram for `gdcm::ImageChangeTransferSyntax`:



Public Member Functions

- `ImageChangeTransferSyntax ()`
- `~ImageChangeTransferSyntax ()=default`
- `bool Change ()`
Change.
- `const TransferSyntax & GetTransferSyntax () const`
Get Transfer Syntax.
- `void SetCompressIconImage (bool b)`
- `void SetForce (bool f)`

- void [SetTransferSyntax](#) (const [TransferSyntax](#) &ts)
Set target Transfer Syntax.
- void [SetUserCodec](#) ([ImageCodec](#) *ic)

Public Member Functions inherited from [gdcm::ImageToImageFilter](#)

- [ImageToImageFilter](#) ()
- [~ImageToImageFilter](#) ()=default
- [Image](#) & [GetInput](#) ()
- const [Image](#) & [GetOutput](#) () const
Get Output image.

Public Member Functions inherited from [gdcm::PixmapToPixmapFilter](#)

- [PixmapToPixmapFilter](#) ()
- [~PixmapToPixmapFilter](#) ()=default
- [Pixmap](#) & [GetInput](#) ()
- const [Pixmap](#) & [GetOutput](#) () const
Get Output image.
- const [Pixmap](#) & [GetOutputAsPixmap](#) () const

Public Member Functions inherited from [gdcm::BitmapToBitmapFilter](#)

- [BitmapToBitmapFilter](#) ()
- [~BitmapToBitmapFilter](#) ()=default
- const [Bitmap](#) & [GetOutput](#) () const
Get Output image.
- const [Bitmap](#) & [GetOutputAsBitmap](#) () const
- void [SetInput](#) (const [Bitmap](#) &image)
Set input image.

Protected Member Functions

- bool [TryJPEG2000Codec](#) (const [DataElement](#) &pixelde, [Bitmap](#) const &input, [Bitmap](#) &output)
- bool [TryJPEGCodec](#) (const [DataElement](#) &pixelde, [Bitmap](#) const &input, [Bitmap](#) &output)
- bool [TryJPEGLSCCodec](#) (const [DataElement](#) &pixelde, [Bitmap](#) const &input, [Bitmap](#) &output)
- bool [TryRAWCodec](#) (const [DataElement](#) &pixelde, [Bitmap](#) const &input, [Bitmap](#) &output)
- bool [TryRLECodec](#) (const [DataElement](#) &pixelde, [Bitmap](#) const &input, [Bitmap](#) &output)

Additional Inherited Members

Protected Attributes inherited from [gdcm::BitmapToBitmapFilter](#)

- [SmartPointer](#)< [Bitmap](#) > [Input](#)
- [SmartPointer](#)< [Bitmap](#) > [Output](#)

10.147.1 Detailed Description

[ImageChangeTransferSyntax](#) class.

Class to change the transfer syntax of an input DICOM

If only Force param is set but no input [TransferSyntax](#) is set, it is assumed that user only wants to inspect encapsulated stream (advanced dev. option).

When using UserCodec it is very important that the [TransferSyntax](#) (as set in SetTransferSyntax) is actually understood by UserCodec (ie. UserCodec->CanCode(TransferSyntax)). Otherwise the behavior is to use a default codec.

See also

[JPEGCodec](#) [JPEGLSCodec](#) [JPEG2000Codec](#)

Examples

[BasicImageAnonymizer.cs](#), [CompressImage.cxx](#), [CompressLossyJPEG.cs](#), [ExplicitLittleEndian.cs](#), and [StandardizeFiles.cs](#).

10.147.2 Constructor & Destructor Documentation

10.147.2.1 ImageChangeTransferSyntax()

```
gdcm::ImageChangeTransferSyntax::ImageChangeTransferSyntax () [inline]
```

10.147.2.2 ~ImageChangeTransferSyntax()

```
gdcm::ImageChangeTransferSyntax::~~ImageChangeTransferSyntax () [default]
```

10.147.3 Member Function Documentation

10.147.3.1 Change()

```
bool gdcm::ImageChangeTransferSyntax::Change ()
```

Change.

Examples

[BasicImageAnonymizer.cs](#), [CompressImage.cxx](#), [CompressLossyJPEG.cs](#), [ExplicitLittleEndian.cs](#), and [StandardizeFiles.cs](#).

10.147.3.2 GetTransferSyntax()

```
const TransferSyntax & gdcm::ImageChangeTransferSyntax::GetTransferSyntax () const [inline]
```

Get Transfer Syntax.

10.147.3.3 SetCompressIconImage()

```
void gdcm::ImageChangeTransferSyntax::SetCompressIconImage (  
    bool b) [inline]
```

Decide whether or not to also compress the Icon [Image](#) using the same Transfer Syntax. Default is to simply decompress icon image

Examples

[StandardizeFiles.cs](#).

10.147.3.4 SetForce()

```
void gdcm::ImageChangeTransferSyntax::SetForce (  
    bool f) [inline]
```

When target Transfer Syntax is identical to input target syntax, no operation is actually done. This is an issue when someone wants to re-compress using GDCM internal implementation a JPEG (for example) image

Examples

[ExplicitLittleEndian.cs](#), and [StandardizeFiles.cs](#).

10.147.3.5 SetTransferSyntax()

```
void gdcm::ImageChangeTransferSyntax::SetTransferSyntax (  
    const TransferSyntax & ts) [inline]
```

Set target Transfer Syntax.

Examples

[BasicImageAnonymizer.cs](#), [CompressImage.cxx](#), [CompressLossyJPEG.cs](#), [ExplicitLittleEndian.cs](#), and [StandardizeFiles.cs](#).

10.147.3.6 SetUserCodec()

```
void gdcm::ImageChangeTransferSyntax::SetUserCodec (
    ImageCodec * ic) [inline]
```

Allow user to specify exactly which codec to use. this is needed to specify special qualities or compression option.

Warning

if the codec 'ic' is not compatible with the [TransferSyntax](#) requested, it will not be used. It is the user responsibility to check that `UserCodec->CanCode(TransferSyntax)`

Examples

[CompressLossyJPEG.cs](#).

10.147.3.7 TryJPEG2000Codec()

```
bool gdcm::ImageChangeTransferSyntax::TryJPEG2000Codec (
    const DataElement & pixelde,
    Bitmap const & input,
    Bitmap & output) [protected]
```

10.147.3.8 TryJPEGCodec()

```
bool gdcm::ImageChangeTransferSyntax::TryJPEGCodec (
    const DataElement & pixelde,
    Bitmap const & input,
    Bitmap & output) [protected]
```

10.147.3.9 TryJPEGLSCodec()

```
bool gdcm::ImageChangeTransferSyntax::TryJPEGLSCodec (
    const DataElement & pixelde,
    Bitmap const & input,
    Bitmap & output) [protected]
```

10.147.3.10 TryRAWCodec()

```
bool gdcm::ImageChangeTransferSyntax::TryRAWCodec (
    const DataElement & pixelde,
    Bitmap const & input,
    Bitmap & output) [protected]
```

10.147.3.11 TryRLECodec()

```
bool gdcm::ImageChangeTransferSyntax::TryRLECodec (
    const DataElement & pixelde,
    Bitmap const & input,
    Bitmap & output) [protected]
```

The documentation for this class was generated from the following file:


- [gdcmImageChangeTransferSyntax.h](#)

10.148 gdcm::ImageCodec Class Reference


[ImageCodec](#).

```
#include <gdcmImageCodec.h>
```

Inheritance diagram for gdcm::ImageCodec:



Collaboration diagram for gdcm::ImageCodec:



Public Member Functions

- [ImageCodec](#) ()
- [~ImageCodec](#) () override
- bool [CanCode](#) ([TransferSyntax](#) const &) const override
Return whether this coder support this transfer syntax (can code it)
- bool [CanDecode](#) ([TransferSyntax](#) const &) const override
Return whether this decoder support this transfer syntax (can decode it)
- bool [CleanupUnusedBits](#) (char *data, size_t datalen)
- virtual [ImageCodec](#) * [Clone](#) () const =0
- bool [Decode](#) ([DataElement](#) const &is_, [DataElement](#) &os) override
Decode.
- const unsigned int * [GetDimensions](#) () const
- virtual bool [GetHeaderInfo](#) (std::istream &is_, [TransferSyntax](#) &ts)
- bool [GetLossyFlag](#) () const
- const [LookupTable](#) & [GetLUT](#) () const
- bool [GetNeedByteSwap](#) () const
- unsigned int [GetNumberOfDimensions](#) () const
- const [PhotometricInterpretation](#) & [GetPhotometricInterpretation](#) () const
- [PixelFormat](#) & [GetPixelFormat](#) ()
- const [PixelFormat](#) & [GetPixelFormat](#) () const
- unsigned int [GetPlanarConfiguration](#) () const
- bool [IsLossy](#) () const
- void [SetDimensions](#) (const std::vector< unsigned int > &d)
- void [SetDimensions](#) (const unsigned int d[3])
- void [SetLossyFlag](#) (bool l)
- void [SetLUT](#) ([LookupTable](#) const &lut)
- void [SetNeedByteSwap](#) (bool b)
- void [SetNeedOverlayCleanup](#) (bool b)
- void [SetNumberOfDimensions](#) (unsigned int dim)
- void [SetPhotometricInterpretation](#) ([PhotometricInterpretation](#) const &pi)
- virtual void [SetPixelFormat](#) ([PixelFormat](#) const &pf)
- void [SetPlanarConfiguration](#) (unsigned int pc)

Public Member Functions inherited from [gdcm::Coder](#)

- virtual [~Coder](#) ()=default
- virtual bool [Code](#) ([DataElement](#) const &in_, [DataElement](#) &out_)
Code.

Public Member Functions inherited from [gdcm::Decoder](#)

- virtual [~Decoder](#) ()=default

Protected Types

- typedef [SmartPointer](#)< [LookupTable](#) > [LUTPtr](#)

Protected Member Functions

- virtual bool [AppendFrameEncode](#) (std::ostream &out, const char *data, size_t datalen)
- virtual bool [AppendRowEncode](#) (std::ostream &out, const char *data, size_t datalen)
- bool [DecodeByStreams](#) (std::istream &is_, std::ostream &os) override
- bool [DoByteSwap](#) (std::istream &is_, std::ostream &os)
- bool [DoInvertMonochrome](#) (std::istream &is_, std::ostream &os)
- bool [DoOverlayCleanup](#) (std::istream &is_, std::ostream &os)
- bool [DoPaddedCompositePixelCode](#) (std::istream &is_, std::ostream &os)
- bool [DoPlanarConfiguration](#) (std::istream &is_, std::ostream &os)
- bool [DoSimpleCopy](#) (std::istream &is_, std::ostream &os)
- bool [DoYBR](#) (std::istream &is_, std::ostream &os)
- bool [DoYBRFull422](#) (std::istream &is_, std::ostream &os)
- virtual bool [IsFrameEncoder](#) ()
- virtual bool [IsRowEncoder](#) ()
- virtual bool [IsValid](#) ([PhotometricInterpretation](#) const &pi)
- virtual bool [StartEncode](#) (std::ostream &os)
- virtual bool [StopEncode](#) (std::ostream &os)

Protected Member Functions inherited from [gdcm::Coder](#)

- virtual bool [InternalCode](#) (const char *bv, unsigned long len, std::ostream &os)

Protected Attributes

- unsigned int [Dimensions](#) [3]
- bool [LossyFlag](#)
- [LUTPtr](#) LUT
- bool [NeedByteSwap](#)
- bool [NeedOverlayCleanup](#)
- unsigned int [NumberOfDimensions](#)
- [PixelFormat](#) PF
- [PhotometricInterpretation](#) PI
- unsigned int [PlanarConfiguration](#)
- bool [RequestPaddedCompositePixelCode](#)
- bool [RequestPlanarConfiguration](#)

Friends

- class [FileChangeTransferSyntax](#)
- class [ImageChangePhotometricInterpretation](#)

10.148.1 Detailed Description

[ImageCodec](#).

Note

Main codec, this is a central place for all implementation

Examples

[FileChangeTSLossy.cs](#).

10.148.2 Member Typedef Documentation

10.148.2.1 LUTPtr

```
typedef SmartPointer<LookupTable> gdcm::ImageCodec::LUTPtr [protected]
```

10.148.3 Constructor & Destructor Documentation

10.148.3.1 ImageCodec()

```
gdcm::ImageCodec::ImageCodec ()
```

Referenced by [Clone\(\)](#), [gdcm::JPEG2000Codec::Clone\(\)](#), [gdcm::JPEGCodec::Clone\(\)](#), [gdcm::JPEGLSCodec::Clone\(\)](#), [gdcm::KAKADUCodec::Clone\(\)](#), [gdcm::PGXCodec::Clone\(\)](#), [gdcm::PNMCodec::Clone\(\)](#), [gdcm::PVRGCodec::Clone\(\)](#), [gdcm::RAWCodec::Clone\(\)](#), and [gdcm::RLECodec::Clone\(\)](#).

10.148.3.2 ~ImageCodec()

```
gdcm::ImageCodec::~~ImageCodec () [override]
```

10.148.4 Member Function Documentation

10.148.4.1 AppendFrameEncode()

```
virtual bool gdcm::ImageCodec::AppendFrameEncode (
    std::ostream & out,
    const char * data,
    size_t datalen) [protected], [virtual]
```

Reimplemented in [gdcm::JPEG2000Codec](#), [gdcm::JPEGCodec](#), [gdcm::JPEGLSCodec](#), and [gdcm::RLECodec](#).

10.148.4.2 AppendRowEncode()

```
virtual bool gdcm::ImageCodec::AppendRowEncode (
    std::ostream & out,
    const char * data,
    size_t datalen) [protected], [virtual]
```

Reimplemented in [gdcm::JPEG2000Codec](#), [gdcm::JPEGCodec](#), [gdcm::JPEGLSCodec](#), and [gdcm::RLECodec](#).

10.148.4.3 CanCode()

```
bool gdcm::ImageCodec::CanCode (
    TransferSyntax const & ) const [inline], [override], [virtual]
```

Return whether this coder support this transfer syntax (can code it)

Implements [gdcm::Coder](#).

Reimplemented in [gdcm::JPEG2000Codec](#), [gdcm::JPEGCodec](#), [gdcm::JPEGLSCodec](#), [gdcm::KAKADUCodec](#), [gdcm::PGXCodec](#), [gdcm::PNMCodec](#), [gdcm::PVRGCodec](#), [gdcm::RAWCodec](#), and [gdcm::RLECodec](#).

10.148.4.4 CanDecode()

```
bool gdcm::ImageCodec::CanDecode (
    TransferSyntax const & ) const [inline], [override], [virtual]
```

Return whether this decoder support this transfer syntax (can decode it)

Implements [gdcm::Decoder](#).

Reimplemented in [gdcm::JPEG2000Codec](#), [gdcm::JPEGCodec](#), [gdcm::JPEGLSCodec](#), [gdcm::KAKADUCodec](#), [gdcm::PGXCodec](#), [gdcm::PNMCodec](#), [gdcm::PVRGCodec](#), [gdcm::RAWCodec](#), and [gdcm::RLECodec](#).

10.148.4.5 CleanupUnusedBits()

```
bool gdcm::ImageCodec::CleanupUnusedBits (
    char * data,
    size_t datalen)
```

10.148.4.6 Clone()

```
virtual ImageCodec * gdcm::ImageCodec::Clone () const [pure virtual]
```

Implemented in [gdcm::JPEG2000Codec](#), [gdcm::JPEGCodec](#), [gdcm::JPEGLSCodec](#), [gdcm::KAKADUCodec](#), [gdcm::PGXCodec](#), [gdcm::PNMCodec](#), [gdcm::PVRGCodec](#), [gdcm::RAWCodec](#), and [gdcm::RLECodec](#).

References [ImageCodec\(\)](#).

10.148.4.7 Decode()

```
bool gdcM::ImageCodec::Decode (
    DataElement const & ,
    DataElement & ) [override], [virtual]
```

Decode.

Reimplemented from [gdcM::Decoder](#).

Reimplemented in [gdcM::JPEG2000Codec](#), [gdcM::JPEGCodec](#), [gdcM::JPEGLSCodec](#), [gdcM::KAKADUCodec](#), [gdcM::PVRGCodec](#), [gdcM::RAWCodec](#), and [gdcM::RLECodec](#).

10.148.4.8 DecodeByStreams()

```
bool gdcM::ImageCodec::DecodeByStreams (
    std::istream & is_,
    std::ostream & os) [override], [protected], [virtual]
```

Reimplemented from [gdcM::Decoder](#).

Reimplemented in [gdcM::JPEG12Codec](#), [gdcM::JPEG16Codec](#), [gdcM::JPEG2000Codec](#), [gdcM::JPEG8Codec](#), [gdcM::JPEGCodec](#), [gdcM::RAWCodec](#), and [gdcM::RLECodec](#).

10.148.4.9 DoByteSwap()

```
bool gdcM::ImageCodec::DoByteSwap (
    std::istream & is_,
    std::ostream & os) [protected]
```

10.148.4.10 DoInvertMonochrome()

```
bool gdcM::ImageCodec::DoInvertMonochrome (
    std::istream & is_,
    std::ostream & os) [protected]
```

10.148.4.11 DoOverlayCleanup()

```
bool gdcM::ImageCodec::DoOverlayCleanup (
    std::istream & is_,
    std::ostream & os) [protected]
```

10.148.4.12 DoPaddedCompositePixelCode()

```
bool gdcM::ImageCodec::DoPaddedCompositePixelCode (
    std::istream & is_,
    std::ostream & os) [protected]
```

10.148.4.13 DoPlanarConfiguration()

```
bool gdcm::ImageCodec::DoPlanarConfiguration (
    std::istream & is_,
    std::ostream & os) [protected]
```

10.148.4.14 DoSimpleCopy()

```
bool gdcm::ImageCodec::DoSimpleCopy (
    std::istream & is_,
    std::ostream & os) [protected]
```

10.148.4.15 DoYBR()

```
bool gdcm::ImageCodec::DoYBR (
    std::istream & is_,
    std::ostream & os) [protected]
```

10.148.4.16 DoYBRFull422()

```
bool gdcm::ImageCodec::DoYBRFull422 (
    std::istream & is_,
    std::ostream & os) [protected]
```

10.148.4.17 GetDimensions()

```
const unsigned int * gdcm::ImageCodec::GetDimensions () const [inline]
```

References [Dimensions](#).

10.148.4.18 GetHeaderInfo()

```
virtual bool gdcm::ImageCodec::GetHeaderInfo (
    std::istream & is_,
    TransferSyntax & ts) [virtual]
```

Reimplemented in [gdcm::JPEG12Codec](#), [gdcm::JPEG16Codec](#), [gdcm::JPEG2000Codec](#), [gdcm::JPEG8Codec](#), [gdcm::JPEGCodec](#), [gdcm::JPEGLSCodec](#), [gdcm::PGXCodec](#), [gdcm::PNMCodec](#), [gdcm::RAWCodec](#), and [gdcm::RLECodec](#).

10.148.4.19 GetLossyFlag()

```
bool gdcm::ImageCodec::GetLossyFlag () const
```

10.148.4.20 GetLUT()

```
const LookupTable & gdcM::ImageCodec::GetLUT () const [inline]
```

References [LUT](#).

10.148.4.21 GetNeedByteSwap()

```
bool gdcM::ImageCodec::GetNeedByteSwap () const [inline]
```

References [NeedByteSwap](#).

10.148.4.22 GetNumberOfDimensions()

```
unsigned int gdcM::ImageCodec::GetNumberOfDimensions () const
```

10.148.4.23 GetPhotometricInterpretation()

```
const PhotometricInterpretation & gdcM::ImageCodec::GetPhotometricInterpretation () const
```

10.148.4.24 GetPixelFormat() [1/2]

```
PixelFormat & gdcM::ImageCodec::GetPixelFormat () [inline]
```

Examples

[GetJPEGSamplePrecision.cxx](#).

References [PF](#).

10.148.4.25 GetPixelFormat() [2/2]

```
const PixelFormat & gdcM::ImageCodec::GetPixelFormat () const [inline]
```

References [PF](#).

10.148.4.26 GetPlanarConfiguration()

```
unsigned int gdcM::ImageCodec::GetPlanarConfiguration () const [inline]
```

References [PlanarConfiguration](#).

10.148.4.27 IsFrameEncoder()

```
virtual bool gdcm::ImageCodec::IsFrameEncoder () [protected], [virtual]
```

Reimplemented in [gdcm::JPEG2000Codec](#), [gdcm::JPEGCodec](#), [gdcm::JPEGLSCodec](#), and [gdcm::RLECodec](#).

10.148.4.28 IsLossy()

```
bool gdcm::ImageCodec::IsLossy () const
```

10.148.4.29 IsRowEncoder()

```
virtual bool gdcm::ImageCodec::IsRowEncoder () [protected], [virtual]
```

Reimplemented in [gdcm::JPEG2000Codec](#), [gdcm::JPEGCodec](#), [gdcm::JPEGLSCodec](#), and [gdcm::RLECodec](#).

10.148.4.30 IsValid()

```
virtual bool gdcm::ImageCodec::IsValid (
    PhotometricInterpretation const & pi) [protected], [virtual]
```

Reimplemented in [gdcm::JPEGCodec](#).

10.148.4.31 SetDimensions() [1/2]

```
void gdcm::ImageCodec::SetDimensions (
    const std::vector< unsigned int > & d)
```

10.148.4.32 SetDimensions() [2/2]

```
void gdcm::ImageCodec::SetDimensions (
    const unsigned int d[3])
```

Examples

[ExtractIconFromFile.cxx](#).

10.148.4.33 SetLossyFlag()

```
void gdcm::ImageCodec::SetLossyFlag (
    bool l)
```

10.148.4.34 SetLUT()

```
void gdcM::ImageCodec::SetLUT (
    LookupTable const & lut) [inline]
```

Examples

[ExtractIconFromFile.cxx](#).

References [LUT](#).

10.148.4.35 SetNeedByteSwap()

```
void gdcM::ImageCodec::SetNeedByteSwap (
    bool b) [inline]
```

References [NeedByteSwap](#).

10.148.4.36 SetNeedOverlayCleanup()

```
void gdcM::ImageCodec::SetNeedOverlayCleanup (
    bool b) [inline]
```

References [NeedOverlayCleanup](#).

10.148.4.37 SetNumberOfDimensions()

```
void gdcM::ImageCodec::SetNumberOfDimensions (
    unsigned int dim)
```

10.148.4.38 SetPhotometricInterpretation()

```
void gdcM::ImageCodec::SetPhotometricInterpretation (
    PhotometricInterpretation const & pi)
```

Examples

[ExtractIconFromFile.cxx](#).

10.148.4.39 SetPixelFormat()

```
virtual void gdcm::ImageCodec::SetPixelFormat (
    PixelFormat const & pf) [inline], [virtual]
```

Reimplemented in [gdcm::JPEGCodec](#).

Examples

[ExtractIconFromFile.cxx](#).

References [PF](#).

10.148.4.40 SetPlanarConfiguration()

```
void gdcm::ImageCodec::SetPlanarConfiguration (
    unsigned int pc) [inline]
```

References [gdcm_assert](#), and [PlanarConfiguration](#).

10.148.4.41 StartEncode()

```
virtual bool gdcm::ImageCodec::StartEncode (
    std::ostream & os) [protected], [virtual]
```

Reimplemented in [gdcm::JPEG2000Codec](#), [gdcm::JPEGCodec](#), [gdcm::JPEGLSCodec](#), and [gdcm::RLECodec](#).

10.148.4.42 StopEncode()

```
virtual bool gdcm::ImageCodec::StopEncode (
    std::ostream & os) [protected], [virtual]
```

Reimplemented in [gdcm::JPEG2000Codec](#), [gdcm::JPEGCodec](#), [gdcm::JPEGLSCodec](#), and [gdcm::RLECodec](#).

10.148.5 Friends And Related Symbol Documentation

10.148.5.1 FileChangeTransferSyntax

```
friend class FileChangeTransferSyntax [friend]
```

This is a high level API to encode in a streaming fashion. Each plugin will handle differently the caching mechanism so that a limited memory is used when compressing dataset. [Codec](#) will fall into two categories:

- Full row encoder: only a single scanline (row) of data is needed to be loaded at a time;
- Full frame encoder (default): a complete frame (row x col) is needed to be loaded at a time

References [FileChangeTransferSyntax](#).

Referenced by [FileChangeTransferSyntax](#).

10.148.5.2 ImageChangePhotometricInterpretation

```
friend class ImageChangePhotometricInterpretation [friend]
```

References [ImageChangePhotometricInterpretation](#).

Referenced by [ImageChangePhotometricInterpretation](#).

10.148.6 Member Data Documentation

10.148.6.1 Dimensions

```
unsigned int gdcm::ImageCodec::Dimensions[3] [protected]
```

Referenced by [GetDimensions\(\)](#).

10.148.6.2 LossyFlag

```
bool gdcm::ImageCodec::LossyFlag [protected]
```

10.148.6.3 LUT

```
LUTPtr gdcm::ImageCodec::LUT [protected]
```

Referenced by [GetLUT\(\)](#), and [SetLUT\(\)](#).

10.148.6.4 NeedByteSwap

```
bool gdcm::ImageCodec::NeedByteSwap [protected]
```

Referenced by [GetNeedByteSwap\(\)](#), and [SetNeedByteSwap\(\)](#).

10.148.6.5 NeedOverlayCleanup

```
bool gdcm::ImageCodec::NeedOverlayCleanup [protected]
```

Referenced by [SetNeedOverlayCleanup\(\)](#).

10.148.6.6 NumberOfDimensions

```
unsigned int gdcm::ImageCodec::NumberOfDimensions [protected]
```


10.148.6.7 PF

`PixelFormat` `gdcm::ImageCodec::PF` [protected]

Referenced by [GetPixelFormat\(\)](#), [GetPixelFormat\(\)](#), and [SetPixelFormat\(\)](#).

10.148.6.8 PI

`PhotometricInterpretation` `gdcm::ImageCodec::PI` [protected]

10.148.6.9 PlanarConfiguration

`unsigned int` `gdcm::ImageCodec::PlanarConfiguration` [protected]

Referenced by [GetPlanarConfiguration\(\)](#), and [SetPlanarConfiguration\(\)](#).

10.148.6.10 RequestPaddedCompositePixelCode

`bool` `gdcm::ImageCodec::RequestPaddedCompositePixelCode` [protected]

10.148.6.11 RequestPlanarConfiguration

`bool` `gdcm::ImageCodec::RequestPlanarConfiguration` [protected]

The documentation for this class was generated from the following file:

- [gdcmImageCodec.h](#)

10.149 gdcm::ImageConverter Class Reference

[Image](#) Converter.

```
#include <gdcmImageConverter.h>
```

Public Member Functions

- [ImageConverter](#) ()
- [~ImageConverter](#) ()
- void [Convert](#) ()
- const [Image](#) & [GetOutput](#) () const
- void [SetInput](#) ([Image](#) const &input)

10.149.1 Detailed Description

[Image](#) Converter.

Note

This is the class used to convert from on [Image](#) to another This is typically used to convert let say YBR JPEG compressed [Image](#) to a RAW RGB [Image](#). So that the buffer can be directly pass to third party application. This filter is application level and not integrated directly in GDCM

10.149.2 Constructor & Destructor Documentation

10.149.2.1 ImageConverter()

```
gdcm::ImageConverter::ImageConverter ()
```

10.149.2.2 ~ImageConverter()

```
gdcm::ImageConverter::~~ImageConverter ()
```

10.149.3 Member Function Documentation

10.149.3.1 Convert()

```
void gdcm::ImageConverter::Convert ()
```

10.149.3.2 GetOutput()

```
const Image & gdcm::ImageConverter::GetOutput () const
```

10.149.3.3 SetInput()

```
void gdcm::ImageConverter::SetInput (  
    Image const & input)
```

The documentation for this class was generated from the following file:

- [gdcmImageConverter.h](#)

10.150 gdcm::ImageFragmentSplitter Class Reference


[ImageFragmentSplitter](#) class.

```
#include <gdcmImageFragmentSplitter.h>
```

Inheritance diagram for gdcm::ImageFragmentSplitter:



Collaboration diagram for `gdcm::ImageFragmentSplitter`:



Public Member Functions

- `ImageFragmentSplitter ()`
- `~ImageFragmentSplitter ()=default`
- `unsigned int GetFragmentSizeMax () const`
- `void SetForce (bool f)`
- `void SetFragmentSizeMax (unsigned int fragsize)`
FragmentSizeMax needs to be an even number.
- `bool Split ()`
Split.

Public Member Functions inherited from [gdcm::ImageToImageFilter](#)

- [ImageToImageFilter](#) ()
- [~ImageToImageFilter](#) ()=default
- [Image](#) & [GetInput](#) ()
- const [Image](#) & [GetOutput](#) () const

Get Output image.

Public Member Functions inherited from [gdcm::PixmapToPixmapFilter](#)

- [PixmapToPixmapFilter](#) ()
- [~PixmapToPixmapFilter](#) ()=default
- [Pixmap](#) & [GetInput](#) ()
- const [Pixmap](#) & [GetOutput](#) () const
- const [Pixmap](#) & [GetOutputAsPixmap](#) () const

Get Output image.

Public Member Functions inherited from [gdcm::BitmapToBitmapFilter](#)

- [BitmapToBitmapFilter](#) ()
- [~BitmapToBitmapFilter](#) ()=default
- const [Bitmap](#) & [GetOutput](#) () const
- const [Bitmap](#) & [GetOutputAsBitmap](#) () const
- void [SetInput](#) (const [Bitmap](#) &image)

Get Output image.

Set input image.

Additional Inherited Members**Protected Attributes inherited from [gdcm::BitmapToBitmapFilter](#)**

- [SmartPointer](#)< [Bitmap](#) > [Input](#)
- [SmartPointer](#)< [Bitmap](#) > [Output](#)

10.150.1 Detailed Description

[ImageFragmentSplitter](#) class.

For single frame image, DICOM standard allow splitting the frame into multiple fragments

10.150.2 Constructor & Destructor Documentation**10.150.2.1 [ImageFragmentSplitter](#)()**

```
gdcm::ImageFragmentSplitter::ImageFragmentSplitter () [inline]
```

10.150.2.2 ~ImageFragmentSplitter()

```
gdcm::ImageFragmentSplitter::~~ImageFragmentSplitter () [default]
```

10.150.3 Member Function Documentation

10.150.3.1 GetFragmentSizeMax()

```
unsigned int gdcm::ImageFragmentSplitter::GetFragmentSizeMax () const [inline]
```

10.150.3.2 SetForce()

```
void gdcm::ImageFragmentSplitter::SetForce (
    bool f) [inline]
```

When file already has all it's segment < FragmentSizeMax there is not need to run the filter. Unless the user explicitly say 'force' recomputation !

10.150.3.3 SetFragmentSizeMax()

```
void gdcm::ImageFragmentSplitter::SetFragmentSizeMax (
    unsigned int fragsize)
```

FragmentSizeMax needs to be an even number.

10.150.3.4 Split()

```
bool gdcm::ImageFragmentSplitter::Split ()
```

Split.

The documentation for this class was generated from the following file:

- [gdcmImageFragmentSplitter.h](#)

10.151 gdcm::ImageHelper Class Reference

[ImageHelper](#) (internal class, not intended for user level)

```
#include <gdcmImageHelper.h>
```

Static Public Member Functions

- static [MediaStorage](#) [ComputeMediaStorageFromModality](#) (const char *modality, unsigned int dimension=2, [PixelFormat](#) const &pf=[PixelFormat](#)(), [PhotometricInterpretation](#) const &pi=[PhotometricInterpretation](#)(), double rescaleintercept=0, double rescaleslope=1)

Moved from [MediaStorage](#) here, since we need extra info stored in [PixelFormat](#) & [PhotometricInterpretation](#).

- static bool [ComputeSpacingFromImagePositionPatient](#) (const std::vector< double > &imageposition, std::vector< double > &spacing)

DO NOT USE.

- static std::vector< unsigned int > [GetDimensionsValue](#) (const [File](#) &f)
- static bool [GetDirectionCosinesFromDataSet](#) ([DataSet](#) const &ds, std::vector< double > &dircos)
- static std::vector< double > [GetDirectionCosinesValue](#) ([File](#) const &f)
- static bool [GetForcePixelSpacing](#) ()
- static bool [GetForceRescaleInterceptSlope](#) ()
- static [SmartPointer< LookupTable >](#) [GetLUT](#) ([File](#) const &f)

returns the lookup table of an image file

- static std::vector< double > [GetOriginValue](#) ([File](#) const &f)

Set/Get Origin (IPP) from/to a file.

- static [PhotometricInterpretation](#) [GetPhotometricInterpretationValue](#) ([File](#) const &f)
- static [PixelFormat](#) [GetPixelFormatValue](#) (const [File](#) &f)
- static unsigned int [GetPlanarConfigurationValue](#) (const [File](#) &f)
- static bool [GetPMSRescaleInterceptSlope](#) ()
- static const [ByteValue](#) * [GetPointerFromElement](#) ([Tag](#) const &tag, [File](#) const &f)
- static bool [GetRealWorldValueMappingContent](#) ([File](#) const &f, [RealWorldValueMappingContent](#) &rwvmc)
- static std::vector< double > [GetRescaleInterceptSlopeValue](#) ([File](#) const &f)
- static bool [GetSecondaryCaptureImagePlaneModule](#) ()
- static std::vector< double > [GetSpacingValue](#) ([File](#) const &f)

Set/Get [Spacing](#) from/to a [File](#).

- static void [SetDimensionsValue](#) ([File](#) &f, const [Pixmap](#) &img)
- static void [SetDirectionCosinesValue](#) ([DataSet](#) &ds, const std::vector< double > &dircos)
- static void [SetForcePixelSpacing](#) (bool)
- static void [SetForceRescaleInterceptSlope](#) (bool)
- static void [SetOriginValue](#) ([DataSet](#) &ds, const [Image](#) &img)
- static void [SetPMSRescaleInterceptSlope](#) (bool)
- static void [SetRescaleInterceptSlopeValue](#) ([File](#) &f, const [Image](#) &img)
- static void [SetSecondaryCaptureImagePlaneModule](#) (bool)
- static void [SetSpacingValue](#) ([DataSet](#) &ds, const std::vector< double > &spacing)

Static Protected Member Functions

- static [Tag](#) [GetSpacingTagFromMediaStorage](#) ([MediaStorage](#) const &ms)
- static [Tag](#) [GetZSpacingTagFromMediaStorage](#) ([MediaStorage](#) const &ms)

10.151.1 Detailed Description

[ImageHelper](#) (internal class, not intended for user level)

Helper for writing World images in DICOM. DICOM has a 'template' approach to image where MR [Image](#) Storage are distinct object from Enhanced MR [Image](#) Storage. For example the Pixel [Spacing](#) in one object is not at the same position (ie [Tag](#)) as in the other this class is the central (read: fragile) place where all the dispatching is done from a unified view of a world image (typically VTK or ITK point of view) down to the low level DICOM point of view.

Warning

: do not expect the API of this class to be maintained at any point, since as Modalities are added the API might have to be augmented or behavior changed to cope with new modalities.

Examples

[ExtractImageRegion.cs](#), [ExtractImageRegionWithLUT.cs](#), and [ExtractOneFrame.cs](#).

10.151.2 Member Function Documentation

10.151.2.1 ComputeMediaStorageFromModality()

```
MediaStorage gdcm::ImageHelper::ComputeMediaStorageFromModality (
    const char * modality,
    unsigned int dimension = 2,
    PixelFormat const & pf = PixelFormat(),
    PhotometricInterpretation const & pi = PhotometricInterpretation(),
    double rescaleintercept = 0,
    double rescaleslope = 1) [static]
```

Moved from [MediaStorage](#) here, since we need extra info stored in [PixelFormat](#) & [PhotometricInterpretation](#).

10.151.2.2 ComputeSpacingFromImagePositionPatient()

```
bool gdcm::ImageHelper::ComputeSpacingFromImagePositionPatient (
    const std::vector< double > & imageposition,
    std::vector< double > & spacing) [static]
```

DO NOT USE.

10.151.2.3 GetDimensionsValue()

```
std::vector< unsigned int > gdcm::ImageHelper::GetDimensionsValue (
    const File & f) [static]
```

This function checks tags (0x0028, 0x0010) and (0x0028, 0x0011) for the rows and columns of the image in pixels (as opposed to actual distances). The output is {col , row}

Examples

[ExtractImageRegion.cs](#), [ExtractImageRegionWithLUT.cs](#), [ExtractOneFrame.cs](#), [Extracting_All_Resolution.cxx](#), [Fake_Image_Using_Stream_Image_Writer.cxx](#), and [StreamImageReaderTest.cxx](#).

10.151.2.4 GetDirectionCosinesFromDataSet()

```
bool gdcm::ImageHelper::GetDirectionCosinesFromDataSet (
    DataSet const & ds,
    std::vector< double > & dircos) [static]
```

10.151.2.5 GetDirectionCosinesValue()

```
std::vector< double > gdcm::ImageHelper::GetDirectionCosinesValue (
    File const & f) [static]
```

Get Direction Cosines (IOP) from/to a file Requires a file because mediastorage must be known

10.151.2.6 GetForcePixelSpacing()

```
bool gdcm::ImageHelper::GetForcePixelSpacing () [static]
```

10.151.2.7 GetForceRescaleInterceptSlope()

```
bool gdcm::ImageHelper::GetForceRescaleInterceptSlope () [static]
```

10.151.2.8 GetLUT()

```
SmartPointer< LookupTable > gdcm::ImageHelper::GetLUT (
    File const & f) [static]
```

returns the lookup table of an image file

10.151.2.9 GetOriginValue()

```
std::vector< double > gdcm::ImageHelper::GetOriginValue (
    File const & f) [static]
```

Set/Get Origin (IPP) from/to a file.

10.151.2.10 GetPhotometricInterpretationValue()

```
PhotometricInterpretation gdcm::ImageHelper::GetPhotometricInterpretationValue (
    File const & f) [static]
```

Examples

[ExtractImageRegion.cs](#).

10.151.2.11 GetPixelFormatValue()

```
PixelFormat gdcM::ImageHelper::GetPixelFormatValue (
    const File & f) [static]
```

This function returns pixel information about an image from its dataset That includes samples per pixel and bit depth (in that order)

Examples

[ExtractImageRegion.cs](#), [ExtractImageRegionWithLUT.cs](#), and [ExtractOneFrame.cs](#).

10.151.2.12 GetPlanarConfigurationValue()

```
unsigned int gdcM::ImageHelper::GetPlanarConfigurationValue (
    const File & f) [static]
```

10.151.2.13 GetPMSRescaleInterceptSlope()

```
bool gdcM::ImageHelper::GetPMSRescaleInterceptSlope () [static]
```

10.151.2.14 GetPointerFromElement()

```
const ByteValue * gdcM::ImageHelper::GetPointerFromElement (
    Tag const & tag,
    File const & f) [static]
```

10.151.2.15 GetRealWorldValueMappingContent()

```
bool gdcM::ImageHelper::GetRealWorldValueMappingContent (
    File const & f,
    RealWorldValueMappingContent & rwvmc) [static]
```

10.151.2.16 GetRescaleInterceptSlopeValue()

```
std::vector< double > gdcM::ImageHelper::GetRescaleInterceptSlopeValue (
    File const & f) [static]
```

Set/Get shift/scale from/to a file

Warning

this function reads/sets the Slope/Intercept in appropriate class storage, but also Grid Scaling in RT Dose Storage
Can't take a dataset because the mediastorage of the file must be known

10.151.2.17 GetSecondaryCaptureImagePlaneModule()

```
bool gdcm::ImageHelper::GetSecondaryCaptureImagePlaneModule () [static]
```

10.151.2.18 GetSpacingTagFromMediaStorage()

```
Tag gdcm::ImageHelper::GetSpacingTagFromMediaStorage (
    MediaStorage const & ms) [static], [protected]
```

10.151.2.19 GetSpacingValue()

```
std::vector< double > gdcm::ImageHelper::GetSpacingValue (
    File const & f) [static]
```

Set/Get [Spacing](#) from/to a [File](#).

10.151.2.20 GetZSpacingTagFromMediaStorage()

```
Tag gdcm::ImageHelper::GetZSpacingTagFromMediaStorage (
    MediaStorage const & ms) [static], [protected]
```

10.151.2.21 SetDimensionsValue()

```
void gdcm::ImageHelper::SetDimensionsValue (
    File & f,
    const Pixmap & img) [static]
```

10.151.2.22 SetDirectionCosinesValue()

```
void gdcm::ImageHelper::SetDirectionCosinesValue (
    DataSet & ds,
    const std::vector< double > & dircos) [static]
```

Set Direction Cosines (IOP) from/to a file When [IOD](#) does not defines what is IOP (eg. typically Secondary Capture [Image](#) Storage) this call will simply remove the IOP attribute. Else in case of MR/CT image storage, this call will properly lookup the correct attribute to store the IOP.

10.151.2.23 SetForcePixelSpacing()

```
void gdcm::ImageHelper::SetForcePixelSpacing (
    bool ) [static]
```

GDCM 1.x compatibility issue: When using ReWrite an MR [Image](#) Storage would be rewritten as Secondary Capture [Object](#) while still having a Pixel [Spacing](#) tag (0028,0030). If you have deal with those files, use this very special flag to handle them Unless explicitly set elsewhere by the standard, it will use value from 0028,0030 / 0018,0088 for the Pixel [Spacing](#) of the [Image](#)

10.151.2.24 SetForceRescaleInterceptSlope()

```
void gdcmm::ImageHelper::SetForceRescaleInterceptSlope (
    bool ) [static]
```

GDCM 1.x compatibility issue: Do not use anymore. This hack was used for some MR [Image](#) Storage generated by Philips Modality. When "Combine MR Rescaling" is set to TRUE, rescaling is removed. But when set to FALSE, the Modality LUT was exported. Internally GDCM now handles this gracefully.

10.151.2.25 SetOriginValue()

```
void gdcmm::ImageHelper::SetOriginValue (
    DataSet & ds,
    const Image & img) [static]
```

10.151.2.26 SetPMSRescaleInterceptSlope()

```
void gdcmm::ImageHelper::SetPMSRescaleInterceptSlope (
    bool ) [static]
```

Since GDCM 2.6.1 Philips Medical [System](#) are read using the Private Field For Rescale Slope/Intercept by default. This mechanism can be deactivated using the following API: This option has no effect when ForceRescaleInterceptSlope is set to true GDCM will only read those private attribute but never write them out.

10.151.2.27 SetRescaleInterceptSlopeValue()

```
void gdcmm::ImageHelper::SetRescaleInterceptSlopeValue (
    File & f,
    const Image & img) [static]
```

10.151.2.28 SetSecondaryCaptureImagePlaneModule()

```
void gdcmm::ImageHelper::SetSecondaryCaptureImagePlaneModule (
    bool ) [static]
```

Opt into [Image Plane Module](#) for Secondary Capture [Image](#) Storage Enable reading [Image](#) Position [Patient](#) (IPP), [Image Orientation Patient](#) (IOP) and Pixel [Spacing](#) (0028,0030) This is a custom extension for some existing dataset (academic)

10.151.2.29 SetSpacingValue()

```
void gdcm::ImageHelper::SetSpacingValue (
    DataSet & ds,
    const std::vector< double > & spacing) [static]
```

Warning

You need to call SetSpacingValue after SetOriginValue / SetDirectionCosinesValue

The documentation for this class was generated from the following file:


- [gdcmImageHelper.h](#)

10.152 gdcm::ImageReader Class Reference


[ImageReader](#).

```
#include <gdcmImageReader.h>
```

Inheritance diagram for gdcm::ImageReader:



Collaboration diagram for `gdcm::ImageReader`:



Public Member Functions

- `ImageReader ()`
- `~ImageReader ()` override
- `Image & GetImage ()`
- `const Image & GetImage () const`
Return the read image.
- `bool Read ()` override

Public Member Functions inherited from `gdcm::PixmapReader`

- `PixmapReader ()`
- `~PixmapReader ()` override
- `Pixmap & GetPixmap ()`
- `const Pixmap & GetPixmap () const`
Return the read image (need to call `Read()` first)
- `bool Read ()` override

Public Member Functions inherited from [gdcm::Reader](#)

- [Reader](#) ()
- virtual [~Reader](#) ()
- bool [CanRead](#) () const
- [File](#) & [GetFile](#) ()
Set/Get File.
- const [File](#) & [GetFile](#) () const
Set/Get File.
- size_t [GetStreamCurrentPosition](#) () const
- bool [ReadSelectedPrivateTags](#) (std::set< [PrivateTag](#) > const &ptags, bool readvalues=true)
Will only read the specified selected private tags.
- bool [ReadSelectedTags](#) (std::set< [Tag](#) > const &tags, bool readvalues=true)
Will only read the specified selected tags.
- bool [ReadUpToTag](#) (const [Tag](#) &tag, std::set< [Tag](#) > const &skiptags=std::set< [Tag](#) >())
- void [SetFile](#) ([File](#) &file)
Set/Get File.
- void [SetFileName](#) (const char *filename_native)
- void [SetStream](#) (std::istream &input_stream)
Set the open-ed stream directly.

Protected Member Functions

- bool [ReadACRNEMAImage](#) () override
- bool [ReadImage](#) ([MediaStorage](#) const &ms) override

Protected Member Functions inherited from [gdcm::PixmapReader](#)

- bool [ReadImageInternal](#) ([MediaStorage](#) const &ms, bool handlepixeldata=true)

Protected Member Functions inherited from [gdcm::Reader](#)

- std::istream * [GetStreamPtr](#) () const
- bool [ReadDataSet](#) ()
- bool [ReadMetaInformation](#) ()
- bool [ReadPreamble](#) ()

Additional Inherited Members

Protected Attributes inherited from [gdcm::PixmapReader](#)

- [SmartPointer](#)< [Pixmap](#) > [PixelData](#)

Protected Attributes inherited from [gdcm::Reader](#)

- [SmartPointer](#) < [File](#) > [F](#)

10.152.1 Detailed Description

[ImageReader](#).

Note

its role is to convert the DICOM [DataSet](#) into a [Image](#) representation [Image](#) is different from [Pixmap](#) has it has a position and a direction in Space.

See also

[Image](#)

Examples

[BasicImageAnonymizer.cs](#), [CheckBigEndianBug.cxx](#), [CompressImage.cxx](#), [CompressLossyJPEG.cs](#), [ConvertToQImage.cxx](#), [DecompressImage.cs](#), [ExplicitLittleEndian.cs](#), [ExtractIconFromFile.cxx](#), [FixBrokenJ2K.cxx](#), [FixJAIBugJPEGLS.cxx](#), [GetArray.cs](#), [GetJPEGSamplePrecision.cxx](#), [HelloVizWorld.cxx](#), [MergeTwoFiles.cxx](#), [MpegVideoInfo.cs](#), [MrProtocol.cxx](#), [PatchFile.cxx](#), [PrintLUT.cxx](#), [ReadMultiTimesException.cxx](#), [RescaleImage.cs](#), and [threadgdcm.cxx](#).

10.152.2 Constructor & Destructor Documentation

10.152.2.1 ImageReader()

```
gdcm::ImageReader::ImageReader ()
```

10.152.2.2 ~ImageReader()

```
gdcm::ImageReader::~~ImageReader () [override]
```

10.152.3 Member Function Documentation

10.152.3.1 GetImage() [1/2]

```
Image & gdcm::ImageReader::GetImage ()
```


10.152.3.2 GetImage() [2/2]

```
const Image & gdcm::ImageReader::GetImage () const
```

Return the read image.

Examples

[BasicImageAnonymizer.cs](#), [CompressImage.cxx](#), [CompressLossyJPEG.cs](#), [ConvertToQImage.cxx](#), [DecompressImage.cs](#), [ExplicitLittleEndian.cs](#), [ExtractIconFromFile.cxx](#), [ExtractImageRegionWithLUT.cs](#), [FixJAIBugJPEGLS.cxx](#), [GetArray.cs](#), [GetJPEGSamplePrecision.cxx](#), [HelloVizWorld.cxx](#), [MergeTwoFiles.cxx](#), [MpegVideoInfo.cs](#), [PatchFile.cxx](#), [PrintLUT.cxx](#), [ReadMultiTimesException.cxx](#), [RescaleImage.cs](#), [TemplateEmptyImage.cxx](#), and [threadgdcm.cxx](#).

10.152.3.3 Read()

```
bool gdcm::ImageReader::Read () [override], [virtual]
```

Read the DICOM image. There are two reason for failure:

1. The input filename is not DICOM
2. The input DICOM file does not contains an [Image](#).

Reimplemented from [gdcm::Reader](#).

Reimplemented in [gdcm::ImageRegionReader](#).

Examples

[BasicImageAnonymizer.cs](#), [CheckBigEndianBug.cxx](#), [CompressImage.cxx](#), [CompressLossyJPEG.cs](#), [ConvertToQImage.cxx](#), [DecompressImage.cs](#), [ExplicitLittleEndian.cs](#), [ExtractIconFromFile.cxx](#), [FixBrokenJ2K.cxx](#), [FixJAIBugJPEGLS.cxx](#), [GetArray.cs](#), [GetJPEGSamplePrecision.cxx](#), [HelloVizWorld.cxx](#), [MergeTwoFiles.cxx](#), [MrProtocol.cxx](#), [PatchFile.cxx](#), [PrintLUT.cxx](#), [ReadMultiTimesException.cxx](#), [RescaleImage.cs](#), and [threadgdcm.cxx](#).

10.152.3.4 ReadACRNEMAImage()

```
bool gdcm::ImageReader::ReadACRNEMAImage () [override], [protected], [virtual]
```

Reimplemented from [gdcm::PixmapReader](#).

10.152.3.5 ReadImage()

```
bool gdcm::ImageReader::ReadImage (  
    MediaStorage const & ms) [override], [protected], [virtual]
```

Reimplemented from [gdcm::PixmapReader](#).

The documentation for this class was generated from the following file:


- [gdcmImageReader.h](#)

10.153 gdcm::ImageRegionReader Class Reference


[ImageRegionReader](#).

```
#include <gdcmImageRegionReader.h>
```

Inheritance diagram for gdcm::ImageRegionReader:



Collaboration diagram for gdcm::ImageRegionReader:



Public Member Functions

- [ImageRegionReader](#) ()
- [~ImageRegionReader](#) () override
- [size_t ComputeBufferLength](#) () const
- [Region](#) const & [GetRegion](#) () const
- bool [ReadInformation](#) ()
- bool [ReadIntoBuffer](#) (char *inreadbuffer, size_t buflen)
- void [SetRegion](#) ([Region](#) const ®ion)

Set/Get [Region](#) to be read.

Public Member Functions inherited from [gdcm::ImageReader](#)

- [ImageReader](#) ()
- [~ImageReader](#) () override
- [Image](#) & [GetImage](#) ()
- const [Image](#) & [GetImage](#) () const

Return the read image.

Public Member Functions inherited from [gdcm::PixmapReader](#)

- [PixmapReader](#) ()
 - [~PixmapReader](#) () override
 - [Pixmap](#) & [GetPixmap](#) ()
 - const [Pixmap](#) & [GetPixmap](#) () const
- Return the read image (need to call [Read\(\)](#) first)*
- bool [Read](#) () override

Public Member Functions inherited from [gdcm::Reader](#)

- [Reader](#) ()
 - virtual [~Reader](#) ()
 - bool [CanRead](#) () const
 - [File](#) & [GetFile](#) ()
- Set/Get File.*
- const [File](#) & [GetFile](#) () const
- Set/Get File.*
- size_t [GetStreamCurrentPosition](#) () const
 - bool [ReadSelectedPrivateTags](#) (std::set< [PrivateTag](#) > const &ptags, bool readvalues=true)
- Will only read the specified selected private tags.*
- bool [ReadSelectedTags](#) (std::set< [Tag](#) > const &tags, bool readvalues=true)
- Will only read the specified selected tags.*
- bool [ReadUpToTag](#) (const [Tag](#) &tag, std::set< [Tag](#) > const &skiptags=std::set< [Tag](#) >())
 - void [SetFile](#) ([File](#) &file)
- Set/Get File.*
- void [SetFileName](#) (const char *filename_native)
 - void [SetStream](#) (std::istream &input_stream)
- Set the open-ed stream directly.*

Protected Member Functions

- bool [Read](#) () override
- To prevent user from calling super class [Read\(\)](#) function.*

Protected Member Functions inherited from [gdcm::ImageReader](#)

- bool [ReadACRNEMAIImage](#) () override
- bool [ReadImage](#) ([MediaStorage](#) const &ms) override

Protected Member Functions inherited from [gdcm::PixmapReader](#)

- bool [ReadImageInternal](#) ([MediaStorage](#) const &ms, bool handlepixeldata=true)

Protected Member Functions inherited from [gdcm::Reader](#)

- std::istream * [GetStreamPtr](#) () const
- bool [ReadDataSet](#) ()
- bool [ReadMetaInformation](#) ()
- bool [ReadPreamble](#) ()

Additional Inherited Members

Protected Attributes inherited from [gdcm::PixmapReader](#)

- [SmartPointer](#)< [Pixmap](#) > [PixelData](#)

Protected Attributes inherited from [gdcm::Reader](#)

- [SmartPointer](#)< [File](#) > [F](#)

10.153.1 Detailed Description

[ImageRegionReader](#).

This class is able to read a region from a DICOM file containing an image. This implementation requires that the information stored in the DICOM header are consistent with what is in the encapsulated Pixel Data. This is technically not required by DICOM standard, which makes this implementation illegal with regards to the famous JPEG note: http://dicom.nema.org/medical/dicom/current/output/chtml/part05/sect_8.2.↵html#para_4bcb841e-c6bf-4e26-82a5-3fad3c942da0

See also

[ImageReader](#)

Examples

[ExtractImageRegion.cs](#), [ExtractImageRegionWithLUT.cs](#), and [TemplateEmptyImage.cxx](#).

10.153.2 Constructor & Destructor Documentation

10.153.2.1 [ImageRegionReader](#)()

```
gdcm::ImageRegionReader::ImageRegionReader ()
```

10.153.2.2 ~ImageRegionReader()

```
gdcm::ImageRegionReader::~~ImageRegionReader () [override]
```

10.153.3 Member Function Documentation

10.153.3.1 ComputeBufferLength()

```
size_t gdcm::ImageRegionReader::ComputeBufferLength () const
```

Explicit call which will compute the minimal buffer length that can hold the whole uncompressed image as defined by [Region](#) region.

Returns

0 upon error

10.153.3.2 GetRegion()

```
Region const & gdcm::ImageRegionReader::GetRegion () const
```

10.153.3.3 Read()

```
bool gdcm::ImageRegionReader::Read () [override], [protected], [virtual]
```

To prevent user from calling super class [Read\(\)](#) function.

Reimplemented from [gdcm::ImageReader](#).

10.153.3.4 ReadInformation()

```
bool gdcm::ImageRegionReader::ReadInformation ()
```

Read meta information (not Pixel Data) from the DICOM file.

Returns

false upon error

Examples

[ExtractImageRegion.cs](#), [ExtractImageRegionWithLUT.cs](#), and [TemplateEmptyImage.cxx](#).

10.153.3.5 ReadIntoBuffer()

```
bool gdcm::ImageRegionReader::ReadIntoBuffer (
    char * inreadbuffer,
    size_t buflen)
```

Read into buffer: For Python, the `buflen` param is deduced directly from the input bytearray passed as parameter (function only takes one param).

Returns

false upon error

Examples

[ExtractImageRegion.cs](#), and [ExtractImageRegionWithLUT.cs](#).

10.153.3.6 SetRegion()

```
void gdcm::ImageRegionReader::SetRegion (
    Region const & region)
```

Set/Get [Region](#) to be read.

Examples

[ExtractImageRegion.cs](#), and [ExtractImageRegionWithLUT.cs](#).

The documentation for this class was generated from the following file:

- [gdcmImageRegionReader.h](#)

10.154 gdcm::ImageToImageFilter Class Reference


[ImageToImageFilter](#) class.

```
#include <gdcmImageToImageFilter.h>
```

Inheritance diagram for `gdcm::ImageToImageFilter`:



Collaboration diagram for `gdcm::ImageToImageFilter`:



Public Member Functions

- [ImageToImageFilter \(\)](#)
- [~ImageToImageFilter \(\)](#)=default
- [Image & GetInput \(\)](#)
- [const Image & GetOutput \(\)](#) const
Get Output image.

Public Member Functions inherited from [gdcm::PixmapToPixmapFilter](#)

- [PixmapToPixmapFilter \(\)](#)
- [~PixmapToPixmapFilter \(\)](#)=default
- [Pixmap & GetInput \(\)](#)
- [const Pixmap & GetOutput \(\)](#) const
Get Output image.
- [const Pixmap & GetOutputAsPixmap \(\)](#) const

Public Member Functions inherited from [gdcm::BitmapToBitmapFilter](#)

- [BitmapToBitmapFilter](#) ()
- [~BitmapToBitmapFilter](#) ()=default
- const [Bitmap](#) & [GetOutput](#) () const
Get Output image.
- const [Bitmap](#) & [GetOutputAsBitmap](#) () const
- void [SetInput](#) (const [Bitmap](#) &image)
Set input image.

Additional Inherited Members**Protected Attributes inherited from [gdcm::BitmapToBitmapFilter](#)**

- [SmartPointer](#)< [Bitmap](#) > [Input](#)
- [SmartPointer](#)< [Bitmap](#) > [Output](#)

10.154.1 Detailed Description

[ImageToImageFilter](#) class.

Super class for all filter taking an image and producing an output image

10.154.2 Constructor & Destructor Documentation**10.154.2.1 [ImageToImageFilter](#)()**

```
gdcm::ImageToImageFilter::ImageToImageFilter ()
```

10.154.2.2 [~ImageToImageFilter](#)()

```
gdcm::ImageToImageFilter::~~ImageToImageFilter () [default]
```

10.154.3 Member Function Documentation**10.154.3.1 [GetInput](#)()**

```
Image & gdcm::ImageToImageFilter::GetInput ()
```

10.154.3.2 GetOutput()

```
const Image & gdcM::ImageToImageFilter::GetOutput () const
```

Get Output image.

Examples

[BasicImageAnonymizer.cs](#), [CompressImage.cxx](#), [CompressLossyJPEG.cs](#), and [ExplicitLittleEndian.cs](#).

The documentation for this class was generated from the following file:


- [gdcMImageToImageFilter.h](#)

10.155 gdcM::ImageWriter Class Reference


[ImageWriter](#).

```
#include <gdcMImageWriter.h>
```

Inheritance diagram for gdcM::ImageWriter:



Collaboration diagram for gdcm::ImageWriter:



Public Member Functions

- `ImageWriter ()`
- `~ImageWriter ()` override
- `MediaStorage ComputeTargetMediaStorage ()`
- `const Image & GetImage ()` const override
- `Image & GetImage ()` override
- `bool Write ()` override

Write.

Public Member Functions inherited from [gdcm::PixmapWriter](#)

- [PixmapWriter](#) ()
- [~PixmapWriter](#) () override
- [Pixmap](#) & [GetPixmap](#) ()
- const [Pixmap](#) & [GetPixmap](#) () const
- virtual void [SetImage](#) ([Pixmap](#) const &img)
- void [SetPixmap](#) ([Pixmap](#) const &img)
- bool [Write](#) () override

Write.

Public Member Functions inherited from [gdcm::Writer](#)

- [Writer](#) ()
 - virtual [~Writer](#) ()
 - void [CheckFileMetaInformationOff](#) ()
 - void [CheckFileMetaInformationOn](#) ()
 - [File](#) & [GetFile](#) ()
 - void [SetCheckFileMetaInformation](#) (bool b)
- Undocumented function, do not use (= leave default)*
- void [SetFile](#) (const [File](#) &f)
- Set/Get the DICOM file ([DataSet](#) + Header)*
- void [SetFileName](#) (const char *filename_native)
- Set the filename of DICOM file to write:*
- void [SetStream](#) (std::ostream &output_stream)

Set user ostream buffer.

Additional Inherited Members

Protected Member Functions inherited from [gdcm::PixmapWriter](#)

- void [DolconImage](#) ([DataSet](#) &ds, [Pixmap](#) const &image)
- bool [PrepareWrite](#) ([MediaStorage](#) const &refms)

Protected Member Functions inherited from [gdcm::Writer](#)

- bool [GetCheckFileMetaInformation](#) () const
- std::ostream * [GetStreamPtr](#) () const
- void [SetWriteDataSetOnly](#) (bool b)

Protected Attributes inherited from [gdcm::PixmapWriter](#)

- [SmartPointer](#)< [Pixmap](#) > [PixelData](#)

Protected Attributes inherited from [gdcm::Writer](#)

- `std::ofstream` * [Ofstream](#)
- `std::ostream` * [Stream](#)

10.155.1 Detailed Description

[ImageWriter](#).

This is an extended version of the [PixmapWriter](#). Pay attention that:

1. It will populate missing attribute for Secondary Capture [Image](#) Storage instances,
2. It may also change an input MR [Image](#) Storage instance into a pseudo Enhanced MR [Image](#) Storage instance whenever Modality LUT is required.
3. Some [DataElement](#) related to [gdcm::Image](#) may be slightly altered.

Examples

[BasicImageAnonymizer.cs](#), [CompressImage.cxx](#), [CompressLossyJPEG.cs](#), [CreateARGBImage.cxx](#), [CreateCMYKImage.cxx](#), [DecompressImage.cs](#), [ExplicitLittleEndian.cs](#), [GenFakeImage.cxx](#), [GetSubSequenceData.cxx](#), [HelloVizWorld.cxx](#), [MergeTwoFiles.cxx](#), [MpegVideoInfo.cs](#), [TemplateEmptyImage.cxx](#), [csa2img.cxx](#), and [iU22tomultisc.cxx](#).

10.155.2 Constructor & Destructor Documentation

10.155.2.1 [ImageWriter\(\)](#)

```
gdcm::ImageWriter::ImageWriter ()
```

10.155.2.2 [~ImageWriter\(\)](#)

```
gdcm::ImageWriter::~~ImageWriter () [override]
```

10.155.3 Member Function Documentation

10.155.3.1 [ComputeTargetMediaStorage\(\)](#)

```
MediaStorage gdcm::ImageWriter::ComputeTargetMediaStorage ()
```

internal function used to compute a target [MediaStorage](#) the most appropriate User may want to call this function ahead of time (before Write)

Examples

[TemplateEmptyImage.cxx](#).

10.155.3.2 GetImage() [1/2]

```
const Image & gdcM::ImageWriter::GetImage () const [inline], [override], [virtual]
```

Set/Get [Image](#) to be written It will overwrite anything [Image](#) infos found in [DataSet](#) (see parent class to see how to pass dataset)

Reimplemented from [gdcM::PixmapWriter](#).

Examples

[CreateARGBImage.cxx](#), [CreateCMYKImage.cxx](#), [csa2img.cxx](#), and [iU22tomultisc.cxx](#).

10.155.3.3 GetImage() [2/2]

```
Image & gdcM::ImageWriter::GetImage () [inline], [override], [virtual]
```

Reimplemented from [gdcM::PixmapWriter](#).

10.155.3.4 Write()

```
bool gdcM::ImageWriter::Write () [override], [virtual]
```

Write.

Reimplemented from [gdcM::Writer](#).

Examples

[BasicImageAnonymizer.cs](#), [CompressImage.cxx](#), [CompressLossyJPEG.cs](#), [CreateARGBImage.cxx](#), [CreateCMYKImage.cxx](#), [DecompressImage.cs](#), [GenFakeImage.cxx](#), [GetSubSequenceData.cxx](#), [HelloVizWorld.cxx](#), [MergeTwoFiles.cxx](#), [MpegVideoInfo.cs](#), [TemplateEmptyImage.cxx](#), [csa2img.cxx](#), and [iU22tomultisc.cxx](#).

The documentation for this class was generated from the following file:

- [gdcMImageWriter.h](#)

10.156 gdcM::network::ImplementationClassUIDSub Class Reference

[ImplementationClassUIDSub](#).

```
#include <gdcMImplementationClassUIDSub.h>
```

Public Member Functions

- [ImplementationClassUIDSub](#) ()
- void [Print](#) (std::ostream &os) const
- std::istream & [Read](#) (std::istream &is)
- size_t [Size](#) () const
- const std::ostream & [Write](#) (std::ostream &os) const

10.156.1 Detailed Description

[ImplementationClassUIDSub](#).

PS 3.7 [Table D.3-1](#) IMPLEMENTATION CLASS UID SUB-ITEM FIELDS (A-ASSOCIATE-RQ)

10.156.2 Constructor & Destructor Documentation

10.156.2.1 ImplementationClassUIDSub()

```
gdcm::network::ImplementationClassUIDSub::ImplementationClassUIDSub ()
```

10.156.3 Member Function Documentation

10.156.3.1 Print()

```
void gdcm::network::ImplementationClassUIDSub::Print (  
    std::ostream & os) const
```

10.156.3.2 Read()

```
std::istream & gdcm::network::ImplementationClassUIDSub::Read (  
    std::istream & is)
```

10.156.3.3 Size()

```
size_t gdcm::network::ImplementationClassUIDSub::Size () const
```

10.156.3.4 Write()

```
const std::ostream & gdcm::network::ImplementationClassUIDSub::Write (  
    std::ostream & os) const
```

The documentation for this class was generated from the following file:

- [gdcmImplementationClassUIDSub.h](#)

10.157 gdcm::network::ImplementationUIDSub Class Reference

[ImplementationUIDSub.](#)

```
#include <gdcmImplementationUIDSub.h>
```

Public Member Functions

- [ImplementationUIDSub](#) ()
- const std::ostream & [Write](#) (std::ostream &os) const

10.157.1 Detailed Description

[ImplementationUIDSub.](#)

[Table](#) D.3-2 IMPLEMENTATION UID SUB-ITEM FIELDS (A-ASSOCIATE-AC)

10.157.2 Constructor & Destructor Documentation

10.157.2.1 ImplementationUIDSub()

```
gdcm::network::ImplementationUIDSub::ImplementationUIDSub ()
```

10.157.3 Member Function Documentation

10.157.3.1 Write()

```
const std::ostream & gdcm::network::ImplementationUIDSub::Write (  
    std::ostream & os) const
```

The documentation for this class was generated from the following file:

- [gdcmImplementationUIDSub.h](#)

10.158 gdcm::network::ImplementationVersionNameSub Class Reference

[ImplementationVersionNameSub.](#)

```
#include <gdcmImplementationVersionNameSub.h>
```


Public Member Functions

- [ImplementationVersionNameSub](#) ()
- void [Print](#) (std::ostream &os) const
- std::istream & [Read](#) (std::istream &is)
- size_t [Size](#) () const
- const std::ostream & [Write](#) (std::ostream &os) const

10.158.1 Detailed Description

[ImplementationVersionNameSub](#).

[Table](#) D.3-3 IMPLEMENTATION VERSION NAME SUB-ITEM FIELDS (A-ASSOCIATE-RQ)

10.158.2 Constructor & Destructor Documentation

10.158.2.1 ImplementationVersionNameSub()

```
gdcm::network::ImplementationVersionNameSub::ImplementationVersionNameSub ()
```

10.158.3 Member Function Documentation

10.158.3.1 Print()

```
void gdcm::network::ImplementationVersionNameSub::Print (  
    std::ostream & os) const
```

10.158.3.2 Read()

```
std::istream & gdcm::network::ImplementationVersionNameSub::Read (  
    std::istream & is)
```

10.158.3.3 Size()

```
size_t gdcm::network::ImplementationVersionNameSub::Size () const
```

10.158.3.4 Write()

```
const std::ostream & gdcm::network::ImplementationVersionNameSub::Write (  
    std::ostream & os) const
```

The documentation for this class was generated from the following file:


- [gdcmImplementationVersionNameSub.h](#)

10.159 gdcm::ImplicitDataElement Class Reference


Class to represent an *Implicit VR Data Element*.

```
#include <gdcmImplicitDataElement.h>
```

Inheritance diagram for gdcm::ImplicitDataElement:



Collaboration diagram for gdcm::ImplicitDataElement:



Public Member Functions

- [VL GetLength](#) () const

- template<typename TSwap>
std::istream & [Read](#) (std::istream &is)
- template<typename TSwap>
std::istream & [ReadPreValue](#) (std::istream &is)
- template<typename TSwap>
std::istream & [ReadValue](#) (std::istream &is, bool readvalues=true)
- template<typename TSwap>
std::istream & [ReadValueWithLength](#) (std::istream &is, [VL](#) &length, bool readvalues=true)
- template<typename TSwap>
std::istream & [ReadWithLength](#) (std::istream &is, [VL](#) &length, bool readvalues=true)
- template<typename TSwap>
const std::ostream & [Write](#) (std::ostream &os) const

Public Member Functions inherited from [gdcm::DataElement](#)

- [DataElement](#) (const [DataElement](#) &_val)
- [DataElement](#) (const [Tag](#) &t=[Tag](#)(0), const [VL](#) &vl=0, const [VR](#) &vr=[VR::INVALID](#))
- void [Clear](#) ()
Clear Data [Element](#) (make [Value](#) empty and invalidate [Tag](#) & [VR](#))
- void [Empty](#) ()
Make Data [Element](#) empty (no [Value](#))
- const [ByteValue](#) * [GetByteValue](#) () const
- template<typename TDE>
[VL](#) [GetLength](#) () const
- [SequenceOfFragments](#) * [GetSequenceOfFragments](#) ()
- const [SequenceOfFragments](#) * [GetSequenceOfFragments](#) () const
- [Tag](#) & [GetTag](#) ()
- const [Tag](#) & [GetTag](#) () const
Get [Tag](#).
- [Value](#) & [GetValue](#) ()
- [Value](#) const & [GetValue](#) () const
Set/Get [Value](#) (bytes array, SQ of items, SQ of fragments):
- [SmartPointer](#)< [SequenceOfItems](#) > [GetValueAsSQ](#) () const
- [VL](#) & [GetVL](#) ()
- const [VL](#) & [GetVL](#) () const
Get [VL](#).
- [VR](#) const & [GetVR](#) () const
- bool [IsEmpty](#) () const
Check if Data [Element](#) is empty.
- bool [IsUndefinedLength](#) () const
return if [Value](#) Length if of undefined length
- bool [operator<](#) (const [DataElement](#) &de) const
- [DataElement](#) & [operator=](#) (const [DataElement](#) &)=default
- bool [operator==](#) (const [DataElement](#) &de) const
- template<typename TDE, typename TSwap>
std::istream & [Read](#) (std::istream &is)
- template<typename TDE, typename TSwap>
std::istream & [ReadOrSkip](#) (std::istream &is, std::set< [Tag](#) > const &skiptags)

- `template<typename TDE, typename TSwap>`
`std::istream & ReadPreValue (std::istream &is, std::set< Tag > const &skiptags)`
- `template<typename TDE, typename TSwap>`
`std::istream & ReadValue (std::istream &is, std::set< Tag > const &skiptags)`
- `template<typename TDE, typename TSwap>`
`std::istream & ReadValueWithLength (std::istream &is, VL &length, std::set< Tag > const &skiptags)`
- `template<typename TDE, typename TSwap>`
`std::istream & ReadWithLength (std::istream &is, VL &length)`
- `void SetByteValue (const char *array, VL length)`
- `void SetTag (const Tag &t)`
- `void SetValue (Value const &vl)`
- `void SetVL (const VL &vl)`
- `void SetVLToUndefined ()`
- `void SetVR (VR const &vr)`
- `template<typename TDE, typename TSwap>`
`const std::ostream & Write (std::ostream &os) const`

Additional Inherited Members

Protected Types inherited from [gdcm::DataElement](#)

- `typedef SmartPointer< Value > ValuePtr`

Protected Member Functions inherited from [gdcm::DataElement](#)

- `void SetValueFieldLength (VL vl, bool readvalues)`

Protected Attributes inherited from [gdcm::DataElement](#)

- [Tag](#) [TagField](#)
- [ValuePtr](#) [ValueField](#)
- [VL](#) [ValueLengthField](#)
- [VR](#) [VRField](#)

10.159.1 Detailed Description

Class to represent an *Implicit* [VR](#) Data [Element](#).

Note

bla

Examples

[ReadExplicitLengthSQIVR.cxx](#).

10.159.2 Member Function Documentation

10.159.2.1 GetLength()

```
VL gdcm::ImplicitDataElement::GetLength () const
```

10.159.2.2 Read()

```
template<typename TSwap>
std::istream & gdcm::ImplicitDataElement::Read (
    std::istream & is)
```

10.159.2.3 ReadPreValue()

```
template<typename TSwap>
std::istream & gdcm::ImplicitDataElement::ReadPreValue (
    std::istream & is)
```

10.159.2.4 ReadValue()

```
template<typename TSwap>
std::istream & gdcm::ImplicitDataElement::ReadValue (
    std::istream & is,
    bool readvalues = true)
```

10.159.2.5 ReadValueWithLength()

```
template<typename TSwap>
std::istream & gdcm::ImplicitDataElement::ReadValueWithLength (
    std::istream & is,
    VL & length,
    bool readvalues = true)
```

10.159.2.6 ReadWithLength()

```
template<typename TSwap>
std::istream & gdcm::ImplicitDataElement::ReadWithLength (
    std::istream & is,
    VL & length,
    bool readvalues = true)
```

10.159.2.7 Write()

```
template<typename TSwap>
const std::ostream & gdcM::ImplicitDataElement::Write (
    std::ostream & os) const
```


The documentation for this class was generated from the following file:

- [gdcMImplicitDataElement.h](#)


10.160 gdcM::InitializeEvent Class Reference

```
#include <gdcMEvent.h>
```

Inheritance diagram for gdcM::InitializeEvent:



Collaboration diagram for gdcm::InitializeEvent:



Additional Inherited Members

Public Member Functions inherited from [gdcm::Event](#)

- [Event](#) ()
- [Event](#) (const [Event](#) &)
- virtual [~Event](#) ()
- virtual bool [CheckEvent](#) (const [Event](#) *) const =0
- virtual const char * [GetEventName](#) () const =0
- virtual [Event](#) * [MakeObject](#) () const =0
- void [operator=](#) (const [Event](#) &)=delete
- virtual void [Print](#) (std::ostream &os) const

The documentation for this class was generated from the following file:

- [gdcmEvent.h](#)

10.161 gdcm::IOD Class Reference

Class for representing a [IOD](#).

```
#include <gdcmIOD.h>
```

Public Types

- typedef std::vector< [IODEntry](#) > [MapIODEntry](#)
- typedef MapIODEntry::size_type [SizeType](#)

Public Member Functions

- [IOD](#) ()=default
- void [AddIODEntry](#) (const [IODEntry](#) &iode)
- void [Clear](#) ()
- const [IODEntry](#) & [GetIODEntry](#) ([SizeType](#) idx) const
- [SizeType](#) [GetNumberOfIODs](#) () const
- [Type](#) [GetTypeFromTag](#) (const [Defs](#) &defs, const [Tag](#) &tag) const

Friends

- std::ostream & [operator<<](#) (std::ostream &_os, const [IOD](#) &_val)

10.161.1 Detailed Description

Class for representing a [IOD](#).

Note

bla

See also

[Dict](#)

Examples

[TraverseModules.cxx](#).

10.161.2 Member Typedef Documentation

10.161.2.1 MapIODEntry

```
typedef std::vector<IODEntry> gdcm::IOD::MapIODEntry
```

10.161.2.2 SizeType

```
typedef MapIODEntry::size\_type gdcm::IOD::SizeType
```


10.161.3 Constructor & Destructor Documentation

10.161.3.1 IOD()

gdcm::IOD::IOD () [default]

References [IOD\(\)](#), and [operator<<](#).

Referenced by [IOD\(\)](#), and [operator<<](#).

10.161.4 Member Function Documentation

10.161.4.1 AddIODEntry()

```
void gdcm::IOD::AddIODEntry (  
    const IODEntry & iode) [inline]
```

10.161.4.2 Clear()

```
void gdcm::IOD::Clear () [inline]
```

10.161.4.3 GetIODEntry()

```
const IODEntry & gdcm::IOD::GetIODEntry (  
    SizeType idx) const [inline]
```

Examples

[TraverseModules.cxx](#).

10.161.4.4 GetNumberOfIODs()

```
SizeType gdcm::IOD::GetNumberOfIODs () const [inline]
```

Examples

[TraverseModules.cxx](#).

10.161.4.5 GetTypeFromTag()

```
Type gdcm::IOD::GetTypeFromTag (  
    const Defs & defs,  
    const Tag & tag) const
```

10.161.5 Friends And Related Symbol Documentation

10.161.5.1 `operator<<`

```
std::ostream & operator<< (  
    std::ostream & _os,  
    const IOD & _val) [friend]
```

References [IOD\(\)](#).

Referenced by [IOD\(\)](#).

The documentation for this class was generated from the following file:

- [gdcmIOD.h](#)

10.162 `gdcm::IODEntry` Class Reference

Class for representing a [IODEntry](#).

```
#include <gdcmIODEntry.h>
```

Public Member Functions

- [IODEntry](#) (const char *name="", const char *ref="", const char *inUsage="")
- const char * [GetIE](#) () const
- const char * [GetName](#) () const
- const char * [GetRef](#) () const
- const char * [GetUsage](#) () const
- [Usage::UsageType](#) [GetUsageType](#) () const
- void [SetIE](#) (const char *ie)
- void [SetName](#) (const char *name)
- void [SetRef](#) (const char *ref)
- void [SetUsage](#) (const char *inUsage)

Friends

- std::ostream & [operator<<](#) (std::ostream &_os, const [IODEntry](#) &_val)

10.162.1 Detailed Description

Class for representing a [IODEntry](#).

Note

A.1.3 [IOD Module Table](#) and Functional Group [Macro Table](#) This Section of each [IOD](#) defines in a tabular form the [Modules](#) comprising the [IOD](#). The following information must be specified for each [Module](#) in the table:

- The name of the [Module](#) or Functional Group
- A reference to the Section in Annex C which defines the [Module](#) or Functional Group
- The usage of the [Module](#) or Functional Group; whether it is:
 - Mandatory (see A.1.3.1) , abbreviated M
 - Conditional (see A.1.3.2) , abbreviated C
 - User Option (see A.1.3.3) , abbreviated U
- The [Modules](#) referenced are defined in Annex C. A.1.3.1 MANDATORY MODULES For each [IOD](#), Mandatory [Modules](#) shall be supported per the definitions, semantics and requirements defined in Annex C. PS 3.3 - 2008 Page 96
- Standard - A.1.3.2 CONDITIONAL MODULES Conditional [Modules](#) are Mandatory [Modules](#) if specific conditions are met. If the specified conditions are not met, this [Module](#) shall not be supported; that is, no information defined in that [Module](#) shall be sent. A.1.3.3 USER OPTION MODULES User Option [Modules](#) may or may not be supported. If an optional [Module](#) is supported, the [Attribute](#) Types specified in the [Modules](#) in Annex C shall be supported.

See also

[DictEntry](#)

Examples

[TraverseModules.cxx](#).

10.162.2 Constructor & Destructor Documentation

10.162.2.1 IODEntry()

```
gdcm::IODEntry::IODEntry (
    const char * name = "",
    const char * ref = "",
    const char * inUsage = "") [inline]
```

Referenced by [operator<<](#).

10.162.3 Member Function Documentation

10.162.3.1 GetIE()

```
const char * gdcm::IODEntry::GetIE () const [inline]
```

10.162.3.2 GetName()

```
const char * gdcm::IODEntry::GetName () const [inline]
```

10.162.3.3 GetRef()

```
const char * gdcm::IODEntry::GetRef () const [inline]
```

Examples

[TraverseModules.cxx](#).

10.162.3.4 GetUsage()

```
const char * gdcm::IODEntry::GetUsage () const [inline]
```

10.162.3.5 GetUsageType()

```
Usage::UsageType gdcm::IODEntry::GetUsageType () const
```

10.162.3.6 SetIE()

```
void gdcm::IODEntry::SetIE (  
    const char * ie) [inline]
```

10.162.3.7 SetName()

```
void gdcm::IODEntry::SetName (  
    const char * name) [inline]
```

10.162.3.8 SetRef()

```
void gdcm::IODEntry::SetRef (  
    const char * ref) [inline]
```

10.162.3.9 SetUsage()

```
void gdcm::IODEntry::SetUsage (  
    const char * inUsage) [inline]
```

10.162.4 Friends And Related Symbol Documentation

10.162.4.1 operator<<

```
std::ostream & operator<< (  
    std::ostream & _os,  
    const IODEntry & _val) [friend]
```

References [IODEntry\(\)](#).

The documentation for this class was generated from the following file:

- [gdcmIODEntry.h](#)

10.163 gdcm::IODs Class Reference

Class for representing a [IODs](#).

```
#include <gdcmIODs.h>
```

Public Types

- typedef std::map< [IODName](#), [IOD](#) > [IODMapType](#)
- typedef [IODMapType](#)::const_iterator [IODMapTypeConstIterator](#)
- typedef std::string [IODName](#)

Public Member Functions

- [IODs](#) ()=default
- void [AddIOD](#) (const char *name, const [IOD](#) &module)
- [IODMapTypeConstIterator](#) [Begin](#) () const
- void [Clear](#) ()
- [IODMapTypeConstIterator](#) [End](#) () const
- const [IOD](#) & [GetIOD](#) (const char *name) const

Friends

- std::ostream & [operator<<](#) (std::ostream &_os, const [IODs](#) &_val)

10.163.1 Detailed Description

Class for representing a [IODs](#).

Note

bla

See also

[IOD](#)

Examples

[TraverseModules.cxx](#).

10.163.2 Member Typedef Documentation

10.163.2.1 IODMapType

```
typedef std::map<IODName, IOD> gdcm::IODs::IODMapType
```

10.163.2.2 IODMapTypeConstIterator

```
typedef IODMapType::const_iterator gdcm::IODs::IODMapTypeConstIterator
```

Examples

[TraverseModules.cxx](#).

10.163.2.3 IODName

```
typedef std::string gdcm::IODs::IODName
```

Examples

[TraverseModules.cxx](#).

10.163.3 Constructor & Destructor Documentation

10.163.3.1 IODs()

```
gdcm::IODs::IODs () [default]
```

References [IODs\(\)](#), and [operator<<](#).

Referenced by [IODs\(\)](#), and [operator<<](#).

10.163.4 Member Function Documentation

10.163.4.1 AddIOD()

```
void gdcm::IODs::AddIOD (
    const char * name,
    const IOD & module) [inline]
```

10.163.4.2 Begin()

```
IODMapTypeConstIterator gdcm::IODs::Begin () const [inline]
```

Examples

[TraverseModules.cxx](#).

10.163.4.3 Clear()

```
void gdcm::IODs::Clear () [inline]
```

10.163.4.4 End()

```
IODMapTypeConstIterator gdcm::IODs::End () const [inline]
```

Examples

[TraverseModules.cxx](#).

10.163.4.5 GetIOD()

```
const IOD & gdcm::IODs::GetIOD (
    const char * name) const [inline]
```

References [gdcm_assert](#).

10.163.5 Friends And Related Symbol Documentation

10.163.5.1 operator<<

```
std::ostream & operator<< (
    std::ostream & _os,
    const IODs & _val) [friend]
```

References [IODs\(\)](#).

Referenced by [IODs\(\)](#).

The documentation for this class was generated from the following file:

- [gdcmIODs.h](#)

Public Member Functions inherited from [gdcm::Sorter](#)

- [Sorter](#) ()
- virtual [~Sorter](#) ()
- bool [AddSelect](#) ([Tag](#) const &tag, const char *value)
UNSUPPORTED FOR NOW.
- const std::vector< std::string > & [GetFileNames](#) () const
- void [Print](#) (std::ostream &os) const
Print.
- void [SetSortFunction](#) ([SortFunction](#) f)
- void [SetTagsToRead](#) (std::set< [Tag](#) > const &tags)
- virtual bool [StableSort](#) (std::vector< std::string > const &filenames)

Protected Attributes

- bool [ComputeZSpacing](#)
- double [DirCosTolerance](#)
- bool [DropDuplicatePositions](#)
- double [ZSpacing](#)
- double [ZTolerance](#)

Protected Attributes inherited from [gdcm::Sorter](#)

- std::vector< std::string > [FileNames](#)
- std::map< [Tag](#), std::string > [Selection](#)
- [SortFunction](#) [SortFunc](#)
- std::set< [Tag](#) > [TagsToRead](#)

Additional Inherited Members

Public Types inherited from [gdcm::Sorter](#)

- typedef bool(* [SortFunction](#)) ([DataSet](#) const &, [DataSet](#) const &)
Set the sort function which compares one dataset to the other.

Protected Types inherited from [gdcm::Sorter](#)

- typedef std::map< [Tag](#), std::string > [SelectionMap](#)

10.164.1 Detailed Description

[IPPSorter](#).

Implement a simple [Image](#) Position ([Patient](#)) sorter, along the [Image Orientation](#) ([Patient](#)) direction. This algorithm does NOT support duplicate and will FAIL in case of duplicate IPP.

Warning

See special note for `SetZSpacingTolerance` when computing the ZSpacing from the IPP of each DICOM files (default tolerance for consistent spacing is: 1e-6mm)

For more information on [Spacing](#), and how it is defined in DICOM, advanced users may refers to:

http://gdcm.sourceforge.net/wiki/index.php/Imager_Pixel_Spacing

Bug There are currently a couple of bugs in this implementation:

- Gantry Tilt is not considered (always an error)
- Application programmer should only sort valid [DataSet](#) (eg. `MRImageStorage`, `CTImageStorage`, `PETImageStorage`)

Examples

[Compute3DSpacing.cxx](#), [VolumeSorter.cxx](#), and [gdcmorthoplanes.cxx](#).

10.164.2 Constructor & Destructor Documentation

10.164.2.1 IPPSorter()

```
gdcm::IPPSorter::IPPSorter ()
```

10.164.3 Member Function Documentation

10.164.3.1 GetDirectionCosinesTolerance()

```
double gdcm::IPPSorter::GetDirectionCosinesTolerance () const [inline]
```

References [DirCosTolerance](#).

10.164.3.2 GetZSpacing()

```
double gdcm::IPPSorter::GetZSpacing () const [inline]
```

Read-only function to provide access to the computed value for the Z-Spacing The ComputeZSpacing must have been set to true before execution of sort algorithm. Call this function *after* calling [Sort\(\)](#); Z-Spacing will be 0 on 2 occasions:

- Sorting simply failed, potentially duplicate IPP => ZSpacing = 0
- ZSpacing could not be computed (Z-Spacing is not constant, or ZTolerance is too low)

Examples

[Compute3DSpacing.cxx](#), [gdcmorthoplanes.cxx](#), and [reslicesphere.cxx](#).

References [ZSpacing](#).

10.164.3.3 GetZSpacingTolerance()

```
double gdcm::IPPSorter::GetZSpacingTolerance () const [inline]
```

References [ZTolerance](#).

10.164.3.4 SetComputeZSpacing()

```
void gdcm::IPPSorter::SetComputeZSpacing (  
    bool b) [inline]
```

Functions related to Z-Spacing computation Set to true when sort algorithm should also perform a regular Z-Spacing computation using the [Image](#) Position ([Patient](#)) Potential reason for failure:

1. ALL slices are taken into account, if one slice is missing then ZSpacing will be set to 0 since the spacing will not be found to be regular along the [Series](#)

Examples

[Compute3DSpacing.cxx](#), [VolumeSorter.cxx](#), [gdcmorthoplanes.cxx](#), and [reslicesphere.cxx](#).

References [ComputeZSpacing](#).

10.164.3.5 SetDirectionCosinesTolerance()

```
void gdcM::IPPSorter::SetDirectionCosinesTolerance (
    double tol) [inline]
```

Sometimes IOP along a series is slightly changing for example: "0.999081\\0.0426953\\0.00369272\\-0.0419025\\0.955059\\0.293439", "0.999081\\0.0426953\\0.00369275\\-0.0419025\\0.955059\\0.293439", "0.999081\\0.0426952\\0.00369272\\-0.0419025\\0.955059\\0.293439", We need an API to define the tolerance which is allowed. Internally the cross vector of each direction cosines is computed. The tolerance then define the distance in between 1.0 to the dot product of those cross vectors. In a perfect world this dot product is of course 1.0 which imply a [DirectionCosines](#) tolerance of exactly 0.0 (default).

References [DirCosTolerance](#).

10.164.3.6 SetDropDuplicatePositions()

```
void gdcM::IPPSorter::SetDropDuplicatePositions (
    bool b) [inline]
```

Makes the [IPPSorter](#) ignore multiple images located at the same position. Only the first occurrence will be kept. [DropDuplicatePositions](#) defaults to false.

References [DropDuplicatePositions](#).

10.164.3.7 SetZSpacingTolerance()

```
void gdcM::IPPSorter::SetZSpacingTolerance (
    double tol) [inline]
```

1. Another reason for failure is that that Z-Spacing is only slightly changing (eg 1e-3) along the series, a human can determine that this is ok and change the tolerance from its default value: 1e-6

Examples

[Compute3DSpacing.cxx](#), [gdcMorthoplanes.cxx](#), and [reslicesphere.cxx](#).

References [ZTolerance](#).

10.164.3.8 Sort()

```
bool gdcM::IPPSorter::Sort (
    std::vector< std::string > const & filenames) [override], [virtual]
```

Main entry point to the sorter. It will execute the filter, option should be set before running this function ([SetZSpacingTolerance](#), ...) Return value indicate if sorting could be achieved,. Warning this does *NOT* imply that spacing is consistent, it only means the file are sorted according to IPP You should check if ZSpacing is 0 or not to deduce if file are actually a 3D volume

Reimplemented from [gdcM::Sorter](#).

Examples

[Compute3DSpacing.cxx](#), [VolumeSorter.cxx](#), [gdcMorthoplanes.cxx](#), and [reslicesphere.cxx](#).

10.164.4 Member Data Documentation

10.164.4.1 ComputeZSpacing

`bool gdcm::IPPSorter::ComputeZSpacing` [protected]

Referenced by [SetComputeZSpacing\(\)](#).

10.164.4.2 DirCosTolerance

`double gdcm::IPPSorter::DirCosTolerance` [protected]

Referenced by [GetDirectionCosinesTolerance\(\)](#), and [SetDirectionCosinesTolerance\(\)](#).

10.164.4.3 DropDuplicatePositions

`bool gdcm::IPPSorter::DropDuplicatePositions` [protected]

Referenced by [SetDropDuplicatePositions\(\)](#).

10.164.4.4 ZSpacing

`double gdcm::IPPSorter::ZSpacing` [protected]

Referenced by [GetZSpacing\(\)](#).

10.164.4.5 ZTolerance

`double gdcm::IPPSorter::ZTolerance` [protected]

Referenced by [GetZSpacingTolerance\(\)](#), and [SetZSpacingTolerance\(\)](#).

The documentation for this class was generated from the following file:


- [gdcmIPPSorter.h](#)

10.165 gdcm::Item Class Reference


Class to represent an [Item](#).

```
#include <gdcmItem.h>
```

Inheritance diagram for gdcm::Item:



Collaboration diagram for gdcm::Item:



Public Member Functions

- [Item](#) ()

- [Item](#) ([Item](#) const &val)
- void [Clear](#) ()
- bool [FindDataElement](#) (const [Tag](#) &t) const
- const [DataElement](#) & [GetDataElement](#) (const [Tag](#) &t) const
- template<typename TDE>
 [VL GetLength](#) () const
- [DataSet](#) & [GetNestedDataSet](#) ()
- const [DataSet](#) & [GetNestedDataSet](#) () const
- void [InsertDataElement](#) (const [DataElement](#) &de)
- template<typename TDE, typename TSwap>
 std::istream & [Read](#) (std::istream &is)
- void [SetNestedDataSet](#) (const [DataSet](#) &nested)
- template<typename TDE, typename TSwap>
 const std::ostream & [Write](#) (std::ostream &os) const

Public Member Functions inherited from [gdcm::DataElement](#)

- [DataElement](#) (const [DataElement](#) &_val)
- [DataElement](#) (const [Tag](#) &t=[Tag](#)(0), const [VL](#) &vl=0, const [VR](#) &vr=[VR::INVALID](#))
- void [Clear](#) ()
 Clear Data [Element](#) (make [Value](#) empty and invalidate [Tag](#) & [VR](#))
- void [Empty](#) ()
 Make Data [Element](#) empty (no [Value](#))
- const [ByteValue](#) * [GetByteValue](#) () const
- template<typename TDE>
 [VL GetLength](#) () const
- [SequenceOfFragments](#) * [GetSequenceOfFragments](#) ()
- const [SequenceOfFragments](#) * [GetSequenceOfFragments](#) () const
- [Tag](#) & [GetTag](#) ()
- const [Tag](#) & [GetTag](#) () const
 Get [Tag](#).
- [Value](#) & [GetValue](#) ()
- [Value](#) const & [GetValue](#) () const
 Set/Get [Value](#) (bytes array, SQ of items, SQ of fragments):
- [SmartPointer](#)< [SequenceOfItems](#) > [GetValueAsSQ](#) () const
- [VL](#) & [GetVL](#) ()
- const [VL](#) & [GetVL](#) () const
 Get [VL](#).
- [VR](#) const & [GetVR](#) () const
- bool [IsEmpty](#) () const
 Check if Data [Element](#) is empty.
- bool [IsUndefinedLength](#) () const
 return if [Value](#) Length if of undefined length
- bool [operator](#)< (const [DataElement](#) &de) const
- [DataElement](#) & [operator](#)= (const [DataElement](#) &)=default
- bool [operator](#)== (const [DataElement](#) &de) const
- template<typename TDE, typename TSwap>
 std::istream & [Read](#) (std::istream &is)

- `template<typename TDE, typename TSwap>`
`std::istream & ReadOrSkip (std::istream &is, std::set< Tag > const &skiptags)`
- `template<typename TDE, typename TSwap>`
`std::istream & ReadPreValue (std::istream &is, std::set< Tag > const &skiptags)`
- `template<typename TDE, typename TSwap>`
`std::istream & ReadValue (std::istream &is, std::set< Tag > const &skiptags)`
- `template<typename TDE, typename TSwap>`
`std::istream & ReadValueWithLength (std::istream &is, VL &length, std::set< Tag > const &skiptags)`
- `template<typename TDE, typename TSwap>`
`std::istream & ReadWithLength (std::istream &is, VL &length)`
- `void SetByteValue (const char *array, VL length)`
- `void SetTag (const Tag &t)`
- `void SetValue (Value const &vl)`
- `void SetVL (const VL &vl)`
- `void SetVLToUndefined ()`
- `void SetVR (VR const &vr)`
- `template<typename TDE, typename TSwap>`
`const std::ostream & Write (std::ostream &os) const`

Friends

- `std::ostream & operator<< (std::ostream &os, const Item &val)`

Additional Inherited Members

Protected Types inherited from `gdcm::DataElement`

- `typedef SmartPointer< Value > ValuePtr`

Protected Member Functions inherited from `gdcm::DataElement`

- `void SetValueFieldLength (VL vl, bool readvalues)`

Protected Attributes inherited from `gdcm::DataElement`

- `Tag TagField`
- `ValuePtr ValueField`
- `VL ValueLengthField`
- `VR VRField`

10.165.1 Detailed Description

Class to represent an [Item](#).

A component of the value of a Data [Element](#) that is of [Value](#) Representation Sequence of Items. An [Item](#) contains a Data Set . See PS 3.5 7.5.1 [Item](#) Encoding Rules Each [Item](#) of a Data [Element](#) of [VR](#) SQ shall be encoded as a DICOM Standard Data [Element](#) with a specific Data [Element](#) Tag of [Value](#) (FFFE,E000). The [Item](#) Tag is followed by a 4 byte [Item](#) Length field encoded in one of the following two ways Explicit/ Implicit

Note

ITEM: A component of the [Value](#) of a Data [Element](#) that is of [Value](#) Representation Sequence of Items. An [Item](#) contains a Data Set.

Examples

[ChangeSequenceUltrasound.cxx](#), [DumpExamCard.cxx](#), [DumpGEMSMovieGroup.cxx](#), [DumpPhilipsECHO.cxx](#), [DumpToshibaDTI.cxx](#), [DumpToshibaDTI2.cxx](#), [DumpVisusChange.cxx](#), [ExtractEncryptedContent.cxx](#), [Extracting_All_Resolution.cxx](#), [Fake_Image_Using_Stream_Image_Writer.cxx](#), [GenAllVR.cxx](#), [GenFakeIdentifyFile.cxx](#), [GenLongSeqs.cxx](#), [GenSeqs.cxx](#), [GetSequenceUltrasound.cxx](#), [GetSubSequenceData.cxx](#), [LargeVRDSExplicit.cxx](#), [NewSequence.cs](#), [SimplePrint.cs](#), [gdcmrtionplan.cxx](#), and [gdcmrtplan.cxx](#).

10.165.2 Constructor & Destructor Documentation

10.165.2.1 Item() [1/2]

```
gdcm::Item::Item () [inline]
```

References [gdcm::DataElement::DataElement\(\)](#).

Referenced by [Item\(\)](#), and [operator<<](#).

10.165.2.2 Item() [2/2]

```
gdcm::Item::Item (
    Item const & val) [inline]
```

References [gdcm::DataElement::DataElement\(\)](#), and [Item\(\)](#).

10.165.3 Member Function Documentation

10.165.3.1 Clear()

```
void gdcm::Item::Clear () [inline]
```

References [gdcm::DataElement::Clear\(\)](#).

Referenced by [gdcm::SequenceOfItems::Read\(\)](#).

10.165.3.2 FindDataElement()

```
bool gdcm::Item::FindDataElement (
    const Tag & t) const [inline]
```

10.165.3.3 GetDataElement()

```
const DataElement & gdcm::Item::GetDataElement (
    const Tag & t) const [inline]
```

References [gdcm::DataElement::DataElement\(\)](#).

10.165.3.4 GetLength()

```
template<typename TDE>
VL gdcm::Item::GetLength () const
```

10.165.3.5 GetNestedDataSet() [1/2]

```
DataSet & gdcm::Item::GetNestedDataSet () [inline]
```

10.165.3.6 GetNestedDataSet() [2/2]

```
const DataSet & gdcm::Item::GetNestedDataSet () const [inline]
```

Examples

[ChangeSequenceUltrasound.cxx](#), [DumpExamCard.cxx](#), [DumpGEMSMovieGroup.cxx](#), [DumpPhilipsECHO.cxx](#), [DumpToshibaDTI.cxx](#), [DumpToshibaDTI2.cxx](#), [DumpVisusChange.cxx](#), [ExtractEncryptedContent.cxx](#), [Extracting_All_Resolution.cxx](#), [Fake_Image_Using_Stream_Image_Writer.cxx](#), [GenAllVR.cxx](#), [GenFakeIdentifyFile.cxx](#), [GenSeqs.cxx](#), [GetSequenceUltrasound.cxx](#), [GetSubSequenceData.cxx](#), [LargeVRDSExplicit.cxx](#), [NewSequence.cs](#), [SimplePrint.cs](#), [gdcmrtionplan.cxx](#), and [gdcmrtplan.cxx](#).

Referenced by [gdcm::SequenceOfItems::Read\(\)](#).

10.165.3.7 InsertDataElement()

```
void gdcm::Item::InsertDataElement (
    const DataElement & de) [inline]
```

References [gdcm::DataElement::DataElement\(\)](#), [gdcm_assert](#), and [gdcm::DataElement::IsUndefinedLength\(\)](#).

10.165.3.8 Read()

```
template<typename TDE, typename TSwap>
std::istream & gdcm::Item::Read (
    std::istream & is) [inline]
```

References [gdcm::ByteSwapFilter::ByteSwap\(\)](#), [gdcm::DataSet::Clear\(\)](#), [gdcm_assert](#), [gdcmDebugMacro](#), [gdcmErrorMacro](#), [gdcmWarningMacro](#), [gdcm::DataSet::IsEmpty\(\)](#), [gdcm::DataElement::ReadWithLength\(\)](#), [gdcm::ByteSwapFilter::SetByteSwapTag\(\)](#), [gdcm::SwapperDoOp::Swap\(\)](#), [gdcm::DataElement::TagField](#), and [gdcm::DataElement::ValueLengthField](#).

Referenced by [gdcm::SequenceOfItems::Read\(\)](#).

10.165.3.9 SetNestedDataSet()

```
void gdcm::Item::SetNestedDataSet (
    const DataSet & nested) [inline]
```

10.165.3.10 Write()

```
template<typename TDE, typename TSwap>
const std::ostream & gdcm::Item::Write (
    std::ostream & os) const [inline]
```

References [gdcm_assert](#), [gdcmWarningMacro](#), [gdcm::VL::GetLength\(\)](#), [gdcm::DataElement::TagField](#), [gdcm::DataElement::ValueLengthField](#), [gdcm::Tag::Write\(\)](#), and [gdcm::VL::Write\(\)](#).

10.165.4 Friends And Related Symbol Documentation

10.165.4.1 operator<<

```
std::ostream & operator<< (
    std::ostream & os,
    const Item & val) [friend]
```

References [Item\(\)](#), [operator<<](#), [gdcm::DataSet::Print\(\)](#), [gdcm::DataElement::TagField](#), and [gdcm::DataElement::ValueLengthField](#).

Referenced by [operator<<](#).


The documentation for this class was generated from the following file:

- [gdcmItem.h](#)


10.166 gdcm::IterationEvent Class Reference

```
#include <gdcmEvent.h>
```

Inheritance diagram for gdcm::IterationEvent:



Collaboration diagram for gdcm::IterationEvent:



Additional Inherited Members

Public Member Functions inherited from [gdcm::Event](#)

- [Event](#) ()

- [Event](#) (const [Event](#) &)
- virtual [~Event](#) ()
- virtual bool [CheckEvent](#) (const [Event](#) *) const =0
- virtual const char * [GetEventName](#) () const =0
- virtual [Event](#) * [MakeObject](#) () const =0
- void [operator=](#) (const [Event](#) &)=delete
- virtual void [Print](#) (std::ostream &os) const

The documentation for this class was generated from the following file:


- [gdcmEvent.h](#)

10.167 gdcm::JPEG12Codec Class Reference


Class to do JPEG 12bits (lossy & lossless)

```
#include <gdcmJPEG12Codec.h>
```

Inheritance diagram for gdcm::JPEG12Codec:



Collaboration diagram for `gdcm::JPEG12Codec`:



Public Member Functions

- `JPEG12Codec` ()
- `~JPEG12Codec` () override
- `bool DecodeByStreams` (std::istream &is, std::ostream &os) override
- `bool GetHeaderInfo` (std::istream &is, `TransferSyntax` &ts) override
- `bool InternalCode` (const char *input, unsigned long len, std::ostream &os) override

Public Member Functions inherited from `gdcm::JPGCodec`

- `JPGCodec` ()
- `~JPGCodec` () override
- `bool CanCode` (`TransferSyntax` const &ts) const override
Return whether this coder support this transfer syntax (can code it)
- `bool CanDecode` (`TransferSyntax` const &ts) const override
Return whether this decoder support this transfer syntax (can decode it)
- `ImageCodec * Clone` () const override
- `bool Code` (`DataElement` const &in, `DataElement` &out) override
Compress into JPEG.
- `void ComputeOffsetTable` (bool b)
Compute the offset table:
- `bool Decode` (`DataElement` const &is, `DataElement` &os) override
Decode.
- `bool GetHeaderInfo` (std::istream &is, `TransferSyntax` &ts) override
- `bool GetLossless` () const
- `double GetQuality` () const
- `void SetLossless` (bool l)
- `void SetPixelFormat` (`PixelFormat` const &pf) override
- `void SetQuality` (double q)

Public Member Functions inherited from [gdcm::ImageCodec](#)

- [ImageCodec](#) ()
- [~ImageCodec](#) () override
- bool [CleanupUnusedBits](#) (char *data, size_t datalen)
- const unsigned int * [GetDimensions](#) () const
- bool [GetLossyFlag](#) () const
- const [LookupTable](#) & [GetLUT](#) () const
- bool [GetNeedByteSwap](#) () const
- unsigned int [GetNumberOfDimensions](#) () const
- const [PhotometricInterpretation](#) & [GetPhotometricInterpretation](#) () const
- [PixelFormat](#) & [GetPixelFormat](#) ()
- const [PixelFormat](#) & [GetPixelFormat](#) () const
- unsigned int [GetPlanarConfiguration](#) () const
- bool [IsLossy](#) () const
- void [SetDimensions](#) (const std::vector< unsigned int > &d)
- void [SetDimensions](#) (const unsigned int d[3])
- void [SetLossyFlag](#) (bool l)
- void [SetLUT](#) ([LookupTable](#) const &lut)
- void [SetNeedByteSwap](#) (bool b)
- void [SetNeedOverlayCleanup](#) (bool b)
- void [SetNumberOfDimensions](#) (unsigned int dim)
- void [SetPhotometricInterpretation](#) ([PhotometricInterpretation](#) const &pi)
- void [SetPlanarConfiguration](#) (unsigned int pc)

Public Member Functions inherited from [gdcm::Coder](#)

- virtual [~Coder](#) ()=default

Public Member Functions inherited from [gdcm::Decoder](#)

- virtual [~Decoder](#) ()=default

Protected Member Functions

- bool [EncodeBuffer](#) (std::ostream &os, const char *data, size_t datalen) override
- bool [IsStateSuspension](#) () const override

Protected Member Functions inherited from [gdcm::JPEGCodec](#)

- bool [AppendFrameEncode](#) (std::ostream &out, const char *data, size_t datalen) override
- bool [AppendRowEncode](#) (std::ostream &out, const char *data, size_t datalen) override
- bool [DecodeByStreams](#) (std::istream &is, std::ostream &os) override
- bool [DecodeExtent](#) (char *buffer, unsigned int xmin, unsigned int xmax, unsigned int ymin, unsigned int ymax, unsigned int zmin, unsigned int zmax, std::istream &is)
- bool [IsFrameEncoder](#) () override
- bool [IsRowEncoder](#) () override
- bool [IsValid](#) ([PhotometricInterpretation](#) const &pi) override
- void [SetBitSample](#) (int bit)
- bool [StartEncode](#) (std::ostream &) override
- bool [StopEncode](#) (std::ostream &) override

Protected Member Functions inherited from [gdcm::ImageCodec](#)

- bool [DoByteSwap](#) (std::istream &is_, std::ostream &os)
- bool [DoInvertMonochrome](#) (std::istream &is_, std::ostream &os)
- bool [DoOverlayCleanup](#) (std::istream &is_, std::ostream &os)
- bool [DoPaddedCompositePixelCode](#) (std::istream &is_, std::ostream &os)
- bool [DoPlanarConfiguration](#) (std::istream &is_, std::ostream &os)
- bool [DoSimpleCopy](#) (std::istream &is_, std::ostream &os)
- bool [DoYBR](#) (std::istream &is_, std::ostream &os)
- bool [DoYBRFull422](#) (std::istream &is_, std::ostream &os)

Additional Inherited Members

Protected Types inherited from [gdcm::ImageCodec](#)

- typedef [SmartPointer](#)< [LookupTable](#) > [LUTPtr](#)

Protected Attributes inherited from [gdcm::JPEGCodec](#)

- int [BitSample](#)
- int [Quality](#)

Protected Attributes inherited from [gdcm::ImageCodec](#)

- unsigned int [Dimensions](#) [3]
- bool [LossyFlag](#)
- [LUTPtr](#) [LUT](#)
- bool [NeedByteSwap](#)
- bool [NeedOverlayCleanup](#)
- unsigned int [NumberOfDimensions](#)
- [PixelFormat](#) [PF](#)
- [PhotometricInterpretation](#) [PI](#)
- unsigned int [PlanarConfiguration](#)
- bool [RequestPaddedCompositePixelCode](#)
- bool [RequestPlanarConfiguration](#)

10.167.1 Detailed Description

Class to do JPEG 12bits (lossy & lossless)

Note

internal class

10.167.2 Constructor & Destructor Documentation

10.167.2.1 JPEG12Codec()

```
gdcm::JPEG12Codec::JPEG12Codec ()
```

10.167.2.2 ~JPEG12Codec()

```
gdcm::JPEG12Codec::~~JPEG12Codec () [override]
```

10.167.3 Member Function Documentation

10.167.3.1 DecodeByStreams()

```
bool gdcm::JPEG12Codec::DecodeByStreams (
    std::istream & is,
    std::ostream & os) [override], [virtual]
```

Reimplemented from [gdcm::ImageCodec](#).

10.167.3.2 EncodeBuffer()

```
bool gdcm::JPEG12Codec::EncodeBuffer (
    std::ostream & os,
    const char * data,
    size_t datalen) [override], [protected], [virtual]
```

Reimplemented from [gdcm::JPEGCodec](#).

10.167.3.3 GetHeaderInfo()

```
bool gdcm::JPEG12Codec::GetHeaderInfo (
    std::istream & is,
    TransferSyntax & ts) [override], [virtual]
```

Reimplemented from [gdcm::ImageCodec](#).

10.167.3.4 InternalCode()

```
bool gdcm::JPEG12Codec::InternalCode (
    const char * input,
    unsigned long len,
    std::ostream & os) [override], [virtual]
```

Reimplemented from [gdcm::Coder](#).

10.167.3.5 IsStateSuspension()

```
bool gdcM::JPEG12Codec::IsStateSuspension () const [override], [protected], [virtual]
```

Reimplemented from [gdcM::JPEGCodec](#).

The documentation for this class was generated from the following file:


- [gdcMJPEG12Codec.h](#)

10.168 gdcM::JPEG16Codec Class Reference


Class to do JPEG 16bits (lossless)

```
#include <gdcMJPEG16Codec.h>
```

Inheritance diagram for gdcM::JPEG16Codec:



Collaboration diagram for gdcm::JPEG16Codec:



Public Member Functions

- [JPEG16Codec](#) ()
- [~JPEG16Codec](#) () override
- bool [DecodeByStreams](#) (std::istream &is, std::ostream &os) override
- bool [GetHeaderInfo](#) (std::istream &is, [TransferSyntax](#) &ts) override
- bool [InternalCode](#) (const char *input, unsigned long len, std::ostream &os) override

Public Member Functions inherited from [gdcm::JPEGCodec](#)

- [JPEGCodec](#) ()
- [~JPEGCodec](#) () override
- bool [CanCode](#) ([TransferSyntax](#) const &ts) const override
Return whether this coder support this transfer syntax (can code it)
- bool [CanDecode](#) ([TransferSyntax](#) const &ts) const override
Return whether this decoder support this transfer syntax (can decode it)
- [ImageCodec](#) * [Clone](#) () const override
- bool [Code](#) ([DataElement](#) const &in, [DataElement](#) &out) override
Compress into JPEG.
- void [ComputeOffsetTable](#) (bool b)
Compute the offset table:
- bool [Decode](#) ([DataElement](#) const &is, [DataElement](#) &os) override
Decode.
- bool [GetHeaderInfo](#) (std::istream &is, [TransferSyntax](#) &ts) override
- bool [GetLossless](#) () const
- double [GetQuality](#) () const
- void [SetLossless](#) (bool l)
- void [SetPixelFormat](#) ([PixelFormat](#) const &pf) override
- void [SetQuality](#) (double q)

Public Member Functions inherited from [gdcm::ImageCodec](#)

- [ImageCodec](#) ()
- [~ImageCodec](#) () override
- bool [CleanupUnusedBits](#) (char *data, size_t datalen)
- const unsigned int * [GetDimensions](#) () const
- bool [GetLossyFlag](#) () const
- const [LookupTable](#) & [GetLUT](#) () const
- bool [GetNeedByteSwap](#) () const
- unsigned int [GetNumberOfDimensions](#) () const
- const [PhotometricInterpretation](#) & [GetPhotometricInterpretation](#) () const
- [PixelFormat](#) & [GetPixelFormat](#) ()
- const [PixelFormat](#) & [GetPixelFormat](#) () const
- unsigned int [GetPlanarConfiguration](#) () const
- bool [IsLossy](#) () const
- void [SetDimensions](#) (const std::vector< unsigned int > &d)
- void [SetDimensions](#) (const unsigned int d[3])
- void [SetLossyFlag](#) (bool l)
- void [SetLUT](#) ([LookupTable](#) const &lut)
- void [SetNeedByteSwap](#) (bool b)
- void [SetNeedOverlayCleanup](#) (bool b)
- void [SetNumberOfDimensions](#) (unsigned int dim)
- void [SetPhotometricInterpretation](#) ([PhotometricInterpretation](#) const &pi)
- void [SetPlanarConfiguration](#) (unsigned int pc)

Public Member Functions inherited from [gdcm::Coder](#)

- virtual [~Coder](#) ()=default

Public Member Functions inherited from [gdcm::Decoder](#)

- virtual [~Decoder](#) ()=default

Protected Member Functions

- bool [EncodeBuffer](#) (std::ostream &os, const char *data, size_t datalen) override
- bool [IsStateSuspension](#) () const override

Protected Member Functions inherited from [gdcm::JPEGCodec](#)

- bool [AppendFrameEncode](#) (std::ostream &out, const char *data, size_t datalen) override
- bool [AppendRowEncode](#) (std::ostream &out, const char *data, size_t datalen) override
- bool [DecodeByStreams](#) (std::istream &is, std::ostream &os) override
- bool [DecodeExtent](#) (char *buffer, unsigned int xmin, unsigned int xmax, unsigned int ymin, unsigned int ymax, unsigned int zmin, unsigned int zmax, std::istream &is)
- bool [IsFrameEncoder](#) () override
- bool [IsRowEncoder](#) () override
- bool [IsValid](#) ([PhotometricInterpretation](#) const &pi) override
- void [SetBitSample](#) (int bit)
- bool [StartEncode](#) (std::ostream &) override
- bool [StopEncode](#) (std::ostream &) override

Protected Member Functions inherited from [gdcm::ImageCodec](#)

- bool [DoByteSwap](#) (std::istream &is_, std::ostream &os)
- bool [DoInvertMonochrome](#) (std::istream &is_, std::ostream &os)
- bool [DoOverlayCleanup](#) (std::istream &is_, std::ostream &os)
- bool [DoPaddedCompositePixelCode](#) (std::istream &is_, std::ostream &os)
- bool [DoPlanarConfiguration](#) (std::istream &is_, std::ostream &os)
- bool [DoSimpleCopy](#) (std::istream &is_, std::ostream &os)
- bool [DoYBR](#) (std::istream &is_, std::ostream &os)
- bool [DoYBRFull422](#) (std::istream &is_, std::ostream &os)

Additional Inherited Members

Protected Types inherited from [gdcm::ImageCodec](#)

- typedef [SmartPointer](#)< [LookupTable](#) > LUTPtr

Protected Attributes inherited from [gdcm::JPEGCodec](#)

- int [BitSample](#)
- int [Quality](#)

Protected Attributes inherited from [gdcm::ImageCodec](#)

- unsigned int [Dimensions](#) [3]
- bool [LossyFlag](#)
- [LUTPtr](#) LUT
- bool [NeedByteSwap](#)
- bool [NeedOverlayCleanup](#)
- unsigned int [NumberOfDimensions](#)
- [PixelFormat](#) PF
- [PhotometricInterpretation](#) PI
- unsigned int [PlanarConfiguration](#)
- bool [RequestPaddedCompositePixelCode](#)
- bool [RequestPlanarConfiguration](#)

10.168.1 Detailed Description

Class to do JPEG 16bits (lossless)

Note

internal class

10.168.2 Constructor & Destructor Documentation

10.168.2.1 JPEG16Codec()

```
gdcm::JPEG16Codec::JPEG16Codec ()
```

10.168.2.2 ~JPEG16Codec()

```
gdcm::JPEG16Codec::~~JPEG16Codec () [override]
```

10.168.3 Member Function Documentation

10.168.3.1 DecodeByStreams()

```
bool gdcm::JPEG16Codec::DecodeByStreams (
    std::istream & is,
    std::ostream & os) [override], [virtual]
```

Reimplemented from [gdcm::ImageCodec](#).

10.168.3.2 EncodeBuffer()

```
bool gdcm::JPEG16Codec::EncodeBuffer (
    std::ostream & os,
    const char * data,
    size_t datalen) [override], [protected], [virtual]
```

Reimplemented from [gdcm::JPEGCodec](#).

10.168.3.3 GetHeaderInfo()

```
bool gdcm::JPEG16Codec::GetHeaderInfo (
    std::istream & is,
    TransferSyntax & ts) [override], [virtual]
```

Reimplemented from [gdcm::ImageCodec](#).

10.168.3.4 InternalCode()

```
bool gdcm::JPEG16Codec::InternalCode (
    const char * input,
    unsigned long len,
    std::ostream & os) [override], [virtual]
```

Reimplemented from [gdcm::Coder](#).

10.168.3.5 IsStateSuspension()

```
bool gdcm::JPEG16Codec::IsStateSuspension () const [override], [protected], [virtual]
```

Reimplemented from [gdcm::JPEGCodec](#).

The documentation for this class was generated from the following file:


- [gdcmJPEG16Codec.h](#)

10.169 gdcm::JPEG2000Codec Class Reference


Class to do JPEG 2000.

```
#include <gdcmJPEG2000Codec.h>
```

Inheritance diagram for gdcm::JPEG2000Codec:



Collaboration diagram for gdcm::JPEG2000Codec:



Public Member Functions

- [JPEG2000Codec](#) ()
- [~JPEG2000Codec](#) () override
- bool [CanCode](#) ([TransferSyntax](#) const &ts) const override
Return whether this coder support this transfer syntax (can code it)
- bool [CanDecode](#) ([TransferSyntax](#) const &ts) const override
Return whether this decoder support this transfer syntax (can decode it)
- [ImageCodec](#) * [Clone](#) () const override
- bool [Code](#) ([DataElement](#) const &in, [DataElement](#) &out) override
Code.
- bool [Decode](#) ([DataElement](#) const &is, [DataElement](#) &os) override
Decode.
- bool [GetHeaderInfo](#) (std::istream &is, [TransferSyntax](#) &ts) override
- double [GetQuality](#) (unsigned int idx=0) const
- double [GetRate](#) (unsigned int idx=0) const
- void [SetMCT](#) (unsigned int mct)
- void [SetNumberOfResolutions](#) (unsigned int nres)
- void [SetNumberOfThreadsForDecompression](#) (int nThreads)
- void [SetQuality](#) (unsigned int idx, double q)
- void [SetRate](#) (unsigned int idx, double rate)
- void [SetReversible](#) (bool res)
- void [SetTileSize](#) (unsigned int tx, unsigned int ty)

Public Member Functions inherited from [gdcm::ImageCodec](#)

- [ImageCodec](#) ()
- [~ImageCodec](#) () override
- bool [CleanupUnusedBits](#) (char *data, size_t datalen)
- const unsigned int * [GetDimensions](#) () const
- bool [GetLossyFlag](#) () const
- const [LookupTable](#) & [GetLUT](#) () const
- bool [GetNeedByteSwap](#) () const
- unsigned int [GetNumberOfDimensions](#) () const
- const [PhotometricInterpretation](#) & [GetPhotometricInterpretation](#) () const
- [PixelFormat](#) & [GetPixelFormat](#) ()
- const [PixelFormat](#) & [GetPixelFormat](#) () const
- unsigned int [GetPlanarConfiguration](#) () const
- bool [IsLossy](#) () const
- void [SetDimensions](#) (const std::vector< unsigned int > &d)
- void [SetDimensions](#) (const unsigned int d[3])
- void [SetLossyFlag](#) (bool l)
- void [SetLUT](#) ([LookupTable](#) const &lut)
- void [SetNeedByteSwap](#) (bool b)
- void [SetNeedOverlayCleanup](#) (bool b)
- void [SetNumberOfDimensions](#) (unsigned int dim)
- void [SetPhotometricInterpretation](#) ([PhotometricInterpretation](#) const &pi)
- virtual void [SetPixelFormat](#) ([PixelFormat](#) const &pf)
- void [SetPlanarConfiguration](#) (unsigned int pc)

Public Member Functions inherited from [gdcm::Coder](#)

- virtual [~Coder](#) ()=default

Public Member Functions inherited from [gdcm::Decoder](#)

- virtual [~Decoder](#) ()=default

Protected Member Functions

- bool [AppendFrameEncode](#) (std::ostream &out, const char *data, size_t datalen) override
- bool [AppendRowEncode](#) (std::ostream &out, const char *data, size_t datalen) override
- bool [DecodeByStreams](#) (std::istream &is, std::ostream &os) override
- bool [DecodeExtent](#) (char *buffer, unsigned int xmin, unsigned int xmax, unsigned int ymin, unsigned int ymax, unsigned int zmin, unsigned int zmax, std::istream &is)
- bool [IsFrameEncoder](#) () override
- bool [IsRowEncoder](#) () override
- bool [StartEncode](#) (std::ostream &) override
- bool [StopEncode](#) (std::ostream &) override

Protected Member Functions inherited from [gdcm::ImageCodec](#)

- bool [DoByteSwap](#) (std::istream &is_, std::ostream &os)
- bool [DoInvertMonochrome](#) (std::istream &is_, std::ostream &os)
- bool [DoOverlayCleanup](#) (std::istream &is_, std::ostream &os)
- bool [DoPaddedCompositePixelCode](#) (std::istream &is_, std::ostream &os)
- bool [DoPlanarConfiguration](#) (std::istream &is_, std::ostream &os)
- bool [DoSimpleCopy](#) (std::istream &is_, std::ostream &os)
- bool [DoYBR](#) (std::istream &is_, std::ostream &os)
- bool [DoYBRFull422](#) (std::istream &is_, std::ostream &os)
- virtual bool [IsValid](#) ([PhotometricInterpretation](#) const &pi)

Protected Member Functions inherited from [gdcm::Coder](#)

- virtual bool [InternalCode](#) (const char *bv, unsigned long len, std::ostream &os)

Friends

- class [Bitmap](#)
- class [ImageRegionReader](#)

Additional Inherited Members

Protected Types inherited from [gdcm::ImageCodec](#)

- typedef [SmartPointer](#)< [LookupTable](#) > [LUTPtr](#)

Protected Attributes inherited from [gdcm::ImageCodec](#)

- unsigned int [Dimensions](#) [3]
- bool [LossyFlag](#)
- [LUTPtr](#) LUT
- bool [NeedByteSwap](#)
- bool [NeedOverlayCleanup](#)
- unsigned int [NumberOfDimensions](#)
- [PixelFormat](#) PF
- [PhotometricInterpretation](#) PI
- unsigned int [PlanarConfiguration](#)
- bool [RequestPaddedCompositePixelCode](#)
- bool [RequestPlanarConfiguration](#)

10.169.1 Detailed Description

Class to do JPEG 2000.

Note

the class will produce JPC (JPEG 2000 codestream), since some private implementor are using full jp2 file the decoder tolerate jp2 input this is an implementation of an [ImageCodec](#)

10.169.2 Constructor & Destructor Documentation

10.169.2.1 JPEG2000Codec()

```
gdcm::JPEG2000Codec::JPEG2000Codec ()
```

10.169.2.2 ~JPEG2000Codec()

```
gdcm::JPEG2000Codec::~~JPEG2000Codec () [override]
```

10.169.3 Member Function Documentation

10.169.3.1 AppendFrameEncode()

```
bool gdcm::JPEG2000Codec::AppendFrameEncode (
    std::ostream & out,
    const char * data,
    size_t datalen) [override], [protected], [virtual]
```

Reimplemented from [gdcm::ImageCodec](#).

10.169.3.2 AppendRowEncode()

```
bool gdcm::JPEG2000Codec::AppendRowEncode (
    std::ostream & out,
    const char * data,
    size_t datalen) [override], [protected], [virtual]
```

Reimplemented from [gdcm::ImageCodec](#).

10.169.3.3 CanCode()

```
bool gdcm::JPEG2000Codec::CanCode (
    TransferSyntax const & ) const [override], [virtual]
```

Return whether this coder support this transfer syntax (can code it)

Reimplemented from [gdcm::ImageCodec](#).

10.169.3.4 CanDecode()

```
bool gdcm::JPEG2000Codec::CanDecode (
    TransferSyntax const & ) const [override], [virtual]
```

Return whether this decoder support this transfer syntax (can decode it)

Reimplemented from [gdcm::ImageCodec](#).

10.169.3.5 Clone()

```
ImageCodec * gdcm::JPEG2000Codec::Clone () const [override], [virtual]
```

Implements [gdcm::ImageCodec](#).

References [gdcm::ImageCodec::ImageCodec\(\)](#).

10.169.3.6 Code()

```
bool gdcm::JPEG2000Codec::Code (
    DataElement const & in_,
    DataElement & out_) [override], [virtual]
```

Code.

Reimplemented from [gdcm::Coder](#).

10.169.3.7 Decode()

```
bool gdcM::JPEG2000Codec::Decode (
    DataElement const & ,
    DataElement & ) [override], [virtual]
```

Decode.

Reimplemented from [gdcM::ImageCodec](#).

10.169.3.8 DecodeByStreams()

```
bool gdcM::JPEG2000Codec::DecodeByStreams (
    std::istream & is,
    std::ostream & os) [override], [protected], [virtual]
```

Reimplemented from [gdcM::ImageCodec](#).

10.169.3.9 DecodeExtent()

```
bool gdcM::JPEG2000Codec::DecodeExtent (
    char * buffer,
    unsigned int xmin,
    unsigned int xmax,
    unsigned int ymin,
    unsigned int ymax,
    unsigned int zmin,
    unsigned int zmax,
    std::istream & is) [protected]
```

10.169.3.10 GetHeaderInfo()

```
bool gdcM::JPEG2000Codec::GetHeaderInfo (
    std::istream & is,
    TransferSyntax & ts) [override], [virtual]
```

Reimplemented from [gdcM::ImageCodec](#).

Referenced by [StopEncode\(\)](#).

10.169.3.11 GetQuality()

```
double gdcM::JPEG2000Codec::GetQuality (
    unsigned int idx = 0) const
```

10.169.3.12 GetRate()

```
double gdcm::JPEG2000Codec::GetRate (
    unsigned int idx = 0) const
```

10.169.3.13 IsFrameEncoder()

```
bool gdcm::JPEG2000Codec::IsFrameEncoder () [override], [protected], [virtual]
```

Reimplemented from [gdcm::ImageCodec](#).

10.169.3.14 IsRowEncoder()

```
bool gdcm::JPEG2000Codec::IsRowEncoder () [override], [protected], [virtual]
```

Reimplemented from [gdcm::ImageCodec](#).

10.169.3.15 SetMCT()

```
void gdcm::JPEG2000Codec::SetMCT (
    unsigned int mct)
```

10.169.3.16 SetNumberOfResolutions()

```
void gdcm::JPEG2000Codec::SetNumberOfResolutions (
    unsigned int nres)
```

10.169.3.17 SetNumberOfThreadsForDecompression()

```
void gdcm::JPEG2000Codec::SetNumberOfThreadsForDecompression (
    int nThreads)
```

Set Number of threads

Parameters

<i>nThreads</i>	: number of threads for decompression codec, if 0 or 1 decompression is done in current thread, if negative value is set determine how many virtual threads are available
-----------------	---

10.169.3.18 SetQuality()

```
void gdcm::JPEG2000Codec::SetQuality (
    unsigned int idx,
    double q)
```

10.169.3.19 SetRate()

```
void gdcmm::JPEG2000Codec::SetRate (
    unsigned int idx,
    double rate)
```

10.169.3.20 SetReversible()

```
void gdcmm::JPEG2000Codec::SetReversible (
    bool res)
```

10.169.3.21 SetTileSize()

```
void gdcmm::JPEG2000Codec::SetTileSize (
    unsigned int tx,
    unsigned int ty)
```

10.169.3.22 StartEncode()

```
bool gdcmm::JPEG2000Codec::StartEncode (
    std::ostream & ) [override], [protected], [virtual]
```

Reimplemented from [gdcmm::ImageCodec](#).

10.169.3.23 StopEncode()

```
bool gdcmm::JPEG2000Codec::StopEncode (
    std::ostream & ) [override], [protected], [virtual]
```

Reimplemented from [gdcmm::ImageCodec](#).

References [GetHeaderInfo\(\)](#).

10.169.4 Friends And Related Symbol Documentation**10.169.4.1 Bitmap**

```
friend class Bitmap [friend]
```

References [Bitmap](#).

Referenced by [Bitmap](#).

10.169.4.2 ImageRegionReader

```
friend class ImageRegionReader [friend]
```

References [ImageRegionReader](#).

Referenced by [ImageRegionReader](#).

The documentation for this class was generated from the following file:


- [gdcmJPEG2000Codec.h](#)

10.170 gdcm::JPEG8Codec Class Reference


Class to do JPEG 8bits (lossy & lossless)

```
#include <gdcmJPEG8Codec.h>
```

Inheritance diagram for gdcm::JPEG8Codec:



Collaboration diagram for `gdcm::JPEG8Codec`:



Public Member Functions

- `JPEG8Codec` ()
- `~JPEG8Codec` () override
- `bool DecodeByStreams` (std::istream &is, std::ostream &os) override
- `bool GetHeaderInfo` (std::istream &is, `TransferSyntax` &ts) override
- `bool InternalCode` (const char *input, unsigned long len, std::ostream &os) override

Public Member Functions inherited from `gdcm::JPEGCodec`

- `JPEGCodec` ()
- `~JPEGCodec` () override
- `bool CanCode` (`TransferSyntax` const &ts) const override
Return whether this coder support this transfer syntax (can code it)
- `bool CanDecode` (`TransferSyntax` const &ts) const override
Return whether this decoder support this transfer syntax (can decode it)
- `ImageCodec * Clone` () const override
- `bool Code` (`DataElement` const &in, `DataElement` &out) override
Compress into JPEG.
- `void ComputeOffsetTable` (bool b)
Compute the offset table:
- `bool Decode` (`DataElement` const &is, `DataElement` &os) override
Decode.
- `bool GetHeaderInfo` (std::istream &is, `TransferSyntax` &ts) override
- `bool GetLossless` () const
- `double GetQuality` () const
- `void SetLossless` (bool l)
- `void SetPixelFormat` (`PixelFormat` const &pf) override
- `void SetQuality` (double q)

Public Member Functions inherited from [gdcm::ImageCodec](#)

- [ImageCodec](#) ()
- [~ImageCodec](#) () override
- bool [CleanupUnusedBits](#) (char *data, size_t datalen)
- const unsigned int * [GetDimensions](#) () const
- bool [GetLossyFlag](#) () const
- const [LookupTable](#) & [GetLUT](#) () const
- bool [GetNeedByteSwap](#) () const
- unsigned int [GetNumberOfDimensions](#) () const
- const [PhotometricInterpretation](#) & [GetPhotometricInterpretation](#) () const
- [PixelFormat](#) & [GetPixelFormat](#) ()
- const [PixelFormat](#) & [GetPixelFormat](#) () const
- unsigned int [GetPlanarConfiguration](#) () const
- bool [IsLossy](#) () const
- void [SetDimensions](#) (const std::vector< unsigned int > &d)
- void [SetDimensions](#) (const unsigned int d[3])
- void [SetLossyFlag](#) (bool l)
- void [SetLUT](#) ([LookupTable](#) const &lut)
- void [SetNeedByteSwap](#) (bool b)
- void [SetNeedOverlayCleanup](#) (bool b)
- void [SetNumberOfDimensions](#) (unsigned int dim)
- void [SetPhotometricInterpretation](#) ([PhotometricInterpretation](#) const &pi)
- void [SetPlanarConfiguration](#) (unsigned int pc)

Public Member Functions inherited from [gdcm::Coder](#)

- virtual [~Coder](#) ()=default

Public Member Functions inherited from [gdcm::Decoder](#)

- virtual [~Decoder](#) ()=default

Protected Member Functions

- bool [EncodeBuffer](#) (std::ostream &os, const char *data, size_t datalen) override
- bool [IsStateSuspension](#) () const override

Protected Member Functions inherited from [gdcm::JPEGCodec](#)

- bool [AppendFrameEncode](#) (std::ostream &out, const char *data, size_t datalen) override
- bool [AppendRowEncode](#) (std::ostream &out, const char *data, size_t datalen) override
- bool [DecodeByStreams](#) (std::istream &is, std::ostream &os) override
- bool [DecodeExtent](#) (char *buffer, unsigned int xmin, unsigned int xmax, unsigned int ymin, unsigned int ymax, unsigned int zmin, unsigned int zmax, std::istream &is)
- bool [IsFrameEncoder](#) () override
- bool [IsRowEncoder](#) () override
- bool [IsValid](#) ([PhotometricInterpretation](#) const &pi) override
- void [SetBitSample](#) (int bit)
- bool [StartEncode](#) (std::ostream &) override
- bool [StopEncode](#) (std::ostream &) override

Protected Member Functions inherited from [gdcm::ImageCodec](#)

- bool [DoByteSwap](#) (std::istream &is_, std::ostream &os)
- bool [DoInvertMonochrome](#) (std::istream &is_, std::ostream &os)
- bool [DoOverlayCleanup](#) (std::istream &is_, std::ostream &os)
- bool [DoPaddedCompositePixelCode](#) (std::istream &is_, std::ostream &os)
- bool [DoPlanarConfiguration](#) (std::istream &is_, std::ostream &os)
- bool [DoSimpleCopy](#) (std::istream &is_, std::ostream &os)
- bool [DoYBR](#) (std::istream &is_, std::ostream &os)
- bool [DoYBRFull422](#) (std::istream &is_, std::ostream &os)

Additional Inherited Members

Protected Types inherited from [gdcm::ImageCodec](#)

- typedef [SmartPointer](#)< [LookupTable](#) > [LUTPtr](#)

Protected Attributes inherited from [gdcm::JPEGCodec](#)

- int [BitSample](#)
- int [Quality](#)

Protected Attributes inherited from [gdcm::ImageCodec](#)

- unsigned int [Dimensions](#) [3]
- bool [LossyFlag](#)
- [LUTPtr](#) [LUT](#)
- bool [NeedByteSwap](#)
- bool [NeedOverlayCleanup](#)
- unsigned int [NumberOfDimensions](#)
- [PixelFormat](#) [PF](#)
- [PhotometricInterpretation](#) [PI](#)
- unsigned int [PlanarConfiguration](#)
- bool [RequestPaddedCompositePixelCode](#)
- bool [RequestPlanarConfiguration](#)

10.170.1 Detailed Description

Class to do JPEG 8bits (lossy & lossless)

Note

internal class

10.170.2 Constructor & Destructor Documentation

10.170.2.1 JPEG8Codec()

```
gdcm::JPEG8Codec::JPEG8Codec ()
```

10.170.2.2 ~JPEG8Codec()

```
gdcm::JPEG8Codec::~~JPEG8Codec () [override]
```

10.170.3 Member Function Documentation

10.170.3.1 DecodeByStreams()

```
bool gdcm::JPEG8Codec::DecodeByStreams (
    std::istream & is,
    std::ostream & os) [override], [virtual]
```

Reimplemented from [gdcm::ImageCodec](#).

10.170.3.2 EncodeBuffer()

```
bool gdcm::JPEG8Codec::EncodeBuffer (
    std::ostream & os,
    const char * data,
    size_t datalen) [override], [protected], [virtual]
```

Reimplemented from [gdcm::JPEGCodec](#).

10.170.3.3 GetHeaderInfo()

```
bool gdcm::JPEG8Codec::GetHeaderInfo (
    std::istream & is,
    TransferSyntax & ts) [override], [virtual]
```

Reimplemented from [gdcm::ImageCodec](#).

10.170.3.4 InternalCode()

```
bool gdcm::JPEG8Codec::InternalCode (
    const char * input,
    unsigned long len,
    std::ostream & os) [override], [virtual]
```

Reimplemented from [gdcm::Coder](#).

10.170.3.5 IsStateSuspension()

```
bool gdcM::JPEG8Codec::IsStateSuspension () const [override], [protected], [virtual]
```

Reimplemented from [gdcM::JPEGCodec](#).

The documentation for this class was generated from the following file:


- [gdcMJPEG8Codec.h](#)

10.171 gdcM::JPEGCodec Class Reference


JPEG codec.

```
#include <gdcMJPEGCodec.h>
```

Inheritance diagram for gdcM::JPEGCodec:



Collaboration diagram for gdcM::JPEGCodec:



Public Member Functions

- [JPEGCodec](#) ()
- [~JPEGCodec](#) () override
- bool [CanCode](#) ([TransferSyntax](#) const &ts) const override
Return whether this coder support this transfer syntax (can code it)
- bool [CanDecode](#) ([TransferSyntax](#) const &ts) const override
Return whether this decoder support this transfer syntax (can decode it)
- [ImageCodec](#) * [Clone](#) () const override
- bool [Code](#) ([DataElement](#) const &in, [DataElement](#) &out) override
Compress into JPEG.
- void [ComputeOffsetTable](#) (bool b)
Compute the offset table:
- bool [Decode](#) ([DataElement](#) const &is, [DataElement](#) &os) override
Decode.
- virtual bool [EncodeBuffer](#) (std::ostream &out, const char *inbuffer, size_t inlen)
- bool [GetHeaderInfo](#) (std::istream &is, [TransferSyntax](#) &ts) override
- bool [GetLossless](#) () const
- double [GetQuality](#) () const
- void [SetLossless](#) (bool l)
- void [SetPixelFormat](#) ([PixelFormat](#) const &pf) override
- void [SetQuality](#) (double q)

Public Member Functions inherited from [gdcm::ImageCodec](#)

- [ImageCodec](#) ()
- [~ImageCodec](#) () override
- bool [CleanupUnusedBits](#) (char *data, size_t datalen)
- const unsigned int * [GetDimensions](#) () const
- bool [GetLossyFlag](#) () const
- const [LookupTable](#) & [GetLUT](#) () const
- bool [GetNeedByteSwap](#) () const
- unsigned int [GetNumberOfDimensions](#) () const
- const [PhotometricInterpretation](#) & [GetPhotometricInterpretation](#) () const
- [PixelFormat](#) & [GetPixelFormat](#) ()
- const [PixelFormat](#) & [GetPixelFormat](#) () const
- unsigned int [GetPlanarConfiguration](#) () const
- bool [IsLossy](#) () const
- void [SetDimensions](#) (const std::vector< unsigned int > &d)
- void [SetDimensions](#) (const unsigned int d[3])
- void [SetLossyFlag](#) (bool l)
- void [SetLUT](#) ([LookupTable](#) const &lut)
- void [SetNeedByteSwap](#) (bool b)
- void [SetNeedOverlayCleanup](#) (bool b)
- void [SetNumberOfDimensions](#) (unsigned int dim)
- void [SetPhotometricInterpretation](#) ([PhotometricInterpretation](#) const &pi)
- void [SetPlanarConfiguration](#) (unsigned int pc)

Public Member Functions inherited from [gdcm::Coder](#)

- virtual [~Coder](#) ()=default

Public Member Functions inherited from [gdcm::Decoder](#)

- virtual [~Decoder](#) ()=default

Protected Member Functions

- bool [AppendFrameEncode](#) (std::ostream &out, const char *data, size_t datalen) override
- bool [AppendRowEncode](#) (std::ostream &out, const char *data, size_t datalen) override
- bool [DecodeByStreams](#) (std::istream &is, std::ostream &os) override
- bool [DecodeExtent](#) (char *buffer, unsigned int xmin, unsigned int xmax, unsigned int ymin, unsigned int ymax, unsigned int zmin, unsigned int zmax, std::istream &is)
- bool [IsFrameEncoder](#) () override
- bool [IsRowEncoder](#) () override
- virtual bool [IsStateSuspension](#) () const
- bool [IsValid](#) ([PhotometricInterpretation](#) const &pi) override
- void [SetBitSample](#) (int bit)
- bool [StartEncode](#) (std::ostream &) override
- bool [StopEncode](#) (std::ostream &) override

Protected Member Functions inherited from [gdcm::ImageCodec](#)

- bool [DoByteSwap](#) (std::istream &is_, std::ostream &os)
- bool [DoInvertMonochrome](#) (std::istream &is_, std::ostream &os)
- bool [DoOverlayCleanup](#) (std::istream &is_, std::ostream &os)
- bool [DoPaddedCompositePixelCode](#) (std::istream &is_, std::ostream &os)
- bool [DoPlanarConfiguration](#) (std::istream &is_, std::ostream &os)
- bool [DoSimpleCopy](#) (std::istream &is_, std::ostream &os)
- bool [DoYBR](#) (std::istream &is_, std::ostream &os)
- bool [DoYBRFull422](#) (std::istream &is_, std::ostream &os)

Protected Member Functions inherited from [gdcm::Coder](#)

- virtual bool [InternalCode](#) (const char *bv, unsigned long len, std::ostream &os)

Protected Attributes

- int [BitSample](#)
- int [Quality](#)

Protected Attributes inherited from [gdcm::ImageCodec](#)

- unsigned int [Dimensions](#) [3]
- bool [LossyFlag](#)
- [LUTPtr](#) LUT
- bool [NeedByteSwap](#)
- bool [NeedOverlayCleanup](#)
- unsigned int [NumberOfDimensions](#)
- [PixelFormat](#) PF
- [PhotometricInterpretation](#) PI
- unsigned int [PlanarConfiguration](#)
- bool [RequestPaddedCompositePixelCode](#)
- bool [RequestPlanarConfiguration](#)

Friends

- class [ImageRegionReader](#)

Additional Inherited Members

Protected Types inherited from [gdcm::ImageCodec](#)

- typedef [SmartPointer](#)< [LookupTable](#) > [LUTPtr](#)

10.171.1 Detailed Description

JPEG codec.

Class to do JPEG (8bits, 12bits, 16bits lossy & lossless). It redispach in between the different codec implementation: [JPEG8Codec](#), [JPEG12Codec](#) & [JPEG16Codec](#) It also support inconsistency in between DICOM header and JPEG compressed stream [ImageCodec](#) implementation for the JPEG case

Note

Things you should know if you ever want to dive into DICOM/JPEG world (among other):

- http://groups.google.com/group/comp.protocols.dicom/browse_thread/thread/625e46919f208
- http://groups.google.com/group/comp.protocols.dicom/browse_thread/thread/75fdfccc65a62
- http://groups.google.com/group/comp.protocols.dicom/browse_thread/thread/2d525ef6a2f09
- http://groups.google.com/group/comp.protocols.dicom/browse_thread/thread/6b93af410f8c9

Examples

[CompressLossyJPEG.cs](#), [FileChangeTSLossy.cs](#), and [GetJPEGSamplePrecision.cxx](#).

10.171.2 Constructor & Destructor Documentation

10.171.2.1 JPEGCodec()

```
gdcM::JPEGCodec::JPEGCodec ()
```

10.171.2.2 ~JPEGCodec()

```
gdcM::JPEGCodec::~~JPEGCodec () [override]
```

10.171.3 Member Function Documentation

10.171.3.1 AppendFrameEncode()

```
bool gdcM::JPEGCodec::AppendFrameEncode (
    std::ostream & out,
    const char * data,
    size_t datalen) [override], [protected], [virtual]
```

Reimplemented from [gdcM::ImageCodec](#).

10.171.3.2 AppendRowEncode()

```
bool gdcM::JPEGCodec::AppendRowEncode (
    std::ostream & out,
    const char * data,
    size_t datalen) [override], [protected], [virtual]
```

Reimplemented from [gdcM::ImageCodec](#).

10.171.3.3 CanCode()

```
bool gdcM::JPEGCodec::CanCode (
    TransferSyntax const & ) const [override], [virtual]
```

Return whether this coder support this transfer syntax (can code it)

Reimplemented from [gdcM::ImageCodec](#).

Examples

[CompressLossyJPEG.cs](#).

10.171.3.4 CanDecode()

```
bool gdcm::JPEGCodec::CanDecode (
    TransferSyntax const & ) const [override], [virtual]
```

Return whether this decoder support this transfer syntax (can decode it)

Reimplemented from [gdcm::ImageCodec](#).

10.171.3.5 Clone()

```
ImageCodec * gdcm::JPEGCodec::Clone () const [override], [virtual]
```

Implements [gdcm::ImageCodec](#).

References [gdcm::ImageCodec::ImageCodec\(\)](#).

10.171.3.6 Code()

```
bool gdcm::JPEGCodec::Code (
    DataElement const & in,
    DataElement & out) [override], [virtual]
```

Compress into JPEG.

Reimplemented from [gdcm::Coder](#).

10.171.3.7 ComputeOffsetTable()

```
void gdcm::JPEGCodec::ComputeOffsetTable (
    bool b)
```

Compute the offset table:

10.171.3.8 Decode()

```
bool gdcm::JPEGCodec::Decode (
    DataElement const & ,
    DataElement & ) [override], [virtual]
```

Decode.

Reimplemented from [gdcm::ImageCodec](#).

10.171.3.9 DecodeByStreams()

```
bool gdcm::JPEGCodec::DecodeByStreams (
    std::istream & is,
    std::ostream & os) [override], [protected], [virtual]
```

Reimplemented from [gdcm::ImageCodec](#).

10.171.3.10 DecodeExtent()

```
bool gdcm::JPEGCodec::DecodeExtent (
    char * buffer,
    unsigned int xmin,
    unsigned int xmax,
    unsigned int ymin,
    unsigned int ymax,
    unsigned int zmin,
    unsigned int zmax,
    std::istream & is) [protected]
```

10.171.3.11 EncodeBuffer()

```
virtual bool gdcm::JPEGCodec::EncodeBuffer (
    std::ostream & out,
    const char * inbuffer,
    size_t inlen) [virtual]
```

Reimplemented in [gdcm::JPEG12Codec](#), [gdcm::JPEG16Codec](#), and [gdcm::JPEG8Codec](#).

10.171.3.12 GetHeaderInfo()

```
bool gdcm::JPEGCodec::GetHeaderInfo (
    std::istream & is,
    TransferSyntax & ts) [override], [virtual]
```

Reimplemented from [gdcm::ImageCodec](#).

Examples

[GetJPEGSamplePrecision.cxx](#).

10.171.3.13 GetLossless()

```
bool gdcm::JPEGCodec::GetLossless () const
```

10.171.3.14 GetQuality()

```
double gdcm::JPEGCodec::GetQuality () const
```

10.171.3.15 IsFrameEncoder()

```
bool gdcm::JPEGCodec::IsFrameEncoder () [override], [protected], [virtual]
```

Reimplemented from [gdcm::ImageCodec](#).

10.171.3.16 IsRowEncoder()

```
bool gdcm::JPEGCodec::IsRowEncoder () [override], [protected], [virtual]
```

Reimplemented from [gdcm::ImageCodec](#).

10.171.3.17 IsStateSuspension()

```
virtual bool gdcm::JPEGCodec::IsStateSuspension () const [protected], [virtual]
```

Reimplemented in [gdcm::JPEG12Codec](#), [gdcm::JPEG16Codec](#), and [gdcm::JPEG8Codec](#).

10.171.3.18 IsValid()

```
bool gdcm::JPEGCodec::IsValid (  
    PhotometricInterpretation const & pi) [override], [protected], [virtual]
```

Reimplemented from [gdcm::ImageCodec](#).

10.171.3.19 SetBitSample()

```
void gdcm::JPEGCodec::SetBitSample (  
    int bit) [protected]
```

10.171.3.20 SetLossless()

```
void gdcm::JPEGCodec::SetLossless (  
    bool l)
```

Examples

[CompressLossyJPEG.cs](#), and [FileChangeTSLossy.cs](#).

10.171.3.21 SetPixelFormat()

```
void gdcm::JPEGCodec::SetPixelFormat (
    PixelFormat const & pf) [override], [virtual]
```

Reimplemented from [gdcm::ImageCodec](#).

Examples

[GetJPEGSamplePrecision.cxx](#).

10.171.3.22 SetQuality()

```
void gdcm::JPEGCodec::SetQuality (
    double q)
```

Examples

[CompressLossyJPEG.cs](#), and [FileChangeTSLossy.cs](#).

10.171.3.23 StartEncode()

```
bool gdcm::JPEGCodec::StartEncode (
    std::ostream & ) [override], [protected], [virtual]
```

Reimplemented from [gdcm::ImageCodec](#).

10.171.3.24 StopEncode()

```
bool gdcm::JPEGCodec::StopEncode (
    std::ostream & ) [override], [protected], [virtual]
```

Reimplemented from [gdcm::ImageCodec](#).

10.171.4 Friends And Related Symbol Documentation

10.171.4.1 ImageRegionReader

```
friend class ImageRegionReader [friend]
```

References [ImageRegionReader](#).

Referenced by [ImageRegionReader](#).

10.171.5 Member Data Documentation

10.171.5.1 BitSample

```
int gdcm::JPEGCodec::BitSample [protected]
```

10.171.5.2 Quality

```
int gdcm::JPEGCodec::Quality [protected]
```

The documentation for this class was generated from the following file:


- [gdcmJPEGCodec.h](#)

10.172 gdcm::JPEGLSCodec Class Reference


JPEG-LS.

```
#include <gdcmJPEGLSCodec.h>
```

Inheritance diagram for gdcm::JPEGLSCodec:



Collaboration diagram for `gdcm::JPEGLSCodec`:



Public Member Functions

- [JPEGLSCodec](#) ()
- [~JPEGLSCodec](#) () override
- bool [CanCode](#) ([TransferSyntax](#) const &ts) const override
Return whether this coder support this transfer syntax (can code it)
- bool [CanDecode](#) ([TransferSyntax](#) const &ts) const override
Return whether this decoder support this transfer syntax (can decode it)
- [ImageCodec](#) * [Clone](#) () const override
- bool [Code](#) ([DataElement](#) const &in, [DataElement](#) &out) override
Code.
- bool [Decode](#) ([DataElement](#) const &in, char *outBuffer, size_t inBufferLength, uint32_t inXMin, uint32_t inXMax, uint32_t inYMin, uint32_t inYMax, uint32_t inZMin, uint32_t inZMax)
- bool [Decode](#) ([DataElement](#) const &is, [DataElement](#) &os) override
Decode.
- unsigned long [GetBufferLength](#) () const
- bool [GetHeaderInfo](#) (std::istream &is, [TransferSyntax](#) &ts) override
- bool [GetLossless](#) () const
- void [SetBufferLength](#) (unsigned long l)
- void [SetLossless](#) (bool l)
- void [SetLossyError](#) (int error)
[0-3] generally

Public Member Functions inherited from [gdcm::ImageCodec](#)

- [ImageCodec](#) ()
- [~ImageCodec](#) () override
- bool [CleanupUnusedBits](#) (char *data, size_t datalen)
- const unsigned int * [GetDimensions](#) () const
- bool [GetLossyFlag](#) () const
- const [LookupTable](#) & [GetLUT](#) () const
- bool [GetNeedByteSwap](#) () const
- unsigned int [GetNumberOfDimensions](#) () const
- const [PhotometricInterpretation](#) & [GetPhotometricInterpretation](#) () const
- [PixelFormat](#) & [GetPixelFormat](#) ()
- const [PixelFormat](#) & [GetPixelFormat](#) () const

- unsigned int [GetPlanarConfiguration](#) () const
- bool [IsLossy](#) () const
- void [SetDimensions](#) (const std::vector< unsigned int > &d)
- void [SetDimensions](#) (const unsigned int d[3])
- void [SetLossyFlag](#) (bool l)
- void [SetLUT](#) ([LookupTable](#) const &lut)
- void [SetNeedByteSwap](#) (bool b)
- void [SetNeedOverlayCleanup](#) (bool b)
- void [SetNumberOfDimensions](#) (unsigned int dim)
- void [SetPhotometricInterpretation](#) ([PhotometricInterpretation](#) const &pi)
- virtual void [SetPixelFormat](#) ([PixelFormat](#) const &pf)
- void [SetPlanarConfiguration](#) (unsigned int pc)

Public Member Functions inherited from [gdcm::Coder](#)

- virtual [~Coder](#) ()=default

Public Member Functions inherited from [gdcm::Decoder](#)

- virtual [~Decoder](#) ()=default

Protected Member Functions

- bool [AppendFrameEncode](#) (std::ostream &out, const char *data, size_t datalen) override
- bool [AppendRowEncode](#) (std::ostream &out, const char *data, size_t datalen) override
- bool [DecodeExtent](#) (char *buffer, unsigned int xmin, unsigned int xmax, unsigned int ymin, unsigned int ymax, unsigned int zmin, unsigned int zmax, std::istream &is)
- bool [IsFrameEncoder](#) () override
- bool [IsRowEncoder](#) () override
- bool [StartEncode](#) (std::ostream &) override
- bool [StopEncode](#) (std::ostream &) override

Protected Member Functions inherited from [gdcm::ImageCodec](#)

- bool [DecodeByStreams](#) (std::istream &is_, std::ostream &os) override
- bool [DoByteSwap](#) (std::istream &is_, std::ostream &os)
- bool [DoInvertMonochrome](#) (std::istream &is_, std::ostream &os)
- bool [DoOverlayCleanup](#) (std::istream &is_, std::ostream &os)
- bool [DoPaddedCompositePixelCode](#) (std::istream &is_, std::ostream &os)
- bool [DoPlanarConfiguration](#) (std::istream &is_, std::ostream &os)
- bool [DoSimpleCopy](#) (std::istream &is_, std::ostream &os)
- bool [DoYBR](#) (std::istream &is_, std::ostream &os)
- bool [DoYBRFull422](#) (std::istream &is_, std::ostream &os)
- virtual bool [IsValid](#) ([PhotometricInterpretation](#) const &pi)

Protected Member Functions inherited from [gdcm::Coder](#)

- virtual bool [InternalCode](#) (const char *bv, unsigned long len, std::ostream &os)

Friends

- class [ImageRegionReader](#)

Additional Inherited Members

Protected Types inherited from [gdcm::ImageCodec](#)

- typedef [SmartPointer](#)< [LookupTable](#) > LUTPtr

Protected Attributes inherited from [gdcm::ImageCodec](#)

- unsigned int [Dimensions](#) [3]
- bool [LossyFlag](#)
- [LUTPtr](#) LUT
- bool [NeedByteSwap](#)
- bool [NeedOverlayCleanup](#)
- unsigned int [NumberOfDimensions](#)
- [PixelFormat](#) PF
- [PhotometricInterpretation](#) PI
- unsigned int [PlanarConfiguration](#)
- bool [RequestPaddedCompositePixelCode](#)
- bool [RequestPlanarConfiguration](#)

10.172.1 Detailed Description

JPEG-LS.

Note

codec that implement the JPEG-LS compression this is an implementation of [ImageCodec](#) for JPEG-LS

It uses the CharLS JPEG-LS implementation <https://github.com/team-charls/charls>

10.172.2 Constructor & Destructor Documentation

10.172.2.1 JPEGLSCodec()

```
gdcm::JPEGLSCodec::JPEGLSCodec ()
```


10.172.2.2 ~JPEGLSCodec()

```
gdcm::JPEGLSCodec::~~JPEGLSCodec () [override]
```

10.172.3 Member Function Documentation

10.172.3.1 AppendFrameEncode()

```
bool gdcm::JPEGLSCodec::AppendFrameEncode (
    std::ostream & out,
    const char * data,
    size_t datalen) [override], [protected], [virtual]
```

Reimplemented from [gdcm::ImageCodec](#).

10.172.3.2 AppendRowEncode()

```
bool gdcm::JPEGLSCodec::AppendRowEncode (
    std::ostream & out,
    const char * data,
    size_t datalen) [override], [protected], [virtual]
```

Reimplemented from [gdcm::ImageCodec](#).

10.172.3.3 CanCode()

```
bool gdcm::JPEGLSCodec::CanCode (
    TransferSyntax const & ) const [override], [virtual]
```

Return whether this coder support this transfer syntax (can code it)

Reimplemented from [gdcm::ImageCodec](#).

10.172.3.4 CanDecode()

```
bool gdcm::JPEGLSCodec::CanDecode (
    TransferSyntax const & ) const [override], [virtual]
```

Return whether this decoder support this transfer syntax (can decode it)

Reimplemented from [gdcm::ImageCodec](#).

10.172.3.5 Clone()

```
ImageCodec * gdcm::JPEGLSCodec::Clone () const [override], [virtual]
```

Implements [gdcm::ImageCodec](#).

References [gdcm::ImageCodec::ImageCodec\(\)](#).

10.172.3.6 Code()

```
bool gdcm::JPEGLSCodec::Code (
    DataElement const & in_,
    DataElement & out_) [override], [virtual]
```

Code.

Reimplemented from [gdcm::Coder](#).

10.172.3.7 Decode() [1/2]

```
bool gdcm::JPEGLSCodec::Decode (
    DataElement const & in,
    char * outBuffer,
    size_t inBufferLength,
    uint32_t inXMin,
    uint32_t inXMax,
    uint32_t inYMin,
    uint32_t inYMax,
    uint32_t inZMin,
    uint32_t inZMax)
```

10.172.3.8 Decode() [2/2]

```
bool gdcm::JPEGLSCodec::Decode (
    DataElement const & ,
    DataElement & ) [override], [virtual]
```

Decode.

Reimplemented from [gdcm::ImageCodec](#).

10.172.3.9 DecodeExtent()

```
bool gdcm::JPEGLSCodec::DecodeExtent (
    char * buffer,
    unsigned int xmin,
    unsigned int xmax,
    unsigned int ymin,
    unsigned int ymax,
    unsigned int zmin,
    unsigned int zmax,
    std::istream & is) [protected]
```

10.172.3.10 GetBufferLength()

```
unsigned long gdcm::JPEGLSCodec::GetBufferLength () const [inline]
```

10.172.3.11 GetHeaderInfo()

```
bool gdcm::JPEGLSCodec::GetHeaderInfo (
    std::istream & is,
    TransferSyntax & ts) [override], [virtual]
```

Reimplemented from [gdcm::ImageCodec](#).

10.172.3.12 GetLossless()

```
bool gdcm::JPEGLSCodec::GetLossless () const
```

10.172.3.13 IsFrameEncoder()

```
bool gdcm::JPEGLSCodec::IsFrameEncoder () [override], [protected], [virtual]
```

Reimplemented from [gdcm::ImageCodec](#).

10.172.3.14 IsRowEncoder()

```
bool gdcm::JPEGLSCodec::IsRowEncoder () [override], [protected], [virtual]
```

Reimplemented from [gdcm::ImageCodec](#).

10.172.3.15 SetBufferLength()

```
void gdcm::JPEGLSCodec::SetBufferLength (
    unsigned long l) [inline]
```

10.172.3.16 SetLossless()

```
void gdcm::JPEGLSCodec::SetLossless (
    bool l)
```

10.172.3.17 SetLossyError()

```
void gdcm::JPEGLSCodec::SetLossyError (
    int error)
```

[0-3] generally

10.172.3.18 StartEncode()

```
bool gdcm::JPEGLSCodec::StartEncode (
    std::ostream & ) [override], [protected], [virtual]
```

Reimplemented from [gdcm::ImageCodec](#).

10.172.3.19 StopEncode()

```
bool gdcm::JPEGLSCodec::StopEncode (
    std::ostream & ) [override], [protected], [virtual]
```

Reimplemented from [gdcm::ImageCodec](#).

10.172.4 Friends And Related Symbol Documentation

10.172.4.1 ImageRegionReader

```
friend class ImageRegionReader [friend]
```

References [ImageRegionReader](#).

Referenced by [ImageRegionReader](#).

The documentation for this class was generated from the following file:

- [gdcmJPEGLSCodec.h](#)

10.173 gdcm::JSON Class Reference

```
#include <gdcmJSON.h>
```

Public Member Functions

- [JSON](#) ()
- [~JSON](#) ()
- bool [Code](#) ([DataSet](#) const &in, std::ostream &os)
- bool [Decode](#) (std::istream &is, [DataSet](#) &out)
- bool [GetPrettyPrint](#) () const
- void [PrettyPrintOff](#) ()
- void [PrettyPrintOn](#) ()
- void [SetPrettyPrint](#) (bool onoff)

10.173.1 Detailed Description

Examples

[QIDO-RS.cxx](#).

10.173.2 Constructor & Destructor Documentation

10.173.2.1 JSON()

```
gdcm::JSON::JSON ()
```

10.173.2.2 ~JSON()

```
gdcm::JSON::~~JSON ()
```

10.173.3 Member Function Documentation

10.173.3.1 Code()

```
bool gdcm::JSON::Code (
    DataSet const & in,
    std::ostream & os)
```

Examples

[QIDO-RS.cxx](#).

10.173.3.2 Decode()

```
bool gdcm::JSON::Decode (
    std::istream & is,
    DataSet & out)
```

Examples

[QIDO-RS.cxx](#).

10.173.3.3 GetPrettyPrint()

```
bool gdcm::JSON::GetPrettyPrint () const
```

10.173.3.4 PrettyPrintOff()

```
void gdcm::JSON::PrettyPrintOff ()
```

10.173.3.5 PrettyPrintOn()

```
void gdcm::JSON::PrettyPrintOn ()
```

Examples

[QIDO-RS.cxx](#).

10.173.3.6 SetPrettyPrint()

```
void gdcm::JSON::SetPrettyPrint (
    bool onoff)
```

The documentation for this class was generated from the following file:


- [gdcmJSON.h](#)

10.174 gdcm::KAKADUCodec Class Reference


[KAKADUCodec](#).

```
#include <gdcmKAKADUCodec.h>
```

Inheritance diagram for gdcm::KAKADUCodec:



Collaboration diagram for gdcm::KAKADUCodec:



Public Member Functions

- `KAKADUCodec` ()
- `~KAKADUCodec` () override
- `bool CanCode (TransferSyntax const &ts) const` override
Return whether this coder support this transfer syntax (can code it)
- `bool CanDecode (TransferSyntax const &ts) const` override
Return whether this decoder support this transfer syntax (can decode it)
- `ImageCodec * Clone` () const override
- `bool Code (DataElement const &in, DataElement &out) override`
Code.
- `bool Decode (DataElement const &is, DataElement &os) override`
Decode.

Public Member Functions inherited from `gdcm::ImageCodec`

- `ImageCodec` ()
- `~ImageCodec` () override
- `bool CleanupUnusedBits (char *data, size_t datalen)`
- `const unsigned int * GetDimensions` () const
- `virtual bool GetHeaderInfo (std::istream &is_, TransferSyntax &ts)`
- `bool GetLossyFlag` () const
- `const LookupTable & GetLUT` () const
- `bool GetNeedByteSwap` () const
- `unsigned int GetNumberOfDimensions` () const
- `const PhotometricInterpretation & GetPhotometricInterpretation` () const
- `PixelFormat & GetPixelFormat` ()
- `const PixelFormat & GetPixelFormat` () const
- `unsigned int GetPlanarConfiguration` () const
- `bool IsLossy` () const
- `void SetDimensions (const std::vector< unsigned int > &d)`
- `void SetDimensions (const unsigned int d[3])`
- `void SetLossyFlag (bool l)`
- `void SetLUT (LookupTable const &lut)`
- `void SetNeedByteSwap (bool b)`
- `void SetNeedOverlayCleanup (bool b)`
- `void SetNumberOfDimensions (unsigned int dim)`
- `void SetPhotometricInterpretation (PhotometricInterpretation const &pi)`
- `virtual void SetPixelFormat (PixelFormat const &pf)`
- `void SetPlanarConfiguration (unsigned int pc)`

Public Member Functions inherited from [gdcm::Coder](#)

- virtual [~Coder](#) ()=default

Public Member Functions inherited from [gdcm::Decoder](#)

- virtual [~Decoder](#) ()=default

Additional Inherited Members

Protected Types inherited from [gdcm::ImageCodec](#)

- typedef [SmartPointer](#)< [LookupTable](#) > LUTPtr

Protected Member Functions inherited from [gdcm::ImageCodec](#)

- virtual bool [AppendFrameEncode](#) (std::ostream &out, const char *data, size_t datalen)
- virtual bool [AppendRowEncode](#) (std::ostream &out, const char *data, size_t datalen)
- bool [DecodeByStreams](#) (std::istream &is_, std::ostream &os) override
- bool [DoByteSwap](#) (std::istream &is_, std::ostream &os)
- bool [DoInvertMonochrome](#) (std::istream &is_, std::ostream &os)
- bool [DoOverlayCleanup](#) (std::istream &is_, std::ostream &os)
- bool [DoPaddedCompositePixelCode](#) (std::istream &is_, std::ostream &os)
- bool [DoPlanarConfiguration](#) (std::istream &is_, std::ostream &os)
- bool [DoSimpleCopy](#) (std::istream &is_, std::ostream &os)
- bool [DoYBR](#) (std::istream &is_, std::ostream &os)
- bool [DoYBRFull422](#) (std::istream &is_, std::ostream &os)
- virtual bool [IsFrameEncoder](#) ()
- virtual bool [IsRowEncoder](#) ()
- virtual bool [IsValid](#) ([PhotometricInterpretation](#) const &pi)
- virtual bool [StartEncode](#) (std::ostream &os)
- virtual bool [StopEncode](#) (std::ostream &os)

Protected Member Functions inherited from [gdcm::Coder](#)

- virtual bool [InternalCode](#) (const char *bv, unsigned long len, std::ostream &os)

Protected Attributes inherited from [gdcm::ImageCodec](#)

- unsigned int [Dimensions](#) [3]
- bool [LossyFlag](#)
- [LUTPtr](#) LUT
- bool [NeedByteSwap](#)
- bool [NeedOverlayCleanup](#)
- unsigned int [NumberOfDimensions](#)
- [PixelFormat](#) PF
- [PhotometricInterpretation](#) PI
- unsigned int [PlanarConfiguration](#)
- bool [RequestPaddedCompositePixelCode](#)
- bool [RequestPlanarConfiguration](#)

10.174.1 Detailed Description

[KAKADUCodec](#).

10.174.2 Constructor & Destructor Documentation

10.174.2.1 KAKADUCodec()

```
gdcm::KAKADUCodec::KAKADUCodec ()
```

10.174.2.2 ~KAKADUCodec()

```
gdcm::KAKADUCodec::~~KAKADUCodec () [override]
```

10.174.3 Member Function Documentation

10.174.3.1 CanCode()

```
bool gdcm::KAKADUCodec::CanCode (
    TransferSyntax const & ) const [override], [virtual]
```

Return whether this coder support this transfer syntax (can code it)

Reimplemented from [gdcm::ImageCodec](#).

10.174.3.2 CanDecode()

```
bool gdcm::KAKADUCodec::CanDecode (
    TransferSyntax const & ) const [override], [virtual]
```

Return whether this decoder support this transfer syntax (can decode it)

Reimplemented from [gdcm::ImageCodec](#).

10.174.3.3 Clone()

```
ImageCodec * gdcm::KAKADUCodec::Clone () const [override], [virtual]
```

Implements [gdcm::ImageCodec](#).

References [gdcm::ImageCodec::ImageCodec\(\)](#).

10.174.3.4 Code()

```
bool gdcm::KAKADUCodec::Code (
    DataElement const & in_,
    DataElement & out_) [override], [virtual]
```

Code.

Reimplemented from [gdcm::Coder](#).

10.174.3.5 Decode()

```
bool gdcm::KAKADUCodec::Decode (
    DataElement const & ,
    DataElement & ) [override], [virtual]
```

Decode.

Reimplemented from [gdcm::ImageCodec](#).

The documentation for this class was generated from the following file:


- [gdcmKAKADUCodec.h](#)

10.175 gdcm::LO Class Reference


[LO](#).

```
#include <gdcmLO.h>
```

Inheritance diagram for gdcm::LO:



Collaboration diagram for gdcm::LO:



Public Types

- typedef [Superclass::const_iterator](#) `const_iterator`
- typedef [Superclass::const_reference](#) `const_reference`
- typedef [Superclass::const_reverse_iterator](#) `const_reverse_iterator`
- typedef [Superclass::difference_type](#) `difference_type`
- typedef [Superclass::iterator](#) `iterator`
- typedef [Superclass::pointer](#) `pointer`
- typedef [Superclass::reference](#) `reference`
- typedef [Superclass::reverse_iterator](#) `reverse_iterator`
- typedef [Superclass::size_type](#) `size_type`
- typedef [String<'\\', 64 >](#) `Superclass`
- typedef [Superclass::value_type](#) `value_type`

Public Member Functions

- [LO](#) ()
- [LO](#) (const [Superclass](#) &s, [size_type](#) pos=0, [size_type](#) n=npos)
- [LO](#) (const [value_type](#) *s)
- [LO](#) (const [value_type](#) *s, [size_type](#) n)
- bool [IsValid](#) () const

10.175.1 Detailed Description

[LO](#).

Note

TODO

10.175.2 Member Typedef Documentation

10.175.2.1 `const_iterator`

```
typedef Superclass::const_iterator gdc::LO::const_iterator
```

10.175.2.2 `const_reference`

```
typedef Superclass::const_reference gdc::LO::const_reference
```

10.175.2.3 `const_reverse_iterator`

```
typedef Superclass::const_reverse_iterator gdc::LO::const_reverse_iterator
```

10.175.2.4 `difference_type`

```
typedef Superclass::difference_type gdc::LO::difference_type
```

10.175.2.5 `iterator`

```
typedef Superclass::iterator gdc::LO::iterator
```

10.175.2.6 `pointer`

```
typedef Superclass::pointer gdc::LO::pointer
```

10.175.2.7 `reference`

```
typedef Superclass::reference gdc::LO::reference
```

10.175.2.8 `reverse_iterator`

```
typedef Superclass::reverse_iterator gdc::LO::reverse_iterator
```

10.175.2.9 `size_type`

```
typedef Superclass::size_type gdc::LO::size_type
```

10.175.2.10 Superclass

```
typedef String<'\\', 64> gdcmm::LO::Superclass
```

10.175.2.11 value_type

```
typedef Superclass::value\_type gdcmm::LO::value\_type
```

10.175.3 Constructor & Destructor Documentation

10.175.3.1 LO() [1/4]

```
gdcmm::LO::LO () [inline]
```

10.175.3.2 LO() [2/4]

```
gdcmm::LO::LO (  
    const value\_type * s) [inline]
```

10.175.3.3 LO() [3/4]

```
gdcmm::LO::LO (  
    const value\_type * s,  
    size\_type n) [inline]
```

10.175.3.4 LO() [4/4]

```
gdcmm::LO::LO (  
    const Superclass & s,  
    size\_type pos = 0,  
    size\_type n = npos) [inline]
```

10.175.4 Member Function Documentation

10.175.4.1 IsValid()

```
bool gdcmm::LO::IsValid () const [inline]
```

References [gdcmm::String](#)<'\\', 64 >::IsValid().

The documentation for this class was generated from the following file:


- [gdcmmLO.h](#)

10.176 gdcm::LookupTable Class Reference


[LookupTable](#) class.

```
#include <gdcmLookupTable.h>
```

Inheritance diagram for gdcm::LookupTable:



Collaboration diagram for gdcm::LookupTable:



Public Types

- enum [LookupTableType](#) {
 [RED](#) = 0 ,
 [GREEN](#) ,
 [BLUE](#) ,
 [GRAY](#) ,
 [UNKNOWN](#) }

Public Member Functions

- [LookupTable](#) ()
- [LookupTable](#) ([LookupTable](#) const &lut)
- [~LookupTable](#) () override
- void [Allocate](#) (unsigned short bitsample=8)
Allocate the LUT.
- void [Clear](#) ()
Clear the LUT.
- bool [Decode](#) (char *outputbuffer, size_t outlen, const char *inputbuffer, size_t inlen) const
- void [Decode](#) (std::istream &is, std::ostream &os) const
Decode the LUT.
- bool [Decode8](#) (char *outputbuffer, size_t outlen, const char *inputbuffer, size_t inlen) const
Decode into RGB 8 bits space.
- unsigned short [GetBitSample](#) () const
return the bit sample
- bool [GetBufferAsRGBA](#) (unsigned char *rgba) const
return the LUT as RGBA buffer
- void [GetLUT](#) ([LookupTableType](#) type, unsigned char *array, unsigned int &length) const
- void [GetLUTDescriptor](#) ([LookupTableType](#) type, unsigned short &length, unsigned short &subscript, unsigned short &bitsize) const
- unsigned int [GetLUTLength](#) ([LookupTableType](#) type) const
- const unsigned char * [GetPointer](#) () const
return a raw pointer to the LUT
- void [InitializeBlueLUT](#) (unsigned short length, unsigned short subscript, unsigned short bitsize)
- bool [Initialized](#) () const
return whether the LUT has been initialized
- void [InitializeGreenLUT](#) (unsigned short length, unsigned short subscript, unsigned short bitsize)
- void [InitializeLUT](#) ([LookupTableType](#) type, unsigned short length, unsigned short subscript, unsigned short bitsize)
Generic interface:
- void [InitializeRedLUT](#) (unsigned short length, unsigned short subscript, unsigned short bitsize)
RED / GREEN / BLUE specific:
- bool [IsRGB8](#) () const
Return whether 16 bits LUT is in RGB 8 bits space.
- void [Print](#) (std::ostream &) const override
- void [SetBlueLUT](#) (const unsigned char *blue, unsigned int length)
- void [SetGreenLUT](#) (const unsigned char *green, unsigned int length)
- virtual void [SetLUT](#) ([LookupTableType](#) type, const unsigned char *array, unsigned int length)
- void [SetRedLUT](#) (const unsigned char *red, unsigned int length)
- bool [WriteBufferAsRGBA](#) (const unsigned char *rgba)
Write the LUT as RGBA.

Public Member Functions inherited from [gdcm::Object](#)

- [Object](#) ()
- [Object](#) (const [Object](#) &)
Special requirement for copy/cstor, assignment operator.
- virtual [~Object](#) ()
- void [operator=](#) (const [Object](#) &)

Protected Attributes

- unsigned short [BitSample](#)
- bool [IncompleteLUT](#):1
- LookupTableInternal * [Internal](#)

Additional Inherited Members**Protected Member Functions inherited from [gdcm::Object](#)**

- void [Register](#) ()
- void [UnRegister](#) ()

10.176.1 Detailed Description

[LookupTable](#) class.

Examples

[ExtractImageRegionWithLUT.cs](#), and [PrintLUT.cxx](#).

10.176.2 Member Enumeration Documentation**10.176.2.1 LookupTableType**

```
enum gdcm::LookupTable::LookupTableType
```

Enumerator

RED	
GREEN	
BLUE	
GRAY	
UNKNOWN	

10.176.3 Constructor & Destructor Documentation**10.176.3.1 [LookupTable](#)() [1/2]**

```
gdcm::LookupTable::LookupTable ()
```

Referenced by [LookupTable\(\)](#).

10.176.3.2 ~LookupTable()

```
gdcm::LookupTable::~~LookupTable () [override]
```

10.176.3.3 LookupTable() [2/2]

```
gdcm::LookupTable::LookupTable (  
    LookupTable const & lut) [inline]
```

References [LookupTable\(\)](#), [gdcm::Object::Object\(\)](#), [BitSample](#), [gdcm_assert](#), [IncompleteLUT](#), and [Internal](#).

10.176.4 Member Function Documentation

10.176.4.1 Allocate()

```
void gdcm::LookupTable::Allocate (  
    unsigned short bitsample = 8)
```

Allocate the LUT.

10.176.4.2 Clear()

```
void gdcm::LookupTable::Clear ()
```

Clear the LUT.

10.176.4.3 Decode() [1/2]

```
bool gdcm::LookupTable::Decode (  
    char * outputbuffer,  
    size_t outlen,  
    const char * inputbuffer,  
    size_t inlen) const
```

Decode the LUT outputbuffer will contains the RGB decoded PALETTE COLOR input image of size inlen the outputbuffer should be at least 3 times the size of inlen

10.176.4.4 Decode() [2/2]

```
void gdcm::LookupTable::Decode (  
    std::istream & is,  
    std::ostream & os) const
```

Decode the LUT.

Examples

[ExtractImageRegionWithLUT.cs](#).

10.176.4.5 Decode8()

```
bool gdc::LookupTable::Decode8 (
    char * outputbuffer,
    size_t outlen,
    const char * inputbuffer,
    size_t inlen) const
```

Decode into RGB 8 bits space.

10.176.4.6 GetBitSample()

```
unsigned short gdc::LookupTable::GetBitSample () const [inline]
```

return the bit sample

References [BitSample](#).

10.176.4.7 GetBufferAsRGBA()

```
bool gdc::LookupTable::GetBufferAsRGBA (
    unsigned char * rgba) const
```

return the LUT as RGBA buffer

10.176.4.8 GetLUT()

```
void gdc::LookupTable::GetLUT (
    LookupTableType type,
    unsigned char * array,
    unsigned int & length) const
```

10.176.4.9 GetLUTDescriptor()

```
void gdc::LookupTable::GetLUTDescriptor (
    LookupTableType type,
    unsigned short & length,
    unsigned short & subscript,
    unsigned short & bitsize) const
```

10.176.4.10 GetLUTLength()

```
unsigned int gdc::LookupTable::GetLUTLength (
    LookupTableType type) const
```

10.176.4.11 GetPointer()

```
const unsigned char * gdcm::LookupTable::GetPointer () const
```

return a raw pointer to the LUT

10.176.4.12 InitializeBlueLUT()

```
void gdcm::LookupTable::InitializeBlueLUT (
    unsigned short length,
    unsigned short subscript,
    unsigned short bitsize)
```

10.176.4.13 Initialized()

```
bool gdcm::LookupTable::Initialized () const
```

return whether the LUT has been initialized

10.176.4.14 InitializeGreenLUT()

```
void gdcm::LookupTable::InitializeGreenLUT (
    unsigned short length,
    unsigned short subscript,
    unsigned short bitsize)
```

10.176.4.15 InitializeLUT()

```
void gdcm::LookupTable::InitializeLUT (
    LookupTableType type,
    unsigned short length,
    unsigned short subscript,
    unsigned short bitsize)
```

Generic interface:

10.176.4.16 InitializeRedLUT()

```
void gdcm::LookupTable::InitializeRedLUT (
    unsigned short length,
    unsigned short subscript,
    unsigned short bitsize)
```

RED / GREEN / BLUE specific:

10.176.4.17 IsRGB8()

```
bool gdcm::LookupTable::IsRGB8 () const
```

Return whether 16 bits LUT is in RGB 8 bits space.

10.176.4.18 Print()

```
void gdcm::LookupTable::Print (
    std::ostream & ) const [override], [virtual]
```

Reimplemented from [gdcm::Object](#).

Reimplemented in [gdcm::SegmentedPaletteColorLookupTable](#).

Examples

[PrintLUT.cxx](#).

10.176.4.19 SetBlueLUT()

```
void gdcm::LookupTable::SetBlueLUT (
    const unsigned char * blue,
    unsigned int length)
```

10.176.4.20 SetGreenLUT()

```
void gdcm::LookupTable::SetGreenLUT (
    const unsigned char * green,
    unsigned int length)
```

10.176.4.21 SetLUT()

```
virtual void gdcm::LookupTable::SetLUT (
    LookupTableType type,
    const unsigned char * array,
    unsigned int length) [virtual]
```

Reimplemented in [gdcm::SegmentedPaletteColorLookupTable](#).

10.176.4.22 SetRedLUT()

```
void gdcm::LookupTable::SetRedLUT (
    const unsigned char * red,
    unsigned int length)
```

10.176.4.23 WriteBufferAsRGBA()

```
bool gdcm::LookupTable::WriteBufferAsRGBA (
    const unsigned char * rgba)
```

Write the LUT as RGBA.

10.176.5 Member Data Documentation

10.176.5.1 BitSample

```
unsigned short gdcm::LookupTable::BitSample [protected]
```

Referenced by [LookupTable\(\)](#), and [GetBitSample\(\)](#).

10.176.5.2 IncompleteLUT

```
bool gdcm::LookupTable::IncompleteLUT [protected]
```

Referenced by [LookupTable\(\)](#).

10.176.5.3 Internal

```
LookupTableInternal* gdcm::LookupTable::Internal [protected]
```

Referenced by [LookupTable\(\)](#).

The documentation for this class was generated from the following file:

- [gdcmLookupTable.h](#)

10.177 gdcm::Scanner2::Itstr Struct Reference

```
#include <gdcmScanner2.h>
```

Public Member Functions

- bool [operator\(\)](#) (const char *s1, const char *s2) const

10.177.1 Member Function Documentation

10.177.1.1 operator>()

```
bool gdcM::Scanner2::ltstr::operator() (
    const char * s1,
    const char * s2) const [inline]
```

References [gdcM_assert](#).

The documentation for this struct was generated from the following file:

- [gdcMScanner2.h](#)

10.178 gdcM::Scanner::ltstr Struct Reference

```
#include <gdcMScanner.h>
```

Public Member Functions

- bool [operator\(\)](#) (const char *s1, const char *s2) const

10.178.1 Member Function Documentation

10.178.1.1 operator>()

```
bool gdcM::Scanner::ltstr::operator() (
    const char * s1,
    const char * s2) const [inline]
```

References [gdcM_assert](#).

The documentation for this struct was generated from the following file:

- [gdcMScanner.h](#)

10.179 gdcM::StrictScanner2::ltstr Struct Reference

```
#include <gdcMStrictScanner2.h>
```

Public Member Functions

- bool [operator\(\)](#) (const char *s1, const char *s2) const

10.179.1 Member Function Documentation

10.179.1.1 operator>()

```
bool gdcm::StrictScanner2::ltstr::operator() (
    const char * s1,
    const char * s2) const [inline]
```

References [gdcm_assert](#).

The documentation for this struct was generated from the following file:

- [gdcmStrictScanner2.h](#)

10.180 gdcm::StrictScanner::ltstr Struct Reference

```
#include <gdcmStrictScanner.h>
```

Public Member Functions

- bool [operator\(\)](#) (const char *s1, const char *s2) const

10.180.1 Member Function Documentation

10.180.1.1 operator>()

```
bool gdcm::StrictScanner::ltstr::operator() (
    const char * s1,
    const char * s2) const [inline]
```

References [gdcm_assert](#).

The documentation for this struct was generated from the following file:

- [gdcmStrictScanner.h](#)

10.181 gdcm::Macro Class Reference

Class for representing a [Macro](#).

```
#include <gdcmMacro.h>
```

Public Types

- typedef std::vector< std::string > [ArrayIncludeMacrosType](#)
- typedef std::map< [Tag](#), [MacroEntry](#) > [MapModuleEntry](#)

Public Member Functions

- [Macro](#) ()=default
- void [AddMacroEntry](#) (const [Tag](#) &tag, const [MacroEntry](#) &module)
Will add a [ModuleEntry](#) directly at root-level. See [Macro](#) for nested-included level.
- void [Clear](#) ()
- bool [FindMacroEntry](#) (const [Tag](#) &tag) const
- const [MacroEntry](#) & [GetMacroEntry](#) (const [Tag](#) &tag) const
- const char * [GetName](#) () const
- void [SetName](#) (const char *name)
- bool [Verify](#) (const [DataSet](#) &ds, [Usage](#) const &usage) const

Friends

- std::ostream & [operator<<](#) (std::ostream &_os, const [Macro](#) &_val)

10.181.1 Detailed Description

Class for representing a [Macro](#).

Note

[Attribute Macro](#): a set of Attributes that are described in a single table that is referenced by multiple [Module](#) or other tables.

See also

[Module](#)

10.181.2 Member Typedef Documentation

10.181.2.1 ArrayIncludeMacrosType

```
typedef std::vector<std::string> gdcm::Macro::ArrayIncludeMacrosType
```


10.181.2.2 MapModuleEntry

```
typedef std::map<Tag, MacroEntry> gdcmmacro::Macro::MapModuleEntry
```

10.181.3 Constructor & Destructor Documentation

10.181.3.1 Macro()

```
gdcmmacro::Macro::Macro () [default]
```

References [Macro\(\)](#), and [operator<<](#).

Referenced by [Macro\(\)](#), and [operator<<](#).

10.181.4 Member Function Documentation

10.181.4.1 AddMacroEntry()

```
void gdcmmacro::Macro::AddMacroEntry (
    const Tag & tag,
    const MacroEntry & module) [inline]
```

Will add a [ModuleEntry](#) directly at root-level. See [Macro](#) for nested-included level.

10.181.4.2 Clear()

```
void gdcmmacro::Macro::Clear () [inline]
```

10.181.4.3 FindMacroEntry()

```
bool gdcmmacro::Macro::FindMacroEntry (
    const Tag & tag) const
```

Find or Get a [ModuleEntry](#). [ModuleEntry](#) are either search are root-level or within nested-macro included in module.

10.181.4.4 GetMacroEntry()

```
const MacroEntry & gdcmmacro::Macro::GetMacroEntry (
    const Tag & tag) const
```

10.181.4.5 GetName()

```
const char * gdcmmacro::Macro::GetName () const [inline]
```

10.181.4.6 SetName()

```
void gdcmmacro::Macro::SetName (
    const char * name) [inline]
```

10.181.4.7 Verify()

```
bool gdcmmacro::Macro::Verify (
    const DataSet & ds,
    Usage const & usage) const
```

10.181.5 Friends And Related Symbol Documentation

10.181.5.1 operator<<

```
std::ostream & operator<< (
    std::ostream & _os,
    const Macro & _val) [friend]
```

References [Macro\(\)](#).

Referenced by [Macro\(\)](#).

The documentation for this class was generated from the following file:

- [gdcmmacro.h](#)

10.182 gdcmmacro::Macros Class Reference

Class for representing a [Modules](#).

```
#include <gdcmmacros.h>
```

Public Types

- typedef std::map< std::string, [Macro](#) > [ModuleMapType](#)

Public Member Functions

- [Macros](#) ()=default
- void [AddMacro](#) (const char *ref, const [Macro](#) &module)
- void [Clear](#) ()
- const [Macro](#) & [GetMacro](#) (const char *name) const
- bool [IsEmpty](#) () const

Friends

- `std::ostream & operator<< (std::ostream &_os, const Macros &_val)`

10.182.1 Detailed Description

Class for representing a [Modules](#).

Note

bla

See also

[Module](#)

Examples

[TraverseModules.cxx](#).

10.182.2 Member Typedef Documentation

10.182.2.1 ModuleMapType

```
typedef std::map<std::string, Macro> gdcm::Macros::ModuleMapType
```

10.182.3 Constructor & Destructor Documentation

10.182.3.1 Macros()

```
gdcm::Macros::Macros () [default]
```

References [Macros\(\)](#), and [operator<<](#).

Referenced by [Macros\(\)](#), and [operator<<](#).

10.182.4 Member Function Documentation

10.182.4.1 AddMacro()

```
void gdcm::Macros::AddMacro (  
    const char * ref,  
    const Macro & module) [inline]
```

References [gdcm_assert](#).

10.182.4.2 Clear()

```
void gdcM::Macros::Clear () [inline]
```

10.182.4.3 GetMacro()

```
const Macro & gdcM::Macros::GetMacro (
    const char * name) const [inline]
```

References [gdcM_assert](#).

10.182.4.4 IsEmpty()

```
bool gdcM::Macros::IsEmpty () const [inline]
```

10.182.5 Friends And Related Symbol Documentation**10.182.5.1 operator<<**

```
std::ostream & operator<< (
    std::ostream & _os,
    const Macros & _val) [friend]
```

References [Macros\(\)](#).

Referenced by [Macros\(\)](#).

The documentation for this class was generated from the following file:

- [gdcMMacros.h](#)

10.183 gdcM::network::MaximumLengthSub Class Reference

[MaximumLengthSub](#).

```
#include <gdcMMaximumLengthSub.h>
```

Public Member Functions

- [MaximumLengthSub](#) ()
- [uint32_t GetMaximumLength](#) () const
- [void Print](#) (std::ostream &os) const
- [std::istream & Read](#) (std::istream &is)
- [void SetMaximumLength](#) (uint32_t maximumlength)
- [size_t Size](#) () const
- [const std::ostream & Write](#) (std::ostream &os) const

10.183.1 Detailed Description

[MaximumLengthSub](#).

Annex D [Table D.1-1](#) MAXIMUM LENGTH SUB-ITEM FIELDS (A-ASSOCIATE-RQ)

or

[Table D.1-2](#) Maximum length sub-item fields (A-ASSOCIATE-AC)

10.183.2 Constructor & Destructor Documentation

10.183.2.1 MaximumLengthSub()

```
gdcmm::network::MaximumLengthSub::MaximumLengthSub ()
```

10.183.3 Member Function Documentation

10.183.3.1 GetMaximumLength()

```
uint32_t gdcmm::network::MaximumLengthSub::GetMaximumLength () const [inline]
```

10.183.3.2 Print()

```
void gdcmm::network::MaximumLengthSub::Print (  
    std::ostream & os) const
```

10.183.3.3 Read()

```
std::istream & gdcmm::network::MaximumLengthSub::Read (  
    std::istream & is)
```

10.183.3.4 SetMaximumLength()

```
void gdcmm::network::MaximumLengthSub::SetMaximumLength (  
    uint32_t maximumlength)
```

10.183.3.5 Size()

```
size_t gdcmm::network::MaximumLengthSub::Size () const
```

10.183.3.6 Write()

```
const std::ostream & gdcmm::network::MaximumLengthSub::Write (
    std::ostream & os) const
```

The documentation for this class was generated from the following file:

- [gdcmmMaximumLengthSub.h](#)

10.184 gdcmm::MD5 Class Reference

Class for [MD5](#).

```
#include <gdcmmMD5.h>
```

Static Public Member Functions

- static bool [Compute](#) (const char *buffer, size_t buf_len, char digest_str[33])
- static bool [ComputeFile](#) (const char *filename, char digest_str[33])
Compute md5 from a file filename

10.184.1 Detailed Description

Class for [MD5](#).

Warning

this class is able to pick from two implementations:

1. a lightweight md5 implementation (when GDCM_BUILD_TESTING is turned ON)
2. the one from OpenSSL (when GDCM_USE_SYSTEM_OPENSSL is turned ON)

In all other cases it will return an error

10.184.2 Member Function Documentation

10.184.2.1 Compute()

```
bool gdcmm::MD5::Compute (
    const char * buffer,
    size_t buf_len,
    char digest_str[33]) [static]
```

10.184.2.2 ComputeFile()

```
bool gdcm::MD5::ComputeFile (
    const char * filename,
    char digest_str[33]) [static]
```

Compute md5 from a file `filename`

The documentation for this class was generated from the following file:

- [gdcmMD5.h](#)

10.185 gdcm::MEC_MR3 Class Reference

Class for [MEC_MR3](#).

```
#include <gdcmMEC_MR3.h>
```

Static Public Member Functions

- static const [PrivateTag](#) & [GetCanonMECMR3Tag](#) ()
- static const [PrivateTag](#) & [GetPMTFInformationDataTag](#) ()
- static const [PrivateTag](#) & [GetToshibaMECMR3Tag](#) ()
- static bool [Print](#) (const char *src, size_t srclen)

10.185.1 Detailed Description

Class for [MEC_MR3](#).

10.185.2 Member Function Documentation

10.185.2.1 GetCanonMECMR3Tag()

```
const PrivateTag & gdcm::MEC_MR3::GetCanonMECMR3Tag () [static]
```

Return the private tag used by CANON to store the [MEC_MR3](#) data This is: [PrivateTag](#)(0x0029,0x90,"CANON_MEC←_MR3");

10.185.2.2 GetPMTFInformationDataTag()

```
const PrivateTag & gdcm::MEC_MR3::GetPMTFInformationDataTag () [static]
```

Return the private tag used by PMTF to store the [MEC_MR3](#) data This is: [PrivateTag](#)(0x0029,0x90,"PMTF INFORMATION DATA");

10.185.2.3 GetToshibaMECMR3Tag()

```
const PrivateTag & gdcmm::MECMR3::GetToshibaMECMR3Tag () [static]
```

Return the private tag used by TOSHIBA to store the MEC_MR3 data This is: PrivateTag(0x0029,0x90,"TOSHIBA_MEC_MR3");

10.185.2.4 Print()

```
bool gdcmm::MECMR3::Print (
    const char * src,
    size_t srclen) [static]
```

The documentation for this class was generated from the following file:

- [gdcmmMECMR3.h](#)

10.186 gdcmm::MediaStorage Class Reference

[MediaStorage](#).

```
#include <gdcmmMediaStorage.h>
```

Public Types

- enum [MSType](#) {
 [MediaStorageDirectoryStorage](#) = 0 ,
 [ComputedRadiographyImageStorage](#) ,
 [DigitalXRayImageStorageForPresentation](#) ,
 [DigitalXRayImageStorageForProcessing](#) ,
 [DigitalMammographyImageStorageForPresentation](#) ,
 [DigitalMammographyImageStorageForProcessing](#) ,
 [DigitalIntraoralXRayImageStorageForPresentation](#) ,
 [DigitalIntraoralXRayImageStorageForProcessing](#) ,
 [CTImageStorage](#) ,
 [EnhancedCTImageStorage](#) ,
 [UltrasoundImageStorageRetired](#) ,
 [UltrasoundImageStorage](#) ,
 [UltrasoundMultiFrameImageStorageRetired](#) ,
 [UltrasoundMultiFrameImageStorage](#) ,
 [MRIImageStorage](#) ,
 [EnhancedMRIImageStorage](#) ,
 [MRSpectroscopyStorage](#) ,
 [NuclearMedicineImageStorageRetired](#) ,
 [SecondaryCaptureImageStorage](#) ,
 [MultiframeSingleBitSecondaryCaptureImageStorage](#) ,
 [MultiframeGrayscaleByteSecondaryCaptureImageStorage](#) ,
 [MultiframeGrayscaleWordSecondaryCaptureImageStorage](#) ,
 }

[MultiframeTrueColorSecondaryCaptureImageStorage](#) ,
[StandaloneOverlayStorage](#) ,
[StandaloneCurveStorage](#) ,
[LeadECGWaveformStorage](#) ,
[GeneralECGWaveformStorage](#) ,
[AmbulatoryECGWaveformStorage](#) ,
[HemodynamicWaveformStorage](#) ,
[CardiacElectrophysiologyWaveformStorage](#) ,
[BasicVoiceAudioWaveformStorage](#) ,
[StandaloneModalityLUTStorage](#) ,
[StandaloneVOILUTStorage](#) ,
[GrayscaleSoftcopyPresentationStateStorageSOPClass](#) ,
[XRayAngiographicImageStorage](#) ,
[XRayRadiofluoroscopicImageStorage](#) ,
[XRayAngiographicBiPlaneImageStorageRetired](#) ,
[NuclearMedicineImageStorage](#) ,
[RawDataStorage](#) ,
[SpacialRegistrationStorage](#) ,
[SpacialFiducialsStorage](#) ,
[PETImageStorage](#) ,
[RTImageStorage](#) ,
[RTDoseStorage](#) ,
[RTStructureSetStorage](#) ,
[RTPlanStorage](#) ,
[CSANonImageStorage](#) ,
[Philips3D](#) ,
[EnhancedSR](#) ,
[BasicTextSR](#) ,
[HardcopyGrayscaleImageStorage](#) ,
[ComprehensiveSR](#) ,
[DetachedStudyManagementSOPClass](#) ,
[EncapsulatedPDFStorage](#) ,
[EncapsulatedCDASStorage](#) ,
[StudyComponentManagementSOPClass](#) ,
[DetachedVisitManagementSOPClass](#) ,
[DetachedPatientManagementSOPClass](#) ,
[VideoEndoscopicImageStorage](#) ,
[GeneralElectricMagneticResonanceImageStorage](#) ,
[GEPrivate3DModelStorage](#) ,
[ToshibaPrivateDataStorage](#) ,
[MammographyCADSR](#) ,
[KeyObjectSelectionDocument](#) ,
[HangingProtocolStorage](#) ,
[ModalityPerformedProcedureStepSOPClass](#) ,
[PhilipsPrivateMRSyntheticImageStorage](#) ,
[VLPhotographicImageStorage](#) ,
[SegmentationStorage](#) ,
[RTIonPlanStorage](#) ,
[XRay3DAngiographicImageStorage](#) ,
[EnhancedXAImageStorage](#) ,
[RTIonBeamsTreatmentRecordStorage](#) ,
[SurfaceSegmentationStorage](#) ,
[VLWholeSlideMicroscopyImageStorage](#) ,
[RTTreatmentSummaryRecordStorage](#) ,

```

    EnhancedUSVolumeStorage ,
    XRayRadiationDoseSR ,
    VLEndoscopicImageStorage ,
    BreastTomosynthesisImageStorage ,
    FujiPrivateCRImageStorage ,
    OphthalmicPhotography8BitImageStorage ,
    OphthalmicTomographyImageStorage ,
    VLMicroscopicImageStorage ,
    EnhancedPETImageStorage ,
    VideoPhotographicImageStorage ,
    XRay3DCraniofacialImageStorage ,
    IVOCTForPresentation ,
    IVOCTForProcessing ,
    LegacyConvertedEnhancedCTImageStorage ,
    LegacyConvertedEnhancedMRIImageStorage ,
    LegacyConvertedEnhancedPETImageStorage ,
    BreastProjectionXRayImageStorageForPresentation ,
    BreastProjectionXRayImageStorageForProcessing ,
    HardcopyColorImageStorage ,
    EnhancedMRColorImageStorage ,
    FujiPrivateMammoCRImageStorage ,
    OphthalmicPhotography16BitImageStorage ,
    VideoMicroscopicImageStorage ,
    MS_END }
• enum ObjectType {
    NoObject = 0 ,
    Video ,
    Waveform ,
    Audio ,
    PDF ,
    URI ,
    Segmentation ,
    ObjectEnd }

```

Public Member Functions

- [MediaStorage](#) (MSType type=MS_END)
- const char * [GetModality](#) () const
- unsigned int [GetModalityDimension](#) () const
- const char * [GetString](#) () const

Return the Media [String](#) of the object.
- void [GuessFromModality](#) (const char *modality, unsigned int dimension=2)
- bool [IsUndefined](#) () const
- operator MSType () const
- bool [SetFromDataSet](#) (DataSet const &ds)
- bool [SetFromFile](#) (File const &file)
- bool [SetFromHeader](#) (FileMetaInformation const &fmi)
- bool [SetFromModality](#) (DataSet const &ds)

Static Public Member Functions

- static const char * [GetMSString](#) (MSType ts)
Return the Media [String](#) associated. Will return NULL for MS_END.
- static MSType [GetMSType](#) (const char *str)
- static unsigned int [GetNumberOfModality](#) ()
- static unsigned int [GetNumberOfMSString](#) ()
- static unsigned int [GetNumberOfMSType](#) ()
- static bool [IsImage](#) (MSType ts)

Protected Member Functions

- void [SetFromSourceImageSequence](#) (DataSet const &ds)

Friends

- std::ostream & [operator<<](#) (std::ostream &os, const [MediaStorage](#) &ms)

10.186.1 Detailed Description

[MediaStorage](#).

Note

FIXME There should not be any notion of [Image](#) and/or PDF at that point Only the codec can answer yes I support this Media Storage or not... For instance an [ImageCodec](#) will answer yes to most of them while a [PDFCodec](#) will answer only for the Encapsulated PDF

See also

[UIDs](#)

Examples

[CreateJPIPDataSet.cxx](#), [EncapsulateFileInRawData.cxx](#), [Extracting_All_Resolution.cxx](#), [Fake_Image_Using_Stream_Image_Writer](#), [GenAllVR.cxx](#), [GenFakeIdentifyFile.cxx](#), [GenerateStandardSOPClasses.cxx](#), [GetSubSequenceData.cxx](#), [MpegVideoInfo.cs](#), [ReadAndDumpDICOMDIR.cxx](#), [ReadAndDumpDICOMDIR2.cxx](#), [StreamImageReaderTest.cxx](#), [TemplateEmptyImage.cxx](#), [TestReader.cxx](#), [gdcmrtionplan.cxx](#), [gdcmrtplan.cxx](#), and [iU22tomultisc.cxx](#).

10.186.2 Member Enumeration Documentation

10.186.2.1 MSType

enum [gdcm::MediaStorage::MSType](#)

Enumerator

MediaStorageDirectoryStorage	
ComputedRadiographyImageStorage	
DigitalXRayImageStorageForPresentation	
DigitalXRayImageStorageForProcessing	
DigitalMammographyImageStorageForPresentation	
DigitalMammographyImageStorageForProcessing	
DigitalIntraoralXrayImageStorageForPresentation	
DigitalIntraoralXRayImageStorageForProcessing	
CTImageStorage	
EnhancedCTImageStorage	
UltrasoundImageStorageRetired	
UltrasoundImageStorage	
UltrasoundMultiFrameImageStorageRetired	
UltrasoundMultiFrameImageStorage	
MRImageStorage	
EnhancedMRImageStorage	
MRSpectroscopyStorage	
NuclearMedicineImageStorageRetired	
SecondaryCaptureImageStorage	
MultiframeSingleBitSecondaryCaptureImageStorage	
MultiframeGrayscaleByteSecondaryCaptureImageStorage	
MultiframeGrayscaleWordSecondaryCaptureImageStorage	
MultiframeTrueColorSecondaryCaptureImageStorage	
StandaloneOverlayStorage	
StandaloneCurveStorage	
LeadECGWaveformStorage	
GeneralECGWaveformStorage	
AmbulatoryECGWaveformStorage	
HemodynamicWaveformStorage	
CardiacElectrophysiologyWaveformStorage	
BasicVoiceAudioWaveformStorage	
StandaloneModalityLUTStorage	
StandaloneVOILUTStorage	
GrayscaleSoftcopyPresentationStateStorageSOPClass	
XRayAngiographicImageStorage	
XRayRadiofluoroscopingImageStorage	
XRayAngiographicBiPlaneImageStorageRetired	
NuclearMedicineImageStorage	
RawDataStorage	
SpacialRegistrationStorage	
SpacialFiducialsStorage	
PETImageStorage	
RTImageStorage	

Enumerator

RTDoseStorage	
RTStructureSetStorage	
RTPlanStorage	
CSANonImageStorage	
Philips3D	
EnhancedSR	
BasicTextSR	
HardcopyGrayscaleImageStorage	
ComprehensiveSR	
DetachedStudyManagementSOPClass	
EncapsulatedPDFStorage	
EncapsulatedCDAStorage	
StudyComponentManagementSOPClass	
DetachedVisitManagementSOPClass	
DetachedPatientManagementSOPClass	
VideoEndoscopicImageStorage	
GeneralElectricMagneticResonanceImageStorage	
GEPrivate3DModelStorage	
ToshibaPrivateDataStorage	
MammographyCADSR	
KeyObjectSelectionDocument	
HangingProtocolStorage	
ModalityPerformedProcedureStepSOPClass	
PhilipsPrivateMRSyntheticImageStorage	
VLPhotographicImageStorage	
SegmentationStorage	
RTIonPlanStorage	
XRay3DAngiographicImageStorage	
EnhancedXAImageStorage	
RTIonBeamsTreatmentRecordStorage	
SurfaceSegmentationStorage	
VLWholeSlideMicroscopyImageStorage	
RTTreatmentSummaryRecordStorage	
EnhancedUSVolumeStorage	
XRayRadiationDoseSR	
VLEndoscopicImageStorage	
BreastTomosynthesisImageStorage	
FujiPrivateCRImageStorage	
OphthalmicPhotography8BitImageStorage	
OphthalmicTomographyImageStorage	
VLMicroscopicImageStorage	
EnhancedPETImageStorage	
VideoPhotographicImageStorage	

Enumerator

XRay3DCraniofacialImageStorage	
IVOCTForPresentation	
IVOCTForProcessing	
LegacyConvertedEnhancedCTImageStorage	
LegacyConvertedEnhancedMRImageStorage	
LegacyConvertedEnhancedPETImageStorage	
BreastProjectionXRayImageStorageForPresentation	
BreastProjectionXRayImageStorageForProcessing	
HardcopyColorImageStorage	
EnhancedMRColorImageStorage	
FujiPrivateMammoCRImageStorage	
OphthalmicPhotography16BitImageStorage	
VideoMicroscopicImageStorage	
MS_END	

Examples

[GenerateStandardSOPClasses.cxx](#), and [MpegVideoInfo.cs](#).

10.186.2.2 ObjectType

```
enum gdcm::MediaStorage::ObjectType
```

Enumerator

NoObject	
Video	
Waveform	
Audio	
PDF	
URI	
Segmentation	
ObjectEnd	

10.186.3 Constructor & Destructor Documentation

10.186.3.1 MediaStorage()

```
gdcm::MediaStorage::MediaStorage (
    MSType type = MS_END) [inline]
```

References [MS_END](#).

Referenced by [GuessFromModality\(\)](#), and [operator<<](#).

10.186.4 Member Function Documentation

10.186.4.1 GetModality()

```
const char * gdcm::MediaStorage::GetModality () const
```

10.186.4.2 GetModalityDimension()

```
unsigned int gdcm::MediaStorage::GetModalityDimension () const
```

10.186.4.3 GetMSString()

```
const char * gdcm::MediaStorage::GetMSString (  
    MStype ts) [static]
```

Return the Media [String](#) associated. Will return NULL for MS_END.

Examples

[GenerateStandardSOPClasses.cxx](#).

Referenced by [operator<<](#).

10.186.4.4 GetMStype()

```
MStype gdcm::MediaStorage::GetMStype (  
    const char * str) [static]
```

Examples

[MetaImageMD5Activiz.cs](#), and [TestReader.cxx](#).

10.186.4.5 GetNumberOfModality()

```
unsigned int gdcm::MediaStorage::GetNumberOfModality () [static]
```

10.186.4.6 GetNumberOfMSString()

```
unsigned int gdcm::MediaStorage::GetNumberOfMSString () [static]
```

10.186.4.7 GetNumberOfMSType()

```
unsigned int gdcm::MediaStorage::GetNumberOfMSType () [static]
```

10.186.4.8 GetString()

```
const char * gdcm::MediaStorage::GetString () const
```

Return the Media [String](#) of the object.

Examples

[CreateJPIPDataSet.cxx](#), [EncapsulateFileInRawData.cxx](#), [Fake_Image_Using_Stream_Image_Writer.cxx](#), [GetSubSequenceData.cxx](#), [MpegVideoInfo.cs](#), [StreamImageReaderTest.cxx](#), [TemplateEmptyImage.cxx](#), and [iU22tomultisc.cxx](#).

10.186.4.9 GuessFromModality()

```
void gdcm::MediaStorage::GuessFromModality (  
    const char * modality,  
    unsigned int dimension = 2)
```

References [MediaStorage\(\)](#), and [operator<<](#).

10.186.4.10 IsImage()

```
bool gdcm::MediaStorage::IsImage (  
    MSType ts) [static]
```

Returns whether DICOM has a Pixel Data element (7fe0,0010)

Warning

MRSpectroscopyStorage could be image but are not

Examples

[MetalImageMD5Activiz.cs](#).

10.186.4.11 IsUndefined()

```
bool gdcm::MediaStorage::IsUndefined () const [inline]
```

Examples

[TestReader.cxx](#).

References [MS_END](#).

10.186.4.12 operator MType()

```
gdcm::MediaStorage::operator MType () const [inline]
```

10.186.4.13 SetFromDataSet()

```
bool gdcm::MediaStorage::SetFromDataSet (  
    DataSet const & ds)
```

Advanced user only (functions should be protected level...) Those function are lower level than SetFromFile

10.186.4.14 SetFromFile()

```
bool gdcm::MediaStorage::SetFromFile (  
    File const & file)
```

Attempt to set the [MediaStorage](#) from a file: WARNING: When no [MediaStorage](#) & Modality are found BUT a PixelData element is found then [MediaStorage](#) is set to the default SecondaryCaptureImageStorage (return value is false in this case)

Examples

[ReadAndDumpDICOMDIR.cxx](#), [ReadAndDumpDICOMDIR2.cxx](#), [TestReader.cxx](#), [gdcmrtionplan.cxx](#), and [gdcmrtplan.cxx](#).

10.186.4.15 SetFromHeader()

```
bool gdcm::MediaStorage::SetFromHeader (  
    FileMetaInformation const & fmi)
```

10.186.4.16 SetFromModality()

```
bool gdcm::MediaStorage::SetFromModality (  
    DataSet const & ds)
```

10.186.4.17 SetFromSourceImageSequence()

```
void gdcm::MediaStorage::SetFromSourceImageSequence (  
    DataSet const & ds) [protected]
```

10.186.5 Friends And Related Symbol Documentation

10.186.5.1 operator<<

```
std::ostream & operator<< (
    std::ostream & os,
    const MediaStorage & ms) [friend]
```

References [MediaStorage\(\)](#), [GetMSString\(\)](#), and [operator<<](#).

Referenced by [GuessFromModality\(\)](#), and [operator<<](#).

The documentation for this class was generated from the following file:


- [gdcmMediaStorage.h](#)

10.187 gdcm::MemberCommand< T > Class Template Reference


[Command](#) subclass that calls a pointer to a member function.

```
#include <gdcmCommand.h>
```

Inheritance diagram for `gdcm::MemberCommand< T >`:



Collaboration diagram for gdcmmembercommand< T >:



Public Types

- typedef `MemberCommand Self`
- typedef void(T::* `TConstMemberFunctionPointer`) (const `Subject` *, const `Event` &)
- typedef void(T::* `TMemberFunctionPointer`) (`Subject` *, const `Event` &)

Public Member Functions

- `MemberCommand` (const `Self` &)=delete
- void `Execute` (const `Subject` *caller, const `Event` &event) override
- void `Execute` (`Subject` *caller, const `Event` &event) override
- void `operator=` (const `Self` &)=delete
- void `SetCallbackFunction` (T *object, `TConstMemberFunctionPointer` memberFunction)
- void `SetCallbackFunction` (T *object, `TMemberFunctionPointer` memberFunction)

Public Member Functions inherited from `gdcmcommand`

- `Command` (const `Command` &)=delete
- void `operator=` (const `Command` &)=delete

Public Member Functions inherited from [gdcm::Subject](#)

- [Subject](#) ()
- [~Subject](#) () override
- unsigned long [AddObserver](#) (const [Event](#) &event, [Command](#) *)
- unsigned long [AddObserver](#) (const [Event](#) &event, [Command](#) *) const
- [Command](#) * [GetCommand](#) (unsigned long tag)
- bool [HasObserver](#) (const [Event](#) &event) const
- void [InvokeEvent](#) (const [Event](#) &)
- void [InvokeEvent](#) (const [Event](#) &) const
- void [RemoveAllObservers](#) ()
- void [RemoveObserver](#) (unsigned long tag)

Public Member Functions inherited from [gdcm::Object](#)

- [Object](#) ()
- [Object](#) (const [Object](#) &)
Special requirement for copy/cstor, assignment operator.
- virtual [~Object](#) ()
- void [operator=](#) (const [Object](#) &)
- virtual void [Print](#) (std::ostream &) const

Static Public Member Functions

- static [SmartPointer](#)< [MemberCommand](#) > [New](#) ()

Protected Member Functions

- [MemberCommand](#) ()
- [~MemberCommand](#) () override=default

Protected Member Functions inherited from [gdcm::Command](#)

- [Command](#) ()
- [~Command](#) () override

Protected Member Functions inherited from [gdcm::Object](#)

- void [Register](#) ()
- void [UnRegister](#) ()

Protected Attributes

- [TConstMemberFunctionPointer](#) [m_ConstMemberFunction](#)
- [TMemberFunctionPointer](#) [m_MemberFunction](#)
- T * [m_This](#)

10.187.1 Detailed Description

```
template<class T>
class gdcm::MemberCommand< T >
```

[Command](#) subclass that calls a pointer to a member function.

[MemberCommand](#) calls a pointer to a member function with the same arguments as [Execute](#) on [Command](#).

10.187.2 Member Typedef Documentation

10.187.2.1 Self

```
template<class T>
typedef MemberCommand gdcm::MemberCommand< T >::Self
```

Standard class typedefs.

10.187.2.2 TConstMemberFunctionPointer

```
template<class T>
typedef void(T::* gdcm::MemberCommand< T >::TConstMemberFunctionPointer) (const Subject *, const
Event &)
```

10.187.2.3 TMemberFunctionPointer

```
template<class T>
typedef void(T::* gdcm::MemberCommand< T >::TMemberFunctionPointer) (Subject *, const Event &)
```

pointer to a member function that takes a [Subject](#)* and the event

10.187.3 Constructor & Destructor Documentation

10.187.3.1 MemberCommand() [1/2]

```
template<class T>
gdcm::MemberCommand< T >::MemberCommand (
    const Self & ) [delete]
```

10.187.3.2 MemberCommand() [2/2]

```
template<class T>
gdcm::MemberCommand< T >::MemberCommand () [inline], [protected]
```

10.187.3.3 ~MemberCommand()

```
template<class T>
gdcmm::MemberCommand< T >::~~MemberCommand () [override], [protected], [default]
```

10.187.4 Member Function Documentation

10.187.4.1 Execute() [1/2]

```
template<class T>
void gdcmm::MemberCommand< T >::Execute (
    const Subject * caller,
    const Event & event) [inline], [override], [virtual]
```

Invoke the member function with a const object.

Implements [gdcmm::Command](#).

10.187.4.2 Execute() [2/2]

```
template<class T>
void gdcmm::MemberCommand< T >::Execute (
    Subject * caller,
    const Event & event) [inline], [override], [virtual]
```

Invoke the member function.

Implements [gdcmm::Command](#).

10.187.4.3 New()

```
template<class T>
SmartPointer< MemberCommand > gdcmm::MemberCommand< T >::New () [inline], [static]
```

Method for creation through the object factory.

10.187.4.4 operator=()

```
template<class T>
void gdcmm::MemberCommand< T >::operator= (
    const Self & ) [delete]
```

10.187.4.5 SetCallbackFunction() [1/2]

```
template<class T>
void gdcm::MemberCommand< T >::SetCallbackFunction (
    T * object,
    TConstMemberFunctionPointer memberFunction) [inline]
```

10.187.4.6 SetCallbackFunction() [2/2]

```
template<class T>
void gdcm::MemberCommand< T >::SetCallbackFunction (
    T * object,
    TMemberFunctionPointer memberFunction) [inline]
```

Run-time type information (and related methods). Set the callback function along with the object that it will be invoked on.

10.187.5 Member Data Documentation

10.187.5.1 m_ConstMemberFunction

```
template<class T>
TConstMemberFunctionPointer gdcm::MemberCommand< T >::m_ConstMemberFunction [protected]
```

10.187.5.2 m_MemberFunction

```
template<class T>
TMemberFunctionPointer gdcm::MemberCommand< T >::m_MemberFunction [protected]
```

10.187.5.3 m_This

```
template<class T>
T* gdcm::MemberCommand< T >::m_This [protected]
```

The documentation for this class was generated from the following file:


- [gdcmCommand.h](#)

10.188 gdcmmeshprimitive Class Reference


This class defines surface mesh primitives.

```
#include <gdcmmeshprimitive.h>
```

Inheritance diagram for gdcmmeshprimitive:



Collaboration diagram for gdcmmeshprimitive:



Public Types

- enum [MPTType](#) {
[VERTEX](#) = 0 ,
[EDGE](#) ,
[TRIANGLE](#) ,
[TRIANGLE_STRIP](#) ,
[TRIANGLE_FAN](#) ,
[LINE](#) ,
[FACET](#) ,
[MPTType_END](#) }

This enumeration defines primitive types.

- typedef std::vector< [DataElement](#) > [PrimitivesData](#)

Public Member Functions

- [MeshPrimitive](#) ()
- [~MeshPrimitive](#) () override
- void [AddPrimitiveData](#) ([DataElement](#) const &de)
- unsigned int [GetNumberOfPrimitivesData](#) () const
- [DataElement](#) & [GetPrimitiveData](#) ()
- const [DataElement](#) & [GetPrimitiveData](#) () const
- [DataElement](#) & [GetPrimitiveData](#) (const unsigned int idx)
- const [DataElement](#) & [GetPrimitiveData](#) (const unsigned int idx) const
- [PrimitivesData](#) & [GetPrimitivesData](#) ()
- const [PrimitivesData](#) & [GetPrimitivesData](#) () const
- [MPTType](#) [GetPrimitiveType](#) () const
- void [SetPrimitiveData](#) (const unsigned int idx, [DataElement](#) const &de)
- void [SetPrimitiveData](#) ([DataElement](#) const &de)
- void [SetPrimitivesData](#) ([PrimitivesData](#) const &DEs)
- void [SetPrimitiveType](#) (const [MPTType](#) type)

Public Member Functions inherited from [gdcm::Object](#)

- [Object](#) ()
- [Object](#) (const [Object](#) &)
- *Special requirement for copy/cstor, assignment operator.*
- virtual [~Object](#) ()
- void [operator=](#) (const [Object](#) &)
- virtual void [Print](#) (std::ostream &) const

Static Public Member Functions

- static [MPTType](#) [GetMPTType](#) (const char *type)
- static const char * [GetMPTTypeString](#) (const [MPTType](#) type)

Protected Attributes

- [PrimitivesData](#) [PrimitiveData](#)
- [MPType](#) [PrimitiveType](#)

Additional Inherited Members

Protected Member Functions inherited from [gdcm::Object](#)

- void [Register](#) ()
- void [UnRegister](#) ()

10.188.1 Detailed Description

This class defines surface mesh primitives.

It is designed from surface mesh primitives macro.

See also

PS 3.3 C.27.4

10.188.2 Member Typedef Documentation

10.188.2.1 PrimitivesData

```
typedef std::vector< DataElement > gdcm::MeshPrimitive::PrimitivesData
```

10.188.3 Member Enumeration Documentation

10.188.3.1 MPType

```
enum gdcm::MeshPrimitive::MPType
```

This enumeration defines primitive types.

See also

PS 3.3 C.27.4.1

Enumerator

VERTEX	
EDGE	
TRIANGLE	
TRIANGLE_STRIP	
TRIANGLE_FAN	
LINE	
FACET	
MPType_END	

10.188.4 Constructor & Destructor Documentation

10.188.4.1 MeshPrimitive()

```
gdcM::MeshPrimitive::MeshPrimitive ()
```

10.188.4.2 ~MeshPrimitive()

```
gdcM::MeshPrimitive::~~MeshPrimitive () [override]
```

10.188.5 Member Function Documentation

10.188.5.1 AddPrimitiveData()

```
void gdcM::MeshPrimitive::AddPrimitiveData (  
    DataElement const & de)
```

10.188.5.2 GetMPType()

```
MPType gdcM::MeshPrimitive::GetMPType (  
    const char * type) [static]
```

10.188.5.3 GetMPTypeString()

```
const char * gdcM::MeshPrimitive::GetMPTypeString (  
    const MPType type) [static]
```

10.188.5.4 GetNumberOfPrimitivesData()

```
unsigned int gdcM::MeshPrimitive::GetNumberOfPrimitivesData () const
```

10.188.5.5 GetPrimitiveData() [1/4]

```
DataElement & gdcM::MeshPrimitive::GetPrimitiveData ()
```

10.188.5.6 GetPrimitiveData() [2/4]

```
const DataElement & gdcM::MeshPrimitive::GetPrimitiveData () const
```

10.188.5.7 GetPrimitiveData() [3/4]

```
DataElement & gdcM::MeshPrimitive::GetPrimitiveData (
    const unsigned int idx)
```

10.188.5.8 GetPrimitiveData() [4/4]

```
const DataElement & gdcM::MeshPrimitive::GetPrimitiveData (
    const unsigned int idx) const
```

10.188.5.9 GetPrimitivesData() [1/2]

```
PrimitivesData & gdcM::MeshPrimitive::GetPrimitivesData ()
```

10.188.5.10 GetPrimitivesData() [2/2]

```
const PrimitivesData & gdcM::MeshPrimitive::GetPrimitivesData () const
```

10.188.5.11 GetPrimitiveType()

```
MPTType gdcM::MeshPrimitive::GetPrimitiveType () const
```

10.188.5.12 SetPrimitiveData() [1/2]

```
void gdcM::MeshPrimitive::SetPrimitiveData (
    const unsigned int idx,
    DataElement const & de)
```

10.188.5.13 SetPrimitiveData() [2/2]

```
void gdcM::MeshPrimitive::SetPrimitiveData (
    DataElement const & de)
```

10.188.5.14 SetPrimitivesData()

```
void gdcM::MeshPrimitive::SetPrimitivesData (
    PrimitivesData const & DEs)
```

10.188.5.15 SetPrimitiveType()

```
void gdcm::MeshPrimitive::SetPrimitiveType (
    const MPType type)
```

10.188.6 Member Data Documentation

10.188.6.1 PrimitiveData

```
PrimitivesData gdcm::MeshPrimitive::PrimitiveData [protected]
```

10.188.6.2 PrimitiveType

```
MPType gdcm::MeshPrimitive::PrimitiveType [protected]
```

The documentation for this class was generated from the following file:


- [gdcmMeshPrimitive.h](#)

10.189 gdcm::ModalityPerformedProcedureStepCreateQuery Class Reference


[ModalityPerformedProcedureStepCreateQuery](#).

```
#include <gdcmModalityPerformedProcedureStepCreateQuery.h>
```

Inheritance diagram for gdcm::ModalityPerformedProcedureStepCreateQuery:



Collaboration diagram for `gdcm::ModalityPerformedProcedureStepCreateQuery`:



Public Member Functions

- [ModalityPerformedProcedureStepCreateQuery](#) (const std::string &iSopInstanceUID)
- [UIDs::TSName GetAbstractSyntaxUID](#) () const override
- [gdcm::DataSet GetRequiredDataSet](#) () const
- bool [ValidateQuery](#) (bool inStrict=true) const override

Public Member Functions inherited from [gdcm::BaseQuery](#)

- [~BaseQuery](#) () override
- void [AddQueryDataSet](#) (const [DataSet](#) &ds)
- [DataSet](#) & [GetQueryDataSet](#) ()
- [DataSet](#) const & [GetQueryDataSet](#) () const
Set/Get the internal representation of the query as a [DataSet](#).
- std::string [GetSOPInstanceUID](#) () const
- void [Print](#) (std::ostream &os) const override
- void [SetSearchParameter](#) (const std::string &inKeyword, const std::string &inValue)
- void [SetSearchParameter](#) (const [Tag](#) &inTag, const std::string &inValue)
- void [SetSOPInstanceUID](#) (const std::string &iSopInstanceUID)
- const std::ostream & [WriteHelpFile](#) (std::ostream &os)
- bool [WriteQuery](#) (const std::string &inFileName)

Public Member Functions inherited from [gdcm::Object](#)

- [Object](#) ()
- [Object](#) (const [Object](#) &)
Special requirement for copy/cstor, assignment operator.
- virtual [~Object](#) ()
- void [operator=](#) (const [Object](#) &)

Friends

- class [QueryFactory](#)

Additional Inherited Members

Protected Member Functions inherited from [gdcm::BaseQuery](#)

- [BaseQuery](#) ()
- void [SetSearchParameter](#) (const [Tag](#) &inTag, const [DictEntry](#) &inDictEntry, const std::string &inValue)
- bool [ValidDataSet](#) (const [DataSet](#) &dataSetToValid, const [DataSet](#) &dataSetReference) const

Protected Member Functions inherited from [gdcm::Object](#)

- void [Register](#) ()
- void [UnRegister](#) ()

Protected Attributes inherited from [gdcm::BaseQuery](#)

- [DataSet](#) [mDataSet](#)
- std::string [mSopInstanceUID](#)

10.189.1 Detailed Description

[ModalityPerformedProcedureStepCreateQuery](#).

contains: the class which will produce a dataset for n-create for Modality Performed Procedure Step sop class

10.189.2 Constructor & Destructor Documentation

10.189.2.1 [ModalityPerformedProcedureStepCreateQuery](#)()

```
gdcm::ModalityPerformedProcedureStepCreateQuery::ModalityPerformedProcedureStepCreateQuery (
    const std::string & iSopInstanceUID)
```

10.189.3 Member Function Documentation

10.189.3.1 GetAbstractSyntaxUID()

```
UIDs::TSName gdcM::ModalityPerformedProcedureStepCreateQuery::GetAbstractSyntaxUID () const [override],  
[virtual]
```

Implements [gdcM::BaseQuery](#).

10.189.3.2 GetRequiredDataSet()

```
gdcM::DataSet gdcM::ModalityPerformedProcedureStepCreateQuery::GetRequiredDataSet () const
```

10.189.3.3 ValidateQuery()

```
bool gdcM::ModalityPerformedProcedureStepCreateQuery::ValidateQuery (  
    bool inStrict = true) const [override], [virtual]
```

Implements [gdcM::BaseQuery](#).

10.189.4 Friends And Related Symbol Documentation

10.189.4.1 QueryFactory

```
friend class QueryFactory [friend]
```

References [QueryFactory](#).

Referenced by [QueryFactory](#).

The documentation for this class was generated from the following file:


- [gdcMModalityPerformedProcedureStepCreateQuery.h](#)

10.190 gdcm::ModalityPerformedProcedureStepSetQuery Class Reference


[ModalityPerformedProcedureStepSetQuery](#).

```
#include <gdcmModalityPerformedProcedureStepSetQuery.h>
```

Inheritance diagram for gdcm::ModalityPerformedProcedureStepSetQuery:



Collaboration diagram for gdcm::ModalityPerformedProcedureStepSetQuery:



Public Member Functions

- [ModalityPerformedProcedureStepSetQuery](#) (const std::string &iSopInstanceUID)
- [UIDs::TSName GetAbstractSyntaxUID](#) () const override
- [gdcm::DataSet GetRequiredDataSet](#) () const
- bool [ValidateQuery](#) (bool inStrict=true) const override

Public Member Functions inherited from [gdcm::BaseQuery](#)

- [~BaseQuery](#) () override
- void [AddQueryDataSet](#) (const [DataSet](#) &ds)
- [DataSet](#) & [GetQueryDataSet](#) ()
- [DataSet](#) const & [GetQueryDataSet](#) () const
Set/Get the internal representation of the query as a [DataSet](#).
- std::string [GetSOPInstanceUID](#) () const
- void [Print](#) (std::ostream &os) const override
- void [SetSearchParameter](#) (const std::string &inKeyword, const std::string &inValue)
- void [SetSearchParameter](#) (const [Tag](#) &inTag, const std::string &inValue)
- void [SetSOPInstanceUID](#) (const std::string &iSopInstanceUID)
- const std::ostream & [WriteHelpFile](#) (std::ostream &os)
- bool [WriteQuery](#) (const std::string &inFileName)

Public Member Functions inherited from [gdcm::Object](#)

- [Object](#) ()
- [Object](#) (const [Object](#) &)
Special requirement for copy/cstor, assignment operator.
- virtual [~Object](#) ()
- void [operator=](#) (const [Object](#) &)

Friends

- class [QueryFactory](#)

Additional Inherited Members

Protected Member Functions inherited from [gdcm::BaseQuery](#)

- [BaseQuery](#) ()
- void [SetSearchParameter](#) (const [Tag](#) &inTag, const [DictEntry](#) &inDictEntry, const std::string &inValue)
- bool [ValidDataSet](#) (const [DataSet](#) &dataSetToValid, const [DataSet](#) &dataSetReference) const

Protected Member Functions inherited from [gdcm::Object](#)

- void [Register](#) ()
- void [UnRegister](#) ()

Protected Attributes inherited from [gdcm::BaseQuery](#)

- [DataSet](#) `mDataSet`
- `std::string` `mSopInstanceUID`

10.190.1 Detailed Description

[ModalityPerformedProcedureStepSetQuery](#).

contains: the class which will produce a dataset for n-set for Modality Performed Procedure Step sop class

10.190.2 Constructor & Destructor Documentation

10.190.2.1 ModalityPerformedProcedureStepSetQuery()

```
gdcm::ModalityPerformedProcedureStepSetQuery::ModalityPerformedProcedureStepSetQuery (  
    const std::string & iSopInstanceUID)
```

10.190.3 Member Function Documentation

10.190.3.1 GetAbstractSyntaxUID()

```
UIDs::TSName gdcm::ModalityPerformedProcedureStepSetQuery::GetAbstractSyntaxUID () const [override],  
[virtual]
```

Implements [gdcm::BaseQuery](#).

10.190.3.2 GetRequiredDataSet()

```
gdcm::DataSet gdcm::ModalityPerformedProcedureStepSetQuery::GetRequiredDataSet () const
```

10.190.3.3 ValidateQuery()

```
bool gdcm::ModalityPerformedProcedureStepSetQuery::ValidateQuery (  
    bool inStrict = true) const [override], [virtual]
```

Implements [gdcm::BaseQuery](#).

10.190.4 Friends And Related Symbol Documentation

10.190.4.1 QueryFactory

friend class [QueryFactory](#) [friend]

References [QueryFactory](#).

Referenced by [QueryFactory](#).


The documentation for this class was generated from the following file:

- [gdcmModalityPerformedProcedureStepSetQuery.h](#)


10.191 gdcm::ModifiedEvent Class Reference

```
#include <gdcmEvent.h>
```

Inheritance diagram for gdcm::ModifiedEvent:



Collaboration diagram for gdcm::ModifiedEvent:



Additional Inherited Members

Public Member Functions inherited from [gdcm::Event](#)

- [Event](#) ()
- [Event](#) (const [Event](#) &)
- virtual [~Event](#) ()
- virtual bool [CheckEvent](#) (const [Event](#) *) const =0
- virtual const char * [GetEventName](#) () const =0
- virtual [Event](#) * [MakeObject](#) () const =0
- void [operator=](#) (const [Event](#) &)=delete
- virtual void [Print](#) (std::ostream &os) const

The documentation for this class was generated from the following file:

- [gdcmEvent.h](#)

10.192 gdcm::Module Class Reference

Class for representing a [Module](#).

```
#include <gdcmModule.h>
```

Public Types

- typedef std::vector< std::string > [ArrayIncludeMacrosType](#)
- typedef std::map< [Tag](#), [ModuleEntry](#) > [MapModuleEntry](#)

Public Member Functions

- [Module](#) ()=default
- void [AddMacro](#) (const char *include)
- void [AddModuleEntry](#) (const [Tag](#) &tag, const [ModuleEntry](#) &module)
Will add a [ModuleEntry](#) directly at root-level. See [Macro](#) for nested-included level.
- void [Clear](#) ()
- bool [FindModuleEntryInMacros](#) ([Macros](#) const ¯os, const [Tag](#) &tag) const
- const [ModuleEntry](#) & [GetModuleEntryInMacros](#) ([Macros](#) const ¯os, const [Tag](#) &tag) const
- const char * [GetName](#) () const
- void [SetName](#) (const char *name)
- bool [Verify](#) (const [DataSet](#) &ds, [Usage](#) const &usage) const

Friends

- std::ostream & [operator<<](#) (std::ostream &_os, const [Module](#) &_val)

10.192.1 Detailed Description

Class for representing a [Module](#).

Note

[Module](#): A set of Attributes within an Information Entity or Normalized [IOD](#) which are logically related to each other.

See also

[Macro](#)

Examples

[TraverseModules.cxx](#).

10.192.2 Member Typedef Documentation

10.192.2.1 ArrayIncludeMacrosType

```
typedef std::vector<std::string> gdcmm::Module::ArrayIncludeMacrosType
```

10.192.2.2 MapModuleEntry

```
typedef std::map<Tag, ModuleEntry> gdcmm::Module::MapModuleEntry
```

10.192.3 Constructor & Destructor Documentation

10.192.3.1 Module()

```
gdcmmodule::Module::Module () [default]
```

References [Module\(\)](#), and [operator<<](#).

Referenced by [Module\(\)](#), and [operator<<](#).

10.192.4 Member Function Documentation

10.192.4.1 AddMacro()

```
void gdcmmodule::Module::AddMacro (  
    const char * include) [inline]
```

10.192.4.2 AddModuleEntry()

```
void gdcmmodule::Module::AddModuleEntry (  
    const Tag & tag,  
    const ModuleEntry & module) [inline]
```

Will add a [ModuleEntry](#) directly at root-level. See [Macro](#) for nested-included level.

10.192.4.3 Clear()

```
void gdcmmodule::Module::Clear () [inline]
```

10.192.4.4 FindModuleEntryInMacros()

```
bool gdcmmodule::Module::FindModuleEntryInMacros (  
    Macros const & macros,  
    const Tag & tag) const
```

Find or Get a [ModuleEntry](#). [ModuleEntry](#) are either search are root-level or within nested-macro included in module.

Examples

[TraverseModules.cxx](#).

10.192.4.5 GetModuleEntryInMacros()

```
const ModuleEntry & gdcM::Module::GetModuleEntryInMacros (
    Macros const & macros,
    const Tag & tag) const
```

10.192.4.6 GetName()

```
const char * gdcM::Module::GetName () const [inline]
```

10.192.4.7 SetName()

```
void gdcM::Module::SetName (
    const char * name) [inline]
```

10.192.4.8 Verify()

```
bool gdcM::Module::Verify (
    const DataSet & ds,
    Usage const & usage) const
```

10.192.5 Friends And Related Symbol Documentation

10.192.5.1 operator<<

```
std::ostream & operator<< (
    std::ostream & _os,
    const Module & _val) [friend]
```

References [Module\(\)](#).

Referenced by [Module\(\)](#).

The documentation for this class was generated from the following file:


- [gdcMModule.h](#)

10.193 gdcm::ModuleEntry Class Reference


Class for representing a [ModuleEntry](#).

```
#include <gdcmModuleEntry.h>
```

Inheritance diagram for gdcm::ModuleEntry:



Collaboration diagram for gdcm::ModuleEntry:



Public Types

- typedef std::string [Description](#)

Public Member Functions

- [ModuleEntry](#) (const char *name="", const char *type="3", const char *description="")
- virtual [~ModuleEntry](#) ()=default
- const [Description](#) & [GetDescription](#) () const
- const char * [GetName](#) () const
- const [Type](#) & [GetType](#) () const
- void [SetDescription](#) (const char *d)
- void [SetName](#) (const char *name)
- void [SetType](#) (const [Type](#) &type)

Protected Attributes

- [Type](#) [DataElementType](#)
- [Description](#) [DescriptionField](#)
- std::string [Name](#)

Friends

- std::ostream & [operator<<](#) (std::ostream &_os, const [ModuleEntry](#) &_val)

10.193.1 Detailed Description

Class for representing a [ModuleEntry](#).

Note

bla

See also

[DictEntry](#)

Examples

[TraverseModules.cxx](#).

10.193.2 Member Typedef Documentation

10.193.2.1 Description

```
typedef std::string gdcm::ModuleEntry::Description
```

10.193.3 Constructor & Destructor Documentation

10.193.3.1 ModuleEntry()

```
gdcm::ModuleEntry::ModuleEntry (
    const char * name = "",
    const char * type = "3",
    const char * description = "") [inline]
```

References [DataElementType](#), [DescriptionField](#), [gdcm::Type::GetTypeType\(\)](#), and [Name](#).

Referenced by [gdcm::NestedModuleEntries::NestedModuleEntries\(\)](#), [~ModuleEntry\(\)](#), [gdcm::NestedModuleEntries::AddModuleEntry\(\)](#), [gdcm::NestedModuleEntries::GetModuleEntry\(\)](#), [gdcm::NestedModuleEntries::GetModuleEntry\(\)](#), and [operator<<](#).

10.193.3.2 ~ModuleEntry()

```
virtual gdcm::ModuleEntry::~~ModuleEntry () [virtual], [default]
```

References [ModuleEntry\(\)](#), and [operator<<](#).

10.193.4 Member Function Documentation

10.193.4.1 GetDescription()

```
const Description & gdcm::ModuleEntry::GetDescription () const [inline]
```

References [DescriptionField](#).

10.193.4.2 GetName()

```
const char * gdcm::ModuleEntry::GetName () const [inline]
```

References [Name](#).

10.193.4.3 GetType()

```
const Type & gdcm::ModuleEntry::GetType () const [inline]
```

Examples

[TraverseModules.cxx](#).

References [DataElementType](#).

10.193.4.4 SetDescription()

```
void gdcmm::ModuleEntry::SetDescription (
    const char * d) [inline]
```

References [DescriptionField](#).

10.193.4.5 SetName()

```
void gdcmm::ModuleEntry::SetName (
    const char * name) [inline]
```

References [Name](#).

10.193.4.6 SetType()

```
void gdcmm::ModuleEntry::SetType (
    const Type & type) [inline]
```

References [DataElementType](#).

10.193.5 Friends And Related Symbol Documentation

10.193.5.1 operator<<

```
std::ostream & operator<< (
    std::ostream & _os,
    const ModuleEntry & _val) [friend]
```

References [ModuleEntry\(\)](#), [DataElementType](#), [DescriptionField](#), and [Name](#).

Referenced by [~ModuleEntry\(\)](#).

10.193.6 Member Data Documentation

10.193.6.1 DataElementType

```
Type gdcmm::ModuleEntry::DataElementType [protected]
```

Referenced by [ModuleEntry\(\)](#), [GetType\(\)](#), [operator<<](#), [gdcmm::NestedModuleEntries::operator<<](#), and [SetType\(\)](#).

10.193.6.2 DescriptionField

`Description` gdcm::ModuleEntry::DescriptionField [protected]

Referenced by [ModuleEntry\(\)](#), [GetDescription\(\)](#), [operator<<](#), [gdcm::NestedModuleEntries::operator<<](#), and [SetDescription\(\)](#).

10.193.6.3 Name

`std::string` gdcm::ModuleEntry::Name [protected]

Referenced by [ModuleEntry\(\)](#), [GetName\(\)](#), [operator<<](#), [gdcm::NestedModuleEntries::operator<<](#), and [SetName\(\)](#).

The documentation for this class was generated from the following file:

- [gdcmModuleEntry.h](#)

10.194 gdcm::Modules Class Reference

Class for representing a [Modules](#).

```
#include <gdcmModules.h>
```

Public Types

- `typedef std::map< std::string, Module > ModuleMapType`

Public Member Functions

- [Modules](#) ()=default
- void [AddModule](#) (const char *ref, const [Module](#) &module)
- void [Clear](#) ()
- const [Module](#) & [GetModule](#) (const char *name) const
- bool [IsEmpty](#) () const

Friends

- `std::ostream & operator<< (std::ostream &_os, const Modules &_val)`

10.194.1 Detailed Description

Class for representing a [Modules](#).

Note

bla

See also

[Module](#)

Examples

[TraverseModules.cxx](#).

10.194.2 Member Typedef Documentation

10.194.2.1 ModuleMapType

```
typedef std::map<std::string, Module> gdcmm::Modules::ModuleMapType
```

10.194.3 Constructor & Destructor Documentation

10.194.3.1 Modules()

```
gdcmm::Modules::Modules () [default]
```

References [Modules\(\)](#), and [operator<<](#).

Referenced by [Modules\(\)](#), and [operator<<](#).

10.194.4 Member Function Documentation

10.194.4.1 AddModule()

```
void gdcmm::Modules::AddModule (  
    const char * ref,  
    const Module & module) [inline]
```

References [gdcmm_assert](#).

10.194.4.2 Clear()

```
void gdcm::Modules::Clear () [inline]
```

10.194.4.3 GetModule()

```
const Module & gdcm::Modules::GetModule (
    const char * name) const [inline]
```

Examples

[TraverseModules.cxx](#).

References [gdcm_assert](#).

10.194.4.4 IsEmpty()

```
bool gdcm::Modules::IsEmpty () const [inline]
```

10.194.5 Friends And Related Symbol Documentation

10.194.5.1 operator<<

```
std::ostream & operator<< (
    std::ostream & _os,
    const Modules & _val) [friend]
```

References [Modules\(\)](#).

Referenced by [Modules\(\)](#).

The documentation for this class was generated from the following file:


- [gdcmModules.h](#)

10.195 gdcm::MovePatientRootQuery Class Reference


[MovePatientRootQuery](#).

```
#include <gdcmMovePatientRootQuery.h>
```

Inheritance diagram for gdcm::MovePatientRootQuery:



Collaboration diagram for gdcm::MovePatientRootQuery:



Public Member Functions

- [MovePatientRootQuery](#) ()
- `UIDs::TSName GetAbstractSyntaxUID` () const override
- `std::vector< Tag > GetTagListByLevel` (const [EQueryLevel](#) &inQueryLevel) override
- void `InitializeDataSet` (const [EQueryLevel](#) &inQueryLevel) override
- bool `ValidateQuery` (bool inStrict=true) const override

Public Member Functions inherited from [gdcm::BaseRootQuery](#)

- [~BaseRootQuery](#) () override=default
- [EQueryLevel](#) [GetQueryLevelFromQueryRoot](#) ([ERootType](#) roottype)

Public Member Functions inherited from [gdcm::BaseQuery](#)

- [~BaseQuery](#) () override
 - void [AddQueryDataSet](#) (const [DataSet](#) &ds)
 - [DataSet](#) & [GetQueryDataSet](#) ()
 - [DataSet](#) const & [GetQueryDataSet](#) () const
- Set/Get the internal representation of the query as a [DataSet](#).*
- std::string [GetSOPInstanceUID](#) () const
 - void [Print](#) (std::ostream &os) const override
 - void [SetSearchParameter](#) (const std::string &inKeyword, const std::string &inValue)
 - void [SetSearchParameter](#) (const [Tag](#) &inTag, const std::string &inValue)
 - void [SetSOPInstanceUID](#) (const std::string &iSopInstanceUID)
 - const std::ostream & [WriteHelpFile](#) (std::ostream &os)
 - bool [WriteQuery](#) (const std::string &inFileName)

Public Member Functions inherited from [gdcm::Object](#)

- [Object](#) ()
 - [Object](#) (const [Object](#) &)
- Special requirement for copy/cstor, assignment operator.*
- virtual [~Object](#) ()
 - void [operator=](#) (const [Object](#) &)

Friends

- class [QueryFactory](#)

Additional Inherited Members

Static Public Member Functions inherited from [gdcm::BaseRootQuery](#)

- static [QueryBase](#) * [Construct](#) ([ERootType](#) inRootType, [EQueryLevel](#) qllevel)
- static int [GetQueryLevelFromString](#) (const char *str)
- static const char * [GetQueryLevelString](#) ([EQueryLevel](#) ql)

Protected Member Functions inherited from [gdcm::BaseRootQuery](#)

- [BaseRootQuery](#) ()

Protected Member Functions inherited from [gdcm::BaseQuery](#)

- [BaseQuery](#) ()
- void [SetSearchParameter](#) (const [Tag](#) &inTag, const [DictEntry](#) &inDictEntry, const std::string &inValue)
- bool [ValidDataSet](#) (const [DataSet](#) &dataSetToValid, const [DataSet](#) &dataSetReference) const

Protected Member Functions inherited from [gdcm::Object](#)

- void [Register](#) ()
- void [UnRegister](#) ()

Protected Attributes inherited from [gdcm::BaseRootQuery](#)

- std::string [mHelpDescription](#)
- [QueryImage](#) [mImage](#)
- [QueryPatient](#) [mPatient](#)
- [ERootType](#) [mRootType](#)
- [QuerySeries](#) [mSeries](#)
- [QueryStudy](#) [mStudy](#)

Protected Attributes inherited from [gdcm::BaseQuery](#)

- [DataSet](#) [mDataSet](#)
- std::string [mSopInstanceUID](#)

10.195.1 Detailed Description

[MovePatientRootQuery](#).

contains: the class which will produce a dataset for c-move with patient root

10.195.2 Constructor & Destructor Documentation

10.195.2.1 [MovePatientRootQuery](#)()

```
gdcm::MovePatientRootQuery::MovePatientRootQuery ()
```

10.195.3 Member Function Documentation

10.195.3.1 [GetAbstractSyntaxUID](#)()

```
UIDs::TSName gdcm::MovePatientRootQuery::GetAbstractSyntaxUID () const [override], [virtual]
```

Implements [gdcm::BaseQuery](#).

10.195.3.2 GetTagListByLevel()

```
std::vector< Tag > gdcm::MovePatientRootQuery::GetTagListByLevel (
    const EQueryLevel & inQueryLevel) [override], [virtual]
```

this function will return all tags at a given query level, so that they maybe selected for searching. The boolean forFind is true if the query is a find query, or false for a move query.

Implements [gdcm::BaseRootQuery](#).

10.195.3.3 InitializeDataSet()

```
void gdcm::MovePatientRootQuery::InitializeDataSet (
    const EQueryLevel & inQueryLevel) [override], [virtual]
```

this function sets tag 8,52 to the appropriate value based on query level also fills in the right unique tags, as per the standard's requirements should allow for connection with dcmTk

Implements [gdcm::BaseRootQuery](#).

10.195.3.4 ValidateQuery()

```
bool gdcm::MovePatientRootQuery::ValidateQuery (
    bool inStrict = true) const [override], [virtual]
```

have to be able to ensure that 0x8,0x52 is set (which will be true if InitializeDataSet is called...) that the level is appropriate (ie, not setting PATIENT for a study query that the tags in the query match the right level (either required, unique, optional) by default, this function checks to see if the query is for finding, which is more permissive than for moving. For moving, only the unique tags are allowed. 10 Jan 2011: adding in the 'strict' mode. according to the standard (at least, how I've read it), only tags for a particular level should be allowed in a particular query (ie, just series level tags in a series level query). However, it seems that dcm4chee doesn't share that interpretation. So, if 'inStrict' is false, then tags from the current level and all higher levels are now considered valid. So, if you're doing a non-strict series-level query, tags from the patient and study level can be passed along as well.

Implements [gdcm::BaseRootQuery](#).

10.195.4 Friends And Related Symbol Documentation

10.195.4.1 QueryFactory

```
friend class QueryFactory [friend]
```

References [QueryFactory](#).

Referenced by [QueryFactory](#).

The documentation for this class was generated from the following file:


- [gdcmMovePatientRootQuery.h](#)

10.196 gdcm::MoveStudyRootQuery Class Reference


[MoveStudyRootQuery](#).

```
#include <gdcmMoveStudyRootQuery.h>
```

Inheritance diagram for gdcm::MoveStudyRootQuery:



Collaboration diagram for gdcm::MoveStudyRootQuery:



Public Member Functions

- [MoveStudyRootQuery](#) ()
- `UIDs::TSName GetAbstractSyntaxUID` () const override
- `std::vector< Tag > GetTagListByLevel` (const [EQueryLevel](#) &inQueryLevel) override
- void `InitializeDataSet` (const [EQueryLevel](#) &inQueryLevel) override
- bool `ValidateQuery` (bool inStrict=true) const override

Public Member Functions inherited from [gdcm::BaseRootQuery](#)

- [~BaseRootQuery](#) () override=default
- [EQueryLevel](#) [GetQueryLevelFromQueryRoot](#) ([ERootType](#) roottype)

Public Member Functions inherited from [gdcm::BaseQuery](#)

- [~BaseQuery](#) () override
 - void [AddQueryDataSet](#) (const [DataSet](#) &ds)
 - [DataSet](#) & [GetQueryDataSet](#) ()
 - [DataSet](#) const & [GetQueryDataSet](#) () const
- Set/Get the internal representation of the query as a [DataSet](#).*
- std::string [GetSOPInstanceUID](#) () const
 - void [Print](#) (std::ostream &os) const override
 - void [SetSearchParameter](#) (const std::string &inKeyword, const std::string &inValue)
 - void [SetSearchParameter](#) (const [Tag](#) &inTag, const std::string &inValue)
 - void [SetSOPInstanceUID](#) (const std::string &iSopInstanceUID)
 - const std::ostream & [WriteHelpFile](#) (std::ostream &os)
 - bool [WriteQuery](#) (const std::string &inFileName)

Public Member Functions inherited from [gdcm::Object](#)

- [Object](#) ()
 - [Object](#) (const [Object](#) &)
- Special requirement for copy/cstor, assignment operator.*
- virtual [~Object](#) ()
 - void [operator=](#) (const [Object](#) &)

Friends

- class [QueryFactory](#)

Additional Inherited Members

Static Public Member Functions inherited from [gdcm::BaseRootQuery](#)

- static [QueryBase](#) * [Construct](#) ([ERootType](#) inRootType, [EQueryLevel](#) qllevel)
- static int [GetQueryLevelFromString](#) (const char *str)
- static const char * [GetQueryLevelString](#) ([EQueryLevel](#) ql)

Protected Member Functions inherited from [gdcm::BaseRootQuery](#)

- [BaseRootQuery](#) ()

Protected Member Functions inherited from [gdcm::BaseQuery](#)

- [BaseQuery](#) ()
- void [SetSearchParameter](#) (const [Tag](#) &inTag, const [DictEntry](#) &inDictEntry, const std::string &inValue)
- bool [ValidDataSet](#) (const [DataSet](#) &dataSetToValid, const [DataSet](#) &dataSetReference) const

Protected Member Functions inherited from [gdcm::Object](#)

- void [Register](#) ()
- void [UnRegister](#) ()

Protected Attributes inherited from [gdcm::BaseRootQuery](#)

- std::string [mHelpDescription](#)
- [QueryImage](#) [mImage](#)
- [QueryPatient](#) [mPatient](#)
- [ERootType](#) [mRootType](#)
- [QuerySeries](#) [mSeries](#)
- [QueryStudy](#) [mStudy](#)

Protected Attributes inherited from [gdcm::BaseQuery](#)

- [DataSet](#) [mDataSet](#)
- std::string [mSopInstanceUID](#)

10.196.1 Detailed Description

[MoveStudyRootQuery](#).

contains: the class which will produce a dataset for C-MOVE with study root

10.196.2 Constructor & Destructor Documentation

10.196.2.1 [MoveStudyRootQuery](#)()

```
gdcm::MoveStudyRootQuery::MoveStudyRootQuery ()
```

10.196.3 Member Function Documentation

10.196.3.1 [GetAbstractSyntaxUID](#)()

```
UIDs::TSName gdcm::MoveStudyRootQuery::GetAbstractSyntaxUID () const [override], [virtual]
```

Implements [gdcm::BaseQuery](#).

10.196.3.2 GetTagListByLevel()

```
std::vector< Tag > gdcm::MoveStudyRootQuery::GetTagListByLevel (
    const EQueryLevel & inQueryLevel) [override], [virtual]
```

this function will return all tags at a given query level, so that they maybe selected for searching. The boolean forFind is true if the query is a find query, or false for a move query.

Implements [gdcm::BaseRootQuery](#).

10.196.3.3 InitializeDataSet()

```
void gdcm::MoveStudyRootQuery::InitializeDataSet (
    const EQueryLevel & inQueryLevel) [override], [virtual]
```

this function sets tag 8,52 to the appropriate value based on query level also fills in the right unique tags, as per the standard's requirements should allow for connection with dcmTk

Implements [gdcm::BaseRootQuery](#).

10.196.3.4 ValidateQuery()

```
bool gdcm::MoveStudyRootQuery::ValidateQuery (
    bool inStrict = true) const [override], [virtual]
```

have to be able to ensure that 0x8,0x52 is set (which will be true if InitializeDataSet is called...) that the level is appropriate (ie, not setting PATIENT for a study query that the tags in the query match the right level (either required, unique, optional) by default, this function checks to see if the query is for finding, which is more permissive than for moving. For moving, only the unique tags are allowed. 10 Jan 2011: adding in the 'strict' mode. according to the standard (at least, how I've read it), only tags for a particular level should be allowed in a particular query (ie, just series level tags in a series level query). However, it seems that dcm4chee doesn't share that interpretation. So, if 'inStrict' is false, then tags from the current level and all higher levels are now considered valid. So, if you're doing a non-strict series-level query, tags from the patient and study level can be passed along as well.

Implements [gdcm::BaseRootQuery](#).

10.196.4 Friends And Related Symbol Documentation

10.196.4.1 QueryFactory

```
friend class QueryFactory [friend]
```

References [QueryFactory](#).

Referenced by [QueryFactory](#).

The documentation for this class was generated from the following file:

- [gdcmMoveStudyRootQuery.h](#)

10.197 gdcm::MrProtocol Class Reference

Class for [MrProtocol](#).

```
#include <gdcmMrProtocol.h>
```

Classes

- struct [Slice](#)
- struct [SliceArray](#)
- struct [Vector3](#)

Public Member Functions

- [MrProtocol](#) ()
- [~MrProtocol](#) ()
- bool [FindMrProtocolByName](#) (const char *name) const
- const char * [GetMrProtocolByName](#) (const char *name) const
- bool [GetSliceArray](#) ([MrProtocol::SliceArray](#) &sa) const
- int [GetVersion](#) () const
- bool [Load](#) (const [ByteValue](#) *bv, const char *str, int version)
- void [Print](#) (std::ostream &os) const

Friends

- std::ostream & [operator<<](#) (std::ostream &_os, const [MrProtocol](#) &d)

10.197.1 Detailed Description

Class for [MrProtocol](#).

Examples

[MrProtocol.cxx](#).

10.197.2 Constructor & Destructor Documentation

10.197.2.1 MrProtocol()

```
gdcm::MrProtocol::MrProtocol ()
```

Referenced by [operator<<](#).

10.197.2.2 ~MrProtocol()

```
gdcm::MrProtocol::~~MrProtocol ()
```

10.197.3 Member Function Documentation

10.197.3.1 FindMrProtocolByName()

```
bool gdcm::MrProtocol::FindMrProtocolByName (
    const char * name) const
```

10.197.3.2 GetMrProtocolByName()

```
const char * gdcm::MrProtocol::GetMrProtocolByName (
    const char * name) const
```

10.197.3.3 GetSliceArray()

```
bool gdcm::MrProtocol::GetSliceArray (
    MrProtocol::SliceArray & sa) const
```

10.197.3.4 GetVersion()

```
int gdcm::MrProtocol::GetVersion () const
```

10.197.3.5 Load()

```
bool gdcm::MrProtocol::Load (
    const ByteValue * bv,
    const char * str,
    int version)
```

10.197.3.6 Print()

```
void gdcm::MrProtocol::Print (
    std::ostream & os) const
```

Referenced by [operator<<](#).

10.197.4 Friends And Related Symbol Documentation

10.197.4.1 `operator<<`

```
std::ostream & operator<< (  
    std::ostream & _os,  
    const MrProtocol & d) [friend]
```

References [MrProtocol\(\)](#), and [Print\(\)](#).

The documentation for this class was generated from the following file:


- [gdcmMrProtocol.h](#)

10.198 `gdcm::network::NActionRQ` Class Reference


[NActionRQ](#).

```
#include <gdcmNActionMessages.h>
```

Inheritance diagram for `gdcm::network::NActionRQ`:



Collaboration diagram for `gdcm::network::NActionRQ`:



Public Member Functions

- `std::vector< PresentationDataValue > ConstructPDV` (`const ULConnection &inConnection`, `const BaseQuery *inQuery`) override

Public Member Functions inherited from [gdcm::network::BaseNormalizedMessage](#)

- `virtual ~BaseNormalizedMessage ()`=default

10.198.1 Detailed Description

[NActionRQ](#).

this file defines the messages for the NAction action

10.198.2 Member Function Documentation**10.198.2.1 ConstructPDV()**

```
std::vector< PresentationDataValue > gdcm::network::NActionRQ::ConstructPDV (
    const ULConnection & inConnection,
    const BaseQuery * inQuery) [override], [virtual]
```

Implements [gdcm::network::BaseNormalizedMessage](#).

The documentation for this class was generated from the following file:


- [gdcmNActionMessages.h](#)

10.199 gdcm::network::NActionRSP Class Reference


[NActionRSP](#) this file defines the messages for the NAction action.

```
#include <gdcmNActionMessages.h>
```

Inheritance diagram for `gdcm::network::NActionRSP`:



Collaboration diagram for `gdcm::network::NActionRSP`:



Public Member Functions

- `std::vector< PresentationDataValue > ConstructPDVByDataSet` (const [DataSet](#) *inDataSet)

Public Member Functions inherited from [gdcm::network::BaseNormalizedMessage](#)

- virtual `~BaseNormalizedMessage` ()=default
- virtual `std::vector< PresentationDataValue > ConstructPDV` (const [ULConnection](#) &inConnection, const [BaseQuery](#) *inQuery)=0

10.199.1 Detailed Description

[NActionRSP](#) this file defines the messages for the NAction action.

10.199.2 Member Function Documentation

10.199.2.1 ConstructPDVByDataSet()

```
std::vector< PresentationDataValue > gdcm::network::NActionRSP::ConstructPDVByDataSet (
    const DataSet * inDataSet)
```

The documentation for this class was generated from the following file:


- [gdcmNActionMessages.h](#)

10.200 gdcm::network::NCreateRQ Class Reference


[NCreateRQ](#).

```
#include <gdcmNCreateMessages.h>
```

Inheritance diagram for gdcm::network::NCreateRQ:



Collaboration diagram for gdcm::network::NCreateRQ:



Public Member Functions

- `std::vector< PresentationDataValue > ConstructPDV` (const [ULConnection](#) &inConnection, const [BaseQuery](#) *inQuery) override

Public Member Functions inherited from [gdcm::network::BaseNormalizedMessage](#)

- virtual `~BaseNormalizedMessage` ()=default

10.200.1 Detailed Description

[NCreateRQ](#).

this file defines the messages for the ncreate action

10.200.2 Member Function Documentation

10.200.2.1 ConstructPDV()

```
std::vector< PresentationDataValue > gdcM::network::NCreateRQ::ConstructPDV (
    const ULConnection & inConnection,
    const BaseQuery * inQuery) [override], [virtual]
```

Implements [gdcM::network::BaseNormalizedMessage](#).

The documentation for this class was generated from the following file:


- [gdcMNCreateMessages.h](#)

10.201 gdcM::network::NCreateRSP Class Reference


[NCreateRSP](#) this file defines the messages for the ncreate action.

```
#include <gdcMNCreateMessages.h>
```

Inheritance diagram for gdcM::network::NCreateRSP:



Collaboration diagram for gdcm::network::NCreateRSP:



Public Member Functions

- `std::vector< PresentationDataValue > ConstructPDVByDataSet (const DataSet *inDataSet)`

Public Member Functions inherited from [gdcm::network::BaseNormalizedMessage](#)

- `virtual ~BaseNormalizedMessage ()=default`
- `virtual std::vector< PresentationDataValue > ConstructPDV (const ULConnection &inConnection, const BaseQuery *inQuery)=0`

10.201.1 Detailed Description

[NCreateRSP](#) this file defines the messages for the ncreate action.

10.201.2 Member Function Documentation

10.201.2.1 ConstructPDVByDataSet()

```
std::vector< PresentationDataValue > gdcm::network::NCreateRSP::ConstructPDVByDataSet (
    const DataSet * inDataSet)
```

The documentation for this class was generated from the following file:


- [gdcmNCreateMessages.h](#)

10.202 gdcm::network::NDeleteRQ Class Reference


[NDeleteRQ](#).

```
#include <gdcmNDeleteMessages.h>
```

Inheritance diagram for `gdcm::network::NDeleteRQ`:



Collaboration diagram for `gdcm::network::NDeleteRQ`:



Public Member Functions

- `std::vector< PresentationDataValue > ConstructPDV` (const [ULConnection](#) &inConnection, const [BaseQuery](#) *inQuery) override

Public Member Functions inherited from [gdcm::network::BaseNormalizedMessage](#)

- virtual `~BaseNormalizedMessage` ()=default

10.202.1 Detailed Description

[NDeleteRQ](#).

this file defines the messages for the ndelete action

10.202.2 Member Function Documentation

10.202.2.1 ConstructPDV()

```
std::vector< PresentationDataValue > gdcm::network::NDeleteRQ::ConstructPDV (  
    const ULConnection & inConnection,  
    const BaseQuery * inQuery) [override], [virtual]
```

Implements [gdcm::network::BaseNormalizedMessage](#).

The documentation for this class was generated from the following file:


- [gdcmNDeleteMessages.h](#)

10.203 gdcm::network::NDeleteRSP Class Reference


[NDeleteRSP](#) this file defines the messages for the ndelete action.

```
#include <gdcmNDeleteMessages.h>
```

Inheritance diagram for gdcm::network::NDeleteRSP:



Collaboration diagram for `gdcm::network::NDeleteRSP`:



Public Member Functions

- `std::vector< PresentationDataValue > ConstructPDVByDataSet` (const [DataSet](#) *inDataSet)

Public Member Functions inherited from [gdcm::network::BaseNormalizedMessage](#)

- virtual `~BaseNormalizedMessage` ()=default
- virtual `std::vector< PresentationDataValue > ConstructPDV` (const [ULConnection](#) &inConnection, const [BaseQuery](#) *inQuery)=0

10.203.1 Detailed Description

[NDeleteRSP](#) this file defines the messages for the ndelete action.

10.203.2 Member Function Documentation

10.203.2.1 ConstructPDVByDataSet()

```
std::vector< PresentationDataValue > gdcm::network::NDeleteRSP::ConstructPDVByDataSet (
    const DataSet * inDataSet)
```

The documentation for this class was generated from the following file:


- [gdcmNDeleteMessages.h](#)

10.204 gdcm::NestedModuleEntries Class Reference


Class for representing a [NestedModuleEntries](#).

```
#include <gdcmNestedModuleEntries.h>
```

Inheritance diagram for gdcm::NestedModuleEntries:



Collaboration diagram for gdcm::NestedModuleEntries:



Public Types

- typedef std::vector< [ModuleEntry](#) >::size_type [SizeType](#)

Public Types inherited from [gdcm::ModuleEntry](#)

- typedef std::string [Description](#)

Public Member Functions

- [NestedModuleEntries](#) (const char *name="", const char *type="3", const char *description="")
- void [AddModuleEntry](#) (const [ModuleEntry](#) &me)
- [ModuleEntry](#) & [GetModuleEntry](#) ([SizeType](#) idx)
- const [ModuleEntry](#) & [GetModuleEntry](#) ([SizeType](#) idx) const
- [SizeType](#) [GetNumberOfModuleEntries](#) ()

Public Member Functions inherited from [gdcm::ModuleEntry](#)

- [ModuleEntry](#) (const char *name="", const char *type="3", const char *description="")
- virtual [~ModuleEntry](#) ()=default
- const [Description](#) & [GetDescription](#) () const
- const char * [GetName](#) () const
- const [Type](#) & [GetType](#) () const
- void [SetDescription](#) (const char *d)
- void [SetName](#) (const char *name)
- void [SetType](#) (const [Type](#) &type)

Friends

- std::ostream & [operator<<](#) (std::ostream &_os, const [NestedModuleEntries](#) &_val)

Additional Inherited Members

Protected Attributes inherited from [gdcm::ModuleEntry](#)

- [Type](#) [DataElementType](#)
- [Description](#) [DescriptionField](#)
- std::string [Name](#)

10.204.1 Detailed Description

Class for representing a [NestedModuleEntries](#).

Note

bla

See also

[ModuleEntry](#)

10.204.2 Member Typedef Documentation

10.204.2.1 SizeType

```
typedef std::vector<ModuleEntry>::size_type gdcm::NestedModuleEntries::SizeType
```

10.204.3 Constructor & Destructor Documentation

10.204.3.1 NestedModuleEntries()

```
gdcm::NestedModuleEntries::NestedModuleEntries (
    const char * name = "",
    const char * type = "3",
    const char * description = "") [inline]
```

References [gdcm::ModuleEntry::ModuleEntry\(\)](#).

Referenced by [operator<<](#).

10.204.4 Member Function Documentation

10.204.4.1 AddModuleEntry()

```
void gdcm::NestedModuleEntries::AddModuleEntry (
    const ModuleEntry & me) [inline]
```

References [gdcm::ModuleEntry::ModuleEntry\(\)](#).

10.204.4.2 GetModuleEntry() [1/2]

```
ModuleEntry & gdcm::NestedModuleEntries::GetModuleEntry (
    SizeType idx) [inline]
```

References [gdcm::ModuleEntry::ModuleEntry\(\)](#).

10.204.4.3 GetModuleEntry() [2/2]

```
const ModuleEntry & gdcM::NestedModuleEntries::GetModuleEntry (
    SizeType idx) const [inline]
```

References [gdcM::ModuleEntry::ModuleEntry\(\)](#).

10.204.4.4 GetNumberOfModuleEntries()

```
SizeType gdcM::NestedModuleEntries::GetNumberOfModuleEntries () [inline]
```

10.204.5 Friends And Related Symbol Documentation

10.204.5.1 operator<<

```
std::ostream & operator<< (
    std::ostream & _os,
    const NestedModuleEntries & _val) [friend]
```

References [NestedModuleEntries\(\)](#), [gdcM::ModuleEntry::DataElementType](#), [gdcM::ModuleEntry::DescriptionField](#), and [gdcM::ModuleEntry::Name](#).

The documentation for this class was generated from the following file:


- [gdcMNestedModuleEntries.h](#)

10.205 gdcM::network::NEventReportRQ Class Reference


[NEventReportRQ](#).

```
#include <gdcMNEventReportMessages.h>
```

Inheritance diagram for gdcM::network::NEventReportRQ:



Collaboration diagram for gdcm::network::NEventReportRQ:



Public Member Functions

- `std::vector< PresentationDataValue > ConstructPDV` (const [ULConnection](#) &*inConnection*, const [BaseQuery](#) **inQuery*) override

Public Member Functions inherited from [gdcm::network::BaseNormalizedMessage](#)

- virtual `~BaseNormalizedMessage` ()=default

10.205.1 Detailed Description

[NEventReportRQ](#).

this file defines the messages for the neventreport action

10.205.2 Member Function Documentation

10.205.2.1 ConstructPDV()

```
std::vector< PresentationDataValue > gdcm::network::NEventReportRQ::ConstructPDV (
    const ULConnection & inConnection,
    const BaseQuery * inQuery) [override], [virtual]
```

Implements [gdcm::network::BaseNormalizedMessage](#).

The documentation for this class was generated from the following file:


- [gdcmNEventReportMessages.h](#)

10.206 gdcm::network::NEventReportRSP Class Reference


[NEventReportRSP](#) this file defines the messages for the neventreport action.

```
#include <gdcmNEventReportMessages.h>
```

Inheritance diagram for `gdcm::network::NEventReportRSP`:



Collaboration diagram for `gdcm::network::NEventReportRSP`:



Public Member Functions

- `std::vector< PresentationDataValue > ConstructPDVByDataSet` (const [DataSet](#) *inDataSet)

Public Member Functions inherited from [gdcm::network::BaseNormalizedMessage](#)

- virtual `~BaseNormalizedMessage` ()=default
- virtual `std::vector< PresentationDataValue > ConstructPDV` (const [ULConnection](#) &inConnection, const [BaseQuery](#) *inQuery)=0

10.206.1 Detailed Description

[NEventReportRSP](#) this file defines the messages for the neventreport action.

10.206.2 Member Function Documentation

10.206.2.1 ConstructPDVByDataSet()

```
std::vector< PresentationDataValue > gdcm::network::NEventReportRSP::ConstructPDVByDataSet (
    const DataSet * inDataSet)
```

The documentation for this class was generated from the following file:


- [gdcmNEventReportMessages.h](#)

10.207 gdcm::network::NGetRQ Class Reference


[NGetRQ](#).

```
#include <gdcmNGetMessages.h>
```

Inheritance diagram for gdcm::network::NGetRQ:



Collaboration diagram for `gdcm::network::NGetRQ`:



Public Member Functions

- `std::vector< PresentationDataValue > ConstructPDV` (const [ULConnection](#) &`inConnection`, const [BaseQuery](#) *`inQuery`) override

Public Member Functions inherited from [gdcm::network::BaseNormalizedMessage](#)

- virtual `~BaseNormalizedMessage` ()=default

10.207.1 Detailed Description

[NGetRQ](#).

this file defines the messages for the nget action

10.207.2 Member Function Documentation

10.207.2.1 ConstructPDV()

```
std::vector< PresentationDataValue > gdcm::network::NGetRQ::ConstructPDV (
    const ULConnection & inConnection,
    const BaseQuery * inQuery) [override], [virtual]
```

Implements [gdcm::network::BaseNormalizedMessage](#).

The documentation for this class was generated from the following file:


- [gdcmNGetMessages.h](#)

10.208 gdcm::network::NGetRSP Class Reference


[NGetRSP](#) this file defines the messages for the nget action.

```
#include <gdcmNGetMessages.h>
```

Inheritance diagram for gdcm::network::NGetRSP:



Collaboration diagram for gdcm::network::NGetRSP:



Public Member Functions

- `std::vector< PresentationDataValue > ConstructPDVByDataSet` (const [DataSet](#) *inDataSet)

Public Member Functions inherited from [gdcm::network::BaseNormalizedMessage](#)

- virtual `~BaseNormalizedMessage` ()=default
- virtual `std::vector< PresentationDataValue > ConstructPDV` (const [ULConnection](#) &inConnection, const [BaseQuery](#) *inQuery)=0

10.208.1 Detailed Description

[NGetRSP](#) this file defines the messages for the nget action.

10.208.2 Member Function Documentation

10.208.2.1 ConstructPDVByDataSet()

```
std::vector< PresentationDataValue > gdcM::network::NGetRSP::ConstructPDVByDataSet (
    const DataSet * inDataSet)
```


The documentation for this class was generated from the following file:

- [gdcMNGetMessages.h](#)


10.209 gdcM::NoEvent Class Reference

```
#include <gdcMEvent.h>
```

Inheritance diagram for gdcM::NoEvent:



Collaboration diagram for gdcM::NoEvent:



Additional Inherited Members

Public Member Functions inherited from [gdcm::Event](#)

- [Event](#) ()
- [Event](#) (const [Event](#) &)
- virtual [~Event](#) ()
- virtual bool [CheckEvent](#) (const [Event](#) *) const =0
- virtual const char * [GetEventName](#) () const =0
- virtual [Event](#) * [MakeObject](#) () const =0
- void [operator=](#) (const [Event](#) &)=delete
- virtual void [Print](#) (std::ostream &os) const

10.209.1 Detailed Description

Define some common GDCM events

The documentation for this class was generated from the following file:

- [gdcmEvent.h](#)

10.210 gdcm::network::NormalizedMessageFactory Class Reference

```
#include <gdcmNormalizedMessageFactory.h>
```

Static Public Member Functions

- static std::vector< [PresentationDataValue](#) > [ConstructNAction](#) (const [ULConnection](#) &inConnection, const [BaseQuery](#) *inQuery)
- static std::vector< [PresentationDataValue](#) > [ConstructNCreate](#) (const [ULConnection](#) &inConnection, const [BaseQuery](#) *inQuery)
- static std::vector< [PresentationDataValue](#) > [ConstructNDelete](#) (const [ULConnection](#) &inConnection, const [BaseQuery](#) *inQuery)
- static std::vector< [PresentationDataValue](#) > [ConstructNEventReport](#) (const [ULConnection](#) &inConnection, const [BaseQuery](#) *inQuery)
- static std::vector< [PresentationDataValue](#) > [ConstructNGet](#) (const [ULConnection](#) &inConnection, const [BaseQuery](#) *inQuery)
- static std::vector< [PresentationDataValue](#) > [ConstructNSet](#) (const [ULConnection](#) &inConnection, const [BaseQuery](#) *inQuery)

10.210.1 Member Function Documentation

10.210.1.1 ConstructNAction()

```
std::vector< PresentationDataValue > gdcm::network::NormalizedMessageFactory::ConstructNAction (
    const ULConnection & inConnection,
    const BaseQuery * inQuery) [static]
```

10.210.1.2 ConstructNCreate()

```
std::vector< PresentationDataValue > gdcm::network::NormalizedMessageFactory::ConstructNCreate (
    const ULConnection & inConnection,
    const BaseQuery * inQuery) [static]
```

10.210.1.3 ConstructNDelete()

```
std::vector< PresentationDataValue > gdcm::network::NormalizedMessageFactory::ConstructNDelete (
    const ULConnection & inConnection,
    const BaseQuery * inQuery) [static]
```

10.210.1.4 ConstructNEventReport()

```
std::vector< PresentationDataValue > gdcm::network::NormalizedMessageFactory::ConstructNEvent↵
Report (
    const ULConnection & inConnection,
    const BaseQuery * inQuery) [static]
```

10.210.1.5 ConstructNGet()

```
std::vector< PresentationDataValue > gdcm::network::NormalizedMessageFactory::ConstructNGet (
    const ULConnection & inConnection,
    const BaseQuery * inQuery) [static]
```

10.210.1.6 ConstructNSet()

```
std::vector< PresentationDataValue > gdcm::network::NormalizedMessageFactory::ConstructNSet (
    const ULConnection & inConnection,
    const BaseQuery * inQuery) [static]
```

The documentation for this class was generated from the following file:

- [gdcmNormalizedMessageFactory.h](#)

10.211 gdcm::NormalizedNetworkFunctions Class Reference

Normalized Network Functions.

```
#include <gdcmNormalizedNetworkFunctions.h>
```

Static Public Member Functions

- static [BaseQuery](#) * [ConstructQuery](#) (const std::string &sopInstanceUID, const [DataSet](#) &queryds, [ENQueryType](#) queryType=[eCreateMMPS](#))
- static bool [NAction](#) (const char *remote, uint16_t portno, const [BaseQuery](#) *query, std::vector< [DataSet](#) > &retDataSets, const char *aetitle, const char *call)
- static bool [NCreate](#) (const char *remote, uint16_t portno, [BaseQuery](#) *query, std::vector< [DataSet](#) > &retDataSets, const char *aetitle, const char *call)
- static bool [NDelete](#) (const char *remote, uint16_t portno, const [BaseQuery](#) *query, std::vector< [DataSet](#) > &retDataSets, const char *aetitle, const char *call)
- static bool [NEventReport](#) (const char *remote, uint16_t portno, const [BaseQuery](#) *query, std::vector< [DataSet](#) > &retDataSets, const char *aetitle, const char *call)
- static bool [NGet](#) (const char *remote, uint16_t portno, const [BaseQuery](#) *query, std::vector< [DataSet](#) > &retDataSets, const char *aetitle, const char *call)
- static bool [NSet](#) (const char *remote, uint16_t portno, const [BaseQuery](#) *query, std::vector< [DataSet](#) > &retDataSets, const char *aetitle, const char *call)

10.211.1 Detailed Description

Normalized Network Functions.

These functions provide a generic API to the DICOM functions implemented in GDCM. Advanced users can use this code as a template for building their own versions of these functions (for instance, to provide progress bars or some other way of handling returned query information), but for most users, these functions should be sufficient to interface with a PACS to a local machine. Note that these functions are not contained within a static class or some other class-style interface, because multiple connections can be instantiated in the same program. The DICOM standard is much more function oriented rather than class oriented in this instance, so the design of this API reflects that functional approach. These functions implements the following SCU operations:

- N-EVENT-REPORT
- N-GET
- N-SET
- N-ACTION
- N-CREATE
- N-DELETE

10.211.2 Member Function Documentation

10.211.2.1 ConstructQuery()

```
BaseQuery * gdcn::NormalizedNetworkFunctions::ConstructQuery (
    const std::string & sopInstanceUID,
    const DataSet & queryds,
    ENQueryType queryType = eCreateMMPS) [static]
```

References [gdcn::eCreateMMPS](#).

10.211.2.2 NAction()

```
bool gdcmm::NormalizedNetworkFunctions::NAction (
    const char * remote,
    uint16_t portno,
    const BaseQuery * query,
    std::vector< DataSet > & retDataSets,
    const char * aetitle,
    const char * call) [static]
```

10.211.2.3 NCreate()

```
bool gdcmm::NormalizedNetworkFunctions::NCreate (
    const char * remote,
    uint16_t portno,
    BaseQuery * query,
    std::vector< DataSet > & retDataSets,
    const char * aetitle,
    const char * call) [static]
```

10.211.2.4 NDelete()

```
bool gdcmm::NormalizedNetworkFunctions::NDelete (
    const char * remote,
    uint16_t portno,
    const BaseQuery * query,
    std::vector< DataSet > & retDataSets,
    const char * aetitle,
    const char * call) [static]
```

10.211.2.5 NEventReport()

```
bool gdcmm::NormalizedNetworkFunctions::NEventReport (
    const char * remote,
    uint16_t portno,
    const BaseQuery * query,
    std::vector< DataSet > & retDataSets,
    const char * aetitle,
    const char * call) [static]
```

10.211.2.6 NGet()

```
bool gdcmm::NormalizedNetworkFunctions::NGet (
    const char * remote,
    uint16_t portno,
    const BaseQuery * query,
    std::vector< DataSet > & retDataSets,
    const char * aetitle,
    const char * call) [static]
```


10.211.2.7 NSet()

```
bool gdcm::NormalizedNetworkFunctions::NSet (
    const char * remote,
    uint16_t portno,
    const BaseQuery * query,
    std::vector< DataSet > & retDataSets,
    const char * aetitle,
    const char * call) [static]
```

The documentation for this class was generated from the following file:


- [gdcmNormalizedNetworkFunctions.h](#)

10.212 gdcm::network::NSetRQ Class Reference


[NSetRQ](#).

```
#include <gdcmNSetMessages.h>
```

Inheritance diagram for gdcm::network::NSetRQ:



Collaboration diagram for gdcm::network::NSetRQ:



Public Member Functions

- `std::vector< PresentationDataValue > ConstructPDV` (const [ULConnection](#) &inConnection, const [BaseQuery](#) *inQuery) override

Public Member Functions inherited from [gdcm::network::BaseNormalizedMessage](#)

- virtual `~BaseNormalizedMessage` ()=default

10.212.1 Detailed Description

[NSetRQ](#).

this file defines the messages for the nset action

10.212.2 Member Function Documentation

10.212.2.1 ConstructPDV()

```
std::vector< PresentationDataValue > gdcm::network::NSetRQ::ConstructPDV (
    const ULConnection & inConnection,
    const BaseQuery * inQuery) [override], [virtual]
```

Implements [gdcm::network::BaseNormalizedMessage](#).

The documentation for this class was generated from the following file:


- [gdcmNSetMessages.h](#)

10.213 gdcm::network::NSetRSP Class Reference


[NSetRSP](#) this file defines the messages for the nset action.

```
#include <gdcmNSetMessages.h>
```

Inheritance diagram for `gdcm::network::NSetRSP`:



Collaboration diagram for gdcm::network::NSetRSP:



Public Member Functions

- `std::vector< PresentationDataValue > ConstructPDVByDataSet` (const [DataSet](#) *inDataSet)

Public Member Functions inherited from [gdcm::network::BaseNormalizedMessage](#)

- virtual `~BaseNormalizedMessage` ()=default
- virtual `std::vector< PresentationDataValue > ConstructPDV` (const [ULConnection](#) &inConnection, const [BaseQuery](#) *inQuery)=0

10.213.1 Detailed Description

[NSetRSP](#) this file defines the messages for the nset action.

10.213.2 Member Function Documentation

10.213.2.1 ConstructPDVByDataSet()

```
std::vector< PresentationDataValue > gdcm::network::NSetRSP::ConstructPDVByDataSet (
    const DataSet * inDataSet)
```

The documentation for this class was generated from the following file:


- [gdcmNSetMessages.h](#)

10.214 gdcm::Object Class Reference

Object.

```
#include <gdcmObject.h>
```

Inheritance diagram for gdcm::Object:



Public Member Functions

- [Object](#) ()
 - [Object](#) (const [Object](#) &)
 - virtual [~Object](#) ()
 - void [operator=](#) (const [Object](#) &)
 - virtual void [Print](#) (std::ostream &) const
- Special requirement for copy/cstor, assignment operator.*

Protected Member Functions

- void [Register](#) ()
- void [UnRegister](#) ()

Friends

- `std::ostream & operator<< (std::ostream &os, const Object &obj)`
- `template<class ObjectType>`
`class SmartPointer`

10.214.1 Detailed Description

[Object](#).

Note

main superclass for object that want to use [SmartPointer](#) invasive ref counting system

See also

[SmartPointer](#)

10.214.2 Constructor & Destructor Documentation

10.214.2.1 [Object\(\)](#) [1/2]

```
gdcmm::Object::Object () [inline]
```

Referenced by [gdcmm::LookupTable::LookupTable\(\)](#), [Object\(\)](#), [operator<<](#), [operator=\(\)](#), and [SmartPointer](#).

10.214.2.2 [~Object\(\)](#)

```
virtual gdcmm::Object::~~Object () [inline], [virtual]
```

References [gdcmm_forced_assert](#).

10.214.2.3 [Object\(\)](#) [2/2]

```
gdcmm::Object::Object (  
    const Object & ) [inline]
```

Special requirement for copy/cstor, assignment operator.

References [Object\(\)](#).

10.214.3 Member Function Documentation

10.214.3.1 operator=()

```
void gdcM::Object::operator= (
    const Object & ) [inline]
```

References [Object\(\)](#).

10.214.3.2 Print()

```
virtual void gdcM::Object::Print (
    std::ostream & ) const [inline], [virtual]
```

Reimplemented in [gdcM::BaseQuery](#), [gdcM::Bitmap](#), [gdcM::ByteValue](#), [gdcM::Curve](#), [gdcM::Image](#), [gdcM::LookupTable](#), [gdcM::Overlay](#), [gdcM::Pixmap](#), [gdcM::Scanner2](#), [gdcM::Scanner](#), [gdcM::SegmentedPaletteColorLookupTable](#), [gdcM::SequenceOfFragments](#), [gdcM::SequenceOfItems](#), [gdcM::StrictScanner2](#), and [gdcM::StrictScanner](#).

Examples

[ReadAndDumpDICOMDIR.cxx](#).

Referenced by [gdcM::DataElement::operator<<](#), and [operator<<](#).

10.214.3.3 Register()

```
void gdcM::Object::Register () [inline], [protected]
```

References [gdcM_assert](#).

10.214.3.4 UnRegister()

```
void gdcM::Object::UnRegister () [inline], [protected]
```

References [gdcM_assert](#).

10.214.4 Friends And Related Symbol Documentation

10.214.4.1 operator<<

```
std::ostream & operator<< (
    std::ostream & os,
    const Object & obj) [friend]
```

References [Object\(\)](#), and [Print\(\)](#).

Referenced by [SmartPointer](#).

10.214.4.2 SmartPointer

```
template<class ObjectType>
friend class SmartPointer [friend]
```

References [Object\(\)](#), [operator<<](#), and [SmartPointer](#).

Referenced by [gdcm::Segment::AddSurface\(\)](#), [gdcm::Segment::GetSurface\(\)](#), [gdcm::Bitmap::SetLUT\(\)](#), [gdcm::Surface::SetMeshPrimitive](#) and [SmartPointer](#).


The documentation for this class was generated from the following file:

- [gdcmObject.h](#)


10.215 gdcm::OpenSSLCryptoFactory Class Reference

```
#include <gdcmOpenSSLCryptoFactory.h>
```

Inheritance diagram for gdcm::OpenSSLCryptoFactory:



Collaboration diagram for gdcm::OpenSSLCryptoFactory:



Public Member Functions

- [OpenSSLCryptoFactory](#) ([CryptoLib](#) id)
- [CryptographicMessageSyntax](#) * [CreateCMSProvider](#) ()

Protected Member Functions

- void [InitOpenSSL](#) ()

Protected Member Functions inherited from [gdcm::CryptoFactory](#)

- [CryptoFactory](#) ()=default
- [CryptoFactory](#) ([CryptoLib](#) id)
- [~CryptoFactory](#) ()=default

Additional Inherited Members

Public Types inherited from [gdcm::CryptoFactory](#)

- enum [CryptoLib](#) {
 [DEFAULT](#) = 0 ,
 [OPENSSL](#) = 1 ,
 [CAPI](#) = 2 ,
 [OPENSSL7](#) = 3 }

Static Public Member Functions inherited from [gdcm::CryptoFactory](#)

- static [CryptoFactory](#) * [GetFactoryInstance](#) ([CryptoLib](#) id=DEFAULT)

10.215.1 Constructor & Destructor Documentation

10.215.1.1 [OpenSSLCryptoFactory](#)()

```
gdcm::OpenSSLCryptoFactory::OpenSSLCryptoFactory (  
    CryptoLib id) [inline]
```

References [gdcm::CryptoFactory::CryptoFactory\(\)](#), and [gdcmDebugMacro](#).

Referenced by [InitOpenSSL\(\)](#).

10.215.2 Member Function Documentation

10.215.2.1 CreateCMSProvider()

`CryptographicMessageSyntax * gdcm::OpenSSLCryptoFactory::CreateCMSProvider () [inline], [virtual]`

Implements [gdcm::CryptoFactory](#).

References [InitOpenSSL\(\)](#).

10.215.2.2 InitOpenSSL()

`void gdcm::OpenSSLCryptoFactory::InitOpenSSL () [protected]`

References [OpenSSLCryptoFactory\(\)](#).

Referenced by [CreateCMSProvider\(\)](#).


The documentation for this class was generated from the following file:

- [gdcmOpenSSLCryptoFactory.h](#)


10.216 gdcm::OpenSSLCryptographicMessageSyntax Class Reference

```
#include <gdcmOpenSSLCryptographicMessageSyntax.h>
```

Inheritance diagram for `gdcm::OpenSSLCryptographicMessageSyntax`:



Collaboration diagram for `gdcm::OpenSSLCryptographicMessageSyntax`:



Public Member Functions

- [OpenSSLCryptographicMessageSyntax](#) ()
- [~OpenSSLCryptographicMessageSyntax](#) ()
- bool [Decrypt](#) (char *output, size_t &outlen, const char *array, size_t len) const
decrypt content from a PKCS#7 envelopedData structure
- bool [Encrypt](#) (char *output, size_t &outlen, const char *array, size_t len) const
create a CMS envelopedData structure
- [CipherTypes](#) [GetCipherType](#) () const
- bool [ParseCertificateFile](#) (const char *filename)
- bool [ParseKeyFile](#) (const char *filename)
- void [SetCipherType](#) ([CipherTypes](#) type)
- bool [SetPassword](#) (const char *pass, size_t passLen)

Public Member Functions inherited from [gdcm::CryptographicMessageSyntax](#)

- [CryptographicMessageSyntax](#) ()=default
- [CryptographicMessageSyntax](#) (const [CryptographicMessageSyntax](#) &)=delete
- virtual [~CryptographicMessageSyntax](#) ()=default
- void [operator=](#) (const [CryptographicMessageSyntax](#) &)=delete

Additional Inherited Members

Public Types inherited from [gdcm::CryptographicMessageSyntax](#)

- enum [CipherTypes](#) {
 [DES3_CIPHER](#) ,
 [AES128_CIPHER](#) ,
 [AES192_CIPHER](#) ,
 [AES256_CIPHER](#) }

10.216.1 Constructor & Destructor Documentation

10.216.1.1 OpenSSLCryptographicMessageSyntax()

```
gdcmm::OpenSSLCryptographicMessageSyntax::OpenSSLCryptographicMessageSyntax ()
```

Referenced by [Decrypt\(\)](#).

10.216.1.2 ~OpenSSLCryptographicMessageSyntax()

```
gdcmm::OpenSSLCryptographicMessageSyntax::~~OpenSSLCryptographicMessageSyntax ()
```

10.216.2 Member Function Documentation

10.216.2.1 Decrypt()

```
bool gdcmm::OpenSSLCryptographicMessageSyntax::Decrypt (
    char * output,
    size_t & outlen,
    const char * array,
    size_t len) const [virtual]
```

decrypt content from a PKCS#7 envelopedData structure

Implements [gdcmm::CryptographicMessageSyntax](#).

References [OpenSSLCryptographicMessageSyntax\(\)](#).

10.216.2.2 Encrypt()

```
bool gdcmm::OpenSSLCryptographicMessageSyntax::Encrypt (
    char * output,
    size_t & outlen,
    const char * array,
    size_t len) const [virtual]
```

create a CMS envelopedData structure

Implements [gdcmm::CryptographicMessageSyntax](#).

10.216.2.3 GetCipherType()

```
CipherTypes gdcmm::OpenSSLCryptographicMessageSyntax::GetCipherType () const [virtual]
```

Implements [gdcmm::CryptographicMessageSyntax](#).

10.216.2.4 ParseCertificateFile()

```
bool gdcM::OpenSSLCryptographicMessageSyntax::ParseCertificateFile (
    const char * filename) [virtual]
```

Implements [gdcM::CryptographicMessageSyntax](#).

10.216.2.5 ParseKeyFile()

```
bool gdcM::OpenSSLCryptographicMessageSyntax::ParseKeyFile (
    const char * filename) [virtual]
```

Implements [gdcM::CryptographicMessageSyntax](#).

10.216.2.6 SetCipherType()

```
void gdcM::OpenSSLCryptographicMessageSyntax::SetCipherType (
    CipherTypes type) [virtual]
```

Set Cipher [Type](#). Default is: AES256_CIPHER

Implements [gdcM::CryptographicMessageSyntax](#).

10.216.2.7 SetPassword()

```
bool gdcM::OpenSSLCryptographicMessageSyntax::SetPassword (
    const char * pass,
    size_t passLen) [virtual]
```

Implements [gdcM::CryptographicMessageSyntax](#).


The documentation for this class was generated from the following file:

- [gdcMOpenSSLCryptographicMessageSyntax.h](#)


10.217 gdcmm::OpenSSLP7CryptoFactory Class Reference

```
#include <gdcmmOpenSSLP7CryptoFactory.h>
```

Inheritance diagram for gdcmm::OpenSSLP7CryptoFactory:



Collaboration diagram for gdcmm::OpenSSLP7CryptoFactory:



Public Member Functions

- [OpenSSLP7CryptoFactory](#) ([CryptoLib](#) id)
- [CryptographicMessageSyntax](#) * [CreateCMSProvider](#) ()

Additional Inherited Members

Public Types inherited from [gdcmm::CryptoFactory](#)

- enum [CryptoLib](#) {
 [DEFAULT](#) = 0 ,
 [OPENSSL](#) = 1 ,
 [CAPI](#) = 2 ,
 [OPENSSLP7](#) = 3 }

Static Public Member Functions inherited from [gdcmm::CryptoFactory](#)

- static [CryptoFactory](#) * [GetFactoryInstance](#) ([CryptoLib](#) id=DEFAULT)

Protected Member Functions inherited from [gdcmm::CryptoFactory](#)

- [CryptoFactory](#) ()=default
- [CryptoFactory](#) ([CryptoLib](#) id)
- [~CryptoFactory](#) ()=default

10.217.1 Constructor & Destructor Documentation

10.217.1.1 [OpenSSL7CryptoFactory\(\)](#)

```
gdcmm::OpenSSL7CryptoFactory::OpenSSL7CryptoFactory (  
    CryptoLib id) [inline]
```

References [gdcmm::CryptoFactory::CryptoFactory\(\)](#), and [gdcmmDebugMacro](#).

10.217.2 Member Function Documentation

10.217.2.1 [CreateCMSProvider\(\)](#)

```
CryptographicMessageSyntax * gdcmm::OpenSSL7CryptoFactory::CreateCMSProvider () [inline], [virtual]
```

Implements [gdcmm::CryptoFactory](#).


The documentation for this class was generated from the following file:

- [gdcmmOpenSSL7CryptoFactory.h](#)


10.218 gdcmm::OpenSSL7CryptographicMessageSyntax Class Reference

```
#include <gdcmmOpenSSL7CryptographicMessageSyntax.h>
```

Inheritance diagram for gdcmm::OpenSSL7CryptographicMessageSyntax:



Collaboration diagram for gdcmm::OpenSSL7CryptographicMessageSyntax:



Public Member Functions

- [OpenSSL7CryptographicMessageSyntax](#) ()
- [~OpenSSL7CryptographicMessageSyntax](#) ()
- bool [Decrypt](#) (char *output, size_t &outlen, const char *array, size_t len) const
decrypt content from a PKCS#7 envelopedData structure
- bool [Encrypt](#) (char *output, size_t &outlen, const char *array, size_t len) const
create a PKCS#7 envelopedData structure
- [CipherTypes GetCipherType](#) () const
- bool [ParseCertificateFile](#) (const char *filename)
- bool [ParseKeyFile](#) (const char *filename)
- void [SetCipherType](#) ([CipherTypes](#) type)
- bool [SetPassword](#) (const char *, size_t)

Public Member Functions inherited from [gdcmm::CryptographicMessageSyntax](#)

- [CryptographicMessageSyntax](#) ()=default
- [CryptographicMessageSyntax](#) (const [CryptographicMessageSyntax](#) &)=delete
- virtual [~CryptographicMessageSyntax](#) ()=default
- void [operator=](#) (const [CryptographicMessageSyntax](#) &)=delete

Additional Inherited Members

Public Types inherited from [gdcmm::CryptographicMessageSyntax](#)

- enum [CipherTypes](#) {
[DES3_CIPHER](#) ,
[AES128_CIPHER](#) ,
[AES192_CIPHER](#) ,
[AES256_CIPHER](#) }

10.218.1 Detailed Description

Class for [CryptographicMessageSyntax](#) encryption. This is just a simple wrapper around openssl PKCS7_encrypt functionalities

See online documentation http://www.openssl.org/docs/crypto/PKCS7_encrypt.html

10.218.2 Constructor & Destructor Documentation

10.218.2.1 OpenSSLP7CryptographicMessageSyntax()

```
gdcmm::OpenSSLP7CryptographicMessageSyntax::OpenSSLP7CryptographicMessageSyntax ()
```

Referenced by [Decrypt\(\)](#).

10.218.2.2 ~OpenSSLP7CryptographicMessageSyntax()

```
gdcmm::OpenSSLP7CryptographicMessageSyntax::~~OpenSSLP7CryptographicMessageSyntax ()
```

10.218.3 Member Function Documentation

10.218.3.1 Decrypt()

```
bool gdcmm::OpenSSLP7CryptographicMessageSyntax::Decrypt (
    char * output,
    size_t & outlen,
    const char * array,
    size_t len) const [virtual]
```

decrypt content from a PKCS#7 envelopedData structure

Implements [gdcmm::CryptographicMessageSyntax](#).

References [OpenSSLP7CryptographicMessageSyntax\(\)](#).

10.218.3.2 Encrypt()

```
bool gdcmm::OpenSSLP7CryptographicMessageSyntax::Encrypt (
    char * output,
    size_t & outlen,
    const char * array,
    size_t len) const [virtual]
```

create a PKCS#7 envelopedData structure

Implements [gdcmm::CryptographicMessageSyntax](#).

10.218.3.3 GetCipherType()

```
CipherTypes gdcmm::OpenSSLP7CryptographicMessageSyntax::GetCipherType () const [virtual]
```

Implements [gdcmm::CryptographicMessageSyntax](#).

10.218.3.4 ParseCertificateFile()

```
bool gdcmm::OpenSSLP7CryptographicMessageSyntax::ParseCertificateFile (
    const char * filename) [virtual]
```

Implements [gdcmm::CryptographicMessageSyntax](#).

10.218.3.5 ParseKeyFile()

```
bool gdcmm::OpenSSLP7CryptographicMessageSyntax::ParseKeyFile (
    const char * filename) [virtual]
```

Implements [gdcmm::CryptographicMessageSyntax](#).

10.218.3.6 SetCipherType()

```
void gdcmm::OpenSSLP7CryptographicMessageSyntax::SetCipherType (
    CipherTypes type) [virtual]
```

Set Cipher [Type](#). Default is: AES256_CIPHER

Implements [gdcmm::CryptographicMessageSyntax](#).

10.218.3.7 SetPassword()

```
bool gdcM::OpenSSL7CryptographicMessageSyntax::SetPassword (
    const char * ,
    size_t ) [inline], [virtual]
```

Implements [gdcM::CryptographicMessageSyntax](#).

References [gdcMWarningMacro](#).

The documentation for this class was generated from the following file:

- [gdcMOpenSSL7CryptographicMessageSyntax.h](#)

10.219 gdcM::Orientation Class Reference

class to handle [Orientation](#)

```
#include <gdcMOrientation.h>
```

Public Types

- enum [OrientationType](#) {
[UNKNOWN](#) ,
[AXIAL](#) ,
[CORONAL](#) ,
[SAGITTAL](#) ,
[OBLIQUE](#) }

Public Member Functions

- [Orientation](#) ()
- [~Orientation](#) ()=default
- void [Print](#) (std::ostream &) const
Print.

Static Public Member Functions

- static const char * [GetLabel](#) ([OrientationType](#) type)
Return the label of an [Orientation](#).
- static double [GetObliquityThresholdCosineValue](#) ()
- static [OrientationType](#) [GetType](#) (const double dircos[6])
- static void [SetObliquityThresholdCosineValue](#) (double val)
ObliquityThresholdCosineValue stuff.

Static Protected Member Functions

- static char [GetMajorAxisFromPatientRelativeDirectionCosine](#) (double x, double y, double z)

Friends

- std::ostream & [operator<<](#) (std::ostream &_os, const [Orientation](#) &o)

10.219.1 Detailed Description

class to handle [Orientation](#)

10.219.2 Member Enumeration Documentation

10.219.2.1 OrientationType

```
enum gdcm::Orientation::OrientationType
```

Enumerator

UNKNOWN	
AXIAL	
CORONAL	
SAGITTAL	
OBLIQUE	

Examples

[FixOrientation.cxx](#).

10.219.3 Constructor & Destructor Documentation

10.219.3.1 Orientation()

```
gdcm::Orientation::Orientation ()
```

Referenced by [operator<<](#).

10.219.3.2 ~Orientation()

```
gdcm::Orientation::~~Orientation () [default]
```

10.219.4 Member Function Documentation

10.219.4.1 GetLabel()

```
const char * gdcM::Orientation::GetLabel (
    OrientationType type) [static]
```

Return the label of an [Orientation](#).

Examples

[FixOrientation.cxx](#).

10.219.4.2 GetMajorAxisFromPatientRelativeDirectionCosine()

```
char gdcM::Orientation::GetMajorAxisFromPatientRelativeDirectionCosine (
    double x,
    double y,
    double z) [static], [protected]
```

10.219.4.3 GetObliquityThresholdCosineValue()

```
double gdcM::Orientation::GetObliquityThresholdCosineValue () [static]
```

10.219.4.4 GetType()

```
OrientationType gdcM::Orientation::GetType (
    const double dircos[6]) [static]
```

Return the type of orientation from a direction cosines Input is an array of 6 double

Examples

[FixOrientation.cxx](#).

10.219.4.5 Print()

```
void gdcM::Orientation::Print (
    std::ostream & ) const
```

Print.

Referenced by [operator<<](#).

10.219.4.6 SetObliquityThresholdCosineValue()

```
void gdcm::Orientation::SetObliquityThresholdCosineValue (
    double val) [static]
```

ObliquityThresholdCosineValue stuff.

10.219.5 Friends And Related Symbol Documentation

10.219.5.1 operator<<

```
std::ostream & operator<< (
    std::ostream & _os,
    const Orientation & o) [friend]
```

References [Orientation\(\)](#), and [Print\(\)](#).

The documentation for this class was generated from the following file:


- [gdcmOrientation.h](#)

10.220 gdcm::Overlay Class Reference


[Overlay](#) class.

```
#include <gdcmOverlay.h>
```

Inheritance diagram for gdcm::Overlay:



Collaboration diagram for `gdcm::Overlay`:



Public Types

- enum `OverlayType` {
 `Invalid` = 0 ,
 `Graphics` = 1 ,
 `ROI` = 2 }

Public Member Functions

- `Overlay ()`
- `Overlay (Overlay const &ov)`
- `~Overlay ()` override
- void `Decompress (std::ostream &os) const`
 Decode the internal OverlayData (packed bits) into unpacked representation.
- unsigned short `GetBitPosition () const`
 return bit position
- unsigned short `GetBitsAllocated () const`
 return bits allocated
- unsigned short `GetColumns () const`
 get columns
- const char * `GetDescription () const`
 get description
- unsigned short `GetGroup () const`
 Get Group number.
- const signed short * `GetOrigin () const`
 get origin
- const `ByteValue` & `GetOverlayData () const`
- unsigned short `GetRows () const`
 get rows
- const char * `GetType () const`
 get type
- `OverlayType` `GetTypeAsEnum () const`

- bool [GetUnpackBuffer](#) (char *buffer, size_t len) const
- size_t [GetUnpackBufferLength](#) () const
- bool [GrabOverlayFromPixelData](#) ([DataSet](#) const &ds)
- bool [IsEmpty](#) () const
 - Return whether or not the [Overlay](#) is empty:*
- bool [IsInPixelData](#) () const
 - return if the [Overlay](#) is stored in the pixel data or not*
- void [IsInPixelData](#) (bool b)
 - Set whether or no the OverlayData is in the Pixel Data:*
- bool [IsZero](#) () const
 - return true if all bits are set to 0*
- [Overlay](#) & [operator=](#) ([Overlay](#) const &ov)
- void [Print](#) (std::ostream &) const override
 - Print.*
- void [SetBitPosition](#) (unsigned short bitposition)
 - set bit position*
- void [SetBitsAllocated](#) (unsigned short bitsallocated)
 - set bits allocated*
- void [SetColumns](#) (unsigned short columns)
 - set columns*
- void [SetDescription](#) (const char *description)
 - set description*
- void [SetFrameOrigin](#) (unsigned short frameorigin)
 - set frame origin*
- void [SetGroup](#) (unsigned short group)
 - Set Group number.*
- void [SetNumberOfFrames](#) (unsigned int numberofframes)
 - set number of frames*
- void [SetOrigin](#) (const signed short origin[2])
 - set origin*
- void [SetOverlay](#) (const char *array, size_t length)
 - set overlay from byte array + length*
- void [SetRows](#) (unsigned short rows)
 - set rows*
- void [SetType](#) (const char *type)
 - set type*
- void [Update](#) (const [DataElement](#) &de)
 - Update overlay from data element de:*

Public Member Functions inherited from [gdcm::Object](#)

- [Object](#) ()
- [Object](#) (const [Object](#) &)
 - Special requirement for copy/cstor, assignment operator.*
- virtual [~Object](#) ()
- void [operator=](#) (const [Object](#) &)

Static Public Member Functions

- static const char * [GetOverlayTypeAsString](#) ([OverlayType](#) ot)
- static [OverlayType](#) [GetOverlayTypeFromString](#) (const char *)

Additional Inherited Members

Protected Member Functions inherited from [gdcm::Object](#)

- void [Register](#) ()
- void [UnRegister](#) ()

10.220.1 Detailed Description

[Overlay](#) class.

Note

see [AreOverlaysInPixelData](#)

Todo Is there actually any way to recognize an overlay ? On images with multiple overlay I do not see any way to differentiate them (other than the group tag).

Example:

10.220.2 Member Enumeration Documentation

10.220.2.1 OverlayType

```
enum gdcm::Overlay::OverlayType
```

Enumerator

Invalid	
Graphics	
ROI	

10.220.3 Constructor & Destructor Documentation

10.220.3.1 Overlay() [1/2]

```
gdcm::Overlay::Overlay ()
```

Referenced by [Overlay\(\)](#), and [operator=\(\)](#).

10.220.3.2 ~Overlay()

```
gdcm::Overlay::~~Overlay () [override]
```

10.220.3.3 Overlay() [2/2]

```
gdcm::Overlay::Overlay (  
    Overlay const & ov)
```

References [Overlay\(\)](#).

10.220.4 Member Function Documentation

10.220.4.1 Decompress()

```
void gdcm::Overlay::Decompress (  
    std::ostream & os) const
```

Decode the internal OverlayData (packed bits) into unpacked representation.

10.220.4.2 GetBitPosition()

```
unsigned short gdcm::Overlay::GetBitPosition () const
```

return bit position

10.220.4.3 GetBitsAllocated()

```
unsigned short gdcm::Overlay::GetBitsAllocated () const
```

return bits allocated

10.220.4.4 GetColumns()

```
unsigned short gdcm::Overlay::GetColumns () const
```

get columns

10.220.4.5 GetDescription()

```
const char * gdcm::Overlay::GetDescription () const
```

get description

10.220.4.6 GetGroup()

```
unsigned short gdcm::Overlay::GetGroup () const
```

Get Group number.

10.220.4.7 GetOrigin()

```
const signed short * gdcm::Overlay::GetOrigin () const
```

get origin

10.220.4.8 GetOverlayData()

```
const ByteValue & gdcm::Overlay::GetOverlayData () const
```

Return the [Overlay](#) Data as [ByteValue](#): Not thread safe

10.220.4.9 GetOverlayTypeAsString()

```
const char * gdcm::Overlay::GetOverlayTypeAsString (  
    OverlayType ot) [static]
```

10.220.4.10 GetOverlayTypeFromString()

```
OverlayType gdcm::Overlay::GetOverlayTypeFromString (  
    const char * ) [static]
```

10.220.4.11 GetRows()

```
unsigned short gdcm::Overlay::GetRows () const
```

get rows

10.220.4.12 GetType()

```
const char * gdcm::Overlay::GetType () const
```

get type

10.220.4.13 GetTypeAsEnum()

```
OverlayType gdcm::Overlay::GetTypeAsEnum () const
```

10.220.4.14 GetUnpackBuffer()

```
bool gdcm::Overlay::GetUnpackBuffer (
    char * buffer,
    size_t len) const
```

Retrieve the unpack buffer for [Overlay](#). This is an error if the size is below [GetUnpackBufferLength\(\)](#)

10.220.4.15 GetUnpackBufferLength()

```
size_t gdcm::Overlay::GetUnpackBufferLength () const
```

Retrieve the size of the buffer needed to hold the [Overlay](#) as specified by Col & Row parameters

10.220.4.16 GrabOverlayFromPixelData()

```
bool gdcm::Overlay::GrabOverlayFromPixelData (
    DataSet const & ds)
```

10.220.4.17 IsEmpty()

```
bool gdcm::Overlay::IsEmpty () const
```

Return whether or not the [Overlay](#) is empty:

10.220.4.18 IsInPixelData() [1/2]

```
bool gdcm::Overlay::IsInPixelData () const
```

return if the [Overlay](#) is stored in the pixel data or not

10.220.4.19 IsInPixelData() [2/2]

```
void gdcm::Overlay::IsInPixelData (
    bool b)
```

Set whether or no the OverlayData is in the Pixel Data:

10.220.4.20 IsZero()

```
bool gdcm::Overlay::IsZero () const
```

return true if all bits are set to 0

10.220.4.21 operator=()

```
Overlay & gdcm::Overlay::operator= (  
    Overlay const & ov)
```

References [Overlay\(\)](#).

10.220.4.22 Print()

```
void gdcm::Overlay::Print (  
    std::ostream & ) const [override], [virtual]
```

Print.

Reimplemented from [gdcm::Object](#).

10.220.4.23 SetBitPosition()

```
void gdcm::Overlay::SetBitPosition (  
    unsigned short bitposition)
```

set bit position

10.220.4.24 SetBitsAllocated()

```
void gdcm::Overlay::SetBitsAllocated (  
    unsigned short bitsallocated)
```

set bits allocated

10.220.4.25 SetColumns()

```
void gdcm::Overlay::SetColumns (  
    unsigned short columns)
```

set columns

10.220.4.26 SetDescription()

```
void gdcmm::Overlay::SetDescription (
    const char * description)
```

set description

10.220.4.27 SetFrameOrigin()

```
void gdcmm::Overlay::SetFrameOrigin (
    unsigned short frameorigin)
```

set frame origin

10.220.4.28 SetGroup()

```
void gdcmm::Overlay::SetGroup (
    unsigned short group)
```

Set Group number.

10.220.4.29 SetNumberOfFrames()

```
void gdcmm::Overlay::SetNumberOfFrames (
    unsigned int numberofframes)
```

set number of frames

10.220.4.30 SetOrigin()

```
void gdcmm::Overlay::SetOrigin (
    const signed short origin[2])
```

set origin

10.220.4.31 SetOverlay()

```
void gdcmm::Overlay::SetOverlay (
    const char * array,
    size_t length)
```

set overlay from byte array + length

10.220.4.32 SetRows()

```
void gdcM::Overlay::SetRows (
    unsigned short rows)
```

set rows

10.220.4.33 SetType()

```
void gdcM::Overlay::SetType (
    const char * type)
```

set type

10.220.4.34 Update()

```
void gdcM::Overlay::Update (
    const DataElement & de)
```

Update overlay from data element de:

The documentation for this class was generated from the following file:


- [gdcMOverlay.h](#)

10.221 gdcM::ParseException Class Reference


[ParseException](#) Standard exception handling object.

```
#include <gdcMParseException.h>
```

Inheritance diagram for gdcM::ParseException:



Collaboration diagram for gdcm::ParseException:



Public Member Functions

- [ParseException](#) ()=default
- [ParseException](#) (const [ParseException](#) &orig)
- [~ParseException](#) () override throw ()
- const [DataElement](#) & [GetLastElement](#) () const
- [ParseException](#) & [operator=](#) (const [ParseException](#) &orig)
- void [SetLastElement](#) (const [DataElement](#) &de)

Public Member Functions inherited from [gdcm::Exception](#)

- [Exception](#) (const char *desc="None", const char *file=__FILE__, unsigned int lineNumber=__LINE__, const char *func="")
- [~Exception](#) () override throw ()
- const char * [GetDescription](#) () const
Return the Description.
- const char * [what](#) () const override throw ()
what implementation

10.221.1 Detailed Description

[ParseException](#) Standard exception handling object.

10.221.2 Constructor & Destructor Documentation

10.221.2.1 ParseException() [1/2]

```
gdcm::ParseException::ParseException () [default]
```

Referenced by [ParseException\(\)](#), and [operator=\(\)](#).

10.221.2.2 ~ParseException()

```
gdcm::ParseException::~~ParseException () throw ( ) [inline], [override]
```

10.221.2.3 ParseException() [2/2]

```
gdcm::ParseException::ParseException (
    const ParseException & orig) [inline]
```

References [gdcm::Exception::Exception\(\)](#), and [ParseException\(\)](#).

10.221.3 Member Function Documentation

10.221.3.1 GetLastElement()

```
const DataElement & gdcm::ParseException::GetLastElement () const [inline]
```

10.221.3.2 operator=()

```
ParseException & gdcm::ParseException::operator= (
    const ParseException & orig) [inline]
```

Assignment operator.

References [ParseException\(\)](#).

10.221.3.3 SetLastElement()

```
void gdcm::ParseException::SetLastElement (
    const DataElement & de) [inline]
```

Equivalence operator.

Referenced by [gdcm::BasicOffsetTable::Read\(\)](#), [gdcm::Fragment::ReadBacktrack\(\)](#), and [gdcm::Fragment::ReadValue\(\)](#).

The documentation for this class was generated from the following file:

- [gdcmParseException.h](#)

10.222 gdcm::Parser Class Reference

[Parser](#) ala XML_Parser from expat (SAX)

```
#include <gdcmParser.h>
```

Public Types

- typedef void(* [EndElementHandler](#)) (void *userData, const [Tag](#) &name)
- enum [ErrorType](#) {
 [NoError](#) ,
 [NoMemoryError](#) ,
 [SyntaxError](#) ,
 [NoElementsError](#) ,
 [TagMismatchError](#) ,
 [DuplicateAttributeError](#) ,
 [JunkAfterDocElementError](#) ,
 [UndefinedEntityError](#) ,
 [UnexpectedStateError](#) }
- typedef void(* [StartElementHandler](#)) (void *userData, const [Tag](#) &tag, const char *atts[])

Public Member Functions

- [Parser](#) ()
- [~Parser](#) ()
- unsigned long [GetCurrentByteIndex](#) () const
- [ErrorType](#) [GetErrorCode](#) () const
- void * [GetUserData](#) () const
- bool [Parse](#) (const char *s, int len, bool isFinal)
- void [SetElementHandler](#) ([StartElementHandler](#) start, [EndElementHandler](#) end)
- void [SetUserData](#) (void *userData)

Static Public Member Functions

- static const char * [GetErrorString](#) ([ErrorType](#) const &err)

Protected Member Functions

- char * [GetBuffer](#) (int len)
- bool [ParseBuffer](#) (int len, bool isFinal)
- [ErrorType](#) [Process](#) ()

10.222.1 Detailed Description

[Parser](#) ala XML_Parser from expat (SAX)

Detailed description here

Note

Simple API for DICOM

10.222.2 Member Typedef Documentation

10.222.2.1 EndElementHandler

```
typedef void(* gdcM::Parser::EndElementHandler) (void *userData, const Tag &name)
```

10.222.2.2 StartElementHandler

```
typedef void(* gdcM::Parser::StartElementHandler) (void *userData, const Tag &tag, const char  
*atts[ ])
```

10.222.3 Member Enumeration Documentation

10.222.3.1 ErrorType

```
enum gdcM::Parser::ErrorType
```

Enumerator

NoError	
NoMemoryError	
SyntaxError	
NoElementsError	
TagMismatchError	
DuplicateAttributeError	
JunkAfterDocElementError	
UndefinedEntityError	
UnexpectedStateError	

10.222.4 Constructor & Destructor Documentation

10.222.4.1 Parser()

```
gdcm::Parser::Parser () [inline]
```

References [NoError](#).

10.222.4.2 ~Parser()

```
gdcm::Parser::~~Parser () [inline]
```

10.222.5 Member Function Documentation

10.222.5.1 GetBuffer()

```
char * gdcm::Parser::GetBuffer (
    int len) [protected]
```

10.222.5.2 GetCurrentByteIndex()

```
unsigned long gdcm::Parser::GetCurrentByteIndex () const
```

10.222.5.3 GetErrorCode()

```
ErrorType gdcm::Parser::GetErrorCode () const
```

10.222.5.4 GetErrorString()

```
const char * gdcm::Parser::GetErrorString (
    ErrorType const & err) [static]
```

10.222.5.5 GetUserData()

```
void * gdcm::Parser::GetUserData () const
```

10.222.5.6 Parse()

```
bool gdcm::Parser::Parse (
    const char * s,
    int len,
    bool isFinal)
```

10.222.5.7 ParseBuffer()

```
bool gdcM::Parser::ParseBuffer (
    int len,
    bool isFinal) [protected]
```

10.222.5.8 Process()

```
ErrorType gdcM::Parser::Process () [protected]
```

10.222.5.9 SetElementHandler()

```
void gdcM::Parser::SetElementHandler (
    StartElementHandler start,
    EndElementHandler end)
```

10.222.5.10 SetUserData()

```
void gdcM::Parser::SetUserData (
    void * userData)
```

The documentation for this class was generated from the following file:

- [gdcMParser.h](#)

10.223 gdcM::Patient Class Reference

See PS 3.3 - 2007 DICOM MODEL OF THE REAL-WORLD, p 54.

```
#include <gdcMPatient.h>
```

Public Member Functions

- [Patient](#) ()=default

10.223.1 Detailed Description

See PS 3.3 - 2007 DICOM MODEL OF THE REAL-WORLD, p 54.

10.223.2 Constructor & Destructor Documentation

10.223.2.1 Patient()

```
gdcm::Patient::Patient () [default]
```

The documentation for this class was generated from the following file:


- [gdcmPatient.h](#)

10.224 gdcm::network::PDataTFPDU Class Reference


[PDataTFPDU](#).

```
#include <gdcmPDataTFPDU.h>
```

Inheritance diagram for gdcm::network::PDataTFPDU:



Collaboration diagram for gdcm::network::PDataTFPDU:



Public Types

- typedef std::vector< [PresentationDataValue](#) >::size_type [SizeType](#)

Public Member Functions

- [PDataTFPDU](#) ()
- void [AddPresentationDataValue](#) ([PresentationDataValue](#) const &pdv)
- [SizeType](#) [GetNumberOfPresentationDataValues](#) () const
- [PresentationDataValue](#) const & [GetPresentationDataValue](#) ([SizeType](#) i) const
- bool [IsLastFragment](#) () const override
- void [Print](#) (std::ostream &os) const override
- std::istream & [Read](#) (std::istream &is) override
- size_t [Size](#) () const override
- const std::ostream & [Write](#) (std::ostream &os) const override

Public Member Functions inherited from [gdcm::network::BasePDU](#)

- virtual [~BasePDU](#) ()=default

Protected Member Functions

- std::istream & [ReadInfo](#) (std::istream &is, std::ostream &os)

10.224.1 Detailed Description

[PDataTFPDU](#).

[Table](#) 9-22 P-DATA-TF PDU FIELDS

10.224.2 Member Typedef Documentation

10.224.2.1 SizeType

```
typedef std::vector<PresentationDataValue>::size_type gdcm::network::PDataTFPDU::SizeType
```

10.224.3 Constructor & Destructor Documentation

10.224.3.1 PDataTFPDU()

```
gdcm::network::PDataTFPDU::PDataTFPDU ()
```

10.224.4 Member Function Documentation

10.224.4.1 AddPresentationDataValue()

```
void gdcm::network::PDataTFPDU::AddPresentationDataValue (  
    PresentationDataValue const & pdv) [inline]
```

References [gdcm_assert](#), and [Size\(\)](#).

10.224.4.2 GetNumberOfPresentationDataValues()

```
SizeType gdcm::network::PDataTFPDU::GetNumberOfPresentationDataValues () const [inline]
```

10.224.4.3 GetPresentationDataValue()

```
PresentationDataValue const & gdcm::network::PDataTFPDU::GetPresentationDataValue (  
    SizeType i) const [inline]
```

References [gdcm_assert](#).

10.224.4.4 IsLastFragment()

```
bool gdcm::network::PDataTFPDU::IsLastFragment () const [override], [virtual]
```

Implements [gdcm::network::BasePDU](#).

10.224.4.5 Print()

```
void gdcm::network::PDataTFPDU::Print (  
    std::ostream & os) const [override], [virtual]
```

Implements [gdcm::network::BasePDU](#).

10.224.4.6 Read()

```
std::istream & gdcm::network::PDataTFPDU::Read (  
    std::istream & is) [override], [virtual]
```

Implements [gdcm::network::BasePDU](#).

10.224.4.7 ReadInto()

```
std::istream & gdcM::network::PDataTFPDU::ReadInto (
    std::istream & is,
    std::ostream & os) [protected]
```

10.224.4.8 Size()

```
size_t gdcM::network::PDataTFPDU::Size () const [override], [virtual]
```

Implements [gdcM::network::BasePDU](#).

Referenced by [AddPresentationDataValue\(\)](#).

10.224.4.9 Write()

```
const std::ostream & gdcM::network::PDataTFPDU::Write (
    std::ostream & os) const [override], [virtual]
```

Implements [gdcM::network::BasePDU](#).

The documentation for this class was generated from the following file:


- [gdcMPDataTFPDU.h](#)

10.225 gdcM::PDBelement Class Reference

Class to represent a PDB [Element](#).

```
#include <gdcMPDBelement.h>
```

Collaboration diagram for gdcM::PDBelement:



Public Member Functions

- [PDBelement](#) ()=default
- const char * [GetName](#) () const
Set/Get Name.
- const char * [GetValue](#) () const
Set/Get Value.
- bool [operator==](#) (const [PDBelement](#) &de) const
- void [SetName](#) (const char *name)
- void [SetValue](#) (const char *value)

Protected Attributes

- std::string [NameField](#)
- std::string [ValueField](#)

Friends

- std::ostream & [operator<<](#) (std::ostream &os, const [PDBelement](#) &val)

10.225.1 Detailed Description

Class to represent a PDB [Element](#).

See also

[PDBHeader](#)

10.225.2 Constructor & Destructor Documentation

10.225.2.1 PDBelement()

```
gdcm::PDBelement::PDBelement () [default]
```

References [PDBelement\(\)](#), and [operator<<](#).

Referenced by [PDBelement\(\)](#), [operator<<](#), and [operator==\(\)](#).

10.225.3 Member Function Documentation

10.225.3.1 GetName()

```
const char * gdcm::PDBelement::GetName () const [inline]
```

Set/Get Name.

References [NameField](#).

10.225.3.2 GetValue()

```
const char * gdcM::PDBelement::GetValue () const [inline]
```

Set/Get [Value](#).

References [ValueField](#).

10.225.3.3 operator==()

```
bool gdcM::PDBelement::operator== (
    const PDBelement & de) const [inline]
```

References [PDBelement\(\)](#), [NameField](#), and [ValueField](#).

10.225.3.4 SetName()

```
void gdcM::PDBelement::SetName (
    const char * name) [inline]
```

References [NameField](#).

10.225.3.5 SetValue()

```
void gdcM::PDBelement::SetValue (
    const char * value) [inline]
```

References [ValueField](#).

10.225.4 Friends And Related Symbol Documentation

10.225.4.1 operator<<

```
std::ostream & operator<< (
    std::ostream & os,
    const PDBelement & val) [friend]
```

References [PDBelement\(\)](#), [NameField](#), and [ValueField](#).

Referenced by [PDBelement\(\)](#).

10.225.5 Member Data Documentation

10.225.5.1 NameField

`std::string gdcm::PDBElement::NameField` [protected]

Referenced by [GetName\(\)](#), [operator<<](#), [operator==\(\)](#), and [SetName\(\)](#).

10.225.5.2 ValueField

`std::string gdcm::PDBElement::ValueField` [protected]

Referenced by [GetValue\(\)](#), [operator<<](#), [operator==\(\)](#), and [SetValue\(\)](#).

The documentation for this class was generated from the following file:

- [gdcmPDBElement.h](#)

10.226 gdcm::PDBHeader Class Reference

Class for [PDBHeader](#).

```
#include <gdcmPDBHeader.h>
```

Public Member Functions

- [PDBHeader](#) ()=default
- [~PDBHeader](#) ()=default
- bool [FindPDBElementByName](#) (const char *name)
Return true if the PDB element matching name is found or not.
- const [PDBElement](#) & [GetPDBElementByName](#) (const char *name)
- bool [LoadFromDataElement](#) ([DataElement](#) const &de)
Load the PDB Header from a [DataElement](#) of a [DataSet](#).
- void [Print](#) (std::ostream &os) const
Print.

Static Public Member Functions

- static const [PrivateTag](#) & [GetPDBInfoTag](#) ()
Return the Private [Tag](#) where the PDB header is stored within a DICOM [DataSet](#).

Protected Member Functions

- const [PDBElement](#) & [GetPDBEEnd](#) () const

Friends

- `std::ostream & operator<< (std::ostream &_os, const PDBHeader &d)`

10.226.1 Detailed Description

Class for [PDBHeader](#).

GEMS MR [Image](#) have an [Attribute](#) (0025,1b,GEMS_SERS_01) which store the Acquisition parameter of the MR [Image](#). It is compressed and can therefore not be used as is. This class de-encapsulated the Protocol Data Block and allow users to query element by name.

Warning

Everything you do with this code is at your own risk, since decoding process was not written from specification documents.

: the API of this class might change.

: SEDESC is not always pure ASCII it can contains latin1

See also

[CSAHeader](#)

10.226.2 Constructor & Destructor Documentation

10.226.2.1 PDBHeader()

```
gdcm::PDBHeader::PDBHeader () [default]
```

Referenced by [operator<<](#).

10.226.2.2 ~PDBHeader()

```
gdcm::PDBHeader::~~PDBHeader () [default]
```

10.226.3 Member Function Documentation

10.226.3.1 FindPDBElementByName()

```
bool gdcm::PDBHeader::FindPDBElementByName (
    const char * name)
```

Return true if the PDB element matching name is found or not.

10.226.3.2 GetPDBEEnd()

```
const PDBElement & gdcmm::PDBHeader::GetPDBEEnd () const [protected]
```

10.226.3.3 GetPDBElementByName()

```
const PDBElement & gdcmm::PDBHeader::GetPDBElementByName (
    const char * name)
```

Lookup in the PDB header if a PDB element match the name 'name':

Warning

Case Sensitive

10.226.3.4 GetPDBInfoTag()

```
const PrivateTag & gdcmm::PDBHeader::GetPDBInfoTag () [static]
```

Return the Private [Tag](#) where the PDB header is stored within a DICOM [DataSet](#).

10.226.3.5 LoadFromDataElement()

```
bool gdcmm::PDBHeader::LoadFromDataElement (
    DataElement const & de)
```

Load the PDB Header from a [DataElement](#) of a [DataSet](#).

10.226.3.6 Print()

```
void gdcmm::PDBHeader::Print (
    std::ostream & os) const
```

Print.

Referenced by [operator<<](#).

10.226.4 Friends And Related Symbol Documentation

10.226.4.1 operator<<

```
std::ostream & operator<< (
    std::ostream & _os,
    const PDBHeader & d) [friend]
```

References [PDBHeader\(\)](#), and [Print\(\)](#).

The documentation for this class was generated from the following file:


- [gdcmmPDBHeader.h](#)

10.227 gdcm::PDFCodec Class Reference


[PDFCodec](#) class.

```
#include <gdcmPDFCodec.h>
```

Inheritance diagram for gdcm::PDFCodec:



Collaboration diagram for gdcm::PDFCodec:



Public Member Functions

- [PDFCodec](#) ()
- [~PDFCodec](#) () override
- bool [CanCode](#) ([TransferSyntax](#) const &) const override
Return whether this coder support this transfer syntax (can code it)
- bool [CanDecode](#) ([TransferSyntax](#) const &) const override
Return whether this decoder support this transfer syntax (can decode it)
- bool [Decode](#) ([DataElement](#) const &is, [DataElement](#) &os) override
Decode.

Public Member Functions inherited from [gdcm::Coder](#)

- virtual [~Coder](#) ()=default
- virtual bool [Code](#) ([DataElement](#) const &in_, [DataElement](#) &out_)
Code.

Public Member Functions inherited from [gdcm::Decoder](#)

- virtual [~Decoder](#) ()=default

Additional Inherited Members**Protected Member Functions inherited from [gdcm::Coder](#)**

- virtual bool [InternalCode](#) (const char *bv, unsigned long len, std::ostream &os)

Protected Member Functions inherited from [gdcm::Decoder](#)

- virtual bool [DecodeByStreams](#) (std::istream &, std::ostream &)

10.227.1 Detailed Description

[PDFCodec](#) class.

10.227.2 Constructor & Destructor Documentation**10.227.2.1 PDFCodec()**

```
gdcm::PDFCodec::PDFCodec ()
```

10.227.2.2 ~PDFCodec()

```
gdcm::PDFCodec::~~PDFCodec () [override]
```

10.227.3 Member Function Documentation

10.227.3.1 CanCode()

```
bool gdcm::PDFCodec::CanCode (
    TransferSyntax const & ) const [inline], [override], [virtual]
```

Return whether this coder support this transfer syntax (can code it)

Implements [gdcm::Coder](#).

10.227.3.2 CanDecode()

```
bool gdcm::PDFCodec::CanDecode (
    TransferSyntax const & ) const [inline], [override], [virtual]
```

Return whether this decoder support this transfer syntax (can decode it)

Implements [gdcm::Decoder](#).

10.227.3.3 Decode()

```
bool gdcm::PDFCodec::Decode (
    DataElement const & ,
    DataElement & ) [override], [virtual]
```

Decode.

Reimplemented from [gdcm::Decoder](#).

The documentation for this class was generated from the following file:

- [gdcmPDFCodec.h](#)

10.228 gdcm::network::PDUFactory Class Reference

[PDUFactory](#) basically, given an initial byte, construct the.

```
#include <gdcmPDUFactory.h>
```


Static Public Member Functions

- static [BasePDU](#) * [ConstructAbortPDU](#) ()
- static [BasePDU](#) * [ConstructPDU](#) (uint8_t itemtype)
- static [BasePDU](#) * [ConstructReleasePDU](#) ()
- static std::vector< [BasePDU](#) * > [CreateCEchoPDU](#) (const [ULConnection](#) &inConnection)
- static std::vector< [BasePDU](#) * > [CreateCFindPDU](#) (const [ULConnection](#) &inConnection, const [BaseRootQuery](#) *inRootQuery)
- static std::vector< [BasePDU](#) * > [CreateCMovePDU](#) (const [ULConnection](#) &inConnection, const [BaseRootQuery](#) *inRootQuery)
- static std::vector< [BasePDU](#) * > [CreateCStoreRQPDU](#) (const [ULConnection](#) &inConnection, const [File](#) &file, bool writeDataSet=true)
- static std::vector< [BasePDU](#) * > [CreateCStoreRSPPDU](#) (const [DataSet](#) *inDataSet, const [BasePDU](#) *inPC)
- static std::vector< [BasePDU](#) * > [CreateNActionPDU](#) (const [ULConnection](#) &inConnection, const [BaseQuery](#) *inQuery)
- static std::vector< [BasePDU](#) * > [CreateNCreatePDU](#) (const [ULConnection](#) &inConnection, const [BaseQuery](#) *inQuery)
- static std::vector< [BasePDU](#) * > [CreateNDeletePDU](#) (const [ULConnection](#) &inConnection, const [BaseQuery](#) *inQuery)
- static std::vector< [BasePDU](#) * > [CreateNEventReportPDU](#) (const [ULConnection](#) &inConnection, const [BaseQuery](#) *inQuery)
- static std::vector< [BasePDU](#) * > [CreateNGetPDU](#) (const [ULConnection](#) &inConnection, const [BaseQuery](#) *inQuery)
- static std::vector< [BasePDU](#) * > [CreateNSetPDU](#) (const [ULConnection](#) &inConnection, const [BaseQuery](#) *inQuery)
- static [EEventID](#) [DetermineEventByPDU](#) (const [BasePDU](#) *inPDU)
- static std::vector< [PresentationDataValue](#) > [GetPDVs](#) (const std::vector< [BasePDU](#) * > &inDataPDUs)

10.228.1 Detailed Description

[PDUFactory](#) basically, given an initial byte, construct the.

appropriate PDU. This way, the event loop doesn't have to know about all the different PDU types.

10.228.2 Member Function Documentation

10.228.2.1 ConstructAbortPDU()

```
BasePDU * gdcmm::network::PDUFactory::ConstructAbortPDU () [static]
```

10.228.2.2 ConstructPDU()

```
BasePDU * gdcmm::network::PDUFactory::ConstructPDU (
    uint8_t itemtype) [static]
```

10.228.2.3 ConstructReleasePDU()

```
BasePDU * gdc::network::PDUFactory::ConstructReleasePDU () [static]
```

10.228.2.4 CreateCEchoPDU()

```
std::vector< BasePDU * > gdc::network::PDUFactory::CreateCEchoPDU (
    const ULConnection & inConnection) [static]
```

10.228.2.5 CreateCFindPDU()

```
std::vector< BasePDU * > gdc::network::PDUFactory::CreateCFindPDU (
    const ULConnection & inConnection,
    const BaseRootQuery * inRootQuery) [static]
```

10.228.2.6 CreateCMovePDU()

```
std::vector< BasePDU * > gdc::network::PDUFactory::CreateCMovePDU (
    const ULConnection & inConnection,
    const BaseRootQuery * inRootQuery) [static]
```

10.228.2.7 CreateCStoreRQPDU()

```
std::vector< BasePDU * > gdc::network::PDUFactory::CreateCStoreRQPDU (
    const ULConnection & inConnection,
    const File & file,
    bool writeDataSet = true) [static]
```

10.228.2.8 CreateCStoreRSPPDU()

```
std::vector< BasePDU * > gdc::network::PDUFactory::CreateCStoreRSPPDU (
    const DataSet * inDataSet,
    const BasePDU * inPC) [static]
```

10.228.2.9 CreateNActionPDU()

```
std::vector< BasePDU * > gdc::network::PDUFactory::CreateNActionPDU (
    const ULConnection & inConnection,
    const BaseQuery * inQuery) [static]
```

10.228.2.10 CreateNCreatePDU()

```
std::vector< BasePDU * > gdcm::network::PDUFactory::CreateNCreatePDU (
    const ULConnection & inConnection,
    const BaseQuery * inQuery) [static]
```

10.228.2.11 CreateNDeletePDU()

```
std::vector< BasePDU * > gdcm::network::PDUFactory::CreateNDeletePDU (
    const ULConnection & inConnection,
    const BaseQuery * inQuery) [static]
```

10.228.2.12 CreateNEventReportPDU()

```
std::vector< BasePDU * > gdcm::network::PDUFactory::CreateNEventReportPDU (
    const ULConnection & inConnection,
    const BaseQuery * inQuery) [static]
```

10.228.2.13 CreateNGetPDU()

```
std::vector< BasePDU * > gdcm::network::PDUFactory::CreateNGetPDU (
    const ULConnection & inConnection,
    const BaseQuery * inQuery) [static]
```

10.228.2.14 CreateNSetPDU()

```
std::vector< BasePDU * > gdcm::network::PDUFactory::CreateNSetPDU (
    const ULConnection & inConnection,
    const BaseQuery * inQuery) [static]
```

10.228.2.15 DetermineEventByPDU()

```
EEEventID gdcm::network::PDUFactory::DetermineEventByPDU (
    const BasePDU * inPDU) [static]
```

10.228.2.16 GetPDVs()

```
std::vector< PresentationDataValue > gdcm::network::PDUFactory::GetPDVs (
    const std::vector< BasePDU * > & inDataPDUs) [static]
```

The documentation for this class was generated from the following file:

- [gdcmPDUFactory.h](#)

10.229 gdcm::PersonName Class Reference

[PersonName](#) class.

```
#include <gdcmPersonName.h>
```

Public Member Functions

- unsigned int [GetMaxLength](#) () const
- unsigned int [GetNumberOfComponents](#) () const
- void [Print](#) (std::ostream &os) const
- void [SetBlob](#) (const std::vector< char > &v)
- void [SetComponents](#) (const char *comp1="", const char *comp2="", const char *comp3="", const char *comp4="", const char *comp5="")
- void [SetComponents](#) (const char *components[])

Public Attributes

- char [Component](#) [[MaxNumberOfComponents](#)][[MaxLength](#)+1]

Static Public Attributes

- static const unsigned int [MaxLength](#) = 64
- static const unsigned int [MaxNumberOfComponents](#) = 5
- static const char [Padding](#) = ' '
- static const char [Separator](#) = '^'

10.229.1 Detailed Description

[PersonName](#) class.

10.229.2 Member Function Documentation

10.229.2.1 GetMaxLength()

```
unsigned int gdcm::PersonName::GetMaxLength () const [inline]
```

References [MaxLength](#).

Referenced by [SetComponents\(\)](#).

10.229.2.2 GetNumberOfComponents()

```
unsigned int gdcm::PersonName::GetNumberOfComponents () const [inline]
```

References [Component](#).

10.229.2.3 Print()

```
void gdcm::PersonName::Print (  
    std::ostream & os) const [inline]
```

References [Component](#).

10.229.2.4 SetBlob()

```
void gdcm::PersonName::SetBlob (  
    const std::vector< char > & v) [inline]
```

10.229.2.5 SetComponents() [1/2]

```
void gdcm::PersonName::SetComponents (  
    const char * comp1 = "",  
    const char * comp2 = "",  
    const char * comp3 = "",  
    const char * comp4 = "",  
    const char * comp5 = "") [inline]
```

References [SetComponents\(\)](#).

Referenced by [SetComponents\(\)](#).

10.229.2.6 SetComponents() [2/2]

```
void gdcm::PersonName::SetComponents (  
    const char * components[]) [inline]
```

References [Component](#), [gdcm_assert](#), and [GetMaxLength\(\)](#).

10.229.3 Member Data Documentation

10.229.3.1 Component

```
char gdcm::PersonName::Component [MaxNumberOfComponents] [MaxLength+1]
```

Referenced by [GetNumberOfComponents\(\)](#), [Print\(\)](#), and [SetComponents\(\)](#).

10.229.3.2 MaxLength

```
const unsigned int gdcm::PersonName::MaxLength = 64 [static]
```

Referenced by [GetMaxLength\(\)](#).

10.229.3.3 MaxNumberOfComponents

```
const unsigned int gdcm::PersonName::MaxNumberOfComponents = 5 [static]
```

10.229.3.4 Padding

```
const char gdcm::PersonName::Padding = ' ' [static]
```

10.229.3.5 Separator

```
const char gdcm::PersonName::Separator = '^' [static]
```

The documentation for this class was generated from the following file:


- [gdcmPersonName.h](#)

10.230 gdcm::PGXCodec Class Reference


Class to do PGX.

```
#include <gdcmPGXCodec.h>
```

Inheritance diagram for gdcm::PGXCodec:



Collaboration diagram for gdcm::PGXCodec:



Public Member Functions

- [PGXCodec](#) ()
- [~PGXCodec](#) () override
- bool [CanCode](#) ([TransferSyntax](#) const &ts) const override
Return whether this coder support this transfer syntax (can code it)
- bool [CanDecode](#) ([TransferSyntax](#) const &ts) const override
Return whether this decoder support this transfer syntax (can decode it)
- [ImageCodec](#) * [Clone](#) () const override
- bool [GetHeaderInfo](#) (std::istream &is, [TransferSyntax](#) &ts) override
- bool [Read](#) (const char *filename, [DataElement](#) &out) const
- bool [Write](#) (const char *filename, const [DataElement](#) &out) const

Public Member Functions inherited from [gdcm::ImageCodec](#)

- [ImageCodec](#) ()
- [~ImageCodec](#) () override
- bool [CleanupUnusedBits](#) (char *data, size_t datalen)
- bool [Decode](#) ([DataElement](#) const &is_, [DataElement](#) &os) override
Decode.
- const unsigned int * [GetDimensions](#) () const
- bool [GetLossyFlag](#) () const
- const [LookupTable](#) & [GetLUT](#) () const
- bool [GetNeedByteSwap](#) () const
- unsigned int [GetNumberOfDimensions](#) () const
- const [PhotometricInterpretation](#) & [GetPhotometricInterpretation](#) () const
- [PixelFormat](#) & [GetPixelFormat](#) ()
- const [PixelFormat](#) & [GetPixelFormat](#) () const
- unsigned int [GetPlanarConfiguration](#) () const
- bool [IsLossy](#) () const
- void [SetDimensions](#) (const std::vector< unsigned int > &d)
- void [SetDimensions](#) (const unsigned int d[3])
- void [SetLossyFlag](#) (bool l)
- void [SetLUT](#) ([LookupTable](#) const &lut)
- void [SetNeedByteSwap](#) (bool b)
- void [SetNeedOverlayCleanup](#) (bool b)
- void [SetNumberOfDimensions](#) (unsigned int dim)
- void [SetPhotometricInterpretation](#) ([PhotometricInterpretation](#) const &pi)
- virtual void [SetPixelFormat](#) ([PixelFormat](#) const &pf)
- void [SetPlanarConfiguration](#) (unsigned int pc)

Public Member Functions inherited from [gdcm::Coder](#)

- virtual [~Coder](#) ()=default
- virtual bool [Code](#) ([DataElement](#) const &in_, [DataElement](#) &out_)
Code.

Public Member Functions inherited from [gdcm::Decoder](#)

- virtual [~Decoder](#) ()=default

Additional Inherited Members

Protected Types inherited from [gdcm::ImageCodec](#)

- typedef [SmartPointer](#)< [LookupTable](#) > [LUTPtr](#)

Protected Member Functions inherited from [gdcm::ImageCodec](#)

- virtual bool [AppendFrameEncode](#) (std::ostream &out, const char *data, size_t datalen)
- virtual bool [AppendRowEncode](#) (std::ostream &out, const char *data, size_t datalen)
- bool [DecodeByStreams](#) (std::istream &is_, std::ostream &os) override
- bool [DoByteSwap](#) (std::istream &is_, std::ostream &os)
- bool [DoInvertMonochrome](#) (std::istream &is_, std::ostream &os)
- bool [DoOverlayCleanup](#) (std::istream &is_, std::ostream &os)
- bool [DoPaddedCompositePixelCode](#) (std::istream &is_, std::ostream &os)
- bool [DoPlanarConfiguration](#) (std::istream &is_, std::ostream &os)
- bool [DoSimpleCopy](#) (std::istream &is_, std::ostream &os)
- bool [DoYBR](#) (std::istream &is_, std::ostream &os)
- bool [DoYBRFull422](#) (std::istream &is_, std::ostream &os)
- virtual bool [IsFrameEncoder](#) ()
- virtual bool [IsRowEncoder](#) ()
- virtual bool [IsValid](#) ([PhotometricInterpretation](#) const &pi)
- virtual bool [StartEncode](#) (std::ostream &os)
- virtual bool [StopEncode](#) (std::ostream &os)

Protected Member Functions inherited from [gdcm::Coder](#)

- virtual bool [InternalCode](#) (const char *bv, unsigned long len, std::ostream &os)

Protected Attributes inherited from [gdcm::ImageCodec](#)

- unsigned int [Dimensions](#) [3]
- bool [LossyFlag](#)
- [LUTPtr](#) LUT
- bool [NeedByteSwap](#)
- bool [NeedOverlayCleanup](#)
- unsigned int [NumberOfDimensions](#)
- [PixelFormat](#) PF
- [PhotometricInterpretation](#) PI
- unsigned int [PlanarConfiguration](#)
- bool [RequestPaddedCompositePixelCode](#)
- bool [RequestPlanarConfiguration](#)

10.230.1 Detailed Description

Class to do PGX.

See PGX as used in JPEG 2000 implementation and reference images

10.230.2 Constructor & Destructor Documentation

10.230.2.1 PGXCodec()

```
gdcm::PGXCodec::PGXCodec ()
```

10.230.2.2 ~PGXCodec()

```
gdcm::PGXCodec::~~PGXCodec () [override]
```

10.230.3 Member Function Documentation

10.230.3.1 CanCode()

```
bool gdcm::PGXCodec::CanCode (
    TransferSyntax const & ) const [override], [virtual]
```

Return whether this coder support this transfer syntax (can code it)

Reimplemented from [gdcm::ImageCodec](#).

10.230.3.2 CanDecode()

```
bool gdcM::PGXCodec::CanDecode (
    TransferSyntax const & ) const [override], [virtual]
```

Return whether this decoder support this transfer syntax (can decode it)

Reimplemented from [gdcM::ImageCodec](#).

10.230.3.3 Clone()

```
ImageCodec * gdcM::PGXCodec::Clone () const [override], [virtual]
```

Implements [gdcM::ImageCodec](#).

References [gdcM::ImageCodec::ImageCodec\(\)](#).

10.230.3.4 GetHeaderInfo()

```
bool gdcM::PGXCodec::GetHeaderInfo (
    std::istream & is,
    TransferSyntax & ts) [override], [virtual]
```

Reimplemented from [gdcM::ImageCodec](#).

10.230.3.5 Read()

```
bool gdcM::PGXCodec::Read (
    const char * filename,
    DataElement & out) const
```

10.230.3.6 Write()

```
bool gdcM::PGXCodec::Write (
    const char * filename,
    const DataElement & out) const
```

The documentation for this class was generated from the following file:

- [gdcM_PGXCodec.h](#)

10.231 gdcM::PhotometricInterpretation Class Reference

Class to represent an [PhotometricInterpretation](#).

```
#include <gdcMPhotometricInterpretation.h>
```

Public Types

- enum [PType](#) {
[UNKNOWN](#) = 0 ,
[MONOCHROME1](#) ,
[MONOCHROME2](#) ,
[PALETTE_COLOR](#) ,
[RGB](#) ,
[HSV](#) ,
[ARGB](#) ,
[CMYK](#) ,
[YBR_FULL](#) ,
[YBR_FULL_422](#) ,
[YBR_PARTIAL_422](#) ,
[YBR_PARTIAL_420](#) ,
[YBR_ICT](#) ,
[YBR_RCT](#) ,
[PI_END](#) }

Public Member Functions

- [PhotometricInterpretation](#) ([PType](#) pi=[UNKNOWN](#))
- unsigned short [GetSamplesPerPixel](#) () const
return the value for Sample Per Pixel associated with a particular Photometric Interpretation
- const char * [GetString](#) () const
- [PType](#) [GetType](#) () const
- bool [IsLossless](#) () const
- bool [IsLossy](#) () const
- bool [IsSameColorSpace](#) ([PhotometricInterpretation](#) const &pi) const
- [operator PType](#) () const

Static Public Member Functions

- static const char * [GetPIString](#) ([PType](#) pi)
- static [PType](#) [GetPType](#) (const char *pi)
- static bool [IsRetired](#) ([PType](#) pi)

Friends

- std::ostream & [operator<<](#) (std::ostream &os, const [PhotometricInterpretation](#) &pi)

10.231.1 Detailed Description

Class to represent an [PhotometricInterpretation](#).

Examples

[CreateARGBImage.cxx](#), [CreateCMYKImage.cxx](#), [DecompressImage.cs](#), [DecompressImageMultiframe.cs](#), [DecompressJPEGFile.cs](#), [ExtractImageRegion.cs](#), [FileChangeTS.cs](#), [FileChangeTSLossy.cs](#), [HelloVizWorld.cxx](#), [MpegVideoInfo.cs](#), [csa2img.cxx](#), and [iU22tomultisc.cxx](#).

10.231.2 Member Enumeration Documentation

10.231.2.1 PType

```
enum gdcm::PhotometricInterpretation::PType
```

Enumerator

UNKNOWN	
MONOCHROME1	
MONOCHROME2	
PALETTE_COLOR	
RGB	
HSV	
ARGB	
CMYK	
YBR_FULL	
YBR_FULL_422	
YBR_PARTIAL_422	
YBR_PARTIAL_420	
YBR_ICT	
YBR_RCT	
PI_END	

Examples

[DecompressImageMultiframe.cs](#), [DecompressJPEGFile.cs](#), [FileChangeTS.cs](#), [FileChangeTSLossy.cs](#), and [MpegVideoInfo.cs](#).

10.231.3 Constructor & Destructor Documentation

10.231.3.1 PhotometricInterpretation()

```
gdcm::PhotometricInterpretation::PhotometricInterpretation (
    PType pi = UNKNOWN) [inline]
```

References [UNKNOWN](#).

Referenced by [GetSamplesPerPixel\(\)](#), [IsSameColorSpace\(\)](#), and [operator<<](#).

10.231.4 Member Function Documentation

10.231.4.1 GetPIString()

```
const char * gdcm::PhotometricInterpretation::GetPIString (
    PType pi) [static]
```

Referenced by [operator<<](#).

10.231.4.2 GetPIType()

```
PIType gdcm::PhotometricInterpretation::GetPIType (  
    const char * pi) [static]
```

10.231.4.3 GetSamplesPerPixel()

```
unsigned short gdcm::PhotometricInterpretation::GetSamplesPerPixel () const
```

return the value for Sample Per Pixel associated with a particular Photometric Interpretation

References [PhotometricInterpretation\(\)](#), and [operator<<](#).

10.231.4.4 GetString()

```
const char * gdcm::PhotometricInterpretation::GetString () const
```

10.231.4.5 GetType()

```
PIType gdcm::PhotometricInterpretation::GetType () const [inline]
```

10.231.4.6 IsLossless()

```
bool gdcm::PhotometricInterpretation::IsLossless () const
```

10.231.4.7 IsLossy()

```
bool gdcm::PhotometricInterpretation::IsLossy () const
```

10.231.4.8 IsRetired()

```
bool gdcm::PhotometricInterpretation::IsRetired (  
    PIType pi) [static]
```

10.231.4.9 IsSameColorSpace()

```
bool gdcm::PhotometricInterpretation::IsSameColorSpace (  
    PhotometricInterpretation const & pi) const
```

References [PhotometricInterpretation\(\)](#).

10.231.4.10 operator PType()

```
gdcmm::PhotometricInterpretation::operator PType () const [inline]
```

10.231.5 Friends And Related Symbol Documentation

10.231.5.1 operator<<

```
std::ostream & operator<< (
    std::ostream & os,
    const PhotometricInterpretation & pi) [friend]
```

References [PhotometricInterpretation\(\)](#), and [GetPIString\(\)](#).

Referenced by [GetSamplesPerPixel\(\)](#).

The documentation for this class was generated from the following file:

- [gdcmmPhotometricInterpretation.h](#)

10.232 gdcm::PixelFormat Class Reference

[PixelFormat](#).

```
#include <gdcmPixelFormat.h>
```

Public Types

- enum [ScalarType](#) {
 - [UINT8](#),
 - [INT8](#),
 - [UINT12](#),
 - [INT12](#),
 - [UINT16](#),
 - [INT16](#),
 - [UINT32](#),
 - [INT32](#),
 - [UINT64](#),
 - [INT64](#),
 - [FLOAT16](#),
 - [FLOAT32](#),
 - [FLOAT64](#),
 - [SINGLEBIT](#),
 - [UNKNOWN](#) }

Public Member Functions

- [PixelFormat](#) ()
- [PixelFormat](#) ([ScalarType](#) st)
- [PixelFormat](#) (unsigned short samplesperpixel, unsigned short bitsallocated=8, unsigned short bitsstored=8, unsigned short highbit=7, unsigned short pixelrepresentation=0)
- unsigned short [GetBitsAllocated](#) () const
BitsAllocated see [Tag](#) (0028,0100) US Bits Allocated.
- unsigned short [GetBitsStored](#) () const
BitsStored see [Tag](#) (0028,0101) US Bits Stored.
- unsigned short [GetHighBit](#) () const
HighBit see [Tag](#) (0028,0102) US High Bit.
- int64_t [GetMax](#) () const
return the max possible of the pixel
- int64_t [GetMin](#) () const
return the min possible of the pixel
- unsigned short [GetPixelRepresentation](#) () const
PixelRepresentation: 0 or 1, see [Tag](#) (0028,0103) US Pixel Representation.
- uint8_t [GetPixelSize](#) () const
- unsigned short [GetSamplesPerPixel](#) () const
- [ScalarType](#) [GetScalarType](#) () const
ScalarType does not take into account the sample per pixel.
- const char * [GetScalarTypeAsString](#) () const
- bool [IsCompatible](#) (const [TransferSyntax](#) &ts) const
- bool [IsValid](#) () const
return IsValid
- [operator ScalarType](#) () const
- bool [operator!=](#) (const [PixelFormat](#) &pf) const
- bool [operator!=](#) ([ScalarType](#) st) const
- bool [operator==](#) (const [PixelFormat](#) &pf) const
- bool [operator==](#) ([ScalarType](#) st) const
- void [Print](#) (std::ostream &os) const
Print.
- void [SetBitsAllocated](#) (unsigned short ba)
- void [SetBitsStored](#) (unsigned short bs)
- void [SetHighBit](#) (unsigned short hb)
- void [SetPixelRepresentation](#) (unsigned short pr)
- void [SetSamplesPerPixel](#) (unsigned short spp)
- void [SetScalarType](#) ([ScalarType](#) st)

Protected Member Functions

- bool [Validate](#) ()
When image with 24/24/23 was read, need to validate.

Friends

- class [Bitmap](#)
- std::ostream & [operator<<](#) (std::ostream &_os, const [PixelFormat](#) &pf)

10.232.1 Detailed Description

[PixelFormat](#).

By default the Pixel [Type](#) will be instantiated with the following parameters:

- SamplesPerPixel : 1
- BitsAllocated : 8
- BitsStored : 8
- HighBit : 7
- PixelRepresentation : 0

Fundamentally [PixelFormat](#) is very close to what DICOM allows. It will be very hard to extend this class for the upcoming DICOM standard where Floating 32 and 64bits will be allowed.

It is also very hard for this class to fully support 64bits integer type (see GetMin / GetMax signature restricted to 64bits signed).

Examples

[CreateARGBImage.cxx](#), [CreateCMYKImage.cxx](#), [DecompressImage.cs](#), [DecompressImageMultiframe.cs](#), [DecompressJPEGFile.cs](#), [ExtractImageRegion.cs](#), [ExtractImageRegionWithLUT.cs](#), [ExtractOneFrame.cs](#), [FixJAIBugJPEGLS.cxx](#), [GetArray.cs](#), [GetJPEGSamplePrecision.cxx](#), [MpegVideoInfo.cs](#), [RescaleImage.cs](#), [TemplateEmptyImage.cxx](#), [csa2img.cxx](#), [iU22tomultisc.cxx](#), and [threadgdcm.cxx](#).

10.232.2 Member Enumeration Documentation

10.232.2.1 ScalarType

```
enum gdcm::PixelFormat::ScalarType
```

Enumerator

UINT8	
INT8	
UINT12	
INT12	
UINT16	
INT16	
UINT32	
INT32	
UINT64	
INT64	
FLOAT16	
FLOAT32	
FLOAT64	
SINGLEBIT	
UNKNOWN	

Examples

[GetArray.cs](#).

10.232.3 Constructor & Destructor Documentation

10.232.3.1 PixelFormat() [1/3]

```
gdcm::PixelFormat::PixelFormat () [inline]
```

References [PixelFormat\(\)](#).

Referenced by [PixelFormat\(\)](#), [Bitmap](#), [operator!=\(\)](#), [operator<<](#), and [operator==\(\)](#).

10.232.3.2 PixelFormat() [2/3]

```
gdcm::PixelFormat::PixelFormat (  
    unsigned short samplesperpixel,  
    unsigned short bitsallocated = 8,  
    unsigned short bitsstored = 8,  
    unsigned short highbit = 7,  
    unsigned short pixelrepresentation = 0) [inline], [explicit]
```

10.232.3.3 PixelFormat() [3/3]

```
gdcm::PixelFormat::PixelFormat (  
    ScalarType st)
```

10.232.4 Member Function Documentation

10.232.4.1 GetBitsAllocated()

```
unsigned short gdcm::PixelFormat::GetBitsAllocated () const [inline]
```

BitsAllocated see [Tag](#) (0028,0100) US Bits Allocated.

Examples

[GetJPEGSamplePrecision.cxx](#).

10.232.4.2 GetBitsStored()

```
unsigned short gdcm::PixelFormat::GetBitsStored () const [inline]
```

BitsStored see [Tag](#) (0028,0101) US Bits Stored.

Examples

[GetJPEGSamplePrecision.cxx](#).

References [gdcm_assert](#).

10.232.4.3 GetHighBit()

```
unsigned short gdcm::PixelFormat::GetHighBit () const [inline]
```

HighBit see [Tag](#) (0028,0102) US High Bit.

References [gdcm_assert](#).

10.232.4.4 GetMax()

```
int64_t gdcm::PixelFormat::GetMax () const
```

return the max possible of the pixel

10.232.4.5 GetMin()

```
int64_t gdcm::PixelFormat::GetMin () const
```

return the min possible of the pixel

10.232.4.6 GetPixelRepresentation()

```
unsigned short gdcm::PixelFormat::GetPixelRepresentation () const [inline]
```

PixelRepresentation: 0 or 1, see [Tag](#) (0028,0103) US Pixel Representation.

10.232.4.7 GetPixelSize()

```
uint8_t gdcm::PixelFormat::GetPixelSize () const
```

return the size of the pixel This is the number of words it would take to store one pixel

Warning

the return value takes into account the SamplesPerPixel

in the rare case when BitsAllocated == 12, the function assume word padding and value returned will be identical as if BitsAllocated == 16

Examples

[ExtractImageRegion.cs](#), [ExtractImageRegionWithLUT.cs](#), [ExtractOneFrame.cs](#), and [threadgdcm.cxx](#).

10.232.4.8 GetSamplesPerPixel()

```
unsigned short gdcm::PixelFormat::GetSamplesPerPixel () const
```

Samples Per Pixel see (0028,0002) US Samples Per Pixel DICOM - only allows 1, 3 and 4 as valid value. Other value are undefined behavior.

Examples

[threadgdcm.cxx](#).

10.232.4.9 GetScalarType()

```
ScalarType gdcm::PixelFormat::GetScalarType () const
```

[ScalarType](#) does not take into account the sample per pixel.

Examples

[GetArray.cs](#).

Referenced by [operator ScalarType\(\)](#), [operator!=\(\)](#), and [operator==\(\)](#).

10.232.4.10 GetScalarTypeAsString()

```
const char * gdcm::PixelFormat::GetScalarTypeAsString () const
```

Examples

[GetArray.cs](#).

10.232.4.11 IsCompatible()

```
bool gdcm::PixelFormat::IsCompatible (  
    const TransferSyntax & ts) const
```

10.232.4.12 IsValid()

```
bool gdcm::PixelFormat::IsValid () const
```

return IsValid

10.232.4.13 operator ScalarType()

```
gdcm::PixelFormat::operator ScalarType () const [inline]
```

References [GetScalarType\(\)](#).

10.232.4.14 operator!=() [1/2]

```
bool gdcm::PixelFormat::operator!= (
    const PixelFormat & pf) const [inline]
```

References [PixelFormat\(\)](#).

10.232.4.15 operator!=() [2/2]

```
bool gdcm::PixelFormat::operator!= (
    ScalarType st) const [inline]
```

References [GetScalarType\(\)](#).

10.232.4.16 operator==() [1/2]

```
bool gdcm::PixelFormat::operator== (
    const PixelFormat & pf) const [inline]
```

References [PixelFormat\(\)](#).

10.232.4.17 operator==() [2/2]

```
bool gdcm::PixelFormat::operator== (
    ScalarType st) const [inline]
```

References [GetScalarType\(\)](#).

10.232.4.18 Print()

```
void gdcm::PixelFormat::Print (
    std::ostream & os) const
```

Print.

Referenced by [operator<<](#).

10.232.4.19 SetBitsAllocated()

```
void gdcm::PixelFormat::SetBitsAllocated (
    unsigned short ba) [inline]
```

10.232.4.20 SetBitsStored()

```
void gdcm::PixelFormat::SetBitsStored (
    unsigned short bs) [inline]
```

References [SetHighBit\(\)](#).

10.232.4.21 SetHighBit()

```
void gdcm::PixelFormat::SetHighBit (
    unsigned short hb) [inline]
```

Referenced by [SetBitsStored\(\)](#).

10.232.4.22 SetPixelRepresentation()

```
void gdcm::PixelFormat::SetPixelRepresentation (
    unsigned short pr) [inline]
```

Examples

[TemplateEmptyImage.cxx](#).

10.232.4.23 SetSamplesPerPixel()

```
void gdcm::PixelFormat::SetSamplesPerPixel (
    unsigned short spp) [inline]
```

Examples

[CreateARGBImage.cxx](#), and [CreateCMYKImage.cxx](#).

References [gdcm_assert](#), and [gdcmAssertMacro](#).

10.232.4.24 SetScalarType()

```
void gdcmm::PixelFormat::SetScalarType (  
    ScalarType st)
```

Set [PixelFormat](#) based only on the [ScalarType](#)

Warning

: You need to call SetScalarType *before* SetSamplesPerPixel

10.232.4.25 Validate()

```
bool gdcmm::PixelFormat::Validate () [protected]
```

When image with 24/24/23 was read, need to validate.

10.232.5 Friends And Related Symbol Documentation

10.232.5.1 Bitmap

```
friend class Bitmap [friend]
```

References [PixelFormat\(\)](#), [Bitmap](#), and [operator<<](#).

Referenced by [Bitmap](#).

10.232.5.2 operator<<

```
std::ostream & operator<< (  
    std::ostream & _os,  
    const PixelFormat & pf) [friend]
```

References [PixelFormat\(\)](#), and [Print\(\)](#).


Referenced by [Bitmap](#).

The documentation for this class was generated from the following file:

- [gdcmmPixelFormat.h](#)

Pixmap class.

Inheritance diagram for gdcm::Pixmap:



Public Member Functions

- [Pixmap](#) ()
- [~Pixmap](#) () override
- bool [AreOverlaysInPixelData](#) () const override
returns if Overlays are stored in the unused bit of the pixel data:
- [Curve](#) & [GetCurve](#) (size_t i=0)
Curve: group 50xx.
- const [Curve](#) & [GetCurve](#) (size_t i=0) const
- [IconImage](#) & [GetIconImage](#) ()
- const [IconImage](#) & [GetIconImage](#) () const
Set/Get Icon Image.
- size_t [GetNumberOfCurves](#) () const
- size_t [GetNumberOfOverlays](#) () const
- [Overlay](#) & [GetOverlay](#) (size_t i=0)
Overlay: group 60xx.
- const [Overlay](#) & [GetOverlay](#) (size_t i=0) const
- void [Print](#) (std::ostream &) const override
- void [RemoveOverlay](#) (size_t i)
- void [SetIconImage](#) ([IconImage](#) const &ii)
- void [SetNumberOfCurves](#) (size_t n)
- void [SetNumberOfOverlays](#) (size_t n)
- bool [UnusedBitsPresentInPixelData](#) () const override
returns if there are unused bits in the pixel data

Public Member Functions inherited from [gdcm::Bitmap](#)

- [Bitmap](#) ()
- [~Bitmap](#) () override
- void [Clear](#) ()
- bool [GetBuffer](#) (char *buffer) const
Access the raw data.
- unsigned long [GetBufferLength](#) () const
- unsigned int [GetColumns](#) () const
- [DataElement](#) & [GetDataElement](#) ()
- const [DataElement](#) & [GetDataElement](#) () const
- unsigned int [GetDimension](#) (unsigned int idx) const
- const unsigned int * [GetDimensions](#) () const
Return the dimension of the pixel data, first dimension (x), then 2nd (y), then 3rd (z)...
- [LookupTable](#) & [GetLUT](#) ()
- const [LookupTable](#) & [GetLUT](#) () const
- bool [GetNeedByteSwap](#) () const
INTERNAL do not use.
- unsigned int [GetNumberOfDimensions](#) () const
Return the number of dimension of the pixel data bytes; for example 2 for a 2D matrices of values.
- const [PhotometricInterpretation](#) & [GetPhotometricInterpretation](#) () const
return the photometric interpretation
- [PixelFormat](#) & [GetPixelFormat](#) ()

- const [PixelFormat](#) & [GetPixelFormat](#) () const
Get/Set PixelFormat.
- unsigned int [GetPlanarConfiguration](#) () const
return the planar configuration
- unsigned int [GetRows](#) () const
- const [TransferSyntax](#) & [GetTransferSyntax](#) () const
- bool [IsEmpty](#) () const
- bool [IsLossy](#) () const
Return whether or not the image was compressed using a lossy compressor or not.
- bool [IsTransferSyntaxCompatible](#) ([TransferSyntax](#) const &ts) const
- void [SetColumns](#) (unsigned int col)
- void [SetDataElement](#) ([DataElement](#) const &de)
- void [SetDimension](#) (unsigned int idx, unsigned int dim)
- void [SetDimensions](#) (const unsigned int dims[3])
- void [SetLossyFlag](#) (bool f)
Specifically set that the image was compressed using a lossy compression mechanism.
- void [SetLUT](#) ([LookupTable](#) const &lut)
Set/Get LUT.
- void [SetNeedByteSwap](#) (bool b)
- void [SetNumberOfDimensions](#) (unsigned int dim)
- void [SetPhotometricInterpretation](#) ([PhotometricInterpretation](#) const &pi)
- void [SetPixelFormat](#) ([PixelFormat](#) const &pf)
- void [SetPlanarConfiguration](#) (unsigned int pc)
- void [SetRows](#) (unsigned int rows)
- void [SetTransferSyntax](#) ([TransferSyntax](#) const &ts)
Transfer syntax.

Public Member Functions inherited from [gdcm::Object](#)

- [Object](#) ()
- [Object](#) (const [Object](#) &)
Special requirement for copy/cstor, assignment operator.
- virtual [~Object](#) ()
- void [operator=](#) (const [Object](#) &)

Protected Attributes

- std::vector< [Curve](#) > [Curves](#)
- [SmartPointer](#)< [IconImage](#) > [Icon](#)
- std::vector< [Overlay](#) > [Overlays](#)

Protected Attributes inherited from [gdcm::Bitmap](#)

- `std::vector< unsigned int >` [Dimensions](#)
- `bool` [LossyFlag](#)
- `LUTPtr` [LUT](#)
- `bool` [NeedByteSwap](#)
- `unsigned int` [NumberOfDimensions](#)
- `PixelFormat` [PF](#)
- `PhotometricInterpretation` [PI](#)
- `DataElement` [PixelData](#)
- `unsigned int` [PlanarConfiguration](#)
- `TransferSyntax` [TS](#)

Additional Inherited Members

Protected Types inherited from [gdcm::Bitmap](#)

- `typedef` [SmartPointer< LookupTable >](#) [LUTPtr](#)

Protected Member Functions inherited from [gdcm::Bitmap](#)

- `bool` [ComputeLossyFlag](#) ()
- `bool` [GetBuffer2](#) (std::ostream &os) const
- `bool` [TryJPEG2000Codec](#) (char *buffer, bool &lossyflag) const
- `bool` [TryJPEG2000Codec2](#) (std::ostream &os) const
- `bool` [TryJPEGCodec](#) (char *buffer, bool &lossyflag) const
- `bool` [TryJPEGCodec2](#) (std::ostream &os) const
- `bool` [TryJPEGLSCodec](#) (char *buffer, bool &lossyflag) const
- `bool` [TryKAKADUCodec](#) (char *buffer, bool &lossyflag) const
- `bool` [TryPVRGCodec](#) (char *buffer, bool &lossyflag) const
- `bool` [TryRAWCodec](#) (char *buffer, bool &lossyflag) const
- `bool` [TryRLECodec](#) (char *buffer, bool &lossyflag) const

Protected Member Functions inherited from [gdcm::Object](#)

- `void` [Register](#) ()
- `void` [UnRegister](#) ()

10.233.1 Detailed Description

[Pixmap](#) class.

A bitmap based image. Used as parent for both [IconImage](#) and the main Pixel Data [Image](#) It does not contains any World Space information (IPP, IOP)

See also

[PixmapReader](#)

Examples

[FileChangeTS.cs](#), [FileChangeTSLossy.cs](#), and [StandardizeFiles.cs](#).

10.233.2 Constructor & Destructor Documentation

10.233.2.1 Pixmap()

```
gdcm::Pixmap::Pixmap ()
```

10.233.2.2 ~Pixmap()

```
gdcm::Pixmap::~Pixmap () [override]
```

10.233.3 Member Function Documentation

10.233.3.1 AreOverlaysInPixelData()

```
bool gdcm::Pixmap::AreOverlaysInPixelData () const [override], [virtual]
```

returns if Overlays are stored in the unused bit of the pixel data:

Reimplemented from [gdcm::Bitmap](#).

10.233.3.2 GetCurve() [1/2]

```
Curve & gdcm::Pixmap::GetCurve (
    size_t i = 0) [inline]
```

[Curve](#): group 50xx.

References [Curves](#), and [gdcm_assert](#).

10.233.3.3 GetCurve() [2/2]

```
const Curve & gdcm::Pixmap::GetCurve (
    size_t i = 0) const [inline]
```

References [Curves](#), and [gdcm_assert](#).

10.233.3.4 GetIconImage() [1/2]

```
IconImage & gdcm::Pixmap::GetIconImage () [inline]
```

References [Icon](#).

10.233.3.5 GetIconImage() [2/2]

```
const IconImage & gdcm::Pixmap::GetIconImage () const [inline]
```

Set/Get [Icon Image](#).

References [Icon](#).

10.233.3.6 GetNumberOfCurves()

```
size_t gdcm::Pixmap::GetNumberOfCurves () const [inline]
```

References [Curves](#).

10.233.3.7 GetNumberOfOverlays()

```
size_t gdcm::Pixmap::GetNumberOfOverlays () const [inline]
```

References [Overlays](#).

10.233.3.8 GetOverlay() [1/2]

```
Overlay & gdcm::Pixmap::GetOverlay (  
    size_t i = 0) [inline]
```

[Overlay](#): group 60xx.

References [gdcm_assert](#), and [Overlays](#).

10.233.3.9 GetOverlay() [2/2]

```
const Overlay & gdcm::Pixmap::GetOverlay (  
    size_t i = 0) const [inline]
```

References [gdcm_assert](#), and [Overlays](#).

10.233.3.10 Print()

```
void gdcm::Pixmap::Print (  
    std::ostream & ) const [override], [virtual]
```

Reimplemented from [gdcm::Bitmap](#).

10.233.3.11 RemoveOverlay()

```
void gdcm::Pixmap::RemoveOverlay (
    size_t i) [inline]
```

References [gdcm_assert](#), and [Overlays](#).

10.233.3.12 SetIconImage()

```
void gdcm::Pixmap::SetIconImage (
    IconImage const & ii) [inline]
```

References [Icon](#).

10.233.3.13 SetNumberOfCurves()

```
void gdcm::Pixmap::SetNumberOfCurves (
    size_t n) [inline]
```

References [Curves](#).

10.233.3.14 SetNumberOfOverlays()

```
void gdcm::Pixmap::SetNumberOfOverlays (
    size_t n) [inline]
```

References [Overlays](#).

10.233.3.15 UnusedBitsPresentInPixelData()

```
bool gdcm::Pixmap::UnusedBitsPresentInPixelData () const [override], [virtual]
```

returns if there are unused bits in the pixel data

Reimplemented from [gdcm::Bitmap](#).

10.233.4 Member Data Documentation

10.233.4.1 Curves

```
std::vector<Curve> gdcm::Pixmap::Curves [protected]
```

Referenced by [GetCurve\(\)](#), [GetCurve\(\)](#), [GetNumberOfCurves\(\)](#), and [SetNumberOfCurves\(\)](#).

10.233.4.2 Icon

```
SmartPointer<IconImage> gdcM::Pixmap::Icon [protected]
```

Referenced by [GetIconImage\(\)](#), [GetIconImage\(\)](#), and [SetIconImage\(\)](#).

10.233.4.3 Overlays

```
std::vector<Overlay> gdcM::Pixmap::Overlays [protected]
```

Referenced by [GetNumberOfOverlays\(\)](#), [GetOverlay\(\)](#), [GetOverlay\(\)](#), [RemoveOverlay\(\)](#), and [SetNumberOfOverlays\(\)](#).

The documentation for this class was generated from the following file:


- [gdcMPixmap.h](#)

10.234 gdcM::PixmapReader Class Reference


[PixmapReader](#).

```
#include <gdcMPixmapReader.h>
```

Inheritance diagram for gdcM::PixmapReader:



Collaboration diagram for gdcm::PixmapReader:



Public Member Functions

- [PixmapReader](#) ()
- [~PixmapReader](#) () override
- [Pixmap](#) & [GetPixmap](#) ()
- const [Pixmap](#) & [GetPixmap](#) () const
Return the read image (need to call [Read\(\)](#) first)
- bool [Read](#) () override

Public Member Functions inherited from [gdcm::Reader](#)

- [Reader](#) ()
- virtual [~Reader](#) ()
- bool [CanRead](#) () const
- [File](#) & [GetFile](#) ()
Set/Get [File](#).
- const [File](#) & [GetFile](#) () const
Set/Get [File](#).
- size_t [GetStreamCurrentPosition](#) () const

- bool [ReadSelectedPrivateTags](#) (std::set< [PrivateTag](#) > const &ptags, bool readvalues=true)
Will only read the specified selected private tags.
- bool [ReadSelectedTags](#) (std::set< [Tag](#) > const &tags, bool readvalues=true)
Will only read the specified selected tags.
- bool [ReadUpToTag](#) (const [Tag](#) &tag, std::set< [Tag](#) > const &skiptags=std::set< [Tag](#) >())
- void [SetFile](#) ([File](#) &file)
Set/Get [File](#).
- void [SetFileName](#) (const char *filename_native)
- void [SetStream](#) (std::istream &input_stream)
Set the open-ed stream directly.

Protected Member Functions

- virtual bool [ReadACRNEMAIImage](#) ()
- virtual bool [ReadImage](#) ([MediaStorage](#) const &ms)
- bool [ReadImageInternal](#) ([MediaStorage](#) const &ms, bool handlepixeldata=true)

Protected Member Functions inherited from [gdcm::Reader](#)

- std::istream * [GetStreamPtr](#) () const
- bool [ReadDataSet](#) ()
- bool [ReadMetaInformation](#) ()
- bool [ReadPreamble](#) ()

Protected Attributes

- [SmartPointer](#)< [Pixmap](#) > [PixelData](#)

Protected Attributes inherited from [gdcm::Reader](#)

- [SmartPointer](#)< [File](#) > [F](#)

10.234.1 Detailed Description

[PixmapReader](#).

Note

its role is to convert the DICOM [DataSet](#) into a [Pixmap](#) representation By default it is also loading the lookup table and overlay when found as they impact the rendering or the image

See PS 3.3-2008, [Table C.7-11b](#) IMAGE PIXEL MACRO ATTRIBUTES for the list of attribute that belong to what gdcm calls a '[Pixmap](#)'

Warning

the API [ReadUpToTag](#) and [ReadSelectedTag](#)

See also

[Pixmap](#)

Examples

[StandardizeFiles.cs](#).

10.234.2 Constructor & Destructor Documentation

10.234.2.1 PixmapReader()

```
gdcm::PixmapReader::PixmapReader ()
```

10.234.2.2 ~PixmapReader()

```
gdcm::PixmapReader::~~PixmapReader () [override]
```

10.234.3 Member Function Documentation

10.234.3.1 GetPixmap() [1/2]

```
Pixmap & gdcm::PixmapReader::GetPixmap ()
```

10.234.3.2 GetPixmap() [2/2]

```
const Pixmap & gdcm::PixmapReader::GetPixmap () const
```

Return the read image (need to call [Read\(\)](#) first)

Examples

[StandardizeFiles.cs](#).

10.234.3.3 Read()

```
bool gdcm::PixmapReader::Read () [override], [virtual]
```

Read the DICOM image. There are two reason for failure:

1. The input filename is not DICOM
2. The input DICOM file does not contains an [Pixmap](#).

Reimplemented from [gdcm::Reader](#).

Examples

[StandardizeFiles.cs](#).

10.234.3.4 ReadACRNEMAIImage()

```
virtual bool gdcm::PixmapReader::ReadACRNEMAIImage () [protected], [virtual]
```

Reimplemented in [gdcm::ImageReader](#).

10.234.3.5 ReadImage()

```
virtual bool gdcm::PixmapReader::ReadImage (
    MediaStorage const & ms) [protected], [virtual]
```

Reimplemented in [gdcm::ImageReader](#).

10.234.3.6 ReadImageInternal()

```
bool gdcm::PixmapReader::ReadImageInternal (
    MediaStorage const & ms,
    bool handlepixeldata = true) [protected]
```

10.234.4 Member Data Documentation

10.234.4.1 PixelData

```
SmartPointer<Pixmap> gdcm::PixmapReader::PixelData [protected]
```

The documentation for this class was generated from the following file:

- [gdcmPixmapReader.h](#)

10.235 gdcm::PixmapToPixmapFilter Class Reference


[PixmapToPixmapFilter](#) class.

```
#include <gdcmPixmapToPixmapFilter.h>
```

Inheritance diagram for `gdcm::PixmapToPixmapFilter`:



Collaboration diagram for gdcm::PixmapToPixmapFilter:



Public Member Functions

- [PixmapToPixmapFilter](#) ()
- [~PixmapToPixmapFilter](#) ()=default
- [Pixmap](#) & [GetInput](#) ()
- const [Pixmap](#) & [GetOutput](#) () const
Get Output image.
- const [Pixmap](#) & [GetOutputAsPixmap](#) () const

Public Member Functions inherited from [gdcm::BitmapToBitmapFilter](#)

- [BitmapToBitmapFilter](#) ()
- [~BitmapToBitmapFilter](#) ()=default
- const [Bitmap](#) & [GetOutput](#) () const
Get Output image.
- const [Bitmap](#) & [GetOutputAsBitmap](#) () const
- void [SetInput](#) (const [Bitmap](#) &image)
Set input image.

Additional Inherited Members

Protected Attributes inherited from [gdcm::BitmapToBitmapFilter](#)

- [SmartPointer](#)< [Bitmap](#) > Input
- [SmartPointer](#)< [Bitmap](#) > Output

10.235.1 Detailed Description

[PixmapToPixmapFilter](#) class.

Super class for all filter taking an image and producing an output image

Examples

[StandardizeFiles.cs](#).

10.235.2 Constructor & Destructor Documentation

10.235.2.1 [PixmapToPixmapFilter](#)()

```
gdcm::PixmapToPixmapFilter::PixmapToPixmapFilter ()
```

10.235.2.2 [~PixmapToPixmapFilter](#)()

```
gdcm::PixmapToPixmapFilter::~~PixmapToPixmapFilter () [default]
```

10.235.3 Member Function Documentation

10.235.3.1 [GetInput](#)()

```
Pixmap & gdcm::PixmapToPixmapFilter::GetInput ()
```

10.235.3.2 [GetOutput](#)()

```
const Pixmap & gdcm::PixmapToPixmapFilter::GetOutput () const
```

Get Output image.

10.235.3.3 GetOutputAsPixmap()

```
const Pixmap & gdcm::PixmapToPixmapFilter::GetOutputAsPixmap () const
```

The documentation for this class was generated from the following file:


- [gdcmPixmapToPixmapFilter.h](#)

10.236 gdcm::PixmapWriter Class Reference


[PixmapWriter](#).

```
#include <gdcmPixmapWriter.h>
```

Inheritance diagram for gdcm::PixmapWriter:



Collaboration diagram for `gdcm::PixmapWriter`:



Public Member Functions

- `PixmapWriter ()`
- `~PixmapWriter ()` override
- virtual `Pixmap & GetImage ()`
- virtual const `Pixmap & GetImage ()` const
- `Pixmap & GetPixmap ()`
- const `Pixmap & GetPixmap ()` const
- virtual void `SetImage (Pixmap const &img)`
- void `SetPixmap (Pixmap const &img)`
- bool `Write ()` override

Write.

Public Member Functions inherited from [gdcm::Writer](#)

- [Writer](#) ()
- virtual [~Writer](#) ()
- void [CheckFileMetaInformationOff](#) ()
- void [CheckFileMetaInformationOn](#) ()
- [File](#) & [GetFile](#) ()
- void [SetCheckFileMetaInformation](#) (bool b)
Undocumented function, do not use (= leave default)
- void [SetFile](#) (const [File](#) &f)
Set/Get the DICOM file ([DataSet](#) + Header)
- void [SetFileName](#) (const char *filename_native)
Set the filename of DICOM file to write:
- void [SetStream](#) (std::ostream &output_stream)
Set user ostream buffer.

Protected Member Functions

- void [DolconImage](#) ([DataSet](#) &ds, [Pixmap](#) const &image)
- bool [PrepareWrite](#) ([MediaStorage](#) const &refms)

Protected Member Functions inherited from [gdcm::Writer](#)

- bool [GetCheckFileMetaInformation](#) () const
- std::ostream * [GetStreamPtr](#) () const
- void [SetWriteDataSetOnly](#) (bool b)

Protected Attributes

- [SmartPointer](#)< [Pixmap](#) > [PixelData](#)

Protected Attributes inherited from [gdcm::Writer](#)

- std::ofstream * [Ofstream](#)
- std::ostream * [Stream](#)

10.236.1 Detailed Description

[PixmapWriter](#).

This class will takes two inputs:

1. The DICOM [DataSet](#)
2. The [Image](#) input It will override any info from the [Image](#) over the [DataSet](#).

For instance when one read in a lossy compressed image and write out as unencapsulated (ie implicitly lossless) then some attribute are definitely needed to mark this dataset as Lossy (typically 0028,2114)

Examples

[StandardizeFiles.cs](#).

10.236.2 Constructor & Destructor Documentation

10.236.2.1 PixmapWriter()

```
gdcm::PixmapWriter::PixmapWriter ()
```

10.236.2.2 ~PixmapWriter()

```
gdcm::PixmapWriter::~~PixmapWriter () [override]
```

10.236.3 Member Function Documentation

10.236.3.1 DoIconImage()

```
void gdcm::PixmapWriter::DoIconImage (  
    DataSet & ds,  
    Pixmap const & image) [protected]
```

10.236.3.2 GetImage() [1/2]

```
virtual Pixmap & gdcm::PixmapWriter::GetImage () [inline], [virtual]
```

Reimplemented in [gdcm::ImageWriter](#).

References [PixelData](#).

10.236.3.3 GetImage() [2/2]

```
virtual const Pixmap & gdcm::PixmapWriter::GetImage () const [inline], [virtual]
```

Set/Get [Pixmap](#) to be written It will overwrite anything [Pixmap](#) infos found in [DataSet](#) (see parent class to see how to pass dataset)

Reimplemented in [gdcm::ImageWriter](#).

References [PixelData](#).

10.236.3.4 GetPixmap() [1/2]

```
Pixmap & gdcm::PixmapWriter::GetPixmap () [inline]
```

References [PixelData](#).

10.236.3.5 GetPixmap() [2/2]

```
const Pixmap & gdcm::PixmapWriter::GetPixmap () const [inline]
```

References [PixelData](#).

10.236.3.6 PrepareWrite()

```
bool gdcm::PixmapWriter::PrepareWrite (  
    MediaStorage const & refs) [protected]
```

10.236.3.7 SetImage()

```
virtual void gdcm::PixmapWriter::SetImage (  
    Pixmap const & img) [virtual]
```

Examples

[BasicImageAnonymizer.cs](#), [CompressImage.cxx](#), [CompressLossyJPEG.cs](#), [DecompressImage.cs](#), [GenFakeImage.cxx](#), [GetSubSequenceData.cxx](#), [HelloVizWorld.cxx](#), [MergeTwoFiles.cxx](#), [MpegVideoInfo.cs](#), and [TemplateEmptyImage.cxx](#).

10.236.3.8 SetPixmap()

```
void gdcm::PixmapWriter::SetPixmap (  
    Pixmap const & img)
```

Examples

[StandardizeFiles.cs](#).

10.236.3.9 Write()

```
bool gdcm::PixmapWriter::Write () [override], [virtual]
```

Write.

Reimplemented from [gdcm::Writer](#).

Examples

[StandardizeFiles.cs](#).

10.236.4 Member Data Documentation

10.236.4.1 PixelData

`SmartPointer<Pixmap> gdcM::PixmapWriter::PixelData` [protected]

Referenced by [GetImage\(\)](#), [GetImage\(\)](#), [GetPixmap\(\)](#), and [GetPixmap\(\)](#).

The documentation for this class was generated from the following file:


- [gdcMPixmapWriter.h](#)

10.237 gdcM::PNMCodec Class Reference


Class to do PNM.

```
#include <gdcMPNMCodec.h>
```

Inheritance diagram for gdcM::PNMCodec:



Collaboration diagram for gdcm::PNMCodec:



Public Member Functions

- [PNMCodec](#) ()
- [~PNMCodec](#) () override
- bool [CanCode](#) ([TransferSyntax](#) const &ts) const override
Return whether this coder support this transfer syntax (can code it)
- bool [CanDecode](#) ([TransferSyntax](#) const &ts) const override
Return whether this decoder support this transfer syntax (can decode it)
- [ImageCodec](#) * [Clone](#) () const override
- unsigned long [GetBufferLength](#) () const
- bool [GetHeaderInfo](#) (std::istream &is, [TransferSyntax](#) &ts) override
- bool [Read](#) (const char *filename, [DataElement](#) &out) const
- void [SetBufferLength](#) (unsigned long l)
- bool [Write](#) (const char *filename, const [DataElement](#) &out) const

Public Member Functions inherited from [gdcm::ImageCodec](#)

- [ImageCodec](#) ()
- [~ImageCodec](#) () override
- bool [CleanupUnusedBits](#) (char *data, size_t datalen)
- bool [Decode](#) ([DataElement](#) const &is_, [DataElement](#) &os) override
Decode.
- const unsigned int * [GetDimensions](#) () const
- bool [GetLossyFlag](#) () const
- const [LookupTable](#) & [GetLUT](#) () const
- bool [GetNeedByteSwap](#) () const
- unsigned int [GetNumberOfDimensions](#) () const
- const [PhotometricInterpretation](#) & [GetPhotometricInterpretation](#) () const
- [PixelFormat](#) & [GetPixelFormat](#) ()
- const [PixelFormat](#) & [GetPixelFormat](#) () const
- unsigned int [GetPlanarConfiguration](#) () const
- bool [IsLossy](#) () const
- void [SetDimensions](#) (const std::vector< unsigned int > &d)
- void [SetDimensions](#) (const unsigned int d[3])
- void [SetLossyFlag](#) (bool l)
- void [SetLUT](#) ([LookupTable](#) const &lut)

- void [SetNeedByteSwap](#) (bool b)
- void [SetNeedOverlayCleanup](#) (bool b)
- void [SetNumberOfDimensions](#) (unsigned int dim)
- void [SetPhotometricInterpretation](#) ([PhotometricInterpretation](#) const &pi)
- virtual void [SetPixelFormat](#) ([PixelFormat](#) const &pf)
- void [SetPlanarConfiguration](#) (unsigned int pc)

Public Member Functions inherited from [gdcm::Coder](#)

- virtual [~Coder](#) ()=default
- virtual bool [Code](#) ([DataElement](#) const &in_, [DataElement](#) &out_)
Code.

Public Member Functions inherited from [gdcm::Decoder](#)

- virtual [~Decoder](#) ()=default

Additional Inherited Members

Protected Types inherited from [gdcm::ImageCodec](#)

- typedef [SmartPointer](#)< [LookupTable](#) > [LUTPtr](#)

Protected Member Functions inherited from [gdcm::ImageCodec](#)

- virtual bool [AppendFrameEncode](#) (std::ostream &out, const char *data, size_t datalen)
- virtual bool [AppendRowEncode](#) (std::ostream &out, const char *data, size_t datalen)
- bool [DecodeByStreams](#) (std::istream &is_, std::ostream &os) override
- bool [DoByteSwap](#) (std::istream &is_, std::ostream &os)
- bool [DoInvertMonochrome](#) (std::istream &is_, std::ostream &os)
- bool [DoOverlayCleanup](#) (std::istream &is_, std::ostream &os)
- bool [DoPaddedCompositePixelCode](#) (std::istream &is_, std::ostream &os)
- bool [DoPlanarConfiguration](#) (std::istream &is_, std::ostream &os)
- bool [DoSimpleCopy](#) (std::istream &is_, std::ostream &os)
- bool [DoYBR](#) (std::istream &is_, std::ostream &os)
- bool [DoYBRFull422](#) (std::istream &is_, std::ostream &os)
- virtual bool [IsFrameEncoder](#) ()
- virtual bool [IsRowEncoder](#) ()
- virtual bool [IsValid](#) ([PhotometricInterpretation](#) const &pi)
- virtual bool [StartEncode](#) (std::ostream &os)
- virtual bool [StopEncode](#) (std::ostream &os)

Protected Member Functions inherited from [gdcm::Coder](#)

- virtual bool [InternalCode](#) (const char *bv, unsigned long len, std::ostream &os)

Protected Attributes inherited from [gdcm::ImageCodec](#)

- unsigned int [Dimensions](#) [3]
- bool [LossyFlag](#)
- [LUTPtr](#) LUT
- bool [NeedByteSwap](#)
- bool [NeedOverlayCleanup](#)
- unsigned int [NumberOfDimensions](#)
- [PixelFormat](#) PF
- [PhotometricInterpretation](#) PI
- unsigned int [PlanarConfiguration](#)
- bool [RequestPaddedCompositePixelCode](#)
- bool [RequestPlanarConfiguration](#)

10.237.1 Detailed Description

Class to do PNM.

PNM is the Portable anymap file format. The main web page can be found at: <http://netpbm.sourceforge.net/>.↵

Note

Only support P5 & P6 PNM file (binary grayscale and binary rgb)

Examples

[ExtractIconFromFile.cxx](#).

10.237.2 Constructor & Destructor Documentation

10.237.2.1 PNMCodec()

```
gdcm::PNMCodec::PNMCodec ()
```

10.237.2.2 ~PNMCodec()

```
gdcm::PNMCodec::~~PNMCodec () [override]
```

10.237.3 Member Function Documentation

10.237.3.1 CanCode()

```
bool gdcm::PNMCodec::CanCode (
    TransferSyntax const & ) const [override], [virtual]
```

Return whether this coder support this transfer syntax (can code it)

Reimplemented from [gdcm::ImageCodec](#).

10.237.3.2 CanDecode()

```
bool gdcM::PNMCodec::CanDecode (
    TransferSyntax const & ) const [override], [virtual]
```

Return whether this decoder support this transfer syntax (can decode it)

Reimplemented from [gdcM::ImageCodec](#).

10.237.3.3 Clone()

```
ImageCodec * gdcM::PNMCodec::Clone () const [override], [virtual]
```

Implements [gdcM::ImageCodec](#).

References [gdcM::ImageCodec::ImageCodec\(\)](#).

10.237.3.4 GetBufferLength()

```
unsigned long gdcM::PNMCodec::GetBufferLength () const [inline]
```

10.237.3.5 GetHeaderInfo()

```
bool gdcM::PNMCodec::GetHeaderInfo (
    std::istream & is,
    TransferSyntax & ts) [override], [virtual]
```

Reimplemented from [gdcM::ImageCodec](#).

10.237.3.6 Read()

```
bool gdcM::PNMCodec::Read (
    const char * filename,
    DataElement & out) const
```

10.237.3.7 SetBufferLength()

```
void gdcM::PNMCodec::SetBufferLength (
    unsigned long l) [inline]
```

10.237.3.8 Write()

```
bool gdcm::PNMCodec::Write (
    const char * filename,
    const DataElement & out) const
```

Examples

[ExtractIconFromFile.cxx](#).

The documentation for this class was generated from the following file:

- [gdcmPNMCodec.h](#)

10.238 gdcm::Preamble Class Reference

DICOM [Preamble](#) (Part 10)

```
#include <gdcmPreamble.h>
```

Public Member Functions

- [Preamble](#) ()
- [Preamble](#) ([Preamble](#) const &)
- [~Preamble](#) ()
- void [Clear](#) ()
Clear.
- void [Create](#) ()
- const char * [GetInternal](#) () const
Get internal pointer to preamble.
- [VL GetLength](#) () const
Return size of [Preamble](#).
- bool [IsEmpty](#) () const
Check if [Preamble](#) is empty.
- [Preamble](#) & [operator=](#) ([Preamble](#) const &)
- void [Print](#) (std::ostream &os) const
Print [Preamble](#).
- std::istream & [Read](#) (std::istream &is)
Read [Preamble](#).
- void [Remove](#) ()
- void [Valid](#) ()
Set [Preamble](#) to the default one.
- std::ostream const & [Write](#) (std::ostream &os) const
Write [Preamble](#).

Protected Member Functions

- bool [IsValid](#) () const

Friends

- std::ostream & [operator<<](#) (std::ostream &_os, const [Preamble](#) &_val)

10.238.1 Detailed Description

DICOM [Preamble](#) (Part 10)

10.238.2 Constructor & Destructor Documentation

10.238.2.1 Preamble() [1/2]

```
gdcm::Preamble::Preamble ()
```

Referenced by [Preamble\(\)](#), [~Preamble\(\)](#), [operator<<](#), and [operator=\(\)](#).

10.238.2.2 ~Preamble()

```
gdcm::Preamble::~~Preamble ()
```

References [Preamble\(\)](#), and [operator<<](#).

10.238.2.3 Preamble() [2/2]

```
gdcm::Preamble::Preamble (
    Preamble const & ) [inline]
```

References [Preamble\(\)](#), and [Create\(\)](#).

10.238.3 Member Function Documentation

10.238.3.1 Clear()

```
void gdcm::Preamble::Clear ()
```

Clear.

10.238.3.2 Create()

```
void gdcm::Preamble::Create ()
```

Referenced by [Preamble\(\)](#), and [operator=\(\)](#).

10.238.3.3 GetInternal()

```
const char * gdcm::Preamble::GetInternal () const [inline]
```

Get internal pointer to preamble.

10.238.3.4 GetLength()

```
VL gdcm::Preamble::GetLength () const [inline]
```

Return size of [Preamble](#).

10.238.3.5 IsEmpty()

```
bool gdcm::Preamble::IsEmpty () const [inline]
```

Check if [Preamble](#) is empty.

10.238.3.6 IsValid()

```
bool gdcm::Preamble::IsValid () const [inline], [protected]
```

10.238.3.7 operator=()

```
Preamble & gdcm::Preamble::operator= (  
    Preamble const & ) [inline]
```

References [Preamble\(\)](#), and [Create\(\)](#).

10.238.3.8 Print()

```
void gdcm::Preamble::Print (  
    std::ostream & os) const
```

Print [Preamble](#).

10.238.3.9 Read()

```
std::istream & gdcM::Preamble::Read (  
    std::istream & is)
```

Read [Preamble](#).

10.238.3.10 Remove()

```
void gdcM::Preamble::Remove ()
```

10.238.3.11 Valid()

```
void gdcM::Preamble::Valid ()
```

Set [Preamble](#) to the default one.

10.238.3.12 Write()

```
std::ostream const & gdcM::Preamble::Write (  
    std::ostream & os) const
```

Write [Preamble](#).

10.238.4 Friends And Related Symbol Documentation

10.238.4.1 operator<<

```
std::ostream & operator<< (  
    std::ostream & _os,  
    const Preamble & _val) [friend]
```

References [Preamble\(\)](#).

Referenced by [~Preamble\(\)](#).

The documentation for this class was generated from the following file:


- [gdcM_Preamble.h](#)

10.239 gdcm::PresentationContext Class Reference

[PresentationContext](#).

```
#include <gdcmPresentationContext.h>
```

Collaboration diagram for gdcm::PresentationContext:



Public Types

- typedef TransferSyntaxArrayType::size_type [SizeType](#)
- typedef std::vector< std::string > [TransferSyntaxArrayType](#)

Public Member Functions

- [PresentationContext](#) ()
- [PresentationContext](#) (UIDs::TSName asname, UIDs::TSName tsname=UIDs::ImplicitVRLittleEndianDefaultTransferSyntaxforDICOM)
- void [AddTransferSyntax](#) (const char *sstr)
- const char * [GetAbstractSyntax](#) () const
- [SizeType](#) [GetNumberOfTransferSyntaxes](#) () const
- uint8_t [GetPresentationContextID](#) () const
- const char * [GetTransferSyntax](#) ([SizeType](#) i) const
- bool [operator==](#) (const [PresentationContext](#) &pc) const
- void [Print](#) (std::ostream &os) const
- void [SetAbstractSyntax](#) (const char *absyn)
- void [SetPresentationContextID](#) (uint8_t id)

Protected Attributes

- std::string [AbstractSyntax](#)
- uint8_t [ID](#)
- std::vector< std::string > [TransferSyntaxes](#)

10.239.1 Detailed Description

[PresentationContext](#).

See also

[PresentationContextAC](#) [PresentationContextRQ](#)

10.239.2 Member Typedef Documentation**10.239.2.1 SizeType**

```
typedef TransferSyntaxArrayType::size_type gdcmm::PresentationContext::SizeType
```

10.239.2.2 TransferSyntaxArrayType

```
typedef std::vector<std::string> gdcmm::PresentationContext::TransferSyntaxArrayType
```

10.239.3 Constructor & Destructor Documentation**10.239.3.1 PresentationContext() [1/2]**

```
gdcmm::PresentationContext::PresentationContext ()
```

Referenced by [operator==\(.\)](#).

10.239.3.2 PresentationContext() [2/2]

```
gdcmm::PresentationContext::PresentationContext (
    UIDs::TSName asname,
    UIDs::TSName tsname = UIDs::ImplicitVRLittleEndianDefaultTransferSyntaxforDICOM)
```

Initialize Presentation Context with AbstractSyntax set to asname and with a single [TransferSyntax](#) set to tsname (default to Implicit [VR](#) LittleEndian when not specified).

References [gdcmm::UIDs::ImplicitVRLittleEndianDefaultTransferSyntaxforDICOM](#).

10.239.4 Member Function Documentation

10.239.4.1 AddTransferSyntax()

```
void gdcm::PresentationContext::AddTransferSyntax (
    const char * tsstr)
```

10.239.4.2 GetAbstractSyntax()

```
const char * gdcm::PresentationContext::GetAbstractSyntax () const [inline]
```

References [AbstractSyntax](#).

10.239.4.3 GetNumberOfTransferSyntaxes()

```
SizeType gdcm::PresentationContext::GetNumberOfTransferSyntaxes () const [inline]
```

References [TransferSyntaxes](#).

10.239.4.4 GetPresentationContextID()

```
uint8_t gdcm::PresentationContext::GetPresentationContextID () const
```

10.239.4.5 GetTransferSyntax()

```
const char * gdcm::PresentationContext::GetTransferSyntax (
    SizeType i) const [inline]
```

References [TransferSyntaxes](#).

10.239.4.6 operator==()

```
bool gdcm::PresentationContext::operator== (
    const PresentationContext & pc) const [inline]
```

References [PresentationContext\(\)](#), [AbstractSyntax](#), [gdcm_assert](#), and [TransferSyntaxes](#).

10.239.4.7 Print()

```
void gdcm::PresentationContext::Print (
    std::ostream & os) const
```

10.239.4.8 SetAbstractSyntax()

```
void gdcM::PresentationContext::SetAbstractSyntax (  
    const char * absyn)    [inline]
```

References [AbstractSyntax](#).

10.239.4.9 SetPresentationContextID()

```
void gdcM::PresentationContext::SetPresentationContextID (  
    uint8_t id)
```

10.239.5 Member Data Documentation

10.239.5.1 AbstractSyntax

```
std::string gdcM::PresentationContext::AbstractSyntax    [protected]
```

Referenced by [GetAbstractSyntax\(\)](#), [operator==\(\)](#), and [SetAbstractSyntax\(\)](#).

10.239.5.2 ID

```
uint8_t gdcM::PresentationContext::ID    [protected]
```

10.239.5.3 TransferSyntaxes

```
std::vector<std::string> gdcM::PresentationContext::TransferSyntaxes    [protected]
```

Referenced by [GetNumberOfTransferSyntaxes\(\)](#), [GetTransferSyntax\(\)](#), and [operator==\(\)](#).

The documentation for this class was generated from the following file:

- [gdcMPresentationContext.h](#)

10.240 gdcM::network::PresentationContextAC Class Reference

[PresentationContextAC](#).

```
#include <gdcMPresentationContextAC.h>
```

Public Member Functions

- [PresentationContextAC](#) ()
- [uint8_t GetPresentationContextID](#) () const
- [uint8_t GetReason](#) () const
- [TransferSyntaxSub](#) const & [GetTransferSyntax](#) () const
- void [Print](#) (std::ostream &os) const
- std::istream & [Read](#) (std::istream &is)
- void [SetPresentationContextID](#) (uint8_t id)
- void [SetReason](#) (uint8_t r)
- void [SetTransferSyntax](#) ([TransferSyntaxSub](#) const &ts)
- [size_t Size](#) () const
- const std::ostream & [Write](#) (std::ostream &os) const

10.240.1 Detailed Description

[PresentationContextAC](#).

[Table](#) 9-18 PRESENTATION CONTEXT ITEM FIELDS

See also

[PresentationContext](#)

10.240.2 Constructor & Destructor Documentation

10.240.2.1 PresentationContextAC()

```
gdcm::network::PresentationContextAC::PresentationContextAC ()
```

10.240.3 Member Function Documentation

10.240.3.1 GetPresentationContextID()

```
uint8_t gdcm::network::PresentationContextAC::GetPresentationContextID () const [inline]
```

10.240.3.2 GetReason()

```
uint8_t gdcm::network::PresentationContextAC::GetReason () const [inline]
```

10.240.3.3 GetTransferSyntax()

```
TransferSyntaxSub const & gdcm::network::PresentationContextAC::GetTransferSyntax () const [inline]
```

10.240.3.4 Print()

```
void gdcm::network::PresentationContextAC::Print (
    std::ostream & os) const
```

10.240.3.5 Read()

```
std::istream & gdcm::network::PresentationContextAC::Read (
    std::istream & is)
```

10.240.3.6 SetPresentationContextID()

```
void gdcm::network::PresentationContextAC::SetPresentationContextID (
    uint8_t id)
```

10.240.3.7 SetReason()

```
void gdcm::network::PresentationContextAC::SetReason (
    uint8_t r) [inline]
```

10.240.3.8 SetTransferSyntax()

```
void gdcm::network::PresentationContextAC::SetTransferSyntax (
    TransferSyntaxSub const & ts)
```

10.240.3.9 Size()

```
size_t gdcm::network::PresentationContextAC::Size () const
```

10.240.3.10 Write()

```
const std::ostream & gdcm::network::PresentationContextAC::Write (
    std::ostream & os) const
```

The documentation for this class was generated from the following file:

- [gdcmPresentationContextAC.h](#)

10.241 gdcm::PresentationContextGenerator Class Reference

[PresentationContextGenerator](#).

```
#include <gdcmPresentationContextGenerator.h>
```

Public Types

- typedef std::vector< [PresentationContext](#) > [PresentationContextArrayType](#)
- typedef [PresentationContextArrayType](#)::size_type [SizeType](#)

Public Member Functions

- [PresentationContextGenerator](#) ()
- bool [AddFromFile](#) (const [File](#) &file)
- bool [GenerateFromFilenames](#) (const [Directory::FilenamesType](#) &files)
- bool [GenerateFromUID](#) ([UIDs::TSName](#) asname)
Generate the [PresentationContext](#) array from a UID (eg. [VerificationSOPClass](#))
- [PresentationContextArrayType](#) const & [GetPresentationContexts](#) ()
- void [SetDefaultTransferSyntax](#) (const [TransferSyntax](#) &ts)
Not implemented for now. GDCM internally uses Implicit Little Endian.
- void [SetMergeModeToAbstractSyntax](#) ()
- void [SetMergeModeToTransferSyntax](#) ()

Protected Member Functions

- bool [AddPresentationContext](#) (const char *absyn, const char *ts)
- const char * [GetDefaultTransferSyntax](#) () const

10.241.1 Detailed Description

[PresentationContextGenerator](#).

This class is responsible for generating the proper [PresentationContext](#) that will be used in subsequent operation during a DICOM Query/Retrieve association. The step of the association is very sensible as special care need to be taken to explicitly define what instance are going to be send and how they are encoded.

For example a [PresentationContext](#) will express that negotiation requires that CT [Image](#) Storage are send using JPEG Lossless, while US [Image](#) Storage are sent using RLE Transfer Syntax.

Two very different API are exposed one which will always default to little endian transfer syntax see [GenerateFromUID\(\)](#) This API is used for C-ECHO, C-FIND and C-MOVE (SCU). Another API: [GenerateFromFilenames\(\)](#) is used for C-↔ STORE (SCU) as it will loop over all filenames argument to detect the actual encoding. and therefore find the proper encoding to be used.

Two modes are available. The default mode ([SetMergeModeToAbstractSyntax](#)) append [PresentationContext](#) (one [AbstractSyntax](#) and one [TransferSyntax](#)), as long a they are different. Eg MR [Image](#) Storage/JPEG2000 and MR [Image](#) Storage/JPEGLossless would be considered different. the other mode [SetMergeModeToTransferSyntax](#) merge any new [TransferSyntax](#) to the already existing [PresentationContext](#) in order to re-use the same [AbstractSyntax](#).

See also

[PresentationContext](#)

Examples

[CStoreQtProgress.cxx](#).

10.241.2 Member Typedef Documentation

10.241.2.1 PresentationContextArrayType

```
typedef std::vector<PresentationContext> gdcm::PresentationContextGenerator::PresentationContextArrayType
```

10.241.2.2 SizeType

```
typedef PresentationContextArrayType::size_type gdcm::PresentationContextGenerator::SizeType
```

10.241.3 Constructor & Destructor Documentation

10.241.3.1 PresentationContextGenerator()

```
gdcm::PresentationContextGenerator::PresentationContextGenerator ()
```

10.241.4 Member Function Documentation

10.241.4.1 AddFromFile()

```
bool gdcm::PresentationContextGenerator::AddFromFile (
    const File & file)
```

Add a single [PresentationContext](#) from a single [File](#). Call multiple times when dealing with multiple files.

10.241.4.2 AddPresentationContext()

```
bool gdcm::PresentationContextGenerator::AddPresentationContext (
    const char * absyn,
    const char * ts) [protected]
```

10.241.4.3 GenerateFromFileNames()

```
bool gdcm::PresentationContextGenerator::GenerateFromFileNames (
    const Directory::FileNamesType & files)
```

Generate the [PresentationContext](#) array from a File-Set. [File](#) specified needs to be valid DICOM files. Used for C-↔-STORE operations

Examples

[CStoreQtProgress.cxx](#).

10.241.4.4 GenerateFromUID()

```
bool gdcm::PresentationContextGenerator::GenerateFromUID (
    UIDs::TSName asname)
```

Generate the [PresentationContext](#) array from a UID (eg. VerificationSOPClass)

10.241.4.5 GetDefaultTransferSyntax()

```
const char * gdcm::PresentationContextGenerator::GetDefaultTransferSyntax () const [protected]
```

10.241.4.6 GetPresentationContexts()

```
PresentationContextArrayType const & gdcm::PresentationContextGenerator::GetPresentationContexts
() [inline]
```

Examples

[CStoreQtProgress.cxx](#).

10.241.4.7 SetDefaultTransferSyntax()

```
void gdcm::PresentationContextGenerator::SetDefaultTransferSyntax (
    const TransferSyntax & ts)
```

Not implemented for now. GDCM internally uses Implicit Little Endian.

10.241.4.8 SetMergeModeToAbstractSyntax()

```
void gdcm::PresentationContextGenerator::SetMergeModeToAbstractSyntax ()
```

10.241.4.9 SetMergeModeToTransferSyntax()

```
void gdcm::PresentationContextGenerator::SetMergeModeToTransferSyntax ()
```

The documentation for this class was generated from the following file:

- [gdcmPresentationContextGenerator.h](#)

10.242 gdcm::network::PresentationContextRQ Class Reference

[PresentationContextRQ.](#)

```
#include <gdcmPresentationContextRQ.h>
```

Public Types

- typedef std::vector< [TransferSyntaxSub](#) >::size_type [SizeType](#)

Public Member Functions

- [PresentationContextRQ](#) ()
- [PresentationContextRQ](#) (const [PresentationContext](#) &pc)
- [PresentationContextRQ](#) (UIDs::TSName asname, UIDs::TSName tsname=UIDs::ImplicitVRLittleEndianDefaultTransferSyntaxforDICOM)
- void [AddTransferSyntax](#) ([TransferSyntaxSub](#) const &ts)
- [AbstractSyntax](#) & [GetAbstractSyntax](#) ()
- [AbstractSyntax](#) const & [GetAbstractSyntax](#) () const
- [SizeType](#) [GetNumberOfTransferSyntaxes](#) () const
- uint8_t [GetPresentationContextID](#) () const
- [TransferSyntaxSub](#) & [GetTransferSyntax](#) ([SizeType](#) i)
- [TransferSyntaxSub](#) const & [GetTransferSyntax](#) ([SizeType](#) i) const
- std::vector< [TransferSyntaxSub](#) > const & [GetTransferSyntaxes](#) () const
- bool [operator==](#) (const [PresentationContextRQ](#) &pc) const
- void [Print](#) (std::ostream &os) const
- std::istream & [Read](#) (std::istream &is)
- void [SetAbstractSyntax](#) ([AbstractSyntax](#) const &absyn)
- void [SetPresentationContextID](#) (uint8_t id)
- size_t [Size](#) () const
- const std::ostream & [Write](#) (std::ostream &os) const

10.242.1 Detailed Description

[PresentationContextRQ.](#)

[Table 9-13 PRESENTATION CONTEXT ITEM FIELDS](#)

See also

[PresentationContextAC](#)

10.242.2 Member Typedef Documentation

10.242.2.1 SizeType

```
typedef std::vector<TransferSyntaxSub>::size_type gdcm::network::PresentationContextRQ::SizeType
```

10.242.3 Constructor & Destructor Documentation

10.242.3.1 PresentationContextRQ() [1/3]

```
gdcm::network::PresentationContextRQ::PresentationContextRQ ()
```

Referenced by [operator==\(.\)](#).

10.242.3.2 PresentationContextRQ() [2/3]

```
gdcm::network::PresentationContextRQ::PresentationContextRQ (
    UIDs::TSName asname,
    UIDs::TSName tsname = UIDs::ImplicitVRLittleEndianDefaultTransferSyntaxforDICOM)
```

Initialize Presentation Context with [AbstractSyntax](#) set to asname and with a single [TransferSyntax](#) set to tsname (default to Implicit VR LittleEndian when not specified).

References [gdcm::UIDs::ImplicitVRLittleEndianDefaultTransferSyntaxforDICOM](#).

10.242.3.3 PresentationContextRQ() [3/3]

```
gdcm::network::PresentationContextRQ::PresentationContextRQ (
    const PresentationContext & pc)
```

10.242.4 Member Function Documentation

10.242.4.1 AddTransferSyntax()

```
void gdcm::network::PresentationContextRQ::AddTransferSyntax (
    TransferSyntaxSub const & ts)
```

10.242.4.2 GetAbstractSyntax() [1/2]

```
AbstractSyntax & gdcm::network::PresentationContextRQ::GetAbstractSyntax () [inline]
```

10.242.4.3 GetAbstractSyntax() [2/2]

```
AbstractSyntax const & gdcm::network::PresentationContextRQ::GetAbstractSyntax () const [inline]
```

10.242.4.4 GetNumberOfTransferSyntaxes()

```
SizeType gdcm::network::PresentationContextRQ::GetNumberOfTransferSyntaxes () const [inline]
```

10.242.4.5 GetPresentationContextID()

```
uint8_t gdcM::network::PresentationContextRQ::GetPresentationContextID () const
```

10.242.4.6 GetTransferSyntax() [1/2]

```
TransferSyntaxSub & gdcM::network::PresentationContextRQ::GetTransferSyntax (
    SizeType i) [inline]
```

10.242.4.7 GetTransferSyntax() [2/2]

```
TransferSyntaxSub const & gdcM::network::PresentationContextRQ::GetTransferSyntax (
    SizeType i) const [inline]
```

10.242.4.8 GetTransferSyntaxes()

```
std::vector< TransferSyntaxSub > const & gdcM::network::PresentationContextRQ::GetTransfer←
Syntaxes () const [inline]
```

10.242.4.9 operator==(

```
bool gdcM::network::PresentationContextRQ::operator== (
    const PresentationContextRQ & pc) const [inline]
```

References [PresentationContextRQ\(\)](#), and [gdcM_assert](#).

10.242.4.10 Print()

```
void gdcM::network::PresentationContextRQ::Print (
    std::ostream & os) const
```

10.242.4.11 Read()

```
std::istream & gdcM::network::PresentationContextRQ::Read (
    std::istream & is)
```

10.242.4.12 SetAbstractSyntax()

```
void gdcM::network::PresentationContextRQ::SetAbstractSyntax (
    AbstractSyntax const & absyn)
```

10.242.4.13 SetPresentationContextID()

```
void gdcm::network::PresentationContextRQ::SetPresentationContextID (
    uint8_t id)
```

10.242.4.14 Size()

```
size_t gdcm::network::PresentationContextRQ::Size () const
```

10.242.4.15 Write()

```
const std::ostream & gdcm::network::PresentationContextRQ::Write (
    std::ostream & os) const
```

The documentation for this class was generated from the following file:

- [gdcmPresentationContextRQ.h](#)

10.243 gdcm::network::PresentationDataValue Class Reference

[PresentationDataValue](#).

```
#include <gdcmPresentationDataValue.h>
```

Public Member Functions

- [PresentationDataValue](#) ()
- const std::string & [GetBlob](#) () const
- bool [GetIsCommand](#) () const
- bool [GetIsLastFragment](#) () const
- uint8_t [GetMessageHeader](#) () const
- uint8_t [GetPresentationContextID](#) () const
- void [Print](#) (std::ostream &os) const
- std::istream & [Read](#) (std::istream &is)
- std::istream & [ReadInfo](#) (std::istream &is, std::ostream &os)
- void [SetBlob](#) (const std::string &partialblob)
- void [SetCommand](#) (bool inCommand)
- void [SetDataSet](#) (const [DataSet](#) &ds)
- void [SetLastFragment](#) (bool inLast)
- void [SetMessageHeader](#) (uint8_t messageheader)
- void [SetPresentationContextID](#) (uint8_t id)
- size_t [Size](#) () const
- const std::ostream & [Write](#) (std::ostream &os) const

Static Public Member Functions

- static [DataSet ConcatenatePDVBlobs](#) (const std::vector< [PresentationDataValue](#) > &inPDVs)
- static [DataSet ConcatenatePDVBlobsAsExplicit](#) (const std::vector< [PresentationDataValue](#) > &inPDVs)

10.243.1 Detailed Description

[PresentationDataValue](#).

[Table](#) 9-23 PRESENTATION-DATA-VALUE ITEM FIELDS

10.243.2 Constructor & Destructor Documentation

10.243.2.1 PresentationDataValue()

```
gdcm::network::PresentationDataValue::PresentationDataValue ()
```

10.243.3 Member Function Documentation

10.243.3.1 ConcatenatePDVBlobs()

```
DataSet gdcm::network::PresentationDataValue::ConcatenatePDVBlobs (
    const std::vector< PresentationDataValue > & inPDVs) [static]
```

Warning

[DataSet](#) will be read as Implicit Little Endian TS

10.243.3.2 ConcatenatePDVBlobsAsExplicit()

```
DataSet gdcm::network::PresentationDataValue::ConcatenatePDVBlobsAsExplicit (
    const std::vector< PresentationDataValue > & inPDVs) [static]
```

10.243.3.3 GetBlob()

```
const std::string & gdcm::network::PresentationDataValue::GetBlob () const
```

10.243.3.4 GetIsCommand()

```
bool gdcm::network::PresentationDataValue::GetIsCommand () const
```


10.243.3.5 GetIsLastFragment()

```
bool gdcm::network::PresentationDataValue::GetIsLastFragment () const
```

10.243.3.6 GetMessageHeader()

```
uint8_t gdcm::network::PresentationDataValue::GetMessageHeader () const [inline]
```

References [gdcm_assert](#).

10.243.3.7 GetPresentationContextID()

```
uint8_t gdcm::network::PresentationDataValue::GetPresentationContextID () const [inline]
```

10.243.3.8 Print()

```
void gdcm::network::PresentationDataValue::Print (  
    std::ostream & os) const
```

10.243.3.9 Read()

```
std::istream & gdcm::network::PresentationDataValue::Read (  
    std::istream & is)
```

10.243.3.10 ReadInto()

```
std::istream & gdcm::network::PresentationDataValue::ReadInto (  
    std::istream & is,  
    std::ostream & os)
```

10.243.3.11 SetBlob()

```
void gdcm::network::PresentationDataValue::SetBlob (  
    const std::string & partialblob)
```

10.243.3.12 SetCommand()

```
void gdcm::network::PresentationDataValue::SetCommand (  
    bool inCommand)
```

10.243.3.13 SetDataSet()

```
void gdcm::network::PresentationDataValue::SetDataSet (
    const DataSet & ds)
```

Set [DataSet](#). Write [DataSet](#) in implicit.

Warning

size of dataset should be below maxpdusize

10.243.3.14 SetLastFragment()

```
void gdcm::network::PresentationDataValue::SetLastFragment (
    bool inLast)
```

10.243.3.15 SetMessageHeader()

```
void gdcm::network::PresentationDataValue::SetMessageHeader (
    uint8_t messageheader) [inline]
```

References [gdcm_assert](#).

10.243.3.16 SetPresentationContextID()

```
void gdcm::network::PresentationDataValue::SetPresentationContextID (
    uint8_t id) [inline]
```

References [gdcm_assert](#).

10.243.3.17 Size()

```
size_t gdcm::network::PresentationDataValue::Size () const
```

10.243.3.18 Write()

```
const std::ostream & gdcm::network::PresentationDataValue::Write (
    std::ostream & os) const
```

The documentation for this class was generated from the following file:


- [gdcmPresentationDataValue.h](#)

10.244 gdcm::Printer Class Reference


[Printer](#) class.

```
#include <gdcmPrinter.h>
```

Inheritance diagram for gdcm::Printer:



Collaboration diagram for gdcm::Printer:



Public Types

- enum [PrintStyles](#) {
 [VERBOSE_STYLE](#) = 0 ,
 [CONDENSED_STYLE](#) ,
 [XML](#) ,
 [CXX](#) }

Public Member Functions

- [Printer](#) ()
- [~Printer](#) ()=default
- [PrintStyles](#) [GetPrintStyle](#) () const
Get PrintStyle value.
- void [Print](#) (std::ostream &os)
Print.
- void [PrintDataSet](#) (const [DataSet](#) &ds, std::ostream &os, const std::string &s="")
Print an individual dataset.
- void [SetColor](#) (bool c)
Set color mode or not.
- void [SetFile](#) ([File](#) const &f)
Set file.
- void [SetStyle](#) ([PrintStyles](#) ps)
Set PrintStyle value.

Protected Member Functions

- [VR PrintDataElement](#) (std::ostream &os, const [Dicts](#) &dicts, const [DataSet](#) &ds, const [DataElement](#) &de, std::ostream &out, std::string const &indent)
- void [PrintSQ](#) (const [SequenceOfItems](#) *sqi, std::ostream &os, std::string const &indent)

Protected Attributes

- const [File](#) * F
- [VL MaxPrintLength](#)
- [PrintStyles](#) [PrintStyle](#)

10.244.1 Detailed Description

[Printer](#) class.

Examples

[DumpSiemensBase64.cxx](#), [DumpToshibaDTI.cxx](#), and [DumpToshibaDTI2.cxx](#).

10.244.2 Member Enumeration Documentation

10.244.2.1 PrintStyles

```
enum gdcm::Printer::PrintStyles
```

Enumerator

VERBOSE_STYLE	
CONDENSED_STYLE	
XML	
CXX	

10.244.3 Constructor & Destructor Documentation

10.244.3.1 Printer()

```
gdcm::Printer::Printer ()
```

10.244.3.2 ~Printer()

```
gdcm::Printer::~~Printer () [default]
```

10.244.4 Member Function Documentation

10.244.4.1 GetPrintStyle()

```
PrintStyle gdcm::Printer::GetPrintStyle () const [inline]
```

Get PrintStyle value.

References [PrintStyle](#).

10.244.4.2 Print()

```
void gdcm::Printer::Print (  
    std::ostream & os)
```

Print.

Examples

[DumpSiemensBase64.cxx](#).

10.244.4.3 PrintDataElement()

```
VR gdcmm::Printer::PrintDataElement (
    std::ostringstream & os,
    const Dicts & dicts,
    const DataSet & ds,
    const DataElement & de,
    std::ostream & out,
    std::string const & indent) [protected]
```

10.244.4.4 PrintDataSet()

```
void gdcmm::Printer::PrintDataSet (
    const DataSet & ds,
    std::ostream & os,
    const std::string & s = "")
```

Print an individual dataset.

10.244.4.5 PrintSQ()

```
void gdcmm::Printer::PrintSQ (
    const SequenceOfItems * sqi,
    std::ostream & os,
    std::string const & indent) [protected]
```

10.244.4.6 SetColor()

```
void gdcmm::Printer::SetColor (
    bool c)
```

Set color mode or not.

10.244.4.7 SetFile()

```
void gdcmm::Printer::SetFile (
    File const & f) [inline]
```

Set file.

Examples

[DumpSiemensBase64.cxx](#), [DumpToshibaDTI.cxx](#), and [DumpToshibaDTI2.cxx](#).

References

[F](#).

10.244.4.8 SetStyle()

```
void gdcm::Printer::SetStyle (
    PrintStyles ps) [inline]
```

Set PrintStyle value.

References [PrintStyle](#).

10.244.5 Member Data Documentation

10.244.5.1 F

```
const File* gdcm::Printer::F [protected]
```

Referenced by [SetFile\(\)](#).

10.244.5.2 MaxPrintLength

```
VL gdcm::Printer::MaxPrintLength [protected]
```

10.244.5.3 PrintStyle

```
PrintStyles gdcm::Printer::PrintStyle [protected]
```

Referenced by [gdcm::Dumper::Dumper\(\)](#), [GetPrintStyle\(\)](#), and [SetStyle\(\)](#).

The documentation for this class was generated from the following file:

- [gdcmPrinter.h](#)

10.245 gdcm::PrivateDict Class Reference

Private [Dict](#).

```
#include <gdcmDict.h>
```

Public Member Functions

- [PrivateDict](#) ()=default
- [~PrivateDict](#) ()=default
- void [AddDictEntry](#) (const [PrivateTag](#) &tag, const [DictEntry](#) &de)
- bool [FindDictEntry](#) (const [PrivateTag](#) &tag) const
- const [DictEntry](#) & [GetDictEntry](#) (const [PrivateTag](#) &tag) const
- bool [IsEmpty](#) () const
- void [PrintXML](#) () const
- bool [RemoveDictEntry](#) (const [PrivateTag](#) &tag)

Protected Member Functions

- void [LoadDefault](#) ()

Friends

- class [Dicts](#)
- `std::ostream & operator<< (std::ostream &os, const PrivateDict &val)`

10.245.1 Detailed Description

Private [Dict](#).

10.245.2 Constructor & Destructor Documentation

10.245.2.1 PrivateDict()

```
gdcm::PrivateDict::PrivateDict () [default]
```

Referenced by [LoadDefault\(\)](#), and [operator<<](#).

10.245.2.2 ~PrivateDict()

```
gdcm::PrivateDict::~~PrivateDict () [default]
```

10.245.3 Member Function Documentation

10.245.3.1 AddDictEntry()

```
void gdcm::PrivateDict::AddDictEntry (
    const PrivateTag & tag,
    const DictEntry & de) [inline]
```

References [gdcm_assert](#), [GetDictEntry\(\)](#), [gdcm::DictEntry::GetVM\(\)](#), [gdcm::DictEntry::GetVR\(\)](#), [gdcm::DictEntry::SetVM\(\)](#), [gdcm::DictEntry::SetVR\(\)](#), and [gdcm::VR::UN](#).

10.245.3.2 FindDictEntry()

```
bool gdcm::PrivateDict::FindDictEntry (
    const PrivateTag & tag) const [inline]
```


10.245.3.3 GetDictEntry()

```
const DictEntry & gdcM::PrivateDict::GetDictEntry (
    const PrivateTag & tag) const [inline]
```

References [gdcM_assert](#).

Referenced by [AddDictEntry\(\)](#).

10.245.3.4 IsEmpty()

```
bool gdcM::PrivateDict::IsEmpty () const [inline]
```

10.245.3.5 LoadDefault()

```
void gdcM::PrivateDict::LoadDefault () [protected]
```

References [PrivateDict\(\)](#).

10.245.3.6 PrintXML()

```
void gdcM::PrivateDict::PrintXML () const [inline]
```

References [gdcM::Tag::GetElement\(\)](#), [gdcM::Tag::GetGroup\(\)](#), [gdcM::DictEntry::GetName\(\)](#), [gdcM::PrivateTag::GetOwner\(\)](#), [gdcM::DictEntry::GetVM\(\)](#), and [gdcM::DictEntry::GetVR\(\)](#).

10.245.3.7 RemoveDictEntry()

```
bool gdcM::PrivateDict::RemoveDictEntry (
    const PrivateTag & tag) [inline]
```

Remove entry 'tag'. Return true on success (element was found and remove). return false if element was not found.

References [gdcM_assert](#).

10.245.4 Friends And Related Symbol Documentation

10.245.4.1 Dicts

```
friend class Dicts [friend]
```

References [Dicts](#).

Referenced by [Dicts](#).

10.245.4.2 operator<<

```
std::ostream & operator<< (  
    std::ostream & os,  
    const PrivateDict & val) [friend]
```

References [PrivateDict\(\)](#).

The documentation for this class was generated from the following file:


- [gdcmDict.h](#)

10.246 gdcm::PrivateTag Class Reference


Class to represent a Private DICOM Data [Element](#) ([Attribute](#)) [Tag](#) (Group, [Element](#), Owner)

```
#include <gdcmPrivateTag.h>
```

Inheritance diagram for gdcm::PrivateTag:



Collaboration diagram for gdcm::PrivateTag:



Public Member Functions

- [PrivateTag](#) ([Tag](#) const &t, const char *owner="")
- [PrivateTag](#) (uint16_t group=0, uint16_t element=0, const char *owner="")
- [DataElement GetAsDataElement](#) () const
- const char * [GetOwner](#) () const
- bool [operator!=](#) (const [PrivateTag](#) &_val) const
- bool [operator!=](#) (const [Tag](#) &_val) const
- bool [operator<](#) (const [PrivateTag](#) &_val) const
- [PrivateTag](#) & [operator=](#) (const [PrivateTag](#) &_val)
- bool [operator==](#) (const [PrivateTag](#) &_val) const
- bool [operator==](#) (const [Tag](#) &_val) const
- bool [ReadFromCommaSeparatedString](#) (const char *str)
- void [SetOwner](#) (const char *owner)

Public Member Functions inherited from [gdcm::Tag](#)

- [Tag](#) (const [Tag](#) &_val)
- [Tag](#) (uint16_t group, uint16_t element)
*Constructor with 2*uint16_t.*
- [Tag](#) (uint32_t tag=0)
*Constructor with 1*uint32_t Prefer the ctor that takes two uint16_t.*
- uint16_t [GetElement](#) () const
Returns the 'Element number' of the given Tag.
- uint32_t [GetElementTag](#) () const
Returns the full tag value of the given Tag.
- uint16_t [GetGroup](#) () const
Returns the 'Group number' of the given Tag.
- uint32_t [GetLength](#) () const
return the length of tag (read: size on disk)
- [Tag](#) [GetPrivateCreator](#) () const
Return the Private Creator Data Element tag of a private data element.
- bool [IsGroupLength](#) () const
return whether the tag correspond to a group length tag:
- bool [IsGroupXX](#) (const [Tag](#) &t) const
e.g 6002,3000 belong to groupXX: 6000,3000
- bool [IsIllegal](#) () const
return if the tag is considered to be an illegal tag
- bool [IsPrivate](#) () const
- bool [IsPrivateCreator](#) () const
- bool [IsPublic](#) () const
- bool [operator!=](#) (const [Tag](#) &_val) const
- bool [operator<](#) (const [Tag](#) &_val) const
- bool [operator<=](#) (const [Tag](#) &t2) const
- [Tag](#) & [operator=](#) (const [Tag](#) &_val)
- bool [operator==](#) (const [Tag](#) &_val) const
- uint16_t & [operator\[\]](#) (const unsigned int &_id)
Returns the Group or Element of the given Tag, depending on id (0/1)

- `const uint16_t & operator[] (const unsigned int &_id) const`
Returns the Group or Element of the given Tag, depending on id (0/1)
- `std::string PrintAsContinuousString () const`
- `std::string PrintAsContinuousUpperCaseString () const`
Same as PrintAsContinuousString, but hexadecimal [a-f] are printed using upper case.
- `std::string PrintAsPipeSeparatedString () const`
- `template<typename TSwap>`
`std::istream & Read (std::istream &is)`
Read a tag from binary representation.
- `bool ReadFromCommaSeparatedString (const char *str)`
- `bool ReadFromContinuousString (const char *str)`
- `bool ReadFromPipeSeparatedString (const char *str)`
- `void SetElement (uint16_t element)`
Sets the 'Element number' of the given Tag.
- `void SetElementTag (uint16_t group, uint16_t element)`
Sets the 'Group number' & 'Element number' of the given Tag.
- `void SetElementTag (uint32_t tag)`
Sets the full tag value of the given Tag.
- `void SetGroup (uint16_t group)`
Sets the 'Group number' of the given Tag.
- `void SetPrivateCreator (Tag const &t)`
Set private creator:
- `template<typename TSwap>`
`const std::ostream & Write (std::ostream &os) const`
Write a tag in binary rep.

Friends

- `std::ostream & operator<< (std::ostream &_os, const PrivateTag &_val)`

10.246.1 Detailed Description

Class to represent a Private DICOM Data Element (Attribute) Tag (Group, Element, Owner)

Note

private tag have element value in: [0x10,0xff], for instance 0x0009,0x0000 is NOT a private tag

Examples

[ChangePrivateTags.cxx](#), [DumpADAC.cxx](#), [DumpCSA.cs](#), [DumpExamCard.cxx](#), [DumpGEMSMovieGroup.cxx](#), [DumpImageHeaderInfo.cxx](#), [DumpPhilipsECHO.cxx](#), [DumpSiemensBase64.cxx](#), [DumpToshibaDTI.cxx](#), [DumpToshibaDTI2.cxx](#), [DumpVisusChange.cxx](#), [ELSCINT1WaveToText.cxx](#), [FileStreaming.cs](#), [GetSubSequenceData.cxx](#), [MrProtocol.cxx](#), [PublicDict.cxx](#), [ReadGEMSSDO.cxx](#), [csa2img.cxx](#), [iU22tomultisc.cxx](#), [pmsct_rgb1.cxx](#), and [rle2img.cxx](#).

10.246.2 Constructor & Destructor Documentation

10.246.2.1 PrivateTag() [1/2]

```
gdcm::PrivateTag::PrivateTag (  
    uint16_t group = 0,  
    uint16_t element = 0,  
    const char * owner = "") [inline]
```

References [gdcm::Tag::Tag\(\)](#), and [gdcm::Tag::SetElement\(\)](#).

Referenced by [operator!=\(\)](#), [operator<\(\)](#), [operator<<](#), [operator=\(\)](#), and [operator==\(\)](#).

10.246.2.2 PrivateTag() [2/2]

```
gdcm::PrivateTag::PrivateTag (  
    Tag const & t,  
    const char * owner = "") [inline]
```

References [gdcm::Tag::Tag\(\)](#), [gdcm::Tag::GetElement\(\)](#), and [gdcm::Tag::SetElement\(\)](#).

10.246.3 Member Function Documentation

10.246.3.1 GetAsDataElement()

```
DataElement gdcm::PrivateTag::GetAsDataElement () const
```

10.246.3.2 GetOwner()

```
const char * gdcm::PrivateTag::GetOwner () const [inline]
```

Examples

[PublicDict.cxx](#).

Referenced by [gdcm::PrivateDict::PrintXML\(\)](#).

10.246.3.3 operator"!="() [1/2]

```
bool gdcm::PrivateTag::operator!= (  
    const PrivateTag & _val) const [inline]
```

References [PrivateTag\(\)](#), and [gdcm::Tag::GetElementTag\(\)](#).

10.246.3.4 operator"!=() [2/2]

```
bool gdcm::PrivateTag::operator!= (
    const Tag & _val) const [inline]
```

References [gdcm::Tag::Tag\(\)](#), and [gdcm::Tag::GetElementTag\(\)](#).

10.246.3.5 operator<()

```
bool gdcm::PrivateTag::operator< (
    const PrivateTag & _val) const
```

References [PrivateTag\(\)](#).

10.246.3.6 operator=()

```
PrivateTag & gdcm::PrivateTag::operator= (
    const PrivateTag & _val) [inline]
```

References [PrivateTag\(\)](#), [gdcm::Tag::GetElementTag\(\)](#), and [gdcm::Tag::SetElementTag\(\)](#).

10.246.3.7 operator==() [1/2]

```
bool gdcm::PrivateTag::operator== (
    const PrivateTag & _val) const [inline]
```

References [PrivateTag\(\)](#), and [gdcm::Tag::GetElementTag\(\)](#).

10.246.3.8 operator==() [2/2]

```
bool gdcm::PrivateTag::operator== (
    const Tag & _val) const [inline]
```

References [gdcm::Tag::Tag\(\)](#), and [gdcm::Tag::GetElementTag\(\)](#).

10.246.3.9 ReadFromCommaSeparatedString()

```
bool gdcm::PrivateTag::ReadFromCommaSeparatedString (
    const char * str)
```

Read [PrivateTag](#) from a string. [Element](#) number will be truncated to 8bits. Eg: "1234,5678,GDCM" is private tag: (1234,78,"GDCM")

10.246.3.10 SetOwner()

```
void gdcm::PrivateTag::SetOwner (
    const char * owner) [inline]
```

References [gdcm::String<'\\', 64 >::Trim\(\)](#).

10.246.4 Friends And Related Symbol Documentation

10.246.4.1 operator<<

```
std::ostream & operator<< (
    std::ostream & _os,
    const PrivateTag & _val) [friend]
```

References [PrivateTag\(\)](#), and [operator<<](#).

Referenced by [operator<<](#).

The documentation for this class was generated from the following file:


- [gdcmPrivateTag.h](#)

10.247 gdcm::ProgressEvent Class Reference


[ProgressEvent](#).

```
#include <gdcmProgressEvent.h>
```

Inheritance diagram for gdcm::ProgressEvent:



Collaboration diagram for `gdcm::ProgressEvent`:



Public Types

- typedef [ProgressEvent](#) `Self`
- typedef [AnyEvent](#) `Superclass`

Public Member Functions

- [ProgressEvent](#) (`const Self &s`)
- [ProgressEvent](#) (`double p=0`)
- [~ProgressEvent](#) () `override=default`
- `bool` [CheckEvent](#) (`const ::gdcm::Event *e`) `const override`
- `const char *` [GetEventName](#) () `const override`
- `double` [GetProgress](#) () `const`
- `::gdcm::Event *` [MakeObject](#) () `const override`
- `void` [operator=](#) (`const Self &`) `=delete`
- `void` [SetProgress](#) (`double p`)

Public Member Functions inherited from [gdcm::Event](#)

- [Event](#) ()
- [Event](#) (`const Event &`)
- `virtual` [~Event](#) ()
- `virtual bool` [CheckEvent](#) (`const Event *`) `const =0`
- `void` [operator=](#) (`const Event &`) `=delete`
- `virtual void` [Print](#) (`std::ostream &os`) `const`

10.247.1 Detailed Description

[ProgressEvent](#).

Special type of event triggered during

See also

[AnyEvent](#)

Examples

[BasicAnonymizer.cs](#), [Cleaner.cs](#), and [ClinicalTrialIdentificationWorkflow.cs](#).

10.247.2 Member Typedef Documentation

10.247.2.1 Self

```
typedef ProgressEvent gdcm::ProgressEvent::Self
```

10.247.2.2 Superclass

```
typedef AnyEvent gdcm::ProgressEvent::Superclass
```

10.247.3 Constructor & Destructor Documentation

10.247.3.1 ProgressEvent() [1/2]

```
gdcm::ProgressEvent::ProgressEvent (
    double p = 0) [inline]
```

10.247.3.2 ~ProgressEvent()

```
gdcm::ProgressEvent::~~ProgressEvent () [override], [default]
```

10.247.3.3 ProgressEvent() [2/2]

```
gdcm::ProgressEvent::ProgressEvent (
    const Self & s) [inline]
```

10.247.4 Member Function Documentation

10.247.4.1 CheckEvent()

```
bool gdcm::ProgressEvent::CheckEvent (
    const ::gdcm::Event * e) const [inline], [override]
```

10.247.4.2 GetEventName()

```
const char * gdcm::ProgressEvent::GetEventName () const [inline], [override], [virtual]
```

Return the StringName associated with the event.

Implements [gdcm::Event](#).

10.247.4.3 GetProgress()

```
double gdcm::ProgressEvent::GetProgress () const [inline]
```

Examples

[BasicAnonymizer.cs](#), [Cleaner.cs](#), and [ClinicalTrialIdentificationWorkflow.cs](#).

10.247.4.4 MakeObject()

```
::gdcm::Event * gdcm::ProgressEvent::MakeObject () const [inline], [override], [virtual]
```

Create an [Event](#) of this type This method work as a Factory for creating events of each particular type.

Implements [gdcm::Event](#).

10.247.4.5 operator=()

```
void gdcm::ProgressEvent::operator= (
    const Self & ) [delete]
```

10.247.4.6 SetProgress()

```
void gdcm::ProgressEvent::SetProgress (
    double p) [inline]
```

The documentation for this class was generated from the following file:


- [gdcmProgressEvent.h](#)

10.248 gdcm::PVRGCodec Class Reference


[PVRGCodec](#).

```
#include <gdcmPVRGCodec.h>
```

Inheritance diagram for gdcm::PVRGCodec:



Collaboration diagram for gdcm::PVRGCodec:



Public Member Functions

- [PVRGCodec](#) ()
- [~PVRGCodec](#) () override
- bool [CanCode](#) ([TransferSyntax](#) const &ts) const override
Return whether this coder support this transfer syntax (can code it)

- bool [CanDecode](#) ([TransferSyntax](#) const &ts) const override
Return whether this decoder support this transfer syntax (can decode it)
- [ImageCodec](#) * [Clone](#) () const override
- bool [Code](#) ([DataElement](#) const &in, [DataElement](#) &out) override
Code.
- bool [Decode](#) ([DataElement](#) const &is, [DataElement](#) &os) override
Decode.
- void [SetLossyFlag](#) (bool l)

Public Member Functions inherited from [gdcm::ImageCodec](#)

- [ImageCodec](#) ()
- [~ImageCodec](#) () override
- bool [CleanupUnusedBits](#) (char *data, size_t datalen)
- const unsigned int * [GetDimensions](#) () const
- virtual bool [GetHeaderInfo](#) (std::istream &is_, [TransferSyntax](#) &ts)
- bool [GetLossyFlag](#) () const
- const [LookupTable](#) & [GetLUT](#) () const
- bool [GetNeedByteSwap](#) () const
- unsigned int [GetNumberOfDimensions](#) () const
- const [PhotometricInterpretation](#) & [GetPhotometricInterpretation](#) () const
- [PixelFormat](#) & [GetPixelFormat](#) ()
- const [PixelFormat](#) & [GetPixelFormat](#) () const
- unsigned int [GetPlanarConfiguration](#) () const
- bool [IsLossy](#) () const
- void [SetDimensions](#) (const std::vector< unsigned int > &d)
- void [SetDimensions](#) (const unsigned int d[3])
- void [SetLossyFlag](#) (bool l)
- void [SetLUT](#) ([LookupTable](#) const &lut)
- void [SetNeedByteSwap](#) (bool b)
- void [SetNeedOverlayCleanup](#) (bool b)
- void [SetNumberOfDimensions](#) (unsigned int dim)
- void [SetPhotometricInterpretation](#) ([PhotometricInterpretation](#) const &pi)
- virtual void [SetPixelFormat](#) ([PixelFormat](#) const &pf)
- void [SetPlanarConfiguration](#) (unsigned int pc)

Public Member Functions inherited from [gdcm::Coder](#)

- virtual [~Coder](#) ()=default

Public Member Functions inherited from [gdcm::Decoder](#)

- virtual [~Decoder](#) ()=default

Additional Inherited Members

Protected Types inherited from [gdcm::ImageCodec](#)

- typedef [SmartPointer](#)< [LookupTable](#) > LUTPtr

Protected Member Functions inherited from [gdcm::ImageCodec](#)

- virtual bool [AppendFrameEncode](#) (std::ostream &out, const char *data, size_t datalen)
- virtual bool [AppendRowEncode](#) (std::ostream &out, const char *data, size_t datalen)
- bool [DecodeByStreams](#) (std::istream &is_, std::ostream &os) override
- bool [DoByteSwap](#) (std::istream &is_, std::ostream &os)
- bool [DoInvertMonochrome](#) (std::istream &is_, std::ostream &os)
- bool [DoOverlayCleanup](#) (std::istream &is_, std::ostream &os)
- bool [DoPaddedCompositePixelCode](#) (std::istream &is_, std::ostream &os)
- bool [DoPlanarConfiguration](#) (std::istream &is_, std::ostream &os)
- bool [DoSimpleCopy](#) (std::istream &is_, std::ostream &os)
- bool [DoYBR](#) (std::istream &is_, std::ostream &os)
- bool [DoYBRFull422](#) (std::istream &is_, std::ostream &os)
- virtual bool [IsFrameEncoder](#) ()
- virtual bool [IsRowEncoder](#) ()
- virtual bool [IsValid](#) ([PhotometricInterpretation](#) const &pi)
- virtual bool [StartEncode](#) (std::ostream &os)
- virtual bool [StopEncode](#) (std::ostream &os)

Protected Member Functions inherited from [gdcm::Coder](#)

- virtual bool [InternalCode](#) (const char *bv, unsigned long len, std::ostream &os)

Protected Attributes inherited from [gdcm::ImageCodec](#)

- unsigned int [Dimensions](#) [3]
- bool [LossyFlag](#)
- [LUTPtr](#) LUT
- bool [NeedByteSwap](#)
- bool [NeedOverlayCleanup](#)
- unsigned int [NumberOfDimensions](#)
- [PixelFormat](#) PF
- [PhotometricInterpretation](#) PI
- unsigned int [PlanarConfiguration](#)
- bool [RequestPaddedCompositePixelCode](#)
- bool [RequestPlanarConfiguration](#)

10.248.1 Detailed Description

[PVRGCodec](#).

Note

pvrgr is a broken implementation of the JPEG standard. It is known to have a bug in the 16bits lossless implementation of the standard.

In an ideal world, you should not need this codec at all. But to support some broken file such as:

PHILIPS_Gyrosan-12-Jpeg_Extended_Process_2_4.dcm

we have to...

10.248.2 Constructor & Destructor Documentation

10.248.2.1 PVRGCodec()

```
gdcm::PVRGCodec::PVRGCodec ()
```

10.248.2.2 ~PVRGCodec()

```
gdcm::PVRGCodec::~~PVRGCodec () [override]
```

10.248.3 Member Function Documentation

10.248.3.1 CanCode()

```
bool gdcm::PVRGCodec::CanCode (
    TransferSyntax const & ) const [override], [virtual]
```

Return whether this coder support this transfer syntax (can code it)

Reimplemented from [gdcm::ImageCodec](#).

10.248.3.2 CanDecode()

```
bool gdcm::PVRGCodec::CanDecode (
    TransferSyntax const & ) const [override], [virtual]
```

Return whether this decoder support this transfer syntax (can decode it)

Reimplemented from [gdcm::ImageCodec](#).

10.248.3.3 Clone()

```
ImageCodec * gdcm::PVRGCodec::Clone () const [override], [virtual]
```

Implements [gdcm::ImageCodec](#).

References [gdcm::ImageCodec::ImageCodec\(\)](#).

10.248.3.4 Code()

```
bool gdcm::PVRGCodec::Code (  
    DataElement const & in_,  
    DataElement & out_) [override], [virtual]
```

Code.

Reimplemented from [gdcm::Coder](#).

10.248.3.5 Decode()

```
bool gdcm::PVRGCodec::Decode (  
    DataElement const & ,  
    DataElement & ) [override], [virtual]
```

Decode.

Reimplemented from [gdcm::ImageCodec](#).

10.248.3.6 SetLossyFlag()

```
void gdcm::PVRGCodec::SetLossyFlag (  
    bool l)
```

The documentation for this class was generated from the following file:

- [gdcmPVRGCodec.h](#)

10.249 gdcm::PythonFilter Class Reference

[PythonFilter](#) [PythonFilter](#) is the class that make gdcm2.x looks more like gdcm1 and transform the binary blob contained in a [DataElement](#) into a string, typically this is a nice feature to have for wrapped language.

```
#include <gdcmPythonFilter.h>
```

Public Member Functions

- [PythonFilter](#) ()
- [~PythonFilter](#) ()
- [File](#) & [GetFile](#) ()
- const [File](#) & [GetFile](#) () const
- void [SetDicts](#) (const [Dicts](#) &dicts)
- void [SetFile](#) (const [File](#) &f)
- PyObject * [ToPyObject](#) (const [Tag](#) &t) const
- void [UseDictAlways](#) (bool)

10.249.1 Detailed Description

[PythonFilter](#) [PythonFilter](#) is the class that make gdcm2.x looks more like gdcm1 and transform the binary blob contained in a [DataElement](#) into a string, typically this is a nice feature to have for wrapped language.

10.249.2 Constructor & Destructor Documentation

10.249.2.1 [PythonFilter](#)()

```
gdcm::PythonFilter::PythonFilter ()
```

10.249.2.2 [~PythonFilter](#)()

```
gdcm::PythonFilter::~~PythonFilter ()
```

10.249.3 Member Function Documentation

10.249.3.1 [GetFile](#)() [1/2]

```
File & gdcm::PythonFilter::GetFile ()
```

10.249.3.2 [GetFile](#)() [2/2]

```
const File & gdcm::PythonFilter::GetFile () const
```

10.249.3.3 [SetDicts](#)()

```
void gdcm::PythonFilter::SetDicts (
    const Dicts & dicts)
```


10.249.3.4 SetFile()

```
void gdcm::PythonFilter::SetFile (
    const File & f)
```

10.249.3.5 ToPyObject()

```
PyObject * gdcm::PythonFilter::ToPyObject (
    const Tag & t) const
```

10.249.3.6 UseDictAlways()

```
void gdcm::PythonFilter::UseDictAlways (
    bool ) [inline]
```

The documentation for this class was generated from the following file:


- [gdcmPythonFilter.h](#)

10.250 gdcm::QueryBase Class Reference

[QueryBase](#).

```
#include <gdcmQueryBase.h>
```

Inheritance diagram for gdcm::QueryBase:

**Public Member Functions**

- virtual [~QueryBase](#) ()=default
- std::vector< [Tag](#) > [GetAllRequiredTags](#) (const [ERootType](#) &inRootType) const
- std::vector< [Tag](#) > [GetAllTags](#) (const [ERootType](#) &inRootType) const
- virtual std::vector< [Tag](#) > [GetHierarchicalSearchTags](#) (const [ERootType](#) &inRootType) const =0
Return all Unique Key for a particular Query Root type (from the same level and above).
- virtual const char * [GetName](#) () const =0
- virtual std::vector< [Tag](#) > [GetOptionalTags](#) (const [ERootType](#) &inRootType) const =0
- virtual [DataElement](#) [GetQueryLevel](#) () const =0
- virtual std::vector< [Tag](#) > [GetRequiredTags](#) (const [ERootType](#) &inRootType) const =0
- virtual std::vector< [Tag](#) > [GetUniqueTags](#) (const [ERootType](#) &inRootType) const =0

10.250.1 Detailed Description

[QueryBase](#).

contains: the base class for constructing a query dataset for a C-FIND and a C-MOVE

There are four levels of C-FIND and C-MOVE query:

- [Patient](#)
- [Study](#)
- [Series](#)
- [Image](#)

Each one has its own required and optional tags. This class provides an interface for getting those tags. This is an interface class.

See 3.4 C 6.1 and 3.4 C 6.2 for the patient and study root query types. These sections define the tags allowed by a particular query. The caller must pass in which root type they want, patient or study. A third root type, Modality Worklist Query, isn't yet supported.

This class (or rather it's derived classes) will be held in the RootQuery types. These query types actually make the dataset, and will use this dataset to list the required, unique, and optional tags for each type of query. This design is somewhat overly complicated, but is kept so that if we ever wanted to try to guess the query type from the given tags, we could do so.

10.250.2 Constructor & Destructor Documentation

10.250.2.1 ~QueryBase()

```
virtual gdcm::QueryBase::~~QueryBase () [virtual], [default]
```

10.250.3 Member Function Documentation

10.250.3.1 GetAllRequiredTags()

```
std::vector< Tag > gdcm::QueryBase::GetAllRequiredTags (
    const ERootType & inRootType) const
```

In order to validate a query dataset we need to check that there exists at least one required (or unique) key

10.250.3.2 GetAllTags()

```
std::vector< Tag > gdcm::QueryBase::GetAllTags (
    const ERootType & inRootType) const
```

In order to validate a query dataset, just check for the presence of a tag, not it's requirement level in the spec

10.250.3.3 GetHierarchicalSearchTags()

```
virtual std::vector< Tag > gdcmm::QueryBase::GetHierarchicalSearchTags (
    const ERootType & inRootType) const [pure virtual]
```

Return all Unique Key for a particular Query Root type (from the same level and above).

Implemented in [gdcmm::QueryImage](#), [gdcmm::QueryPatient](#), [gdcmm::QuerySeries](#), and [gdcmm::QueryStudy](#).

10.250.3.4 GetName()

```
virtual const char * gdcmm::QueryBase::GetName () const [pure virtual]
```

Implemented in [gdcmm::QueryImage](#), [gdcmm::QueryPatient](#), [gdcmm::QuerySeries](#), and [gdcmm::QueryStudy](#).

10.250.3.5 GetOptionalTags()

```
virtual std::vector< Tag > gdcmm::QueryBase::GetOptionalTags (
    const ERootType & inRootType) const [pure virtual]
```

Implemented in [gdcmm::QueryImage](#), [gdcmm::QueryPatient](#), [gdcmm::QuerySeries](#), and [gdcmm::QueryStudy](#).

10.250.3.6 GetQueryLevel()

```
virtual DataElement gdcmm::QueryBase::GetQueryLevel () const [pure virtual]
```

Implemented in [gdcmm::QueryImage](#), [gdcmm::QueryPatient](#), [gdcmm::QuerySeries](#), and [gdcmm::QueryStudy](#).

10.250.3.7 GetRequiredTags()

```
virtual std::vector< Tag > gdcmm::QueryBase::GetRequiredTags (
    const ERootType & inRootType) const [pure virtual]
```

Implemented in [gdcmm::QueryImage](#), [gdcmm::QueryPatient](#), [gdcmm::QuerySeries](#), and [gdcmm::QueryStudy](#).

10.250.3.8 GetUniqueTags()

```
virtual std::vector< Tag > gdcmm::QueryBase::GetUniqueTags (
    const ERootType & inRootType) const [pure virtual]
```

Implemented in [gdcmm::QueryImage](#), [gdcmm::QueryPatient](#), [gdcmm::QuerySeries](#), and [gdcmm::QueryStudy](#).

The documentation for this class was generated from the following file:

- [gdcmmQueryBase.h](#)

10.251 gdcm::QueryFactory Class Reference

QueryFactory.h.

```
#include <gdcmQueryFactory.h>
```

Static Public Member Functions

- static [ECharSet](#) [GetCharacterFromCurrentLocale](#) ()
- static void [ListCharSets](#) (std::ostream &os)
List all possible CharSet.
- static [DataElement](#) [ProduceCharacterSetDataElement](#) (const std::vector< [ECharSet](#) > &inCharSetType)
- static [BaseQuery](#) * [ProduceQuery](#) (const std::string &sopInstanceUID, [ENQueryType](#) inQueryType)
- static [BaseRootQuery](#) * [ProduceQuery](#) ([ERootType](#) inRootType, [EQueryType](#) inQueryType, [EQueryLevel](#) inQueryLevel)

10.251.1 Detailed Description

QueryFactory.h.

contains: a class to produce a query based off of user-entered information

Essentially, this class is used to construct a query based off of user input (typically from the command line; if in code directly, the query itself could just be instantiated)

In theory, could also be used as the interface to validate incoming datasets as belonging to a particular query style

10.251.2 Member Function Documentation

10.251.2.1 GetCharacterFromCurrentLocale()

```
ECharSet gdcm::QueryFactory::GetCharacterFromCurrentLocale () [static]
```

This function will return the corresponding [ECharSet](#) associated with the current locale of the running system (based on the value of locale()).

10.251.2.2 ListCharSets()

```
void gdcm::QueryFactory::ListCharSets (  
    std::ostream & os) [static]
```

List all possible CharSet.

10.251.2.3 ProduceCharacterSetDataElement()

```
DataElement gdcm::QueryFactory::ProduceCharacterSetDataElement (
    const std::vector< ECharSet > & inCharSetType) [static]
```

This function will produce the appropriate dataelement given a list of charsets. The first charset will be used directly, while the second and subsequent will be prepended with "ISO2022 ". Redundant character sets are not permitted, so if they are encountered, they will just be skipped. if UTF8 or GB18030 is used, no subsequent character sets will be used if the vector passed in is empty, then the dataelement that's passed out will be empty and Latin1 is the presumed encoding

10.251.2.4 ProduceQuery() [1/2]

```
BaseQuery * gdcm::QueryFactory::ProduceQuery (
    const std::string & sopInstanceUID,
    ENQueryType inQueryType) [static]
```

10.251.2.5 ProduceQuery() [2/2]

```
BaseRootQuery * gdcm::QueryFactory::ProduceQuery (
    ERootType inRootType,
    EQueryType inQueryType,
    EQueryLevel inQueryLevel) [static]
```

this function will produce a query (basically, a wrapper to a dataset that can validate whether or not the query is a valid cfind/cmove query) and the level of the query (patient, study, series, image). If the user provides an invalid instantiation (ie, study root type, query level of patient), then the result is NULL.

The documentation for this class was generated from the following file:


- [gdcmQueryFactory.h](#)

10.252 gdcm::QueryImage Class Reference


[QueryImage.](#)

```
#include <gdcmQueryImage.h>
```

Inheritance diagram for gdcm::QueryImage:



Collaboration diagram for `gdcm::QueryImage`:



Public Member Functions

- `std::vector< Tag > GetHierachicalSearchTags` (const `ERootType` &`inRootType`) const override
Return all Unique Key for a particular Query Root type (from the same level and above).
- `const char * GetName` () const override
- `std::vector< Tag > GetOptionalTags` (const `ERootType` &`inRootType`) const override
- `DataElement GetQueryLevel` () const override
- `std::vector< Tag > GetRequiredTags` (const `ERootType` &`inRootType`) const override
- `std::vector< Tag > GetUniqueTags` (const `ERootType` &`inRootType`) const override

Public Member Functions inherited from `gdcm::QueryBase`

- virtual `~QueryBase` ()=default
- `std::vector< Tag > GetAllRequiredTags` (const `ERootType` &`inRootType`) const
- `std::vector< Tag > GetAllTags` (const `ERootType` &`inRootType`) const

10.252.1 Detailed Description

`QueryImage`.

contains: class to construct an image-based query for C-FIND and C-MOVE

10.252.2 Member Function Documentation

10.252.2.1 `GetHierachicalSearchTags()`

```
std::vector< Tag > gdcm::QueryImage::GetHierachicalSearchTags (
    const ERootType & inRootType) const [override], [virtual]
```

Return all Unique Key for a particular Query Root type (from the same level and above).

Implements `gdcm::QueryBase`.

10.252.2.2 GetName()

```
const char * gdcm::QueryImage::GetName () const [override], [virtual]
```

Implements [gdcm::QueryBase](#).

10.252.2.3 GetOptionalTags()

```
std::vector< Tag > gdcm::QueryImage::GetOptionalTags (
    const ERootType & inRootType) const [override], [virtual]
```

Implements [gdcm::QueryBase](#).

10.252.2.4 GetQueryLevel()

```
DataElement gdcm::QueryImage::GetQueryLevel () const [override], [virtual]
```

Implements [gdcm::QueryBase](#).

10.252.2.5 GetRequiredTags()

```
std::vector< Tag > gdcm::QueryImage::GetRequiredTags (
    const ERootType & inRootType) const [override], [virtual]
```

Implements [gdcm::QueryBase](#).

10.252.2.6 GetUniqueTags()

```
std::vector< Tag > gdcm::QueryImage::GetUniqueTags (
    const ERootType & inRootType) const [override], [virtual]
```

Implements [gdcm::QueryBase](#).

The documentation for this class was generated from the following file:


- [gdcmQueryImage.h](#)

10.253 gdcm::QueryPatient Class Reference


[QueryPatient.](#)

```
#include <gdcmQueryPatient.h>
```

Inheritance diagram for gdcm::QueryPatient:



Collaboration diagram for gdcm::QueryPatient:



Public Member Functions

- `std::vector< Tag > GetHierarchicalSearchTags` (const [ERootType](#) &inRootType) const override
Return all Unique Key for a particular Query Root type (from the same level and above).
- `const char * GetName` () const override
- `std::vector< Tag > GetOptionalTags` (const [ERootType](#) &inRootType) const override
- `DataElement GetQueryLevel` () const override
- `std::vector< Tag > GetRequiredTags` (const [ERootType](#) &inRootType) const override
- `std::vector< Tag > GetUniqueTags` (const [ERootType](#) &inRootType) const override

Public Member Functions inherited from [gdcm::QueryBase](#)

- virtual [~QueryBase](#) ()=default
- std::vector< [Tag](#) > [GetAllRequiredTags](#) (const [ERootType](#) &inRootType) const
- std::vector< [Tag](#) > [GetAllTags](#) (const [ERootType](#) &inRootType) const

10.253.1 Detailed Description

[QueryPatient](#).

contains: class to construct a patient-based query for c-find and c-move

10.253.2 Member Function Documentation

10.253.2.1 GetHierachicalSearchTags()

```
std::vector< Tag > gdcm::QueryPatient::GetHierachicalSearchTags (
    const ERootType & inRootType) const [override], [virtual]
```

Return all Unique Key for a particular Query Root type (from the same level and above).

Implements [gdcm::QueryBase](#).

10.253.2.2 GetName()

```
const char * gdcm::QueryPatient::GetName () const [override], [virtual]
```

Implements [gdcm::QueryBase](#).

10.253.2.3 GetOptionalTags()

```
std::vector< Tag > gdcm::QueryPatient::GetOptionalTags (
    const ERootType & inRootType) const [override], [virtual]
```

Implements [gdcm::QueryBase](#).

10.253.2.4 GetQueryLevel()

```
DataElement gdcm::QueryPatient::GetQueryLevel () const [override], [virtual]
```

Implements [gdcm::QueryBase](#).

10.253.2.5 GetRequiredTags()

```
std::vector< Tag > gdcM::QueryPatient::GetRequiredTags (
    const ERootType & inRootType) const [override], [virtual]
```

Implements [gdcM::QueryBase](#).

10.253.2.6 GetUniqueTags()

```
std::vector< Tag > gdcM::QueryPatient::GetUniqueTags (
    const ERootType & inRootType) const [override], [virtual]
```

Implements [gdcM::QueryBase](#).

The documentation for this class was generated from the following file:


- [gdcMQueryPatient.h](#)

10.254 gdcM::QuerySeries Class Reference


[QuerySeries](#).

```
#include <gdcMQuerySeries.h>
```

Inheritance diagram for gdcM::QuerySeries:



Collaboration diagram for gdcm::QuerySeries:



Public Member Functions

- `std::vector< Tag > GetHierachicalSearchTags` (const `ERootType` &`inRootType`) const override
Return all Unique Key for a particular Query Root type (from the same level and above).
- `const char * GetName` () const override
- `std::vector< Tag > GetOptionalTags` (const `ERootType` &`inRootType`) const override
- `DataElement GetQueryLevel` () const override
- `std::vector< Tag > GetRequiredTags` (const `ERootType` &`inRootType`) const override
- `std::vector< Tag > GetUniqueTags` (const `ERootType` &`inRootType`) const override

Public Member Functions inherited from `gdcm::QueryBase`

- `virtual ~QueryBase` ()=default
- `std::vector< Tag > GetAllRequiredTags` (const `ERootType` &`inRootType`) const
- `std::vector< Tag > GetAllTags` (const `ERootType` &`inRootType`) const

10.254.1 Detailed Description

`QuerySeries`.

contains: class to construct a series-based query for c-find and c-move

10.254.2 Member Function Documentation

10.254.2.1 `GetHierachicalSearchTags()`

```
std::vector< Tag > gdcm::QuerySeries::GetHierachicalSearchTags (
    const ERootType & inRootType) const [override], [virtual]
```

Return all Unique Key for a particular Query Root type (from the same level and above).

Implements `gdcm::QueryBase`.

10.254.2.2 GetName()

```
const char * gdcM::QuerySeries::GetName () const [override], [virtual]
```

Implements [gdcM::QueryBase](#).

10.254.2.3 GetOptionalTags()

```
std::vector< Tag > gdcM::QuerySeries::GetOptionalTags (  
    const ERootType & inRootType) const [override], [virtual]
```

Implements [gdcM::QueryBase](#).

10.254.2.4 GetQueryLevel()

```
DataElement gdcM::QuerySeries::GetQueryLevel () const [override], [virtual]
```

Implements [gdcM::QueryBase](#).

10.254.2.5 GetRequiredTags()

```
std::vector< Tag > gdcM::QuerySeries::GetRequiredTags (  
    const ERootType & inRootType) const [override], [virtual]
```

Implements [gdcM::QueryBase](#).

10.254.2.6 GetUniqueTags()

```
std::vector< Tag > gdcM::QuerySeries::GetUniqueTags (  
    const ERootType & inRootType) const [override], [virtual]
```

Implements [gdcM::QueryBase](#).

The documentation for this class was generated from the following file:


- [gdcMQuerySeries.h](#)

10.255 gdcm::QueryStudy Class Reference


QueryStudy.h.

```
#include <gdcmQueryStudy.h>
```

Inheritance diagram for gdcm::QueryStudy:



Collaboration diagram for gdcm::QueryStudy:



Public Member Functions

- `std::vector< Tag > GetHierachicalSearchTags` (const `ERootType` &inRootType) const override
Return all Unique Key for a particular Query Root type (from the same level and above).
- `const char * GetName` () const override
- `std::vector< Tag > GetOptionalTags` (const `ERootType` &inRootType) const override
- `DataElement GetQueryLevel` () const override
- `std::vector< Tag > GetRequiredTags` (const `ERootType` &inRootType) const override
- `std::vector< Tag > GetUniqueTags` (const `ERootType` &inRootType) const override

Public Member Functions inherited from [gdcm::QueryBase](#)

- virtual [~QueryBase](#) ()=default
- std::vector< [Tag](#) > [GetAllRequiredTags](#) (const [ERootType](#) &inRootType) const
- std::vector< [Tag](#) > [GetAllTags](#) (const [ERootType](#) &inRootType) const

10.255.1 Detailed Description

QueryStudy.h.

contains: class to construct a study-based query for C-FIND and C-MOVE

10.255.2 Member Function Documentation

10.255.2.1 GetHierarchicalSearchTags()

```
std::vector< Tag > gdcm::QueryStudy::GetHierarchicalSearchTags (
    const ERootType & inRootType) const [override], [virtual]
```

Return all Unique Key for a particular Query Root type (from the same level and above).

Implements [gdcm::QueryBase](#).

10.255.2.2 GetName()

```
const char * gdcm::QueryStudy::GetName () const [override], [virtual]
```

Implements [gdcm::QueryBase](#).

10.255.2.3 GetOptionalTags()

```
std::vector< Tag > gdcm::QueryStudy::GetOptionalTags (
    const ERootType & inRootType) const [override], [virtual]
```

Implements [gdcm::QueryBase](#).

10.255.2.4 GetQueryLevel()

```
DataElement gdcm::QueryStudy::GetQueryLevel () const [override], [virtual]
```

Implements [gdcm::QueryBase](#).

10.255.2.5 GetRequiredTags()

```
std::vector< Tag > gdcm::QueryStudy::GetRequiredTags (
    const ERootType & inRootType) const [override], [virtual]
```

Implements [gdcm::QueryBase](#).

10.255.2.6 GetUniqueTags()

```
std::vector< Tag > gdcm::QueryStudy::GetUniqueTags (
    const ERootType & inRootType) const [override], [virtual]
```

Implements [gdcm::QueryBase](#).

The documentation for this class was generated from the following file:


- [gdcmQueryStudy.h](#)

10.256 gdcm::RAWCodec Class Reference


[RAWCodec](#) class.

```
#include <gdcmRAWCodec.h>
```

Inheritance diagram for [gdcm::RAWCodec](#):



Collaboration diagram for `gdcm::RAWCodec`:



Public Member Functions

- [RAWCodec](#) ()
- [~RAWCodec](#) () override
- bool [CanCode](#) ([TransferSyntax](#) const &ts) const override
Return whether this coder support this transfer syntax (can code it)
- bool [CanDecode](#) ([TransferSyntax](#) const &ts) const override
Return whether this decoder support this transfer syntax (can decode it)
- [ImageCodec](#) * [Clone](#) () const override
- bool [Code](#) ([DataElement](#) const &in, [DataElement](#) &out) override
Code.
- bool [Decode](#) ([DataElement](#) const &is, [DataElement](#) &os) override
Decode.
- bool [DecodeBytes](#) (const char *inBytes, size_t inBufferLength, char *outBytes, size_t inOutBufferLength)
- bool [GetHeaderInfo](#) (std::istream &is, [TransferSyntax](#) &ts) override

Public Member Functions inherited from [gdcm::ImageCodec](#)

- [ImageCodec](#) ()
- [~ImageCodec](#) () override
- bool [CleanupUnusedBits](#) (char *data, size_t datalen)
- const unsigned int * [GetDimensions](#) () const
- bool [GetLossyFlag](#) () const
- const [LookupTable](#) & [GetLUT](#) () const
- bool [GetNeedByteSwap](#) () const
- unsigned int [GetNumberOfDimensions](#) () const
- const [PhotometricInterpretation](#) & [GetPhotometricInterpretation](#) () const
- [PixelFormat](#) & [GetPixelFormat](#) ()
- const [PixelFormat](#) & [GetPixelFormat](#) () const
- unsigned int [GetPlanarConfiguration](#) () const
- bool [IsLossy](#) () const
- void [SetDimensions](#) (const std::vector< unsigned int > &d)
- void [SetDimensions](#) (const unsigned int d[3])
- void [SetLossyFlag](#) (bool l)
- void [SetLUT](#) ([LookupTable](#) const &lut)

- void [SetNeedByteSwap](#) (bool b)
- void [SetNeedOverlayCleanup](#) (bool b)
- void [SetNumberOfDimensions](#) (unsigned int dim)
- void [SetPhotometricInterpretation](#) ([PhotometricInterpretation](#) const &pi)
- virtual void [SetPixelFormat](#) ([PixelFormat](#) const &pf)
- void [SetPlanarConfiguration](#) (unsigned int pc)

Public Member Functions inherited from [gdcm::Coder](#)

- virtual [~Coder](#) ()=default

Public Member Functions inherited from [gdcm::Decoder](#)

- virtual [~Decoder](#) ()=default

Protected Member Functions

- bool [DecodeByStreams](#) (std::istream &is, std::ostream &os) override

Protected Member Functions inherited from [gdcm::ImageCodec](#)

- virtual bool [AppendFrameEncode](#) (std::ostream &out, const char *data, size_t datalen)
- virtual bool [AppendRowEncode](#) (std::ostream &out, const char *data, size_t datalen)
- bool [DoByteSwap](#) (std::istream &is_, std::ostream &os)
- bool [DoInvertMonochrome](#) (std::istream &is_, std::ostream &os)
- bool [DoOverlayCleanup](#) (std::istream &is_, std::ostream &os)
- bool [DoPaddedCompositePixelCode](#) (std::istream &is_, std::ostream &os)
- bool [DoPlanarConfiguration](#) (std::istream &is_, std::ostream &os)
- bool [DoSimpleCopy](#) (std::istream &is_, std::ostream &os)
- bool [DoYBR](#) (std::istream &is_, std::ostream &os)
- bool [DoYBRFull422](#) (std::istream &is_, std::ostream &os)
- virtual bool [IsFrameEncoder](#) ()
- virtual bool [IsRowEncoder](#) ()
- virtual bool [IsValid](#) ([PhotometricInterpretation](#) const &pi)
- virtual bool [StartEncode](#) (std::ostream &os)
- virtual bool [StopEncode](#) (std::ostream &os)

Protected Member Functions inherited from [gdcm::Coder](#)

- virtual bool [InternalCode](#) (const char *bv, unsigned long len, std::ostream &os)

Additional Inherited Members

Protected Types inherited from [gdcm::ImageCodec](#)

- typedef [SmartPointer](#)< [LookupTable](#) > [LUTPtr](#)

Protected Attributes inherited from [gdcm::ImageCodec](#)

- unsigned int [Dimensions](#) [3]
- bool [LossyFlag](#)
- [LUTPtr](#) LUT
- bool [NeedByteSwap](#)
- bool [NeedOverlayCleanup](#)
- unsigned int [NumberOfDimensions](#)
- [PixelFormat](#) PF
- [PhotometricInterpretation](#) PI
- unsigned int [PlanarConfiguration](#)
- bool [RequestPaddedCompositePixelCode](#)
- bool [RequestPlanarConfiguration](#)

10.256.1 Detailed Description

[RAWCodec](#) class.

10.256.2 Constructor & Destructor Documentation

10.256.2.1 RAWCodec()

```
gdcm::RAWCodec::RAWCodec ()
```

10.256.2.2 ~RAWCodec()

```
gdcm::RAWCodec::~~RAWCodec () [override]
```

10.256.3 Member Function Documentation

10.256.3.1 CanCode()

```
bool gdcm::RAWCodec::CanCode (
    TransferSyntax const & ) const [override], [virtual]
```

Return whether this coder support this transfer syntax (can code it)

Reimplemented from [gdcm::ImageCodec](#).

10.256.3.2 CanDecode()

```
bool gdcm::RAWCodec::CanDecode (
    TransferSyntax const & ) const [override], [virtual]
```

Return whether this decoder support this transfer syntax (can decode it)

Reimplemented from [gdcm::ImageCodec](#).

10.256.3.3 Clone()

```
ImageCodec * gdcm::RAWCodec::Clone () const [override], [virtual]
```

Implements [gdcm::ImageCodec](#).

References [gdcm::ImageCodec::ImageCodec\(\)](#).

10.256.3.4 Code()

```
bool gdcm::RAWCodec::Code (
    DataElement const & in_,
    DataElement & out_) [override], [virtual]
```

Code.

Reimplemented from [gdcm::Coder](#).

10.256.3.5 Decode()

```
bool gdcm::RAWCodec::Decode (
    DataElement const & ,
    DataElement & ) [override], [virtual]
```

Decode.

Reimplemented from [gdcm::ImageCodec](#).

10.256.3.6 DecodeByStreams()

```
bool gdcm::RAWCodec::DecodeByStreams (
    std::istream & is,
    std::ostream & os) [override], [protected], [virtual]
```

Reimplemented from [gdcm::ImageCodec](#).

10.256.3.7 DecodeBytes()

```
bool gdcm::RAWCodec::DecodeBytes (
    const char * inBytes,
    size_t inBufferLength,
    char * outBytes,
    size_t inOutBufferLength)
```

Used by the ImageStreamReader– converts a read in buffer into one with the proper encodings.

10.256.3.8 GetHeaderInfo()

```
bool gdcM::RAWCodec::GetHeaderInfo (
    std::istream & is,
    TransferSyntax & ts) [override], [virtual]
```

Reimplemented from [gdcM::ImageCodec](#).

The documentation for this class was generated from the following file:


- [gdcMRAWCodec.h](#)

10.257 gdcM::Reader Class Reference


[Reader](#) ala DOM (Document [Object](#) Model)

```
#include <gdcMReader.h>
```

Inheritance diagram for gdcM::Reader:



Collaboration diagram for gdcm::Reader:



Public Member Functions

- [Reader](#) ()
- virtual [~Reader](#) ()
- bool [CanRead](#) () const
- [File](#) & [GetFile](#) ()
 - Set/Get File.*
- const [File](#) & [GetFile](#) () const
 - Set/Get File.*
- size_t [GetStreamCurrentPosition](#) () const
- virtual bool [Read](#) ()
 - Main function to read a file.*
- bool [ReadSelectedPrivateTags](#) (std::set< [PrivateTag](#) > const &ptags, bool readvalues=true)
 - Will only read the specified selected private tags.*
- bool [ReadSelectedTags](#) (std::set< [Tag](#) > const &tags, bool readvalues=true)
 - Will only read the specified selected tags.*
- bool [ReadUpToTag](#) (const [Tag](#) &tag, std::set< [Tag](#) > const &skiptags=std::set< [Tag](#) >())
- void [SetFile](#) ([File](#) &file)
 - Set/Get File.*
- void [SetFileName](#) (const char *filename_native)
- void [SetStream](#) (std::istream &input_stream)
 - Set the open-ed stream directly.*

Protected Member Functions

- `std::istream * GetStreamPtr () const`
- `bool ReadDataSet ()`
- `bool ReadMetaInformation ()`
- `bool ReadPreamble ()`

Protected Attributes

- `SmartPointer< File > F`

Friends

- class [StreamImageReader](#)

10.257.1 Detailed Description

[Reader](#) ala DOM (Document [Object](#) Model)

This class is a non-validating reader, it will only performs well- formedness check only, and to some extent catch known error (non well-formed document).

Detailed description here

A [DataSet](#) DOES NOT contains group 0x0002 (see [FileMetaInformation](#))

This is really a [DataSet](#) reader. This will not make sure the dataset conform to any [IOD](#) at all. This is a completely different step. The reasoning was that user could control the [IOD](#) there lib would handle and thus we would not be able to read a [DataSet](#) if the [IOD](#) was not found Instead we separate the reading from the validation.

Note

From GDCM1.x. Users will realize that one feature is missing from this DOM implementation. In GDCM 1.x user used to be able to control the size of the [Value](#) to be read. By default it was 0xffff. The main author of GDCM2 thought this was too dangerous and harmful and therefore this feature did not make it into GDCM2

Warning

GDCM will not produce warning for unordered (non-alphabetical order).

See also

[Writer](#) [FileMetaInformation](#) [DataSet](#) [File](#)

Examples

[ChangePrivateTags.cxx](#), [ChangeSequenceUltrasound.cxx](#), [ClinicalTrialAnnotate.cxx](#), [ClinicalTrialIdentificationWorkflow.cs](#), [CreateFakeRTDOSE.cxx](#), [DeriveSeries.cxx](#), [DiffFile.cxx](#), [DumpADAC.cxx](#), [DumpCSA.cs](#), [DumpExamCard.cxx](#), [DumpGEMSMovieGroup.cxx](#), [DumpImageHeaderInfo.cxx](#), [DumpPhilipsECHO.cxx](#), [DumpSiemensBase64.cxx](#), [DumpToshibaDTI.cxx](#), [DumpToshibaDTI2.cxx](#), [DumpVisusChange.cxx](#), [DuplicatePCDE.cxx](#), [ELSCINT1WaveToText.cxx](#), [ExtractEncapsulatedFile.cs](#), [ExtractEncryptedContent.cxx](#), [FixBrokenJ2K.cxx](#), [FixOrientation.cxx](#), [GenLongSeqs.cxx](#), [GenSeqs.cxx](#), [GetSequenceUltrasound.cxx](#), [GetSubSequenceData.cxx](#), [HelloWorld.cxx](#), [LargeVRDSExplicit.cxx](#), [MakeTemplate.cxx](#), [ManipulateFile.cs](#), [NewSequence.cs](#), [PatchFile.cxx](#), [QIDO-RS.cxx](#), [ReadAndDumpDICOMDIR.cxx](#), [ReadAndDumpDICOMDIR2.cxx](#), [ReadAndPrintAttributes.cxx](#), [ReadExplicitLengthSQIVR.cxx](#), [ReadGEMSSDO.cxx](#), [ReadUTF8QtDir.cxx](#), [ReformatFile.cs](#), [SimplePrint.cs](#), [SimplePrintPatientName.cs](#), [TestReader.cxx](#), [csa2img.cxx](#), [gdcmrtnplan.cxx](#), [gdcmrtpplan.cxx](#), [iU22tomultisc.cxx](#), [pmsct_rgb1.cxx](#), and [rle2img.cxx](#).

10.257.2 Constructor & Destructor Documentation

10.257.2.1 Reader()

```
gdcm::Reader::Reader ()
```

10.257.2.2 ~Reader()

```
virtual gdcm::Reader::~Reader () [virtual]
```

10.257.3 Member Function Documentation

10.257.3.1 CanRead()

```
bool gdcm::Reader::CanRead () const
```

Test whether this is a DICOM file

Warning

need to call either SetFileName or SetStream first

Examples

[ReadUTF8QtDir.cxx](#).

10.257.3.2 GetFile() [1/2]

```
File & gdcm::Reader::GetFile () [inline]
```

Set/Get [File](#).

References [F](#).

10.257.3.3 GetFile() [2/2]

```
const File & gdcm::Reader::GetFile () const [inline]
```

Set/Get [File](#).

Examples

[BasicAnonymizer.cs](#), [BasicImageAnonymizer.cs](#), [ChangePrivateTags.cxx](#), [ChangeSequenceUltrasound.cxx](#), [Cleaner.cs](#), [ClinicalTrialAnnotate.cxx](#), [ClinicalTrialIdentificationWorkflow.cs](#), [CompressImage.cxx](#), [CompressLossyJPEG.cs](#), [CreateFakeRTDOSE.cxx](#), [DecompressImage.cs](#), [DeriveSeries.cxx](#), [DiffFile.cxx](#), [DumpADAC.cxx](#), [DumpCSA.cs](#), [DumpExamCard.cxx](#), [DumpGEMSMovieGroup.cxx](#), [DumpImageHeaderInfo.cxx](#), [DumpPhilipsECHO.cxx](#), [DumpSiemensBase64.cxx](#), [DumpToshibaDTI.cxx](#), [DumpToshibaDTI2.cxx](#), [DumpVisusChange.cxx](#), [DuplicatePCDE.cxx](#), [ELSCINT1WaveToText.cxx](#), [ExplicitLittleEndian.cs](#), [ExtractEncapsulatedFile.cs](#), [ExtractEncryptedContent.cxx](#), [ExtractIconFromFile.cxx](#), [ExtractImageRegion.cs](#), [ExtractImageRegionWithLUT.cs](#), [FixBrokenJ2K.cxx](#), [FixJAI BugJPEGLS.cxx](#), [FixOrientation.cxx](#), [GenLongSeqs.cxx](#), [GenSeqs.cxx](#), [GetJPEGSamplePrecision.cxx](#), [GetSequenceUltrasound.cxx](#), [GetSubSequenceData.cxx](#), [HelloWorld.cxx](#), [LargeVRDSExplicit.cxx](#), [MakeTemplate.cxx](#), [ManipulateFile.cs](#), [MergeTwoFiles.cxx](#), [MrProtocol.cxx](#), [NewSequence.cs](#), [PatchFile.cxx](#), [QIDO-RS.cxx](#), [ReadAndDumpDICOMDIR.cxx](#), [ReadAndDumpDICOMDIR2.cxx](#), [ReadAndPrintAttributes.cxx](#), [ReadExplicitLengthSQIVR.cxx](#), [ReadGEMSSDO.cxx](#), [ReformatFile.cs](#), [SimplePrint.cs](#), [SimplePrintPatientName.cs](#), [StandardizeFiles.cs](#), [TestReader.cxx](#), [csa2img.cxx](#), [gdcmrtionplan.cxx](#), [gdcmrtplan.cxx](#), [iU22tomultisc.cxx](#), [pmsct_rgb1.cxx](#), and [rle2img.cxx](#).

References [F](#).

10.257.3.4 GetStreamCurrentPosition()

```
size_t gdcm::Reader::GetStreamCurrentPosition () const
```

For wrapped language. return type is compatible with [System::FileSize](#) return type Use native `std::streampos` / `std::streamoff` directly from the stream from C++

Examples

[ExtractImageRegion.cs](#).

10.257.3.5 GetStreamPtr()

```
std::istream * gdcm::Reader::GetStreamPtr () const [inline], [protected]
```

10.257.3.6 Read()

```
virtual bool gdcm::Reader::Read () [virtual]
```

Main function to read a file.

Reimplemented in [gdcm::ImageReader](#), [gdcm::ImageRegionReader](#), [gdcm::PixmapReader](#), [gdcm::SegmentReader](#), and [gdcm::SurfaceReader](#).

Examples

[BasicAnonymizer.cs](#), [ChangePrivateTags.cxx](#), [ChangeSequenceUltrasound.cxx](#), [Cleaner.cs](#), [ClinicalTrialAnnotate.cxx](#), [ClinicalTrialIdentificationWorkflow.cs](#), [CreateFakeRTDOSE.cxx](#), [DeriveSeries.cxx](#), [DiffFile.cxx](#), [DumpADAC.cxx](#), [DumpCSA.cs](#), [DumpExamCard.cxx](#), [DumpGEMSMovieGroup.cxx](#), [DumpImageHeaderInfo.cxx](#), [DumpPhilipsECHO.cxx](#), [DumpSiemensBase64.cxx](#), [DumpToshibaDTI.cxx](#), [DumpToshibaDTI2.cxx](#), [DuplicatePCDE.cxx](#), [ELSCINT1WaveToText.cxx](#), [ExtractEncapsulatedFile.cs](#), [ExtractEncryptedContent.cxx](#), [FixBrokenJ2K.cxx](#), [FixOrientation.cxx](#), [GenLongSeqs.cxx](#), [GenSeqs.cxx](#), [GetSequenceUltrasound.cxx](#), [GetSubSequenceData.cxx](#), [HelloWorld.cxx](#), [LargeVRDSExplicit.cxx](#), [MakeTemplate.cxx](#), [ManipulateFile.cs](#), [NewSequence.cs](#), [PatchFile.cxx](#), [QIDO-RS.cxx](#), [ReadAndDumpDICOMDIR.cxx](#), [ReadAndDumpDICOMDIR2.cxx](#), [ReadAndPrintAttributes.cxx](#), [ReadExplicitLengthSQIVR.cxx](#), [ReadGEMSSDO.cxx](#), [ReformatFile.cs](#), [SimplePrint.cs](#), [SimplePrintPatientName.cs](#), [TestReader.cxx](#), [csa2img.cxx](#), [gdcmrtionplan.cxx](#), [gdcmrtplan.cxx](#), [iU22tomultisc.cxx](#), [pmsct_rgb1.cxx](#), and [rle2img.cxx](#).

10.257.3.7 ReadDataSet()

```
bool gdcm::Reader::ReadDataSet () [protected]
```

10.257.3.8 ReadMetaInformation()

```
bool gdcm::Reader::ReadMetaInformation () [protected]
```


10.257.3.9 ReadPreamble()

```
bool gdcm::Reader::ReadPreamble () [protected]
```

10.257.3.10 ReadSelectedPrivateTags()

```
bool gdcm::Reader::ReadSelectedPrivateTags (
    std::set< PrivateTag > const & ptags,
    bool readvalues = true)
```

Will only read the specified selected private tags.

10.257.3.11 ReadSelectedTags()

```
bool gdcm::Reader::ReadSelectedTags (
    std::set< Tag > const & tags,
    bool readvalues = true)
```

Will only read the specified selected tags.

10.257.3.12 ReadUpToTag()

```
bool gdcm::Reader::ReadUpToTag (
    const Tag & tag,
    std::set< Tag > const & skiptags = std::set< Tag >())
```

Will read only up to [Tag](#)

Parameters

<i>tag</i>	and skipping any tag specified in
<i>skiptags</i>	

Examples

[DumpVisusChange.cxx](#).

10.257.3.13 SetFile()

```
void gdcm::Reader::SetFile (
    File & file) [inline]
```

Set/Get [File](#).

References [F](#).

10.257.3.14 SetFileName()

```
void gdcmm::Reader::SetFileName (
    const char * filename_native)
```

Set the filename to open. This will create a `std::ifstream` internally See `SetStream` if you are dealing with different `std::istream` object

Examples

[BasicAnonymizer.cs](#), [BasicImageAnonymizer.cs](#), [ChangePrivateTags.cxx](#), [ChangeSequenceUltrasound.cxx](#), [CheckBigEndianBug.cxx](#), [Cleaner.cs](#), [ClinicalTrialAnnotate.cxx](#), [ClinicalTrialIdentificationWorkflow.cs](#), [CompressImage.cxx](#), [CompressLossyJPEG.cs](#), [ConvertToQImage.cxx](#), [CreateFakeRTDOSE.cxx](#), [DecompressImage.cs](#), [DeriveSeries.cxx](#), [DiffFile.cxx](#), [DumpADAC.cxx](#), [DumpCSA.cs](#), [DumpExamCard.cxx](#), [DumpGEMSMovieGroup.cxx](#), [DumpImageHeaderInfo.cxx](#), [DumpPhilipsECHO.cxx](#), [DumpSiemensBase64.cxx](#), [DumpToshibaDTI.cxx](#), [DumpToshibaDTI2.cxx](#), [DumpVisusChange.cxx](#), [DuplicatePCDE.cxx](#), [ELSCINT1WaveToText.cxx](#), [ExplicitLittleEndian.cs](#), [ExtractEncapsulatedFile.cs](#), [ExtractEncryptedContent.cxx](#), [ExtractIconFromFile.cxx](#), [ExtractImageRegion.cs](#), [ExtractImageRegionWithLUT.cs](#), [FixBrokenJ2K.cxx](#), [FixJAIBugJPEGLS.cxx](#), [FixOrientation.cxx](#), [GenLongSeqs.cxx](#), [GenSeqs.cxx](#), [GetArray.cs](#), [GetJPEGSamplePrecision.cxx](#), [GetSequenceUltrasound.cxx](#), [GetSubSequenceData.cxx](#), [HelloVizWorld.cxx](#), [HelloWorld.cxx](#), [LargeVRDSExplicit.cxx](#), [MakeTemplate.cxx](#), [ManipulateFile.cs](#), [MergeTwoFiles.cxx](#), [MrProtocol.cxx](#), [NewSequence.cs](#), [PatchFile.cxx](#), [PrintLUT.cxx](#), [QIDO-RS.cxx](#), [ReadAndDumpDICOMDIR.cxx](#), [ReadAndDumpDICOMDIR2.cxx](#), [ReadAndPrintAttributes.cxx](#), [ReadExplicitLengthSQIVR.cxx](#), [ReadGEMSSDO.cxx](#), [ReadMultiTimesException.cxx](#), [ReadUTF8QtDir.cxx](#), [ReformatFile.cs](#), [RescaleImage.cs](#), [SimplePrint.cs](#), [SimplePrintPatientName.cs](#), [StandardizeFiles.cs](#), [TemplateEmptyImage.cxx](#), [TestReader.cxx](#), [csa2img.cxx](#), [gdcmmrtionplan.cxx](#), [gdcmmrtplan.cxx](#), [iU22tomultisc.cxx](#), [pmsct_rgb1.cxx](#), [rle2img.cxx](#), and [threadgdcmm.cxx](#).

10.257.3.15 SetStream()

```
void gdcmm::Reader::SetStream (
    std::istream & input_stream) [inline]
```

Set the open-ed stream directly.

Examples

[ReadUTF8QtDir.cxx](#).

10.257.4 Friends And Related Symbol Documentation

10.257.4.1 StreamImageReader

```
friend class StreamImageReader [friend]
```

References [StreamImageReader](#).

Referenced by [StreamImageReader](#).

10.257.5 Member Data Documentation

10.257.5.1 F

`SmartPointer<File> gdcm::Reader::F` [protected]

Referenced by [GetFile\(\)](#), [GetFile\(\)](#), and [SetFile\(\)](#).


The documentation for this class was generated from the following file:

- [gdcmReader.h](#)

10.258 gdcm::RealWorldValueMappingContent Struct Reference

```
#include <gdcmImageHelper.h>
```

Collaboration diagram for gdcm::RealWorldValueMappingContent:



Public Attributes

- `std::string` [CodeMeaning](#)
- `std::string` [CodeValue](#)
- `double` [RealWorldValueIntercept](#)
- `double` [RealWorldValueSlope](#)

10.258.1 Member Data Documentation

10.258.1.1 CodeMeaning

```
std::string gdcM::RealWorldValueMappingContent::CodeMeaning
```

10.258.1.2 CodeValue

```
std::string gdcM::RealWorldValueMappingContent::CodeValue
```

10.258.1.3 RealWorldValueIntercept

```
double gdcM::RealWorldValueMappingContent::RealWorldValueIntercept
```

10.258.1.4 RealWorldValueSlope

```
double gdcM::RealWorldValueMappingContent::RealWorldValueSlope
```

The documentation for this struct was generated from the following file:


- [gdcmImageHelper.h](#)

10.259 gdcm::Region Class Reference

Class for manipulation region.

```
#include <gdcmRegion.h>
```

Inheritance diagram for gdcm::Region:



Public Member Functions

- [Region](#) ()
- virtual [~Region](#) ()
- virtual size_t [Area](#) () const =0
compute the area
- virtual [Region](#) * [Clone](#) () const =0
- virtual [BoxRegion](#) [ComputeBoundingBox](#) ()=0
Return the Axis-Aligned minimum bounding box for all regions.
- virtual bool [Empty](#) () const =0
return whether this domain is empty:
- virtual bool [IsValid](#) () const =0
return whether this is valid domain
- virtual void [Print](#) (std::ostream &os=std::cout) const
Print.

10.259.1 Detailed Description

Class for manipulation region.

10.259.2 Constructor & Destructor Documentation

10.259.2.1 Region()

```
gdcm::Region::Region ()
```

Referenced by [gdcm::BoxRegion::Clone\(\)](#), and [Clone\(\)](#).

10.259.2.2 ~Region()

```
virtual gdcm::Region::~~Region () [virtual]
```

10.259.3 Member Function Documentation

10.259.3.1 Area()

```
virtual size_t gdcm::Region::Area () const [pure virtual]
```

compute the area

Implemented in [gdcm::BoxRegion](#).

10.259.3.2 Clone()

```
virtual Region * gdcm::Region::Clone () const [pure virtual]
```

Implemented in [gdcm::BoxRegion](#).

References [Region\(\)](#).

10.259.3.3 ComputeBoundingBox()

```
virtual BoxRegion gdcm::Region::ComputeBoundingBox () [pure virtual]
```

Return the Axis-Aligned minimum bounding box for all regions.

Implemented in [gdcm::BoxRegion](#).

10.259.3.4 Empty()

```
virtual bool gdcm::Region::Empty () const [pure virtual]
```

return whether this domain is empty:

Implemented in [gdcm::BoxRegion](#).

10.259.3.5 IsValid()

```
virtual bool gdcm::Region::IsValid () const [pure virtual]
```

return whether this is valid domain

Implemented in [gdcm::BoxRegion](#).

10.259.3.6 Print()

```
virtual void gdcm::Region::Print (  
    std::ostream & os = std::cout) const [virtual]
```

Print.

Reimplemented in [gdcm::BoxRegion](#).

Referenced by [gdcm::operator<<\(\)](#).

The documentation for this class was generated from the following file:

- [gdcmRegion.h](#)

10.260 gdcm::Rescaler Class Reference

Rescale class.

```
#include <gdcmRescaler.h>
```

Public Member Functions

- [Rescaler](#) ()
- [~Rescaler](#) ()=default
- [PixelFormat::ScalarType ComputeInterceptSlopePixelFormat](#) ()
- [PixelFormat ComputePixelFormatFromMinMax](#) ()
- double [GetIntercept](#) () const
- double [GetSlope](#) () const
- bool [InverseRescale](#) (char *out, const char *in, size_t n)
Inverse transform.
- bool [Rescale](#) (char *out, const char *in, size_t n)
Direct transform.
- void [SetIntercept](#) (double i)
Set Intercept: used for both direct&inverse transformation.
- void [SetMinMaxForPixelFormat](#) (double min, double max)
- void [SetPixelFormat](#) ([PixelFormat](#) const &pf)
Set Pixel Format of input data.
- void [SetSlope](#) (double s)
Set Slope: user for both direct&inverse transformation.
- void [SetTargetPixelFormat](#) ([PixelFormat](#) const &targetst)
- void [SetUseTargetPixelFormat](#) (bool b)
Override default behavior of Rescale.

Protected Member Functions

- template<typename TIn>
void [InverseRescaleFunctionIntoBestFit](#) (char *out, const TIn *in, size_t n)
- template<typename TIn>
void [RescaleFunctionIntoBestFit](#) (char *out, const TIn *in, size_t n)

10.260.1 Detailed Description

Rescale class.

This class is meant to apply the linear transform of Stored Pixel [Value](#) to Real World [Value](#). This is mostly found in CT or PET dataset, where the value are stored using one type, but need to be converted to another scale using a linear transform. There are basically two cases: In CT: the linear transform is generally integer based. E.g. the Stored Pixel [Type](#) is unsigned short 12bits, but to get Hounsfield unit, one need to apply the linear transform:

$$RWV = 1. * SV - 1024$$

So the best scalar to store the Real World [Value](#) will be 16 bits signed type.

In PET: the linear transform is generally floating point based. Since the dynamic range can be quite high, the Rescale Slope / Rescale Intercept can be changing throughout the [Series](#). So it is important to read all linear transform and deduce the best Pixel [Type](#) only at the end (when all the images to be read have been parsed).

Warning

Internally any time a floating point value is found either in the Rescale Slope or the Rescale Intercept it is assumed that the best matching output pixel type is FLOAT64 (in previous implementation it was FLOAT32). Because [VR:DS](#) is closer to a 64bits floating point type FLOAT64 is thus a best matching pixel type for the floating point transformation.

Example: Let say input is FLOAT64, and we want UINT16 as output, we would do:

```
Rescaler ir;
ir.SetIntercept( 0 );
ir.SetSlope( 5.6789 );
ir.SetPixelFormat( FLOAT64 );
ir.SetMinMaxForPixelType( ((PixelFormat)UINT16).GetMin(), ((PixelFormat)UINT16).GetMax() );
ir.InverseRescale(output,input,numberofbytes );
```

Note

handle floating point transformation back and forth to integer properly (no loss)

See also

[Unpacker12Bits](#)

Examples

[RescaleImage.cs](#).

10.260.2 Constructor & Destructor Documentation

10.260.2.1 Rescaler()

```
gdcm::Rescaler::Rescaler () [inline]
```

10.260.2.2 ~Rescaler()

```
gdcm::Rescaler::~~Rescaler () [default]
```

10.260.3 Member Function Documentation

10.260.3.1 ComputeInterceptSlopePixelType()

```
PixelFormat::ScalarType gdcm::Rescaler::ComputeInterceptSlopePixelType ()
```

Compute the Pixel Format of the output data Used for direct transformation

Examples

[RescaleImage.cs](#).

10.260.3.2 ComputePixelTypeFromMinMax()

```
PixelFormat gdcm::Rescaler::ComputePixelTypeFromMinMax ()
```

Compute the Pixel Format of the output data Used for inverse transformation

10.260.3.3 GetIntercept()

```
double gdcm::Rescaler::GetIntercept () const [inline]
```

10.260.3.4 GetSlope()

```
double gdcm::Rescaler::GetSlope () const [inline]
```

10.260.3.5 InverseRescale()

```
bool gdcm::Rescaler::InverseRescale (  
    char * out,  
    const char * in,  
    size_t n)
```

Inverse transform.

10.260.3.6 InverseRescaleFunctionIntoBestFit()

```
template<typename TIn>  
void gdcm::Rescaler::InverseRescaleFunctionIntoBestFit (  
    char * out,  
    const TIn * in,  
    size_t n) [protected]
```

10.260.3.7 Rescale()

```
bool gdcm::Rescaler::Rescale (  
    char * out,  
    const char * in,  
    size_t n)
```

Direct transform.

Examples

[RescaleImage.cs](#).

10.260.3.8 RescaleFunctionIntoBestFit()

```
template<typename TIn>
void gdcM::Rescaler::RescaleFunctionIntoBestFit (
    char * out,
    const TIn * in,
    size_t n) [protected]
```

10.260.3.9 SetIntercept()

```
void gdcM::Rescaler::SetIntercept (
    double i) [inline]
```

Set Intercept: used for both direct&inverse transformation.

Examples

[RescaleImage.cs.](#)

10.260.3.10 SetMinMaxForPixelType()

```
void gdcM::Rescaler::SetMinMaxForPixelType (
    double min,
    double max)
```

Set target interval for output data. A best match will be computed (if possible) Used for inverse transformation

10.260.3.11 SetPixelFormat()

```
void gdcM::Rescaler::SetPixelFormat (
    PixelFormat const & pf) [inline]
```

Set Pixel Format of input data.

Examples

[RescaleImage.cs.](#)

10.260.3.12 SetSlope()

```
void gdcM::Rescaler::SetSlope (
    double s) [inline]
```

Set Slope: user for both direct&inverse transformation.

Examples

[RescaleImage.cs.](#)

10.260.3.13 SetTargetPixelFormat()

```
void gdcm::Rescaler::SetTargetPixelFormat (
    PixelFormat const & targetst)
```

By default (when UseTargetPixelFormat is false), a best matching Target Pixel [Type](#) is computed. However user can override this auto selection by switching UseTargetPixelFormat:true and also specifying the specific Target Pixel [Type](#)

10.260.3.14 SetUseTargetPixelFormat()

```
void gdcm::Rescaler::SetUseTargetPixelFormat (
    bool b)
```

Override default behavior of Rescale.

The documentation for this class was generated from the following file:


- [gdcmRescaler.h](#)

10.261 gdcm::RLECodec Class Reference


Class to do RLE.

```
#include <gdcmRLECodec.h>
```

Inheritance diagram for gdcm::RLECodec:



Collaboration diagram for `gdcm::RLECodec`:



Public Member Functions

- [RLECodec](#) ()
- [~RLECodec](#) () override
- bool [CanCode](#) ([TransferSyntax](#) const &ts) const override
Return whether this coder support this transfer syntax (can code it)
- bool [CanDecode](#) ([TransferSyntax](#) const &ts) const override
Return whether this decoder support this transfer syntax (can decode it)
- [ImageCodec](#) * [Clone](#) () const override
- bool [Code](#) ([DataElement](#) const &in, [DataElement](#) &out) override
Code.
- bool [Decode](#) ([DataElement](#) const &is, [DataElement](#) &os) override
Decode.
- unsigned long [GetBufferLength](#) () const
- bool [GetHeaderInfo](#) (std::istream &is, [TransferSyntax](#) &ts) override
- void [SetBufferLength](#) (unsigned long l)
- void [SetLength](#) (unsigned long l)

Public Member Functions inherited from [gdcm::ImageCodec](#)

- [ImageCodec](#) ()
- [~ImageCodec](#) () override
- bool [CleanupUnusedBits](#) (char *data, size_t datalen)
- const unsigned int * [GetDimensions](#) () const
- bool [GetLossyFlag](#) () const
- const [LookupTable](#) & [GetLUT](#) () const
- bool [GetNeedByteSwap](#) () const
- unsigned int [GetNumberOfDimensions](#) () const
- const [PhotometricInterpretation](#) & [GetPhotometricInterpretation](#) () const
- [PixelFormat](#) & [GetPixelFormat](#) ()
- const [PixelFormat](#) & [GetPixelFormat](#) () const
- unsigned int [GetPlanarConfiguration](#) () const
- bool [IsLossy](#) () const
- void [SetDimensions](#) (const std::vector< unsigned int > &d)
- void [SetDimensions](#) (const unsigned int d[3])

- void [SetLossyFlag](#) (bool l)
- void [SetLUT](#) ([LookupTable](#) const &lut)
- void [SetNeedByteSwap](#) (bool b)
- void [SetNeedOverlayCleanup](#) (bool b)
- void [SetNumberOfDimensions](#) (unsigned int dim)
- void [SetPhotometricInterpretation](#) ([PhotometricInterpretation](#) const &pi)
- virtual void [SetPixelFormat](#) ([PixelFormat](#) const &pf)
- void [SetPlanarConfiguration](#) (unsigned int pc)

Public Member Functions inherited from [gdcm::Coder](#)

- virtual [~Coder](#) ()=default

Public Member Functions inherited from [gdcm::Decoder](#)

- virtual [~Decoder](#) ()=default

Protected Member Functions

- bool [AppendFrameEncode](#) (std::ostream &out, const char *data, size_t datalen) override
- bool [AppendRowEncode](#) (std::ostream &out, const char *data, size_t datalen) override
- bool [DecodeByStreams](#) (std::istream &is, std::ostream &os) override
- bool [DecodeExtent](#) (char *buffer, unsigned int XMin, unsigned int XMax, unsigned int YMin, unsigned int YMax, unsigned int ZMin, unsigned int ZMax, std::istream &is)
- bool [IsFrameEncoder](#) () override
- bool [IsRowEncoder](#) () override
- bool [StartEncode](#) (std::ostream &) override
- bool [StopEncode](#) (std::ostream &) override

Protected Member Functions inherited from [gdcm::ImageCodec](#)

- bool [DoByteSwap](#) (std::istream &is_, std::ostream &os)
- bool [DoInvertMonochrome](#) (std::istream &is_, std::ostream &os)
- bool [DoOverlayCleanup](#) (std::istream &is_, std::ostream &os)
- bool [DoPaddedCompositePixelCode](#) (std::istream &is_, std::ostream &os)
- bool [DoPlanarConfiguration](#) (std::istream &is_, std::ostream &os)
- bool [DoSimpleCopy](#) (std::istream &is_, std::ostream &os)
- bool [DoYBR](#) (std::istream &is_, std::ostream &os)
- bool [DoYBRFull422](#) (std::istream &is_, std::ostream &os)
- virtual bool [IsValid](#) ([PhotometricInterpretation](#) const &pi)

Protected Member Functions inherited from [gdcm::Coder](#)

- virtual bool [InternalCode](#) (const char *bv, unsigned long len, std::ostream &os)

Friends

- class [ImageRegionReader](#)

Additional Inherited Members**Protected Types inherited from [gdcm::ImageCodec](#)**

- typedef [SmartPointer](#)< [LookupTable](#) > [LUTPtr](#)

Protected Attributes inherited from [gdcm::ImageCodec](#)

- unsigned int [Dimensions](#) [3]
- bool [LossyFlag](#)
- [LUTPtr](#) [LUT](#)
- bool [NeedByteSwap](#)
- bool [NeedOverlayCleanup](#)
- unsigned int [NumberOfDimensions](#)
- [PixelFormat](#) [PF](#)
- [PhotometricInterpretation](#) [PI](#)
- unsigned int [PlanarConfiguration](#)
- bool [RequestPaddedCompositePixelCode](#)
- bool [RequestPlanarConfiguration](#)

10.261.1 Detailed Description

Class to do RLE.

Note

ANSI X3.9 A.4.2 RLE Compression Annex G defines a RLE Compression Transfer Syntax. This transfer Syntax is identified by the UID value "1.2.840.10008.1.2.5". If the object allows multi-frame images in the pixel data field, then each frame shall be encoded separately. Each frame shall be encoded in one and only one [Fragment](#) (see PS 3.5.8.2).

10.261.2 Constructor & Destructor Documentation**10.261.2.1 RLECodec()**

```
gdcm::RLECodec::RLECodec ()
```

10.261.2.2 ~RLECodec()

```
gdcm::RLECodec::~~RLECodec () [override]
```

10.261.3 Member Function Documentation

10.261.3.1 AppendFrameEncode()

```
bool gdcm::RLECodec::AppendFrameEncode (
    std::ostream & out,
    const char * data,
    size_t datalen) [override], [protected], [virtual]
```

Reimplemented from [gdcm::ImageCodec](#).

10.261.3.2 AppendRowEncode()

```
bool gdcm::RLECodec::AppendRowEncode (
    std::ostream & out,
    const char * data,
    size_t datalen) [override], [protected], [virtual]
```

Reimplemented from [gdcm::ImageCodec](#).

10.261.3.3 CanCode()

```
bool gdcm::RLECodec::CanCode (
    TransferSyntax const & ) const [override], [virtual]
```

Return whether this coder support this transfer syntax (can code it)

Reimplemented from [gdcm::ImageCodec](#).

10.261.3.4 CanDecode()

```
bool gdcm::RLECodec::CanDecode (
    TransferSyntax const & ) const [override], [virtual]
```

Return whether this decoder support this transfer syntax (can decode it)

Reimplemented from [gdcm::ImageCodec](#).

10.261.3.5 Clone()

```
ImageCodec * gdcm::RLECodec::Clone () const [override], [virtual]
```

Implements [gdcm::ImageCodec](#).

References [gdcm::ImageCodec::ImageCodec\(\)](#).

10.261.3.6 Code()

```
bool gdcm::RLECodec::Code (
    DataElement const & in_,
    DataElement & out_) [override], [virtual]
```

Code.

Reimplemented from [gdcm::Coder](#).

10.261.3.7 Decode()

```
bool gdcm::RLECodec::Decode (
    DataElement const & ,
    DataElement & ) [override], [virtual]
```

Decode.

Reimplemented from [gdcm::ImageCodec](#).

10.261.3.8 DecodeByStreams()

```
bool gdcm::RLECodec::DecodeByStreams (
    std::istream & is,
    std::ostream & os) [override], [protected], [virtual]
```

Reimplemented from [gdcm::ImageCodec](#).

10.261.3.9 DecodeExtent()

```
bool gdcm::RLECodec::DecodeExtent (
    char * buffer,
    unsigned int XMin,
    unsigned int XMax,
    unsigned int YMin,
    unsigned int YMax,
    unsigned int ZMin,
    unsigned int ZMax,
    std::istream & is) [protected]
```

10.261.3.10 GetBufferLength()

```
unsigned long gdcm::RLECodec::GetBufferLength () const [inline]
```


10.261.3.11 GetHeaderInfo()

```
bool gdcm::RLECodec::GetHeaderInfo (
    std::istream & is,
    TransferSyntax & ts) [override], [virtual]
```

Reimplemented from [gdcm::ImageCodec](#).

10.261.3.12 IsFrameEncoder()

```
bool gdcm::RLECodec::IsFrameEncoder () [override], [protected], [virtual]
```

Reimplemented from [gdcm::ImageCodec](#).

10.261.3.13 IsRowEncoder()

```
bool gdcm::RLECodec::IsRowEncoder () [override], [protected], [virtual]
```

Reimplemented from [gdcm::ImageCodec](#).

10.261.3.14 SetBufferLength()

```
void gdcm::RLECodec::SetBufferLength (
    unsigned long l) [inline]
```

10.261.3.15 SetLength()

```
void gdcm::RLECodec::SetLength (
    unsigned long l) [inline]
```

10.261.3.16 StartEncode()

```
bool gdcm::RLECodec::StartEncode (
    std::ostream & ) [override], [protected], [virtual]
```

Reimplemented from [gdcm::ImageCodec](#).

10.261.3.17 StopEncode()

```
bool gdcm::RLECodec::StopEncode (
    std::ostream & ) [override], [protected], [virtual]
```

Reimplemented from [gdcm::ImageCodec](#).

10.261.4 Friends And Related Symbol Documentation

10.261.4.1 ImageRegionReader

`friend class ImageRegionReader [friend]`

References [ImageRegionReader](#).

Referenced by [ImageRegionReader](#).

The documentation for this class was generated from the following file:

- [gdcmRLECodec.h](#)

10.262 gdcm::network::RoleSelectionSub Class Reference

[RoleSelectionSub](#).

```
#include <gdcmRoleSelectionSub.h>
```

Public Member Functions

- [RoleSelectionSub](#) ()
- void [Print](#) (std::ostream &os) const
- std::istream & [Read](#) (std::istream &is)
- void [SetTuple](#) (const char *uid, uint8_t scurole, uint8_t scprole)
- size_t [Size](#) () const
- const std::ostream & [Write](#) (std::ostream &os) const

10.262.1 Detailed Description

[RoleSelectionSub](#).

PS 3.7 [Table D.3-9](#) SCP/SCU ROLE SELECTION SUB-ITEM FIELDS (A-ASSOCIATE-RQ)

10.262.2 Constructor & Destructor Documentation

10.262.2.1 RoleSelectionSub()

```
gdcm::network::RoleSelectionSub::RoleSelectionSub ()
```

10.262.3 Member Function Documentation

10.262.3.1 Print()

```
void gdcm::network::RoleSelectionSub::Print (  
    std::ostream & os) const
```

10.262.3.2 Read()

```
std::istream & gdcm::network::RoleSelectionSub::Read (  
    std::istream & is)
```

10.262.3.3 SetTuple()

```
void gdcm::network::RoleSelectionSub::SetTuple (  
    const char * uid,  
    uint8_t scurole,  
    uint8_t scprole)
```

10.262.3.4 Size()

```
size_t gdcm::network::RoleSelectionSub::Size () const
```

10.262.3.5 Write()

```
const std::ostream & gdcm::network::RoleSelectionSub::Write (  
    std::ostream & os) const
```

The documentation for this class was generated from the following file:


- [gdcmRoleSelectionSub.h](#)

10.263 gdcm::Scanner Class Reference


[Scanner](#).

```
#include <gdcmScanner.h>
```

Inheritance diagram for gdcm::Scanner:



Collaboration diagram for gdcm::Scanner:



Classes

- struct [ltstr](#)

Public Types

- typedef MappingType::const_iterator [ConstIterator](#)
- typedef std::map< const char *, [TagToValue](#), [Itstr](#) > [MappingType](#)
- typedef std::map< [Tag](#), const char * > [TagToValue](#)
- typedef TagToValue::value_type [TagToValueValueType](#)
- typedef std::set< std::string > [ValuesType](#)

Public Member Functions

- [Scanner](#) ()
- [~Scanner](#) () override
- void [AddPrivateTag](#) ([PrivateTag](#) const &t)
- void [AddSkipTag](#) ([Tag](#) const &t)
Add a tag that will need to be skipped. Those are root level skip tags.
- void [AddTag](#) ([Tag](#) const &t)
Add a tag that will need to be read. Those are root level tags.
- [ConstIterator](#) [Begin](#) () const
- void [ClearSkipTags](#) ()
- void [ClearTags](#) ()
- [ConstIterator](#) [End](#) () const
- [Directory::FileNamesType](#) [GetAllFileNamesFromTagToValue](#) ([Tag](#) const &t, const char *valueref) const
- const char * [GetFilenameFromTagToValue](#) ([Tag](#) const &t, const char *valueref) const
- [Directory::FileNamesType](#) const & [GetFileNames](#) () const
- [Directory::FileNamesType](#) [GetKeys](#) () const
- [TagToValue](#) const & [GetMapping](#) (const char *filename) const
Get the std::map mapping filenames to value for file 'filename'.
- [TagToValue](#) const & [GetMappingFromTagToValue](#) ([Tag](#) const &t, const char *value) const
See [GetFilenameFromTagToValue\(\)](#). This is simply [GetFilenameFromTagToValue](#) followed.
- [MappingType](#) const & [GetMappings](#) () const
Mappings are the mapping from a particular tag to the map, mapping filename to value:
- [Directory::FileNamesType](#) [GetOrderedValues](#) ([Tag](#) const &t) const
- const char * [GetValue](#) (const char *filename, [Tag](#) const &t) const
- [ValuesType](#) const & [GetValues](#) () const
Get all the values found (in lexicographic order)
- [ValuesType](#) [GetValues](#) ([Tag](#) const &t) const
Get all the values found (in lexicographic order) associated with [Tag](#) 't'.
- bool [IsKey](#) (const char *filename) const
- void [Print](#) (std::ostream &os) const override
Print result.
- void [PrintTable](#) (std::ostream &os) const
- bool [Scan](#) ([Directory::FileNamesType](#) const &filenames)
Start the scan !

Public Member Functions inherited from [gdcm::Subject](#)

- [Subject](#) ()
- [~Subject](#) () override
- unsigned long [AddObserver](#) (const [Event](#) &event, [Command](#) *)
- unsigned long [AddObserver](#) (const [Event](#) &event, [Command](#) *) const
- [Command](#) * [GetCommand](#) (unsigned long tag)
- bool [HasObserver](#) (const [Event](#) &event) const
- void [InvokeEvent](#) (const [Event](#) &)
- void [InvokeEvent](#) (const [Event](#) &) const
- void [RemoveAllObservers](#) ()
- void [RemoveObserver](#) (unsigned long tag)

Public Member Functions inherited from [gdcm::Object](#)

- [Object](#) ()
- [Object](#) (const [Object](#) &)
Special requirement for copy/cstor, assignment operator.
- virtual [~Object](#) ()
- void [operator=](#) (const [Object](#) &)

Static Public Member Functions

- static [SmartPointer](#)< [Scanner](#) > [New](#) ()
for wrapped language: instantiate a reference counted object

Protected Member Functions

- void [ProcessPublicTag](#) ([StringFilter](#) &sf, const char *filename)

Protected Member Functions inherited from [gdcm::Object](#)

- void [Register](#) ()
- void [UnRegister](#) ()

Friends

- std::ostream & [operator<<](#) (std::ostream &_os, const [Scanner](#) &s)

10.263.1 Detailed Description

[Scanner](#).

This filter is meant for quickly browsing a [FileSet](#) (a set of files on disk). Special consideration are taken so as to read the minimum amount of information in each file in order to retrieve the user specified set of DICOM [Attribute](#).

This filter is dealing with both VRASCII and VRBINARY element, thanks to the help of [StringFilter](#)

Warning

IMPORTANT In case of file where tags are not ordered (illegal as per DICOM specification), the output will be missing information

Note

implementation details. All values are stored in a `std::set of std::string`. Then the address of the `cstring` underlying the `std::string` is used in the `std::map`.

This class implement the Subject/Observer pattern trigger the following events:

- [ProgressEvent](#)
- [StartEvent](#)
- [EndEvent](#)

Examples

[DiscriminateVolume.cxx](#), [DumpToSQLITE3.cxx](#), [SortImage.cxx](#), and [VolumeSorter.cxx](#).

10.263.2 Member Typedef Documentation

10.263.2.1 ConstIterator

```
typedef MappingType::const_iterator gdcm::Scanner::ConstIterator
```

10.263.2.2 MappingType

```
typedef std::map<const char *, TagToValue, ltstr> gdcm::Scanner::MappingType
```

10.263.2.3 TagToValue

```
typedef std::map<Tag, const char*> gdcm::Scanner::TagToValue
```

struct to map a filename to a value Implementation note: all `std::map` in this class will be using `const char *` and not `std::string` since we are pointing to existing `std::string` (hold in a `std::vector`) this avoid an extra copy of the byte array. [Tag](#) are used as [Tag](#) class since `sizeof(tag) <= sizeof(pointer)`

10.263.2.4 TagToValueValueType

```
typedef TagToValue::value_type gdcmm::Scanner::TagToValueValueType
```

10.263.2.5 ValueType

```
typedef std::set< std::string > gdcmm::Scanner::ValueType
```

Examples

[DiscriminateVolume.cxx](#), [SortImage.cxx](#), and [VolumeSorter.cxx](#).

10.263.3 Constructor & Destructor Documentation

10.263.3.1 Scanner()

```
gdcmm::Scanner::Scanner () [inline]
```

Referenced by [New\(\)](#), and [operator<<](#).

10.263.3.2 ~Scanner()

```
gdcmm::Scanner::~~Scanner () [override]
```

10.263.4 Member Function Documentation

10.263.4.1 AddPrivateTag()

```
void gdcmm::Scanner::AddPrivateTag (  
    PrivateTag const & t)
```

10.263.4.2 AddSkipTag()

```
void gdcmm::Scanner::AddSkipTag (  
    Tag const & t)
```

Add a tag that will need to be skipped. Those are root level skip tags.

10.263.4.3 AddTag()

```
void gdcm::Scanner::AddTag (  
    Tag const & t)
```

Add a tag that will need to be read. Those are root level tags.

Examples

[DiscriminateVolume.cxx](#), [DumpToSQLITE3.cxx](#), [SortImage.cxx](#), and [VolumeSorter.cxx](#).

10.263.4.4 Begin()

```
ConstIterator gdcm::Scanner::Begin () const [inline]
```

10.263.4.5 ClearSkipTags()

```
void gdcm::Scanner::ClearSkipTags ()
```

10.263.4.6 ClearTags()

```
void gdcm::Scanner::ClearTags ()
```

10.263.4.7 End()

```
ConstIterator gdcm::Scanner::End () const [inline]
```

10.263.4.8 GetAllFileNamesFromTagToValue()

```
Directory::FileNamesType gdcm::Scanner::GetAllFileNamesFromTagToValue (  
    Tag const & t,  
    const char * valuref) const
```

Will loop over all files and return a vector of std::strings of filenames where value match the reference value 'valuref'

10.263.4.9 GetFilenameFromTagToValue()

```
const char * gdcm::Scanner::GetFilenameFromTagToValue (  
    Tag const & t,  
    const char * valuref) const
```

Will loop over all files and return the first file where value match the reference value 'valuref'

10.263.4.10 GetFileNames()

```
Directory::FilenameType const & gdcM::Scanner::GetFileNames () const [inline]
```

10.263.4.11 GetKeys()

```
Directory::FilenameType gdcM::Scanner::GetKeys () const
```

Return the list of filename that are key in the internal map, which means those filename were properly parsed

Examples

[VolumeSorter.cxx](#).

10.263.4.12 GetMapping()

```
TagToValue const & gdcM::Scanner::GetMapping (
    const char * filename) const
```

Get the std::map mapping filenames to value for file 'filename'.

Examples

[DumpToSQLITE3.cxx](#).

10.263.4.13 GetMappingFromTagToValue()

```
TagToValue const & gdcM::Scanner::GetMappingFromTagToValue (
    Tag const & t,
    const char * value) const
```

See [GetFilenameFromTagToValue\(\)](#). This is simply GetFilenameFromTagToValue followed.

10.263.4.14 GetMappings()

```
MappingType const & gdcM::Scanner::GetMappings () const [inline]
```

Mappings are the mapping from a particular tag to the map, mapping filename to value:

10.263.4.15 GetOrderedValues()

```
Directory::FilenameType gdcM::Scanner::GetOrderedValues (
    Tag const & t) const
```

Get all the values found (in a vector) associated with [Tag](#) 't' This function is identical to GetValues, but is accessible from the wrapped layer (python, C#, java)

10.263.4.16 GetValue()

```
const char * gdcm::Scanner::GetValue (
    const char * filename,
    Tag const & t) const
```

Retrieve the value found for tag: t associated with file: filename This is meant for a single short call. If multiple calls (multiple tags) should be done, prefer the GetMapping function, and then reuse the [TagToValue](#) hash table.

Warning

[Tag](#) 't' should have been added via [AddTag\(\)](#) prior to the [Scan\(\)](#) call !

10.263.4.17 GetValues() [1/2]

```
ValueType const & gdcm::Scanner::GetValues () const [inline]
```

Get all the values found (in lexicographic order)

Examples

[SortImage.cxx](#), and [VolumeSorter.cxx](#).

10.263.4.18 GetValues() [2/2]

```
ValueType gdcm::Scanner::GetValues (
    Tag const & t) const
```

Get all the values found (in lexicographic order) associated with [Tag](#) 't'.

10.263.4.19 IsKey()

```
bool gdcm::Scanner::IsKey (
    const char * filename) const
```

Check if filename is a key in the Mapping table. returns true only if file can be found, which means the file was indeed a DICOM file that could be processed

Examples

[DumpToSQLITE3.cxx](#).

10.263.4.20 New()

```
SmartPointer< Scanner > gdcM::Scanner::New () [inline], [static]
```

for wrapped language: instantiate a reference counted object

References [Scanner\(\)](#).

10.263.4.21 Print()

```
void gdcM::Scanner::Print (
    std::ostream & os) const [override], [virtual]
```

Print result.

Reimplemented from [gdcM::Object](#).

Referenced by [operator<<](#).

10.263.4.22 PrintTable()

```
void gdcM::Scanner::PrintTable (
    std::ostream & os) const
```

10.263.4.23 ProcessPublicTag()

```
void gdcM::Scanner::ProcessPublicTag (
    StringFilter & sf,
    const char * filename) [protected]
```

10.263.4.24 Scan()

```
bool gdcM::Scanner::Scan (
    Directory::FileNamesType const & filenames)
```

Start the scan !

Examples

[DiscriminateVolume.cxx](#), [DumpToSQLITE3.cxx](#), [SortImage.cxx](#), and [VolumeSorter.cxx](#).

10.263.5 Friends And Related Symbol Documentation

10.263.5.1 operator<<

```
std::ostream & operator<< (  
    std::ostream & _os,  
    const Scanner & s) [friend]
```

References [Scanner\(\)](#), and [Print\(\)](#).

The documentation for this class was generated from the following file:


- [gdcmScanner.h](#)

10.264 gdcm::Scanner2 Class Reference


[Scanner2](#).

```
#include <gdcmScanner2.h>
```

Inheritance diagram for gdcm::Scanner2:



Collaboration diagram for `gdcm::Scanner2`:



Classes

- struct [Itstr](#)

Public Types

- typedef `PrivateMappingType::const_iterator` [PrivateConstIterator](#)
- typedef `std::map< const char *, PrivateTagToValue, Itstr >` [PrivateMappingType](#)
- typedef `std::map< PrivateTag, const char * >` [PrivateTagToValue](#)
- typedef `PrivateTagToValue::value_type` [PrivateTagToValueValueType](#)
- typedef `PublicMappingType::const_iterator` [PublicConstIterator](#)
- typedef `std::map< const char *, PublicTagToValue, Itstr >` [PublicMappingType](#)
- typedef `std::map< Tag, const char * >` [PublicTagToValue](#)
- typedef `PublicTagToValue::value_type` [PublicTagToValueValueType](#)
- typedef `std::set< std::string >` [ValuesType](#)

Public Member Functions

- [Scanner2](#) ()
- [~Scanner2](#) () override
- bool [AddPrivateTag](#) ([PrivateTag](#) const &pt)
- bool [AddPublicTag](#) ([Tag](#) const &t)
Add a tag that will need to be read. Those are root level tags.
- bool [AddSkipTag](#) ([Tag](#) const &t)
Add a tag that will need to be skipped. Those are root level skip tags.
- [PublicConstIterator](#) [Begin](#) () const
- void [ClearPrivateTags](#) ()
- void [ClearPublicTags](#) ()

- void [ClearSkipTags](#) ()
- [PublicConstIterator End](#) () const
- [Directory::FilenamesType GetAllFilenamesFromPrivateTagToValue](#) ([PrivateTag](#) const &pt, const char *valueref) const
- [Directory::FilenamesType GetAllFilenamesFromPublicTagToValue](#) ([Tag](#) const &t, const char *valueref) const
- const char * [GetFilenameFromPrivateTagToValue](#) ([PrivateTag](#) const &pt, const char *valueref) const
- const char * [GetFilenameFromPublicTagToValue](#) ([Tag](#) const &t, const char *valueref) const
- [Directory::FilenamesType](#) const & [GetFilenames](#) () const

Return the list of filenames.
- [Directory::FilenamesType GetKeys](#) () const
- [PrivateTagToValue](#) const & [GetMappingFromPrivateTagToValue](#) ([PrivateTag](#) const &pt, const char *value) const
- [PublicTagToValue](#) const & [GetMappingFromPublicTagToValue](#) ([Tag](#) const &t, const char *value) const

See [GetFilenameFromTagToValue](#)(). This is simply [GetFilenameFromTagToValue](#) followed.
- [PrivateTagToValue](#) const & [GetPrivateMapping](#) (const char *filename) const
- [PrivateMappingType](#) const & [GetPrivateMappings](#) () const
- [Directory::FilenamesType GetPrivateOrderedValues](#) ([PrivateTag](#) const &pt) const
- const char * [GetPrivateValue](#) (const char *filename, [PrivateTag](#) const &t) const
- [ValuesType GetPrivateValues](#) ([PrivateTag](#) const &pt) const

Get all the values found (in lexicographic order) associated with [PrivateTag](#) 'pt'.
- [PublicTagToValue](#) const & [GetPublicMapping](#) (const char *filename) const

Get the std::map mapping filenames to value for file 'filename'.
- [PublicMappingType](#) const & [GetPublicMappings](#) () const

Mappings are the mapping from a particular tag to the map, mapping filename to value:
- [Directory::FilenamesType GetPublicOrderedValues](#) ([Tag](#) const &t) const
- const char * [GetPublicValue](#) (const char *filename, [Tag](#) const &t) const
- [ValuesType GetPublicValues](#) ([Tag](#) const &t) const

Get all the values found (in lexicographic order) associated with [Tag](#) 't'.
- [ValuesType](#) const & [GetValues](#) () const

Get all the values found (in lexicographic order)
- bool [IsKey](#) (const char *filename) const
- void [Print](#) (std::ostream &os) const override

Print result.
- void [PrintTable](#) (std::ostream &os, bool header=false) const

Print result as CSV table.
- [PrivateConstIterator PrivateBegin](#) () const
- [PrivateConstIterator PrivateEnd](#) () const
- bool [Scan](#) ([Directory::FilenamesType](#) const &filenames)

Start the scan !

Public Member Functions inherited from [gdcmm::Subject](#)

- [Subject](#) ()
- [~Subject](#) () override
- unsigned long [AddObserver](#) (const [Event](#) &event, [Command](#) *)
- unsigned long [AddObserver](#) (const [Event](#) &event, [Command](#) *) const
- [Command](#) * [GetCommand](#) (unsigned long tag)
- bool [HasObserver](#) (const [Event](#) &event) const
- void [InvokeEvent](#) (const [Event](#) &)
- void [InvokeEvent](#) (const [Event](#) &) const
- void [RemoveAllObservers](#) ()
- void [RemoveObserver](#) (unsigned long tag)

Public Member Functions inherited from [gdcm::Object](#)

- [Object](#) ()
- [Object](#) (const [Object](#) &)
Special requirement for copy/cstor, assignment operator.
- virtual [~Object](#) ()
- void [operator=](#) (const [Object](#) &)

Static Public Member Functions

- static [SmartPointer](#)< [Scanner2](#) > [New](#) ()
for wrapped language: instantiate a reference counted object

Protected Member Functions

- void [ProcessPrivateTag](#) ([StringFilter](#) &sf, const char *filename)
- void [ProcessPublicTag](#) ([StringFilter](#) &sf, const char *filename)

Protected Member Functions inherited from [gdcm::Object](#)

- void [Register](#) ()
- void [UnRegister](#) ()

Friends

- std::ostream & [operator<<](#) (std::ostream &_os, const [Scanner2](#) &s)

10.264.1 Detailed Description

[Scanner2](#).

This filter is meant for quickly browsing a [FileSet](#) (a set of files on disk). Special consideration are taken so as to read the minimum amount of information in each file in order to retrieve the user specified set of DICOM [Attribute](#).

This filter is dealing with both VRASCII and VRBINARY element, thanks to the help of [StringFilter](#)

Warning

IMPORTANT In case of file where tags are not ordered (illegal as per DICOM specification), the output will be missing information

Note

implementation details. All values are stored in a std::set of std::string. Then the address of the cstring underlying the std::string is used in the std::map.

This class implement the Subject/Observer pattern trigger the following events:

- [ProgressEvent](#)
- [StartEvent](#)
- [EndEvent](#)

10.264.2 Member Typedef Documentation

10.264.2.1 PrivateConstIterator

```
typedef PrivateMappingType::const_iterator gdcm::Scanner2::PrivateConstIterator
```

10.264.2.2 PrivateMappingType

```
typedef std::map<const char *,PrivateTagToValue, ltstr> gdcm::Scanner2::PrivateMappingType
```

10.264.2.3 PrivateTagToValue

```
typedef std::map<PrivateTag, const char*> gdcm::Scanner2::PrivateTagToValue
```

10.264.2.4 PrivateTagToValueValueType

```
typedef PrivateTagToValue::value_type gdcm::Scanner2::PrivateTagToValueValueType
```

10.264.2.5 PublicConstIterator

```
typedef PublicMappingType::const_iterator gdcm::Scanner2::PublicConstIterator
```

10.264.2.6 PublicMappingType

```
typedef std::map<const char *,PublicTagToValue, ltstr> gdcm::Scanner2::PublicMappingType
```

10.264.2.7 PublicTagToValue

```
typedef std::map<Tag, const char*> gdcm::Scanner2::PublicTagToValue
```

struct to map a filename to a value Implementation note: all std::map in this class will be using const char * and not std::string since we are pointing to existing std::string (held in a std::vector) this avoid an extra copy of the byte array. [Tag](#) are used as [Tag](#) class since sizeof(tag) <= sizeof(pointer)

10.264.2.8 PublicTagToValueValueType

```
typedef PublicTagToValue::value_type gdcm::Scanner2::PublicTagToValueValueType
```

10.264.2.9 ValueType

```
typedef std::set< std::string > gdc::Scanner2::ValueType
```

10.264.3 Constructor & Destructor Documentation

10.264.3.1 Scanner2()

```
gdc::Scanner2::Scanner2 () [inline]
```

Referenced by [New\(\)](#), and [operator<<](#).

10.264.3.2 ~Scanner2()

```
gdc::Scanner2::~~Scanner2 () [override]
```

10.264.4 Member Function Documentation

10.264.4.1 AddPrivateTag()

```
bool gdc::Scanner2::AddPrivateTag (  
    PrivateTag const & pt)
```

10.264.4.2 AddPublicTag()

```
bool gdc::Scanner2::AddPublicTag (  
    Tag const & t)
```

Add a tag that will need to be read. Those are root level tags.

10.264.4.3 AddSkipTag()

```
bool gdc::Scanner2::AddSkipTag (  
    Tag const & t)
```

Add a tag that will need to be skipped. Those are root level skip tags.

10.264.4.4 Begin()

```
PublicConstIterator gdc::Scanner2::Begin () const [inline]
```

10.264.4.5 ClearPrivateTags()

```
void gdcm::Scanner2::ClearPrivateTags ()
```

10.264.4.6 ClearPublicTags()

```
void gdcm::Scanner2::ClearPublicTags ()
```

10.264.4.7 ClearSkipTags()

```
void gdcm::Scanner2::ClearSkipTags ()
```

10.264.4.8 End()

```
PublicConstIterator gdcm::Scanner2::End () const [inline]
```

10.264.4.9 GetAllFileNamesFromPrivateTagToValue()

```
Directory::FileNamesType gdcm::Scanner2::GetAllFileNamesFromPrivateTagToValue (  
    PrivateTag const & pt,  
    const char * valueref) const
```

10.264.4.10 GetAllFileNamesFromPublicTagToValue()

```
Directory::FileNamesType gdcm::Scanner2::GetAllFileNamesFromPublicTagToValue (  
    Tag const & t,  
    const char * valueref) const
```

Will loop over all files and return a vector of std::strings of filenames where value match the reference value 'valueref'

10.264.4.11 GetFilenameFromPrivateTagToValue()

```
const char * gdcm::Scanner2::GetFilenameFromPrivateTagToValue (  
    PrivateTag const & pt,  
    const char * valueref) const
```

10.264.4.12 GetFilenameFromPublicTagToValue()

```
const char * gdcm::Scanner2::GetFilenameFromPublicTagToValue (  
    Tag const & t,  
    const char * valueref) const
```

Will loop over all files and return the first file where value match the reference value 'valueref'

10.264.4.13 GetFilenames()

```
Directory::FilenamesType const & gdcm::Scanner2::GetFilenames () const [inline]
```

Return the list of filenames.

10.264.4.14 GetKeys()

```
Directory::FilenamesType gdcm::Scanner2::GetKeys () const
```

Return the list of filename that are key in the internal map, which means those filename were properly parsed

10.264.4.15 GetMappingFromPrivateTagToValue()

```
PrivateTagToValue const & gdcm::Scanner2::GetMappingFromPrivateTagToValue (  
    PrivateTag const & pt,  
    const char * value) const
```

10.264.4.16 GetMappingFromPublicTagToValue()

```
PublicTagToValue const & gdcm::Scanner2::GetMappingFromPublicTagToValue (  
    Tag const & t,  
    const char * value) const
```

See GetFilenameFromTagToValue(). This is simply GetFilenameFromTagToValue followed.

10.264.4.17 GetPrivateMapping()

```
PrivateTagToValue const & gdcm::Scanner2::GetPrivateMapping (  
    const char * filename) const
```

10.264.4.18 GetPrivateMappings()

```
PrivateMappingType const & gdcm::Scanner2::GetPrivateMappings () const [inline]
```

10.264.4.19 GetPrivateOrderedValues()

```
Directory::FilenamesType gdcm::Scanner2::GetPrivateOrderedValues (  
    PrivateTag const & pt) const
```

10.264.4.20 GetPrivateValue()

```
const char * gdcmm::Scanner2::GetPrivateValue (
    const char * filename,
    PrivateTag const & t) const
```

10.264.4.21 GetPrivateValues()

```
ValueType gdcmm::Scanner2::GetPrivateValues (
    PrivateTag const & pt) const
```

Get all the values found (in lexicographic order) associated with [PrivateTag](#) 'pt'.

10.264.4.22 GetPublicMapping()

```
PublicTagToValue const & gdcmm::Scanner2::GetPublicMapping (
    const char * filename) const
```

Get the std::map mapping filenames to value for file 'filename'.

10.264.4.23 GetPublicMappings()

```
PublicMappingType const & gdcmm::Scanner2::GetPublicMappings () const [inline]
```

Mappings are the mapping from a particular tag to the map, mapping filename to value:

10.264.4.24 GetPublicOrderedValues()

```
Directory::FileNamesType gdcmm::Scanner2::GetPublicOrderedValues (
    Tag const & t) const
```

Get all the values found (in a vector) associated with [Tag](#) 't' This function is identical to `GetValues`, but is accessible from the wrapped layer (python, C#, java)

10.264.4.25 GetPublicValue()

```
const char * gdcmm::Scanner2::GetPublicValue (
    const char * filename,
    Tag const & t) const
```

Retrieve the value found for tag: t associated with file: filename This is meant for a single short call. If multiple calls (multiple tags) should be done, prefer the `GetMapping` function, and then reuse the `TagToValue` hash table.

Warning

[Tag](#) 't' should have been added via `AddTag()` prior to the `Scan()` call !

10.264.4.26 GetPublicValues()

```
ValueType gdcM::Scanner2::GetPublicValues (
    Tag const & t) const
```

Get all the values found (in lexicographic order) associated with [Tag](#) 't'.

10.264.4.27 GetValues()

```
ValueType const & gdcM::Scanner2::GetValues () const [inline]
```

Get all the values found (in lexicographic order)

10.264.4.28 IsKey()

```
bool gdcM::Scanner2::IsKey (
    const char * filename) const
```

Check if filename is a key in the Mapping table. returns true only if file can be found, which means the file was indeed a DICOM file that could be processed

10.264.4.29 New()

```
SmartPointer< Scanner2 > gdcM::Scanner2::New () [inline], [static]
```

for wrapped language: instantiate a reference counted object

References [Scanner2\(\)](#).

10.264.4.30 Print()

```
void gdcM::Scanner2::Print (
    std::ostream & os) const [override], [virtual]
```

Print result.

Reimplemented from [gdcM::Object](#).

Referenced by [operator<<](#).

10.264.4.31 PrintTable()

```
void gdcM::Scanner2::PrintTable (
    std::ostream & os,
    bool header = false) const
```

Print result as CSV table.

10.264.4.32 PrivateBegin()

```
PrivateConstIterator gdcm::Scanner2::PrivateBegin () const [inline]
```

10.264.4.33 PrivateEnd()

```
PrivateConstIterator gdcm::Scanner2::PrivateEnd () const [inline]
```

10.264.4.34 ProcessPrivateTag()

```
void gdcm::Scanner2::ProcessPrivateTag (  
    StringFilter & sf,  
    const char * filename) [protected]
```

10.264.4.35 ProcessPublicTag()

```
void gdcm::Scanner2::ProcessPublicTag (  
    StringFilter & sf,  
    const char * filename) [protected]
```

10.264.4.36 Scan()

```
bool gdcm::Scanner2::Scan (  
    Directory::FileNamesType const & filenames)
```

Start the scan !

10.264.5 Friends And Related Symbol Documentation

10.264.5.1 operator<<

```
std::ostream & operator<< (  
    std::ostream & _os,  
    const Scanner2 & s) [friend]
```

References [Scanner2\(\)](#), and [Print\(\)](#).

The documentation for this class was generated from the following file:


- [gdcmScanner2.h](#)

10.265 gdcm::Segment Class Reference


This class defines a segment.

```
#include <gdcmSegment.h>
```

Inheritance diagram for gdcm::Segment:



Collaboration diagram for gdcm::Segment:



Public Types

- enum `ALGOType` {
`AUTOMATIC` = 0 ,
`SEMIAUTOMATIC` ,
`MANUAL` ,
`ALGOType_END` }
- typedef `std::vector< SegmentHelper::BasicCodedEntry >` `BasicCodedEntryVector`
- typedef `std::vector< SmartPointer< Surface > >` `SurfaceVector`

Public Member Functions

- [Segment](#) ()
- [~Segment](#) () override
- void [AddSurface](#) ([SmartPointer](#)< [Surface](#) > surface)
- [SegmentHelper::BasicCodedEntry](#) & [GetAnatomicRegion](#) ()
- [SegmentHelper::BasicCodedEntry](#) const & [GetAnatomicRegion](#) () const
- [BasicCodedEntryVector](#) & [GetAnatomicRegionModifiers](#) ()
- [BasicCodedEntryVector](#) const & [GetAnatomicRegionModifiers](#) () const
- [SegmentHelper::BasicCodedEntry](#) & [GetPropertyCategory](#) ()
- [SegmentHelper::BasicCodedEntry](#) const & [GetPropertyCategory](#) () const
- [SegmentHelper::BasicCodedEntry](#) & [GetPropertyType](#) ()
- [SegmentHelper::BasicCodedEntry](#) const & [GetPropertyType](#) () const
- [BasicCodedEntryVector](#) & [GetPropertyTypeModifiers](#) ()
- [BasicCodedEntryVector](#) const & [GetPropertyTypeModifiers](#) () const
- const char * [GetSegmentAlgorithmName](#) () const
- [ALGOType](#) [GetSegmentAlgorithmType](#) () const
- const char * [GetSegmentDescription](#) () const
- const char * [GetSegmentLabel](#) () const
- unsigned short [GetSegmentNumber](#) () const
- [SmartPointer](#)< [Surface](#) > [GetSurface](#) (const unsigned int idx=0) const
- unsigned long [GetSurfaceCount](#) ()
- [SurfaceVector](#) & [GetSurfaces](#) ()
- [SurfaceVector](#) const & [GetSurfaces](#) () const
- void [SetAnatomicRegion](#) ([SegmentHelper::BasicCodedEntry](#) const &BSE)
- void [SetAnatomicRegionModifiers](#) ([BasicCodedEntryVector](#) const &BSEV)
- void [SetPropertyCategory](#) ([SegmentHelper::BasicCodedEntry](#) const &BSE)
- void [SetPropertyType](#) ([SegmentHelper::BasicCodedEntry](#) const &BSE)
- void [SetPropertyTypeModifiers](#) ([BasicCodedEntryVector](#) const &BSEV)
- void [SetSegmentAlgorithmName](#) (const char *name)
- void [SetSegmentAlgorithmType](#) ([ALGOType](#) type)
- void [SetSegmentAlgorithmType](#) (const char *typeStr)
- void [SetSegmentDescription](#) (const char *description)
- void [SetSegmentLabel](#) (const char *label)
- void [SetSegmentNumber](#) (const unsigned short num)
- void [SetSurfaceCount](#) (const unsigned long nb)

Public Member Functions inherited from [gdcm::Object](#)

- [Object](#) ()
- [Object](#) (const [Object](#) &)
- *Special requirement for copy/cstor, assignment operator.*
- virtual [~Object](#) ()
- void [operator=](#) (const [Object](#) &)
- virtual void [Print](#) (std::ostream &) const

Static Public Member Functions

- static [ALGOType](#) [GetALGOType](#) (const char *type)
- static const char * [GetALGOTypeString](#) ([ALGOType](#) type)

Protected Attributes

- [SegmentHelper::BasicCodedEntry](#) [AnatomicRegion](#)
- [BasicCodedEntryVector](#) [AnatomicRegionModifiers](#)
- [SegmentHelper::BasicCodedEntry](#) [PropertyCategory](#)
- [SegmentHelper::BasicCodedEntry](#) [PropertyType](#)
- [BasicCodedEntryVector](#) [PropertyTypeModifiers](#)
- `std::string` [SegmentAlgorithmName](#)
- [ALGOType](#) [SegmentAlgorithmType](#)
- `std::string` [SegmentDescription](#)
- `std::string` [SegmentLabel](#)
- `unsigned short` [SegmentNumber](#)
- `unsigned long` [SurfaceCount](#)
- [SurfaceVector](#) [Surfaces](#)

Additional Inherited Members**Protected Member Functions inherited from [gdcm::Object](#)**

- `void` [Register](#) ()
- `void` [UnRegister](#) ()

10.265.1 Detailed Description

This class defines a segment.

It mainly contains attributes of group 0x0062. In addition, it can be associated with surface.

See also

PS 3.3 C.8.20.2 and C.8.23

10.265.2 Member Typedef Documentation**10.265.2.1 BasicCodedEntryVector**

```
typedef std::vector< SegmentHelper::BasicCodedEntry > gdcm::Segment::BasicCodedEntryVector
```

10.265.2.2 SurfaceVector

```
typedef std::vector< SmartPointer< Surface > > gdcm::Segment::SurfaceVector
```

10.265.3 Member Enumeration Documentation**10.265.3.1 ALGOType**

```
enum gdcm::Segment::ALGOType
```

Enumerator

AUTOMATIC	
SEMIAUTOMATIC	
MANUAL	
ALGOType_END	

10.265.4 Constructor & Destructor Documentation

10.265.4.1 Segment()

```
gdcm::Segment::Segment ()
```

10.265.4.2 ~Segment()

```
gdcm::Segment::~~Segment () [override]
```

10.265.5 Member Function Documentation

10.265.5.1 AddSurface()

```
void gdcm::Segment::AddSurface (
    SmartPointer< Surface > surface)
```

References [gdcm::Object::SmartPointer](#).

10.265.5.2 GetALGOType()

```
ALGOType gdcm::Segment::GetALGOType (
    const char * type) [static]
```

10.265.5.3 GetALGOTypeString()

```
const char * gdcm::Segment::GetALGOTypeString (
    ALGOType type) [static]
```

10.265.5.4 GetAnatomicRegion() [1/2]

```
SegmentHelper::BasicCodedEntry & gdcm::Segment::GetAnatomicRegion ()
```

10.265.5.5 GetAnatomicRegion() [2/2]

```
SegmentHelper::BasicCodedEntry const & gdcM::Segment::GetAnatomicRegion () const
```

10.265.5.6 GetAnatomicRegionModifiers() [1/2]

```
BasicCodedEntryVector & gdcM::Segment::GetAnatomicRegionModifiers ()
```

10.265.5.7 GetAnatomicRegionModifiers() [2/2]

```
BasicCodedEntryVector const & gdcM::Segment::GetAnatomicRegionModifiers () const
```

10.265.5.8 GetPropertyCategory() [1/2]

```
SegmentHelper::BasicCodedEntry & gdcM::Segment::GetPropertyCategory ()
```

10.265.5.9 GetPropertyCategory() [2/2]

```
SegmentHelper::BasicCodedEntry const & gdcM::Segment::GetPropertyCategory () const
```

10.265.5.10 GetPropertyType() [1/2]

```
SegmentHelper::BasicCodedEntry & gdcM::Segment::GetPropertyType ()
```

10.265.5.11 GetPropertyType() [2/2]

```
SegmentHelper::BasicCodedEntry const & gdcM::Segment::GetPropertyType () const
```

10.265.5.12 GetPropertyTypeModifiers() [1/2]

```
BasicCodedEntryVector & gdcM::Segment::GetPropertyTypeModifiers ()
```

10.265.5.13 GetPropertyTypeModifiers() [2/2]

```
BasicCodedEntryVector const & gdcM::Segment::GetPropertyTypeModifiers () const
```

10.265.5.14 GetSegmentAlgorithmName()

```
const char * gdcM::Segment::GetSegmentAlgorithmName () const
```

10.265.5.15 GetSegmentAlgorithmType()

```
ALGOType gdcm::Segment::GetSegmentAlgorithmType () const
```

10.265.5.16 GetSegmentDescription()

```
const char * gdcm::Segment::GetSegmentDescription () const
```

10.265.5.17 GetSegmentLabel()

```
const char * gdcm::Segment::GetSegmentLabel () const
```

10.265.5.18 GetSegmentNumber()

```
unsigned short gdcm::Segment::GetSegmentNumber () const
```

10.265.5.19 GetSurface()

```
SmartPointer< Surface > gdcm::Segment::GetSurface (
    const unsigned int idx = 0) const
```

References [gdcm::Object::SmartPointer](#).

10.265.5.20 GetSurfaceCount()

```
unsigned long gdcm::Segment::GetSurfaceCount ()
```

10.265.5.21 GetSurfaces() [1/2]

```
SurfaceVector & gdcm::Segment::GetSurfaces ()
```

10.265.5.22 GetSurfaces() [2/2]

```
SurfaceVector const & gdcm::Segment::GetSurfaces () const
```

10.265.5.23 SetAnatomicRegion()

```
void gdcm::Segment::SetAnatomicRegion (
    SegmentHelper::BasicCodedEntry const & BSE)
```

10.265.5.24 SetAnatomicRegionModifiers()

```
void gdcm::Segment::SetAnatomicRegionModifiers (
    BasicCodedEntryVector const & BSEV)
```

10.265.5.25 SetPropertyCategory()

```
void gdcm::Segment::SetPropertyCategory (
    SegmentHelper::BasicCodedEntry const & BSE)
```

10.265.5.26 SetPropertyType()

```
void gdcm::Segment::SetPropertyType (
    SegmentHelper::BasicCodedEntry const & BSE)
```

10.265.5.27 SetPropertyTypeModifiers()

```
void gdcm::Segment::SetPropertyTypeModifiers (
    BasicCodedEntryVector const & BSEV)
```

10.265.5.28 SetSegmentAlgorithmName()

```
void gdcm::Segment::SetSegmentAlgorithmName (
    const char * name)
```

10.265.5.29 SetSegmentAlgorithmType() [1/2]

```
void gdcm::Segment::SetSegmentAlgorithmType (
    ALGOType type)
```

10.265.5.30 SetSegmentAlgorithmType() [2/2]

```
void gdcm::Segment::SetSegmentAlgorithmType (
    const char * typeStr)
```

10.265.5.31 SetSegmentDescription()

```
void gdcm::Segment::SetSegmentDescription (
    const char * description)
```

10.265.5.32 SetSegmentLabel()

```
void gdcm::Segment::SetSegmentLabel (
    const char * label)
```

10.265.5.33 SetSegmentNumber()

```
void gdcm::Segment::SetSegmentNumber (
    const unsigned short num)
```

10.265.5.34 SetSurfaceCount()

```
void gdcm::Segment::SetSurfaceCount (
    const unsigned long nb)
```

10.265.6 Member Data Documentation

10.265.6.1 AnatomicRegion

```
SegmentHelper::BasicCodedEntry gdcm::Segment::AnatomicRegion [protected]
```

10.265.6.2 AnatomicRegionModifiers

```
BasicCodedEntryVector gdcm::Segment::AnatomicRegionModifiers [protected]
```

10.265.6.3 PropertyCategory

```
SegmentHelper::BasicCodedEntry gdcm::Segment::PropertyCategory [protected]
```

10.265.6.4 PropertyType

```
SegmentHelper::BasicCodedEntry gdcm::Segment::PropertyType [protected]
```

10.265.6.5 PropertyTypeModifiers

```
BasicCodedEntryVector gdcm::Segment::PropertyTypeModifiers [protected]
```

10.265.6.6 SegmentAlgorithmName

```
std::string gdcm::Segment::SegmentAlgorithmName [protected]
```

10.265.6.7 SegmentAlgorithmType

`ALGOType` `gdcm::Segment::SegmentAlgorithmType` [protected]

10.265.6.8 SegmentDescription

`std::string` `gdcm::Segment::SegmentDescription` [protected]

10.265.6.9 SegmentLabel

`std::string` `gdcm::Segment::SegmentLabel` [protected]

10.265.6.10 SegmentNumber

`unsigned short` `gdcm::Segment::SegmentNumber` [protected]

10.265.6.11 SurfaceCount

`unsigned long` `gdcm::Segment::SurfaceCount` [protected]

10.265.6.12 Surfaces

`SurfaceVector` `gdcm::Segment::Surfaces` [protected]

The documentation for this class was generated from the following file:


- [gdcmSegment.h](#)

10.266 gdcm::SegmentedPaletteColorLookupTable Class Reference


[SegmentedPaletteColorLookupTable](#) class.

```
#include <gdcmSegmentedPaletteColorLookupTable.h>
```

Inheritance diagram for gdcm::SegmentedPaletteColorLookupTable:



Collaboration diagram for gdcm::SegmentedPaletteColorLookupTable:



Public Member Functions

- [SegmentedPaletteColorLookupTable](#) ()
- [~SegmentedPaletteColorLookupTable](#) () override
- void [Print](#) (std::ostream &) const override
- void [SetLUT](#) ([LookupTableType](#) type, const unsigned char *array, unsigned int length) override

Initialize a [SegmentedPaletteColorLookupTable](#).

Public Member Functions inherited from [gdcm::LookupTable](#)

- [LookupTable](#) ()
- [LookupTable](#) ([LookupTable](#) const &lut)
- [~LookupTable](#) () override
- void [Allocate](#) (unsigned short bitsample=8)
Allocate the LUT.
- void [Clear](#) ()
Clear the LUT.
- bool [Decode](#) (char *outputbuffer, size_t outlen, const char *inputbuffer, size_t inlen) const
- void [Decode](#) (std::istream &is, std::ostream &os) const
Decode the LUT.
- bool [Decode8](#) (char *outputbuffer, size_t outlen, const char *inputbuffer, size_t inlen) const
Decode into RGB 8 bits space.
- unsigned short [GetBitSample](#) () const
return the bit sample
- bool [GetBufferAsRGBA](#) (unsigned char *rgba) const
return the LUT as RGBA buffer
- void [GetLUT](#) ([LookupTableType](#) type, unsigned char *array, unsigned int &length) const
- void [GetLUTDescriptor](#) ([LookupTableType](#) type, unsigned short &length, unsigned short &subscript, unsigned short &bitsize) const
- unsigned int [GetLUTLength](#) ([LookupTableType](#) type) const
- const unsigned char * [GetPointer](#) () const
return a raw pointer to the LUT
- void [InitializeBlueLUT](#) (unsigned short length, unsigned short subscript, unsigned short bitsize)
- bool [Initialized](#) () const
return whether the LUT has been initialized
- void [InitializeGreenLUT](#) (unsigned short length, unsigned short subscript, unsigned short bitsize)
- void [InitializeLUT](#) ([LookupTableType](#) type, unsigned short length, unsigned short subscript, unsigned short bitsize)
Generic interface:
- void [InitializeRedLUT](#) (unsigned short length, unsigned short subscript, unsigned short bitsize)
RED / GREEN / BLUE specific:
- bool [IsRGB8](#) () const
Return whether 16 bits LUT is in RGB 8 bits space.
- void [SetBlueLUT](#) (const unsigned char *blue, unsigned int length)
- void [SetGreenLUT](#) (const unsigned char *green, unsigned int length)
- void [SetRedLUT](#) (const unsigned char *red, unsigned int length)
- bool [WriteBufferAsRGBA](#) (const unsigned char *rgba)
Write the LUT as RGBA.

Public Member Functions inherited from [gdcm::Object](#)

- [Object](#) ()
- [Object](#) (const [Object](#) &)
Special requirement for copy/cstor, assignment operator.
- virtual [~Object](#) ()
- void [operator=](#) (const [Object](#) &)

Additional Inherited Members**Public Types inherited from [gdcm::LookupTable](#)**

- enum [LookupTableType](#) {
 [RED](#) = 0 ,
 [GREEN](#) ,
 [BLUE](#) ,
 [GRAY](#) ,
 [UNKNOWN](#) }

Protected Member Functions inherited from [gdcm::Object](#)

- void [Register](#) ()
- void [UnRegister](#) ()

Protected Attributes inherited from [gdcm::LookupTable](#)

- unsigned short [BitSample](#)
- bool [IncompleteLUT](#):1
- [LookupTableInternal](#) * [Internal](#)

10.266.1 Detailed Description

[SegmentedPaletteColorLookupTable](#) class.

10.266.2 Constructor & Destructor Documentation**10.266.2.1 [SegmentedPaletteColorLookupTable](#)()**

```
gdcm::SegmentedPaletteColorLookupTable::SegmentedPaletteColorLookupTable ()
```

10.266.2.2 [~SegmentedPaletteColorLookupTable](#)()

```
gdcm::SegmentedPaletteColorLookupTable::~~SegmentedPaletteColorLookupTable () [override]
```

10.266.3 Member Function Documentation

10.266.3.1 Print()

```
void gdcM::SegmentedPaletteColorLookupTable::Print (  
    std::ostream & ) const [inline], [override], [virtual]
```

Reimplemented from [gdcM::LookupTable](#).

10.266.3.2 SetLUT()

```
void gdcM::SegmentedPaletteColorLookupTable::SetLUT (  
    LookupTableType type,  
    const unsigned char * array,  
    unsigned int length) [override], [virtual]
```

Initialize a [SegmentedPaletteColorLookupTable](#).

Reimplemented from [gdcM::LookupTable](#).

The documentation for this class was generated from the following file:


- [gdcMSegmentedPaletteColorLookupTable.h](#)

10.267 gdcM::SegmentReader Class Reference


This class defines a segment reader.

```
#include <gdcMSegmentReader.h>
```

Inheritance diagram for gdcM::SegmentReader:



Collaboration diagram for gdcm::SegmentReader:



Public Types

- typedef std::vector< [SmartPointer< Segment >](#) > [SegmentVector](#)

Public Member Functions

- [SegmentReader](#) ()
- [~SegmentReader](#) () override
- [SegmentVector GetSegments](#) ()
- [SegmentVector GetSegments](#) () const
- bool [Read](#) () override

Read.

Public Member Functions inherited from [gdcm::Reader](#)

- [Reader](#) ()
- virtual [~Reader](#) ()
- bool [CanRead](#) () const

- [File](#) & [GetFile](#) ()
Set/Get File.
- const [File](#) & [GetFile](#) () const
Set/Get File.
- size_t [GetStreamCurrentPosition](#) () const
- bool [ReadSelectedPrivateTags](#) (std::set< [PrivateTag](#) > const &ptags, bool readvalues=true)
Will only read the specified selected private tags.
- bool [ReadSelectedTags](#) (std::set< [Tag](#) > const &tags, bool readvalues=true)
Will only read the specified selected tags.
- bool [ReadUpToTag](#) (const [Tag](#) &tag, std::set< [Tag](#) > const &skiptags=std::set< [Tag](#) >())
- void [SetFile](#) ([File](#) &file)
Set/Get File.
- void [SetFileName](#) (const char *filename_native)
- void [SetStream](#) (std::istream &input_stream)
Set the open-ed stream directly.

Protected Types

- typedef std::map< unsigned long, [SmartPointer](#)< [Segment](#) > > [SegmentMap](#)

Protected Member Functions

- bool [ReadSegment](#) (const [Item](#) &segmentItem, const unsigned int idx)
- bool [ReadSegments](#) ()

Protected Member Functions inherited from [gdcm::Reader](#)

- std::istream * [GetStreamPtr](#) () const
- bool [ReadDataSet](#) ()
- bool [ReadMetaInformation](#) ()
- bool [ReadPreamble](#) ()

Protected Attributes

- [SegmentMap](#) Segments

Protected Attributes inherited from [gdcm::Reader](#)

- [SmartPointer](#)< [File](#) > F

10.267.1 Detailed Description

This class defines a segment reader.

It reads attributes of group 0x0062.

See also

PS 3.3 C.8.20.2 and C.8.23

10.267.2 Member Typedef Documentation

10.267.2.1 SegmentMap

```
typedef std::map< unsigned long, SmartPointer< Segment > > gdcm::SegmentReader::SegmentMap [protected]
```

10.267.2.2 SegmentVector

```
typedef std::vector< SmartPointer< Segment > > gdcm::SegmentReader::SegmentVector
```

10.267.3 Constructor & Destructor Documentation

10.267.3.1 SegmentReader()

```
gdcm::SegmentReader::SegmentReader ()
```

10.267.3.2 ~SegmentReader()

```
gdcm::SegmentReader::~~SegmentReader () [override]
```

10.267.4 Member Function Documentation

10.267.4.1 GetSegments() [1/2]

```
SegmentVector gdcm::SegmentReader::GetSegments ()
```

10.267.4.2 GetSegments() [2/2]

```
SegmentVector gdcm::SegmentReader::GetSegments () const
```

10.267.4.3 Read()

```
bool gdcm::SegmentReader::Read () [override], [virtual]
```

Read.

Reimplemented from [gdcm::Reader](#).

Reimplemented in [gdcm::SurfaceReader](#).

10.267.4.4 ReadSegment()

```
bool gdcm::SegmentReader::ReadSegment (
    const Item & segmentItem,
    const unsigned int idx) [protected]
```

10.267.4.5 ReadSegments()

```
bool gdcm::SegmentReader::ReadSegments () [protected]
```

10.267.5 Member Data Documentation

10.267.5.1 Segments

```
SegmentMap gdcm::SegmentReader::Segments [protected]
```

The documentation for this class was generated from the following file:


- [gdcmSegmentReader.h](#)

10.268 gdcm::SegmentWriter Class Reference


This class defines a segment writer.

```
#include <gdcmSegmentWriter.h>
```


Inheritance diagram for gdcm::SegmentWriter:



Collaboration diagram for `gdcm::SegmentWriter`:



Public Types

- typedef `std::vector< SmartPointer< Segment > >` [SegmentVector](#)

Public Member Functions

- [SegmentWriter](#) ()
- [~SegmentWriter](#) () override
- void [AddSegment](#) ([SmartPointer< Segment >](#) segment)
- unsigned int [GetNumberOfSegments](#) () const
- [SmartPointer< Segment >](#) [GetSegment](#) (const unsigned int idx=0) const
- [SegmentVector](#) & [GetSegments](#) ()
- const [SegmentVector](#) & [GetSegments](#) () const
- void [SetNumberOfSegments](#) (const unsigned int size)
- void [SetSegments](#) ([SegmentVector](#) &segments)
- bool [Write](#) () override

Write.

Public Member Functions inherited from [gdcm::Writer](#)

- [Writer](#) ()
- virtual [~Writer](#) ()
- void [CheckFileMetaInformationOff](#) ()
- void [CheckFileMetaInformationOn](#) ()
- [File](#) & [GetFile](#) ()
- void [SetCheckFileMetaInformation](#) (bool b)
Undocumented function, do not use (= leave default)
- void [SetFile](#) (const [File](#) &f)
Set/Get the DICOM file ([DataSet](#) + Header)
- void [SetFileName](#) (const char *filename_native)
Set the filename of DICOM file to write:
- void [SetStream](#) (std::ostream &output_stream)
Set user ostream buffer.

Protected Member Functions

- bool [PrepareWrite](#) ()

Protected Member Functions inherited from [gdcm::Writer](#)

- bool [GetCheckFileMetaInformation](#) () const
- std::ostream * [GetStreamPtr](#) () const
- void [SetWriteDataSetOnly](#) (bool b)

Protected Attributes

- [SegmentVector](#) [Segments](#)

Protected Attributes inherited from [gdcm::Writer](#)

- std::ofstream * [Ofstream](#)
- std::ostream * [Stream](#)

10.268.1 Detailed Description

This class defines a segment writer.

It writes attributes of group 0x0062.

See also

PS 3.3 C.8.20.2 and C.8.23

10.268.2 Member Typedef Documentation

10.268.2.1 SegmentVector

```
typedef std::vector< SmartPointer< Segment > > gdcM::SegmentWriter::SegmentVector
```

10.268.3 Constructor & Destructor Documentation

10.268.3.1 SegmentWriter()

```
gdcM::SegmentWriter::SegmentWriter ()
```

10.268.3.2 ~SegmentWriter()

```
gdcM::SegmentWriter::~~SegmentWriter () [override]
```

10.268.4 Member Function Documentation

10.268.4.1 AddSegment()

```
void gdcM::SegmentWriter::AddSegment (  
    SmartPointer< Segment > segment)
```

10.268.4.2 GetNumberOfSegments()

```
unsigned int gdcM::SegmentWriter::GetNumberOfSegments () const
```

10.268.4.3 GetSegment()

```
SmartPointer< Segment > gdcM::SegmentWriter::GetSegment (  
    const unsigned int idx = 0) const
```

10.268.4.4 GetSegments() [1/2]

```
SegmentVector & gdcM::SegmentWriter::GetSegments ()
```

10.268.4.5 GetSegments() [2/2]

```
const SegmentVector & gdcM::SegmentWriter::GetSegments () const
```

10.268.4.6 PrepareWrite()

```
bool gdcm::SegmentWriter::PrepareWrite () [protected]
```

10.268.4.7 SetNumberOfSegments()

```
void gdcm::SegmentWriter::SetNumberOfSegments (
    const unsigned int size)
```

10.268.4.8 SetSegments()

```
void gdcm::SegmentWriter::SetSegments (
    SegmentVector & segments)
```

10.268.4.9 Write()

```
bool gdcm::SegmentWriter::Write () [override], [virtual]
```

Write.

Reimplemented from [gdcm::Writer](#).

Reimplemented in [gdcm::SurfaceWriter](#).

10.268.5 Member Data Documentation

10.268.5.1 Segments

```
SegmentVector gdcm::SegmentWriter::Segments [protected]
```

The documentation for this class was generated from the following file:


- [gdcmSegmentWriter.h](#)

10.269 gdcm::SequenceOfFragments Class Reference


Class to represent a Sequence Of Fragments.

```
#include <gdcmSequenceOfFragments.h>
```

Inheritance diagram for gdcm::SequenceOfFragments:



Collaboration diagram for gdcm::SequenceOfFragments:



Public Types

- typedef FragmentVector::const_iterator [ConstIterator](#)
- typedef std::vector< [Fragment](#) > [FragmentVector](#)
- typedef FragmentVector::iterator [Iterator](#)
- typedef FragmentVector::size_type [SizeType](#)

Public Member Functions

- [SequenceOfFragments](#) ()
constructor (UndefinedLength by default)
- void [AddFragment](#) ([Fragment](#) const &item)
Appends a [Fragment](#) to the already added ones.
- [Iterator Begin](#) ()
- [ConstIterator Begin](#) () const
- void [Clear](#) () override
Clear.
- unsigned long [ComputeByteLength](#) () const
- [VL ComputeLength](#) () const
- [Iterator End](#) ()
- [ConstIterator End](#) () const
- bool [GetBuffer](#) (char *buffer, unsigned long length) const
- bool [GetFragBuffer](#) (unsigned int fragNb, char *buffer, unsigned long &length) const
- const [Fragment](#) & [GetFragment](#) ([SizeType](#) num) const
- [VL GetLength](#) () const override
Returns the SQ length, as read from disk.
- [SizeType GetNumberOfFragments](#) () const
- [BasicOffsetTable](#) & [GetTable](#) ()
- const [BasicOffsetTable](#) & [GetTable](#) () const
- bool [operator==](#) (const [Value](#) &val) const override
- void [Print](#) (std::ostream &os) const override
- template<typename TSwap>
std::istream & [Read](#) (std::istream &is, bool readvalues=true)
- template<typename TSwap>
std::istream & [ReadPreValue](#) (std::istream &is)
- template<typename TSwap>
std::istream & [ReadValue](#) (std::istream &is, bool)
- void [SetLength](#) ([VL](#) length) override
Sets the actual SQ length.
- template<typename TSwap>
std::ostream const & [Write](#) (std::ostream &os) const
- bool [WriteBuffer](#) (std::ostream &os) const

Public Member Functions inherited from [gdcm::Value](#)

- [Value](#) ()=default
- [~Value](#) () override=default

Public Member Functions inherited from [gdcm::Object](#)

- [Object](#) ()
- [Object](#) (const [Object](#) &)
Special requirement for copy/cstor, assignment operator.
- virtual [~Object](#) ()
- void [operator=](#) (const [Object](#) &)

Static Public Member Functions

- static [SmartPointer](#)< [SequenceOfFragments](#) > [New](#) ()

Additional Inherited Members

Protected Member Functions inherited from [gdcm::Value](#)

- virtual void [SetLengthOnly](#) (VL I)

Protected Member Functions inherited from [gdcm::Object](#)

- void [Register](#) ()
- void [UnRegister](#) ()

10.269.1 Detailed Description

Class to represent a Sequence Of Fragments.

Todo I do not enforce that Sequence of Fragments ends with a SQ end del

Examples

[DecompressImageMultiframe.cs](#), [DecompressJPEGFile.cs](#), [FixBrokenJ2K.cxx](#), [FixJAIBugJPEGLS.cxx](#),
[GetJPEGSamplePrecision.cxx](#), and [MpegVideoInfo.cs](#).

10.269.2 Member Typedef Documentation

10.269.2.1 ConstIterator

```
typedef FragmentVector::const_iterator gdcm::SequenceOfFragments::ConstIterator
```

10.269.2.2 FragmentVector

```
typedef std::vector<Fragment> gdcm::SequenceOfFragments::FragmentVector
```

10.269.2.3 Iterator

```
typedef FragmentVector::iterator gdcm::SequenceOfFragments::Iterator
```


10.269.2.4 SizeType

```
typedef FragmentVector::size_type gdcm::SequenceOfFragments::SizeType
```

10.269.3 Constructor & Destructor Documentation

10.269.3.1 SequenceOfFragments()

```
gdcm::SequenceOfFragments::SequenceOfFragments () [inline]
```

constructor (UndefinedLength by default)

Referenced by [New\(\)](#), and [operator==\(\)](#).

10.269.4 Member Function Documentation

10.269.4.1 AddFragment()

```
void gdcm::SequenceOfFragments::AddFragment (
    Fragment const & item)
```

Appends a [Fragment](#) to the already added ones.

10.269.4.2 Begin() [1/2]

```
Iterator gdcm::SequenceOfFragments::Begin () [inline]
```

Referenced by [Print\(\)](#), and [Write\(\)](#).

10.269.4.3 Begin() [2/2]

```
ConstIterator gdcm::SequenceOfFragments::Begin () const [inline]
```

10.269.4.4 Clear()

```
void gdcm::SequenceOfFragments::Clear () [override], [virtual]
```

Clear.

Implements [gdcm::Value](#).

10.269.4.5 ComputeByteLength()

```
unsigned long gdcm::SequenceOfFragments::ComputeByteLength () const
```

10.269.4.6 ComputeLength()

```
VL gdcm::SequenceOfFragments::ComputeLength () const
```

10.269.4.7 End() [1/2]

```
Iterator gdcm::SequenceOfFragments::End () [inline]
```

Referenced by [Print\(\)](#), and [Write\(\)](#).

10.269.4.8 End() [2/2]

```
ConstIterator gdcm::SequenceOfFragments::End () const [inline]
```

10.269.4.9 GetBuffer()

```
bool gdcm::SequenceOfFragments::GetBuffer (  
    char * buffer,  
    unsigned long length) const
```

10.269.4.10 GetFragBuffer()

```
bool gdcm::SequenceOfFragments::GetFragBuffer (  
    unsigned int fragNb,  
    char * buffer,  
    unsigned long & length) const
```

10.269.4.11 GetFragment()

```
const Fragment & gdcm::SequenceOfFragments::GetFragment (  
    SizeType num) const
```

Examples

[DecompressImage.cs](#), [FixBrokenJ2K.cxx](#), and [FixJAIBugJPEGLS.cxx](#).

10.269.4.12 GetLength()

```
VL gdcm::SequenceOfFragments::GetLength () const [inline], [override], [virtual]
```

Returns the SQ length, as read from disk.

Implements [gdcm::Value](#).

10.269.4.13 GetNumberOfFragments()

```
SizeType gdcm::SequenceOfFragments::GetNumberOfFragments () const
```

Examples

[FixJAIBugJPEGLS.cxx](#).

10.269.4.14 GetTable() [1/2]

```
BasicOffsetTable & gdcm::SequenceOfFragments::GetTable () [inline]
```

10.269.4.15 GetTable() [2/2]

```
const BasicOffsetTable & gdcm::SequenceOfFragments::GetTable () const [inline]
```

10.269.4.16 New()

```
SmartPointer< SequenceOfFragments > gdcm::SequenceOfFragments::New () [inline], [static]
```

Examples

[DecompressImageMultiframe.cs](#), [DecompressJPEGFile.cs](#), and [MpegVideoInfo.cs](#).

References [SequenceOfFragments\(\)](#).

10.269.4.17 operator==()

```
bool gdcm::SequenceOfFragments::operator== (
    const Value & val) const [inline], [override], [virtual]
```

Implements [gdcm::Value](#).

References [SequenceOfFragments\(\)](#), and [gdcm::Value::Value\(\)](#).

10.269.4.18 Print()

```
void gdcM::SequenceOfFragments::Print (
    std::ostream & os) const [inline], [override], [virtual]
```

Reimplemented from [gdcM::Object](#).

References [Begin\(\)](#), [End\(\)](#), and [gdcM_assert](#).

10.269.4.19 Read()

```
template<typename TSwap>
std::istream & gdcM::SequenceOfFragments::Read (
    std::istream & is,
    bool readvalues = true) [inline]
```

References [gdcM_assert](#), [ReadPreValue\(\)](#), and [ReadValue\(\)](#).

10.269.4.20 ReadPreValue()

```
template<typename TSwap>
std::istream & gdcM::SequenceOfFragments::ReadPreValue (
    std::istream & is) [inline]
```

References [gdcMDebugMacro](#).

Referenced by [Read\(\)](#).

10.269.4.21 ReadValue()

```
template<typename TSwap>
std::istream & gdcM::SequenceOfFragments::ReadValue (
    std::istream & is,
    bool ) [inline]
```

References [gdcM_assert](#), [gdcMAssertAlwaysMacro](#), [gdcMDebugMacro](#), [gdcMWarningMacro](#), [gdcM::Tag::GetElement\(\)](#), [gdcM::Tag::GetGroup\(\)](#), [gdcM::ByteValue::GetLength\(\)](#), [gdcM::ByteValue::GetPointer\(\)](#), [gdcM::DataElement::GetTag\(\)](#), [gdcM::DataElement::GetVL\(\)](#), [gdcM::Fragment::Read\(\)](#), [gdcM::Fragment::ReadBacktrack\(\)](#), and [gdcM::Exception::what\(\)](#).

Referenced by [Read\(\)](#).

10.269.4.22 SetLength()

```
void gdcM::SequenceOfFragments::SetLength (
    VL length) [inline], [override], [virtual]
```

Sets the actual SQ length.

Implements [gdcM::Value](#).

10.269.4.23 Write()

```
template<typename TSwap>
std::ostream const & gdcm::SequenceOfFragments::Write (
    std::ostream & os) const [inline]
```

References [Begin\(\)](#), [End\(\)](#), [gdcm_assert](#), [gdcm::Tag::Write\(\)](#), and [gdcm::VL::Write\(\)](#).

10.269.4.24 WriteBuffer()

```
bool gdcm::SequenceOfFragments::WriteBuffer (
    std::ostream & os) const
```

Examples

[GetJPEGSamplePrecision.cxx](#).

The documentation for this class was generated from the following file:


- [gdcmSequenceOfFragments.h](#)

10.270 gdcm::SequenceOfItems Class Reference


Class to represent a Sequence Of Items.

```
#include <gdcmSequenceOfItems.h>
```

Inheritance diagram for gdcm::SequenceOfItems:



Collaboration diagram for `gdcM::SequenceOfItems`:



Public Types

- typedef `ItemVector::const_iterator` [ConstIterator](#)
- typedef `std::vector< Item >` [ItemVector](#)
- typedef `ItemVector::iterator` [Iterator](#)
- typedef `ItemVector::size_type` [SizeType](#)

Public Member Functions

- [SequenceOfItems](#) ()
constructor (UndefinedLength by default)
- void [AddItem](#) ([Item](#) const &item)
Appends an [Item](#) to the already added ones.
- [Item](#) & [AddNewUndefinedLengthItem](#) ()
Appends an [Item](#) to the already added ones.
- [Iterator](#) [Begin](#) ()
- [ConstIterator](#) [Begin](#) () const
- void [Clear](#) () override
remove all items within the sequence
- template<typename TDE>
 [VL ComputeLength](#) () const
- [Iterator](#) [End](#) ()

- [ConstIterator End](#) () const
- bool [FindDataElement](#) (const [Tag](#) &t) const
- [Item](#) & [GetItem](#) ([SizeType](#) position)
- const [Item](#) & [GetItem](#) ([SizeType](#) position) const
- [VL GetLength](#) () const override
Returns the SQ length, as read from disk.
- [SizeType GetNumberOfItems](#) () const
- bool [IsEmpty](#) () const
- bool [IsUndefinedLength](#) () const
return if [Value](#) Length if of undefined length
- [SequenceOfItems](#) & [operator=](#) (const [SequenceOfItems](#) &val)
- bool [operator==](#) (const [Value](#) &val) const override
- void [Print](#) (std::ostream &os) const override
- template<typename TDE, typename TSwap>
std::istream & [Read](#) (std::istream &is, bool readvalues=true)
- bool [RemoveItemByIndex](#) (const [SizeType](#) index)
- void [SetLength](#) ([VL](#) length) override
Sets the actual SQ length.
- void [SetLengthToUndefined](#) ()
Properly set the Sequence of [Item](#) to be undefined length.
- void [SetNumberOfItems](#) ([SizeType](#) n)
- template<typename TDE, typename TSwap>
std::ostream const & [Write](#) (std::ostream &os) const

Public Member Functions inherited from [gdcm::Value](#)

- [Value](#) ()=default
- [~Value](#) () override=default

Public Member Functions inherited from [gdcm::Object](#)

- [Object](#) ()
- [Object](#) (const [Object](#) &)
Special requirement for copy/cstor, assignment operator.
- virtual [~Object](#) ()
- void [operator=](#) (const [Object](#) &)

Static Public Member Functions

- static [SmartPointer](#)< [SequenceOfItems](#) > [New](#) ()

Public Attributes

- [ItemVector](#) [Items](#)
Vector of Sequence Items.
- [VL](#) [SequenceLengthField](#)
Total length of the Sequence (or 0xffffffff if undefined).

Additional Inherited Members

Protected Member Functions inherited from [gdcm::Value](#)

- virtual void [SetLengthOnly](#) (VL l)

Protected Member Functions inherited from [gdcm::Object](#)

- void [Register](#) ()
- void [UnRegister](#) ()

10.270.1 Detailed Description

Class to represent a Sequence Of Items.

(value representation : SQ)

- a [Value](#) Representation for Data Elements that contains a sequence of Data Sets.
- Sequence of [Item](#) allows for Nested Data Sets

See PS 3.5, 7.4.6 Data [Element Type](#) Within a Sequence

Note

SEQUENCE OF ITEMS (VALUE REPRESENTATION SQ) A [Value](#) Representation for Data Elements that contain a sequence of Data Sets. Sequence of Items allows for Nested Data Sets.

Examples

[DumpExamCard.cxx](#), [DumpGEMSMovieGroup.cxx](#), [ExtractEncryptedContent.cxx](#), [Extracting_All_Resolution.cxx](#), [Fake_Image_Using_Stream_Image_Writer.cxx](#), [GenAllVR.cxx](#), [GenFakeIdentifyFile.cxx](#), [GenLongSeqs.cxx](#), [GenSeqs.cxx](#), [GetSequenceUltrasound.cxx](#), and [ReadExplicitLengthSQIVR.cxx](#).

10.270.2 Member Typedef Documentation

10.270.2.1 ConstIterator

```
typedef ItemVector::const_iterator gdcm::SequenceOfItems::ConstIterator
```

10.270.2.2 ItemVector

```
typedef std::vector< Item > gdcm::SequenceOfItems::ItemVector
```


10.270.2.3 Iterator

```
typedef ItemVector::iterator gdcmm::SequenceOfItems::Iterator
```

10.270.2.4 SizeType

```
typedef ItemVector::size_type gdcmm::SequenceOfItems::SizeType
```

Examples

[DumpExamCard.cxx](#), [DumpGEMSMovieGroup.cxx](#), and [GetSubSequenceData.cxx](#).

10.270.3 Constructor & Destructor Documentation

10.270.3.1 SequenceOfItems()

```
gdcmm::SequenceOfItems::SequenceOfItems () [inline]
```

constructor (UndefinedLength by default)

References [SequenceLengthField](#).

Referenced by [New\(\)](#), [operator=\(\)](#), and [operator==\(\)](#).

10.270.4 Member Function Documentation

10.270.4.1 AddItem()

```
void gdcmm::SequenceOfItems::AddItem (  
    Item const & item)
```

Appends an [Item](#) to the already added ones.

Examples

[Extracting_All_Resolution.cxx](#).

10.270.4.2 AddNewUndefinedLengthItem()

```
Item & gdcmm::SequenceOfItems::AddNewUndefinedLengthItem ()
```

Appends an [Item](#) to the already added ones.

10.270.4.3 Begin() [1/2]

```
Iterator gdcM::SequenceOfItems::Begin () [inline]
```

References [Items](#).

10.270.4.4 Begin() [2/2]

```
ConstIterator gdcM::SequenceOfItems::Begin () const [inline]
```

References [Items](#).

10.270.4.5 Clear()

```
void gdcM::SequenceOfItems::Clear () [override], [virtual]
```

remove all items within the sequence

Implements [gdcM::Value](#).

10.270.4.6 ComputeLength()

```
template<typename TDE>  
VL gdcM::SequenceOfItems::ComputeLength () const
```

10.270.4.7 End() [1/2]

```
Iterator gdcM::SequenceOfItems::End () [inline]
```

References [Items](#).

10.270.4.8 End() [2/2]

```
ConstIterator gdcM::SequenceOfItems::End () const [inline]
```

References [Items](#).

10.270.4.9 FindDataElement()

```
bool gdcM::SequenceOfItems::FindDataElement (  
    const Tag & t) const
```

10.270.4.10 GetItem() [1/2]

```
Item & gdcm::SequenceOfItems::GetItem (
    SizeType position)
```

10.270.4.11 GetItem() [2/2]

```
const Item & gdcm::SequenceOfItems::GetItem (
    SizeType position) const
```

Examples

[DumpExamCard.cxx](#), [DumpGEMSMovieGroup.cxx](#), [ExtractEncryptedContent.cxx](#), and [GetSequenceUltrasound.cxx](#).

10.270.4.12 GetLength()

```
VL gdcm::SequenceOfItems::GetLength () const [inline], [override], [virtual]
```

Returns the SQ length, as read from disk.

Implements [gdcm::Value](#).

References [SequenceLengthField](#).

Referenced by [Read\(\)](#).

10.270.4.13 GetNumberOfItems()

```
SizeType gdcm::SequenceOfItems::GetNumberOfItems () const [inline]
```

Examples

[DumpExamCard.cxx](#), [DumpGEMSMovieGroup.cxx](#), [ExtractEncryptedContent.cxx](#), and [GetSequenceUltrasound.cxx](#).

References [Items](#).

10.270.4.14 IsEmpty()

```
bool gdcm::SequenceOfItems::IsEmpty () const [inline]
```

References [Items](#).

10.270.4.15 IsUndefinedLength()

```
bool gdcm::SequenceOfItems::IsUndefinedLength () const [inline]
```

return if [Value](#) Length if of undefined length

References [SequenceLengthField](#).

10.270.4.16 New()

```
SmartPointer< SequenceOfItems > gdcm::SequenceOfItems::New () [inline], [static]
```

Examples

[NewSequence.cs](#).

References [SequenceOfItems\(\)](#).

10.270.4.17 operator=()

```
SequenceOfItems & gdcm::SequenceOfItems::operator= (
    const SequenceOfItems & val) [inline]
```

References [SequenceOfItems\(\)](#), [Items](#), and [SequenceLengthField](#).

10.270.4.18 operator==()

```
bool gdcm::SequenceOfItems::operator== (
    const Value & val) const [inline], [override], [virtual]
```

Implements [gdcm::Value](#).

References [SequenceOfItems\(\)](#), [gdcm::Value::Value\(\)](#), [Items](#), and [SequenceLengthField](#).

10.270.4.19 Print()

```
void gdcm::SequenceOfItems::Print (
    std::ostream & os) const [inline], [override], [virtual]
```

Reimplemented from [gdcm::Object](#).

References [Items](#), and [SequenceLengthField](#).

10.270.4.20 Read()

```
template<typename TDE, typename TSwap>
std::istream & gdcmm::SequenceOfItems::Read (
    std::istream & is,
    bool readvalues = true) [inline]
```

References [gdcmm::Item::Clear\(\)](#), [gdcmm_assert](#), [gdcmmDebugMacro](#), [gdcmmWarningMacro](#), [gdcmm::Exception::GetDescription\(\)](#), [GetLength\(\)](#), [gdcmm::Item::GetNestedDataSet\(\)](#), [gdcmm::DataElement::GetTag\(\)](#), [gdcmm::DataElement::GetVL\(\)](#), [Items](#), [gdcmm::Item::Read\(\)](#), [SequenceLengthField](#), and [gdcmm::DataSet::Size\(\)](#).

10.270.4.21 RemoveItemByIndex()

```
bool gdcmm::SequenceOfItems::RemoveItemByIndex (
    const SizeType index)
```

Remove an [Item](#) as specified by its index, if index > size, false is returned Index starts at 1 not 0

10.270.4.22 SetLength()

```
void gdcmm::SequenceOfItems::SetLength (
    VL length) [inline], [override], [virtual]
```

Sets the actual SQ length.

Implements [gdcmm::Value](#).

References [SequenceLengthField](#).

10.270.4.23 SetLengthToUndefined()

```
void gdcmm::SequenceOfItems::SetLengthToUndefined ()
```

Properly set the Sequence of [Item](#) to be undefined length.

10.270.4.24 SetNumberOfItems()

```
void gdcmm::SequenceOfItems::SetNumberOfItems (
    SizeType n) [inline]
```

References [Items](#).

10.270.4.25 Write()

```
template<typename TDE, typename TSwap>
std::ostream const & gdcM::SequenceOfItems::Write (
    std::ostream & os) const [inline]
```

References [Items](#), [SequenceLengthField](#), [gdcM::Tag::Write\(\)](#), and [gdcM::VL::Write\(\)](#).

10.270.5 Member Data Documentation

10.270.5.1 Items

[ItemVector](#) gdcM::SequenceOfItems::Items

Vector of Sequence Items.

Referenced by [Begin\(\)](#), [Begin\(\)](#), [End\(\)](#), [End\(\)](#), [GetNumberOfItems\(\)](#), [IsEmpty\(\)](#), [operator=\(\)](#), [operator==\(\)](#), [Print\(\)](#), [Read\(\)](#), [SetNumberOfItems\(\)](#), and [Write\(\)](#).

10.270.5.2 SequenceLengthField

[VL](#) gdcM::SequenceOfItems::SequenceLengthField

Total length of the Sequence (or 0xffffffff) if undefined.

Referenced by [SequenceOfItems\(\)](#), [GetLength\(\)](#), [IsUndefinedLength\(\)](#), [operator=\(\)](#), [operator==\(\)](#), [Print\(\)](#), [Read\(\)](#), [SetLength\(\)](#), and [Write\(\)](#).

The documentation for this class was generated from the following file:


- [gdcMSequenceOfItems.h](#)

10.271 gdcM::SerieHelper Class Reference

[SerieHelper](#) DO NOT USE this class, it is only a temporary solution for ITK migration from GDCM 1.x to GDCM 2.x It will disappear soon, you've been warned.

```
#include <gdcMSerieHelper.h>
```

Collaboration diagram for gdcm::SerieHelper:



Public Member Functions

- [SerieHelper](#) ()
- [~SerieHelper](#) ()
- void [AddRestriction](#) (const std::string &tag)
- void [AddRestriction](#) (uint16_t group, uint16_t elem, std::string const &value, int op)
- void [Clear](#) ()
- void [CreateDefaultUniqueSeriesIdentifier](#) ()
- std::string [CreateUniqueSeriesIdentifier](#) ([File](#) *inFile)
- [FileList](#) * [GetFirstSingleSerieUIDFileSet](#) ()
- [FileList](#) * [GetNextSingleSerieUIDFileSet](#) ()
- void [OrderFileList](#) ([FileList](#) *fileSet)
- void [SetDirectory](#) (std::string const &dir, bool recursive=false)
- void [SetLoadMode](#) (int)
- void [SetUseSeriesDetails](#) (bool useSeriesDetails)

Protected Types

- using [Rule](#)
- typedef std::vector< [Rule](#) > [SerieRestrictions](#)
- typedef std::map< std::string, [FileList](#) * > [SingleSerieUIDFileSetmap](#)

Protected Member Functions

- bool [AddFile](#) ([FileWithName](#) &header)
- void [AddFileName](#) (std::string const &filename)
- void [AddRestriction](#) (const [Tag](#) &tag)
- bool [FileNameOrdering](#) ([FileList](#) *fileList)
- bool [ImageNumberOrdering](#) ([FileList](#) *fileList)
- bool [ImagePositionPatientOrdering](#) ([FileList](#) *fileSet)
- bool [UserOrdering](#) ([FileList](#) *fileSet)

Protected Attributes

- [SingleSerieUIDFileSetmap::iterator](#) [ItFileSetHt](#)
- [SingleSerieUIDFileSetmap](#) [SingleSerieUIDFileSetHT](#)

10.271.1 Detailed Description

[SerieHelper](#) DO NOT USE this class, it is only a temporary solution for ITK migration from GDCM 1.x to GDCM 2.x It will disappear soon, you've been warned.

Instead see [ImageHelper](#) or [IPPSorter](#)

10.271.2 Member Typedef Documentation

10.271.2.1 Rule

```
using gdc::SerieHelper::Rule [protected]
```

Initial value:

```
struct RuleStructure{
    uint16_t group;
    uint16_t elem;
    std::string value;
    int op;
}
```

10.271.2.2 SerieRestrictions

```
typedef std::vector<Rule> gdc::SerieHelper::SerieRestrictions [protected]
```

10.271.2.3 SingleSerieUIDFileSetmap

```
typedef std::map<std::string, FileList *> gdc::SerieHelper::SingleSerieUIDFileSetmap [protected]
```


10.271.3 Constructor & Destructor Documentation

10.271.3.1 SerieHelper()

```
gdcm::SerieHelper::SerieHelper ()
```

10.271.3.2 ~SerieHelper()

```
gdcm::SerieHelper::~~SerieHelper ()
```

10.271.4 Member Function Documentation

10.271.4.1 AddFile()

```
bool gdcm::SerieHelper::AddFile (  
    FileWithName & header) [protected]
```

10.271.4.2 AddFileName()

```
void gdcm::SerieHelper::AddFileName (  
    std::string const & filename) [protected]
```

10.271.4.3 AddRestriction() [1/3]

```
void gdcm::SerieHelper::AddRestriction (  
    const std::string & tag)
```

10.271.4.4 AddRestriction() [2/3]

```
void gdcm::SerieHelper::AddRestriction (  
    const Tag & tag) [protected]
```

10.271.4.5 AddRestriction() [3/3]

```
void gdcm::SerieHelper::AddRestriction (  
    uint16_t group,  
    uint16_t elem,  
    std::string const & value,  
    int op)
```

10.271.4.6 Clear()

```
void gdcm::SerieHelper::Clear ()
```

10.271.4.7 CreateDefaultUniqueSeriesIdentifier()

```
void gdcm::SerieHelper::CreateDefaultUniqueSeriesIdentifier ()
```

10.271.4.8 CreateUniqueSeriesIdentifier()

```
std::string gdcm::SerieHelper::CreateUniqueSeriesIdentifier (  
    File * inFile)
```

10.271.4.9 FileNameOrdering()

```
bool gdcm::SerieHelper::FileNameOrdering (  
    FileList * fileList) [protected]
```

10.271.4.10 GetFirstSingleSerieUIDFileSet()

```
FileList * gdcm::SerieHelper::GetFirstSingleSerieUIDFileSet ()
```

10.271.4.11 GetNextSingleSerieUIDFileSet()

```
FileList * gdcm::SerieHelper::GetNextSingleSerieUIDFileSet ()
```

10.271.4.12 ImageNumberOrdering()

```
bool gdcm::SerieHelper::ImageNumberOrdering (  
    FileList * fileList) [protected]
```

10.271.4.13 ImagePositionPatientOrdering()

```
bool gdcm::SerieHelper::ImagePositionPatientOrdering (  
    FileList * fileSet) [protected]
```

10.271.4.14 OrderFileList()

```
void gdcm::SerieHelper::OrderFileList (  
    FileList * fileSet)
```

10.271.4.15 SetDirectory()

```
void gdcm::SerieHelper::SetDirectory (
    std::string const & dir,
    bool recursive = false)
```

10.271.4.16 SetLoadMode()

```
void gdcm::SerieHelper::SetLoadMode (
    int ) [inline]
```

10.271.4.17 SetUseSeriesDetails()

```
void gdcm::SerieHelper::SetUseSeriesDetails (
    bool useSeriesDetails)
```

10.271.4.18 UserOrdering()

```
bool gdcm::SerieHelper::UserOrdering (
    FileList * fileSet) [protected]
```

10.271.5 Member Data Documentation

10.271.5.1 ItFileSetHt

```
SingleSerieUIDFileSetmap::iterator gdcm::SerieHelper::ItFileSetHt [protected]
```

10.271.5.2 SingleSerieUIDFileSetHT

```
SingleSerieUIDFileSetmap gdcm::SerieHelper::SingleSerieUIDFileSetHT [protected]
```

The documentation for this class was generated from the following file:

- [gdcmSerieHelper.h](#)

10.272 gdcm::Series Class Reference

[Series.](#)

```
#include <gdcmSeries.h>
```

Public Member Functions

- [Series](#) ()=default

10.272.1 Detailed Description

[Series](#).

10.272.2 Constructor & Destructor Documentation

10.272.2.1 Series()

```
gdcm::Series::Series () [default]
```

The documentation for this class was generated from the following file:

- [gdcmSeries.h](#)

10.273 gdcm::network::ServiceClassApplicationInformation Class Reference

```
#include <gdcmServiceClassApplicationInformation.h>
```

Public Member Functions

- [ServiceClassApplicationInformation](#) ()
- void [Print](#) (std::ostream &os) const
- std::istream & [Read](#) (std::istream &is)
- void [SetTuple](#) (uint8_t levelofsupport, uint8_t levelofdigitalsig, uint8_t elementcoercion)
- size_t [Size](#) () const
- const std::ostream & [Write](#) (std::ostream &os) const

10.273.1 Detailed Description

PS 3.4 [Table B.3-1](#) SERVICE-CLASS-APPLICATION-INFORMATION (A-ASSOCIATE-RQ)

10.273.2 Constructor & Destructor Documentation

10.273.2.1 ServiceClassApplicationInformation()

```
gdcm::network::ServiceClassApplicationInformation::ServiceClassApplicationInformation ()
```

10.273.3 Member Function Documentation

10.273.3.1 Print()

```
void gdcm::network::ServiceClassApplicationInformation::Print (  
    std::ostream & os) const
```

10.273.3.2 Read()

```
std::istream & gdcm::network::ServiceClassApplicationInformation::Read (  
    std::istream & is)
```

10.273.3.3 SetTuple()

```
void gdcm::network::ServiceClassApplicationInformation::SetTuple (  
    uint8_t levelofsupport,  
    uint8_t levelofdigitalsig,  
    uint8_t elementcoercion)
```

10.273.3.4 Size()

```
size_t gdcm::network::ServiceClassApplicationInformation::Size () const
```

10.273.3.5 Write()

```
const std::ostream & gdcm::network::ServiceClassApplicationInformation::Write (  
    std::ostream & os) const
```

The documentation for this class was generated from the following file:


- [gdcmServiceClassApplicationInformation.h](#)

10.274 gdcmm::ServiceClassUser Class Reference


[ServiceClassUser](#).

```
#include <gdcmmServiceClassUser.h>
```

Inheritance diagram for gdcmm::ServiceClassUser:



Collaboration diagram for gdcmm::ServiceClassUser:



Public Member Functions

- [ServiceClassUser](#) ()
- [ServiceClassUser](#) (const [ServiceClassUser](#) &)=delete
- [~ServiceClassUser](#) () override
- const char * [GetAETitle](#) () const
- const char * [GetCalledAETitle](#) () const
- double [GetTimeout](#) () const
- bool [InitializeConnection](#) ()
- bool [IsPresentationContextAccepted](#) (const [PresentationContext](#) &pc) const
Return if the passed in presentation was accepted during association negotiation.
- void [operator=](#) (const [ServiceClassUser](#) &)=delete
- bool [SendEcho](#) ()
C-ECHO.
- bool [SendFind](#) (const [BaseRootQuery](#) *query, std::vector< [DataSet](#) > &retDatasets)
C-FIND a query, return result are in retDatasets.
- bool [SendMove](#) (const [BaseRootQuery](#) *query, const char *outputdir)
Execute a C-MOVE, based on query, return files are written in outputdir.
- bool [SendMove](#) (const [BaseRootQuery](#) *query, std::vector< [DataSet](#) > &retDatasets)
Execute a C-MOVE, based on query, returned dataset are Implicit.
- bool [SendMove](#) (const [BaseRootQuery](#) *query, std::vector< [File](#) > &retFile)
Execute a C-MOVE, based on query, returned Files are stored in vector.
- bool [SendStore](#) (const char *filename)
Execute a C-STORE on file on disk, named filename.
- bool [SendStore](#) ([DataSet](#) const &ds)
Execute a C-STORE on a DataSet, the transfer syntax used will be Implicit.
- bool [SendStore](#) ([File](#) const &file)
- void [SetAETitle](#) (const char *aetitle)
set calling ae title
- void [SetCalledAETitle](#) (const char *aetitle)
set called ae title
- void [SetHostname](#) (const char *hostname)
Set the name of the called hostname (hostname or IP address)
- void [SetPort](#) (uint16_t port)
Set port of remote host (called application)
- void [SetPortSCP](#) (uint16_t portscp)
Set the port for any incoming C-STORE-SCP operation (typically in a return of C-MOVE)
- void [SetPresentationContexts](#) (std::vector< [PresentationContext](#) > const &pcs)
Set the Presentation Context used for the Association.
- void [SetTimeout](#) (double t)
set/get Timeout
- bool [StartAssociation](#) ()
Start the association. Need to call SetPresentationContexts before.
- bool [StopAssociation](#) ()
Stop the running association.

Public Member Functions inherited from [gdcmm::Subject](#)

- [Subject](#) ()
- [~Subject](#) () override
- unsigned long [AddObserver](#) (const [Event](#) &event, [Command](#) *)
- unsigned long [AddObserver](#) (const [Event](#) &event, [Command](#) *) const
- [Command](#) * [GetCommand](#) (unsigned long tag)
- bool [HasObserver](#) (const [Event](#) &event) const
- void [InvokeEvent](#) (const [Event](#) &)
- void [InvokeEvent](#) (const [Event](#) &) const
- void [RemoveAllObservers](#) ()
- void [RemoveObserver](#) (unsigned long tag)

Public Member Functions inherited from [gdcmm::Object](#)

- [Object](#) ()
- [Object](#) (const [Object](#) &)
Special requirement for copy/cstor, assignment operator.
- virtual [~Object](#) ()
- void [operator=](#) (const [Object](#) &)
- virtual void [Print](#) (std::ostream &) const

Static Public Member Functions

- static [SmartPointer](#)< [ServiceClassUser](#) > [New](#) ()
for wrapped language: instantiate a reference counted object

Additional Inherited Members

Protected Member Functions inherited from [gdcmm::Object](#)

- void [Register](#) ()
- void [UnRegister](#) ()

10.274.1 Detailed Description

[ServiceClassUser](#).

Examples

[CStoreQtProgress.cxx](#).

10.274.2 Constructor & Destructor Documentation

10.274.2.1 ServiceClassUser() [1/2]

```
gdcm::ServiceClassUser::ServiceClassUser ()
```

Construct a SCU with default:

- hostname = localhost
- port = 104

Referenced by [ServiceClassUser\(\)](#), [New\(\)](#), and [operator=\(\)](#).

10.274.2.2 ~ServiceClassUser()

```
gdcm::ServiceClassUser::~~ServiceClassUser () [override]
```

10.274.2.3 ServiceClassUser() [2/2]

```
gdcm::ServiceClassUser::ServiceClassUser (  
    const ServiceClassUser & ) [delete]
```

References [ServiceClassUser\(\)](#).

10.274.3 Member Function Documentation

10.274.3.1 GetAETitle()

```
const char * gdcm::ServiceClassUser::GetAETitle () const
```

10.274.3.2 GetCalledAETitle()

```
const char * gdcm::ServiceClassUser::GetCalledAETitle () const
```

10.274.3.3 GetTimeout()

```
double gdcm::ServiceClassUser::GetTimeout () const
```

10.274.3.4 InitializeConnection()

```
bool gdcm::ServiceClassUser::InitializeConnection ()
```

Will try to connect This will setup the actual timeout used during the whole connection time. Need to call SetTimeout first

Examples

[CStoreQtProgress.cxx](#).

10.274.3.5 IsPresentationContextAccepted()

```
bool gdcm::ServiceClassUser::IsPresentationContextAccepted (  
    const PresentationContext & pc) const
```

Return if the passed in presentation was accepted during association negotiation.

10.274.3.6 New()

```
SmartPointer< ServiceClassUser > gdcm::ServiceClassUser::New () [inline], [static]
```

for wrapped language: instantiate a reference counted object

References [ServiceClassUser\(\)](#).

10.274.3.7 operator=()

```
void gdcm::ServiceClassUser::operator= (  
    const ServiceClassUser & ) [delete]
```

References [ServiceClassUser\(\)](#).

10.274.3.8 SendEcho()

```
bool gdcm::ServiceClassUser::SendEcho ()
```

C-ECHO.

10.274.3.9 SendFind()

```
bool gdcm::ServiceClassUser::SendFind (  
    const BaseRootQuery * query,  
    std::vector< DataSet > & retDatasets)
```

C-FIND a query, return result are in retDatasets.

10.274.3.10 SendMove() [1/3]

```
bool gdcmm::ServiceClassUser::SendMove (
    const BaseRootQuery * query,
    const char * outputdir)
```

Execute a C-MOVE, based on query, return files are written in outputdir.

10.274.3.11 SendMove() [2/3]

```
bool gdcmm::ServiceClassUser::SendMove (
    const BaseRootQuery * query,
    std::vector< DataSet > & retDatasets)
```

Execute a C-MOVE, based on query, returned dataset are Implicit.

10.274.3.12 SendMove() [3/3]

```
bool gdcmm::ServiceClassUser::SendMove (
    const BaseRootQuery * query,
    std::vector< File > & retFile)
```

Execute a C-MOVE, based on query, returned Files are stored in vector.

10.274.3.13 SendStore() [1/3]

```
bool gdcmm::ServiceClassUser::SendStore (
    const char * filename)
```

Execute a C-STORE on file on disk, named filename.

Examples

[CStoreQtProgress.cxx](#).

10.274.3.14 SendStore() [2/3]

```
bool gdcmm::ServiceClassUser::SendStore (
    DataSet const & ds)
```

Execute a C-STORE on a [DataSet](#), the transfer syntax used will be Implicit.

10.274.3.15 SendStore() [3/3]

```
bool gdcm::ServiceClassUser::SendStore (
    File const & file)
```

Execute a C-STORE on a [File](#), the transfer syntax used for the query is based on the file.

10.274.3.16 SetAETitle()

```
void gdcm::ServiceClassUser::SetAETitle (
    const char * aetitle)
```

set calling ae title

10.274.3.17 SetCalledAETitle()

```
void gdcm::ServiceClassUser::SetCalledAETitle (
    const char * aetitle)
```

set called ae title

Examples

[CStoreQtProgress.cxx](#).

10.274.3.18 SetHostname()

```
void gdcm::ServiceClassUser::SetHostname (
    const char * hostname)
```

Set the name of the called hostname (hostname or IP address)

Examples

[CStoreQtProgress.cxx](#).

10.274.3.19 SetPort()

```
void gdcm::ServiceClassUser::SetPort (
    uint16_t port)
```

Set port of remote host (called application)

Examples

[CStoreQtProgress.cxx](#).

10.274.3.20 SetPortSCP()

```
void gdcmm::ServiceClassUser::SetPortSCP (
    uint16_t portscp)
```

Set the port for any incoming C-STORE-SCP operation (typically in a return of C-MOVE)

10.274.3.21 SetPresentationContexts()

```
void gdcmm::ServiceClassUser::SetPresentationContexts (
    std::vector< PresentationContext > const & pcs)
```

Set the Presentation Context used for the Association.

Examples

[CStoreQtProgress.cxx](#).

10.274.3.22 SetTimeout()

```
void gdcmm::ServiceClassUser::SetTimeout (
    double t)
```

set/get Timeout

Examples

[CStoreQtProgress.cxx](#).

10.274.3.23 StartAssociation()

```
bool gdcmm::ServiceClassUser::StartAssociation ()
```

Start the association. Need to call SetPresentationContexts before.

Examples

[CStoreQtProgress.cxx](#).

10.274.3.24 StopAssociation()

```
bool gdcmm::ServiceClassUser::StopAssociation ()
```

Stop the running association.

Examples

[CStoreQtProgress.cxx](#).

The documentation for this class was generated from the following file:

- [gdcmmServiceClassUser.h](#)

10.275 gdcmm::SHA1 Class Reference

Class for [SHA1](#).

```
#include <gdcmmSHA1.h>
```

Public Member Functions

- [SHA1](#) ()
- [SHA1](#) (const [SHA1](#) &)=delete
- [~SHA1](#) ()
- void [operator=](#) (const [SHA1](#) &)=delete

Static Public Member Functions

- static bool [Compute](#) (const char *buffer, unsigned long buf_len, char digest_str[20 *2+1])
- static bool [ComputeFile](#) (const char *filename, char digest_str[20 *2+1])

10.275.1 Detailed Description

Class for [SHA1](#).

Warning

this class is able to pick from one implementation:

1. the one from OpenSSL (when GDCM_USE_SYSTEM_OPENSSL is turned ON)

In all other cases it will return an error

10.275.2 Constructor & Destructor Documentation

10.275.2.1 SHA1() [1/2]

```
gdcm::SHA1::SHA1 ()
```

Referenced by [SHA1\(\)](#), and [operator=\(\)](#).

10.275.2.2 ~SHA1()

```
gdcm::SHA1::~~SHA1 ()
```

10.275.2.3 SHA1() [2/2]

```
gdcm::SHA1::SHA1 (  
    const SHA1 & ) [delete]
```

References [SHA1\(\)](#).

10.275.3 Member Function Documentation

10.275.3.1 Compute()

```
bool gdcm::SHA1::Compute (  
    const char * buffer,  
    unsigned long buf_len,  
    char digest_str[20 *2+1]) [static]
```

10.275.3.2 ComputeFile()

```
bool gdcm::SHA1::ComputeFile (  
    const char * filename,  
    char digest_str[20 *2+1]) [static]
```

10.275.3.3 operator=()

```
void gdcm::SHA1::operator= (  
    const SHA1 & ) [delete]
```

References [SHA1\(\)](#).

The documentation for this class was generated from the following file:


- [gdcmSHA1.h](#)

10.276 gdcm::SimpleMemberCommand< T > Class Template Reference


[Command](#) subclass that calls a pointer to a member function.

```
#include <gdcmCommand.h>
```

Inheritance diagram for `gdcm::SimpleMemberCommand< T >`:



Collaboration diagram for gdcm::SimpleMemberCommand< T >:



Public Types

- typedef `SimpleMemberCommand Self`
- typedef `void(T::* TMemberFunctionPointer) ()`

Public Member Functions

- `SimpleMemberCommand (const Self &)=delete`
- `void Execute (const Subject *, const Event &) override`
- `void Execute (Subject *, const Event &) override`
- `void operator= (const Self &)=delete`
- `void SetCallbackFunction (T *object, TMemberFunctionPointer memberFunction)`

Public Member Functions inherited from `gdcm::Command`

- `Command (const Command &)=delete`
- `void operator= (const Command &)=delete`

Public Member Functions inherited from [gdcm::Subject](#)

- [Subject](#) ()
- [~Subject](#) () override
- unsigned long [AddObserver](#) (const [Event](#) &event, [Command](#) *)
- unsigned long [AddObserver](#) (const [Event](#) &event, [Command](#) *) const
- [Command](#) * [GetCommand](#) (unsigned long tag)
- bool [HasObserver](#) (const [Event](#) &event) const
- void [InvokeEvent](#) (const [Event](#) &)
- void [InvokeEvent](#) (const [Event](#) &) const
- void [RemoveAllObservers](#) ()
- void [RemoveObserver](#) (unsigned long tag)

Public Member Functions inherited from [gdcm::Object](#)

- [Object](#) ()
- [Object](#) (const [Object](#) &)
Special requirement for copy/cstor, assignment operator.
- virtual [~Object](#) ()
- void [operator=](#) (const [Object](#) &)
- virtual void [Print](#) (std::ostream &) const

Static Public Member Functions

- static [SmartPointer](#)< [SimpleMemberCommand](#) > [New](#) ()

Protected Member Functions

- [SimpleMemberCommand](#) ()
- [~SimpleMemberCommand](#) () override=default

Protected Member Functions inherited from [gdcm::Command](#)

- [Command](#) ()
- [~Command](#) () override

Protected Member Functions inherited from [gdcm::Object](#)

- void [Register](#) ()
- void [UnRegister](#) ()

Protected Attributes

- [TMemberFunctionPointer](#) [m_MemberFunction](#)
- T * [m_This](#)

10.276.1 Detailed Description

```
template<typename T>
class gdcm::SimpleMemberCommand< T >
```

[Command](#) subclass that calls a pointer to a member function.

[SimpleMemberCommand](#) calls a pointer to a member function with no arguments.

10.276.2 Member Typedef Documentation

10.276.2.1 Self

```
template<typename T>
typedef SimpleMemberCommand gdcm::SimpleMemberCommand< T >::Self
```

Standard class typedefs.

10.276.2.2 TMemberFunctionPointer

```
template<typename T>
typedef void(T::* gdcm::SimpleMemberCommand< T >::TMemberFunctionPointer) ()
```

A method callback.

10.276.3 Constructor & Destructor Documentation

10.276.3.1 SimpleMemberCommand() [1/2]

```
template<typename T>
gdcm::SimpleMemberCommand< T >::SimpleMemberCommand (
    const Self & ) [delete]
```

10.276.3.2 SimpleMemberCommand() [2/2]

```
template<typename T>
gdcm::SimpleMemberCommand< T >::SimpleMemberCommand () [inline], [protected]
```

10.276.3.3 ~SimpleMemberCommand()

```
template<typename T>
gdcm::SimpleMemberCommand< T >::~~SimpleMemberCommand () [override], [protected], [default]
```

10.276.4 Member Function Documentation

10.276.4.1 Execute() [1/2]

```
template<typename T>
void gdcm::SimpleMemberCommand< T >::Execute (
    const Subject * caller,
    const Event & event) [inline], [override], [virtual]
```

Abstract method that defines the action to be taken by the command. This variant is expected to be used when requests comes from a const [Object](#)

Implements [gdcm::Command](#).

10.276.4.2 Execute() [2/2]

```
template<typename T>
void gdcm::SimpleMemberCommand< T >::Execute (
    Subject * ,
    const Event & ) [inline], [override], [virtual]
```

Invoke the callback function.

Implements [gdcm::Command](#).

10.276.4.3 New()

```
template<typename T>
SmartPointer< SimpleMemberCommand > gdcm::SimpleMemberCommand< T >::New () [inline], [static]
```

Run-time type information (and related methods). Method for creation through the object factory.

10.276.4.4 operator=()

```
template<typename T>
void gdcm::SimpleMemberCommand< T >::operator= (
    const Self & ) [delete]
```

10.276.4.5 SetCallbackFunction()

```
template<typename T>
void gdcm::SimpleMemberCommand< T >::SetCallbackFunction (
    T * object,
    TMemberFunctionPointer memberFunction) [inline]
```

Specify the callback function.

10.276.5 Member Data Documentation

10.276.5.1 m_MemberFunction

```
template<typename T>
TMemberFunctionPointer gdcm::SimpleMemberCommand< T >::m_MemberFunction [protected]
```

10.276.5.2 m_This

```
template<typename T>
T* gdcm::SimpleMemberCommand< T >::m_This [protected]
```

The documentation for this class was generated from the following file:

- [gdcmCommand.h](#)

10.277 gdcm::SimpleSubjectWatcher Class Reference

[SimpleSubjectWatcher](#).

```
#include <gdcmSimpleSubjectWatcher.h>
```

Public Member Functions

- [SimpleSubjectWatcher](#) (const [SimpleSubjectWatcher](#) &)=delete
- [SimpleSubjectWatcher](#) ([Subject](#) *s, const char *comment="")
- virtual [~SimpleSubjectWatcher](#) ()
- void [operator=](#) (const [SimpleSubjectWatcher](#) &)=delete

Protected Member Functions

- virtual void [EndFilter](#) ()
- virtual void [ShowAbort](#) ()
- virtual void [ShowAnonymization](#) ([Subject](#) *caller, const [Event](#) &evt)
- virtual void [ShowData](#) ([Subject](#) *caller, const [Event](#) &evt)
- virtual void [ShowDataSet](#) ([Subject](#) *caller, const [Event](#) &evt)
- virtual void [ShowFileName](#) ([Subject](#) *caller, const [Event](#) &evt)
- virtual void [ShowIteration](#) ()
- virtual void [ShowProgress](#) ([Subject](#) *caller, const [Event](#) &evt)
- virtual void [StartFilter](#) ()
- void [TestAbortOff](#) ()
- void [TestAbortOn](#) ()

10.277.1 Detailed Description

[SimpleSubjectWatcher](#).

This is a typical [Subject](#) Watcher class. It will observe all events.

Examples

[BasicAnonymizer.cs](#), [CStoreQtProgress.cxx](#), [Cleaner.cs](#), [ClinicalTrialIdentificationWorkflow.cs](#), [FileChangeTS.cs](#), [FileChangeTSLossy.cs](#), [ScanDirectory.cs](#), and [SimpleScanner.cxx](#).

10.277.2 Constructor & Destructor Documentation

10.277.2.1 SimpleSubjectWatcher() [1/2]

```
gdcmm::SimpleSubjectWatcher::SimpleSubjectWatcher (
    Subject * s,
    const char * comment = "")
```

Referenced by [SimpleSubjectWatcher\(\)](#), and [operator=\(\)](#).

10.277.2.2 ~SimpleSubjectWatcher()

```
virtual gdcmm::SimpleSubjectWatcher::~~SimpleSubjectWatcher () [virtual]
```

10.277.2.3 SimpleSubjectWatcher() [2/2]

```
gdcmm::SimpleSubjectWatcher::SimpleSubjectWatcher (
    const SimpleSubjectWatcher & ) [delete]
```

References [SimpleSubjectWatcher\(\)](#).

10.277.3 Member Function Documentation

10.277.3.1 EndFilter()

```
virtual void gdcmm::SimpleSubjectWatcher::EndFilter () [protected], [virtual]
```

10.277.3.2 operator=()

```
void gdcmm::SimpleSubjectWatcher::operator= (
    const SimpleSubjectWatcher & ) [delete]
```

References [SimpleSubjectWatcher\(\)](#).

10.277.3.3 ShowAbort()

```
virtual void gdcm::SimpleSubjectWatcher::ShowAbort () [protected], [virtual]
```

10.277.3.4 ShowAnonymization()

```
virtual void gdcm::SimpleSubjectWatcher::ShowAnonymization (  
    Subject * caller,  
    const Event & evt) [protected], [virtual]
```

10.277.3.5 ShowData()

```
virtual void gdcm::SimpleSubjectWatcher::ShowData (  
    Subject * caller,  
    const Event & evt) [protected], [virtual]
```

10.277.3.6 ShowDataSet()

```
virtual void gdcm::SimpleSubjectWatcher::ShowDataSet (  
    Subject * caller,  
    const Event & evt) [protected], [virtual]
```

10.277.3.7 ShowFileName()

```
virtual void gdcm::SimpleSubjectWatcher::ShowFileName (  
    Subject * caller,  
    const Event & evt) [protected], [virtual]
```

Examples

[SimpleScanner.cxx](#).

10.277.3.8 ShowIteration()

```
virtual void gdcm::SimpleSubjectWatcher::ShowIteration () [protected], [virtual]
```

10.277.3.9 ShowProgress()

```
virtual void gdcm::SimpleSubjectWatcher::ShowProgress (  
    Subject * caller,  
    const Event & evt) [protected], [virtual]
```

10.277.3.10 StartFilter()

```
virtual void gdcM::SimpleSubjectWatcher::StartFilter () [protected], [virtual]
```

10.277.3.11 TestAbortOff()

```
void gdcM::SimpleSubjectWatcher::TestAbortOff () [protected]
```

10.277.3.12 TestAbortOn()

```
void gdcM::SimpleSubjectWatcher::TestAbortOn () [protected]
```


The documentation for this class was generated from the following file:

- [gdcMSimpleSubjectWatcher.h](#)

10.278 gdcM::MrProtocol::Slice Struct Reference

```
#include <gdcMMrProtocol.h>
```

Collaboration diagram for gdcM::MrProtocol::Slice:



Public Attributes

- [Vector3 Normal](#)
- [Vector3 Position](#)

10.278.1 Member Data Documentation

10.278.1.1 Normal

`Vector3` `gdcm::MrProtocol::Slice::Normal`

10.278.1.2 Position

`Vector3` `gdcm::MrProtocol::Slice::Position`


The documentation for this struct was generated from the following file:

- [gdcmMrProtocol.h](#)

10.279 gdcm::MrProtocol::SliceArray Struct Reference

```
#include <gdcmMrProtocol.h>
```

Collaboration diagram for `gdcm::MrProtocol::SliceArray`:



Public Attributes

- `std::vector< Slice > Slices`

10.279.1 Member Data Documentation**10.279.1.1 Slices**

```
std::vector< Slice > gdcM::MrProtocol::SliceArray::Slices
```

The documentation for this struct was generated from the following file:


- [gdcMMrProtocol.h](#)

10.280 gdcM::SmartPointer< ObjectType > Class Template Reference

Class for Smart Pointer.

```
#include <gdcMSmartPointer.h>
```

Inheritance diagram for `gdcM::SmartPointer< ObjectType >`:



Public Member Functions

- [SmartPointer](#) ()
- [SmartPointer](#) (const [SmartPointer](#)< ObjectType > &p)
- [SmartPointer](#) (ObjectType *p)
- [SmartPointer](#) (ObjectType const &p)
- [~SmartPointer](#) ()
- ObjectType * [GetPointer](#) () const
Explicit function to retrieve the pointer.
- [operator ObjectType *](#) () const
Return pointer to object.
- ObjectType & [operator*](#) () const
- ObjectType * [operator->](#) () const
Overload operator ->
- [SmartPointer](#) & [operator=](#) (ObjectType *r)
Overload operator assignment.
- [SmartPointer](#) & [operator=](#) (ObjectType const &r)
- [SmartPointer](#) & [operator=](#) ([SmartPointer](#) const &r)
Overload operator assignment.

10.280.1 Detailed Description

```
template<class ObjectType>
class gdcmm::SmartPointer< ObjectType >
```

Class for Smart Pointer.

Will only work for subclass of [gdcmm::Object](#) See `tr1/shared_ptr` for a more general approach (not invasive) `#include <tr1/memory> { shared_ptr<Bla> b(new Bla); }`

Note

Class partly based on post by Bill Hubauer: <http://groups.google.com/group/comp.lang.c++.msg/173ddc38a827a930>

See also

<http://www.davethehat.com/articles/smartp.htm>

and `itk::SmartPointer`

Examples

[CStoreQtProgress.cxx](#), [ChangeSequenceUltrasound.cxx](#), [DumpGEMSMovieGroup.cxx](#), [DumpPhilipsECHO.cxx](#), [DumpToshibaDTI.cxx](#), [DumpToshibaDTI2.cxx](#), [DumpVisusChange.cxx](#), [Extracting_All_Resolution.cxx](#), [Fake_Image_Using_Stream_](#), [FixBrokenJ2K.cxx](#), [GenAllVR.cxx](#), [GenFakeIdentifyFile.cxx](#), [GenFakeImage.cxx](#), [GenLongSeqs.cxx](#), [GenSeqs.cxx](#), [GetSubSequenceData.cxx](#), [LargeVRDSExplicit.cxx](#), [ReadAndDumpDICOMDIR.cxx](#), [ReadExplicitLengthSQIVR.cxx](#), [SimpleScanner.cxx](#), [gdcmmrtionplan.cxx](#), and [gdcmmrtplan.cxx](#).

10.280.2 Constructor & Destructor Documentation

10.280.2.1 SmartPointer() [1/4]

```
template<class ObjectType>
gdcM::SmartPointer< ObjectType >::SmartPointer () [inline]
```

10.280.2.2 SmartPointer() [2/4]

```
template<class ObjectType>
gdcM::SmartPointer< ObjectType >::SmartPointer (
    const SmartPointer< ObjectType > & p) [inline]
```

10.280.2.3 SmartPointer() [3/4]

```
template<class ObjectType>
gdcM::SmartPointer< ObjectType >::SmartPointer (
    ObjectType * p) [inline]
```

10.280.2.4 SmartPointer() [4/4]

```
template<class ObjectType>
gdcM::SmartPointer< ObjectType >::SmartPointer (
    ObjectType const & p) [inline]
```

10.280.2.5 ~SmartPointer()

```
template<class ObjectType>
gdcM::SmartPointer< ObjectType >::~SmartPointer () [inline]
```

10.280.3 Member Function Documentation

10.280.3.1 GetPointer()

```
template<class ObjectType>
ObjectType * gdcM::SmartPointer< ObjectType >::GetPointer () const [inline]
```

Explicit function to retrieve the pointer.

10.280.3.2 operator ObjectType *()

```
template<class ObjectType>
gdcmm::SmartPointer< ObjectType >::operator ObjectType * () const [inline]
```

Return pointer to object.

10.280.3.3 operator*()

```
template<class ObjectType>
ObjectType & gdcmm::SmartPointer< ObjectType >::operator* () const [inline]
```

10.280.3.4 operator->()

```
template<class ObjectType>
ObjectType * gdcmm::SmartPointer< ObjectType >::operator-> () const [inline]
```

Overload operator ->

10.280.3.5 operator=() [1/3]

```
template<class ObjectType>
SmartPointer & gdcmm::SmartPointer< ObjectType >::operator= (
    ObjectType * r) [inline]
```

Overload operator assignment.

10.280.3.6 operator=() [2/3]

```
template<class ObjectType>
SmartPointer & gdcmm::SmartPointer< ObjectType >::operator= (
    ObjectType const & r) [inline]
```

10.280.3.7 operator=() [3/3]

```
template<class ObjectType>
SmartPointer & gdcmm::SmartPointer< ObjectType >::operator= (
    SmartPointer< ObjectType > const & r) [inline]
```

Overload operator assignment.

Referenced by [gdcmm::SmartPointer< Value >::operator=\(\)](#), and [gdcmm::SmartPointer< Value >::operator=\(\)](#).

The documentation for this class was generated from the following files:

- [gdcmmObject.h](#)
- [gdcmmSmartPointer.h](#)

10.281 gdcm::network::SOPClassExtendedNegociationSub Class Reference

[SOPClassExtendedNegociationSub.](#)

```
#include <gdcmSOPClassExtendedNegociationSub.h>
```

Public Member Functions

- [SOPClassExtendedNegociationSub](#) ()
- void [Print](#) (std::ostream &os) const
- std::istream & [Read](#) (std::istream &is)
- void [SetTuple](#) (const char *uid, uint8_t levelofsupport=3, uint8_t levelofdigitalsig=0, uint8_t elementcoercion=2)
- size_t [Size](#) () const
- const std::ostream & [Write](#) (std::ostream &os) const

10.281.1 Detailed Description

[SOPClassExtendedNegociationSub.](#)

PS 3.7 [Table](#) D.3-11 SOP CLASS EXTENDED NEGOTIATION SUB-ITEM FIELDS (A-ASSOCIATE-RQ and A-↔ ASSOCIATE-AC)

10.281.2 Constructor & Destructor Documentation

10.281.2.1 SOPClassExtendedNegociationSub()

```
gdcm::network::SOPClassExtendedNegociationSub::SOPClassExtendedNegociationSub ()
```

10.281.3 Member Function Documentation

10.281.3.1 Print()

```
void gdcm::network::SOPClassExtendedNegociationSub::Print (  
    std::ostream & os) const
```

10.281.3.2 Read()

```
std::istream & gdcm::network::SOPClassExtendedNegociationSub::Read (  
    std::istream & is)
```

10.281.3.3 SetTuple()

```
void gdcm::network::SOPClassExtendedNegociationSub::SetTuple (
    const char * uid,
    uint8_t levelofsupport = 3,
    uint8_t levelofdigitalsig = 0,
    uint8_t elementcoercion = 2)
```

10.281.3.4 Size()

```
size_t gdcm::network::SOPClassExtendedNegociationSub::Size () const
```

10.281.3.5 Write()

```
const std::ostream & gdcm::network::SOPClassExtendedNegociationSub::Write (
    std::ostream & os) const
```

The documentation for this class was generated from the following file:

- [gdcmSOPClassExtendedNegociationSub.h](#)

10.282 gdcm::SOPClassUIDToIOD Class Reference

Class convert a class SOP Class UID into [IOD](#).

```
#include <gdcmSOPClassUIDToIOD.h>
```

Public Types

- typedef const char * [const](#)(SOPClassUIDToIODType)[2]

Static Public Member Functions

- static [const](#) char * [GetIOD](#) (UIDs [const](#) &uid)
- static [const](#) char * [GetIODFromSOPClassUID](#) ([const](#) char *sopclassuid)
- static unsigned int [GetNumberOfSOPClassToIOD](#) ()
Return the number of SOP Class UID listed internally.
- static [const](#) char * [GetSOPClassUIDFromIOD](#) ([const](#) char *iod)
- static SOPClassUIDToIODType & [GetSOPClassUIDToIOD](#) (unsigned int i)
- static SOPClassUIDToIODType * [GetSOPClassUIDToIODs](#) ()

10.282.1 Detailed Description

Class convert a class SOP Class UID into [IOD](#).

Reference PS 3.4 [Table B.5-1 STANDARD SOP CLASSES](#)

10.282.2 Member Typedef Documentation

10.282.2.1 const

```
typedef const char * gdcm::SOPClassUIDToIOD::const (SOPClassUIDToIODType) [2]
```

10.282.3 Member Function Documentation

10.282.3.1 GetIOD()

```
const char * gdcm::SOPClassUIDToIOD::GetIOD (
    UIDs const & uid) [static]
```

Return the associated [IOD](#) based on a SOP Class UID uid (there is a one-to-one mapping from SOP Class UID to matching [IOD](#))

Examples

[GenerateStandardSOPClasses.cxx](#).

10.282.3.2 GetIODFromSOPClassUID()

```
const char * gdcm::SOPClassUIDToIOD::GetIODFromSOPClassUID (
    const char * sopclassuid) [static]
```

10.282.3.3 GetNumberOfSOPClassToIOD()

```
unsigned int gdcm::SOPClassUIDToIOD::GetNumberOfSOPClassToIOD () [static]
```

Return the number of SOP Class UID listed internally.

10.282.3.4 GetSOPClassUIDFromIOD()

```
const char * gdcm::SOPClassUIDToIOD::GetSOPClassUIDFromIOD (
    const char * iod) [static]
```


10.282.3.5 GetSOPClassUIDToIOD()

```
SOPClassUIDToIODType & gdcm::SOPClassUIDToIOD::GetSOPClassUIDToIOD (
    unsigned int i) [static]
```

10.282.3.6 GetSOPClassUIDToIODs()

```
SOPClassUIDToIODType * gdcm::SOPClassUIDToIOD::GetSOPClassUIDToIODs () [static]
```

The documentation for this class was generated from the following file:


- [gdcmSOPClassUIDToIOD.h](#)

10.283 gdcm::Sorter Class Reference


[Sorter.](#)

```
#include <gdcmSorter.h>
```

Inheritance diagram for gdcm::Sorter:



Collaboration diagram for gdcm::Sorter:



Public Types

- typedef bool(* [SortFunction](#)) ([DataSet](#) const &, [DataSet](#) const &)
Set the sort function which compares one dataset to the other.

Public Member Functions

- [Sorter](#) ()
- virtual [~Sorter](#) ()
- bool [AddSelect](#) ([Tag](#) const &tag, const char *value)
UNSUPPORTED FOR NOW.
- const std::vector< std::string > & [GetFileNames](#) () const
- void [Print](#) (std::ostream &os) const
Print.
- void [SetSortFunction](#) ([SortFunction](#) f)
- void [SetTagsToRead](#) (std::set< [Tag](#) > const &tags)
- virtual bool [Sort](#) (std::vector< std::string > const &filenames)
Typically the output of [Directory::GetFileNames\(\)](#)
- virtual bool [StableSort](#) (std::vector< std::string > const &filenames)

Protected Types

- typedef std::map< [Tag](#), std::string > [SelectionMap](#)

Protected Attributes

- std::vector< std::string > [FileNames](#)
- std::map< [Tag](#), std::string > [Selection](#)
- [SortFunction](#) [SortFunc](#)
- std::set< [Tag](#) > [TagsToRead](#)

Friends

- std::ostream & [operator<<](#) (std::ostream &_os, const [Sorter](#) &s)

10.283.1 Detailed Description

[Sorter](#).

General class to do sorting using a custom function You simply need to provide a function of type: [Sorter::SortFunction](#)

Warning

implementation details. For now there is no cache mechanism. Which means that every time you call Sort, all files specified as input parameter are *read*

See also

[Scanner](#)

Examples

[SortImage.cxx](#), [SortImage2.cs](#), and [VolumeSorter.cxx](#).

10.283.2 Member Typedef Documentation

10.283.2.1 SelectionMap

```
typedef std::map<Tag, std::string> gdcm::Sorter::SelectionMap [protected]
```

10.283.2.2 SortFunction

```
typedef bool(* gdcm::Sorter::SortFunction) (DataSet const &, DataSet const &)
```

Set the sort function which compares one dataset to the other.

10.283.3 Constructor & Destructor Documentation

10.283.3.1 Sorter()

```
gdcm::Sorter::Sorter ()
```

Referenced by [operator<<](#).

10.283.3.2 ~Sorter()

```
virtual gdcm::Sorter::~Sorter () [virtual]
```

10.283.4 Member Function Documentation

10.283.4.1 AddSelect()

```
bool gdcm::Sorter::AddSelect (
    Tag const & tag,
    const char * value)
```

UNSUPPORTED FOR NOW.

10.283.4.2 GetFileNames()

```
const std::vector< std::string > & gdcm::Sorter::GetFileNames () const [inline]
```

Return the list of filenames as sorted by the specific algorithm used. Empty by default (before [Sort\(\)](#) is called)

Examples

[Compute3DSpacing.cxx](#), [SortImage.cxx](#), [VolumeSorter.cxx](#), [gdcmorthoplanes.cxx](#), and [reslicesphere.cxx](#).

References [FileNames](#).

10.283.4.3 Print()

```
void gdcm::Sorter::Print (
    std::ostream & os) const
```

Print.

Examples

[SortImage.cxx](#), [VolumeSorter.cxx](#), and [gdcmorthoplanes.cxx](#).

Referenced by [operator<<](#).

10.283.4.4 SetSortFunction()

```
void gdcm::Sorter::SetSortFunction (
    SortFunction f)
```

Examples

[SortImage.cxx](#), [SortImage2.cs](#), and [VolumeSorter.cxx](#).

10.283.4.5 SetTagsToRead()

```
void gdcm::Sorter::SetTagsToRead (
    std::set< Tag > const & tags)
```

Specify a set of tags to be read in during the sort procedure. By default this set is empty, in which case the entire image, including pixel data, is read in.

10.283.4.6 Sort()

```
virtual bool gdcm::Sorter::Sort (
    std::vector< std::string > const & filenames) [virtual]
```

Typically the output of [Directory::GetFilenames\(\)](#)

Reimplemented in [gdcm::IPPSorter](#).

Examples

[SortImage.cxx](#).

10.283.4.7 StableSort()

```
virtual bool gdcm::Sorter::StableSort (  
    std::vector< std::string > const & filenames) [virtual]
```

Examples

[SortImage.cxx](#), and [VolumeSorter.cxx](#).

10.283.5 Friends And Related Symbol Documentation

10.283.5.1 operator<<

```
std::ostream & operator<< (  
    std::ostream & _os,  
    const Sorter & s) [friend]
```

References [Sorter\(\)](#), and [Print\(\)](#).

10.283.6 Member Data Documentation

10.283.6.1 Filenames

```
std::vector<std::string> gdcm::Sorter::Filenames [protected]
```

Referenced by [GetFilenames\(\)](#).

10.283.6.2 Selection

```
std::map<Tag,std::string> gdcm::Sorter::Selection [protected]
```

10.283.6.3 SortFunc

```
SortFunction gdcm::Sorter::SortFunc [protected]
```

10.283.6.4 TagsToRead

```
std::set<Tag> gdcm::Sorter::TagsToRead [protected]
```

The documentation for this class was generated from the following file:

- [gdcmSorter.h](#)

10.284 gdcm::Spacing Class Reference

Class for [Spacing](#).

```
#include <gdcmSpacing.h>
```

Public Types

- enum [SpacingType](#) {
 [DETECTOR](#) = 0 ,
 [MAGNIFIED](#) ,
 [CALIBRATED](#) ,
 [UNKNOWN](#) }

Public Member Functions

- [Spacing](#) ()
- [~Spacing](#) ()=default

Static Public Member Functions

- static [Attribute](#)< 0x28, 0x34 > [ComputePixelAspectRatioFromPixelSpacing](#) (const [Attribute](#)< 0x28, 0x30 > &pixelspacing)

10.284.1 Detailed Description

Class for [Spacing](#).

It all began with a mail to WG6:

Subject: Imager Pixel [Spacing](#) vs Pixel [Spacing](#) **Body:** [Apologies for the duplicate post, namely to David Clunie & OFFIS team]

I have been trying to understand CP-586 in the following two cases:

On the one hand:

- DISCIMG/IMAGES/CRIMAGE taken from <http://dclunie.com/images/pixelspacingtestimages.zip>

And on the other hand:

- http://gdcm.sourceforge.net/thingies/cr_pixelspacing.dcm

If I understand correctly the CP, one is required to use Pixel [Spacing](#) for measurement ('true size' print) instead of Imager Pixel [Spacing](#), since the two attributes are present and Pixel [Spacing](#) is different from Imager Pixel [Spacing](#).

If this is correct, then the test data DISCIMG/IMAGES/CRIMAGE is incorrect. If this is incorrect (ie. I need to use Imager Pixel [Spacing](#)), then the display of cr_pixelspacing.dcm for measurement will be incorrect.

Could someone please let me know what am I missing here? I could not find any information in any header that would allow me to differentiate those.

Thank you for your time,

Ref: <http://lists.nema.org/scripts/lyris.pl?sub=488573&id=400720477>

See PS 3.3-2008, [Table C.7-11b](#) IMAGE PIXEL MACRO ATTRIBUTES

Ratio of the vertical size and horizontal size of the pixels in the image specified by a pair of integer values where the first value is the vertical pixel size, and the second value is the horizontal pixel size. Required if the aspect ratio values do not have a ratio of 1:1 and the physical pixel spacing is not specified by Pixel [Spacing](#) (0028,0030), or Imager Pixel [Spacing](#) (0018,1164) or Nominal Scanned Pixel [Spacing](#) (0018,2010), either for the entire [Image](#) or per-frame in a Functional Group [Macro](#). See C.7.6.3.1.7.

PS 3.3-2008 10.7.1.3 Pixel [Spacing Value](#) Order and Valid Values All pixel spacing related attributes shall have non-zero values, except when there is only a single row or column or pixel of data present, in which case the corresponding value may be zero.

Ref: http://gdcm.sourceforge.net/wiki/index.php/Imager_Pixel_Spacing

10.284.2 Member Enumeration Documentation

10.284.2.1 SpacingType

```
enum gdcm::Spacing::SpacingType
```

Enumerator

DETECTOR	
MAGNIFIED	
CALIBRATED	
UNKNOWN	

10.284.3 Constructor & Destructor Documentation

10.284.3.1 Spacing()

```
gdcm::Spacing::Spacing ()
```

10.284.3.2 ~Spacing()

```
gdcM::Spacing::~Spacing () [default]
```

10.284.4 Member Function Documentation

10.284.4.1 ComputePixelAspectRatioFromPixelSpacing()

```
Attribute< 0x28, 0x34 > gdcM::Spacing::ComputePixelAspectRatioFromPixelSpacing (
    const Attribute< 0x28, 0x30 > & pixelspacing) [static]
```

The documentation for this class was generated from the following file:

- [gdcMSpacing.h](#)

10.285 gdcM::Spectroscopy Class Reference

[Spectroscopy](#) class.

```
#include <gdcMSpectroscopy.h>
```

Public Member Functions

- [Spectroscopy](#) ()=default

10.285.1 Detailed Description

[Spectroscopy](#) class.

10.285.2 Constructor & Destructor Documentation

10.285.2.1 Spectroscopy()

```
gdcM::Spectroscopy::Spectroscopy () [default]
```

The documentation for this class was generated from the following file:

- [gdcMSpectroscopy.h](#)

10.286 gdcm::SplitMosaicFilter Class Reference

[SplitMosaicFilter](#) class.

```
#include <gdcmSplitMosaicFilter.h>
```

Public Member Functions

- [SplitMosaicFilter](#) ()
- [~SplitMosaicFilter](#) ()
- bool [ComputeMOSAICDimensions](#) (unsigned int dims[3])
- bool [ComputeMOSAICImagePositionPatient](#) (double pos[3], const double ipp[6], const double dircos[6], const double pixelspacing[3], const unsigned int image_dims[3], const unsigned int mosaic_dims[3], bool inverted)
Extract the value for ImagePositionPatient.
- bool [ComputeMOSAICSliceNormal](#) (double dims[3], bool &inverted)
Extract the value for SliceNormalVector (CSA header)
- bool [ComputeMOSAICSlicePosition](#) (double pos[3], bool inverted)
- [File](#) & [GetFile](#) ()
- const [File](#) & [GetFile](#) () const
- [Image](#) & [GetImage](#) ()
- const [Image](#) & [GetImage](#) () const
- void [SetFile](#) (const [File](#) &f)
- void [SetImage](#) (const [Image](#) &image)
- bool [Split](#) ()
Split the SIEMENS MOSAIC image.

Static Public Member Functions

- static const [DataElement](#) & [ComputeCSAImageHeaderInfo](#) (const [DataSet](#) &ds, bool handleMissingPrivate↵ Creator=true)
Return the [DataElement](#) for the CSA [Image](#) Header.
- static const [DataElement](#) & [ComputeCSASeriesHeaderInfo](#) (const [DataSet](#) &ds, bool handleMissingPrivate↵ Creator=true)
Return the [DataElement](#) for the CSA [Series](#) Header.
- static bool [GetAcquisitionSize](#) (unsigned int size[2], [DataSet](#) const &ds)
Get the Acquisition Matrix (non zero value):
- static unsigned int [GetNumberOfImagesInMosaic](#) ([File](#) const &file)
Return the value for NumberOfImagesInMosaic, or compute it from Acquisition Size.

10.286.1 Detailed Description

[SplitMosaicFilter](#) class.

Class to reshuffle bytes for a SIEMENS Mosaic image Siemens CSA [Image](#) Header CSA:= Common Siemens Architecture, sometimes also known as Common syngo Architecture

Warning

when private attributes are not found, the acquisition matrix is used to compute the NumberOfImagesInMosaic. This means trailing black slices will be considered in the volume (instead of discarded). CSA 0029,1010 is needed for correct NumberOfImagesInMosaic CSA 0029,1020 is needed to compute the correct origin without above info default are taken (may not be accurate).

10.286.2 Constructor & Destructor Documentation

10.286.2.1 SplitMosaicFilter()

```
gdcm::SplitMosaicFilter::SplitMosaicFilter ()
```

10.286.2.2 ~SplitMosaicFilter()

```
gdcm::SplitMosaicFilter::~SplitMosaicFilter ()
```

10.286.3 Member Function Documentation

10.286.3.1 ComputeCSAImageHeaderInfo()

```
const DataElement & gdcm::SplitMosaicFilter::ComputeCSAImageHeaderInfo (
    const DataSet & ds,
    bool handleMissingPrivateCreator = true) [static]
```

Return the [DataElement](#) for the CSA [Image](#) Header.

10.286.3.2 ComputeCSASeriesHeaderInfo()

```
const DataElement & gdcm::SplitMosaicFilter::ComputeCSASeriesHeaderInfo (
    const DataSet & ds,
    bool handleMissingPrivateCreator = true) [static]
```

Return the [DataElement](#) for the CSA [Series](#) Header.

10.286.3.3 ComputeMOSAICDimensions()

```
bool gdcm::SplitMosaicFilter::ComputeMOSAICDimensions (
    unsigned int dims[3])
```

Compute the new dimensions according to private information stored in the MOSAIC header.

10.286.3.4 ComputeMOSAICImagePositionPatient()

```
bool gdcm::SplitMosaicFilter::ComputeMOSAICImagePositionPatient (
    double pos[3],
    const double ipp[6],
    const double dircos[6],
    const double pixelspacing[3],
    const unsigned int image_dims[3],
    const unsigned int mosaic_dims[3],
    bool inverted)
```

Extract the value for ImagePositionPatient.

10.286.3.5 ComputeMOSAICSliceNormal()

```
bool gdcm::SplitMosaicFilter::ComputeMOSAICSliceNormal (
    double dims[3],
    bool & inverted)
```

Extract the value for SliceNormal/Vector (CSA header)

10.286.3.6 ComputeMOSAICSlicePosition()

```
bool gdcm::SplitMosaicFilter::ComputeMOSAICSlicePosition (
    double pos[3],
    bool inverted)
```

Extract the value for ImagePositionPatient (requires inverted flag) Deprecated

10.286.3.7 GetAcquisitionSize()

```
bool gdcm::SplitMosaicFilter::GetAcquisitionSize (
    unsigned int size[2],
    DataSet const & ds) [static]
```

Get the Acquisition Matrix (non zero value):

10.286.3.8 GetFile() [1/2]

```
File & gdcm::SplitMosaicFilter::GetFile () [inline]
```

10.286.3.9 GetFile() [2/2]

```
const File & gdcm::SplitMosaicFilter::GetFile () const [inline]
```

10.286.3.10 GetImage() [1/2]

```
Image & gdcm::SplitMosaicFilter::GetImage () [inline]
```

10.286.3.11 GetImage() [2/2]

```
const Image & gdcm::SplitMosaicFilter::GetImage () const [inline]
```

10.286.3.12 GetNumberOfImagesInMosaic()

```
unsigned int gdcM::SplitMosaicFilter::GetNumberOfImagesInMosaic (  
    File const & file) [static]
```

Return the value for NumberOfImagesInMosaic, or compute it from Acquisition Size.

10.286.3.13 SetFile()

```
void gdcM::SplitMosaicFilter::SetFile (  
    const File & f) [inline]
```

10.286.3.14 SetImage()

```
void gdcM::SplitMosaicFilter::SetImage (  
    const Image & image)
```

10.286.3.15 Split()

```
bool gdcM::SplitMosaicFilter::Split ()
```

Split the SIEMENS MOSAIC image.


The documentation for this class was generated from the following file:

- [gdcMSplitMosaicFilter.h](#)


10.287 gdcM::StartEvent Class Reference

```
#include <gdcMEvent.h>
```

Inheritance diagram for gdcM::StartEvent:



Collaboration diagram for `gdcm::StartEvent`:



Additional Inherited Members

Public Member Functions inherited from [gdcm::Event](#)

- [Event](#) ()
- [Event](#) (const [Event](#) &)
- virtual [~Event](#) ()
- virtual bool [CheckEvent](#) (const [Event](#) *) const =0
- virtual const char * [GetEventName](#) () const =0
- virtual [Event](#) * [MakeObject](#) () const =0
- void [operator=](#) (const [Event](#) &)=delete
- virtual void [Print](#) (std::ostream &os) const

The documentation for this class was generated from the following file:

- [gdcmEvent.h](#)

10.288 `gdcm::static_assert_test< x >` Struct Template Reference


```
#include <gdcmStaticAssert.h>
```

The documentation for this struct was generated from the following file:

- [gdcmStaticAssert.h](#)

10.289 gdcmm::STATIC_ASSERTION_FAILURE< x > Struct Template Reference

Inheritance diagram for gdcmm::STATIC_ASSERTION_FAILURE< x >:




The documentation for this struct was generated from the following file:

- [gdcmmStaticAssert.h](#)


10.290 gdcmm::STATIC_ASSERTION_FAILURE< true > Struct Reference

```
#include <gdcmmStaticAssert.h>
```

Inheritance diagram for gdcmm::STATIC_ASSERTION_FAILURE< true >:



Collaboration diagram for gdcm::STATIC_ASSERTION_FAILURE< true >:



Public Types

- enum { `value` = 1 }

10.290.1 Member Enumeration Documentation

10.290.1.1 anonymous enum

anonymous enum

Enumerator

value	
-------	--

The documentation for this struct was generated from the following file:

- [gdcmStaticAssert.h](#)

10.291 gdcm::StreamImageReader Class Reference

[StreamImageReader](#).

```
#include <gdcmStreamImageReader.h>
```

Public Member Functions

- [StreamImageReader](#) ()
- virtual [~StreamImageReader](#) ()
- bool [CanReadImage](#) () const
- void [DefinePixelExtent](#) (uint16_t inXMin, uint16_t inXMax, uint16_t inYMin, uint16_t inYMax, uint16_t inZMin=0, uint16_t inZMax=1)
- uint32_t [DefineProperBufferLength](#) () const
- std::vector< unsigned int > [GetDimensionsValueForResolution](#) (unsigned int)
- [File](#) const & [GetFile](#) () const
- bool [Read](#) (char *inReadBuffer, const std::size_t &inBufferLength)
- virtual bool [ReadImageInformation](#) ()
- void [SetFileName](#) (const char *inFileName)
- void [SetStream](#) (std::istream &inStream)

10.291.1 Detailed Description

[StreamImageReader](#).

Note

its role is to convert the DICOM [DataSet](#) into a [Image](#) representation via an ITK streaming (ie, multithreaded) interface [Image](#) is different from [Pixmap](#) has it has a position and a direction in Space. Currently, this class is thread safe in that it can read a single extent in a single thread. Multiple versions can be used for multiple extents/threads.

See also

[Image](#)

Examples

[ExtractOneFrame.cs](#), and [StreamImageReaderTest.cxx](#).

10.291.2 Constructor & Destructor Documentation

10.291.2.1 StreamImageReader()

```
gdcm::StreamImageReader::StreamImageReader ()
```

10.291.2.2 ~StreamImageReader()

```
virtual gdcm::StreamImageReader::~~StreamImageReader () [virtual]
```


10.291.3 Member Function Documentation

10.291.3.1 CanReadImage()

```
bool gdcm::StreamImageReader::CanReadImage () const
```

Only RAW images are currently readable by the stream reader. As more streaming codecs are added, then this function will be updated to reflect those changes. Calling this function prior to reading will ensure that only streamable files are streamed. Make sure to call ReadImageInformation prior to calling this function.

Examples

[StreamImageReaderTest.cxx](#).

10.291.3.2 DefinePixelExtent()

```
void gdcm::StreamImageReader::DefinePixelExtent (
    uint16_t inXMin,
    uint16_t inXMax,
    uint16_t inYMin,
    uint16_t inYMax,
    uint16_t inZMin = 0,
    uint16_t inZMax = 1)
```

Defines an image extent for the Read function. DICOM states that an image can have no more than 2^{16} pixels per edge (as of 2009) In this case, the pixel extents ignore the direction cosines entirely, and assumes that the origin of the image is at location 0,0 (regardless of the definition in space per the tags). So, if the first 100 pixels of the first row are to be read in, this function should be called with DefinePixelExtent(0, 100, 0, 1), regardless of pixel size or orientation.

Examples

[ExtractOneFrame.cs](#), and [StreamImageReaderTest.cxx](#).

10.291.3.3 DefineProperBufferLength()

```
uint32_t gdcm::StreamImageReader::DefineProperBufferLength () const
```

Paying attention to the pixel format and so forth, define the proper buffer length for the user. The return amount is in bytes. Call this function to determine the size of the char* buffer that will need to be passed in to ReadImageSubregion(). If the return is 0, then that means that the pixel extent was not defined prior

Examples

[ExtractOneFrame.cs](#), and [StreamImageReaderTest.cxx](#).

10.291.3.4 GetDimensionsValueForResolution()

```
std::vector< unsigned int > gdcM::StreamImageReader::GetDimensionsValueForResolution (
    unsigned int )
```

10.291.3.5 GetFile()

```
File const & gdcM::StreamImageReader::GetFile () const
```

Returns the dataset read by ReadImageInformation Couple this with the [ImageHelper](#) to get statistics about the image, like pixel extent, to be able to initialize buffers for reading

Examples

[ExtractOneFrame.cs](#), and [StreamImageReaderTest.cxx](#).

10.291.3.6 Read()

```
bool gdcM::StreamImageReader::Read (
    char * inReadBuffer,
    const std::size_t & inBufferLength)
```

Read the DICOM image. There are three reasons for failure:

1. The extent is not set
2. the conversion from char* to std::ostream (internally) fails
3. the given buffer isn't large enough to accommodate the desired pixel extent. This method has been implemented to look similar to the metaimageio in itk MUST have an extent defined, or else Read will return false. If no particular extent is required, use [ImageReader](#) instead.

Examples

[ExtractOneFrame.cs](#), and [StreamImageReaderTest.cxx](#).

10.291.3.7 ReadImageInformation()

```
virtual bool gdcM::StreamImageReader::ReadImageInformation () [virtual]
```

Set the spacing and dimension information for the set filename. returns false if the file is not initialized or not an image, with the pixel (7fe0,0010) tag.

Examples

[ExtractOneFrame.cs](#), and [StreamImageReaderTest.cxx](#).

10.291.3.8 SetFileName()

```
void gdcm::StreamImageReader::SetFileName (
    const char * inFileName)
```

One of either SetFileName or SetStream must be called prior to any other functions. These initialize an internal [Reader](#) class to be able to get non-pixel image information.

Examples

[ExtractOneFrame.cs](#), and [StreamImageReaderTest.cxx](#).

10.291.3.9 SetStream()

```
void gdcm::StreamImageReader::SetStream (
    std::istream & inStream)
```

The documentation for this class was generated from the following file:


- [gdcmStreamImageReader.h](#)

10.292 gdcm::StreamImageWriter Class Reference

[StreamImageReader](#).

```
#include <gdcmStreamImageWriter.h>
```

Collaboration diagram for `gdcm::StreamImageWriter`:



Public Member Functions

- [StreamImageWriter](#) ()
- virtual [~StreamImageWriter](#) ()
- bool [CanWriteFile](#) () const
- void [DefinePixelExtent](#) (uint16_t inXMin, uint16_t inXMax, uint16_t inYMin, uint16_t inYMax, uint16_t inZMin=0, uint16_t inZMax=1)
- uint32_t [DefineProperBufferLength](#) ()
- void [SetFile](#) (const [File](#) &inFile)
- void [SetFileName](#) (const char *inFileName)
- void [SetStream](#) (std::ostream &inStream)
- bool [Write](#) (void *inWriteBuffer, const std::size_t &inBufferLength)
- virtual bool [WriteImageInformation](#) ()

Protected Member Functions

- virtual bool [WriteImageSubregionRAW](#) (char *inWriteBuffer, const std::size_t &inBufferLength)
- int [WriteRawHeader](#) ([RAWCodec](#) *inCodec, std::ostream *inStream)

Protected Attributes

- int [mElementOffsets](#)
- int [mElementOffsets1](#)
- [SmartPointer< File >](#) [mspFile](#)
- [Writer](#) [mWriter](#)
- uint16_t [mXMax](#)
- uint16_t [mXMin](#)
- uint16_t [mYMax](#)
- uint16_t [mYMin](#)
- uint16_t [mZMax](#)
- uint16_t [mZMin](#)

10.292.1 Detailed Description

[StreamImageReader](#).

Note

its role is to convert the DICOM [DataSet](#) into a [Image](#) representation via an ITK streaming (ie, multithreaded) interface [Image](#) is different from [Pixmap](#) has it has a position and a direction in Space. Currently, this class is threadsafe in that it can read a single extent in a single thread. Multiple versions can be used for multiple extents/threads.

See also

[Image](#)

Examples

[Extracting_All_Resolution.cxx](#), [Fake_Image_Using_Stream_Image_Writer.cxx](#), and [StreamImageReaderTest.cxx](#).

10.292.2 Constructor & Destructor Documentation**10.292.2.1 StreamImageWriter()**

```
gdcm::StreamImageWriter::StreamImageWriter ()
```

10.292.2.2 ~StreamImageWriter()

```
virtual gdcm::StreamImageWriter::~~StreamImageWriter () [virtual]
```

10.292.3 Member Function Documentation

10.292.3.1 CanWriteFile()

```
bool gdcmm::StreamImageWriter::CanWriteFile () const
```

This function determines if a file can even be written using the streaming writer unlike the reader, can be called before WriteImageInformation, but must be called after SetFile.

Examples

[Extracting_All_Resolution.cxx](#), and [Fake_Image_Using_Stream_Image_Writer.cxx](#).

10.292.3.2 DefinePixelExtent()

```
void gdcmm::StreamImageWriter::DefinePixelExtent (
    uint16_t inXMin,
    uint16_t inXMax,
    uint16_t inYMin,
    uint16_t inYMax,
    uint16_t inZMin = 0,
    uint16_t inZMax = 1)
```

Defines an image extent for the Read function. DICOM states that an image can have no more than 2^{16} pixels per edge (as of 2009) In this case, the pixel extents ignore the direction cosines entirely, and assumes that the origin of the image is at location 0,0 (regardless of the definition in space per the tags). So, if the first 100 pixels of the first row are to be read in, this function should be called with DefinePixelExtent(0, 100, 0, 1), regardless of pixel size or orientation. 15 nov 2010: added z dimension, defaults to being 1 plane large

Examples

[Extracting_All_Resolution.cxx](#), [Fake_Image_Using_Stream_Image_Writer.cxx](#), and [StreamImageReaderTest.cxx](#).

10.292.3.3 DefineProperBufferLength()

```
uint32_t gdcmm::StreamImageWriter::DefineProperBufferLength ()
```

Paying attention to the pixel format and so forth, define the proper buffer length for the user. The return amount is in bytes. If the return is 0, then that means that the pixel extent was not defined prior this return is for RAW inputs which are then encoded by the writer, but are used to ensure that the writer gets the proper buffer size

Examples

[Extracting_All_Resolution.cxx](#), [Fake_Image_Using_Stream_Image_Writer.cxx](#), and [StreamImageReaderTest.cxx](#).

10.292.3.4 SetFile()

```
void gdcm::StreamImageWriter::SetFile (
    const File & inFile)
```

Set the image information to be written to disk that is everything but the pixel information: (7fe0,0010) PixelData

Examples

[Extracting_All_Resolution.cxx](#), [Fake_Image_Using_Stream_Image_Writer.cxx](#), and [StreamImageReaderTest.cxx](#).

10.292.3.5 SetFileName()

```
void gdcm::StreamImageWriter::SetFileName (
    const char * inFileName)
```

One of either SetFileName or SetStream must be called prior to any other functions. These initialize an internal [Reader](#) class to be able to get non-pixel image information.

10.292.3.6 SetStream()

```
void gdcm::StreamImageWriter::SetStream (
    std::ostream & inStream)
```

Examples

[Extracting_All_Resolution.cxx](#), [Fake_Image_Using_Stream_Image_Writer.cxx](#), and [StreamImageReaderTest.cxx](#).

10.292.3.7 Write()

```
bool gdcm::StreamImageWriter::Write (
    void * inWriteBuffer,
    const std::size_t & inBufferLength)
```

Read the DICOM image. There are three reasons for failure:

1. The extent is not set
2. the conversion from void* to std::ostream (internally) fails
3. the given buffer isn't large enough to accommodate the desired pixel extent. This method has been implemented to look similar to the metaimageio in itk MUST have an extent defined, or else Read will return false. If no particular extent is required, use [ImageReader](#) instead.

Examples

[Extracting_All_Resolution.cxx](#), [Fake_Image_Using_Stream_Image_Writer.cxx](#), and [StreamImageReaderTest.cxx](#).

10.292.3.8 WriteImageInformation()

```
virtual bool gdcm::StreamImageWriter::WriteImageInformation () [virtual]
```

Write the header information to disk, and a bunch of zeros for the actual pixel information. Of course, if we're doing a non-compressed format, that works but if it's compressed, we have to force the ordering of chunks that are written.

Examples

[Extracting_All_Resolution.cxx](#), [Fake_Image_Using_Stream_Image_Writer.cxx](#), and [StreamImageReaderTest.cxx](#).

10.292.3.9 WriteImageSubregionRAW()

```
virtual bool gdcm::StreamImageWriter::WriteImageSubregionRAW (
    char * inWriteBuffer,
    const std::size_t & inBufferLength) [protected], [virtual]
```

Using the min, max, etc set by DefinePixelExtent, this will fill the given buffer. Make sure to call DefinePixelExtent and to initialize the buffer with the amount given by DefineProperBufferLength prior to calling this. Reads by the RAW codec; other codecs are added once implemented.

10.292.3.10 WriteRawHeader()

```
int gdcm::StreamImageWriter::WriteRawHeader (
    RAWCodec * inCodec,
    std::ostream * inStream) [protected]
```

When writing a raw file, we know the full extent, and can just write the first 12 bytes out (the tag, the [VR](#), and the size). When we do compressed files, we'll do it in chunks, as described in 2009-3, part 5, Annex A, section 4. Pass the raw codec so that in the rare case of a bigendian explicit raw, the first 12 bytes written out should still be kosher. Returns -1 if there's any failure, or the complete offset (12 bytes) if it works. Those 12 bytes are then added to the position in order to determine where to write.

10.292.4 Member Data Documentation

10.292.4.1 mElementOffsets

```
int gdcm::StreamImageWriter::mElementOffsets [protected]
```

The result of WriteRawHeader (or another header, when that's implemented). This result is saved so that the first N bytes aren't constantly being rewritten for each chunk that's passed in. For compressed data, the offset table will require rewrites of data.

10.292.4.2 mElementOffsets1

```
int gdcm::StreamImageWriter::mElementOffsets1 [protected]
```


10.292.4.3 mspFile

`SmartPointer<File> gdcm::StreamImageWriter::mspFile` [protected]

10.292.4.4 mWriter

`Writer gdcm::StreamImageWriter::mWriter` [protected]

10.292.4.5 mXMax

`uint16_t gdcm::StreamImageWriter::mXMax` [protected]

10.292.4.6 mXMin

`uint16_t gdcm::StreamImageWriter::mXMin` [protected]

10.292.4.7 mYMax

`uint16_t gdcm::StreamImageWriter::mYMax` [protected]

10.292.4.8 mYMin

`uint16_t gdcm::StreamImageWriter::mYMin` [protected]

10.292.4.9 mZMax

`uint16_t gdcm::StreamImageWriter::mZMax` [protected]

10.292.4.10 mZMin

`uint16_t gdcm::StreamImageWriter::mZMin` [protected]

The documentation for this class was generated from the following file:


- [gdcmStreamImageWriter.h](#)

10.293 gdcm::StrictScanner Class Reference


[StrictScanner](#).

```
#include <gdcmStrictScanner.h>
```

Inheritance diagram for gdcm::StrictScanner:



Collaboration diagram for gdcm::StrictScanner:



Classes

- struct [ltstr](#)

Public Types

- typedef MappingType::const_iterator [ConstIterator](#)
- typedef std::map< const char *, [TagToValue](#), [Itstr](#) > [MappingType](#)
- typedef std::map< [Tag](#), const char * > [TagToValue](#)
- typedef TagToValue::value_type [TagToValueValueType](#)
- typedef std::set< std::string > [ValuesType](#)

Public Member Functions

- [StrictScanner](#) ()
- [~StrictScanner](#) () override
- void [AddPrivateTag](#) ([PrivateTag](#) const &t)
- void [AddSkipTag](#) ([Tag](#) const &t)
Add a tag that will need to be skipped. Those are root level skip tags.
- void [AddTag](#) ([Tag](#) const &t)
Add a tag that will need to be read. Those are root level skip tags.
- [ConstIterator](#) [Begin](#) () const
- void [ClearSkipTags](#) ()
- void [ClearTags](#) ()
- [ConstIterator](#) [End](#) () const
- [Directory::FilenameType](#) [GetAllFileNamesFromTagToValue](#) ([Tag](#) const &t, const char *valueref) const
- const char * [GetFilenameFromTagToValue](#) ([Tag](#) const &t, const char *valueref) const
- [Directory::FilenameType](#) const & [GetFileNames](#) () const
- [Directory::FilenameType](#) [GetKeys](#) () const
- [TagToValue](#) const & [GetMapping](#) (const char *filename) const
Get the std::map mapping filenames to value for file 'filename'.
- [TagToValue](#) const & [GetMappingFromTagToValue](#) ([Tag](#) const &t, const char *value) const
See [GetFilenameFromTagToValue\(\)](#). This is simply [GetFilenameFromTagToValue](#) followed.
- [MappingType](#) const & [GetMappings](#) () const
Mappings are the mapping from a particular tag to the map, mapping filename to value:
- [Directory::FilenameType](#) [GetOrderedValues](#) ([Tag](#) const &t) const
- const char * [GetValue](#) (const char *filename, [Tag](#) const &t) const
- [ValuesType](#) const & [GetValues](#) () const
Get all the values found (in lexicographic order)
- [ValuesType](#) [GetValues](#) ([Tag](#) const &t) const
Get all the values found (in lexicographic order) associated with [Tag](#) 't'.
- bool [IsKey](#) (const char *filename) const
- void [Print](#) (std::ostream &os) const override
Print result.
- void [PrintTable](#) (std::ostream &os) const
- bool [Scan](#) ([Directory::FilenameType](#) const &filenames)
Start the scan !

Public Member Functions inherited from [gdcm::Subject](#)

- [Subject](#) ()
- [~Subject](#) () override
- unsigned long [AddObserver](#) (const [Event](#) &event, [Command](#) *)
- unsigned long [AddObserver](#) (const [Event](#) &event, [Command](#) *) const
- [Command](#) * [GetCommand](#) (unsigned long tag)
- bool [HasObserver](#) (const [Event](#) &event) const
- void [InvokeEvent](#) (const [Event](#) &)
- void [InvokeEvent](#) (const [Event](#) &) const
- void [RemoveAllObservers](#) ()
- void [RemoveObserver](#) (unsigned long tag)

Public Member Functions inherited from [gdcm::Object](#)

- [Object](#) ()
- [Object](#) (const [Object](#) &)
Special requirement for copy/cstor, assignment operator.
- virtual [~Object](#) ()
- void [operator=](#) (const [Object](#) &)

Static Public Member Functions

- static [SmartPointer](#)< [StrictScanner](#) > [New](#) ()
for wrapped language: instantiate a reference counted object

Protected Member Functions

- void [ProcessPublicTag](#) ([StringFilter](#) &sf, const char *filename)

Protected Member Functions inherited from [gdcm::Object](#)

- void [Register](#) ()
- void [UnRegister](#) ()

Friends

- std::ostream & [operator<<](#) (std::ostream &_os, const [StrictScanner](#) &s)

10.293.1 Detailed Description

[StrictScanner](#).

This filter is meant for quickly browsing a [FileSet](#) (a set of files on disk). Special consideration are taken so as to read the minimum amount of information in each file in order to retrieve the user specified set of DICOM [Attribute](#).

This filter is dealing with both VRASCII and VRBINARY element, thanks to the help of [StringFilter](#)

Warning

IMPORTANT In case of file where tags are not ordered (illegal as per DICOM specification), the output will be missing information

Note

implementation details. All values are stored in a `std::set` of `std::string`. Then the address of the `cstring` underlying the `std::string` is used in the `std::map`.

This class implement the Subject/Observer pattern trigger the following events:

- [ProgressEvent](#)
- [StartEvent](#)
- [EndEvent](#)

Examples

[ScanDirectory.cs](#), and [SimpleScanner.cxx](#).

10.293.2 Member Typedef Documentation

10.293.2.1 ConstIterator

```
typedef MappingType::const_iterator gdcm::StrictScanner::ConstIterator
```

10.293.2.2 MappingType

```
typedef std::map<const char *, TagToValue, ltstr> gdcm::StrictScanner::MappingType
```

10.293.2.3 TagToValue

```
typedef std::map<Tag, const char*> gdcM::StrictScanner::TagToValue
```

struct to map a filename to a value Implementation note: all std::map in this class will be using const char * and not std::string since we are pointing to existing std::string (hold in a std::vector) this avoid an extra copy of the byte array. [Tag](#) are used as [Tag](#) class since sizeof(tag) <= sizeof(pointer)

Examples

[SimpleScanner.cxx](#).

10.293.2.4 TagToValueValueType

```
typedef TagToValue::value_type gdcM::StrictScanner::TagToValueValueType
```

10.293.2.5 ValueType

```
typedef std::set< std::string > gdcM::StrictScanner::ValueType
```

10.293.3 Constructor & Destructor Documentation

10.293.3.1 StrictScanner()

```
gdcM::StrictScanner::StrictScanner () [inline]
```

Referenced by [New\(\)](#), and [operator<<](#).

10.293.3.2 ~StrictScanner()

```
gdcM::StrictScanner::~~StrictScanner () [override]
```

10.293.4 Member Function Documentation

10.293.4.1 AddPrivateTag()

```
void gdcM::StrictScanner::AddPrivateTag (  
    PrivateTag const & t)
```

10.293.4.2 AddSkipTag()

```
void gdcmm::StrictScanner::AddSkipTag (  
    Tag const & t)
```

Add a tag that will need to be skipped. Those are root level skip tags.

10.293.4.3 AddTag()

```
void gdcmm::StrictScanner::AddTag (  
    Tag const & t)
```

Add a tag that will need to be read. Those are root level skip tags.

Examples

[ScanDirectory.cs](#), and [SimpleScanner.cxx](#).

10.293.4.4 Begin()

```
ConstIterator gdcmm::StrictScanner::Begin () const [inline]
```

10.293.4.5 ClearSkipTags()

```
void gdcmm::StrictScanner::ClearSkipTags ()
```

10.293.4.6 ClearTags()

```
void gdcmm::StrictScanner::ClearTags ()
```

10.293.4.7 End()

```
ConstIterator gdcmm::StrictScanner::End () const [inline]
```

10.293.4.8 GetAllFileNamesFromTagToValue()

```
Directory::FileNamesType gdcmm::StrictScanner::GetAllFileNamesFromTagToValue (  
    Tag const & t,  
    const char * valuref) const
```

Will loop over all files and return a vector of std::strings of filenames where value match the reference value 'valuref'

10.293.4.9 GetFilenameFromTagToValue()

```
const char * gdcM::StrictScanner::GetFilenameFromTagToValue (
    Tag const & t,
    const char * valueref) const
```

Will loop over all files and return the first file where value match the reference value 'valueref'

10.293.4.10 GetFileNames()

```
Directory::FileNamesType const & gdcM::StrictScanner::GetFileNames () const [inline]
```

10.293.4.11 GetKeys()

```
Directory::FileNamesType gdcM::StrictScanner::GetKeys () const
```

Return the list of filename that are key in the internal map, which means those filename were properly parsed

10.293.4.12 GetMapping()

```
TagToValue const & gdcM::StrictScanner::GetMapping (
    const char * filename) const
```

Get the std::map mapping filenames to value for file 'filename'.

Examples

[SimpleScanner.cxx](#).

10.293.4.13 GetMappingFromTagToValue()

```
TagToValue const & gdcM::StrictScanner::GetMappingFromTagToValue (
    Tag const & t,
    const char * value) const
```

See [GetFilenameFromTagToValue\(\)](#). This is simply GetFilenameFromTagToValue followed.

10.293.4.14 GetMappings()

```
MappingType const & gdcM::StrictScanner::GetMappings () const [inline]
```

Mappings are the mapping from a particular tag to the map, mapping filename to value:

10.293.4.15 GetOrderedValues()

```
Directory::FilenameType gdcm::StrictScanner::GetOrderedValues (
    Tag const & t) const
```

Get all the values found (in a vector) associated with [Tag 't'](#) This function is identical to [GetValues](#), but is accessible from the wrapped layer (python, C#, java)

10.293.4.16 GetValue()

```
const char * gdcm::StrictScanner::GetValue (
    const char * filename,
    Tag const & t) const
```

Retrieve the value found for tag: t associated with file: filename This is meant for a single short call. If multiple calls (multiple tags) should be done, prefer the [GetMapping](#) function, and then reuse the [TagToValue](#) hash table.

Warning

[Tag 't'](#) should have been added via [AddTag\(\)](#) prior to the [Scan\(\)](#) call !

10.293.4.17 GetValues() [1/2]

```
ValueType const & gdcm::StrictScanner::GetValues () const [inline]
```

Get all the values found (in lexicographic order)

10.293.4.18 GetValues() [2/2]

```
ValueType gdcm::StrictScanner::GetValues (
    Tag const & t) const
```

Get all the values found (in lexicographic order) associated with [Tag 't'](#).

10.293.4.19 IsKey()

```
bool gdcm::StrictScanner::IsKey (
    const char * filename) const
```

Check if filename is a key in the Mapping table. returns true only if file can be found, which means the file was indeed a DICOM file that could be processed

Examples

[ScanDirectory.cs](#), and [SimpleScanner.cxx](#).

10.293.4.20 New()

```
SmartPointer< StrictScanner > gdcmm::StrictScanner::New () [inline], [static]
```

for wrapped language: instantiate a reference counted object

Examples

[ScanDirectory.cs](#).

References [StrictScanner\(\)](#).

10.293.4.21 Print()

```
void gdcmm::StrictScanner::Print (
    std::ostream & os) const [override], [virtual]
```

Print result.

Reimplemented from [gdcmm::Object](#).

Referenced by [operator<<](#).

10.293.4.22 PrintTable()

```
void gdcmm::StrictScanner::PrintTable (
    std::ostream & os) const
```

10.293.4.23 ProcessPublicTag()

```
void gdcmm::StrictScanner::ProcessPublicTag (
    StringFilter & sf,
    const char * filename) [protected]
```

10.293.4.24 Scan()

```
bool gdcmm::StrictScanner::Scan (
    Directory::FileNamesType const & filenames)
```

Start the scan !

Examples

[ScanDirectory.cs](#), and [SimpleScanner.cxx](#).

10.293.5 Friends And Related Symbol Documentation

10.293.5.1 operator<<

```
std::ostream & operator<< (  
    std::ostream & _os,  
    const StrictScanner & s) [friend]
```

References [StrictScanner\(\)](#), and [Print\(\)](#).

The documentation for this class was generated from the following file:


- [gdcmStrictScanner.h](#)

10.294 gdcm::StrictScanner2 Class Reference


[StrictScanner2](#).

```
#include <gdcmStrictScanner2.h>
```

Inheritance diagram for gdcm::StrictScanner2:



Collaboration diagram for `gdcm::StrictScanner2`:



Classes

- struct [Itstr](#)

Public Types

- typedef `PrivateMappingType::const_iterator` [PrivateConstIterator](#)
- typedef `std::map< const char *, PrivateTagToValue, Itstr >` [PrivateMappingType](#)
- typedef `std::map< PrivateTag, const char * >` [PrivateTagToValue](#)
- typedef `PrivateTagToValue::value_type` [PrivateTagToValueValueType](#)
- typedef `PublicMappingType::const_iterator` [PublicConstIterator](#)
- typedef `std::map< const char *, PublicTagToValue, Itstr >` [PublicMappingType](#)
- typedef `std::map< Tag, const char * >` [PublicTagToValue](#)
- typedef `PublicTagToValue::value_type` [PublicTagToValueValueType](#)
- typedef `std::set< std::string >` [ValuesType](#)

Public Member Functions

- [StrictScanner2](#) ()
- [~StrictScanner2](#) () override
- bool [AddPrivateTag](#) ([PrivateTag](#) const &pt)
- bool [AddPublicTag](#) ([Tag](#) const &t)
Add a tag that will need to be read. Those are root level tags.
- bool [AddSkipTag](#) ([Tag](#) const &t)
Add a tag that will need to be skipped. Those are root level skip tags.
- [PublicConstIterator](#) [Begin](#) () const
- void [ClearPrivateTags](#) ()
- void [ClearPublicTags](#) ()

- void [ClearSkipTags](#) ()
- [PublicConstIterator End](#) () const
- [Directory::FilenameType GetAllFileNamesFromPrivateTagToValue](#) ([PrivateTag](#) const &pt, const char *valueref) const
- [Directory::FilenameType GetAllFileNamesFromPublicTagToValue](#) ([Tag](#) const &t, const char *valueref) const
- const char * [GetFilenameFromPrivateTagToValue](#) ([PrivateTag](#) const &pt, const char *valueref) const
- const char * [GetFilenameFromPublicTagToValue](#) ([Tag](#) const &t, const char *valueref) const
- [Directory::FilenameType](#) const & [GetFileNames](#) () const
Return the list of filenames.
- [Directory::FilenameType GetKeys](#) () const
- [PrivateTagToValue](#) const & [GetMappingFromPrivateTagToValue](#) ([PrivateTag](#) const &pt, const char *value) const
- [PublicTagToValue](#) const & [GetMappingFromPublicTagToValue](#) ([Tag](#) const &t, const char *value) const
- [PrivateTagToValue](#) const & [GetPrivateMapping](#) (const char *filename) const
- [PrivateMappingType](#) const & [GetPrivateMappings](#) () const
- [Directory::FilenameType GetPrivateOrderedValues](#) ([PrivateTag](#) const &pt) const
- const char * [GetPrivateValue](#) (const char *filename, [PrivateTag](#) const &t) const
- [ValueType](#) [GetPrivateValues](#) ([PrivateTag](#) const &pt) const
- [PublicTagToValue](#) const & [GetPublicMapping](#) (const char *filename) const
Get the std::map mapping filenames to value for file 'filename'.
- [PublicMappingType](#) const & [GetPublicMappings](#) () const
- [Directory::FilenameType GetPublicOrderedValues](#) ([Tag](#) const &t) const
- const char * [GetPublicValue](#) (const char *filename, [Tag](#) const &t) const
- [ValueType](#) [GetPublicValues](#) ([Tag](#) const &t) const
Get all the values found (in lexicographic order) associated with [Tag](#) 't'.
- [ValueType](#) const & [GetValues](#) () const
Get all the values found (in lexicographic order)
- bool [IsKey](#) (const char *filename) const
- void [Print](#) (std::ostream &os) const override
Print result.
- void [PrintTable](#) (std::ostream &os, bool header=false) const
Print result as CSV table.
- [PrivateConstIterator PrivateBegin](#) () const
- [PrivateConstIterator PrivateEnd](#) () const
- bool [Scan](#) ([Directory::FilenameType](#) const &filenames)
Start the scan !

Public Member Functions inherited from [gdcm::Subject](#)

- [Subject](#) ()
- [~Subject](#) () override
- unsigned long [AddObserver](#) (const [Event](#) &event, [Command](#) *)
- unsigned long [AddObserver](#) (const [Event](#) &event, [Command](#) *) const
- [Command](#) * [GetCommand](#) (unsigned long tag)
- bool [HasObserver](#) (const [Event](#) &event) const
- void [InvokeEvent](#) (const [Event](#) &)
- void [InvokeEvent](#) (const [Event](#) &) const
- void [RemoveAllObservers](#) ()
- void [RemoveObserver](#) (unsigned long tag)

Public Member Functions inherited from [gdcm::Object](#)

- [Object](#) ()
- [Object](#) (const [Object](#) &)
Special requirement for copy/cstor, assignment operator.
- virtual [~Object](#) ()
- void [operator=](#) (const [Object](#) &)

Static Public Member Functions

- static [SmartPointer](#)< [StrictScanner2](#) > [New](#) ()
for wrapped language: instantiate a reference counted object

Protected Member Functions

- void [ProcessPrivateTag](#) ([StringFilter](#) &sf, const char *filename)
- void [ProcessPublicTag](#) ([StringFilter](#) &sf, const char *filename)

Protected Member Functions inherited from [gdcm::Object](#)

- void [Register](#) ()
- void [UnRegister](#) ()

Friends

- std::ostream & [operator<<](#) (std::ostream &_os, const [StrictScanner2](#) &s)

10.294.1 Detailed Description

[StrictScanner2](#).

This filter is meant for quickly browsing a [FileSet](#) (a set of files on disk). Special consideration are taken so as to read the minimum amount of information in each file in order to retrieve the user specified set of DICOM [Attribute](#).

This filter is dealing with both VRASCII and VRBINARY element, thanks to the help of [StringFilter](#)

Warning

IMPORTANT In case of file where tags are not ordered (illegal as per DICOM specification), the output will be missing information

Note

implementation details. All values are stored in a std::set of std::string. Then the address of the cstring underlying the std::string is used in the std::map.

This class implement the Subject/Observer pattern trigger the following events:

- [ProgressEvent](#)
- [StartEvent](#)
- [EndEvent](#)

10.294.2 Member Typedef Documentation

10.294.2.1 PrivateConstIterator

```
typedef PrivateMappingType::const_iterator gdcm::StrictScanner2::PrivateConstIterator
```

10.294.2.2 PrivateMappingType

```
typedef std::map<const char *, PrivateTagToValue, ltstr> gdcm::StrictScanner2::PrivateMappingType
```

10.294.2.3 PrivateTagToValue

```
typedef std::map<PrivateTag, const char *> gdcm::StrictScanner2::PrivateTagToValue
```

10.294.2.4 PrivateTagToValueValueType

```
typedef PrivateTagToValue::value_type gdcm::StrictScanner2::PrivateTagToValueValueType
```

10.294.2.5 PublicConstIterator

```
typedef PublicMappingType::const_iterator gdcm::StrictScanner2::PublicConstIterator
```

10.294.2.6 PublicMappingType

```
typedef std::map<const char *, PublicTagToValue, ltstr> gdcm::StrictScanner2::PublicMappingType
```

10.294.2.7 PublicTagToValue

```
typedef std::map<Tag, const char *> gdcm::StrictScanner2::PublicTagToValue
```

struct to map a filename to a value Implementation note: all std::map in this class will be using const char * and not std::string since we are pointing to existing std::string (held in a std::vector) this avoid an extra copy of the byte array. [Tag](#) are used as [Tag](#) class since sizeof(tag) <= sizeof(pointer)

10.294.2.8 PublicTagToValueValueType

```
typedef PublicTagToValue::value_type gdcm::StrictScanner2::PublicTagToValueValueType
```

10.294.2.9 ValueType

```
typedef std::set<std::string> gdcm::StrictScanner2::ValueType
```

10.294.3 Constructor & Destructor Documentation

10.294.3.1 StrictScanner2()

```
gdcm::StrictScanner2::StrictScanner2 () [inline]
```

Referenced by [New\(\)](#), and [operator<<](#).

10.294.3.2 ~StrictScanner2()

```
gdcm::StrictScanner2::~~StrictScanner2 () [override]
```

10.294.4 Member Function Documentation

10.294.4.1 AddPrivateTag()

```
bool gdcm::StrictScanner2::AddPrivateTag (  
    PrivateTag const & pt)
```

10.294.4.2 AddPublicTag()

```
bool gdcm::StrictScanner2::AddPublicTag (  
    Tag const & t)
```

Add a tag that will need to be read. Those are root level tags.

10.294.4.3 AddSkipTag()

```
bool gdcm::StrictScanner2::AddSkipTag (  
    Tag const & t)
```

Add a tag that will need to be skipped. Those are root level skip tags.

10.294.4.4 Begin()

```
PublicConstIterator gdcm::StrictScanner2::Begin () const [inline]
```


10.294.4.5 ClearPrivateTags()

```
void gdcm::StrictScanner2::ClearPrivateTags ()
```

10.294.4.6 ClearPublicTags()

```
void gdcm::StrictScanner2::ClearPublicTags ()
```

10.294.4.7 ClearSkipTags()

```
void gdcm::StrictScanner2::ClearSkipTags ()
```

10.294.4.8 End()

```
PublicConstIterator gdcm::StrictScanner2::End () const [inline]
```

10.294.4.9 GetAllFileNamesFromPrivateTagToValue()

```
Directory::FileNamesType gdcm::StrictScanner2::GetAllFileNamesFromPrivateTagToValue (  
    PrivateTag const & pt,  
    const char * valueref) const
```

10.294.4.10 GetAllFileNamesFromPublicTagToValue()

```
Directory::FileNamesType gdcm::StrictScanner2::GetAllFileNamesFromPublicTagToValue (  
    Tag const & t,  
    const char * valueref) const
```

Will loop over all files and return a vector of std::strings of filenames where value match the reference value 'valueref'

10.294.4.11 GetFilenameFromPrivateTagToValue()

```
const char * gdcm::StrictScanner2::GetFilenameFromPrivateTagToValue (  
    PrivateTag const & pt,  
    const char * valueref) const
```

10.294.4.12 GetFilenameFromPublicTagToValue()

```
const char * gdcm::StrictScanner2::GetFilenameFromPublicTagToValue (  
    Tag const & t,  
    const char * valueref) const
```

Will loop over all files and return the first file where value match the reference value 'valueref'

10.294.4.13 GetFilenames()

```
Directory::FilenamesType const & gdc::StrictScanner2::GetFilenames () const [inline]
```

Return the list of filenames.

10.294.4.14 GetKeys()

```
Directory::FilenamesType gdc::StrictScanner2::GetKeys () const
```

Return the list of filename that are key in the internal map, which means those filename were properly parsed

10.294.4.15 GetMappingFromPrivateTagToValue()

```
PrivateTagToValue const & gdc::StrictScanner2::GetMappingFromPrivateTagToValue (  
    PrivateTag const & pt,  
    const char * value) const
```

10.294.4.16 GetMappingFromPublicTagToValue()

```
PublicTagToValue const & gdc::StrictScanner2::GetMappingFromPublicTagToValue (  
    Tag const & t,  
    const char * value) const
```

See GetFilenameFromTagToValue(). This is simply GetFilenameFromTagToValue followed

10.294.4.17 GetPrivateMapping()

```
PrivateTagToValue const & gdc::StrictScanner2::GetPrivateMapping (  
    const char * filename) const
```

10.294.4.18 GetPrivateMappings()

```
PrivateMappingType const & gdc::StrictScanner2::GetPrivateMappings () const [inline]
```

10.294.4.19 GetPrivateOrderedValues()

```
Directory::FilenamesType gdc::StrictScanner2::GetPrivateOrderedValues (  
    PrivateTag const & pt) const
```

10.294.4.20 GetPrivateValue()

```
const char * gdcmm::StrictScanner2::GetPrivateValue (
    const char * filename,
    PrivateTag const & t) const
```

10.294.4.21 GetPrivateValues()

```
ValuesType gdcmm::StrictScanner2::GetPrivateValues (
    PrivateTag const & pt) const
```

Get all the values found (in lexicographic order) associated with [PrivateTag](#) 'pt'

10.294.4.22 GetPublicMapping()

```
PublicTagToValue const & gdcmm::StrictScanner2::GetPublicMapping (
    const char * filename) const
```

Get the std::map mapping filenames to value for file 'filename'.

10.294.4.23 GetPublicMappings()

```
PublicMappingType const & gdcmm::StrictScanner2::GetPublicMappings () const [inline]
```

Mappings are the mapping from a particular tag to the map, mapping filename to value:

10.294.4.24 GetPublicOrderedValues()

```
Directory::FileNamesType gdcmm::StrictScanner2::GetPublicOrderedValues (
    Tag const & t) const
```

Get all the values found (in a vector) associated with [Tag](#) 't' This function is identical to `GetValues`, but is accessible from the wrapped layer (python, C#, java)

10.294.4.25 GetPublicValue()

```
const char * gdcmm::StrictScanner2::GetPublicValue (
    const char * filename,
    Tag const & t) const
```

Retrieve the value found for tag: t associated with file: filename This is meant for a single short call. If multiple calls (multiple tags) should be done, prefer the `GetMapping` function, and then reuse the `TagToValue` hash table.

Warning

[Tag](#) 't' should have been added via `AddTag()` prior to the `Scan()` call !

10.294.4.26 GetPublicValues()

```
ValueType gdcmm::StrictScanner2::GetPublicValues (
    Tag const & t) const
```

Get all the values found (in lexicographic order) associated with [Tag](#) 't'.

10.294.4.27 GetValues()

```
ValueType const & gdcmm::StrictScanner2::GetValues () const [inline]
```

Get all the values found (in lexicographic order)

10.294.4.28 IsKey()

```
bool gdcmm::StrictScanner2::IsKey (
    const char * filename) const
```

Check if filename is a key in the Mapping table. returns true only if file can be found, which means the file was indeed a DICOM file that could be processed

10.294.4.29 New()

```
SmartPointer< StrictScanner2 > gdcmm::StrictScanner2::New () [inline], [static]
```

for wrapped language: instantiate a reference counted object

References [StrictScanner2\(\)](#).

10.294.4.30 Print()

```
void gdcmm::StrictScanner2::Print (
    std::ostream & os) const [override], [virtual]
```

Print result.

Reimplemented from [gdcmm::Object](#).

Referenced by [operator<<](#).

10.294.4.31 PrintTable()

```
void gdcmm::StrictScanner2::PrintTable (
    std::ostream & os,
    bool header = false) const
```

Print result as CSV table.

10.294.4.32 PrivateBegin()

```
PrivateConstIterator gdcm::StrictScanner2::PrivateBegin () const [inline]
```

10.294.4.33 PrivateEnd()

```
PrivateConstIterator gdcm::StrictScanner2::PrivateEnd () const [inline]
```

10.294.4.34 ProcessPrivateTag()

```
void gdcm::StrictScanner2::ProcessPrivateTag (  
    StringFilter & sf,  
    const char * filename) [protected]
```

10.294.4.35 ProcessPublicTag()

```
void gdcm::StrictScanner2::ProcessPublicTag (  
    StringFilter & sf,  
    const char * filename) [protected]
```

10.294.4.36 Scan()

```
bool gdcm::StrictScanner2::Scan (  
    Directory::FileNamesType const & filenames)
```

Start the scan !

10.294.5 Friends And Related Symbol Documentation

10.294.5.1 operator<<

```
std::ostream & operator<< (  
    std::ostream & _os,  
    const StrictScanner2 & s) [friend]
```

References [StrictScanner2\(\)](#), and [Print\(\)](#).

The documentation for this class was generated from the following file:


- [gdcmStrictScanner2.h](#)

10.295 `gdcm::String< TDelimiter, TMaxLength, TPadChar >` Class Template Reference


[String.](#)

```
#include <gdcmString.h>
```

Inheritance diagram for `gdcm::String< TDelimiter, TMaxLength, TPadChar >`:



Collaboration diagram for `gdcm::String< TDelimiter, TMaxLength, TPadChar >`:



Public Types

- typedef `std::string::const_iterator` [const_iterator](#)
- typedef `std::string::const_reference` [const_reference](#)
- typedef `std::string::const_reverse_iterator` [const_reverse_iterator](#)
- typedef `std::string::difference_type` [difference_type](#)

- typedef std::string::iterator [iterator](#)
- typedef std::string::pointer [pointer](#)
- typedef std::string::reference [reference](#)
- typedef std::string::reverse_iterator [reverse_iterator](#)
- typedef std::string::size_type [size_type](#)
- typedef std::string::value_type [value_type](#)

Public Member Functions

- [String](#) ()
String constructors.
- [String](#) (const std::string &s, [size_type](#) pos=0, [size_type](#) n=npos)
- [String](#) (const [value_type](#) *s)
- [String](#) (const [value_type](#) *s, [size_type](#) n)
- bool [IsValid](#) () const
return if string is valid
- [operator const char *](#) () const
WARNING: Trailing \0 might be lost in this operation:
- std::string [Trim](#) () const
- [gdcmm::String](#)< TDelimiter, TMaxLength, TPadChar > [Truncate](#) () const

Static Public Member Functions

- static std::string [Trim](#) (const char *input)

10.295.1 Detailed Description

```
template<char TDelimiter = '\\', unsigned int TMaxLength = 64, char TPadChar = ' '>
class gdcmm::String< TDelimiter, TMaxLength, TPadChar >
```

[String](#).

Note

TDelimiter template parameter is used to separate multiple [String](#) (VM1 >) TMaxLength is only a hint. No one actually respect the max length TPadChar is the string padding (0 or space)

10.295.2 Member Typedef Documentation

10.295.2.1 const_iterator

```
template<char TDelimiter = '\\', unsigned int TMaxLength = 64, char TPadChar = ' '>
typedef std::string::const_iterator gdcmm::String< TDelimiter, TMaxLength, TPadChar >::const_↵
iterator
```

10.295.2.2 const_reference

```
template<char TDelimiter = '\\', unsigned int TMaxLength = 64, char TPadChar = ' '>
typedef std::string::const_reference gdcm::String< TDelimiter, TMaxLength, TPadChar >::const_↵
reference
```

10.295.2.3 const_reverse_iterator

```
template<char TDelimiter = '\\', unsigned int TMaxLength = 64, char TPadChar = ' '>
typedef std::string::const_reverse_iterator gdcm::String< TDelimiter, TMaxLength, TPadChar >↵
::const_reverse_iterator
```

10.295.2.4 difference_type

```
template<char TDelimiter = '\\', unsigned int TMaxLength = 64, char TPadChar = ' '>
typedef std::string::difference_type gdcm::String< TDelimiter, TMaxLength, TPadChar >::difference↵
_type
```

10.295.2.5 iterator

```
template<char TDelimiter = '\\', unsigned int TMaxLength = 64, char TPadChar = ' '>
typedef std::string::iterator gdcm::String< TDelimiter, TMaxLength, TPadChar >::iterator
```

10.295.2.6 pointer

```
template<char TDelimiter = '\\', unsigned int TMaxLength = 64, char TPadChar = ' '>
typedef std::string::pointer gdcm::String< TDelimiter, TMaxLength, TPadChar >::pointer
```

10.295.2.7 reference

```
template<char TDelimiter = '\\', unsigned int TMaxLength = 64, char TPadChar = ' '>
typedef std::string::reference gdcm::String< TDelimiter, TMaxLength, TPadChar >::reference
```

10.295.2.8 reverse_iterator

```
template<char TDelimiter = '\\', unsigned int TMaxLength = 64, char TPadChar = ' '>
typedef std::string::reverse_iterator gdcm::String< TDelimiter, TMaxLength, TPadChar >::reverse↵
_iterator
```

10.295.2.9 size_type

```
template<char TDelimiter = '\\', unsigned int TMaxLength = 64, char TPadChar = ' '>
typedef std::string::size_type gdcm::String< TDelimiter, TMaxLength, TPadChar >::size_type
```


10.295.2.10 value_type

```
template<char TDelimiter = '\\', unsigned int TMaxLength = 64, char TPadChar = ' '>
typedef std::string::value_type gdcm::String< TDelimiter, TMaxLength, TPadChar >::value_type
```

10.295.3 Constructor & Destructor Documentation

10.295.3.1 String() [1/4]

```
template<char TDelimiter = '\\', unsigned int TMaxLength = 64, char TPadChar = ' '>
gdcm::String< TDelimiter, TMaxLength, TPadChar >::String () [inline]
```

[String](#) constructors.

10.295.3.2 String() [2/4]

```
template<char TDelimiter = '\\', unsigned int TMaxLength = 64, char TPadChar = ' '>
gdcm::String< TDelimiter, TMaxLength, TPadChar >::String (
    const value\_type * s) [inline]
```

10.295.3.3 String() [3/4]

```
template<char TDelimiter = '\\', unsigned int TMaxLength = 64, char TPadChar = ' '>
gdcm::String< TDelimiter, TMaxLength, TPadChar >::String (
    const value\_type * s,
    size\_type n) [inline]
```

10.295.3.4 String() [4/4]

```
template<char TDelimiter = '\\', unsigned int TMaxLength = 64, char TPadChar = ' '>
gdcm::String< TDelimiter, TMaxLength, TPadChar >::String (
    const std::string & s,
    size\_type pos = 0,
    size\_type n = npos) [inline]
```

10.295.4 Member Function Documentation

10.295.4.1 IsValid()

```
template<char TDelimiter = '\\', unsigned int TMaxLength = 64, char TPadChar = ' '>
bool gdcm::String< TDelimiter, TMaxLength, TPadChar >::IsValid () const [inline]
```

return if string is valid

Referenced by [gdcm::String< '\\', 16 >::Truncate\(\)](#).

10.295.4.2 operator const char *()

```
template<char TDelimiter = '\\', unsigned int TMaxLength = 64, char TPadChar = ' '>
gdcm::String< TDelimiter, TMaxLength, TPadChar >::operator const char * () const [inline]
```

WARNING: Trailing \0 might be lost in this operation:

10.295.4.3 Trim() [1/2]

```
template<char TDelimiter = '\\', unsigned int TMaxLength = 64, char TPadChar = ' '>
std::string gdcm::String< TDelimiter, TMaxLength, TPadChar >::Trim () const [inline]
```

Trim function is required to return a std::string object, otherwise we could not create a [gdcm::String](#) object with an odd number of bytes...

10.295.4.4 Trim() [2/2]

```
template<char TDelimiter = '\\', unsigned int TMaxLength = 64, char TPadChar = ' '>
std::string gdcm::String< TDelimiter, TMaxLength, TPadChar >::Trim (
    const char * input) [inline], [static]
```

10.295.4.5 Truncate()

```
template<char TDelimiter = '\\', unsigned int TMaxLength = 64, char TPadChar = ' '>
gdcm::String< TDelimiter, TMaxLength, TPadChar > gdcm::String< TDelimiter, TMaxLength, TPadChar
>::Truncate () const [inline]
```

The documentation for this class was generated from the following file:

- [gdcmString.h](#)

10.296 gdcm::StringFilter Class Reference

[StringFilter](#).

```
#include <gdcmStringFilter.h>
```

Public Member Functions

- [StringFilter](#) ()
- [~StringFilter](#) ()
- bool [ExecuteQuery](#) (std::string const &query, std::string &value) const
- std::string [FromString](#) (const [Tag](#) &t, const char *value, size_t len)
Convert to string the char array defined by the pair (value,len)
- [File](#) & [GetFile](#) ()
- const [File](#) & [GetFile](#) () const
- void [SetDicts](#) (const [Dicts](#) &dicts)
Allow user to pass in there own dicts.
- void [SetFile](#) (const [File](#) &f)
Set/Get File.
- std::string [ToString](#) (const [DataElement](#) &de) const
- std::string [ToString](#) (const [PrivateTag](#) &t) const
- std::string [ToString](#) (const [Tag](#) &t) const
Directly from a Tag:
- std::pair< std::string, std::string > [ToStringPair](#) (const [DataElement](#) &de) const
- std::pair< std::string, std::string > [ToStringPair](#) (const [Tag](#) &t) const
Directly from a Tag:
- void [UseDictAlways](#) (bool)

Protected Member Functions

- bool [ExecuteQuery](#) (std::string const &query, [DataSet](#) const &ds, std::string &value) const
- std::pair< std::string, std::string > [ToStringPair](#) (const [Tag](#) &t, [DataSet](#) const &ds) const

10.296.1 Detailed Description

[StringFilter](#).

[StringFilter](#) is the class that make gdcm2.x looks more like gdcm1 and transform the binary blob contained in a [DataElement](#) into a string, typically this is a nice feature to have for wrapped language

Examples

[DumpVisusChange.cxx](#), [ReadAndPrintAttributes.cxx](#), and [SimplePrintPatientName.cs](#).

10.296.2 Constructor & Destructor Documentation

10.296.2.1 StringFilter()

```
gdcm::StringFilter::StringFilter ()
```

10.296.2.2 ~StringFilter()

```
gdcM::StringFilter::~~StringFilter ()
```

10.296.3 Member Function Documentation

10.296.3.1 ExecuteQuery() [1/2]

```
bool gdcM::StringFilter::ExecuteQuery (
    std::string const & query,
    DataSet const & ds,
    std::string & value) const [protected]
```

10.296.3.2 ExecuteQuery() [2/2]

```
bool gdcM::StringFilter::ExecuteQuery (
    std::string const & query,
    std::string & value) const
```

Execute the XPATH query to find a value (as string) return false when attribute is not found (or an error in the XPATH query) You need to make sure that your XPATH query is syntactically correct

10.296.3.3 FromString()

```
std::string gdcM::StringFilter::FromString (
    const Tag & t,
    const char * value,
    size_t len)
```

Convert to string the char array defined by the pair (value,len)

10.296.3.4 GetFile() [1/2]

```
File & gdcM::StringFilter::GetFile () [inline]
```

10.296.3.5 GetFile() [2/2]

```
const File & gdcM::StringFilter::GetFile () const [inline]
```

10.296.3.6 SetDicts()

```
void gdcM::StringFilter::SetDicts (
    const Dicts & dicts)
```

Allow user to pass in there own dicts.

10.296.3.7 SetFile()

```
void gdcm::StringFilter::SetFile (
    const File & f) [inline]
```

Set/Get [File](#).

Examples

[DumpVisusChange.cxx](#), [ReadAndPrintAttributes.cxx](#), and [SimplePrintPatientName.cs](#).

10.296.3.8 ToString() [1/3]

```
std::string gdcm::StringFilter::ToString (
    const DataElement & de) const
```

Convert to string the [ByteValue](#) contained in a [DataElement](#). The [DataElement](#) must be coming from the actual [DataSet](#) associated with [File](#) (see [SetFile](#)).

Examples

[DumpVisusChange.cxx](#), [ReadAndPrintAttributes.cxx](#), and [SimplePrintPatientName.cs](#).

10.296.3.9 ToString() [2/3]

```
std::string gdcm::StringFilter::ToString (
    const PrivateTag & t) const
```

10.296.3.10 ToString() [3/3]

```
std::string gdcm::StringFilter::ToString (
    const Tag & t) const
```

Directly from a [Tag](#):

10.296.3.11 ToStringPair() [1/3]

```
std::pair< std::string, std::string > gdcm::StringFilter::ToStringPair (
    const DataElement & de) const
```

Convert to string the [ByteValue](#) contained in a [DataElement](#) the returned elements are: pair.first : the name as found in the dictionary of [DataElement](#) pari.second : the value encoded into a string (US,UL...) are properly converted

Examples

[ReadAndPrintAttributes.cxx](#).

10.296.3.12 ToStringPair() [2/3]

```
std::pair< std::string, std::string > gdcM::StringFilter::ToStringPair (
    const Tag & t) const
```

Directly from a [Tag](#):

10.296.3.13 ToStringPair() [3/3]

```
std::pair< std::string, std::string > gdcM::StringFilter::ToStringPair (
    const Tag & t,
    DataSet const & ds) const [protected]
```

10.296.3.14 UseDictAlways()

```
void gdcM::StringFilter::UseDictAlways (
    bool ) [inline]
```

The documentation for this class was generated from the following file:

- [gdcMStringFilter.h](#)

10.297 gdcM::Study Class Reference

[Study](#).

```
#include <gdcMStudy.h>
```

Public Member Functions

- [Study](#) ()=default

10.297.1 Detailed Description

[Study](#).

10.297.2 Constructor & Destructor Documentation**10.297.2.1 Study()**

```
gdcM::Study::Study () [default]
```

The documentation for this class was generated from the following file:


- [gdcMStudy.h](#)

10.298 gdcmm::Subject Class Reference


[Subject](#).

```
#include <gdcmmSubject.h>
```

Inheritance diagram for gdcmm::Subject:



Collaboration diagram for gdcmm::Subject:



Public Member Functions

- [Subject](#) ()
- [~Subject](#) () override
- unsigned long [AddObserver](#) (const [Event](#) &event, [Command](#) *)
- unsigned long [AddObserver](#) (const [Event](#) &event, [Command](#) *) const
- [Command](#) * [GetCommand](#) (unsigned long tag)

- bool [HasObserver](#) (const [Event](#) &event) const
- void [InvokeEvent](#) (const [Event](#) &)
- void [InvokeEvent](#) (const [Event](#) &) const
- void [RemoveAllObservers](#) ()
- void [RemoveObserver](#) (unsigned long tag)

Public Member Functions inherited from [gdcm::Object](#)

- [Object](#) ()
- [Object](#) (const [Object](#) &)
Special requirement for copy/cstor, assignment operator.
- virtual [~Object](#) ()
- void [operator=](#) (const [Object](#) &)
- virtual void [Print](#) (std::ostream &) const

Additional Inherited Members

Protected Member Functions inherited from [gdcm::Object](#)

- void [Register](#) ()
- void [UnRegister](#) ()

10.298.1 Detailed Description

[Subject](#).

See also

[Command Event](#)

Examples

[BasicAnonymizer.cs](#), [Cleaner.cs](#), [ClinicalTrialIdentificationWorkflow.cs](#), [ScanDirectory.cs](#), and [SimpleScanner.cxx](#).

10.298.2 Constructor & Destructor Documentation

10.298.2.1 [Subject\(\)](#)

```
gdcm::Subject::Subject ()
```

Referenced by [gdcm::Command::Execute\(\)](#), and [gdcm::Command::Execute\(\)](#).

10.298.2.2 ~Subject()

```
gdcmm::Subject::~~Subject () [override]
```

10.298.3 Member Function Documentation

10.298.3.1 AddObserver() [1/2]

```
unsigned long gdcmm::Subject::AddObserver (
    const Event & event,
    Command * )
```

Allow people to add/remove/invoke observers (callbacks) to any GDCM object. This is an implementation of the subject/observer design pattern. An observer is added by specifying an event to respond to and an [gdcmm::Command](#) to execute. It returns an unsigned long tag which can be used later to remove the event or retrieve the command. The memory for the [Command](#) becomes the responsibility of this object, so don't pass the same instance of a command to two different objects

10.298.3.2 AddObserver() [2/2]

```
unsigned long gdcmm::Subject::AddObserver (
    const Event & event,
    Command * ) const
```

10.298.3.3 GetCommand()

```
Command * gdcmm::Subject::GetCommand (
    unsigned long tag)
```

Get the command associated with the given tag. NOTE: This returns a pointer to a [Command](#), but it is safe to assign this to a [Command::Pointer](#). Since [Command](#) inherits from [LightObject](#), at this point in the code, only a pointer or a reference to the [Command](#) can be used.

10.298.3.4 HasObserver()

```
bool gdcmm::Subject::HasObserver (
    const Event & event) const
```

Return true if an observer is registered for this event.

10.298.3.5 InvokeEvent() [1/2]

```
void gdcmm::Subject::InvokeEvent (
    const Event & )
```

Call Execute on all the Commands observing this event id.

10.298.3.6 InvokeEvent() [2/2]

```
void gdcM::Subject::InvokeEvent (
    const Event & ) const
```

Call Execute on all the Commands observing this event id. The actions triggered by this call doesn't modify this object.

10.298.3.7 RemoveAllObservers()

```
void gdcM::Subject::RemoveAllObservers ()
```

Remove all observers .

10.298.3.8 RemoveObserver()

```
void gdcM::Subject::RemoveObserver (
    unsigned long tag)
```

Remove the observer with this tag value.

The documentation for this class was generated from the following file:


- [gdcMSubject.h](#)

10.299 gdcM::Surface Class Reference


This class defines a SURFACE IE.

```
#include <gdcMSurface.h>
```

Inheritance diagram for gdcM::Surface:



Collaboration diagram for gdcm::Surface:



Public Types

- enum `STATES` {
`NO` = 0 ,
`YES` ,
`UNKNOWN` ,
`STATES_END` }
- enum `VIEWType` {
`SURFACE` = 0 ,
`WIREFRAME` ,
`POINTS` ,
`VIEWType_END` }

Enumeration for Recommended Presentation [Type](#).

Public Member Functions

- `Surface` ()
- `~Surface` () override
- `SegmentHelper::BasicCodedEntry` & `GetAlgorithmFamily` ()
- `SegmentHelper::BasicCodedEntry` const & `GetAlgorithmFamily` () const
- const char * `GetAlgorithmName` () const
- const char * `GetAlgorithmVersion` () const
- const float * `GetAxisOfRotation` () const
- const float * `GetCenterOfRotation` () const
- `STATES` `GetFiniteVolume` () const
- `STATES` `GetManifold` () const
- float `GetMaximumPointDistance` () const
- float `GetMeanPointDistance` () const
- `MeshPrimitive` & `GetMeshPrimitive` ()
- `MeshPrimitive` const & `GetMeshPrimitive` () const
- unsigned long `GetNumberOfSurfacePoints` () const
- unsigned long `GetNumberOfVectors` () const
- `DataElement` & `GetPointCoordinatesData` ()

- const [DataElement](#) & [GetPointCoordinatesData](#) () const
- const float * [GetPointPositionAccuracy](#) () const
- const float * [GetPointsBoundingBoxCoordinates](#) () const
- [SegmentHelper::BasicCodedEntry](#) & [GetProcessingAlgorithm](#) ()
- [SegmentHelper::BasicCodedEntry](#) const & [GetProcessingAlgorithm](#) () const
- const unsigned short * [GetRecommendedDisplayCIELabValue](#) () const
- unsigned short [GetRecommendedDisplayCIELabValue](#) (const unsigned int idx) const
- unsigned short [GetRecommendedDisplayGrayscaleValue](#) () const
- float [GetRecommendedPresentationOpacity](#) () const
- [VIEWType](#) [GetRecommendedPresentationType](#) () const
- const char * [GetSurfaceComments](#) () const
- unsigned long [GetSurfaceNumber](#) () const
- bool [GetSurfaceProcessing](#) () const
- const char * [GetSurfaceProcessingDescription](#) () const
- float [GetSurfaceProcessingRatio](#) () const
- const float * [GetVectorAccuracy](#) () const
- [DataElement](#) & [GetVectorCoordinateData](#) ()
- const [DataElement](#) & [GetVectorCoordinateData](#) () const
- unsigned short [GetVectorDimensionality](#) () const
- void [SetAlgorithmFamily](#) ([SegmentHelper::BasicCodedEntry](#) const &BSE)
- void [SetAlgorithmName](#) (const char *str)
- void [SetAlgorithmVersion](#) (const char *str)
- void [SetAxisOfRotation](#) (const float *axis)
- void [SetCenterOfRotation](#) (const float *center)
- void [SetFiniteVolume](#) ([STATES](#) state)
- void [SetManifold](#) ([STATES](#) state)
- void [SetMaximumPointDistance](#) (float maximum)
- void [SetMeanPointDistance](#) (float average)
- void [SetMeshPrimitive](#) ([MeshPrimitive](#) const &mp)
- void [SetNumberOfSurfacePoints](#) (const unsigned long nb)
- void [SetNumberOfVectors](#) (const unsigned long nb)
- void [SetPointCoordinatesData](#) ([DataElement](#) const &de)
- void [SetPointPositionAccuracy](#) (const float *accuracies)
- void [SetPointsBoundingBoxCoordinates](#) (const float *coordinates)
- void [SetProcessingAlgorithm](#) ([SegmentHelper::BasicCodedEntry](#) const &BSE)
- void [SetRecommendedDisplayCIELabValue](#) (const std::vector< unsigned short > &vl)
- void [SetRecommendedDisplayCIELabValue](#) (const unsigned short vl, const unsigned int idx=0)
- void [SetRecommendedDisplayCIELabValue](#) (const unsigned short vl[3])
- void [SetRecommendedDisplayGrayscaleValue](#) (const unsigned short vl)
- void [SetRecommendedPresentationOpacity](#) (const float opacity)
- void [SetRecommendedPresentationType](#) ([VIEWType](#) type)
- void [SetSurfaceComments](#) (const char *comment)
- void [SetSurfaceNumber](#) (const unsigned long nb)
- void [SetSurfaceProcessing](#) (bool b)
- void [SetSurfaceProcessingDescription](#) (const char *description)
- void [SetSurfaceProcessingRatio](#) (const float ratio)
- void [SetVectorAccuracy](#) (const float *accuracy)
- void [SetVectorCoordinateData](#) ([DataElement](#) const &de)
- void [SetVectorDimensionality](#) (const unsigned short dim)

Public Member Functions inherited from [gdcm::Object](#)

- [Object](#) ()
- [Object](#) (const [Object](#) &)
Special requirement for copy/cstor, assignment operator.
- virtual [~Object](#) ()
- void [operator=](#) (const [Object](#) &)
- virtual void [Print](#) (std::ostream &) const

Static Public Member Functions

- static [STATES](#) [GetSTATES](#) (const char *state)
- static const char * [GetSTATESString](#) ([STATES](#) state)
- static [VIEWType](#) [GetVIEWType](#) (const char *type)
- static const char * [GetVIEWTypeString](#) ([VIEWType](#) type)

Additional Inherited Members

Protected Member Functions inherited from [gdcm::Object](#)

- void [Register](#) ()
- void [UnRegister](#) ()

10.299.1 Detailed Description

This class defines a SURFACE IE.

This members are taken from required surface mesh module attributes.

See also

PS 3.3 A.1.2.18 , A.57 and C.27

10.299.2 Member Enumeration Documentation

10.299.2.1 STATES

```
enum gdcm::Surface::STATES
```

Enumerator

NO	
YES	
UNKNOWN	
STATES_END	

10.299.2.2 VIEWType

enum `gdcm::Surface::VIEWType`

Enumeration for Recommended Presentation [Type](#).

See also

Tag(0x0066, 0x000D) and PS 3.3 C.27.1.1.3

Enumerator

SURFACE	
WIREFRAME	
POINTS	
VIEWType_END	

10.299.3 Constructor & Destructor Documentation

10.299.3.1 Surface()

`gdcm::Surface::Surface ()`

10.299.3.2 ~Surface()

`gdcm::Surface::~~Surface () [override]`

10.299.4 Member Function Documentation

10.299.4.1 GetAlgorithmFamily() [1/2]

`SegmentHelper::BasicCodedEntry & gdcm::Surface::GetAlgorithmFamily ()`

10.299.4.2 GetAlgorithmFamily() [2/2]

`SegmentHelper::BasicCodedEntry const & gdcm::Surface::GetAlgorithmFamily () const`

10.299.4.3 GetAlgorithmName()

`const char * gdcm::Surface::GetAlgorithmName () const`

10.299.4.4 GetAlgorithmVersion()

```
const char * gdcm::Surface::GetAlgorithmVersion () const
```

10.299.4.5 GetAxisOfRotation()

```
const float * gdcm::Surface::GetAxisOfRotation () const
```

Note

Pointer is null if undefined

10.299.4.6 GetCenterOfRotation()

```
const float * gdcm::Surface::GetCenterOfRotation () const
```

Note

Pointer is null if undefined

10.299.4.7 GetFiniteVolume()

```
STATES gdcm::Surface::GetFiniteVolume () const
```

10.299.4.8 GetManifold()

```
STATES gdcm::Surface::GetManifold () const
```

10.299.4.9 GetMaximumPointDistance()

```
float gdcm::Surface::GetMaximumPointDistance () const
```

10.299.4.10 GetMeanPointDistance()

```
float gdcm::Surface::GetMeanPointDistance () const
```

10.299.4.11 GetMeshPrimitive() [1/2]

```
MeshPrimitive & gdcm::Surface::GetMeshPrimitive ()
```

10.299.4.12 GetMeshPrimitive() [2/2]

```
MeshPrimitive const & gdcm::Surface::GetMeshPrimitive () const
```

10.299.4.13 GetNumberOfSurfacePoints()

```
unsigned long gdcm::Surface::GetNumberOfSurfacePoints () const
```

10.299.4.14 GetNumberOfVectors()

```
unsigned long gdcm::Surface::GetNumberOfVectors () const
```

10.299.4.15 GetPointCoordinatesData() [1/2]

```
DataElement & gdcm::Surface::GetPointCoordinatesData ()
```

10.299.4.16 GetPointCoordinatesData() [2/2]

```
const DataElement & gdcm::Surface::GetPointCoordinatesData () const
```

10.299.4.17 GetPointPositionAccuracy()

```
const float * gdcm::Surface::GetPointPositionAccuracy () const
```

Note

Pointer is null if undefined

10.299.4.18 GetPointsBoundingBoxCoordinates()

```
const float * gdcm::Surface::GetPointsBoundingBoxCoordinates () const
```

Note

Pointer is null if undefined

10.299.4.19 GetProcessingAlgorithm() [1/2]

```
SegmentHelper::BasicCodedEntry & gdcm::Surface::GetProcessingAlgorithm ()
```


10.299.4.20 GetProcessingAlgorithm() [2/2]

```
SegmentHelper::BasicCodedEntry const & gdcm::Surface::GetProcessingAlgorithm () const
```

10.299.4.21 GetRecommendedDisplayCIELabValue() [1/2]

```
const unsigned short * gdcm::Surface::GetRecommendedDisplayCIELabValue () const
```

10.299.4.22 GetRecommendedDisplayCIELabValue() [2/2]

```
unsigned short gdcm::Surface::GetRecommendedDisplayCIELabValue (  
    const unsigned int idx) const
```

10.299.4.23 GetRecommendedDisplayGrayscaleValue()

```
unsigned short gdcm::Surface::GetRecommendedDisplayGrayscaleValue () const
```

10.299.4.24 GetRecommendedPresentationOpacity()

```
float gdcm::Surface::GetRecommendedPresentationOpacity () const
```

10.299.4.25 GetRecommendedPresentationType()

```
VIEWType gdcm::Surface::GetRecommendedPresentationType () const
```

10.299.4.26 GetSTATES()

```
STATES gdcm::Surface::GetSTATES (  
    const char * state) [static]
```

10.299.4.27 GetSTATESString()

```
const char * gdcm::Surface::GetSTATESString (  
    STATES state) [static]
```

10.299.4.28 GetSurfaceComments()

```
const char * gdcm::Surface::GetSurfaceComments () const
```

10.299.4.29 GetSurfaceNumber()

```
unsigned long gdcm::Surface::GetSurfaceNumber () const
```

10.299.4.30 GetSurfaceProcessing()

```
bool gdcm::Surface::GetSurfaceProcessing () const
```

10.299.4.31 GetSurfaceProcessingDescription()

```
const char * gdcm::Surface::GetSurfaceProcessingDescription () const
```

10.299.4.32 GetSurfaceProcessingRatio()

```
float gdcm::Surface::GetSurfaceProcessingRatio () const
```

10.299.4.33 GetVectorAccuracy()

```
const float * gdcm::Surface::GetVectorAccuracy () const
```

10.299.4.34 GetVectorCoordinateData() [1/2]

```
DataElement & gdcm::Surface::GetVectorCoordinateData ()
```

10.299.4.35 GetVectorCoordinateData() [2/2]

```
const DataElement & gdcm::Surface::GetVectorCoordinateData () const
```

10.299.4.36 GetVectorDimensionality()

```
unsigned short gdcm::Surface::GetVectorDimensionality () const
```

10.299.4.37 GetVIEWType()

```
VIEWType gdcm::Surface::GetVIEWType (  
    const char * type) [static]
```

10.299.4.38 GetVIEWTypeString()

```
const char * gdcm::Surface::GetVIEWTypeString (
    VIEWType type) [static]
```

10.299.4.39 SetAlgorithmFamily()

```
void gdcm::Surface::SetAlgorithmFamily (
    SegmentHelper::BasicCodedEntry const & BSE)
```

10.299.4.40 SetAlgorithmName()

```
void gdcm::Surface::SetAlgorithmName (
    const char * str)
```

10.299.4.41 SetAlgorithmVersion()

```
void gdcm::Surface::SetAlgorithmVersion (
    const char * str)
```

10.299.4.42 SetAxisOfRotation()

```
void gdcm::Surface::SetAxisOfRotation (
    const float * axis)
```

10.299.4.43 SetCenterOfRotation()

```
void gdcm::Surface::SetCenterOfRotation (
    const float * center)
```

10.299.4.44 SetFiniteVolume()

```
void gdcm::Surface::SetFiniteVolume (
    STATES state)
```

10.299.4.45 SetManifold()

```
void gdcm::Surface::SetManifold (
    STATES state)
```

10.299.4.46 SetMaximumPointDistance()

```
void gdcM::Surface::SetMaximumPointDistance (
    float maximum)
```

10.299.4.47 SetMeanPointDistance()

```
void gdcM::Surface::SetMeanPointDistance (
    float average)
```

10.299.4.48 SetMeshPrimitive()

```
void gdcM::Surface::SetMeshPrimitive (
    MeshPrimitive const & mp)
```

References [gdcM::Object::SmartPointer](#).

10.299.4.49 SetNumberOfSurfacePoints()

```
void gdcM::Surface::SetNumberOfSurfacePoints (
    const unsigned long nb)
```

10.299.4.50 SetNumberOfVectors()

```
void gdcM::Surface::SetNumberOfVectors (
    const unsigned long nb)
```

10.299.4.51 SetPointCoordinatesData()

```
void gdcM::Surface::SetPointCoordinatesData (
    DataElement const & de)
```

10.299.4.52 SetPointPositionAccuracy()

```
void gdcM::Surface::SetPointPositionAccuracy (
    const float * accuracies)
```

10.299.4.53 SetPointsBoundingBoxCoordinates()

```
void gdcM::Surface::SetPointsBoundingBoxCoordinates (
    const float * coordinates)
```

10.299.4.54 SetProcessingAlgorithm()

```
void gdcm::Surface::SetProcessingAlgorithm (
    SegmentHelper::BasicCodedEntry const & BSE)
```

10.299.4.55 SetRecommendedDisplayCIELabValue() [1/3]

```
void gdcm::Surface::SetRecommendedDisplayCIELabValue (
    const std::vector< unsigned short > & vl)
```

10.299.4.56 SetRecommendedDisplayCIELabValue() [2/3]

```
void gdcm::Surface::SetRecommendedDisplayCIELabValue (
    const unsigned short vl,
    const unsigned int idx = 0)
```

10.299.4.57 SetRecommendedDisplayCIELabValue() [3/3]

```
void gdcm::Surface::SetRecommendedDisplayCIELabValue (
    const unsigned short vl[3])
```

10.299.4.58 SetRecommendedDisplayGrayscaleValue()

```
void gdcm::Surface::SetRecommendedDisplayGrayscaleValue (
    const unsigned short vl)
```

10.299.4.59 SetRecommendedPresentationOpacity()

```
void gdcm::Surface::SetRecommendedPresentationOpacity (
    const float opacity)
```

10.299.4.60 SetRecommendedPresentationType()

```
void gdcm::Surface::SetRecommendedPresentationType (
    VIEWType type)
```

10.299.4.61 SetSurfaceComments()

```
void gdcm::Surface::SetSurfaceComments (
    const char * comment)
```

10.299.4.62 SetSurfaceNumber()

```
void gdcM::Surface::SetSurfaceNumber (
    const unsigned long nb)
```

10.299.4.63 SetSurfaceProcessing()

```
void gdcM::Surface::SetSurfaceProcessing (
    bool b)
```

10.299.4.64 SetSurfaceProcessingDescription()

```
void gdcM::Surface::SetSurfaceProcessingDescription (
    const char * description)
```

10.299.4.65 SetSurfaceProcessingRatio()

```
void gdcM::Surface::SetSurfaceProcessingRatio (
    const float ratio)
```

10.299.4.66 SetVectorAccuracy()

```
void gdcM::Surface::SetVectorAccuracy (
    const float * accuracy)
```

10.299.4.67 SetVectorCoordinateData()

```
void gdcM::Surface::SetVectorCoordinateData (
    DataElement const & de)
```

10.299.4.68 SetVectorDimensionality()

```
void gdcM::Surface::SetVectorDimensionality (
    const unsigned short dim)
```

The documentation for this class was generated from the following file:

- [gdcMSurface.h](#)

10.300 gdcm::SurfaceHelper Class Reference

[SurfaceHelper](#).

```
#include <gdcmSurfaceHelper.h>
```

Public Types

- typedef std::vector< unsigned short > [ColorArray](#)

Static Public Member Functions

- template<typename T, typename U>
static std::vector< T > [RecommendedDisplayCIELabToRGB](#) (const [ColorArray](#) &CIELab, const U range←
Max=255)
Convert a DICOM CIE-Lab (after reading) color into RGB.
- template<typename U>
static std::vector< float > [RecommendedDisplayCIELabToRGB](#) (const [ColorArray](#) &CIELab, const U range←
Max=255)
Convert a DICOM CIE-Lab (after reading) color into RGB.
- template<typename T, typename U>
static [ColorArray](#) [RGBToRecommendedDisplayCIELab](#) (const std::vector< T > &RGB, const U rangeMax=255)
Convert a RGB color into DICOM CIE-Lab (ready to write).
- template<typename T, typename U>
static unsigned short [RGBToRecommendedDisplayGrayscale](#) (const std::vector< T > &RGB, const U range←
Max=255)
Convert a RGB color into DICOM grayscale (ready to write).

10.300.1 Detailed Description

[SurfaceHelper](#).

Helper class for [Surface](#) object

10.300.2 Member Typedef Documentation

10.300.2.1 ColorArray

```
typedef std::vector< unsigned short > gdcm::SurfaceHelper::ColorArray
```

10.300.3 Member Function Documentation

10.300.3.1 RecommendedDisplayCIELabToRGB() [1/2]

```
template<typename T, typename U>
std::vector< T > gdcm::SurfaceHelper::RecommendedDisplayCIELabToRGB (
    const ColorArray & CIELab,
    const U rangeMax = 255) [static]
```

Convert a DICOM CIE-Lab (after reading) color into RGB.

See also

PS 3.3 C.10.7.1.1

Parameters

<i>CIELab</i>	DICOM CIE-Lab array.
<i>rangeMax</i>	Max value of the RGB range.

Template Parameters

<i>T</i>	Type of CIELab components.
<i>U</i>	Type of rangeMax value.

References [gdcm_assert](#).

Referenced by [RecommendedDisplayCIELabToRGB\(\)](#).

10.300.3.2 RecommendedDisplayCIELabToRGB() [2/2]

```
template<typename U>
std::vector< float > gdcm::SurfaceHelper::RecommendedDisplayCIELabToRGB (
    const ColorArray & CIELab,
    const U rangeMax = 255) [static]
```

Convert a DICOM CIE-Lab (after reading) color into RGB.

See also

PS 3.3 C.10.7.1.1

Parameters

<i>CIELab</i>	DICOM CIE-Lab array.
<i>rangeMax</i>	Max value of the RGB range.

Template Parameters

<i>U</i>	Type of rangeMax value.
----------	-------------------------

References [RecommendedDisplayCIELabToRGB\(\)](#).

10.300.3.3 RGBToRecommendedDisplayCIELab()

```
template<typename T, typename U>
SurfaceHelper::ColorArray gdcm::SurfaceHelper::RGBToRecommendedDisplayCIELab (
    const std::vector< T > & RGB,
    const U rangeMax = 255) [static]
```

Convert a RGB color into DICOM CIE-Lab (ready to write).

See also

PS 3.3 C.10.7.1.1

Parameters

<i>RGB</i>	RGB array.
<i>rangeMax</i>	Max value of the RGB range.

Template Parameters

<i>T</i>	Type of RGB components.
<i>U</i>	Type of rangeMax value.

References [gdcm_assert](#).

10.300.3.4 RGBToRecommendedDisplayGrayscale()

```
template<typename T, typename U>
unsigned short gdcm::SurfaceHelper::RGBToRecommendedDisplayGrayscale (
    const std::vector< T > & RGB,
    const U rangeMax = 255) [static]
```

Convert a RGB color into DICOM grayscale (ready to write).

See also

PS 3.3 C.27.1 tag(0062,000C)

Parameters

<i>RGB</i>	RGB array.
<i>rangeMax</i>	Max value of the RGB range.

Template Parameters

<i>T</i>	Type of RGB components.
<i>U</i>	Type of rangeMax value.

References [gdcm_assert](#).

The documentation for this class was generated from the following file:


- [gdcmSurfaceHelper.h](#)

10.301 gdcm::SurfaceReader Class Reference


This class defines a SURFACE IE reader.

```
#include <gdcmSurfaceReader.h>
```

Inheritance diagram for gdcm::SurfaceReader:



Collaboration diagram for gdcm::SurfaceReader:



Public Member Functions

- [SurfaceReader](#) ()
 - [~SurfaceReader](#) () override
 - unsigned long [GetNumberOfSurfaces](#) () const
 - bool [Read](#) () override
- Read.*

Public Member Functions inherited from [gdcm::SegmentReader](#)

- [SegmentReader](#) ()
- [~SegmentReader](#) () override
- [SegmentVector](#) [GetSegments](#) ()
- [SegmentVector](#) [GetSegments](#) () const

Public Member Functions inherited from [gdcm::Reader](#)

- [Reader](#) ()
- virtual [~Reader](#) ()
- bool [CanRead](#) () const
- [File](#) & [GetFile](#) ()
Set/Get File.
- const [File](#) & [GetFile](#) () const
Set/Get File.
- size_t [GetStreamCurrentPosition](#) () const
- bool [ReadSelectedPrivateTags](#) (std::set< [PrivateTag](#) > const &ptags, bool readvalues=true)
Will only read the specified selected private tags.
- bool [ReadSelectedTags](#) (std::set< [Tag](#) > const &tags, bool readvalues=true)
Will only read the specified selected tags.
- bool [ReadUpToTag](#) (const [Tag](#) &tag, std::set< [Tag](#) > const &skiptags=std::set< [Tag](#) >())
- void [SetFile](#) ([File](#) &file)
Set/Get File.
- void [SetFileName](#) (const char *filename_native)
- void [SetStream](#) (std::istream &input_stream)
Set the open-ed stream directly.

Protected Member Functions

- bool [ReadPointMacro](#) ([SmartPointer](#)< [Surface](#) > surface, const [DataSet](#) &surfaceDS)
- bool [ReadSurface](#) (const [Item](#) &surfaceItem, const unsigned long idx)
- bool [ReadSurfaces](#) ()

Protected Member Functions inherited from [gdcm::SegmentReader](#)

- bool [ReadSegment](#) (const [Item](#) &segmentItem, const unsigned int idx)
- bool [ReadSegments](#) ()

Protected Member Functions inherited from [gdcm::Reader](#)

- std::istream * [GetStreamPtr](#) () const
- bool [ReadDataSet](#) ()
- bool [ReadMetaInformation](#) ()
- bool [ReadPreamble](#) ()

Additional Inherited Members

Public Types inherited from [gdcm::SegmentReader](#)

- typedef std::vector< [SmartPointer](#)< [Segment](#) > > [SegmentVector](#)

Protected Types inherited from [gdcm::SegmentReader](#)

- typedef std::map< unsigned long, [SmartPointer< Segment > >](#) SegmentMap

Protected Attributes inherited from [gdcm::SegmentReader](#)

- [SegmentMap](#) Segments

Protected Attributes inherited from [gdcm::Reader](#)

- [SmartPointer< File >](#) F

10.301.1 Detailed Description

This class defines a SURFACE IE reader.

It reads surface mesh module attributes.

See also

PS 3.3 A.1.2.18 , A.57 and C.27

10.301.2 Constructor & Destructor Documentation

10.301.2.1 SurfaceReader()

```
gdcm::SurfaceReader::SurfaceReader ()
```

10.301.2.2 ~SurfaceReader()

```
gdcm::SurfaceReader::~~SurfaceReader () [override]
```

10.301.3 Member Function Documentation

10.301.3.1 GetNumberOfSurfaces()

```
unsigned long gdcm::SurfaceReader::GetNumberOfSurfaces () const
```

10.301.3.2 Read()

```
bool gdcm::SurfaceReader::Read () [override], [virtual]
```

Read.

Reimplemented from [gdcm::SegmentReader](#).

10.301.3.3 ReadPointMacro()

```
bool gdcm::SurfaceReader::ReadPointMacro (
    SmartPointer< Surface > surface,
    const DataSet & surfaceDS) [protected]
```

10.301.3.4 ReadSurface()

```
bool gdcm::SurfaceReader::ReadSurface (
    const Item & surfaceItem,
    const unsigned long idx) [protected]
```

10.301.3.5 ReadSurfaces()

```
bool gdcm::SurfaceReader::ReadSurfaces () [protected]
```

The documentation for this class was generated from the following file:

- [gdcmSurfaceReader.h](#)

10.302 gdcm::SurfaceWriter Class Reference


This class defines a SURFACE IE writer.

```
#include <gdcmSurfaceWriter.h>
```

Inheritance diagram for gdcm::SurfaceWriter:



Collaboration diagram for `gdcm::SurfaceWriter`:



Public Member Functions

- [SurfaceWriter](#) ()
 - [~SurfaceWriter](#) () override
 - unsigned long [GetNumberOfSurfaces](#) ()
 - void [SetNumberOfSurfaces](#) (const unsigned long nb)
 - bool [Write](#) () override
- Write.*

Public Member Functions inherited from [gdcm::SegmentWriter](#)

- [SegmentWriter](#) ()
- [~SegmentWriter](#) () override

- void [AddSegment](#) ([SmartPointer](#)< [Segment](#) > segment)
- unsigned int [GetNumberOfSegments](#) () const
- [SmartPointer](#)< [Segment](#) > [GetSegment](#) (const unsigned int idx=0) const
- [SegmentVector](#) & [GetSegments](#) ()
- const [SegmentVector](#) & [GetSegments](#) () const
- void [SetNumberOfSegments](#) (const unsigned int size)
- void [SetSegments](#) ([SegmentVector](#) &segments)

Public Member Functions inherited from [gdcm::Writer](#)

- [Writer](#) ()
- virtual [~Writer](#) ()
- void [CheckFileMetaInformationOff](#) ()
- void [CheckFileMetaInformationOn](#) ()
- [File](#) & [GetFile](#) ()
- void [SetCheckFileMetaInformation](#) (bool b)
Undocumented function, do not use (= leave default)
- void [SetFile](#) (const [File](#) &f)
Set/Get the DICOM file ([DataSet](#) + Header)
- void [SetFileName](#) (const char *filename_native)
Set the filename of DICOM file to write:
- void [SetStream](#) (std::ostream &output_stream)
Set user ostream buffer.

Protected Member Functions

- void [ComputeNumberOfSurfaces](#) ()
- bool [PrepareWrite](#) ()
- bool [PrepareWritePointMacro](#) ([SmartPointer](#)< [Surface](#) > surface, [DataSet](#) &surfaceDS, const [TransferSyntax](#) &ts)

Protected Member Functions inherited from [gdcm::SegmentWriter](#)

- bool [PrepareWrite](#) ()

Protected Member Functions inherited from [gdcm::Writer](#)

- bool [GetCheckFileMetaInformation](#) () const
- std::ostream * [GetStreamPtr](#) () const
- void [SetWriteDataSetOnly](#) (bool b)

Protected Attributes

- unsigned long [NumberOfSurfaces](#)

Protected Attributes inherited from [gdcm::SegmentWriter](#)

- [SegmentVector](#) [Segments](#)

Protected Attributes inherited from [gdcm::Writer](#)

- `std::ofstream` * [Ofstream](#)
- `std::ostream` * [Stream](#)

Additional Inherited Members

Public Types inherited from [gdcm::SegmentWriter](#)

- `typedef std::vector< SmartPointer< Segment > > SegmentVector`

10.302.1 Detailed Description

This class defines a SURFACE IE writer.

It writes surface mesh module attributes.

See also

PS 3.3 A.1.2.18 , A.57 and C.27

10.302.2 Constructor & Destructor Documentation

10.302.2.1 [SurfaceWriter\(\)](#)

```
gdcm::SurfaceWriter::SurfaceWriter ()
```

10.302.2.2 [~SurfaceWriter\(\)](#)

```
gdcm::SurfaceWriter::~~SurfaceWriter () [override]
```

10.302.3 Member Function Documentation

10.302.3.1 [ComputeNumberOfSurfaces\(\)](#)

```
void gdcm::SurfaceWriter::ComputeNumberOfSurfaces () [protected]
```

10.302.3.2 GetNumberOfSurfaces()

```
unsigned long gdcm::SurfaceWriter::GetNumberOfSurfaces ()
```

10.302.3.3 PrepareWrite()

```
bool gdcm::SurfaceWriter::PrepareWrite () [protected]
```

10.302.3.4 PrepareWritePointMacro()

```
bool gdcm::SurfaceWriter::PrepareWritePointMacro (  
    SmartPointer< Surface > surface,  
    DataSet & surfaceDS,  
    const TransferSyntax & ts) [protected]
```

10.302.3.5 SetNumberOfSurfaces()

```
void gdcm::SurfaceWriter::SetNumberOfSurfaces (  
    const unsigned long nb)
```

10.302.3.6 Write()

```
bool gdcm::SurfaceWriter::Write () [override], [virtual]
```

Write.

Reimplemented from [gdcm::SegmentWriter](#).

10.302.4 Member Data Documentation

10.302.4.1 NumberOfSurfaces

```
unsigned long gdcm::SurfaceWriter::NumberOfSurfaces [protected]
```

The documentation for this class was generated from the following file:

- [gdcmSurfaceWriter.h](#)

10.303 gdcm::SwapCode Class Reference

[SwapCode](#) representation.

```
#include <gdcmSwapCode.h>
```

Public Types

- enum [SwapCodeType](#) {
[Unknown](#) = 0 ,
[LittleEndian](#) = 1234 ,
[BigEndian](#) = 4321 ,
[BadLittleEndian](#) = 3412 ,
[BadBigEndian](#) = 2143 }

Public Member Functions

- [SwapCode](#) ([SwapCodeType](#) sc=[Unknown](#))
- [operator SwapCode::SwapCodeType](#) () const

Static Public Member Functions

- static const char * [GetSwapCodeString](#) ([SwapCode](#) const &sc)

Static Protected Member Functions

- static int [GetIndex](#) ([SwapCode](#) const &sc)

Friends

- std::ostream & [operator<<](#) (std::ostream &os, const [SwapCode](#) &sc)

10.303.1 Detailed Description

[SwapCode](#) representation.

Examples

[TestByteSwap.cxx](#).

10.303.2 Member Enumeration Documentation**10.303.2.1 SwapCodeType**

enum [gdcmm::SwapCode::SwapCodeType](#)

Enumerator

Unknown	
LittleEndian	
BigEndian	
BadLittleEndian	
BadBigEndian	

10.303.3 Constructor & Destructor Documentation

10.303.3.1 SwapCode()

```
gdcm::SwapCode::SwapCode (  
    SwapCodeType sc = Unknown) [inline]
```

References [Unknown](#).

Referenced by [GetIndex\(\)](#), [GetSwapCodeString\(\)](#), and [operator<<](#).

10.303.4 Member Function Documentation

10.303.4.1 GetIndex()

```
int gdcm::SwapCode::GetIndex (  
    SwapCode const & sc) [static], [protected]
```

References [SwapCode\(\)](#).

10.303.4.2 GetSwapCodeString()

```
const char * gdcm::SwapCode::GetSwapCodeString (  
    SwapCode const & sc) [static]
```

References [SwapCode\(\)](#), and [operator<<](#).

Referenced by [operator<<](#).

10.303.4.3 operator SwapCode::SwapCodeType()

```
gdcm::SwapCode::operator SwapCode::SwapCodeType () const [inline]
```

10.303.5 Friends And Related Symbol Documentation

10.303.5.1 operator<<

```
std::ostream & operator<< (  
    std::ostream & os,  
    const SwapCode & sc) [friend]
```

References [SwapCode\(\)](#), and [GetSwapCodeString\(\)](#).

Referenced by [GetSwapCodeString\(\)](#).

The documentation for this class was generated from the following file:

- [gdcmSwapCode.h](#)

10.304 gdcm::SwapperDoOp Class Reference

```
#include <gdcmSwapper.h>
```

Static Public Member Functions

- `template<typename T>`
 `static T Swap (T val)`
- `template<typename T>`
 `static void SwapArray (T *array, size_t n)`

10.304.1 Member Function Documentation

10.304.1.1 [Swap\(\)](#)

```
template<typename T>  
T gdcm::SwapperDoOp::Swap (  
    T val) [static]
```

Referenced by [gdcm::Item::Read\(\)](#), and [SwapArray\(\)](#).

10.304.1.2 [SwapArray\(\)](#)

```
template<typename T>  
void gdcm::SwapperDoOp::SwapArray (  
    T * array,  
    size_t n) [inline], [static]
```

References [Swap\(\)](#).

The documentation for this class was generated from the following file:

- [gdcmSwapper.h](#)

10.305 gdcm::SwapperNoOp Class Reference

```
#include <gdcmSwapper.h>
```

Static Public Member Functions

- `template<typename T>`
 `static T Swap (T val)`
- `template<typename T>`
 `static void SwapArray (T *, size_t)`

10.305.1 Detailed Description

Examples

[DumpSiemensBase64.cxx](#), [DumpToshibaDTI.cxx](#), [DumpToshibaDTI2.cxx](#), and [ReadExplicitLengthSQIVR.cxx](#).

10.305.2 Member Function Documentation

10.305.2.1 Swap()

```
template<typename T>
T gdcm::SwapperNoOp::Swap (
    T val) [inline], [static]
```

Referenced by [gdcm::EncodingImplementation< VR::VRBINARY >::Write\(\)](#).

10.305.2.2 SwapArray()

```
template<typename T>
void gdcm::SwapperNoOp::SwapArray (
    T * ,
    size_t ) [inline], [static]
```

Referenced by [gdcm::EncodingImplementation< VR::VRBINARY >::Read\(\)](#).

The documentation for this class was generated from the following file:

- [gdcmSwapper.h](#)

10.306 gdcm::System Class Reference

Class to do system operation.

```
#include <gdcmSystem.h>
```

Static Public Member Functions

- static std::wstring [ConvertToUNC](#) (const char *utf8path)
- static bool [DeleteDirectory](#) (const char *source)
remove a directory named source
- static size_t [EncodeBytes](#) (char *out, const unsigned char *data, int size)
- static bool [FileExists](#) (const char *filename)
Check whether the specified file exist on the system.
- static bool [FileIsDirectory](#) (const char *name)
Check whether the file specified is a directory:
- static bool [FileIsSymlink](#) (const char *name)
Check whether name is a symlink.
- static size_t [FileSize](#) (const char *filename)
- static time_t [FileTime](#) (const char *filename)
- static bool [FormatDateTime](#) (char date[22], time_t t, long milliseconds=0)
- static bool [GetCurrentDateTime](#) (char date[22])
- static const char * [GetCurrentModuleFileName](#) ()
- static const char * [GetCurrentProcessFileName](#) ()
- static const char * [GetCurrentResourcesDirectory](#) ()
- static const char * [GetCWD](#) ()
- static bool [GetHostName](#) (char hostname[255])
- static const char * [GetLastError](#) ()
Return the last error.
- static const char * [GetLocaleCharset](#) ()
return locale charmap
- static const char * [GetTimezoneOffsetFromUTC](#) ()
- static bool [MakeDirectory](#) (const char *path)
Create a directory name path.
- static bool [ParseDateTime](#) (time_t &timep, const char date[22])
Parse a date stored as ASCII text into a time_t structured (discard millisecond if any)
- static bool [ParseDateTime](#) (time_t &timep, long &milliseconds, const char date[22])
- static bool [RemoveFile](#) (const char *source)
remove a file named source
- static int [StrCaseCmp](#) (const char *s1, const char *s2)
consistent func for C99 spec of strcasecmp/strncasecmp
- static int [StrNCaseCmp](#) (const char *s1, const char *s2, size_t n)
- static char * [StrSep](#) (char **stringp, const char *delim)
- static char * [StrTokR](#) (char *ptr, const char *sep, char **end)
strtok_r

Static Protected Member Functions

- static bool [GetPermissions](#) (const char *file, unsigned short &mode)
NOT THREAD SAFE.
- static bool [SetPermissions](#) (const char *file, unsigned short mode)

10.306.1 Detailed Description

Class to do system operation.

OS independent functionalities

Examples

[BasicAnonymizer.cs](#), [BasicImageAnonymizer.cs](#), [Cleaner.cs](#), [ClinicalTrialIdentificationWorkflow.cs](#), [CompressLossyJPEG.cs](#), [DecompressImageMultiframe.cs](#), [DecompressJPEGFile.cs](#), [DumpCSA.cs](#), [ExplicitLittleEndian.cs](#), [ExtractEncapsulatedFile.cs](#), [ExtractImageRegion.cs](#), [ExtractImageRegionWithLUT.cs](#), [ExtractOneFrame.cs](#), [FileAnonymize.cs](#), [FileChangeTS.cs](#), [FileChangeTSLossy.cs](#), [FileStreaming.cs](#), [GetArray.cs](#), [MetaImageMD5Activiz.cs](#), [MpegVideoInfo.cs](#), [ReformatFile.cs](#), [RescaleImage.cs](#), [ScanDirectory.cs](#), [SimplePrint.cs](#), and [StandardizeFiles.cs](#).

10.306.2 Member Function Documentation

10.306.2.1 ConvertToUNC()

```
std::wstring gdcm::System::ConvertToUNC (
    const char * utf8path) [static]
```

When needed convert a PATH into a UNC equivalent. This allow transparent support for path longer than MAX_PATH. Only on _MSC_VER compiler, return empty string otherwise.

10.306.2.2 DeleteDirectory()

```
bool gdcm::System::DeleteDirectory (
    const char * source) [static]
```

remove a directory named source

10.306.2.3 EncodeBytes()

```
size_t gdcm::System::EncodeBytes (
    char * out,
    const unsigned char * data,
    int size) [static]
```

Used internally by the [UIDGenerator](#) class to convert a uuid tape to a DICOM [VR:UI](#) type

10.306.2.4 FileExists()

```
bool gdcm::System::FileExists (
    const char * filename) [static]
```

Check whether the specified file exist on the system.

Examples

[DumpVisusChange.cxx](#), [EncapsulateFileInRawData.cxx](#), [MagnifyFile.cxx](#), and [gdcmorthoplanes.cxx](#).

10.306.2.5 FileIsDirectory()

```
bool gdcmm::System::FileIsDirectory (
    const char * name) [static]
```

Check whether the file specified is a directory:

Examples

[DumpVisusChange.cxx](#), [gdcmmorthoplanes.cxx](#), and [threadgdcmm.cxx](#).

10.306.2.6 FileIsSymlink()

```
bool gdcmm::System::FileIsSymlink (
    const char * name) [static]
```

Check whether name is a symlink.

10.306.2.7 FileSize()

```
size_t gdcmm::System::FileSize (
    const char * filename) [static]
```

Return the filesize. 0 if file does not exist.

Warning

you need to use FileExists to differentiate between empty file and missing file.

for very large size file and on system where size_t is not appropriate to store off_t value the function will return 0.

Examples

[CheckBigEndianBug.cxx](#), [CreateARGBImage.cxx](#), [CreateCMYKImage.cxx](#), [EncapsulateFileInRawData.cxx](#), and [SimpleScanner.cxx](#).

10.306.2.8 FileTime()

```
time_t gdcmm::System::FileTime (
    const char * filename) [static]
```

Return the time of last modification of file 0 if the file does not exist

10.306.2.9 FormatDateTime()

```
bool gdcm::System::FormatDateTime (
    char date[22],
    time_t t,
    long milliseconds = 0) [static]
```

format as ASCII text a time_t with milliseconds See [VR::DT](#) from DICOM PS 3.5 milliseconds is in the range [0, 999999]

10.306.2.10 GetCurrentDateTime()

```
bool gdcm::System::GetCurrentDateTime (
    char date[22]) [static]
```

Return the current data time, and format it as ASCII text. This is simply a call to gettimeofday + FormatDateTime, since WIN32 do not have an implementation for gettimeofday, this is more portable. The call time(0) is not precise for our resolution

Examples

[TemplateEmptyImage.cxx](#).

10.306.2.11 GetCurrentModuleFileName()

```
const char * gdcm::System::GetCurrentModuleFileName () [static]
```

Return the directory the current module is located: NOT THREAD SAFE

10.306.2.12 GetCurrentProcessFileName()

```
const char * gdcm::System::GetCurrentProcessFileName () [static]
```

Return the directory the current process (executable) is located: NOT THREAD SAFE

10.306.2.13 GetCurrentResourcesDirectory()

```
const char * gdcm::System::GetCurrentResourcesDirectory () [static]
```

On some system (Apple) return the path to the current bundled 'Resources' directory NOT THREAD SAFE

10.306.2.14 GetCWD()

```
const char * gdcm::System::GetCWD () [static]
```

Return current working directory Warning: if current working path is too long (>2048 bytes) the call will fail and call will return NULL NOT THREAD SAFE

10.306.2.15 GetHostName()

```
bool gdcM::System::GetHostName (
    char hostname[255]) [static]
```

Retrieve the hostname, only the first 255 byte are copied. This may come handy to specify the Station Name

10.306.2.16 GetLastSystemError()

```
const char * gdcM::System::GetLastSystemError () [static]
```

Return the last error.

10.306.2.17 GetLocaleCharset()

```
const char * gdcM::System::GetLocaleCharset () [static]
```

return locale charmap

10.306.2.18 GetPermissions()

```
bool gdcM::System::GetPermissions (
    const char * file,
    unsigned short & mode) [static], [protected]
```

NOT THREAD SAFE.

10.306.2.19 GetTimezoneOffsetFromUTC()

```
const char * gdcM::System::GetTimezoneOffsetFromUTC () [static]
```

Return the value for Timezone Offset From UTC as string.

Warning

not thread safe

10.306.2.20 MakeDirectory()

```
bool gdcM::System::MakeDirectory (
    const char * path) [static]
```

Create a directory name path.

10.306.2.21 ParseDateTime() [1/2]

```
bool gdcm::System::ParseDateTime (
    time_t & timep,
    const char date[22]) [static]
```

Parse a date stored as ASCII text into a time_t structured (discard millisecond if any)

10.306.2.22 ParseDateTime() [2/2]

```
bool gdcm::System::ParseDateTime (
    time_t & timep,
    long & milliseconds,
    const char date[22]) [static]
```

Parse a date stored as ASCII text into a time_t structured and millisecond

See also

[FormatDateTime](#)

10.306.2.23 RemoveFile()

```
bool gdcm::System::RemoveFile (
    const char * source) [static]
```

remove a file named source

10.306.2.24 SetPermissions()

```
bool gdcm::System::SetPermissions (
    const char * file,
    unsigned short mode) [static], [protected]
```

10.306.2.25 StrCaseCmp()

```
int gdcm::System::StrCaseCmp (
    const char * s1,
    const char * s2) [static]
```

consistent func for C99 spec of strcasecmp/strncasecmp

10.306.2.26 StrNCaseCmp()

```
int gdcM::System::StrNCaseCmp (
    const char * s1,
    const char * s2,
    size_t n) [static]
```

Precondition

`n != 0`

10.306.2.27 StrSep()

```
char * gdcM::System::StrSep (
    char ** stringp,
    const char * delim) [static]
```

strsep param stringp is passed by pointer, it may be modified, you'll need to make a copy, in case you want to free the memory pointed at

10.306.2.28 StrTokR()

```
char * gdcM::System::StrTokR (
    char * ptr,
    const char * sep,
    char ** end) [static]
```

strtok_r

The documentation for this class was generated from the following file:


- [gdcMSystem.h](#)

10.307 gdcM::Table Class Reference

[Table](#).

```
#include <gdcMTable.h>
```

Collaboration diagram for gdcm::Table:



Public Types

- typedef std::map< [Tag](#), [TableEntry](#) > [MapTableEntry](#)

Public Member Functions

- [Table](#) ()=default
- [Table](#) (const [Table](#) &_val)=delete
- [~Table](#) ()=default
- const [TableEntry](#) & [GetTableEntry](#) (const [Tag](#) &tag) const
- void [InsertEntry](#) ([Tag](#) const &tag, [TableEntry](#) const &te)
- [Table](#) & [operator=](#) (const [Table](#) &_val)=delete

Public Attributes

- [MapTableEntry](#) [TableInternal](#)

Friends

- std::ostream & [operator<<](#) (std::ostream &_os, const [Table](#) &_val)

10.307.1 Detailed Description

[Table](#).

10.307.2 Member Typedef Documentation

10.307.2.1 MapTableEntry

```
typedef std::map<Tag, TableEntry> gdcM::Table::MapTableEntry
```

10.307.3 Constructor & Destructor Documentation

10.307.3.1 Table() [1/2]

```
gdcM::Table::Table () [default]
```

Referenced by [Table\(\)](#), [operator<<](#), and [operator=\(\)](#).

10.307.3.2 ~Table()

```
gdcM::Table::~~Table () [default]
```

10.307.3.3 Table() [2/2]

```
gdcM::Table::Table (  
    const Table & _val) [delete]
```

References [Table\(\)](#).

10.307.4 Member Function Documentation

10.307.4.1 GetTableEntry()

```
const TableEntry & gdcM::Table::GetTableEntry (  
    const Tag & tag) const [inline]
```

References [gdcM_assert](#), [GetTableEntry\(\)](#), and [TableInternal](#).

Referenced by [GetTableEntry\(\)](#).

10.307.4.2 InsertEntry()

```
void gdcm::Table::InsertEntry (
    Tag const & tag,
    TableEntry const & te) [inline]
```

References [gdcm_assert](#), and [TableInternal](#).

10.307.4.3 operator=()

```
Table & gdcm::Table::operator= (
    const Table & _val) [delete]
```

References [Table\(\)](#).

10.307.5 Friends And Related Symbol Documentation

10.307.5.1 operator<<

```
std::ostream & operator<< (
    std::ostream & _os,
    const Table & _val) [friend]
```

References [Table\(\)](#).

10.307.6 Member Data Documentation

10.307.6.1 TableInternal

[MapTableEntry](#) gdcm::Table::TableInternal

Referenced by [GetTableEntry\(\)](#), and [InsertEntry\(\)](#).

The documentation for this class was generated from the following file:

- [gdcmTable.h](#)

10.308 gdcm::TableEntry Class Reference

[TableEntry](#).

```
#include <gdcmTableEntry.h>
```

Public Member Functions

- [TableEntry](#) (const char *attribute=nullptr, [Type](#) const &type=[Type](#)(), const char *des=nullptr)
- [~TableEntry](#) ()=default

10.308.1 Detailed Description

[TableEntry](#).

10.308.2 Constructor & Destructor Documentation

10.308.2.1 TableEntry()

```
gdcm::TableEntry::TableEntry (
    const char * attribute = nullptr,
    Type const & type = Type(),
    const char * des = nullptr) [inline]
```

10.308.2.2 ~TableEntry()

```
gdcm::TableEntry::~~TableEntry () [default]
```

The documentation for this class was generated from the following file:


- [gdcmTableEntry.h](#)

10.309 gdcm::TableReader Class Reference

Class for representing a [TableReader](#).

```
#include <gdcmTableReader.h>
```

Inheritance diagram for gdcm::TableReader:



Public Member Functions

- [TableReader](#) ([Defs](#) &defs)
- virtual [~TableReader](#) ()=default
- virtual void [CharacterDataHandler](#) (const char *data, int length)
- virtual void [EndElement](#) (const char *name)
- const [Defs](#) & [GetDefs](#) () const
- const char * [GetFilename](#) ()
- void [HandleIOD](#) (const char **atts)
- void [HandleIODEntry](#) (const char **atts)
- void [HandleMacro](#) (const char **atts)
- void [HandleMacroEntry](#) (const char **atts)
- void [HandleMacroEntryDescription](#) (const char **atts)
- void [HandleModule](#) (const char **atts)
- void [HandleModuleEntry](#) (const char **atts)
- void [HandleModuleEntryDescription](#) (const char **atts)
- void [HandleModuleInclude](#) (const char **atts)
- int [Read](#) ()
- void [SetFilename](#) (const char *filename)
- virtual void [StartElement](#) (const char *name, const char **atts)

10.309.1 Detailed Description

Class for representing a [TableReader](#).

Note

This class is an empty shell meant to be derived

10.309.2 Constructor & Destructor Documentation**10.309.2.1 TableReader()**

```
gdcm::TableReader::TableReader (
    Defs & defs) [inline]
```

10.309.2.2 ~TableReader()

```
virtual gdcm::TableReader::~~TableReader () [virtual], [default]
```

10.309.3 Member Function Documentation

10.309.3.1 CharacterDataHandler()

```
virtual void gdcm::TableReader::CharacterDataHandler (  
    const char * data,  
    int length) [virtual]
```

Reimplemented in [gdcm::XMLDictReader](#), and [gdcm::XMLPrivateDictReader](#).

10.309.3.2 EndElement()

```
virtual void gdcm::TableReader::EndElement (  
    const char * name) [virtual]
```

Reimplemented in [gdcm::XMLDictReader](#), and [gdcm::XMLPrivateDictReader](#).

10.309.3.3 GetDefs()

```
const Defs & gdcm::TableReader::GetDefs () const [inline]
```

10.309.3.4 GetFilename()

```
const char * gdcm::TableReader::GetFilename () [inline]
```

10.309.3.5 HandleIOD()

```
void gdcm::TableReader::HandleIOD (  
    const char ** atts)
```

10.309.3.6 HandleIODEntry()

```
void gdcm::TableReader::HandleIODEntry (  
    const char ** atts)
```

10.309.3.7 HandleMacro()

```
void gdcm::TableReader::HandleMacro (  
    const char ** atts)
```

10.309.3.8 HandleMacroEntry()

```
void gdcm::TableReader::HandleMacroEntry (
    const char ** atts)
```

10.309.3.9 HandleMacroEntryDescription()

```
void gdcm::TableReader::HandleMacroEntryDescription (
    const char ** atts)
```

10.309.3.10 HandleModule()

```
void gdcm::TableReader::HandleModule (
    const char ** atts)
```

10.309.3.11 HandleModuleEntry()

```
void gdcm::TableReader::HandleModuleEntry (
    const char ** atts)
```

10.309.3.12 HandleModuleEntryDescription()

```
void gdcm::TableReader::HandleModuleEntryDescription (
    const char ** atts)
```

10.309.3.13 HandleModuleInclude()

```
void gdcm::TableReader::HandleModuleInclude (
    const char ** atts)
```

10.309.3.14 Read()

```
int gdcm::TableReader::Read ()
```

10.309.3.15 SetFilename()

```
void gdcm::TableReader::SetFilename (
    const char * filename) [inline]
```

10.309.3.16 StartElement()

```
virtual void gdcM::TableReader::StartElement (
    const char * name,
    const char ** atts) [virtual]
```

Reimplemented in [gdcM::XMLDictReader](#), and [gdcM::XMLPrivateDictReader](#).


The documentation for this class was generated from the following file:

- [gdcMTableReader.h](#)

10.310 gdcM::network::TableRow Class Reference

```
#include <gdcMULTransitionTable.h>
```

Collaboration diagram for gdcM::network::TableRow:



Public Member Functions

- [TableRow](#) ()
- [~TableRow](#) ()

Public Attributes

- [Transition](#) * [transitions](#) [`cMaxStateID`]

10.310.1 Constructor & Destructor Documentation

10.310.1.1 TableRow()

```
gdcm::network::TableRow::TableRow () [inline]
```

References [gdcm::network::cMaxStateID](#), and [transitions](#).

10.310.1.2 ~TableRow()

```
gdcm::network::TableRow::~TableRow () [inline]
```

References [gdcm::network::cMaxStateID](#), and [transitions](#).

10.310.2 Member Data Documentation

10.310.2.1 transitions

```
Transition* gdcm::network::TableRow::transitions[cMaxStateID]
```

Referenced by [TableRow\(\)](#), and [~TableRow\(\)](#).

The documentation for this class was generated from the following file:


- [gdcmULTransitionTable.h](#)

10.311 gdcm::Tag Class Reference

Class to represent a DICOM Data [Element](#) ([Attribute](#)) [Tag](#) (Group, [Element](#)).

```
#include <gdcmTag.h>
```

Inheritance diagram for gdcm::Tag:



Public Member Functions

- [Tag](#) (const [Tag](#) &_val)
- [Tag](#) (uint16_t group, uint16_t element)
*Constructor with 2*uint16_t.*
- [Tag](#) (uint32_t tag=0)
*Constructor with 1*uint32_t Prefer the ctor that takes two uint16_t.*
- uint16_t [GetElement](#) () const
Returns the 'Element number' of the given Tag.
- uint32_t [GetElementTag](#) () const
Returns the full tag value of the given Tag.
- uint16_t [GetGroup](#) () const
Returns the 'Group number' of the given Tag.
- uint32_t [GetLength](#) () const
return the length of tag (read: size on disk)
- [Tag](#) [GetPrivateCreator](#) () const
Return the Private Creator Data Element tag of a private data element.
- bool [IsGroupLength](#) () const
return whether the tag correspond to a group length tag:
- bool [IsGroupXX](#) (const [Tag](#) &t) const
e.g 6002,3000 belong to groupXX: 6000,3000
- bool [IsIllegal](#) () const
return if the tag is considered to be an illegal tag
- bool [IsPrivate](#) () const
- bool [IsPrivateCreator](#) () const
- bool [IsPublic](#) () const
- bool [operator!=](#) (const [Tag](#) &_val) const
- bool [operator<](#) (const [Tag](#) &_val) const
- bool [operator<=](#) (const [Tag](#) &t2) const
- [Tag](#) & [operator=](#) (const [Tag](#) &_val)
- bool [operator==](#) (const [Tag](#) &_val) const
- uint16_t & [operator\[\]](#) (const unsigned int &_id)
Returns the Group or Element of the given Tag, depending on id (0/1)
- const uint16_t & [operator\[\]](#) (const unsigned int &_id) const
Returns the Group or Element of the given Tag, depending on id (0/1)
- std::string [PrintAsContinuousString](#) () const
- std::string [PrintAsContinuousUpperCaseString](#) () const
Same as PrintAsContinuousString, but hexadecimal [a-f] are printed using upper case.
- std::string [PrintAsPipeSeparatedString](#) () const
- template<typename TSwap>
std::istream & [Read](#) (std::istream &is)
Read a tag from binary representation.
- bool [ReadFromCommaSeparatedString](#) (const char *str)
- bool [ReadFromContinuousString](#) (const char *str)
- bool [ReadFromPipeSeparatedString](#) (const char *str)
- void [SetElement](#) (uint16_t element)
Sets the 'Element number' of the given Tag.
- void [SetElementTag](#) (uint16_t group, uint16_t element)

- Sets the 'Group number' & 'Element number' of the given [Tag](#).
 - void [SetElementTag](#) (uint32_t tag)
- Sets the full tag value of the given [Tag](#).
 - void [SetGroup](#) (uint16_t group)
- Sets the 'Group number' of the given [Tag](#).
 - void [SetPrivateCreator](#) ([Tag](#) const &t)
- Set private creator:
 - template<typename TSwap>
const std::ostream & [Write](#) (std::ostream &os) const
- Write a tag in binary rep.

Friends

- std::ostream & [operator<<](#) (std::ostream &_os, const [Tag](#) &_val)
- std::istream & [operator>>](#) (std::istream &_is, [Tag](#) &_val)

10.311.1 Detailed Description

Class to represent a DICOM Data [Element](#) ([Attribute](#)) [Tag](#) (Group, [Element](#)).

Basically an uint32_t which can also be expressed as two uint16_t (group and element)

Note

DATA ELEMENT TAG: A unique identifier for a Data [Element](#) composed of an ordered pair of numbers (a Group Number followed by an [Element](#) Number). GROUP NUMBER: The first number in the ordered pair of numbers that makes up a Data [Element Tag](#). ELEMENT NUMBER: The second number in the ordered pair of numbers that makes up a Data [Element Tag](#).

Examples

[BasicAnonymizer.cs](#), [BasicImageAnonymizer.cs](#), [ChangeSequenceUltrasound.cxx](#), [Cleaner.cs](#), [ClinicalTrialAnnotate.cxx](#), [ClinicalTrialIdentificationWorkflow.cs](#), [CreateARGBImage.cxx](#), [CreateCMYKImage.cxx](#), [CreateFakeRTDOSE.cxx](#), [CreateJPIPDataSet.cxx](#), [DecompressImage.cs](#), [DeriveSeries.cxx](#), [DiscriminateVolume.cxx](#), [DumpToSQLITE3.cxx](#), [DumpVisusChange.cxx](#), [DuplicatePCDE.cxx](#), [EncapsulateFileInRawData.cxx](#), [ExtractEncapsulatedFile.cs](#), [ExtractEncryptedContent.cxx](#), [Extracting_All_Resolution.cxx](#), [Fake_Image_Using_Stream_Image_Writer.cxx](#), [FileAnonymize.cs](#), [FileChangeTS.cs](#), [FileChangeTSLossy.cs](#), [FixBrokenJ2K.cxx](#), [FixJAIBugJPEGLS.cxx](#), [GenAllIVR.cxx](#), [GenFakeIdentifyFile.cxx](#), [GenFakeImage.cxx](#), [GenLongSeqs.cxx](#), [GenSeqs.cxx](#), [GetJPEGSamplePrecision.cxx](#), [GetSequenceUltrasound.cxx](#), [GetSubSequenceData.cxx](#), [LargeVRDSExplicit.cxx](#), [MakeTemplate.cxx](#), [ManipulateFile.cs](#), [MergeTwoFiles.cxx](#), [MpegVideoInfo.cs](#), [PatchFile.cxx](#), [PublicDict.cxx](#), [ReadAndDumpDICOMDIR.cxx](#), [ReadAndDumpDICOMDIR2.cxx](#), [ReadAndPrintAttributes.cxx](#), [ReadExplicitLengthSQIVR.cxx](#), [ScanDirectory.cs](#), [SimpleScanner.cxx](#), [SortImage.cxx](#), [StreamImageReaderTest.cxx](#), [TraverseModules.cxx](#), [VolumeSorter.cxx](#), [gdcmrtionplan.cxx](#), [gdcmrtplan.cxx](#), [iU22tomultisc.cxx](#), [pmsct_rgb1.cxx](#), and [rle2img.cxx](#).

10.311.2 Constructor & Destructor Documentation

10.311.2.1 Tag() [1/3]

```
gdcM::Tag::Tag (
    uint16_t group,
    uint16_t element) [inline]
```

Constructor with 2*uint16_t.

Referenced by [gdcM::PrivateTag::PrivateTag\(\)](#), [gdcM::PrivateTag::PrivateTag\(\)](#), [Tag\(\)](#), [GetPrivateCreator\(\)](#), [IsGroupXX\(\)](#), [gdcM::PrivateTag::operator!=\(\)](#), [operator!=\(\)](#), [operator<\(\)](#), [operator<<\(\)](#), [operator<=\(\)](#), [operator=\(\)](#), [gdcM::PrivateTag::operator==\(\)](#), [operator==\(\)](#), [operator>>\(\)](#), and [SetPrivateCreator\(\)](#).

10.311.2.2 Tag() [2/3]

```
gdcM::Tag::Tag (
    uint32_t tag = 0) [inline]
```

Constructor with 1*uint32_t Prefer the ctor that takes two uint16_t.

References [SetElementTag\(\)](#), and [tag](#).

10.311.2.3 Tag() [3/3]

```
gdcM::Tag::Tag (
    const Tag & _val) [inline]
```

References [Tag\(\)](#), and [tag](#).

10.311.3 Member Function Documentation

10.311.3.1 GetElement()

```
uint16_t gdcM::Tag::GetElement () const [inline]
```

Returns the 'Element number' of the given [Tag](#).

Examples

[DuplicatePCDE.cxx](#), and [PublicDict.cxx](#).

Referenced by [gdcM::PrivateTag::PrivateTag\(\)](#), [gdcM::DataSet::ComputeGroupLength\(\)](#), [GetPrivateCreator\(\)](#), [IsGroupLength\(\)](#), [IsGroupXX\(\)](#), [IsIllegal\(\)](#), [IsPrivateCreator\(\)](#), [gdcM::PrivateDict::PrintXML\(\)](#), [gdcM::SequenceOfFragments::ReadValue\(\)](#), and [SetPrivateCreator\(\)](#).

10.311.3.2 GetElementTag()

```
uint32_t gdcM::Tag::GetElementTag () const [inline]
```

Returns the full tag value of the given [Tag](#).

Referenced by [gdcM::PrivateTag::operator!=\(\)](#), [gdcM::PrivateTag::operator!=\(\)](#), [gdcM::PrivateTag::operator=\(\)](#), [gdcM::PrivateTag::operator==\(\)](#), and [gdcM::PrivateTag::operator==\(\)](#).

10.311.3.3 GetGroup()

```
uint16_t gdcM::Tag::GetGroup () const [inline]
```

Returns the 'Group number' of the given [Tag](#).

Examples

[DuplicatePCDE.cxx](#), and [GenAllVR.cxx](#).

Referenced by [gdcM::DataSet::ComputeGroupLength\(\)](#), [gdcM::CommandDataSet::Insert\(\)](#), [gdcM::DataSet::Insert\(\)](#), [gdcM::FileMetaInformation::Insert\(\)](#), [IsGroupXX\(\)](#), [IsIllegal\(\)](#), [gdcM::PrivateDict::PrintXML\(\)](#), [gdcM::SequenceOfFragments::ReadValue\(\)](#), and [SetPrivateCreator\(\)](#).

10.311.3.4 GetLength()

```
uint32_t gdcM::Tag::GetLength () const [inline]
```

return the length of tag (read: size on disk)

10.311.3.5 GetPrivateCreator()

```
Tag gdcM::Tag::GetPrivateCreator () const [inline]
```

Return the Private Creator Data [Element](#) tag of a private data element.

References [Tag\(\)](#), [GetElement\(\)](#), [IsPrivate\(\)](#), [IsPrivateCreator\(\)](#), and [SetElement\(\)](#).

10.311.3.6 IsGroupLength()

```
bool gdcM::Tag::IsGroupLength () const [inline]
```

return whether the tag correspond to a group length tag:

References [GetElement\(\)](#).

10.311.3.7 IsGroupXX()

```
bool gdcM::Tag::IsGroupXX (
    const Tag & t) const [inline]
```

e.g 6002,3000 belong to groupXX: 6000,3000

References [Tag\(\)](#), [GetElement\(\)](#), [GetGroup\(\)](#), and [IsPrivate\(\)](#).

10.311.3.8 IsIllegal()

```
bool gdcM::Tag::IsIllegal () const [inline]
```

return if the tag is considered to be an illegal tag

References [GetElement\(\)](#), [GetGroup\(\)](#), and [IsPrivate\(\)](#).

10.311.3.9 IsPrivate()

```
bool gdcM::Tag::IsPrivate () const [inline]
```

PRIVATE DATA ELEMENT: Additional Data [Element](#), defined by an implementor, to communicate information that is not contained in Standard Data Elements. Private Data elements have odd Group Numbers.

Examples

[DuplicatePCDE.cxx](#).

References [IsPublic\(\)](#).

Referenced by [GetPrivateCreator\(\)](#), [IsGroupXX\(\)](#), [IsIllegal\(\)](#), [IsPrivateCreator\(\)](#), and [SetPrivateCreator\(\)](#).

10.311.3.10 IsPrivateCreator()

```
bool gdcM::Tag::IsPrivateCreator () const [inline]
```

Returns if tag is a Private Creator (xxxx,00yy), where xxxx is odd number and yy in [0x10,0xFF]

Examples

[DuplicatePCDE.cxx](#).

References [GetElement\(\)](#), and [IsPrivate\(\)](#).

Referenced by [GetPrivateCreator\(\)](#).

10.311.3.11 IsPublic()

```
bool gdcm::Tag::IsPublic () const [inline]
```

STANDARD DATA ELEMENT: A Data [Element](#) defined in the DICOM Standard, and therefore listed in the DICOM Data [Element](#) Dictionary in PS 3.6. Is the [Tag](#) from the Public dict...well the implementation is buggy it does not prove the element is indeed in the dict...

Referenced by [IsPrivate\(\)](#).

10.311.3.12 operator"!="()

```
bool gdcm::Tag::operator!= (
    const Tag & _val) const [inline]
```

References [Tag\(\)](#), and [tag](#).

10.311.3.13 operator<()

```
bool gdcm::Tag::operator< (
    const Tag & _val) const [inline]
```

DICOM Standard expects the Data [Element](#) to be sorted by Tags All other comparison can be constructed from this one and operator ==

References [Tag\(\)](#), [tag](#), and [tags](#).

10.311.3.14 operator<=()

```
bool gdcm::Tag::operator<= (
    const Tag & t2) const [inline]
```

References [Tag\(\)](#).

10.311.3.15 operator=()

```
Tag & gdcm::Tag::operator= (
    const Tag & _val) [inline]
```

References [Tag\(\)](#), and [tag](#).

10.311.3.16 operator==(())

```
bool gdcm::Tag::operator==(
    const Tag & _val) const [inline]
```

References [Tag\(\)](#), and [tag](#).

10.311.3.17 operator[]() [1/2]

```
uint16_t & gdcM::Tag::operator[] (
    const unsigned int & _id) [inline]
```

Returns the Group or [Element](#) of the given [Tag](#), depending on id (0/1)

References [gdcM_assert](#).

10.311.3.18 operator[]() [2/2]

```
const uint16_t & gdcM::Tag::operator[] (
    const unsigned int & _id) const [inline]
```

Returns the Group or [Element](#) of the given [Tag](#), depending on id (0/1)

References [gdcM_assert](#).

10.311.3.19 PrintAsContinuousString()

```
std::string gdcM::Tag::PrintAsContinuousString () const
```

Print tag value with no separating comma: eg. tag = "12345678" It comes in useful when reading tag values from XML file(in NativeDICOMModel)

10.311.3.20 PrintAsContinuousUpperCaseString()

```
std::string gdcM::Tag::PrintAsContinuousUpperCaseString () const
```

Same as PrintAsContinuousString, but hexadecimal [a-f] are printed using upper case.

10.311.3.21 PrintAsPipeSeparatedString()

```
std::string gdcM::Tag::PrintAsPipeSeparatedString () const
```

Print as a pipe separated string (GDCM 1.x compat only). Do not use in newer code

See also

[ReadFromPipeSeparatedString](#)

10.311.3.22 Read()

```
template<typename TSwap>
std::istream & gdcm::Tag::Read (
    std::istream & is) [inline]
```

Read a tag from binary representation.

10.311.3.23 ReadFromCommaSeparatedString()

```
bool gdcm::Tag::ReadFromCommaSeparatedString (
    const char * str)
```

Read from a comma separated string. This is a highly user oriented function, the string should be formatted as ← : 1234,5678 to specify the tag (0x1234,0x5678) The notation comes from the DICOM standard, and is handy to use from a command line program

10.311.3.24 ReadFromContinuousString()

```
bool gdcm::Tag::ReadFromContinuousString (
    const char * str)
```

Read From XML formatted tag value eg. tag = "12345678" It comes in useful when reading tag values from XML file(in NativeDICOMModel)

10.311.3.25 ReadFromPipeSeparatedString()

```
bool gdcm::Tag::ReadFromPipeSeparatedString (
    const char * str)
```

Read from a pipe separated string (GDCM 1.x compat only). Do not use in newer code

See also

[ReadFromCommaSeparatedString](#)

10.311.3.26 SetElement()

```
void gdcm::Tag::SetElement (
    uint16_t element) [inline]
```

Sets the '[Element](#) number' of the given [Tag](#).

Examples

[DuplicatePCDE.cxx](#), and [PublicDict.cxx](#).

Referenced by [gdcm::PrivateTag::PrivateTag\(\)](#), [gdcm::PrivateTag::PrivateTag\(\)](#), [GetPrivateCreator\(\)](#), [operator>>](#), and [SetPrivateCreator\(\)](#).

10.311.3.27 SetElementTag() [1/2]

```
void gdcmm::Tag::SetElementTag (
    uint16_t group,
    uint16_t element) [inline]
```

Sets the 'Group number' & 'Element number' of the given [Tag](#).

Referenced by [Tag\(\)](#), and [gdcmm::PrivateTag::operator=\(\)](#).

10.311.3.28 SetElementTag() [2/2]

```
void gdcmm::Tag::SetElementTag (
    uint32_t tag) [inline]
```

Sets the full tag value of the given [Tag](#).

References [tag](#).

10.311.3.29 SetGroup()

```
void gdcmm::Tag::SetGroup (
    uint16_t group) [inline]
```

Sets the 'Group number' of the given [Tag](#).

Referenced by [operator>>](#), and [SetPrivateCreator\(\)](#).

10.311.3.30 SetPrivateCreator()

```
void gdcmm::Tag::SetPrivateCreator (
    Tag const & t) [inline]
```

Set private creator:

Examples

[DuplicatePCDE.cxx](#).

References [Tag\(\)](#), [gdcmm_assert](#), [GetElement\(\)](#), [GetGroup\(\)](#), [IsPrivate\(\)](#), [SetElement\(\)](#), and [SetGroup\(\)](#).

10.311.3.31 Write()

```
template<typename TSwap>
const std::ostream & gdcmm::Tag::Write (
    std::ostream & os) const [inline]
```

Write a tag in binary rep.

Referenced by [gdcmm::Item::Write\(\)](#), [gdcmm::SequenceOfFragments::Write\(\)](#), and [gdcmm::SequenceOfItems::Write\(\)](#).

10.311.4 Friends And Related Symbol Documentation

10.311.4.1 operator<<

```
std::ostream & operator<< (  
    std::ostream & _os,  
    const Tag & _val) [friend]
```

References [Tag\(\)](#).

10.311.4.2 operator>>

```
std::istream & operator>> (  
    std::istream & _is,  
    Tag & _val) [friend]
```

References [Tag\(\)](#), [SetElement\(\)](#), and [SetGroup\(\)](#).

10.311.5 Member Data Documentation

10.311.5.1 bytes

```
char gdcm::Tag::bytes[4]
```

10.311.5.2 tag

```
uint32_t gdcm::Tag::tag
```

Referenced by [Tag\(\)](#), [Tag\(\)](#), [operator!=\(\)](#), [operator<\(\)](#), [operator=\(\)](#), [operator==\(\)](#), and [SetElementTag\(\)](#).

10.311.5.3 tags

```
uint16_t gdcm::Tag::tags[2]
```

Referenced by [operator<\(\)](#).

The documentation for this class was generated from the following file:

- [gdcmTag.h](#)

10.312 gdcm::TagPath Class Reference

class to handle a path of tag.

```
#include <gdcmTagPath.h>
```

Public Member Functions

- [TagPath](#) ()
- [~TagPath](#) ()
- bool [ConstructFromString](#) (const char *path)
- bool [ConstructFromTagList](#) ([Tag](#) const *l, unsigned int n)
Construct from a list of tags.
- void [Print](#) (std::ostream &) const
- bool [Push](#) ([Tag](#) const &t)
- bool [Push](#) (unsigned int itemnum)

Static Public Member Functions

- static bool [IsValid](#) (const char *path)
Return if path is valid or not.

10.312.1 Detailed Description

class to handle a path of tag.

Any Resemblance to Existing XPath is Purely Coincidental [ftp://medical.nema.org/medical/dicom/supps/sup118←_pc.pdf](ftp://medical.nema.org/medical/dicom/supps/sup118/_pc.pdf)

10.312.2 Constructor & Destructor Documentation

10.312.2.1 TagPath()

```
gdcm::TagPath::TagPath ()
```

10.312.2.2 ~TagPath()

```
gdcm::TagPath::~~TagPath ()
```

10.312.3 Member Function Documentation

10.312.3.1 ConstructFromString()

```
bool gdcm::TagPath::ConstructFromString (
    const char * path)
```

"/0018,0018/"... No space allowed, comma is use to separate tag group from tag element and slash is used to separate tag return false if invalid

10.312.3.2 ConstructFromTagList()

```
bool gdcm::TagPath::ConstructFromTagList (
    Tag const * l,
    unsigned int n)
```

Construct from a list of tags.

10.312.3.3 IsValid()

```
bool gdcm::TagPath::IsValid (
    const char * path) [static]
```

Return if path is valid or not.

10.312.3.4 Print()

```
void gdcm::TagPath::Print (
    std::ostream & ) const
```

10.312.3.5 Push() [1/2]

```
bool gdcm::TagPath::Push (
    Tag const & t)
```

10.312.3.6 Push() [2/2]

```
bool gdcm::TagPath::Push (
    unsigned int itemnum)
```

The documentation for this class was generated from the following file:

- [gdcmTagPath.h](#)

10.313 gdcm::Testing Class Reference

class for testing

```
#include <gdcmTesting.h>
```

Public Types

- typedef const char *const (* [MD5DataImagesType](#))[2]
- typedef const char *const (* [MediaStorageDataFilesType](#))[2]
return the table that map the media storage (as string) of a filename (gdcmData)

Public Member Functions

- [Testing](#) ()=default
- [~Testing](#) ()=default
- void [Print](#) (std::ostream &os=std::cout)
Print.

Static Public Member Functions

- static bool [ComputeFileMD5](#) (const char *filename, char digest_str[33])
- static bool [ComputeMD5](#) (const char *buffer, size_t buf_len, char digest_str[33])
- static const char * [GetDataExtraRoot](#) ()
Return the GDCM DATA EXTRA ROOT.
- static const char * [GetDataRoot](#) ()
Return the GDCM DATA ROOT.
- static const char * [GetFileName](#) (unsigned int file)
- static const char *const * [GetFileNames](#) ()
return the table of fullpath to gdcmData DICOM files:
- static int [GetLossyFlagFromFile](#) (const char *filepath)
- static const char *const * [GetMD5DataImage](#) (unsigned int file)
- static [MD5DataImagesType](#) [GetMD5DataImages](#) ()
- static const char * [GetMD5FromBrokenFile](#) (const char *filepath)
- static const char * [GetMD5FromFile](#) (const char *filepath)
- static const char *const * [GetMediaStorageDataFile](#) (unsigned int file)
- static [MediaStorageDataFilesType](#) [GetMediaStorageDataFiles](#) ()
- static const char * [GetMediaStorageFromFile](#) (const char *filepath)
- static unsigned int [GetNumberOfFileNames](#) ()
- static unsigned int [GetNumberOfMD5DataImages](#) ()
- static unsigned int [GetNumberOfMediaStorageDataFiles](#) ()
- static const char * [GetPixelSpacingDataRoot](#) ()
Return the GDCM PIXEL SPACING DATA ROOT (See David Clunie website for dataset)
- static std::streamoff [GetSelectedPrivateGroupOffsetFromFile](#) (const char *filepath)
- static std::streamoff [GetSelectedTagsOffsetFromFile](#) (const char *filepath)
- static const char * [GetSourceDirectory](#) ()
- static std::streamoff [GetStreamOffsetFromFile](#) (const char *filepath)

- static const char * [GetTempDirectory](#) (const char *subdir=nullptr)
- static const wchar_t * [GetTempDirectoryW](#) (const wchar_t *subdir=nullptr)
NOT THREAD SAFE.
- static const char * [GetTempFilename](#) (const char *filename, const char *subdir=nullptr)
NOT THREAD SAFE.
- static const wchar_t * [GetTempFilenameW](#) (const wchar_t *filename, const wchar_t *subdir=nullptr)
NOT THREAD SAFE.

10.313.1 Detailed Description

class for testing

this class is used for the nightly regression system for GDCM It makes heavily use of md5 computation

See also

[gdcm::MD5](#) class for md5 computation

10.313.2 Member Typedef Documentation

10.313.2.1 MD5DataImagesType

```
typedef const char* const (* gdcm::Testing::MD5DataImagesType) [2]
```

return the table that map the md5 (as in md5sum) of the Pixel Data associated to a filename

10.313.2.2 MediaStorageDataFileType

```
typedef const char* const (* gdcm::Testing::MediaStorageDataFileType) [2]
```

return the table that map the media storage (as string) of a filename (gdcmData)

10.313.3 Constructor & Destructor Documentation

10.313.3.1 Testing()

```
gdcm::Testing::Testing () [default]
```

10.313.3.2 ~Testing()

```
gdcm::Testing::~~Testing () [default]
```

10.313.4 Member Function Documentation

10.313.4.1 ComputeFileMD5()

```
bool gdcM::Testing::ComputeFileMD5 (
    const char * filename,
    char digest_str[33]) [static]
```

Examples

[MetalImageMD5Activiz.cs](#).

10.313.4.2 ComputeMD5()

```
bool gdcM::Testing::ComputeMD5 (
    const char * buffer,
    size_t buf_len,
    char digest_str[33]) [static]
```

[MD5](#) stuff digest_str needs to be at least : strlen = [2*16+1]; string will be \0 padded. (md5 are 32 bytes long) [Testing](#) is not meant to be shipped with an installed GDCM release, always prefer the [gdcM::MD5](#) API when doing md5 computation.

10.313.4.3 GetDataExtraRoot()

```
const char * gdcM::Testing::GetDataExtraRoot () [static]
```

Return the GDCM DATA EXTRA ROOT.

Examples

[DiscriminateVolume.cxx](#), [VolumeSorter.cxx](#), and [reslicesphere.cxx](#).

10.313.4.4 GetDataRoot()

```
const char * gdcM::Testing::GetDataRoot () [static]
```

Return the GDCM DATA ROOT.

Examples

[Convert16BitsTo8Bits.cxx](#), [ConvertMultiFrameToSingleFrame.cxx](#), [ConvertRGBToLuminance.cxx](#), and [MagnifyFile.cxx](#).

10.313.4.5 GetFileName()

```
const char * gdcm::Testing::GetFileName (
    unsigned int file) [static]
```

Examples

[MetaImageMD5Activiz.cs](#).

10.313.4.6 GetFileNames()

```
const char *const * gdcm::Testing::GetFileNames () [static]
```

return the table of fullpath to gdcmData DICOM files:

Examples

[TestReader.cxx](#).

10.313.4.7 GetLossyFlagFromFile()

```
int gdcm::Testing::GetLossyFlagFromFile (
    const char * filepath) [static]
```

Return the lossy flag of the given filename -1 -> Error 0 -> Lossless 1 -> Lossy

10.313.4.8 GetMD5DataImage()

```
const char *const * gdcm::Testing::GetMD5DataImage (
    unsigned int file) [static]
```

10.313.4.9 GetMD5DataImages()

```
MD5DataImagesType gdcm::Testing::GetMD5DataImages () [static]
```

10.313.4.10 GetMD5FromBrokenFile()

```
const char * gdcm::Testing::GetMD5FromBrokenFile (
    const char * filepath) [static]
```

Return what should have been the md5 of file 'filepath' This is based on current GDCM implementation to decipher a broken DICOM file.

10.313.4.11 GetMD5FromFile()

```
const char * gdcm::Testing::GetMD5FromFile (
    const char * filepath) [static]
```

10.313.4.12 GetMediaStorageDataFile()

```
const char *const * gdcm::Testing::GetMediaStorageDataFile (
    unsigned int file) [static]
```

10.313.4.13 GetMediaStorageDataFiles()

```
MediaStorageDataFilesType gdcm::Testing::GetMediaStorageDataFiles () [static]
```

10.313.4.14 GetMediaStorageFromFile()

```
const char * gdcm::Testing::GetMediaStorageFromFile (
    const char * filepath) [static]
```

Examples

[MetImageMD5Activiz.cs](#), and [TestReader.cxx](#).

10.313.4.15 GetNumberOfFileNames()

```
unsigned int gdcm::Testing::GetNumberOfFileNames () [static]
```

Examples

[MetImageMD5Activiz.cs](#).

10.313.4.16 GetNumberOfMD5DataImages()

```
unsigned int gdcm::Testing::GetNumberOfMD5DataImages () [static]
```

10.313.4.17 GetNumberOfMediaStorageDataFiles()

```
unsigned int gdcm::Testing::GetNumberOfMediaStorageDataFiles () [static]
```


10.313.4.18 GetPixelSpacingDataRoot()

```
const char * gdcM::Testing::GetPixelSpacingDataRoot () [static]
```

Return the GDCM PIXEL SPACING DATA ROOT (See David Clunie website for dataset)

10.313.4.19 GetSelectedPrivateGroupOffsetFromFile()

```
std::streamoff gdcM::Testing::GetSelectedPrivateGroupOffsetFromFile (
    const char * filepath) [static]
```

Return the offset just after private attribute (0009,0010,"GEMS_IDEN_01") if found. Otherwise the offset of the next attribute -1 if not found

10.313.4.20 GetSelectedTagsOffsetFromFile()

```
std::streamoff gdcM::Testing::GetSelectedTagsOffsetFromFile (
    const char * filepath) [static]
```

Return the offset just after Pixel Data Length (7fe0,0000) if found. Otherwise the offset of the very first pixel cell in Pixel Data -1 if not found

10.313.4.21 GetSourceDirectory()

```
const char * gdcM::Testing::GetSourceDirectory () [static]
```

10.313.4.22 GetStreamOffsetFromFile()

```
std::streamoff gdcM::Testing::GetStreamOffsetFromFile (
    const char * filepath) [static]
```

Return the offset of the very first pixel cell in the PixelData -1 if not found

10.313.4.23 GetTempDirectory()

```
const char * gdcM::Testing::GetTempDirectory (
    const char * subdir = nullptr) [static]
```

NOT THREAD SAFE Returns the temp directory as used in testing needing to output data:

Examples

[MetalImageMD5Activiz.cs](#).

10.313.4.24 GetTempDirectoryW()

```
const wchar_t * gdcM::Testing::GetTempDirectoryW (  
    const wchar_t * subdir = nullptr) [static]
```

NOT THREAD SAFE.

10.313.4.25 GetTempFilename()

```
const char * gdcM::Testing::GetTempFilename (  
    const char * filename,  
    const char * subdir = nullptr) [static]
```

NOT THREAD SAFE.

Examples

[MetalImageMD5Activiz.cs](#).

10.313.4.26 GetTempFilenameW()

```
const wchar_t * gdcM::Testing::GetTempFilenameW (  
    const wchar_t * filename,  
    const wchar_t * subdir = nullptr) [static]
```

NOT THREAD SAFE.

10.313.4.27 Print()

```
void gdcM::Testing::Print (  
    std::ostream & os = std::cout)
```

Print.

The documentation for this class was generated from the following file:

- [gdcMTesting.h](#)

10.314 gdcM::Trace Class Reference

[Trace](#).

```
#include <gdcMTrace.h>
```

Public Member Functions

- [Trace](#) ()
- [~Trace](#) ()

Static Public Member Functions

- static void [DebugOff](#) ()
- static void [DebugOn](#) ()
- static void [ErrorOff](#) ()
- static void [ErrorOn](#) ()
- static bool [GetDebugFlag](#) ()
- static std::ostream & [GetDebugStream](#) ()
- static bool [GetErrorFlag](#) ()
- static std::ostream & [GetErrorStream](#) ()
- static std::ostream & [GetStream](#) ()
- static bool [GetWarningFlag](#) ()
- static std::ostream & [GetWarningStream](#) ()
- static void [SetDebug](#) (bool debug)
Turn debug messages on (default: false)
- static void [SetDebugStream](#) (std::ostream &os)
Explicitly set the stream which receive Debug messages:
- static void [SetError](#) (bool debug)
Turn error messages on (default: true)
- static void [SetErrorStream](#) (std::ostream &os)
Explicitly set the stream which receive Error messages:
- static void [SetStream](#) (std::ostream &os)
- static void [SetStreamToFile](#) (const char *filename)
- static void [SetWarning](#) (bool debug)
Turn warning messages on (default: true)
- static void [SetWarningStream](#) (std::ostream &os)
Explicitly set the stream which receive Warning messages:
- static void [WarningOff](#) ()
- static void [WarningOn](#) ()

10.314.1 Detailed Description

[Trace](#).

Debug / Warning and Error are encapsulated in this class by default the [Trace](#) class will redirect any debug/warning/error to std::cerr. Unless SetStream was specified with another (open) stream or SetStreamToFile was specified to a writable file on the system.

Warning

All string messages are removed during compilation time when compiled with CMAKE_BUILD_TYPE being set to either:

- Release
- MinSizeRel It is recommended to compile with RelWithDebInfo and/or Debug during prototyping of applications.

Examples

[DecompressJPEGFile.cs](#).

10.314.2 Constructor & Destructor Documentation

10.314.2.1 Trace()

```
gdcM::Trace::Trace ()
```

10.314.2.2 ~Trace()

```
gdcM::Trace::~~Trace ()
```

10.314.3 Member Function Documentation

10.314.3.1 DebugOff()

```
void gdcM::Trace::DebugOff () [static]
```

Examples

[MetalImageMD5Activiz.cs](#), and [TestReader.cxx](#).

10.314.3.2 DebugOn()

```
void gdcM::Trace::DebugOn () [static]
```

Examples

[CreateFakePET.cxx](#), [DecompressJPEGFile.cs](#), [Fake_Image_Using_Stream_Image_Writer.cxx](#), and [StreamImageReaderTest.cxx](#).

10.314.3.3 ErrorOff()

```
void gdcM::Trace::ErrorOff () [static]
```

Examples

[MetalImageMD5Activiz.cs](#).

10.314.3.4 ErrorOn()

```
void gdcM::Trace::ErrorOn () [static]
```

10.314.3.5 GetDebugFlag()

```
bool gdcm::Trace::GetDebugFlag () [static]
```

10.314.3.6 GetDebugStream()

```
std::ostream & gdcm::Trace::GetDebugStream () [static]
```

10.314.3.7 GetErrorFlag()

```
bool gdcm::Trace::GetErrorFlag () [static]
```

10.314.3.8 GetErrorStream()

```
std::ostream & gdcm::Trace::GetErrorStream () [static]
```

10.314.3.9 GetStream()

```
std::ostream & gdcm::Trace::GetStream () [static]
```

10.314.3.10 GetWarningFlag()

```
bool gdcm::Trace::GetWarningFlag () [static]
```

10.314.3.11 GetWarningStream()

```
std::ostream & gdcm::Trace::GetWarningStream () [static]
```

10.314.3.12 SetDebug()

```
void gdcm::Trace::SetDebug (  
    bool debug) [static]
```

Turn debug messages on (default: false)

Examples

[DumpToSQLITE3.cxx](#).

10.314.3.13 SetDebugStream()

```
void gdcmm::Trace::SetDebugStream (
    std::ostream & os) [static]
```

Explicitly set the stream which receive Debug messages:

10.314.3.14 SetError()

```
void gdcmm::Trace::SetError (
    bool debug) [static]
```

Turn error messages on (default: true)

10.314.3.15 SetErrorStream()

```
void gdcmm::Trace::SetErrorStream (
    std::ostream & os) [static]
```

Explicitly set the stream which receive Error messages:

Examples

[CStoreQtProgress.cxx](#).

10.314.3.16 SetStream()

```
void gdcmm::Trace::SetStream (
    std::ostream & os) [static]
```

Explicitly set the ostream for [gdcmm::Trace](#) to report to This will set the DebugStream, WarningStream and ErrorStream at once:

10.314.3.17 SetStreamToFile()

```
void gdcmm::Trace::SetStreamToFile (
    const char * filename) [static]
```

Explicitly set the filename for [gdcmm::Trace](#) to report to The file will be created (it will not append to existing file)

10.314.3.18 SetWarning()

```
void gdcm::Trace::SetWarning (
    bool debug) [static]
```

Turn warning messages on (default: true)

Examples

[DumpToSQLITE3.cxx](#).

10.314.3.19 SetWarningStream()

```
void gdcm::Trace::SetWarningStream (
    std::ostream & os) [static]
```

Explicitly set the stream which receive Warning messages:

10.314.3.20 WarningOff()

```
void gdcm::Trace::WarningOff () [static]
```

Examples

[MetalImageMD5Activiz.cs](#), and [TestReader.cxx](#).

10.314.3.21 WarningOn()

```
void gdcm::Trace::WarningOn () [static]
```

Examples

[Fake_Image_Using_Stream_Image_Writer.cxx](#), and [StreamImageReaderTest.cxx](#).

The documentation for this class was generated from the following file:

- [gdcmTrace.h](#)

10.315 gdcm::TransferSyntax Class Reference

Class to manipulate Transfer Syntax.

```
#include <gdcmTransferSyntax.h>
```

Public Types

- enum [NegociatedType](#) {
 [Unknown](#) = 0 ,
 [Explicit](#) ,
 [Implicit](#) }
- enum [TSType](#) {
 [ImplicitVRLittleEndian](#) = 0 ,
 [ImplicitVRBigEndianPrivateGE](#) ,
 [ExplicitVRLittleEndian](#) ,
 [DeflatedExplicitVRLittleEndian](#) ,
 [ExplicitVRBigEndian](#) ,
 [JPEGBaselineProcess1](#) ,
 [JPEGExtendedProcess2_4](#) ,
 [JPEGExtendedProcess3_5](#) ,
 [JPEGSpectralSelectionProcess6_8](#) ,
 [JPEGFullProgressionProcess10_12](#) ,
 [JPEGLosslessProcess14](#) ,
 [JPEGLosslessProcess14_1](#) ,
 [JPEGLSLossless](#) ,
 [JPEGLSNearLossless](#) ,
 [JPEG2000Lossless](#) ,
 [JPEG2000](#) ,
 [JPEG2000Part2Lossless](#) ,
 [JPEG2000Part2](#) ,
 [RLELossless](#) ,
 [MPEG2MainProfile](#) ,
 [ImplicitVRBigEndianACRNEMA](#) ,
 [WeirdPapryus](#) ,
 [CT_private_ELE](#) ,
 [JPIPReferenced](#) ,
 [MPEG2MainProfileHighLevel](#) ,
 [MPEG4AVCH264HighProfileLevel4_1](#) ,
 [MPEG4AVCH264BDcompatibleHighProfileLevel4_1](#) ,
 [HTJ2KLossless](#) ,
 [HTJ2KRPCLLossless](#) ,
 [HTJ2K](#) ,
 [TS_END](#) }

Public Member Functions

- [TransferSyntax](#) ([TSType](#) type=[ImplicitVRLittleEndian](#))
- bool [CanStoreLossy](#) () const
- [NegociatedType](#) [GetNegociatedType](#) () const
- const char * [GetString](#) () const
- [SwapCode](#) [GetSwapCode](#) () const
- bool [IsEncapsulated](#) () const
- bool [IsEncoded](#) () const
- bool [IsExplicit](#) () const
- bool [IsImplicit](#) () const
- bool [IsLossless](#) () const
- bool [IsLossy](#) () const
- bool [IsValid](#) () const
- [operator TSType](#) () const

Static Public Member Functions

- static const char * [GetTSSString](#) (TSType ts)
- static TSType [GetTSType](#) (const char *str)

Friends

- std::ostream & [operator<<](#) (std::ostream &os, const [TransferSyntax](#) &ts)

10.315.1 Detailed Description

Class to manipulate Transfer Syntax.

Note

TRANSFER SYNTAX (Standard and Private): A set of encoding rules that allow Application Entities to unambiguously negotiate the encoding techniques (e.g., Data [Element](#) structure, byte ordering, compression) they are able to support, thereby allowing these Application Entities to communicate.

Todo : The implementation is completely retarded -> see [gdcm::UIDs](#) for a replacement We need: IsSupported We need preprocess of raw/xml file We need GetFullName()

Need a notion of Private Syntax. As defined in PS 3.5. Section 9.2

See also

[UIDs](#)

Examples

[BasicImageAnonymizer.cs](#), [CompressLossyJPEG.cs](#), [DecompressImageMultiframe.cs](#), [DecompressJPEGFile.cs](#), [ExplicitLittleEndian.cs](#), [FileChangeTS.cs](#), [FileChangeTSLossy.cs](#), [GetJPEGSamplePrecision.cxx](#), [LargeVRDSExplicit.cxx](#), [MakeTemplate.cxx](#), [MpegVideoInfo.cs](#), and [StandardizeFiles.cs](#).

10.315.2 Member Enumeration Documentation

10.315.2.1 NegotiatedType

```
enum gdcm::TransferSyntax::NegociatedType
```

Enumerator

Unknown	
Explicit	
Implicit	

10.315.2.2 TSType

```
enum gdcm::TransferSyntax::TSType
```

Enumerator

ImplicitVRLittleEndian	
ImplicitVRBigEndianPrivateGE	
ExplicitVRLittleEndian	
DeflatedExplicitVRLittleEndian	
ExplicitVRBigEndian	
JPEGBaselineProcess1	
JPEGExtendedProcess2_4	
JPEGExtendedProcess3_5	
JPEGSpectralSelectionProcess6_8	
JPEGFullProgressionProcess10_12	
JPEGLosslessProcess14	
JPEGLosslessProcess14_1	
JPEGLSLossless	
JPEGLSNearLossless	
JPEG2000Lossless	
JPEG2000	
JPEG2000Part2Lossless	
JPEG2000Part2	
RLELossless	
MPEG2MainProfile	
ImplicitVRBigEndianACRNEMA	
WeirdPapryus	
CT_private_ELE	
JPIPReferenced	
MPEG2MainProfileHighLevel	
MPEG4AVCH264HighProfileLevel4_1	
MPEG4AVCH264BDcompatibleHighProfileLevel4↔ _1	
HTJ2KLossless	
HTJ2KRPCLLossless	
HTJ2K	
TS_END	

Examples

[BasicImageAnonymizer.cs](#), [CompressLossyJPEG.cs](#), [DecompressImageMultiframe.cs](#), [DecompressJPEGFile.cs](#), [ExplicitLittleEndian.cs](#), [FileChangeTS.cs](#), [FileChangeTSLossy.cs](#), [MpegVideoInfo.cs](#), and [StandardizeFiles.cs](#).

10.315.3 Constructor & Destructor Documentation

10.315.3.1 TransferSyntax()

```
gdcm::TransferSyntax::TransferSyntax (
    TSType type = ImplicitVRLittleEndian) [inline]
```

References [ImplicitVRLittleEndian](#).

Referenced by [operator<<](#).

10.315.4 Member Function Documentation

10.315.4.1 CanStoreLossy()

```
bool gdcm::TransferSyntax::CanStoreLossy () const
```

return true if TransFer Syntax Allow storing of Lossy Pixel Data

10.315.4.2 GetNegociatedType()

```
NegociatedType gdcm::TransferSyntax::GetNegociatedType () const
```

10.315.4.3 GetString()

```
const char * gdcm::TransferSyntax::GetString () const [inline]
```

References [GetTSString\(\)](#).

10.315.4.4 GetSwapCode()

```
SwapCode gdcm::TransferSyntax::GetSwapCode () const
```

Deprecated Return the [SwapCode](#) associated with the Transfer Syntax. Be careful with the special GE private syntax the [DataSet](#) is written in little endian but the Pixel Data is in Big Endian.

10.315.4.5 GetTSString()

```
const char * gdcm::TransferSyntax::GetTSString (
    TSType ts) [static]
```

Examples

[LargeVRDSExplicit.cxx](#).

Referenced by [GetString\(\)](#), and [operator<<](#).

10.315.4.6 GetTSType()

```
TSType gdcM::TransferSyntax::GetTSType (  
    const char * str) [static]
```

10.315.4.7 IsEncapsulated()

```
bool gdcM::TransferSyntax::IsEncapsulated () const
```

Examples

[ExtractIconFromFile.cxx](#).

10.315.4.8 IsEncoded()

```
bool gdcM::TransferSyntax::IsEncoded () const
```

10.315.4.9 IsExplicit()

```
bool gdcM::TransferSyntax::IsExplicit () const
```

10.315.4.10 IsImplicit()

```
bool gdcM::TransferSyntax::IsImplicit () const
```

10.315.4.11 IsLossless()

```
bool gdcM::TransferSyntax::IsLossless () const
```

Return true if the transfer syntax algorithm is a lossless algorithm

10.315.4.12 IsLossy()

```
bool gdcM::TransferSyntax::IsLossy () const
```

Return true if the transfer syntax algorithm is a lossy algorithm

10.315.4.13 IsValid()

```
bool gdcM::TransferSyntax::IsValid () const [inline]
```

References [TS_END](#).

10.315.4.14 operator TType()

```
gdcm::TransferSyntax::operator TType () const [inline]
```

10.315.5 Friends And Related Symbol Documentation

10.315.5.1 operator<<

```
std::ostream & operator<< (
    std::ostream & os,
    const TransferSyntax & ts) [friend]
```

References [TransferSyntax\(\)](#), and [GetTSString\(\)](#).

The documentation for this class was generated from the following file:

- [gdcmTransferSyntax.h](#)

10.316 gdcm::network::TransferSyntaxSub Class Reference

[TransferSyntaxSub](#).

```
#include <gdcmTransferSyntaxSub.h>
```

Public Member Functions

- [TransferSyntaxSub](#) ()
- const char * [GetName](#) () const
- bool [operator==](#) (const [TransferSyntaxSub](#) &ts) const
- void [Print](#) (std::ostream &os) const
- std::istream & [Read](#) (std::istream &is)
- void [SetName](#) (const char *name)
- void [SetNameFromUID](#) (UIDs::TSName tsname)
- size_t [Size](#) () const
- const std::ostream & [Write](#) (std::ostream &os) const

10.316.1 Detailed Description

[TransferSyntaxSub](#).

[Table](#) 9-15 TRANSFER SYNTAX SUB-ITEM FIELDS

TODO what is the goal of :

[Table](#) 9-19 TRANSFER SYNTAX SUB-ITEM FIELDS

10.316.2 Constructor & Destructor Documentation

10.316.2.1 TransferSyntaxSub()

```
gdcm::network::TransferSyntaxSub::TransferSyntaxSub ()
```

Referenced by [operator==\(.\)](#).

10.316.3 Member Function Documentation

10.316.3.1 GetName()

```
const char * gdcm::network::TransferSyntaxSub::GetName () const [inline]
```

10.316.3.2 operator==(.)

```
bool gdcm::network::TransferSyntaxSub::operator== (
    const TransferSyntaxSub & ts) const [inline]
```

References [TransferSyntaxSub\(\)](#).

10.316.3.3 Print()

```
void gdcm::network::TransferSyntaxSub::Print (
    std::ostream & os) const
```

10.316.3.4 Read()

```
std::istream & gdcm::network::TransferSyntaxSub::Read (
    std::istream & is)
```

10.316.3.5 SetName()

```
void gdcm::network::TransferSyntaxSub::SetName (
    const char * name)
```

10.316.3.6 SetNameFromUID()

```
void gdcm::network::TransferSyntaxSub::SetNameFromUID (
    UIDs::TSName tsname)
```

10.316.3.7 Size()

```
size_t gdcm::network::TransferSyntaxSub::Size () const
```

10.316.3.8 Write()

```
const std::ostream & gdcm::network::TransferSyntaxSub::Write (  
    std::ostream & os) const
```


The documentation for this class was generated from the following file:

- [gdcmTransferSyntaxSub.h](#)

10.317 gdcm::network::Transition Struct Reference

```
#include <gdcmULTransitionTable.h>
```

Collaboration diagram for gdcm::network::Transition:



Public Member Functions

- [Transition](#) ()
- [Transition](#) (int inEndState, [ULAction](#) *inAction)
- [~Transition](#) ()

Static Public Member Functions

- static [Transition](#) * [MakeNew](#) (int inEndState, [ULAction](#) *inAction)

Public Attributes

- [ULAction](#) * [mAction](#)
- int [mEnd](#)

10.317.1 Constructor & Destructor Documentation

10.317.1.1 Transition() [1/2]

```
gdcmm::network::Transition::Transition () [inline]
```

References [gdcmm::network::eStaDoesNotExist](#), [mAction](#), and [mEnd](#).

Referenced by [MakeNew\(\)](#).

10.317.1.2 ~Transition()

```
gdcmm::network::Transition::~~Transition () [inline]
```

References [mAction](#).

10.317.1.3 Transition() [2/2]

```
gdcmm::network::Transition::Transition (  
    int inEndState,  
    ULAction * inAction) [inline]
```

References [mAction](#), and [mEnd](#).

10.317.2 Member Function Documentation

10.317.2.1 MakeNew()

```
Transition * gdcmm::network::Transition::MakeNew (  
    int inEndState,  
    ULAction * inAction) [inline], [static]
```

References [Transition\(\)](#).

10.317.3 Member Data Documentation

10.317.3.1 mAction

```
ULAction* gdcmm::network::Transition::mAction
```

Referenced by [Transition\(\)](#), [Transition\(\)](#), and [~Transition\(\)](#).

10.317.3.2 mEnd

```
int gdcm::network::Transition::mEnd
```

Referenced by [Transition\(\)](#), and [Transition\(\)](#).

The documentation for this struct was generated from the following file:

- [gdcmULTransitionTable.h](#)

10.318 gdcm::Type Class Reference

[Type](#).

```
#include <gdcmType.h>
```

Public Types

- enum [TypeType](#) {
 [T1](#) = 0 ,
 [T1C](#) ,
 [T2](#) ,
 [T2C](#) ,
 [T3](#) ,
 [UNKNOWN](#) }

Public Member Functions

- [Type](#) ([TypeType](#) type=[UNKNOWN](#))
- [operator TypeType](#) () const

Static Public Member Functions

- static const char * [GetTypeString](#) ([TypeType](#) type)
- static [TypeType](#) [GetTypeType](#) (const char *type)

Friends

- std::ostream & [operator<<](#) (std::ostream &os, const [Type](#) &vr)

10.318.1 Detailed Description

Type.

Note

PS 3.5 7.4 DATA ELEMENT TYPE 7.4.1 TYPE 1 REQUIRED DATA ELEMENTS 7.4.2 TYPE 1C CONDITIONAL DATA ELEMENTS 7.4.3 TYPE 2 REQUIRED DATA ELEMENTS 7.4.4 TYPE 2C CONDITIONAL DATA ELEMENTS 7.4.5 TYPE 3 OPTIONAL DATA ELEMENTS

The intent of [Type](#) 2 Data Elements is to allow a zero length to be conveyed when the operator or application does not know its value or has a specific reason for not specifying its value. It is the intent that the device should support these Data Elements.

Examples

[TraverseModules.cxx](#).

10.318.2 Member Enumeration Documentation

10.318.2.1 TypeType

```
enum gdcmm::Type::TypeType
```

Enumerator

T1	
T1C	
T2	
T2C	
T3	
UNKNOWN	

10.318.3 Constructor & Destructor Documentation

10.318.3.1 Type()

```
gdcmm::Type::Type (  
    TypeType type = UNKNOWN) [inline]
```

References [UNKNOWN](#).

Referenced by [operator<<](#).

10.318.4 Member Function Documentation

10.318.4.1 GetTypeString()

```
const char * gdcm::Type::GetTypeString (
    TypeType type) [static]
```

Referenced by [operator<<](#).

10.318.4.2 GetTypeType()

```
TypeType gdcm::Type::GetTypeType (
    const char * type) [static]
```

Referenced by [gdcm::ModuleEntry::ModuleEntry\(\)](#).

10.318.4.3 operator TypeType()

```
gdcm::Type::operator TypeType () const [inline]
```

10.318.5 Friends And Related Symbol Documentation

10.318.5.1 operator<<

```
std::ostream & operator<< (
    std::ostream & os,
    const Type & vr) [friend]
```

References [Type\(\)](#), and [GetTypeString\(\)](#).

The documentation for this class was generated from the following file:

- [gdcmType.h](#)

10.319 gdcm::UI Struct Reference

```
#include <gdcmVR.h>
```

Public Attributes

- char [Internal](#) [64+1]

Friends

- `std::ostream & operator<< (std::ostream &_os, const UI &_val)`

10.319.1 Friends And Related Symbol Documentation

10.319.1.1 `operator<<`

```
std::ostream & operator<< (
    std::ostream & _os,
    const UI & _val) [friend]
```

References [Internal](#).

10.319.2 Member Data Documentation

10.319.2.1 Internal

```
char gdcmm::UI::Internal[64+1]
```

Referenced by [operator<<](#).

The documentation for this struct was generated from the following file:

- [gdcmmVR.h](#)

10.320 `gdcmm::UIDGenerator` Class Reference

Class for generating unique UID.

```
#include <gdcmmUIDGenerator.h>
```

Public Member Functions

- [UIDGenerator](#) ()
By default the root of a UID is a GDCM Root...
- const char * [Generate](#) ()

Static Public Member Functions

- static const char * [GetGDCMUID](#) ()
Return the default (GDCM) root UID:
- static const char * [GetRoot](#) ()
- static bool [IsValid](#) (const char *uid)
- static void [SetRoot](#) (const char *root)

Static Protected Member Functions

- static bool [GenerateUUID](#) (unsigned char *uuid_data)

10.320.1 Detailed Description

Class for generating unique UID.

When constructing a [Series](#) or [Study](#) UID, user *has* to keep around the UID, otherwise the UID Generator will simply forget the value and create a new UID.

Examples

[CreateJPIPDataSet.cxx](#), [EncapsulateFileInRawData.cxx](#), [Extracting_All_Resolution.cxx](#), [Fake_Image_Using_Stream_Image_Writer](#), [GenAllVR.cxx](#), [GenFakeIdentifyFile.cxx](#), [GenFakeImage.cxx](#), [GetSubSequenceData.cxx](#), [ManipulateFile.cs](#), [MpegVideoInfo.cs](#), [ReformatFile.cs](#), [StreamImageReaderTest.cxx](#), [TemplateEmptyImage.cxx](#), and [uid_unique.cxx](#).

10.320.2 Constructor & Destructor Documentation

10.320.2.1 UIDGenerator()

```
gdcmm::UIDGenerator::UIDGenerator () [inline]
```

By default the root of a UID is a GDCM Root...

10.320.3 Member Function Documentation

10.320.3.1 Generate()

```
const char * gdcmm::UIDGenerator::Generate ()
```

Internally uses a std::string, so two calls have the same pointer ! save into a std::string In summary do not write code like that: const char *uid1 = uid.Generate(); const char *uid2 = uid.Generate(); since uid1 == uid2

Examples

[CreateJPIPDataSet.cxx](#), [EncapsulateFileInRawData.cxx](#), [Extracting_All_Resolution.cxx](#), [Fake_Image_Using_Stream_Image_Writer](#), [GenAllVR.cxx](#), [GenFakeIdentifyFile.cxx](#), [GenFakeImage.cxx](#), [GetSubSequenceData.cxx](#), [ManipulateFile.cs](#), [ReformatFile.cs](#), [StreamImageReaderTest.cxx](#), [TemplateEmptyImage.cxx](#), and [uid_unique.cxx](#).

10.320.3.2 GenerateUUID()

```
bool gdcmm::UIDGenerator::GenerateUUID (
    unsigned char * uuid_data) [static], [protected]
```

10.320.3.3 GetGDCMUID()

```
const char * gdc::UIDGenerator::GetGDCMUID () [static]
```

Return the default (GDCM) root UID:

10.320.3.4 GetRoot()

```
const char * gdc::UIDGenerator::GetRoot () [static]
```

Examples

[ExplicitLittleEndian.cs](#), [ReformatFile.cs](#), and [StandardizeFiles.cs](#).

10.320.3.5 IsValid()

```
bool gdc::UIDGenerator::IsValid (
    const char * uid) [static]
```

Find out if the string is a valid UID or not

Todo : Move that in DataStructureAndEncoding (see FileMetaInformation::CheckFileMetaInformation)

10.320.3.6 SetRoot()

```
void gdc::UIDGenerator::SetRoot (
    const char * root) [static]
```

The current implementation in GDCM make use of the UUID implementation (RFC 4122) and has been successfully been tested for a root of size 26 bytes. Any longer root should work (the [Generate\(\)](#) function will return a string), but will truncate the high bits of the 128bits UUID until the generated string fits on 64 bits. The authors disclaims any responsablility for guaranteeing uniqueness of [UIDs](#) when the root is longer than 26 bytes.

Examples

[ExplicitLittleEndian.cs](#), [ReformatFile.cs](#), [StandardizeFiles.cs](#), and [uid_unique.cxx](#).

The documentation for this class was generated from the following file:

- [gdc::UIDGenerator.h](#)

10.321 gdcm::UIDs Class Reference

all known uids

```
#include <gdcmUIDs.h>
```

Public Types

- typedef const char *const (* [TransferSyntaxStringsType](#))[2]
- enum [TSName](#) {
 - [VerificationSOPClass](#) = 1 ,
 - [ImplicitVRLittleEndianDefaultTransferSyntaxforDICOM](#) = 2 ,
 - [ExplicitVRLittleEndian](#) = 3 ,
 - [DeflatedExplicitVRLittleEndian](#) = 4 ,
 - [ExplicitVRBigEndian](#) = 5 ,
 - [JPEGBaselineProcess1DefaultTransferSyntaxforLossyJPEG8BitImageCompression](#) = 6 ,
 - [JPEGExtendedProcess24DefaultTransferSyntaxforLossyJPEG12BitImageCompressionProcess4only](#) = 7 ,
 - [JPEGExtendedProcess35Retired](#) = 8 ,
 - [JPEGSpectralSelectionNonHierarchicalProcess68Retired](#) = 9 ,
 - [JPEGSpectralSelectionNonHierarchicalProcess79Retired](#) = 10 ,
 - [JPEGFullProgressionNonHierarchicalProcess1012Retired](#) = 11 ,
 - [JPEGFullProgressionNonHierarchicalProcess1113Retired](#) = 12 ,
 - [JPEGLosslessNonHierarchicalProcess14](#) = 13 ,
 - [JPEGLosslessNonHierarchicalProcess15Retired](#) = 14 ,
 - [JPEGExtendedHierarchicalProcess1618Retired](#) = 15 ,
 - [JPEGExtendedHierarchicalProcess1719Retired](#) = 16 ,
 - [JPEGSpectralSelectionHierarchicalProcess2022Retired](#) = 17 ,
 - [JPEGSpectralSelectionHierarchicalProcess2123Retired](#) = 18 ,
 - [JPEGFullProgressionHierarchicalProcess2426Retired](#) = 19 ,
 - [JPEGFullProgressionHierarchicalProcess2527Retired](#) = 20 ,
 - [JPEGLosslessHierarchicalProcess28Retired](#) = 21 ,
 - [JPEGLosslessHierarchicalProcess29Retired](#) = 22 ,
 - [JPEGLosslessNonHierarchicalFirstOrderPredictionProcess14SelectionValue1DefaultTransferSyntaxforLosslessJPEGImageCompression](#) = 23 ,
 - [JPEGLSLosslessImageCompression](#) = 24 ,
 - [JPEGLSLossyNearLosslessImageCompression](#) = 25 ,
 - [JPEG2000ImageCompressionLosslessOnly](#) = 26 ,
 - [JPEG2000ImageCompression](#) = 27 ,
 - [JPEG2000Part2MulticomponentImageCompressionLosslessOnly](#) = 28 ,
 - [JPEG2000Part2MulticomponentImageCompression](#) = 29 ,
 - [JPIPReferenced](#) = 30 ,
 - [JPIPReferencedDeflate](#) = 31 ,
 - [MPEG2MainProfileMainLevel](#) = 32 ,
 - [RLELossless](#) = 33 ,
 - [RFC2557MIMEencapsulation](#) = 34 ,
 - [XMLEncoding](#) = 35 ,
 - [MediaStorageDirectoryStorage](#) = 36 ,
 - [TalairachBrainAtlasFrameofReference](#) = 37 ,
 - [SPM2T1FrameofReference](#) = 38 ,
 - [SPM2T2FrameofReference](#) = 39 ,
 - [SPM2PDFFrameofReference](#) = 40 ,
 - [SPM2EPIFrameofReference](#) = 41 ,

[SPM2FILT1FrameofReference](#) = 42 ,
[SPM2PETFrameofReference](#) = 43 ,
[SPM2TRANSMFrameofReference](#) = 44 ,
[SPM2SPECTFrameofReference](#) = 45 ,
[SPM2GRAYFrameofReference](#) = 46 ,
[SPM2WHITEFrameofReference](#) = 47 ,
[SPM2CSFFFrameofReference](#) = 48 ,
[SPM2BRAINMASKFrameofReference](#) = 49 ,
[SPM2AVG305T1FrameofReference](#) = 50 ,
[SPM2AVG152T1FrameofReference](#) = 51 ,
[SPM2AVG152T2FrameofReference](#) = 52 ,
[SPM2AVG152PDFrameofReference](#) = 53 ,
[SPM2SINGLESUBJT1FrameofReference](#) = 54 ,
[ICBM452T1FrameofReference](#) = 55 ,
[ICBMSingleSubjectMRIFrameofReference](#) = 56 ,
[BasicStudyContentNotificationSOPClassRetired](#) = 57 ,
[StorageCommitmentPushModelSOPClass](#) = 58 ,
[StorageCommitmentPushModelSOPInstance](#) = 59 ,
[StorageCommitmentPullModelSOPClassRetired](#) = 60 ,
[StorageCommitmentPullModelSOPInstanceRetired](#) = 61 ,
[ProceduralEventLoggingSOPClass](#) = 62 ,
[ProceduralEventLoggingSOPInstance](#) = 63 ,
[SubstanceAdministrationLoggingSOPClass](#) = 64 ,
[SubstanceAdministrationLoggingSOPInstance](#) = 65 ,
[DICOMUIDRegistry](#) = 66 ,
[DICOMControlledTerminology](#) = 67 ,
[DICOMApplicationContextName](#) = 68 ,
[DetachedPatientManagementSOPClassRetired](#) = 69 ,
[DetachedPatientManagementMetaSOPClassRetired](#) = 70 ,
[DetachedVisitManagementSOPClassRetired](#) = 71 ,
[DetachedStudyManagementSOPClassRetired](#) = 72 ,
[StudyComponentManagementSOPClassRetired](#) = 73 ,
[ModalityPerformedProcedureStepSOPClass](#) = 74 ,
[ModalityPerformedProcedureStepRetrieveSOPClass](#) = 75 ,
[ModalityPerformedProcedureStepNotificationSOPClass](#) = 76 ,
[DetachedResultsManagementSOPClassRetired](#) = 77 ,
[DetachedResultsManagementMetaSOPClassRetired](#) = 78 ,
[DetachedStudyManagementMetaSOPClassRetired](#) = 79 ,
[DetachedInterpretationManagementSOPClassRetired](#) = 80 ,
[StorageServiceClass](#) = 81 ,
[BasicFilmSessionSOPClass](#) = 82 ,
[BasicFilmBoxSOPClass](#) = 83 ,
[BasicGrayscaleImageBoxSOPClass](#) = 84 ,
[BasicColorImageBoxSOPClass](#) = 85 ,
[ReferencedImageBoxSOPClassRetired](#) = 86 ,
[BasicGrayscalePrintManagementMetaSOPClass](#) = 87 ,
[ReferencedGrayscalePrintManagementMetaSOPClassRetired](#) = 88 ,
[PrintJobSOPClass](#) = 89 ,
[BasicAnnotationBoxSOPClass](#) = 90 ,
[PrinterSOPClass](#) = 91 ,
[PrinterConfigurationRetrievalSOPClass](#) = 92 ,
[PrinterSOPInstance](#) = 93 ,
[PrinterConfigurationRetrievalSOPInstance](#) = 94 ,
[BasicColorPrintManagementMetaSOPClass](#) = 95 ,

[ReferencedColorPrintManagementMetaSOPClassRetired](#) = 96 ,
[VOILUTBoxSOPClass](#) = 97 ,
[PresentationLUTSOPClass](#) = 98 ,
[ImageOverlayBoxSOPClassRetired](#) = 99 ,
[BasicPrintImageOverlayBoxSOPClassRetired](#) = 100 ,
[PrintQueueSOPInstanceRetired](#) = 101 ,
[PrintQueueManagementSOPClassRetired](#) = 102 ,
[StoredPrintStorageSOPClassRetired](#) = 103 ,
[HardcopyGrayscaleImageStorageSOPClassRetired](#) = 104 ,
[HardcopyColorImageStorageSOPClassRetired](#) = 105 ,
[PullPrintRequestSOPClassRetired](#) = 106 ,
[PullStoredPrintManagementMetaSOPClassRetired](#) = 107 ,
[MediaCreationManagementSOPClassUID](#) = 108 ,
[ComputedRadiographyImageStorage](#) = 109 ,
[DigitalXRayImageStorageForPresentation](#) = 110 ,
[DigitalXRayImageStorageForProcessing](#) = 111 ,
[DigitalMammographyXRayImageStorageForPresentation](#) = 112 ,
[DigitalMammographyXRayImageStorageForProcessing](#) = 113 ,
[DigitalIntraoralXRayImageStorageForPresentation](#) = 114 ,
[DigitalIntraoralXRayImageStorageForProcessing](#) = 115 ,
[CTImageStorage](#) = 116 ,
[EnhancedCTImageStorage](#) = 117 ,
[UltrasoundMultiframeImageStorageRetired](#) = 118 ,
[UltrasoundMultiframeImageStorage](#) = 119 ,
[MRIImageStorage](#) = 120 ,
[EnhancedMRIImageStorage](#) = 121 ,
[MRSpectroscopyStorage](#) = 122 ,
[NuclearMedicineImageStorageRetired](#) = 123 ,
[UltrasoundImageStorageRetired](#) = 124 ,
[UltrasoundImageStorage](#) = 125 ,
[SecondaryCaptureImageStorage](#) = 126 ,
[MultiframeSingleBitSecondaryCaptureImageStorage](#) = 127 ,
[MultiframeGrayscaleByteSecondaryCaptureImageStorage](#) = 128 ,
[MultiframeGrayscaleWordSecondaryCaptureImageStorage](#) = 129 ,
[MultiframeTrueColorSecondaryCaptureImageStorage](#) = 130 ,
[StandaloneOverlayStorageRetired](#) = 131 ,
[StandaloneCurveStorageRetired](#) = 132 ,
[WaveformStorageTrialRetired](#) = 133 ,
[ECG12leadWaveformStorage](#) = 134 ,
[GeneralECGWaveformStorage](#) = 135 ,
[AmbulatoryECGWaveformStorage](#) = 136 ,
[HemodynamicWaveformStorage](#) = 137 ,
[CardiacElectrophysiologyWaveformStorage](#) = 138 ,
[BasicVoiceAudioWaveformStorage](#) = 139 ,
[StandaloneModalityLUTStorageRetired](#) = 140 ,
[StandaloneVOILUTStorageRetired](#) = 141 ,
[GrayscaleSoftcopyPresentationStateStorageSOPClass](#) = 142 ,
[ColorSoftcopyPresentationStateStorageSOPClass](#) = 143 ,
[PseudoColorSoftcopyPresentationStateStorageSOPClass](#) = 144 ,
[BlendingSoftcopyPresentationStateStorageSOPClass](#) = 145 ,
[XRayAngiographicImageStorage](#) = 146 ,
[EnhancedXAImageStorage](#) = 147 ,
[XRayRadiofluoroscopicImageStorage](#) = 148 ,
[EnhancedXRFImageStorage](#) = 149 ,

[XRay3DAngiographicImageStorage](#) = 150 ,
[XRay3DCraniofacialImageStorage](#) = 151 ,
[XRayAngiographicBiPlaneImageStorageRetired](#) = 152 ,
[NuclearMedicineImageStorage](#) = 153 ,
[RawDataStorage](#) = 154 ,
[SpatialRegistrationStorage](#) = 155 ,
[SpatialFiducialsStorage](#) = 156 ,
[DeformableSpatialRegistrationStorage](#) = 157 ,
[SegmentationStorage](#) = 158 ,
[RealWorldValueMappingStorage](#) = 159 ,
[VLImageStorageTrialRetired](#) = 160 ,
[VLMultiframeImageStorageTrialRetired](#) = 161 ,
[VLEndoscopicImageStorage](#) = 162 ,
[VideoEndoscopicImageStorage](#) = 163 ,
[VLMicroscopicImageStorage](#) = 164 ,
[VideoMicroscopicImageStorage](#) = 165 ,
[VLSlideCoordinatesMicroscopicImageStorage](#) = 166 ,
[VLPhotographicImageStorage](#) = 167 ,
[VideoPhotographicImageStorage](#) = 168 ,
[OphthalmicPhotography8BitImageStorage](#) = 169 ,
[OphthalmicPhotography16BitImageStorage](#) = 170 ,
[StereometricRelationshipStorage](#) = 171 ,
[OphthalmicTomographyImageStorage](#) = 172 ,
[TextSRStorageTrialRetired](#) = 173 ,
[AudioSRStorageTrialRetired](#) = 174 ,
[DetailSRStorageTrialRetired](#) = 175 ,
[ComprehensiveSRStorageTrialRetired](#) = 176 ,
[BasicTextSRStorage](#) = 177 ,
[EnhancedSRStorage](#) = 178 ,
[ComprehensiveSRStorage](#) = 179 ,
[ProcedureLogStorage](#) = 180 ,
[MammographyCADSRStorage](#) = 181 ,
[KeyObjectSelectionDocumentStorage](#) = 182 ,
[ChestCADSRStorage](#) = 183 ,
[XRayRadiationDoseSRStorage](#) = 184 ,
[EncapsulatedPDFStorage](#) = 185 ,
[EncapsulatedCDASStorage](#) = 186 ,
[PositronEmissionTomographyImageStorage](#) = 187 ,
[StandalonePETCurveStorageRetired](#) = 188 ,
[RTImageStorage](#) = 189 ,
[RTDoseStorage](#) = 190 ,
[RTStructureSetStorage](#) = 191 ,
[RTBeamsTreatmentRecordStorage](#) = 192 ,
[RTPlanStorage](#) = 193 ,
[RTBrachyTreatmentRecordStorage](#) = 194 ,
[RTTreatmentSummaryRecordStorage](#) = 195 ,
[RTIonPlanStorage](#) = 196 ,
[RTIonBeamsTreatmentRecordStorage](#) = 197 ,
[PatientRootQueryRetrieveInformationModelFIND](#) = 198 ,
[PatientRootQueryRetrieveInformationModelMOVE](#) = 199 ,
[PatientRootQueryRetrieveInformationModelGET](#) = 200 ,
[StudyRootQueryRetrieveInformationModelFIND](#) = 201 ,
[StudyRootQueryRetrieveInformationModelMOVE](#) = 202 ,
[StudyRootQueryRetrieveInformationModelGET](#) = 203 ,

[PatientStudyOnlyQueryRetrieveInformationModelFINDRetired](#) = 204 ,
[PatientStudyOnlyQueryRetrieveInformationModelMOVERetired](#) = 205 ,
[PatientStudyOnlyQueryRetrieveInformationModelGETRetired](#) = 206 ,
[ModalityWorklistInformationModelFIND](#) = 207 ,
[GeneralPurposeWorklistInformationModelFIND](#) = 208 ,
[GeneralPurposeScheduledProcedureStepSOPClass](#) = 209 ,
[GeneralPurposePerformedProcedureStepSOPClass](#) = 210 ,
[GeneralPurposeWorklistManagementMetaSOPClass](#) = 211 ,
[InstanceAvailabilityNotificationSOPClass](#) = 212 ,
[RTBeamsDeliveryInstructionStorageSupplement74FrozenDraft](#) = 213 ,
[RTConventionalMachineVerificationSupplement74FrozenDraft](#) = 214 ,
[RTIonMachineVerificationSupplement74FrozenDraft](#) = 215 ,
[UnifiedWorklistandProcedureStepServiceClass](#) = 216 ,
[UnifiedProcedureStepPushSOPClass](#) = 217 ,
[UnifiedProcedureStepWatchSOPClass](#) = 218 ,
[UnifiedProcedureStepPullSOPClass](#) = 219 ,
[UnifiedProcedureStepEventSOPClass](#) = 220 ,
[UnifiedWorklistandProcedureStepSOPInstance](#) = 221 ,
[GeneralRelevantPatientInformationQuery](#) = 222 ,
[BreastImagingRelevantPatientInformationQuery](#) = 223 ,
[CardiacRelevantPatientInformationQuery](#) = 224 ,
[HangingProtocolStorage](#) = 225 ,
[HangingProtocolInformationModelFIND](#) = 226 ,
[HangingProtocolInformationModelMOVE](#) = 227 ,
[ProductCharacteristicsQuerySOPClass](#) = 228 ,
[SubstanceApprovalQuerySOPClass](#) = 229 ,
[dicomDeviceName](#) = 230 ,
[dicomDescription](#) = 231 ,
[dicomManufacturer](#) = 232 ,
[dicomManufacturerModelName](#) = 233 ,
[dicomSoftwareVersion](#) = 234 ,
[dicomVendorData](#) = 235 ,
[dicomAETitle](#) = 236 ,
[dicomNetworkConnectionReference](#) = 237 ,
[dicomApplicationCluster](#) = 238 ,
[dicomAssociationInitiator](#) = 239 ,
[dicomAssociationAcceptor](#) = 240 ,
[dicomHostname](#) = 241 ,
[dicomPort](#) = 242 ,
[dicomSOPClass](#) = 243 ,
[dicomTransferRole](#) = 244 ,
[dicomTransferSyntax](#) = 245 ,
[dicomPrimaryDeviceType](#) = 246 ,
[dicomRelatedDeviceReference](#) = 247 ,
[dicomPreferredCalledAETitle](#) = 248 ,
[dicomTLSCyphersuite](#) = 249 ,
[dicomAuthorizedNodeCertificateReference](#) = 250 ,
[dicomThisNodeCertificateReference](#) = 251 ,
[dicomInstalled](#) = 252 ,
[dicomStationName](#) = 253 ,
[dicomDeviceSerialNumber](#) = 254 ,
[dicomInstitutionName](#) = 255 ,
[dicomInstitutionAddress](#) = 256 ,
[dicomInstitutionDepartmentName](#) = 257 ,

[dicomIssuerOfPatientID](#) = 258 ,
[dicomPreferredCallingAETitle](#) = 259 ,
[dicomSupportedCharacterSet](#) = 260 ,
[dicomConfigurationRoot](#) = 261 ,
[dicomDevicesRoot](#) = 262 ,
[dicomUniqueAETitlesRegistryRoot](#) = 263 ,
[dicomDevice](#) = 264 ,
[dicomNetworkAE](#) = 265 ,
[dicomNetworkConnection](#) = 266 ,
[dicomUniqueAETitle](#) = 267 ,
[dicomTransferCapability](#) = 268 ,
[VLWholeSlideMicroscopyImageStorage](#) = 269 ,
[EnhancedUSVolumeStorage](#) = 270 ,
[SurfaceSegmentationStorage](#) = 271 ,
[BreastTomosynthesisImageStorage](#) = 272 ,
[LegacyConvertedEnhancedCTImageStorage](#) = 273 ,
[LegacyConvertedEnhancedMRImageStorage](#) = 274 ,
[LegacyConvertedEnhancedPETImageStorage](#) = 275 ,
[MPEG2MainProfileHighLevel](#) = 276 ,
[MPEG4AVCH_264HighProfileLevel4_1](#) = 277 ,
[MPEG4AVCH_264BDcompatibleHighProfileLevel4_1](#) = 278 ,
[PETColorPaletteSOPInstance](#) = 279 ,
[HotMetalBlueColorPaletteSOPInstance](#) = 280 ,
[PET20StepColorPaletteSOPInstance](#) = 281 ,
[SpringColorPaletteSOPInstance](#) = 282 ,
[SummerColorPaletteSOPInstance](#) = 283 ,
[FallColorPaletteSOPInstance](#) = 284 ,
[WinterColorPaletteSOPInstance](#) = 285 ,
[Papyrus3ImplicitVRLittleEndian](#) = 286 ,
[AdultMouseAnatomyOntology](#) = 287 ,
[UberonOntology](#) = 288 ,
[IntegratedTaxonomicInformationSystemITISTaxonomicSerialNumberTSN](#) = 289 ,
[MouseGenomeInitiativeMGI](#) = 290 ,
[PubChemCompoundCID](#) = 291 ,
[ICD11](#) = 292 ,
[NewYorkUniversityMelanomaClinicalCooperativeGroup](#) = 293 ,
[MayoClinicNonradiologicalImagesSBSSAnatomicalSurfaceRegionGuide](#) = 294 ,
[ImageBiomarkerStandardisationInitiative](#) = 295 ,
[RadiomicsOntology](#) = 296 ,
[DisplaySystemSOPClass](#) = 297 ,
[DisplaySystemSOPInstance](#) = 298 ,
[GeneralAudioWaveformStorage](#) = 299 ,
[ArterialPulseWaveformStorage](#) = 300 ,
[RespiratoryWaveformStorage](#) = 301 ,
[XAXRFGrayscaleSoftcopyPresentationStateStorage](#) = 302 ,
[GrayscalePlanarMPRVolumetricPresentationStateStorage](#) = 303 ,
[MPEG4AVCH_264HighProfileLevel4_2For2DVideo](#) = 304 ,
[MPEG4AVCH_264HighProfileLevel4_2For3DVideo](#) = 305 ,
[MPEG4AVCH_264StereoHighProfileLevel4_2](#) = 306 ,
[HEVCH_265MainProfileLevel5_1](#) = 307 ,
[HEVCH_265Main10ProfileLevel5_1](#) = 308 ,
[HotIronColorPaletteSOPInstance](#) = 309 ,
[CompositingPlanarMPRVolumetricPresentationStateStorage](#) = 310 ,
[AdvancedBlendingPresentationStateStorage](#) = 311 ,

VolumeRenderingVolumetricPresentationStateStorage = 312 ,
SegmentedVolumeRenderingVolumetricPresentationStateStorage = 313 ,
MultipleVolumeRenderingVolumetricPresentationStateStorage = 314 ,
Null0 = 315 ,
BreastProjectionXRayImageStorageForPresentation = 316 ,
BreastProjectionXRayImageStorageForProcessing = 317 ,
IntravascularOpticalCoherenceTomographyImageStorageForPresentation = 318 ,
IntravascularOpticalCoherenceTomographyImageStorageForProcessing = 319 ,
ParametricMapStorage = 320 ,
Null1 = 321 ,
TractographyResultsStorage = 322 ,
SurfaceScanMeshStorage = 323 ,
SurfaceScanPointCloudStorage = 324 ,
WideFieldOphthalmicPhotographyStereographicProjectionImageStorage = 325 ,
WideFieldOphthalmicPhotography3DCoordinatesImageStorage = 326 ,
OphthalmicOpticalCoherenceTomographyEnFacelImageStorage = 327 ,
OphthalmicOpticalCoherenceTomographyBscanVolumeAnalysisStorage = 328 ,
LensometryMeasurementsStorage = 329 ,
AutorefractionMeasurementsStorage = 330 ,
KeratometryMeasurementsStorage = 331 ,
SubjectiveRefractionMeasurementsStorage = 332 ,
VisualAcuityMeasurementsStorage = 333 ,
SpectaclePrescriptionReportStorage = 334 ,
OphthalmicAxialMeasurementsStorage = 335 ,
IntraocularLensCalculationsStorage = 336 ,
MacularGridThicknessandVolumeReportStorage = 337 ,
OphthalmicVisualFieldStaticPerimetryMeasurementsStorage = 338 ,
OphthalmicThicknessMapStorage = 339 ,
CornealTopographyMapStorage = 340 ,
Comprehensive3DSRStorage = 341 ,
ExtensibleSRStorage = 342 ,
RadiopharmaceuticalRadiationDoseSRStorage = 343 ,
ColonCADSRStorage = 344 ,
ImplantationPlanSRStorage = 345 ,
AcquisitionContextSRStorage = 346 ,
SimplifiedAdultEchoSRStorage = 347 ,
PatientRadiationDoseSRStorage = 348 ,
PlannedImagingAgentAdministrationSRStorage = 349 ,
PerformedImagingAgentAdministrationSRStorage = 350 ,
ContentAssessmentResultsStorage = 351 ,
EncapsulatedSTLStorage = 352 ,
EnhancedPETImageStorage = 353 ,
BasicStructuredDisplayStorage = 354 ,
CTDefinedProcedureProtocolStorage = 355 ,
CTPerformedProcedureProtocolStorage = 356 ,
ProtocolApprovalStorage = 357 ,
ProtocolApprovalInformationModelFIND = 358 ,
ProtocolApprovalInformationModelMOVE = 359 ,
ProtocolApprovalInformationModelGET = 360 ,
RTPhysicianIntentStorage = 361 ,
RTSegmentAnnotationStorage = 362 ,
DICOSCTImageStorage = 363 ,
DICOSDigitalXRayImageStorageForPresentation = 364 ,
DICOSDigitalXRayImageStorageForProcessing = 365 ,

```

DICOSThreatDetectionReportStorage = 366 ,
DICOS2DAITStorage = 367 ,
DICOS3DAITStorage = 368 ,
DICOSQuadrupoleResonanceQRStorage = 369 ,
EddyCurrentImageStorage = 370 ,
EddyCurrentMultiframeImageStorage = 371 ,
CompositeInstanceRootRetrieveMOVE = 372 ,
CompositeInstanceRootRetrieveGET = 373 ,
CompositeInstanceRetrieveWithoutBulkDataGET = 374 ,
DefinedProcedureProtocolInformationModelFIND = 375 ,
DefinedProcedureProtocolInformationModelMOVE = 376 ,
DefinedProcedureProtocolInformationModelGET = 377 ,
UPSFilteredGlobalSubscriptionSOPInstance = 378 ,
UnifiedWorklistandProcedureStepServiceClass1 = 379 ,
UnifiedProcedureStepPushSOPClass1 = 380 ,
UnifiedProcedureStepWatchSOPClass1 = 381 ,
UnifiedProcedureStepPullSOPClass1 = 382 ,
UnifiedProcedureStepEventSOPClass1 = 383 ,
RTBeamsDeliveryInstructionStorage = 384 ,
RTConventionalMachineVerification = 385 ,
RTIonMachineVerification = 386 ,
RTBrachyApplicationSetupDeliveryInstructionStorage = 387 ,
HangingProtocolInformationModelGET = 388 ,
ColorPaletteStorage = 389 ,
ColorPaletteQueryRetrieveInformationModelFIND = 390 ,
ColorPaletteQueryRetrieveInformationModelMOVE = 391 ,
ColorPaletteQueryRetrieveInformationModelGET = 392 ,
GenericImplantTemplateStorage = 393 ,
GenericImplantTemplateInformationModelFIND = 394 ,
GenericImplantTemplateInformationModelMOVE = 395 ,
GenericImplantTemplateInformationModelGET = 396 ,
ImplantAssemblyTemplateStorage = 397 ,
ImplantAssemblyTemplateInformationModelFIND = 398 ,
ImplantAssemblyTemplateInformationModelMOVE = 399 ,
ImplantAssemblyTemplateInformationModelGET = 400 ,
ImplantTemplateGroupStorage = 401 ,
ImplantTemplateGroupInformationModelFIND = 402 ,
ImplantTemplateGroupInformationModelMOVE = 403 ,
ImplantTemplateGroupInformationModelGET = 404 ,
NativeDICOMModel = 405 ,
AbstractMultiDimensionalImageModel = 406 ,
DICOMContentMappingResource = 407 ,
EnhancedMRColorImageStorage = 408 ,
UniversalCoordinatedTime = 409 }
• enum TSType {
uid_1_2_840_10008_1_1 = 1 ,
uid_1_2_840_10008_1_2 = 2 ,
uid_1_2_840_10008_1_2_1 = 3 ,
uid_1_2_840_10008_1_2_1_99 = 4 ,
uid_1_2_840_10008_1_2_2 = 5 ,
uid_1_2_840_10008_1_2_4_50 = 6 ,
uid_1_2_840_10008_1_2_4_51 = 7 ,
uid_1_2_840_10008_1_2_4_52 = 8 ,
uid_1_2_840_10008_1_2_4_53 = 9 ,

```

```
uid_1_2_840_10008_1_2_4_54 = 10 ,
uid_1_2_840_10008_1_2_4_55 = 11 ,
uid_1_2_840_10008_1_2_4_56 = 12 ,
uid_1_2_840_10008_1_2_4_57 = 13 ,
uid_1_2_840_10008_1_2_4_58 = 14 ,
uid_1_2_840_10008_1_2_4_59 = 15 ,
uid_1_2_840_10008_1_2_4_60 = 16 ,
uid_1_2_840_10008_1_2_4_61 = 17 ,
uid_1_2_840_10008_1_2_4_62 = 18 ,
uid_1_2_840_10008_1_2_4_63 = 19 ,
uid_1_2_840_10008_1_2_4_64 = 20 ,
uid_1_2_840_10008_1_2_4_65 = 21 ,
uid_1_2_840_10008_1_2_4_66 = 22 ,
uid_1_2_840_10008_1_2_4_70 = 23 ,
uid_1_2_840_10008_1_2_4_80 = 24 ,
uid_1_2_840_10008_1_2_4_81 = 25 ,
uid_1_2_840_10008_1_2_4_90 = 26 ,
uid_1_2_840_10008_1_2_4_91 = 27 ,
uid_1_2_840_10008_1_2_4_92 = 28 ,
uid_1_2_840_10008_1_2_4_93 = 29 ,
uid_1_2_840_10008_1_2_4_94 = 30 ,
uid_1_2_840_10008_1_2_4_95 = 31 ,
uid_1_2_840_10008_1_2_4_100 = 32 ,
uid_1_2_840_10008_1_2_5 = 33 ,
uid_1_2_840_10008_1_2_6_1 = 34 ,
uid_1_2_840_10008_1_2_6_2 = 35 ,
uid_1_2_840_10008_1_3_10 = 36 ,
uid_1_2_840_10008_1_4_1_1 = 37 ,
uid_1_2_840_10008_1_4_1_2 = 38 ,
uid_1_2_840_10008_1_4_1_3 = 39 ,
uid_1_2_840_10008_1_4_1_4 = 40 ,
uid_1_2_840_10008_1_4_1_5 = 41 ,
uid_1_2_840_10008_1_4_1_6 = 42 ,
uid_1_2_840_10008_1_4_1_7 = 43 ,
uid_1_2_840_10008_1_4_1_8 = 44 ,
uid_1_2_840_10008_1_4_1_9 = 45 ,
uid_1_2_840_10008_1_4_1_10 = 46 ,
uid_1_2_840_10008_1_4_1_11 = 47 ,
uid_1_2_840_10008_1_4_1_12 = 48 ,
uid_1_2_840_10008_1_4_1_13 = 49 ,
uid_1_2_840_10008_1_4_1_14 = 50 ,
uid_1_2_840_10008_1_4_1_15 = 51 ,
uid_1_2_840_10008_1_4_1_16 = 52 ,
uid_1_2_840_10008_1_4_1_17 = 53 ,
uid_1_2_840_10008_1_4_1_18 = 54 ,
uid_1_2_840_10008_1_4_2_1 = 55 ,
uid_1_2_840_10008_1_4_2_2 = 56 ,
uid_1_2_840_10008_1_9 = 57 ,
uid_1_2_840_10008_1_20_1 = 58 ,
uid_1_2_840_10008_1_20_1_1 = 59 ,
uid_1_2_840_10008_1_20_2 = 60 ,
uid_1_2_840_10008_1_20_2_1 = 61 ,
uid_1_2_840_10008_1_40 = 62 ,
uid_1_2_840_10008_1_40_1 = 63 ,
```

```
uid_1_2_840_10008_1_42 = 64 ,  
uid_1_2_840_10008_1_42_1 = 65 ,  
uid_1_2_840_10008_2_6_1 = 66 ,  
uid_1_2_840_10008_2_16_4 = 67 ,  
uid_1_2_840_10008_3_1_1_1 = 68 ,  
uid_1_2_840_10008_3_1_2_1_1 = 69 ,  
uid_1_2_840_10008_3_1_2_1_4 = 70 ,  
uid_1_2_840_10008_3_1_2_2_1 = 71 ,  
uid_1_2_840_10008_3_1_2_3_1 = 72 ,  
uid_1_2_840_10008_3_1_2_3_2 = 73 ,  
uid_1_2_840_10008_3_1_2_3_3 = 74 ,  
uid_1_2_840_10008_3_1_2_3_4 = 75 ,  
uid_1_2_840_10008_3_1_2_3_5 = 76 ,  
uid_1_2_840_10008_3_1_2_5_1 = 77 ,  
uid_1_2_840_10008_3_1_2_5_4 = 78 ,  
uid_1_2_840_10008_3_1_2_5_5 = 79 ,  
uid_1_2_840_10008_3_1_2_6_1 = 80 ,  
uid_1_2_840_10008_4_2 = 81 ,  
uid_1_2_840_10008_5_1_1_1 = 82 ,  
uid_1_2_840_10008_5_1_1_2 = 83 ,  
uid_1_2_840_10008_5_1_1_4 = 84 ,  
uid_1_2_840_10008_5_1_1_4_1 = 85 ,  
uid_1_2_840_10008_5_1_1_4_2 = 86 ,  
uid_1_2_840_10008_5_1_1_9 = 87 ,  
uid_1_2_840_10008_5_1_1_9_1 = 88 ,  
uid_1_2_840_10008_5_1_1_14 = 89 ,  
uid_1_2_840_10008_5_1_1_15 = 90 ,  
uid_1_2_840_10008_5_1_1_16 = 91 ,  
uid_1_2_840_10008_5_1_1_16_376 = 92 ,  
uid_1_2_840_10008_5_1_1_17 = 93 ,  
uid_1_2_840_10008_5_1_1_17_376 = 94 ,  
uid_1_2_840_10008_5_1_1_18 = 95 ,  
uid_1_2_840_10008_5_1_1_18_1 = 96 ,  
uid_1_2_840_10008_5_1_1_22 = 97 ,  
uid_1_2_840_10008_5_1_1_23 = 98 ,  
uid_1_2_840_10008_5_1_1_24 = 99 ,  
uid_1_2_840_10008_5_1_1_24_1 = 100 ,  
uid_1_2_840_10008_5_1_1_25 = 101 ,  
uid_1_2_840_10008_5_1_1_26 = 102 ,  
uid_1_2_840_10008_5_1_1_27 = 103 ,  
uid_1_2_840_10008_5_1_1_29 = 104 ,  
uid_1_2_840_10008_5_1_1_30 = 105 ,  
uid_1_2_840_10008_5_1_1_31 = 106 ,  
uid_1_2_840_10008_5_1_1_32 = 107 ,  
uid_1_2_840_10008_5_1_1_33 = 108 ,  
uid_1_2_840_10008_5_1_4_1_1_1 = 109 ,  
uid_1_2_840_10008_5_1_4_1_1_1_1 = 110 ,  
uid_1_2_840_10008_5_1_4_1_1_1_1_1 = 111 ,  
uid_1_2_840_10008_5_1_4_1_1_1_2 = 112 ,  
uid_1_2_840_10008_5_1_4_1_1_1_2_1 = 113 ,  
uid_1_2_840_10008_5_1_4_1_1_1_3 = 114 ,  
uid_1_2_840_10008_5_1_4_1_1_1_3_1 = 115 ,  
uid_1_2_840_10008_5_1_4_1_1_2 = 116 ,  
uid_1_2_840_10008_5_1_4_1_1_2_1 = 117 ,
```



```
uid_1_2_840_10008_5_1_4_1_1_3 = 118 ,  
uid_1_2_840_10008_5_1_4_1_1_3_1 = 119 ,  
uid_1_2_840_10008_5_1_4_1_1_4 = 120 ,  
uid_1_2_840_10008_5_1_4_1_1_4_1 = 121 ,  
uid_1_2_840_10008_5_1_4_1_1_4_2 = 122 ,  
uid_1_2_840_10008_5_1_4_1_1_5 = 123 ,  
uid_1_2_840_10008_5_1_4_1_1_6 = 124 ,  
uid_1_2_840_10008_5_1_4_1_1_6_1 = 125 ,  
uid_1_2_840_10008_5_1_4_1_1_7 = 126 ,  
uid_1_2_840_10008_5_1_4_1_1_7_1 = 127 ,  
uid_1_2_840_10008_5_1_4_1_1_7_2 = 128 ,  
uid_1_2_840_10008_5_1_4_1_1_7_3 = 129 ,  
uid_1_2_840_10008_5_1_4_1_1_7_4 = 130 ,  
uid_1_2_840_10008_5_1_4_1_1_8 = 131 ,  
uid_1_2_840_10008_5_1_4_1_1_9 = 132 ,  
uid_1_2_840_10008_5_1_4_1_1_9_1 = 133 ,  
uid_1_2_840_10008_5_1_4_1_1_9_1_1 = 134 ,  
uid_1_2_840_10008_5_1_4_1_1_9_1_2 = 135 ,  
uid_1_2_840_10008_5_1_4_1_1_9_1_3 = 136 ,  
uid_1_2_840_10008_5_1_4_1_1_9_2_1 = 137 ,  
uid_1_2_840_10008_5_1_4_1_1_9_3_1 = 138 ,  
uid_1_2_840_10008_5_1_4_1_1_9_4_1 = 139 ,  
uid_1_2_840_10008_5_1_4_1_1_10 = 140 ,  
uid_1_2_840_10008_5_1_4_1_1_11 = 141 ,  
uid_1_2_840_10008_5_1_4_1_1_11_1 = 142 ,  
uid_1_2_840_10008_5_1_4_1_1_11_2 = 143 ,  
uid_1_2_840_10008_5_1_4_1_1_11_3 = 144 ,  
uid_1_2_840_10008_5_1_4_1_1_11_4 = 145 ,  
uid_1_2_840_10008_5_1_4_1_1_12_1 = 146 ,  
uid_1_2_840_10008_5_1_4_1_1_12_1_1 = 147 ,  
uid_1_2_840_10008_5_1_4_1_1_12_2 = 148 ,  
uid_1_2_840_10008_5_1_4_1_1_12_2_1 = 149 ,  
uid_1_2_840_10008_5_1_4_1_1_13_1_1 = 150 ,  
uid_1_2_840_10008_5_1_4_1_1_13_1_2 = 151 ,  
uid_1_2_840_10008_5_1_4_1_1_12_3 = 152 ,  
uid_1_2_840_10008_5_1_4_1_1_20 = 153 ,  
uid_1_2_840_10008_5_1_4_1_1_66 = 154 ,  
uid_1_2_840_10008_5_1_4_1_1_66_1 = 155 ,  
uid_1_2_840_10008_5_1_4_1_1_66_2 = 156 ,  
uid_1_2_840_10008_5_1_4_1_1_66_3 = 157 ,  
uid_1_2_840_10008_5_1_4_1_1_66_4 = 158 ,  
uid_1_2_840_10008_5_1_4_1_1_67 = 159 ,  
uid_1_2_840_10008_5_1_4_1_1_77_1 = 160 ,  
uid_1_2_840_10008_5_1_4_1_1_77_2 = 161 ,  
uid_1_2_840_10008_5_1_4_1_1_77_1_1 = 162 ,  
uid_1_2_840_10008_5_1_4_1_1_77_1_1_1 = 163 ,  
uid_1_2_840_10008_5_1_4_1_1_77_1_2 = 164 ,  
uid_1_2_840_10008_5_1_4_1_1_77_1_2_1 = 165 ,  
uid_1_2_840_10008_5_1_4_1_1_77_1_3 = 166 ,  
uid_1_2_840_10008_5_1_4_1_1_77_1_4 = 167 ,  
uid_1_2_840_10008_5_1_4_1_1_77_1_4_1 = 168 ,  
uid_1_2_840_10008_5_1_4_1_1_77_1_5_1 = 169 ,  
uid_1_2_840_10008_5_1_4_1_1_77_1_5_2 = 170 ,  
uid_1_2_840_10008_5_1_4_1_1_77_1_5_3 = 171 ,
```

```
uid_1_2_840_10008_5_1_4_1_1_77_1_5_4 = 172 ,
uid_1_2_840_10008_5_1_4_1_1_88_1 = 173 ,
uid_1_2_840_10008_5_1_4_1_1_88_2 = 174 ,
uid_1_2_840_10008_5_1_4_1_1_88_3 = 175 ,
uid_1_2_840_10008_5_1_4_1_1_88_4 = 176 ,
uid_1_2_840_10008_5_1_4_1_1_88_11 = 177 ,
uid_1_2_840_10008_5_1_4_1_1_88_22 = 178 ,
uid_1_2_840_10008_5_1_4_1_1_88_33 = 179 ,
uid_1_2_840_10008_5_1_4_1_1_88_40 = 180 ,
uid_1_2_840_10008_5_1_4_1_1_88_50 = 181 ,
uid_1_2_840_10008_5_1_4_1_1_88_59 = 182 ,
uid_1_2_840_10008_5_1_4_1_1_88_65 = 183 ,
uid_1_2_840_10008_5_1_4_1_1_88_67 = 184 ,
uid_1_2_840_10008_5_1_4_1_1_104_1 = 185 ,
uid_1_2_840_10008_5_1_4_1_1_104_2 = 186 ,
uid_1_2_840_10008_5_1_4_1_1_128 = 187 ,
uid_1_2_840_10008_5_1_4_1_1_129 = 188 ,
uid_1_2_840_10008_5_1_4_1_1_481_1 = 189 ,
uid_1_2_840_10008_5_1_4_1_1_481_2 = 190 ,
uid_1_2_840_10008_5_1_4_1_1_481_3 = 191 ,
uid_1_2_840_10008_5_1_4_1_1_481_4 = 192 ,
uid_1_2_840_10008_5_1_4_1_1_481_5 = 193 ,
uid_1_2_840_10008_5_1_4_1_1_481_6 = 194 ,
uid_1_2_840_10008_5_1_4_1_1_481_7 = 195 ,
uid_1_2_840_10008_5_1_4_1_1_481_8 = 196 ,
uid_1_2_840_10008_5_1_4_1_1_481_9 = 197 ,
uid_1_2_840_10008_5_1_4_1_2_1_1 = 198 ,
uid_1_2_840_10008_5_1_4_1_2_1_2 = 199 ,
uid_1_2_840_10008_5_1_4_1_2_1_3 = 200 ,
uid_1_2_840_10008_5_1_4_1_2_2_1 = 201 ,
uid_1_2_840_10008_5_1_4_1_2_2_2 = 202 ,
uid_1_2_840_10008_5_1_4_1_2_2_3 = 203 ,
uid_1_2_840_10008_5_1_4_1_2_3_1 = 204 ,
uid_1_2_840_10008_5_1_4_1_2_3_2 = 205 ,
uid_1_2_840_10008_5_1_4_1_2_3_3 = 206 ,
uid_1_2_840_10008_5_1_4_31 = 207 ,
uid_1_2_840_10008_5_1_4_32_1 = 208 ,
uid_1_2_840_10008_5_1_4_32_2 = 209 ,
uid_1_2_840_10008_5_1_4_32_3 = 210 ,
uid_1_2_840_10008_5_1_4_32 = 211 ,
uid_1_2_840_10008_5_1_4_33 = 212 ,
uid_1_2_840_10008_5_1_4_34_1 = 213 ,
uid_1_2_840_10008_5_1_4_34_2 = 214 ,
uid_1_2_840_10008_5_1_4_34_3 = 215 ,
uid_1_2_840_10008_5_1_4_34_4 = 216 ,
uid_1_2_840_10008_5_1_4_34_4_1 = 217 ,
uid_1_2_840_10008_5_1_4_34_4_2 = 218 ,
uid_1_2_840_10008_5_1_4_34_4_3 = 219 ,
uid_1_2_840_10008_5_1_4_34_4_4 = 220 ,
uid_1_2_840_10008_5_1_4_34_5 = 221 ,
uid_1_2_840_10008_5_1_4_37_1 = 222 ,
uid_1_2_840_10008_5_1_4_37_2 = 223 ,
uid_1_2_840_10008_5_1_4_37_3 = 224 ,
uid_1_2_840_10008_5_1_4_38_1 = 225 ,
```

uid_1_2_840_10008_5_1_4_38_2 = 226 ,
uid_1_2_840_10008_5_1_4_38_3 = 227 ,
uid_1_2_840_10008_5_1_4_41 = 228 ,
uid_1_2_840_10008_5_1_4_42 = 229 ,
uid_1_2_840_10008_15_0_3_1 = 230 ,
uid_1_2_840_10008_15_0_3_2 = 231 ,
uid_1_2_840_10008_15_0_3_3 = 232 ,
uid_1_2_840_10008_15_0_3_4 = 233 ,
uid_1_2_840_10008_15_0_3_5 = 234 ,
uid_1_2_840_10008_15_0_3_6 = 235 ,
uid_1_2_840_10008_15_0_3_7 = 236 ,
uid_1_2_840_10008_15_0_3_8 = 237 ,
uid_1_2_840_10008_15_0_3_9 = 238 ,
uid_1_2_840_10008_15_0_3_10 = 239 ,
uid_1_2_840_10008_15_0_3_11 = 240 ,
uid_1_2_840_10008_15_0_3_12 = 241 ,
uid_1_2_840_10008_15_0_3_13 = 242 ,
uid_1_2_840_10008_15_0_3_14 = 243 ,
uid_1_2_840_10008_15_0_3_15 = 244 ,
uid_1_2_840_10008_15_0_3_16 = 245 ,
uid_1_2_840_10008_15_0_3_17 = 246 ,
uid_1_2_840_10008_15_0_3_18 = 247 ,
uid_1_2_840_10008_15_0_3_19 = 248 ,
uid_1_2_840_10008_15_0_3_20 = 249 ,
uid_1_2_840_10008_15_0_3_21 = 250 ,
uid_1_2_840_10008_15_0_3_22 = 251 ,
uid_1_2_840_10008_15_0_3_23 = 252 ,
uid_1_2_840_10008_15_0_3_24 = 253 ,
uid_1_2_840_10008_15_0_3_25 = 254 ,
uid_1_2_840_10008_15_0_3_26 = 255 ,
uid_1_2_840_10008_15_0_3_27 = 256 ,
uid_1_2_840_10008_15_0_3_28 = 257 ,
uid_1_2_840_10008_15_0_3_29 = 258 ,
uid_1_2_840_10008_15_0_3_30 = 259 ,
uid_1_2_840_10008_15_0_3_31 = 260 ,
uid_1_2_840_10008_15_0_4_1 = 261 ,
uid_1_2_840_10008_15_0_4_2 = 262 ,
uid_1_2_840_10008_15_0_4_3 = 263 ,
uid_1_2_840_10008_15_0_4_4 = 264 ,
uid_1_2_840_10008_15_0_4_5 = 265 ,
uid_1_2_840_10008_15_0_4_6 = 266 ,
uid_1_2_840_10008_15_0_4_7 = 267 ,
uid_1_2_840_10008_15_0_4_8 = 268 ,
uid_1_2_840_10008_5_1_4_1_1_77_1_6 = 269 ,
uid_1_2_840_10008_5_1_4_1_1_6_2 = 270 ,
uid_1_2_840_10008_5_1_4_1_1_66_5 = 271 ,
uid_1_2_840_10008_5_1_4_1_1_13_1_3 = 272 ,
uid_1_2_840_10008_5_1_4_1_1_2_2 = 273 ,
uid_1_2_840_10008_5_1_4_1_1_4_4 = 274 ,
uid_1_2_840_10008_5_1_4_1_1_128_1 = 275 ,
uid_1_2_840_10008_1_2_4_101 = 276 ,
uid_1_2_840_10008_1_2_4_102 = 277 ,
uid_1_2_840_10008_1_2_4_103 = 278 ,
uid_1_2_840_10008_1_5_2 = 279 ,

```
uid_1_2_840_10008_1_5_3 = 280 ,  
uid_1_2_840_10008_1_5_4 = 281 ,  
uid_1_2_840_10008_1_5_5 = 282 ,  
uid_1_2_840_10008_1_5_6 = 283 ,  
uid_1_2_840_10008_1_5_7 = 284 ,  
uid_1_2_840_10008_1_5_8 = 285 ,  
uid_1_2_840_10008_1_20 = 286 ,  
uid_1_2_840_10008_2_16_5 = 287 ,  
uid_1_2_840_10008_2_16_6 = 288 ,  
uid_1_2_840_10008_2_16_7 = 289 ,  
uid_1_2_840_10008_2_16_8 = 290 ,  
uid_1_2_840_10008_2_16_9 = 291 ,  
uid_1_2_840_10008_2_16_10 = 292 ,  
uid_1_2_840_10008_2_16_11 = 293 ,  
uid_1_2_840_10008_2_16_12 = 294 ,  
uid_1_2_840_10008_2_16_13 = 295 ,  
uid_1_2_840_10008_2_16_14 = 296 ,  
uid_1_2_840_10008_5_1_1_40 = 297 ,  
uid_1_2_840_10008_5_1_1_40_1 = 298 ,  
uid_1_2_840_10008_5_1_4_1_1_9_4_2 = 299 ,  
uid_1_2_840_10008_5_1_4_1_1_9_5_1 = 300 ,  
uid_1_2_840_10008_5_1_4_1_1_9_6_1 = 301 ,  
uid_1_2_840_10008_5_1_4_1_1_11_5 = 302 ,  
uid_1_2_840_10008_5_1_4_1_1_11_6 = 303 ,  
uid_1_2_840_10008_1_2_4_104 = 304 ,  
uid_1_2_840_10008_1_2_4_105 = 305 ,  
uid_1_2_840_10008_1_2_4_106 = 306 ,  
uid_1_2_840_10008_1_2_4_107 = 307 ,  
uid_1_2_840_10008_1_2_4_108 = 308 ,  
uid_1_2_840_10008_1_5_1 = 309 ,  
uid_1_2_840_10008_5_1_4_1_1_11_7 = 310 ,  
uid_1_2_840_10008_5_1_4_1_1_11_8 = 311 ,  
uid_1_2_840_10008_5_1_4_1_1_11_9 = 312 ,  
uid_1_2_840_10008_5_1_4_1_1_11_10 = 313 ,  
uid_1_2_840_10008_5_1_4_1_1_11_11 = 314 ,  
uid_1_2_840_10008_5_1_4_1_1_12_77 = 315 ,  
uid_1_2_840_10008_5_1_4_1_1_13_1_4 = 316 ,  
uid_1_2_840_10008_5_1_4_1_1_13_1_5 = 317 ,  
uid_1_2_840_10008_5_1_4_1_1_14_1 = 318 ,  
uid_1_2_840_10008_5_1_4_1_1_14_2 = 319 ,  
uid_1_2_840_10008_5_1_4_1_1_30 = 320 ,  
uid_1_2_840_10008_5_1_4_1_1_40 = 321 ,  
uid_1_2_840_10008_5_1_4_1_1_66_6 = 322 ,  
uid_1_2_840_10008_5_1_4_1_1_68_1 = 323 ,  
uid_1_2_840_10008_5_1_4_1_1_68_2 = 324 ,  
uid_1_2_840_10008_5_1_4_1_1_77_1_5_5 = 325 ,  
uid_1_2_840_10008_5_1_4_1_1_77_1_5_6 = 326 ,  
uid_1_2_840_10008_5_1_4_1_1_77_1_5_7 = 327 ,  
uid_1_2_840_10008_5_1_4_1_1_77_1_5_8 = 328 ,  
uid_1_2_840_10008_5_1_4_1_1_78_1 = 329 ,  
uid_1_2_840_10008_5_1_4_1_1_78_2 = 330 ,  
uid_1_2_840_10008_5_1_4_1_1_78_3 = 331 ,  
uid_1_2_840_10008_5_1_4_1_1_78_4 = 332 ,  
uid_1_2_840_10008_5_1_4_1_1_78_5 = 333 ,
```

```
uid_1_2_840_10008_5_1_4_1_1_78_6 = 334 ,  
uid_1_2_840_10008_5_1_4_1_1_78_7 = 335 ,  
uid_1_2_840_10008_5_1_4_1_1_78_8 = 336 ,  
uid_1_2_840_10008_5_1_4_1_1_79_1 = 337 ,  
uid_1_2_840_10008_5_1_4_1_1_80_1 = 338 ,  
uid_1_2_840_10008_5_1_4_1_1_81_1 = 339 ,  
uid_1_2_840_10008_5_1_4_1_1_82_1 = 340 ,  
uid_1_2_840_10008_5_1_4_1_1_88_34 = 341 ,  
uid_1_2_840_10008_5_1_4_1_1_88_35 = 342 ,  
uid_1_2_840_10008_5_1_4_1_1_88_68 = 343 ,  
uid_1_2_840_10008_5_1_4_1_1_88_69 = 344 ,  
uid_1_2_840_10008_5_1_4_1_1_88_70 = 345 ,  
uid_1_2_840_10008_5_1_4_1_1_88_71 = 346 ,  
uid_1_2_840_10008_5_1_4_1_1_88_72 = 347 ,  
uid_1_2_840_10008_5_1_4_1_1_88_73 = 348 ,  
uid_1_2_840_10008_5_1_4_1_1_88_74 = 349 ,  
uid_1_2_840_10008_5_1_4_1_1_88_75 = 350 ,  
uid_1_2_840_10008_5_1_4_1_1_90_1 = 351 ,  
uid_1_2_840_10008_5_1_4_1_1_104_3 = 352 ,  
uid_1_2_840_10008_5_1_4_1_1_130 = 353 ,  
uid_1_2_840_10008_5_1_4_1_1_131 = 354 ,  
uid_1_2_840_10008_5_1_4_1_1_200_1 = 355 ,  
uid_1_2_840_10008_5_1_4_1_1_200_2 = 356 ,  
uid_1_2_840_10008_5_1_4_1_1_200_3 = 357 ,  
uid_1_2_840_10008_5_1_4_1_1_200_4 = 358 ,  
uid_1_2_840_10008_5_1_4_1_1_200_5 = 359 ,  
uid_1_2_840_10008_5_1_4_1_1_200_6 = 360 ,  
uid_1_2_840_10008_5_1_4_1_1_481_10 = 361 ,  
uid_1_2_840_10008_5_1_4_1_1_481_11 = 362 ,  
uid_1_2_840_10008_5_1_4_1_1_501_1 = 363 ,  
uid_1_2_840_10008_5_1_4_1_1_501_2_1 = 364 ,  
uid_1_2_840_10008_5_1_4_1_1_501_2_2 = 365 ,  
uid_1_2_840_10008_5_1_4_1_1_501_3 = 366 ,  
uid_1_2_840_10008_5_1_4_1_1_501_4 = 367 ,  
uid_1_2_840_10008_5_1_4_1_1_501_5 = 368 ,  
uid_1_2_840_10008_5_1_4_1_1_501_6 = 369 ,  
uid_1_2_840_10008_5_1_4_1_1_601_1 = 370 ,  
uid_1_2_840_10008_5_1_4_1_1_601_2 = 371 ,  
uid_1_2_840_10008_5_1_4_1_2_4_2 = 372 ,  
uid_1_2_840_10008_5_1_4_1_2_4_3 = 373 ,  
uid_1_2_840_10008_5_1_4_1_2_5_3 = 374 ,  
uid_1_2_840_10008_5_1_4_20_1 = 375 ,  
uid_1_2_840_10008_5_1_4_20_2 = 376 ,  
uid_1_2_840_10008_5_1_4_20_3 = 377 ,  
uid_1_2_840_10008_5_1_4_34_5_1 = 378 ,  
uid_1_2_840_10008_5_1_4_34_6 = 379 ,  
uid_1_2_840_10008_5_1_4_34_6_1 = 380 ,  
uid_1_2_840_10008_5_1_4_34_6_2 = 381 ,  
uid_1_2_840_10008_5_1_4_34_6_3 = 382 ,  
uid_1_2_840_10008_5_1_4_34_6_4 = 383 ,  
uid_1_2_840_10008_5_1_4_34_7 = 384 ,  
uid_1_2_840_10008_5_1_4_34_8 = 385 ,  
uid_1_2_840_10008_5_1_4_34_9 = 386 ,  
uid_1_2_840_10008_5_1_4_34_10 = 387 ,
```

```

uid_1_2_840_10008_5_1_4_38_4 = 388 ,
uid_1_2_840_10008_5_1_4_39_1 = 389 ,
uid_1_2_840_10008_5_1_4_39_2 = 390 ,
uid_1_2_840_10008_5_1_4_39_3 = 391 ,
uid_1_2_840_10008_5_1_4_39_4 = 392 ,
uid_1_2_840_10008_5_1_4_43_1 = 393 ,
uid_1_2_840_10008_5_1_4_43_2 = 394 ,
uid_1_2_840_10008_5_1_4_43_3 = 395 ,
uid_1_2_840_10008_5_1_4_43_4 = 396 ,
uid_1_2_840_10008_5_1_4_44_1 = 397 ,
uid_1_2_840_10008_5_1_4_44_2 = 398 ,
uid_1_2_840_10008_5_1_4_44_3 = 399 ,
uid_1_2_840_10008_5_1_4_44_4 = 400 ,
uid_1_2_840_10008_5_1_4_45_1 = 401 ,
uid_1_2_840_10008_5_1_4_45_2 = 402 ,
uid_1_2_840_10008_5_1_4_45_3 = 403 ,
uid_1_2_840_10008_5_1_4_45_4 = 404 ,
uid_1_2_840_10008_7_1_1 = 405 ,
uid_1_2_840_10008_7_1_2 = 406 ,
uid_1_2_840_10008_8_1_1 = 407 ,
uid_1_2_840_10008_5_1_4_1_1_4_3 = 408 ,
uid_1_2_840_10008_15_1_1 = 409 }

```

Public Member Functions

- [UIDs](#) ()=default
- const char * [GetName](#) () const
- const char * [GetString](#) () const
- [operator TSType](#) () const
- bool [SetFromUID](#) (const char *str)

Static Public Member Functions

- static unsigned int [GetNumberOfTransferSyntaxStrings](#) ()
- static const char *const * [GetTransferSyntaxString](#) (unsigned int ts)
- static [TransferSyntaxStringsType](#) [GetTransferSyntaxStrings](#) ()
- static const char * [GetUIDName](#) (unsigned int ts)
- static const char * [GetUIDString](#) (unsigned int ts)

10.321.1 Detailed Description

all known uids

Examples

[GenerateStandardSOPClasses.cxx](#).

10.321.2 Member Typedef Documentation

10.321.2.1 TransferSyntaxStringsType

```
typedef const char* const(* gdcm::UIDs::TransferSyntaxStringsType)[2]
```

10.321.3 Member Enumeration Documentation

10.321.3.1 TSName

```
enum gdcm::UIDs::TSName
```

Enumerator

VerificationSOPClass
ImplicitVRLittleEndianDefaultTransferSyntaxforDICOM
ExplicitVRLittleEndian
DeflatedExplicitVRLittleEndian
ExplicitVRBigEndian
JPEGBaselineProcess1DefaultTransferSyntaxforLossyJPEG8BitImageCompression
JPEGExtendedProcess24DefaultTransferSyntaxforLossyJPEG12BitImageCompressionProcess4only
JPEGExtendedProcess35Retired
JPEGSpectralSelectionNonHierarchicalProcess68Retired
JPEGSpectralSelectionNonHierarchicalProcess79Retired
JPEGFullProgressionNonHierarchicalProcess1012Retired
JPEGFullProgressionNonHierarchicalProcess1113Retired
JPEGLosslessNonHierarchicalProcess14
JPEGLosslessNonHierarchicalProcess15Retired
JPEGExtendedHierarchicalProcess1618Retired
JPEGExtendedHierarchicalProcess1719Retired
JPEGSpectralSelectionHierarchicalProcess2022Retired
JPEGSpectralSelectionHierarchicalProcess2123Retired
JPEGFullProgressionHierarchicalProcess2426Retired
JPEGFullProgressionHierarchicalProcess2527Retired
JPEGLosslessHierarchicalProcess28Retired
JPEGLosslessHierarchicalProcess29Retired
JPEGLosslessNonHierarchicalFirstOrderPredictionProcess14SelectionValue1DefaultTransferSyntaxforLossless↔ JPEGImageCompression
JPEGLSLosslessImageCompression
JPEGLSLossyNearLosslessImageCompression
JPEG2000ImageCompressionLosslessOnly
JPEG2000ImageCompression
JPEG2000Part2MulticomponentImageCompressionLosslessOnly
JPEG2000Part2MulticomponentImageCompression
JPIPReferenced

Enumerator

JPIPReferencedDeflate
MPEG2MainProfileMainLevel
RLELossless
RFC2557MIMEencapsulation
XMLEncoding
MediaStorageDirectoryStorage
TalairachBrainAtlasFrameofReference
SPM2T1FrameofReference
SPM2T2FrameofReference
SPM2PDFFrameofReference
SPM2EPIFrameofReference
SPM2FILT1FrameofReference
SPM2PETFrameofReference
SPM2TRANSMFrameofReference
SPM2SPECTFrameofReference
SPM2GRAYFrameofReference
SPM2WHITEFrameofReference
SPM2CSFFFrameofReference
SPM2BRAINMASKFrameofReference
SPM2AVG305T1FrameofReference
SPM2AVG152T1FrameofReference
SPM2AVG152T2FrameofReference
SPM2AVG152PDFFrameofReference
SPM2SINGLESUBJT1FrameofReference
ICBM452T1FrameofReference
ICBMSingleSubjectMRIFrameofReference
BasicStudyContentNotificationSOPClassRetired
StorageCommitmentPushModelSOPClass
StorageCommitmentPushModelSOPInstance
StorageCommitmentPullModelSOPClassRetired
StorageCommitmentPullModelSOPInstanceRetired
ProceduralEventLoggingSOPClass
ProceduralEventLoggingSOPInstance
SubstanceAdministrationLoggingSOPClass
SubstanceAdministrationLoggingSOPInstance
DICOMUIDRegistry
DICOMControlledTerminology
DICOMApplicationContextName
DetachedPatientManagementSOPClassRetired
DetachedPatientManagementMetaSOPClassRetired
DetachedVisitManagementSOPClassRetired
DetachedStudyManagementSOPClassRetired
StudyComponentManagementSOPClassRetired
ModalityPerformedProcedureStepSOPClass
ModalityPerformedProcedureStepRetrieveSOPClass

Enumerator

ModalityPerformedProcedureStepNotificationSOPClass	
DetachedResultsManagementSOPClassRetired	
DetachedResultsManagementMetaSOPClassRetired	
DetachedStudyManagementMetaSOPClassRetired	
DetachedInterpretationManagementSOPClassRetired	
StorageServiceClass	
BasicFilmSessionSOPClass	
BasicFilmBoxSOPClass	
BasicGrayscaleImageBoxSOPClass	
BasicColorImageBoxSOPClass	
ReferencedImageBoxSOPClassRetired	
BasicGrayscalePrintManagementMetaSOPClass	
ReferencedGrayscalePrintManagementMetaSOPClassRetired	
PrintJobSOPClass	
BasicAnnotationBoxSOPClass	
PrinterSOPClass	
PrinterConfigurationRetrievalSOPClass	
PrinterSOPInstance	
PrinterConfigurationRetrievalSOPInstance	
BasicColorPrintManagementMetaSOPClass	
ReferencedColorPrintManagementMetaSOPClassRetired	
VOILUTBoxSOPClass	
PresentationLUTSOPClass	
ImageOverlayBoxSOPClassRetired	
BasicPrintImageOverlayBoxSOPClassRetired	
PrintQueueSOPInstanceRetired	
PrintQueueManagementSOPClassRetired	
StoredPrintStorageSOPClassRetired	
HardcopyGrayscaleImageStorageSOPClassRetired	
HardcopyColorImageStorageSOPClassRetired	
PullPrintRequestSOPClassRetired	
PullStoredPrintManagementMetaSOPClassRetired	
MediaCreationManagementSOPClassUID	
ComputedRadiographyImageStorage	
DigitalXRayImageStorageForPresentation	
DigitalXRayImageStorageForProcessing	
DigitalMammographyXRayImageStorageForPresentation	
DigitalMammographyXRayImageStorageForProcessing	
DigitalIntraoralXRayImageStorageForPresentation	
DigitalIntraoralXRayImageStorageForProcessing	
CTImageStorage	
EnhancedCTImageStorage	
UltrasoundMultiframeImageStorageRetired	

Enumerator

UltrasoundMultiframeImageStorage	
MRImageStorage	
EnhancedMRImageStorage	
MRSpectroscopyStorage	
NuclearMedicineImageStorageRetired	
UltrasoundImageStorageRetired	
UltrasoundImageStorage	
SecondaryCaptureImageStorage	
MultiframeSingleBitSecondaryCaptureImageStorage	
MultiframeGrayscaleByteSecondaryCaptureImageStorage	
MultiframeGrayscaleWordSecondaryCaptureImageStorage	
MultiframeTrueColorSecondaryCaptureImageStorage	
StandaloneOverlayStorageRetired	
StandaloneCurveStorageRetired	
WaveformStorageTrialRetired	
ECG12leadWaveformStorage	
GeneralECGWaveformStorage	
AmbulatoryECGWaveformStorage	
HemodynamicWaveformStorage	
CardiacElectrophysiologyWaveformStorage	
BasicVoiceAudioWaveformStorage	
StandaloneModalityLUTStorageRetired	
StandaloneVOILUTStorageRetired	
GrayscaleSoftcopyPresentationStateStorageSOPClass	
ColorSoftcopyPresentationStateStorageSOPClass	
PseudoColorSoftcopyPresentationStateStorageSOPClass	
BlendingSoftcopyPresentationStateStorageSOPClass	
XRyAngiographicImageStorage	
EnhancedXAImageStorage	
XRyRadiofluoroscopicImageStorage	
EnhancedXRFIImageStorage	
XRy3DAngiographicImageStorage	
XRy3DCraniofacialImageStorage	
XRyAngiographicBiPlaneImageStorageRetired	
NuclearMedicineImageStorage	
RawDataStorage	
SpatialRegistrationStorage	
SpatialFiducialsStorage	
DeformableSpatialRegistrationStorage	
SegmentationStorage	
RealWorldValueMappingStorage	
VLIImageStorageTrialRetired	
VLMultiframeImageStorageTrialRetired	

Enumerator

VLEndoscopicImageStorage	
VideoEndoscopicImageStorage	
VLMicroscopicImageStorage	
VideoMicroscopicImageStorage	
VLSlideCoordinatesMicroscopicImageStorage	
VLPhotographicImageStorage	
VideoPhotographicImageStorage	
OphthalmicPhotography8BitImageStorage	
OphthalmicPhotography16BitImageStorage	
StereometricRelationshipStorage	
OphthalmicTomographyImageStorage	
TextSRStorageTrialRetired	
AudioSRStorageTrialRetired	
DetailSRStorageTrialRetired	
ComprehensiveSRStorageTrialRetired	
BasicTextSRStorage	
EnhancedSRStorage	
ComprehensiveSRStorage	
ProcedureLogStorage	
MammographyCADSRStorage	
KeyObjectSelectionDocumentStorage	
ChestCADSRStorage	
XRayRadiationDoseSRStorage	
EncapsulatedPDFStorage	
EncapsulatedCDASStorage	
PositronEmissionTomographyImageStorage	
StandalonePETCurveStorageRetired	
RTImageStorage	
RTDoseStorage	
RTStructureSetStorage	
RTBeamsTreatmentRecordStorage	
RTPlanStorage	
RTBrachyTreatmentRecordStorage	
RTTreatmentSummaryRecordStorage	
RTIonPlanStorage	
RTIonBeamsTreatmentRecordStorage	
PatientRootQueryRetrieveInformationModelFIND	
PatientRootQueryRetrieveInformationModelMOVE	
PatientRootQueryRetrieveInformationModelGET	
StudyRootQueryRetrieveInformationModelFIND	
StudyRootQueryRetrieveInformationModelMOVE	
StudyRootQueryRetrieveInformationModelGET	
PatientStudyOnlyQueryRetrieveInformationModelFINDRetired	

Enumerator

PatientStudyOnlyQueryRetrieveInformationModelMOVERetired	
PatientStudyOnlyQueryRetrieveInformationModelGETRetired	
ModalityWorklistInformationModelFIND	
GeneralPurposeWorklistInformationModelFIND	
GeneralPurposeScheduledProcedureStepSOPClass	
GeneralPurposePerformedProcedureStepSOPClass	
GeneralPurposeWorklistManagementMetaSOPClass	
InstanceAvailabilityNotificationSOPClass	
RTBeamsDeliveryInstructionStorageSupplement74FrozenDraft	
RTConventionalMachineVerificationSupplement74FrozenDraft	
RTIonMachineVerificationSupplement74FrozenDraft	
UnifiedWorklistandProcedureStepServiceClass	
UnifiedProcedureStepPushSOPClass	
UnifiedProcedureStepWatchSOPClass	
UnifiedProcedureStepPullSOPClass	
UnifiedProcedureStepEventSOPClass	
UnifiedWorklistandProcedureStepSOPInstance	
GeneralRelevantPatientInformationQuery	
BreastImagingRelevantPatientInformationQuery	
CardiacRelevantPatientInformationQuery	
HangingProtocolStorage	
HangingProtocolInformationModelFIND	
HangingProtocolInformationModelMOVE	
ProductCharacteristicsQuerySOPClass	
SubstanceApprovalQuerySOPClass	
dicomDeviceName	
dicomDescription	
dicomManufacturer	
dicomManufacturerModelName	
dicomSoftwareVersion	
dicomVendorData	
dicomAETitle	
dicomNetworkConnectionReference	
dicomApplicationCluster	
dicomAssociationInitiator	
dicomAssociationAcceptor	
dicomHostname	
dicomPort	
dicomSOPClass	
dicomTransferRole	
dicomTransferSyntax	
dicomPrimaryDeviceType	
dicomRelatedDeviceReference	
dicomPreferredCalledAETitle	

Enumerator

dicomTLSCyphersuite	
dicomAuthorizedNodeCertificateReference	
dicomThisNodeCertificateReference	
dicomInstalled	
dicomStationName	
dicomDeviceSerialNumber	
dicomInstitutionName	
dicomInstitutionAddress	
dicomInstitutionDepartmentName	
dicomIssuerOfPatientID	
dicomPreferredCallingAETitle	
dicomSupportedCharacterSet	
dicomConfigurationRoot	
dicomDevicesRoot	
dicomUniqueAETitlesRegistryRoot	
dicomDevice	
dicomNetworkAE	
dicomNetworkConnection	
dicomUniqueAETitle	
dicomTransferCapability	
VLWholeSlideMicroscopyImageStorage	
EnhancedUSVolumeStorage	
SurfaceSegmentationStorage	
BreastTomosynthesisImageStorage	
LegacyConvertedEnhancedCTImageStorage	
LegacyConvertedEnhancedMRIImageStorage	
LegacyConvertedEnhancedPETImageStorage	
MPEG2MainProfileHighLevel	
MPEG4AVCH_264HighProfileLevel4_1	
MPEG4AVCH_264BDcompatibleHighProfileLevel4_1	
PETColorPaletteSOPInstance	
HotMetalBlueColorPaletteSOPInstance	
PET20StepColorPaletteSOPInstance	
SpringColorPaletteSOPInstance	
SummerColorPaletteSOPInstance	
FallColorPaletteSOPInstance	
WinterColorPaletteSOPInstance	
Papyrus3ImplicitVRLittleEndian	
AdultMouseAnatomyOntology	
UberonOntology	
IntegratedTaxonomicInformationSystemITISTaxonomicSerialNumberTSN	
MouseGenomeInitiativeMGI	
PubChemCompoundCID	
ICD11	

Enumerator

NewYorkUniversityMelanomaClinicalCooperativeGroup
MayoClinicNonradiologicalImagesSBSAnatomicalSurfaceRegionGuide
ImageBiomarkerStandardisationInitiative
RadiomicsOntology
DisplaySystemSOPClass
DisplaySystemSOPInstance
GeneralAudioWaveformStorage
ArterialPulseWaveformStorage
RespiratoryWaveformStorage
XAXRFGrayscaleSoftcopyPresentationStateStorage
GrayscalePlanarMPRVolumetricPresentationStateStorage
MPEG4AVCH_264HighProfileLevel4_2For2DVideo
MPEG4AVCH_264HighProfileLevel4_2For3DVideo
MPEG4AVCH_264StereoHighProfileLevel4_2
HEVCH_265MainProfileLevel5_1
HEVCH_265Main10ProfileLevel5_1
HotIronColorPaletteSOPInstance
CompositingPlanarMPRVolumetricPresentationStateStorage
AdvancedBlendingPresentationStateStorage
VolumeRenderingVolumetricPresentationStateStorage
SegmentedVolumeRenderingVolumetricPresentationStateStorage
MultipleVolumeRenderingVolumetricPresentationStateStorage
Null0
BreastProjectionXRayImageStorageForPresentation
BreastProjectionXRayImageStorageForProcessing
IntravascularOpticalCoherenceTomographyImageStorageForPresentation
IntravascularOpticalCoherenceTomographyImageStorageForProcessing
ParametricMapStorage
Null1
TractographyResultsStorage
SurfaceScanMeshStorage
SurfaceScanPointCloudStorage
WideFieldOphthalmicPhotographyStereographicProjectionImageStorage
WideFieldOphthalmicPhotography3DCoordinatesImageStorage
OphthalmicOpticalCoherenceTomographyEnFaceImageStorage
OphthalmicOpticalCoherenceTomographyBscanVolumeAnalysisStorage
LensometryMeasurementsStorage
AutorefractionMeasurementsStorage
KeratometryMeasurementsStorage
SubjectiveRefractionMeasurementsStorage
VisualAcuityMeasurementsStorage
SpectaclePrescriptionReportStorage
OphthalmicAxialMeasurementsStorage

Enumerator

IntraocularLensCalculationsStorage	
MacularGridThicknessandVolumeReportStorage	
OphthalmicVisualFieldStaticPerimetryMeasurementsStorage	
OphthalmicThicknessMapStorage	
CornealTopographyMapStorage	
Comprehensive3DSRStorage	
ExtensibleSRStorage	
RadiopharmaceuticalRadiationDoseSRStorage	
ColonCADSRStorage	
ImplantationPlanSRStorage	
AcquisitionContextSRStorage	
SimplifiedAdultEchoSRStorage	
PatientRadiationDoseSRStorage	
PlannedImagingAgentAdministrationSRStorage	
PerformedImagingAgentAdministrationSRStorage	
ContentAssessmentResultsStorage	
EncapsulatedSTLStorage	
EnhancedPETImageStorage	
BasicStructuredDisplayStorage	
CTDefinedProcedureProtocolStorage	
CTPerformedProcedureProtocolStorage	
ProtocolApprovalStorage	
ProtocolApprovalInformationModelFIND	
ProtocolApprovalInformationModelMOVE	
ProtocolApprovalInformationModelGET	
RTPhysicianIntentStorage	
RTSegmentAnnotationStorage	
DICOSCTImageStorage	
DICOSDigitalXRayImageStorageForPresentation	
DICOSDigitalXRayImageStorageForProcessing	
DICOSThreatDetectionReportStorage	
DICOS2DAITStorage	
DICOS3DAITStorage	
DICOSQuadrupoleResonanceQRStorage	
EddyCurrentImageStorage	
EddyCurrentMultiframeImageStorage	
CompositeInstanceRootRetrieveMOVE	
CompositeInstanceRootRetrieveGET	
CompositeInstanceRetrieveWithoutBulkDataGET	
DefinedProcedureProtocolInformationModelFIND	
DefinedProcedureProtocolInformationModelMOVE	
DefinedProcedureProtocolInformationModelGET	
UPSFilteredGlobalSubscriptionSOPInstance	

Enumerator

UnifiedWorklistandProcedureStepServiceClass1	
UnifiedProcedureStepPushSOPClass1	
UnifiedProcedureStepWatchSOPClass1	
UnifiedProcedureStepPullSOPClass1	
UnifiedProcedureStepEventSOPClass1	
RTBeamsDeliveryInstructionStorage	
RTConventionalMachineVerification	
RTIonMachineVerification	
RTBrachyApplicationSetupDeliveryInstructionStorage	
HangingProtocolInformationModelGET	
ColorPaletteStorage	
ColorPaletteQueryRetrieveInformationModelFIND	
ColorPaletteQueryRetrieveInformationModelMOVE	
ColorPaletteQueryRetrieveInformationModelGET	
GenericImplantTemplateStorage	
GenericImplantTemplateInformationModelFIND	
GenericImplantTemplateInformationModelMOVE	
GenericImplantTemplateInformationModelGET	
ImplantAssemblyTemplateStorage	
ImplantAssemblyTemplateInformationModelFIND	
ImplantAssemblyTemplateInformationModelMOVE	
ImplantAssemblyTemplateInformationModelGET	
ImplantTemplateGroupStorage	
ImplantTemplateGroupInformationModelFIND	
ImplantTemplateGroupInformationModelMOVE	
ImplantTemplateGroupInformationModelGET	
NativeDICOMModel	
AbstractMultiDimensionalImageModel	
DICOMContentMappingResource	
EnhancedMRColorImageStorage	
UniversalCoordinatedTime	

10.321.3.2 TSType

```
enum gdcm::UIDs::TSType
```

Enumerator

uid_1_2_840_10008_1_1	
uid_1_2_840_10008_1_2	
uid_1_2_840_10008_1_2_1	
uid_1_2_840_10008_1_2_1_99	
uid_1_2_840_10008_1_2_2	

Enumerator

uid_1_2_840_10008_1_2_4_50	
uid_1_2_840_10008_1_2_4_51	
uid_1_2_840_10008_1_2_4_52	
uid_1_2_840_10008_1_2_4_53	
uid_1_2_840_10008_1_2_4_54	
uid_1_2_840_10008_1_2_4_55	
uid_1_2_840_10008_1_2_4_56	
uid_1_2_840_10008_1_2_4_57	
uid_1_2_840_10008_1_2_4_58	
uid_1_2_840_10008_1_2_4_59	
uid_1_2_840_10008_1_2_4_60	
uid_1_2_840_10008_1_2_4_61	
uid_1_2_840_10008_1_2_4_62	
uid_1_2_840_10008_1_2_4_63	
uid_1_2_840_10008_1_2_4_64	
uid_1_2_840_10008_1_2_4_65	
uid_1_2_840_10008_1_2_4_66	
uid_1_2_840_10008_1_2_4_70	
uid_1_2_840_10008_1_2_4_80	
uid_1_2_840_10008_1_2_4_81	
uid_1_2_840_10008_1_2_4_90	
uid_1_2_840_10008_1_2_4_91	
uid_1_2_840_10008_1_2_4_92	
uid_1_2_840_10008_1_2_4_93	
uid_1_2_840_10008_1_2_4_94	
uid_1_2_840_10008_1_2_4_95	
uid_1_2_840_10008_1_2_4_100	
uid_1_2_840_10008_1_2_5	
uid_1_2_840_10008_1_2_6_1	
uid_1_2_840_10008_1_2_6_2	
uid_1_2_840_10008_1_3_10	
uid_1_2_840_10008_1_4_1_1	
uid_1_2_840_10008_1_4_1_2	
uid_1_2_840_10008_1_4_1_3	
uid_1_2_840_10008_1_4_1_4	
uid_1_2_840_10008_1_4_1_5	
uid_1_2_840_10008_1_4_1_6	
uid_1_2_840_10008_1_4_1_7	
uid_1_2_840_10008_1_4_1_8	
uid_1_2_840_10008_1_4_1_9	
uid_1_2_840_10008_1_4_1_10	
uid_1_2_840_10008_1_4_1_11	
uid_1_2_840_10008_1_4_1_12	
uid_1_2_840_10008_1_4_1_13	
uid_1_2_840_10008_1_4_1_14	
uid_1_2_840_10008_1_4_1_15	

Enumerator

uid_1_2_840_10008_1_4_1_16	
uid_1_2_840_10008_1_4_1_17	
uid_1_2_840_10008_1_4_1_18	
uid_1_2_840_10008_1_4_2_1	
uid_1_2_840_10008_1_4_2_2	
uid_1_2_840_10008_1_9	
uid_1_2_840_10008_1_20_1	
uid_1_2_840_10008_1_20_1_1	
uid_1_2_840_10008_1_20_2	
uid_1_2_840_10008_1_20_2_1	
uid_1_2_840_10008_1_40	
uid_1_2_840_10008_1_40_1	
uid_1_2_840_10008_1_42	
uid_1_2_840_10008_1_42_1	
uid_1_2_840_10008_2_6_1	
uid_1_2_840_10008_2_16_4	
uid_1_2_840_10008_3_1_1_1	
uid_1_2_840_10008_3_1_2_1_1	
uid_1_2_840_10008_3_1_2_1_4	
uid_1_2_840_10008_3_1_2_2_1	
uid_1_2_840_10008_3_1_2_3_1	
uid_1_2_840_10008_3_1_2_3_2	
uid_1_2_840_10008_3_1_2_3_3	
uid_1_2_840_10008_3_1_2_3_4	
uid_1_2_840_10008_3_1_2_3_5	
uid_1_2_840_10008_3_1_2_5_1	
uid_1_2_840_10008_3_1_2_5_4	
uid_1_2_840_10008_3_1_2_5_5	
uid_1_2_840_10008_3_1_2_6_1	
uid_1_2_840_10008_4_2	
uid_1_2_840_10008_5_1_1_1	
uid_1_2_840_10008_5_1_1_2	
uid_1_2_840_10008_5_1_1_4	
uid_1_2_840_10008_5_1_1_4_1	
uid_1_2_840_10008_5_1_1_4_2	
uid_1_2_840_10008_5_1_1_9	
uid_1_2_840_10008_5_1_1_9_1	
uid_1_2_840_10008_5_1_1_14	
uid_1_2_840_10008_5_1_1_15	
uid_1_2_840_10008_5_1_1_16	
uid_1_2_840_10008_5_1_1_16_376	
uid_1_2_840_10008_5_1_1_17	
uid_1_2_840_10008_5_1_1_17_376	
uid_1_2_840_10008_5_1_1_18	
uid_1_2_840_10008_5_1_1_18_1	
uid_1_2_840_10008_5_1_1_22	

Enumerator

uid_1_2_840_10008_5_1_1_23	
uid_1_2_840_10008_5_1_1_24	
uid_1_2_840_10008_5_1_1_24_1	
uid_1_2_840_10008_5_1_1_25	
uid_1_2_840_10008_5_1_1_26	
uid_1_2_840_10008_5_1_1_27	
uid_1_2_840_10008_5_1_1_29	
uid_1_2_840_10008_5_1_1_30	
uid_1_2_840_10008_5_1_1_31	
uid_1_2_840_10008_5_1_1_32	
uid_1_2_840_10008_5_1_1_33	
uid_1_2_840_10008_5_1_4_1_1_1	
uid_1_2_840_10008_5_1_4_1_1_1_1	
uid_1_2_840_10008_5_1_4_1_1_1_1_1	
uid_1_2_840_10008_5_1_4_1_1_1_2	
uid_1_2_840_10008_5_1_4_1_1_1_2_1	
uid_1_2_840_10008_5_1_4_1_1_1_3	
uid_1_2_840_10008_5_1_4_1_1_1_3_1	
uid_1_2_840_10008_5_1_4_1_1_2	
uid_1_2_840_10008_5_1_4_1_1_2_1	
uid_1_2_840_10008_5_1_4_1_1_3	
uid_1_2_840_10008_5_1_4_1_1_3_1	
uid_1_2_840_10008_5_1_4_1_1_4	
uid_1_2_840_10008_5_1_4_1_1_4_1	
uid_1_2_840_10008_5_1_4_1_1_4_2	
uid_1_2_840_10008_5_1_4_1_1_5	
uid_1_2_840_10008_5_1_4_1_1_6	
uid_1_2_840_10008_5_1_4_1_1_6_1	
uid_1_2_840_10008_5_1_4_1_1_7	
uid_1_2_840_10008_5_1_4_1_1_7_1	
uid_1_2_840_10008_5_1_4_1_1_7_2	
uid_1_2_840_10008_5_1_4_1_1_7_3	
uid_1_2_840_10008_5_1_4_1_1_7_4	
uid_1_2_840_10008_5_1_4_1_1_8	
uid_1_2_840_10008_5_1_4_1_1_9	
uid_1_2_840_10008_5_1_4_1_1_9_1	
uid_1_2_840_10008_5_1_4_1_1_9_1_1	
uid_1_2_840_10008_5_1_4_1_1_9_1_2	
uid_1_2_840_10008_5_1_4_1_1_9_1_3	
uid_1_2_840_10008_5_1_4_1_1_9_2_1	
uid_1_2_840_10008_5_1_4_1_1_9_3_1	
uid_1_2_840_10008_5_1_4_1_1_9_4_1	
uid_1_2_840_10008_5_1_4_1_1_10	
uid_1_2_840_10008_5_1_4_1_1_11	
uid_1_2_840_10008_5_1_4_1_1_11_1	
uid_1_2_840_10008_5_1_4_1_1_11_2	

Enumerator

uid_1_2_840_10008_5_1_4_1_1_11_3	
uid_1_2_840_10008_5_1_4_1_1_11_4	
uid_1_2_840_10008_5_1_4_1_1_12_1	
uid_1_2_840_10008_5_1_4_1_1_12_1_1	
uid_1_2_840_10008_5_1_4_1_1_12_2	
uid_1_2_840_10008_5_1_4_1_1_12_2_1	
uid_1_2_840_10008_5_1_4_1_1_13_1_1	
uid_1_2_840_10008_5_1_4_1_1_13_1_2	
uid_1_2_840_10008_5_1_4_1_1_12_3	
uid_1_2_840_10008_5_1_4_1_1_20	
uid_1_2_840_10008_5_1_4_1_1_66	
uid_1_2_840_10008_5_1_4_1_1_66_1	
uid_1_2_840_10008_5_1_4_1_1_66_2	
uid_1_2_840_10008_5_1_4_1_1_66_3	
uid_1_2_840_10008_5_1_4_1_1_66_4	
uid_1_2_840_10008_5_1_4_1_1_67	
uid_1_2_840_10008_5_1_4_1_1_77_1	
uid_1_2_840_10008_5_1_4_1_1_77_2	
uid_1_2_840_10008_5_1_4_1_1_77_1_1	
uid_1_2_840_10008_5_1_4_1_1_77_1_1↵ _1	
uid_1_2_840_10008_5_1_4_1_1_77_1_2	
uid_1_2_840_10008_5_1_4_1_1_77_1_2↵ _1	
uid_1_2_840_10008_5_1_4_1_1_77_1_3	
uid_1_2_840_10008_5_1_4_1_1_77_1_4	
uid_1_2_840_10008_5_1_4_1_1_77_1_4↵ _1	
uid_1_2_840_10008_5_1_4_1_1_77_1_5↵ _1	
uid_1_2_840_10008_5_1_4_1_1_77_1_5↵ _2	
uid_1_2_840_10008_5_1_4_1_1_77_1_5↵ _3	
uid_1_2_840_10008_5_1_4_1_1_77_1_5↵ _4	
uid_1_2_840_10008_5_1_4_1_1_88_1	
uid_1_2_840_10008_5_1_4_1_1_88_2	
uid_1_2_840_10008_5_1_4_1_1_88_3	
uid_1_2_840_10008_5_1_4_1_1_88_4	
uid_1_2_840_10008_5_1_4_1_1_88_11	
uid_1_2_840_10008_5_1_4_1_1_88_22	
uid_1_2_840_10008_5_1_4_1_1_88_33	
uid_1_2_840_10008_5_1_4_1_1_88_40	
uid_1_2_840_10008_5_1_4_1_1_88_50	
uid_1_2_840_10008_5_1_4_1_1_88_59	
uid_1_2_840_10008_5_1_4_1_1_88_65	

Enumerator

uid_1_2_840_10008_5_1_4_1_1_88_67	
uid_1_2_840_10008_5_1_4_1_1_104_1	
uid_1_2_840_10008_5_1_4_1_1_104_2	
uid_1_2_840_10008_5_1_4_1_1_128	
uid_1_2_840_10008_5_1_4_1_1_129	
uid_1_2_840_10008_5_1_4_1_1_481_1	
uid_1_2_840_10008_5_1_4_1_1_481_2	
uid_1_2_840_10008_5_1_4_1_1_481_3	
uid_1_2_840_10008_5_1_4_1_1_481_4	
uid_1_2_840_10008_5_1_4_1_1_481_5	
uid_1_2_840_10008_5_1_4_1_1_481_6	
uid_1_2_840_10008_5_1_4_1_1_481_7	
uid_1_2_840_10008_5_1_4_1_1_481_8	
uid_1_2_840_10008_5_1_4_1_1_481_9	
uid_1_2_840_10008_5_1_4_1_2_1_1	
uid_1_2_840_10008_5_1_4_1_2_1_2	
uid_1_2_840_10008_5_1_4_1_2_1_3	
uid_1_2_840_10008_5_1_4_1_2_2_1	
uid_1_2_840_10008_5_1_4_1_2_2_2	
uid_1_2_840_10008_5_1_4_1_2_2_3	
uid_1_2_840_10008_5_1_4_1_2_3_1	
uid_1_2_840_10008_5_1_4_1_2_3_2	
uid_1_2_840_10008_5_1_4_1_2_3_3	
uid_1_2_840_10008_5_1_4_31	
uid_1_2_840_10008_5_1_4_32_1	
uid_1_2_840_10008_5_1_4_32_2	
uid_1_2_840_10008_5_1_4_32_3	
uid_1_2_840_10008_5_1_4_32	
uid_1_2_840_10008_5_1_4_33	
uid_1_2_840_10008_5_1_4_34_1	
uid_1_2_840_10008_5_1_4_34_2	
uid_1_2_840_10008_5_1_4_34_3	
uid_1_2_840_10008_5_1_4_34_4	
uid_1_2_840_10008_5_1_4_34_4_1	
uid_1_2_840_10008_5_1_4_34_4_2	
uid_1_2_840_10008_5_1_4_34_4_3	
uid_1_2_840_10008_5_1_4_34_4_4	
uid_1_2_840_10008_5_1_4_34_5	
uid_1_2_840_10008_5_1_4_37_1	
uid_1_2_840_10008_5_1_4_37_2	
uid_1_2_840_10008_5_1_4_37_3	
uid_1_2_840_10008_5_1_4_38_1	
uid_1_2_840_10008_5_1_4_38_2	
uid_1_2_840_10008_5_1_4_38_3	
uid_1_2_840_10008_5_1_4_41	
uid_1_2_840_10008_5_1_4_42	

Enumerator

uid_1_2_840_10008_15_0_3_1	
uid_1_2_840_10008_15_0_3_2	
uid_1_2_840_10008_15_0_3_3	
uid_1_2_840_10008_15_0_3_4	
uid_1_2_840_10008_15_0_3_5	
uid_1_2_840_10008_15_0_3_6	
uid_1_2_840_10008_15_0_3_7	
uid_1_2_840_10008_15_0_3_8	
uid_1_2_840_10008_15_0_3_9	
uid_1_2_840_10008_15_0_3_10	
uid_1_2_840_10008_15_0_3_11	
uid_1_2_840_10008_15_0_3_12	
uid_1_2_840_10008_15_0_3_13	
uid_1_2_840_10008_15_0_3_14	
uid_1_2_840_10008_15_0_3_15	
uid_1_2_840_10008_15_0_3_16	
uid_1_2_840_10008_15_0_3_17	
uid_1_2_840_10008_15_0_3_18	
uid_1_2_840_10008_15_0_3_19	
uid_1_2_840_10008_15_0_3_20	
uid_1_2_840_10008_15_0_3_21	
uid_1_2_840_10008_15_0_3_22	
uid_1_2_840_10008_15_0_3_23	
uid_1_2_840_10008_15_0_3_24	
uid_1_2_840_10008_15_0_3_25	
uid_1_2_840_10008_15_0_3_26	
uid_1_2_840_10008_15_0_3_27	
uid_1_2_840_10008_15_0_3_28	
uid_1_2_840_10008_15_0_3_29	
uid_1_2_840_10008_15_0_3_30	
uid_1_2_840_10008_15_0_3_31	
uid_1_2_840_10008_15_0_4_1	
uid_1_2_840_10008_15_0_4_2	
uid_1_2_840_10008_15_0_4_3	
uid_1_2_840_10008_15_0_4_4	
uid_1_2_840_10008_15_0_4_5	
uid_1_2_840_10008_15_0_4_6	
uid_1_2_840_10008_15_0_4_7	
uid_1_2_840_10008_15_0_4_8	
uid_1_2_840_10008_5_1_4_1_1_77_1_6	
uid_1_2_840_10008_5_1_4_1_1_6_2	
uid_1_2_840_10008_5_1_4_1_1_66_5	
uid_1_2_840_10008_5_1_4_1_1_13_1_3	
uid_1_2_840_10008_5_1_4_1_1_2_2	
uid_1_2_840_10008_5_1_4_1_1_4_4	
uid_1_2_840_10008_5_1_4_1_1_128_1	

Enumerator

uid_1_2_840_10008_1_2_4_101	
uid_1_2_840_10008_1_2_4_102	
uid_1_2_840_10008_1_2_4_103	
uid_1_2_840_10008_1_5_2	
uid_1_2_840_10008_1_5_3	
uid_1_2_840_10008_1_5_4	
uid_1_2_840_10008_1_5_5	
uid_1_2_840_10008_1_5_6	
uid_1_2_840_10008_1_5_7	
uid_1_2_840_10008_1_5_8	
uid_1_2_840_10008_1_20	
uid_1_2_840_10008_2_16_5	
uid_1_2_840_10008_2_16_6	
uid_1_2_840_10008_2_16_7	
uid_1_2_840_10008_2_16_8	
uid_1_2_840_10008_2_16_9	
uid_1_2_840_10008_2_16_10	
uid_1_2_840_10008_2_16_11	
uid_1_2_840_10008_2_16_12	
uid_1_2_840_10008_2_16_13	
uid_1_2_840_10008_2_16_14	
uid_1_2_840_10008_5_1_1_40	
uid_1_2_840_10008_5_1_1_40_1	
uid_1_2_840_10008_5_1_4_1_1_9_4_2	
uid_1_2_840_10008_5_1_4_1_1_9_5_1	
uid_1_2_840_10008_5_1_4_1_1_9_6_1	
uid_1_2_840_10008_5_1_4_1_1_11_5	
uid_1_2_840_10008_5_1_4_1_1_11_6	
uid_1_2_840_10008_1_2_4_104	
uid_1_2_840_10008_1_2_4_105	
uid_1_2_840_10008_1_2_4_106	
uid_1_2_840_10008_1_2_4_107	
uid_1_2_840_10008_1_2_4_108	
uid_1_2_840_10008_1_5_1	
uid_1_2_840_10008_5_1_4_1_1_11_7	
uid_1_2_840_10008_5_1_4_1_1_11_8	
uid_1_2_840_10008_5_1_4_1_1_11_9	
uid_1_2_840_10008_5_1_4_1_1_11_10	
uid_1_2_840_10008_5_1_4_1_1_11_11	
uid_1_2_840_10008_5_1_4_1_1_12_77	
uid_1_2_840_10008_5_1_4_1_1_13_1_4	
uid_1_2_840_10008_5_1_4_1_1_13_1_5	
uid_1_2_840_10008_5_1_4_1_1_14_1	
uid_1_2_840_10008_5_1_4_1_1_14_2	
uid_1_2_840_10008_5_1_4_1_1_30	
uid_1_2_840_10008_5_1_4_1_1_40	

Enumerator

uid_1_2_840_10008_5_1_4_1_1_66_6	
uid_1_2_840_10008_5_1_4_1_1_68_1	
uid_1_2_840_10008_5_1_4_1_1_68_2	
uid_1_2_840_10008_5_1_4_1_1_77_1_5↔ _5	
uid_1_2_840_10008_5_1_4_1_1_77_1_5↔ _6	
uid_1_2_840_10008_5_1_4_1_1_77_1_5↔ _7	
uid_1_2_840_10008_5_1_4_1_1_77_1_5↔ _8	
uid_1_2_840_10008_5_1_4_1_1_78_1	
uid_1_2_840_10008_5_1_4_1_1_78_2	
uid_1_2_840_10008_5_1_4_1_1_78_3	
uid_1_2_840_10008_5_1_4_1_1_78_4	
uid_1_2_840_10008_5_1_4_1_1_78_5	
uid_1_2_840_10008_5_1_4_1_1_78_6	
uid_1_2_840_10008_5_1_4_1_1_78_7	
uid_1_2_840_10008_5_1_4_1_1_78_8	
uid_1_2_840_10008_5_1_4_1_1_79_1	
uid_1_2_840_10008_5_1_4_1_1_80_1	
uid_1_2_840_10008_5_1_4_1_1_81_1	
uid_1_2_840_10008_5_1_4_1_1_82_1	
uid_1_2_840_10008_5_1_4_1_1_88_34	
uid_1_2_840_10008_5_1_4_1_1_88_35	
uid_1_2_840_10008_5_1_4_1_1_88_68	
uid_1_2_840_10008_5_1_4_1_1_88_69	
uid_1_2_840_10008_5_1_4_1_1_88_70	
uid_1_2_840_10008_5_1_4_1_1_88_71	
uid_1_2_840_10008_5_1_4_1_1_88_72	
uid_1_2_840_10008_5_1_4_1_1_88_73	
uid_1_2_840_10008_5_1_4_1_1_88_74	
uid_1_2_840_10008_5_1_4_1_1_88_75	
uid_1_2_840_10008_5_1_4_1_1_90_1	
uid_1_2_840_10008_5_1_4_1_1_104_3	
uid_1_2_840_10008_5_1_4_1_1_130	
uid_1_2_840_10008_5_1_4_1_1_131	
uid_1_2_840_10008_5_1_4_1_1_200_1	
uid_1_2_840_10008_5_1_4_1_1_200_2	
uid_1_2_840_10008_5_1_4_1_1_200_3	
uid_1_2_840_10008_5_1_4_1_1_200_4	
uid_1_2_840_10008_5_1_4_1_1_200_5	
uid_1_2_840_10008_5_1_4_1_1_200_6	
uid_1_2_840_10008_5_1_4_1_1_481_10	
uid_1_2_840_10008_5_1_4_1_1_481_11	
uid_1_2_840_10008_5_1_4_1_1_501_1	
uid_1_2_840_10008_5_1_4_1_1_501_2_1	

Enumerator

uid_1_2_840_10008_5_1_4_1_1_501_2_2	
uid_1_2_840_10008_5_1_4_1_1_501_3	
uid_1_2_840_10008_5_1_4_1_1_501_4	
uid_1_2_840_10008_5_1_4_1_1_501_5	
uid_1_2_840_10008_5_1_4_1_1_501_6	
uid_1_2_840_10008_5_1_4_1_1_601_1	
uid_1_2_840_10008_5_1_4_1_1_601_2	
uid_1_2_840_10008_5_1_4_1_2_4_2	
uid_1_2_840_10008_5_1_4_1_2_4_3	
uid_1_2_840_10008_5_1_4_1_2_5_3	
uid_1_2_840_10008_5_1_4_20_1	
uid_1_2_840_10008_5_1_4_20_2	
uid_1_2_840_10008_5_1_4_20_3	
uid_1_2_840_10008_5_1_4_34_5_1	
uid_1_2_840_10008_5_1_4_34_6	
uid_1_2_840_10008_5_1_4_34_6_1	
uid_1_2_840_10008_5_1_4_34_6_2	
uid_1_2_840_10008_5_1_4_34_6_3	
uid_1_2_840_10008_5_1_4_34_6_4	
uid_1_2_840_10008_5_1_4_34_7	
uid_1_2_840_10008_5_1_4_34_8	
uid_1_2_840_10008_5_1_4_34_9	
uid_1_2_840_10008_5_1_4_34_10	
uid_1_2_840_10008_5_1_4_38_4	
uid_1_2_840_10008_5_1_4_39_1	
uid_1_2_840_10008_5_1_4_39_2	
uid_1_2_840_10008_5_1_4_39_3	
uid_1_2_840_10008_5_1_4_39_4	
uid_1_2_840_10008_5_1_4_43_1	
uid_1_2_840_10008_5_1_4_43_2	
uid_1_2_840_10008_5_1_4_43_3	
uid_1_2_840_10008_5_1_4_43_4	
uid_1_2_840_10008_5_1_4_44_1	
uid_1_2_840_10008_5_1_4_44_2	
uid_1_2_840_10008_5_1_4_44_3	
uid_1_2_840_10008_5_1_4_44_4	
uid_1_2_840_10008_5_1_4_45_1	
uid_1_2_840_10008_5_1_4_45_2	
uid_1_2_840_10008_5_1_4_45_3	
uid_1_2_840_10008_5_1_4_45_4	
uid_1_2_840_10008_7_1_1	
uid_1_2_840_10008_7_1_2	
uid_1_2_840_10008_8_1_1	
uid_1_2_840_10008_5_1_4_1_1_4_3	
uid_1_2_840_10008_15_1_1	

10.321.4 Constructor & Destructor Documentation

10.321.4.1 UIDs()

```
gdcm::UIDs::UIDs () [default]
```

10.321.5 Member Function Documentation

10.321.5.1 GetName()

```
const char * gdcm::UIDs::GetName () const
```

When object is Initialize function return the well known name associated with uid return NULL when not initialized

Examples

[GenerateStandardSOPClasses.cxx](#).

Referenced by [gdcm::operator<<\(\)](#).

10.321.5.2 GetNumberOfTransferSyntaxStrings()

```
unsigned int gdcm::UIDs::GetNumberOfTransferSyntaxStrings () [static]
```

10.321.5.3 GetString()

```
const char * gdcm::UIDs::GetString () const
```

When object is Initialize function return the uid return NULL when not initialized

Examples

[GenerateStandardSOPClasses.cxx](#).

Referenced by [gdcm::operator<<\(\)](#).

10.321.5.4 GetTransferSyntaxString()

```
const char *const * gdcm::UIDs::GetTransferSyntaxString (  
    unsigned int ts) [static]
```

10.321.5.5 GetTransferSyntaxStrings()

```
TransferSyntaxStringsType gdcm::UIDs::GetTransferSyntaxStrings () [static]
```

10.321.5.6 GetUIDName()

```
const char * gdcm::UIDs::GetUIDName (  
    unsigned int ts) [static]
```

10.321.5.7 GetUIDString()

```
const char * gdcm::UIDs::GetUIDString (  
    unsigned int ts) [static]
```

10.321.5.8 operator TType()

```
gdcm::UIDs::operator TType () const [inline]
```

10.321.5.9 SetFromUID()

```
bool gdcm::UIDs::SetFromUID (  
    const char * str)
```

Initialize object from a string (a uid number) return false on error, and internal state is set to 0

Examples

[GenerateStandardSOPClasses.cxx](#).

The documentation for this class was generated from the following file:


- [gdcmUIDs.h](#)

10.322 gdcm::network::ULAction Class Reference

[ULAction.](#)

```
#include <gdcmULAction.h>
```

Inheritance diagram for gdcm::network::ULAction:



Public Member Functions

- [ULAction](#) ()=default
- [ULAction](#) (const [ULAction](#) &inAction)=delete
- virtual [~ULAction](#) ()=default
- void [operator=](#) (const [ULAction](#) &)=delete
- virtual [EStateID PerformAction](#) ([Subject](#) *s, [ULEvent](#) &inEvent, [ULConnection](#) &inConnection, bool &outWaiting↔
ForEvent, [EEventID](#) &outRaisedEvent)=0

10.322.1 Detailed Description

[ULAction](#).

A [ULConnection](#) in a given ULState can perform certain ULActions. This base class provides the interface for running those ULActions on a given [ULConnection](#).

Essentially, the [ULConnectionManager](#) will take this object, determined from the current ULState of the [ULConnection](#), and pass the [ULConnection](#) object to the [ULAction](#). The [ULAction](#) will then invoke whatever necessary commands are required by a given action.

The result of a [ULAction](#) is a [ULEvent](#) (ie, what happened as a result of the action).

This [ULEvent](#) is passed to the ULState, so that the transition to the next state can occur.

Actions are associated with Payloads – be those filestreams, AETitles to establish connections, whatever. The actual parameters that the user will pass via an action will come through a Payload object, which should, in itself, be some gdcmm-based object (but not all objects can be payloads; sending a single dataelement as a payload isn't meaningful). As such, each action has its own particular payload.

For the sake of keeping files together, both the particular payload class and the action class will be defined in the same header file. Payloads should JUST be data (or streams), NO METHODS.

Some actions perform changes that should raise events on the local system, and some actions perform changes that will require waiting for events from the remote system.

Therefore, this base action has been modified so that those events are set by each action. When the event loop runs an action, it will then test to see if a local event was raised by the action, and if so, perform the appropriate subsequent action. If the action requires waiting for a response from the remote system, then the event loop will sit there (presumably with the ARTIM timer running) and wait for a response from the remote system. Once a response is obtained, then the the rest of the state transitions can happen.

10.322.2 Constructor & Destructor Documentation

10.322.2.1 [ULAction](#)() [1/2]

```
gdcmm::network::ULAction::ULAction () [default]
```

Referenced by [ULAction\(\)](#), and [operator=\(\)](#).

10.322.2.2 ~ULAction()

```
virtual gdcmm::network::ULAction::~~ULAction () [virtual], [default]
```

10.322.2.3 ULAction() [2/2]

```
gdcmm::network::ULAction::ULAction (
    const ULAction & inAction) [delete]
```

References [ULAction\(\)](#).

10.322.3 Member Function Documentation**10.322.3.1 operator=()**

```
void gdcmm::network::ULAction::operator= (
    const ULAction & ) [delete]
```

References [ULAction\(\)](#).

10.322.3.2 PerformAction()

```
virtual EStateID gdcmm::network::ULAction::PerformAction (
    Subject * s,
    ULEvent & inEvent,
    ULConnection & inConnection,
    bool & outWaitingForEvent,
    EEventID & outRaisedEvent) [pure virtual]
```

Implemented in [gdcmm::network::ULActionAA1](#), [gdcmm::network::ULActionAA2](#), [gdcmm::network::ULActionAA3](#), [gdcmm::network::ULActionAA4](#), [gdcmm::network::ULActionAA5](#), [gdcmm::network::ULActionAA6](#), [gdcmm::network::ULActionAA7](#), [gdcmm::network::ULActionAA8](#), [gdcmm::network::ULActionAE1](#), [gdcmm::network::ULActionAE2](#), [gdcmm::network::ULActionAE3](#), [gdcmm::network::ULActionAE4](#), [gdcmm::network::ULActionAE5](#), [gdcmm::network::ULActionAE6](#), [gdcmm::network::ULActionAE7](#), [gdcmm::network::ULActionAE8](#), [gdcmm::network::ULActionAR10](#), [gdcmm::network::ULActionAR1](#), [gdcmm::network::ULActionAR2](#), [gdcmm::network::ULActionAR3](#), [gdcmm::network::ULActionAR4](#), [gdcmm::network::ULActionAR5](#), [gdcmm::network::ULActionAR6](#), [gdcmm::network::ULActionAR7](#), [gdcmm::network::ULActionAR8](#), [gdcmm::network::ULActionAR9](#), [gdcmm::network::ULActionDT1](#), and [gdcmm::network::ULActionDT2](#).


The documentation for this class was generated from the following file:

- [gdcmmULAction.h](#)


10.323 gdcm::network::ULActionAA1 Class Reference

```
#include <gdcmULActionAA.h>
```

Inheritance diagram for gdcm::network::ULActionAA1:



Collaboration diagram for gdcm::network::ULActionAA1:



Public Member Functions

- [EStateID PerformAction](#) ([Subject](#) *s, [ULEvent](#) &inEvent, [ULConnection](#) &inConnection, bool &outWaitingForEvent, [EEventID](#) &outRaisedEvent) override

Public Member Functions inherited from [gdcm::network::ULAction](#)

- [ULAction](#) ()=default
- [ULAction](#) (const [ULAction](#) &inAction)=delete
- virtual [~ULAction](#) ()=default
- void [operator=](#) (const [ULAction](#) &)=delete

10.323.1 Member Function Documentation

10.323.1.1 PerformAction()

```
EStateID gdcmm::network::ULActionAA1::PerformAction (  
    Subject * s,  
    ULEvent & inEvent,  
    ULConnection & inConnection,  
    bool & outWaitingForEvent,  
    EEventID & outRaisedEvent) [override], [virtual]
```

Implements [gdcmm::network::ULAction](#).


The documentation for this class was generated from the following file:

- [gdcmmULActionAA.h](#)


10.324 gdcmm::network::ULActionAA2 Class Reference

```
#include <gdcmmULActionAA.h>
```

Inheritance diagram for gdcmm::network::ULActionAA2:



Collaboration diagram for gdcmm::network::ULActionAA2:



Public Member Functions

- [EStateID PerformAction](#) ([Subject](#) *s, [ULEvent](#) &inEvent, [ULConnection](#) &inConnection, bool &outWaitingForEvent, [EEventID](#) &outRaisedEvent) override

Public Member Functions inherited from [gdcm::network::ULAction](#)

- [ULAction](#) ()=default
- [ULAction](#) (const [ULAction](#) &inAction)=delete
- virtual [~ULAction](#) ()=default
- void [operator=](#) (const [ULAction](#) &)=delete

10.324.1 Member Function Documentation**10.324.1.1 PerformAction()**

```
EStateID gdcm::network::ULActionAA2::PerformAction (
    Subject * s,
    ULEvent & inEvent,
    ULConnection & inConnection,
    bool & outWaitingForEvent,
    EEventID & outRaisedEvent) [override], [virtual]
```

Implements [gdcm::network::ULAction](#).


The documentation for this class was generated from the following file:

- [gdcmULActionAA.h](#)


10.325 gdcm::network::ULActionAA3 Class Reference

```
#include <gdcmULActionAA.h>
```

Inheritance diagram for [gdcm::network::ULActionAA3](#):



Collaboration diagram for `gdcm::network::ULActionAA3`:



Public Member Functions

- `EStateID PerformAction` (`Subject *s`, `ULEvent &inEvent`, `ULConnection &inConnection`, `bool &outWaitingForEvent`, `EEventID &outRaisedEvent`) override

Public Member Functions inherited from `gdcm::network::ULAction`

- `ULAction` ()=default
- `ULAction` (const `ULAction` &`inAction`)=delete
- virtual `~ULAction` ()=default
- void `operator=` (const `ULAction` &)=delete

10.325.1 Member Function Documentation

10.325.1.1 PerformAction()

```

EStateID gdcm::network::ULActionAA3::PerformAction (
    Subject * s,
    ULEvent & inEvent,
    ULConnection & inConnection,
    bool & outWaitingForEvent,
    EEventID & outRaisedEvent) [override], [virtual]
  
```

Implements `gdcm::network::ULAction`.


The documentation for this class was generated from the following file:

- `gdcmULActionAA.h`


10.326 gdcm::network::ULActionAA4 Class Reference

```
#include <gdcmULActionAA.h>
```

Inheritance diagram for gdcm::network::ULActionAA4:



Collaboration diagram for gdcm::network::ULActionAA4:



Public Member Functions

- [EStateID PerformAction](#) ([Subject](#) *s, [ULEvent](#) &inEvent, [ULConnection](#) &inConnection, bool &outWaitingForEvent, [EEventID](#) &outRaisedEvent) override

Public Member Functions inherited from [gdcm::network::ULAction](#)

- [ULAction](#) ()=default
- [ULAction](#) (const [ULAction](#) &inAction)=delete
- virtual [~ULAction](#) ()=default
- void [operator=](#) (const [ULAction](#) &)=delete

10.326.1 Member Function Documentation

10.326.1.1 PerformAction()

```
EStateID gdcmm::network::ULActionAA4::PerformAction (
    Subject * s,
    ULEvent & inEvent,
    ULConnection & inConnection,
    bool & outWaitingForEvent,
    EEventID & outRaisedEvent) [override], [virtual]
```

Implements [gdcmm::network::ULAction](#).


The documentation for this class was generated from the following file:

- [gdcmmULActionAA.h](#)


10.327 gdcmm::network::ULActionAA5 Class Reference

```
#include <gdcmmULActionAA.h>
```

Inheritance diagram for gdcmm::network::ULActionAA5:



Collaboration diagram for gdcmm::network::ULActionAA5:



Public Member Functions

- [EStateID PerformAction](#) ([Subject](#) *s, [ULEvent](#) &inEvent, [ULConnection](#) &inConnection, bool &outWaitingForEvent, [EEventID](#) &outRaisedEvent) override

Public Member Functions inherited from [gdcm::network::ULAction](#)

- [ULAction](#) ()=default
- [ULAction](#) (const [ULAction](#) &inAction)=delete
- virtual [~ULAction](#) ()=default
- void [operator=](#) (const [ULAction](#) &)=delete

10.327.1 Member Function Documentation**10.327.1.1 PerformAction()**

```
EStateID gdcm::network::ULActionAA5::PerformAction (
    Subject * s,
    ULEvent & inEvent,
    ULConnection & inConnection,
    bool & outWaitingForEvent,
    EEventID & outRaisedEvent) [override], [virtual]
```

Implements [gdcm::network::ULAction](#).


The documentation for this class was generated from the following file:

- [gdcmULActionAA.h](#)


10.328 gdcm::network::ULActionAA6 Class Reference

```
#include <gdcmULActionAA.h>
```

Inheritance diagram for [gdcm::network::ULActionAA6](#):



Collaboration diagram for `gdcm::network::ULActionAA6`:



Public Member Functions

- `EStateID PerformAction (Subject *s, ULEvent &inEvent, ULConnection &inConnection, bool &outWaitingForEvent, EEventID &outRaisedEvent)` override

Public Member Functions inherited from `gdcm::network::ULAction`

- `ULAction ()`=default
- `ULAction (const ULAction &inAction)`=delete
- virtual `~ULAction ()`=default
- void `operator= (const ULAction &)`=delete

10.328.1 Member Function Documentation

10.328.1.1 PerformAction()

```

EStateID gdcm::network::ULActionAA6::PerformAction (
    Subject * s,
    ULEvent & inEvent,
    ULConnection & inConnection,
    bool & outWaitingForEvent,
    EEventID & outRaisedEvent) [override], [virtual]
  
```

Implements `gdcm::network::ULAction`.


The documentation for this class was generated from the following file:

- `gdcmULActionAA.h`


10.329 gdcm::network::ULActionAA7 Class Reference

```
#include <gdcmULActionAA.h>
```

Inheritance diagram for gdcm::network::ULActionAA7:



Collaboration diagram for gdcm::network::ULActionAA7:



Public Member Functions

- [EStateID PerformAction](#) ([Subject](#) *s, [ULEvent](#) &inEvent, [ULConnection](#) &inConnection, bool &outWaitingForEvent, [EEventID](#) &outRaisedEvent) override

Public Member Functions inherited from [gdcm::network::ULAction](#)

- [ULAction](#) ()=default
- [ULAction](#) (const [ULAction](#) &inAction)=delete
- virtual [~ULAction](#) ()=default
- void [operator=](#) (const [ULAction](#) &)=delete

10.329.1 Member Function Documentation

10.329.1.1 PerformAction()

```
EStateID gdcmm::network::ULActionAA7::PerformAction (  
    Subject * s,  
    ULEvent & inEvent,  
    ULConnection & inConnection,  
    bool & outWaitingForEvent,  
    EEventID & outRaisedEvent) [override], [virtual]
```

Implements [gdcmm::network::ULAction](#).


The documentation for this class was generated from the following file:

- [gdcmmULActionAA.h](#)


10.330 gdcmm::network::ULActionAA8 Class Reference

```
#include <gdcmmULActionAA.h>
```

Inheritance diagram for gdcmm::network::ULActionAA8:



Collaboration diagram for gdcmm::network::ULActionAA8:



Public Member Functions

- [EStateID PerformAction](#) ([Subject](#) *s, [ULEvent](#) &inEvent, [ULConnection](#) &inConnection, bool &outWaitingForEvent, [EEventID](#) &outRaisedEvent) override

Public Member Functions inherited from [gdcm::network::ULAction](#)

- [ULAction](#) ()=default
- [ULAction](#) (const [ULAction](#) &inAction)=delete
- virtual [~ULAction](#) ()=default
- void [operator=](#) (const [ULAction](#) &)=delete

10.330.1 Member Function Documentation**10.330.1.1 PerformAction()**

```
EStateID gdcm::network::ULActionAA8::PerformAction (
    Subject * s,
    ULEvent & inEvent,
    ULConnection & inConnection,
    bool & outWaitingForEvent,
    EEventID & outRaisedEvent) [override], [virtual]
```

Implements [gdcm::network::ULAction](#).


The documentation for this class was generated from the following file:

- [gdcmULActionAA.h](#)


10.331 gdcm::network::ULActionAE1 Class Reference

```
#include <gdcmULActionAE.h>
```

Inheritance diagram for [gdcm::network::ULActionAE1](#):



Collaboration diagram for `gdcm::network::ULActionAE1`:



Public Member Functions

- [EStateID PerformAction](#) ([Subject](#) *s, [ULEvent](#) &inEvent, [ULConnection](#) &inConnection, bool &outWaitingForEvent, [EEventID](#) &outRaisedEvent) override

Public Member Functions inherited from [gdcm::network::ULAction](#)

- [ULAction](#) ()=default
- [ULAction](#) (const [ULAction](#) &inAction)=delete
- virtual [~ULAction](#) ()=default
- void [operator=](#) (const [ULAction](#) &)=delete

10.331.1 Member Function Documentation

10.331.1.1 PerformAction()

```

EStateID gdcm::network::ULActionAE1::PerformAction (
    Subject * s,
    ULEvent & inEvent,
    ULConnection & inConnection,
    bool & outWaitingForEvent,
    EEventID & outRaisedEvent) [override], [virtual]
  
```

Implements [gdcm::network::ULAction](#).


The documentation for this class was generated from the following file:

- [gdcmULActionAE.h](#)


10.332 gdcm::network::ULActionAE2 Class Reference

```
#include <gdcmULActionAE.h>
```

Inheritance diagram for gdcm::network::ULActionAE2:



Collaboration diagram for gdcm::network::ULActionAE2:



Public Member Functions

- `EStateID PerformAction (Subject *s, ULEvent &inEvent, ULConnection &inConnection, bool &outWaitingForEvent, EEventID &outRaisedEvent)` override

Public Member Functions inherited from `gdcm::network::ULAction`

- `ULAction ()`=default
- `ULAction (const ULAction &inAction)`=delete
- virtual `~ULAction ()`=default
- void `operator= (const ULAction &)=delete`

10.332.1 Member Function Documentation

10.332.1.1 PerformAction()

```
EStateID gdcmm::network::ULActionAE2::PerformAction (
    Subject * s,
    ULEvent & inEvent,
    ULConnection & inConnection,
    bool & outWaitingForEvent,
    EEventID & outRaisedEvent) [override], [virtual]
```

Implements [gdcmm::network::ULAction](#).


The documentation for this class was generated from the following file:

- [gdcmmULActionAE.h](#)


10.333 gdcmm::network::ULActionAE3 Class Reference

```
#include <gdcmmULActionAE.h>
```

Inheritance diagram for gdcmm::network::ULActionAE3:



Collaboration diagram for gdcmm::network::ULActionAE3:



Public Member Functions

- [EStateID PerformAction](#) ([Subject](#) *s, [ULEvent](#) &inEvent, [ULConnection](#) &inConnection, bool &outWaitingForEvent, [EEventID](#) &outRaisedEvent) override

Public Member Functions inherited from [gdcm::network::ULAction](#)

- [ULAction](#) ()=default
- [ULAction](#) (const [ULAction](#) &inAction)=delete
- virtual [~ULAction](#) ()=default
- void [operator=](#) (const [ULAction](#) &)=delete

10.333.1 Member Function Documentation**10.333.1.1 PerformAction()**

```
EStateID gdcm::network::ULActionAE3::PerformAction (
    Subject * s,
    ULEvent & inEvent,
    ULConnection & inConnection,
    bool & outWaitingForEvent,
    EEventID & outRaisedEvent) [override], [virtual]
```

Implements [gdcm::network::ULAction](#).


The documentation for this class was generated from the following file:

- [gdcmULActionAE.h](#)


10.334 gdcm::network::ULActionAE4 Class Reference

```
#include <gdcmULActionAE.h>
```

Inheritance diagram for [gdcm::network::ULActionAE4](#):



Collaboration diagram for `gdcm::network::ULActionAE4`:



Public Member Functions

- [EStateID PerformAction](#) ([Subject](#) *s, [ULEvent](#) &inEvent, [ULConnection](#) &inConnection, bool &outWaitingForEvent, [EEventID](#) &outRaisedEvent) override

Public Member Functions inherited from [gdcm::network::ULAction](#)

- [ULAction](#) ()=default
- [ULAction](#) (const [ULAction](#) &inAction)=delete
- virtual [~ULAction](#) ()=default
- void [operator=](#) (const [ULAction](#) &)=delete

10.334.1 Member Function Documentation

10.334.1.1 PerformAction()

```

EStateID gdcm::network::ULActionAE4::PerformAction (
    Subject * s,
    ULEvent & inEvent,
    ULConnection & inConnection,
    bool & outWaitingForEvent,
    EEventID & outRaisedEvent) [override], [virtual]
  
```

Implements [gdcm::network::ULAction](#).


The documentation for this class was generated from the following file:

- [gdcmULActionAE.h](#)


10.335 gdcm::network::ULActionAE5 Class Reference

```
#include <gdcmULActionAE.h>
```

Inheritance diagram for gdcm::network::ULActionAE5:



Collaboration diagram for gdcm::network::ULActionAE5:



Public Member Functions

- `EStateID PerformAction (Subject *s, ULEvent &inEvent, ULConnection &inConnection, bool &outWaitingForEvent, EEventID &outRaisedEvent)` override

Public Member Functions inherited from `gdcm::network::ULAction`

- `ULAction ()`=default
- `ULAction (const ULAction &inAction)`=delete
- virtual `~ULAction ()`=default
- void `operator= (const ULAction &)=delete`

10.335.1 Member Function Documentation

10.335.1.1 PerformAction()

```
EStateID gdcmm::network::ULActionAE5::PerformAction (
    Subject * s,
    ULEvent & inEvent,
    ULConnection & inConnection,
    bool & outWaitingForEvent,
    EEventID & outRaisedEvent) [override], [virtual]
```

Implements [gdcmm::network::ULAction](#).


The documentation for this class was generated from the following file:

- [gdcmmULActionAE.h](#)


10.336 gdcmm::network::ULActionAE6 Class Reference

```
#include <gdcmmULActionAE.h>
```

Inheritance diagram for gdcmm::network::ULActionAE6:



Collaboration diagram for gdcmm::network::ULActionAE6:



Public Member Functions

- [EStateID PerformAction](#) ([Subject](#) *s, [ULEvent](#) &inEvent, [ULConnection](#) &inConnection, bool &outWaitingForEvent, [EEventID](#) &outRaisedEvent) override

Public Member Functions inherited from [gdcm::network::ULAction](#)

- [ULAction](#) ()=default
- [ULAction](#) (const [ULAction](#) &inAction)=delete
- virtual [~ULAction](#) ()=default
- void [operator=](#) (const [ULAction](#) &)=delete

10.336.1 Member Function Documentation**10.336.1.1 PerformAction()**

```
EStateID gdcm::network::ULActionAE6::PerformAction (
    Subject * s,
    ULEvent & inEvent,
    ULConnection & inConnection,
    bool & outWaitingForEvent,
    EEventID & outRaisedEvent) [override], [virtual]
```

Implements [gdcm::network::ULAction](#).


The documentation for this class was generated from the following file:

- [gdcmULActionAE.h](#)


10.337 gdcm::network::ULActionAE7 Class Reference

```
#include <gdcmULActionAE.h>
```

Inheritance diagram for [gdcm::network::ULActionAE7](#):



Collaboration diagram for `gdcm::network::ULActionAE7`:



Public Member Functions

- [EStateID PerformAction](#) ([Subject](#) *s, [ULEvent](#) &inEvent, [ULConnection](#) &inConnection, bool &outWaitingForEvent, [EEventID](#) &outRaisedEvent) override

Public Member Functions inherited from [gdcm::network::ULAction](#)

- [ULAction](#) ()=default
- [ULAction](#) (const [ULAction](#) &inAction)=delete
- virtual [~ULAction](#) ()=default
- void [operator=](#) (const [ULAction](#) &)=delete

10.337.1 Member Function Documentation

10.337.1.1 PerformAction()

```

EStateID gdcm::network::ULActionAE7::PerformAction (
    Subject * s,
    ULEvent & inEvent,
    ULConnection & inConnection,
    bool & outWaitingForEvent,
    EEventID & outRaisedEvent) [override], [virtual]
  
```

Implements [gdcm::network::ULAction](#).


The documentation for this class was generated from the following file:

- [gdcmULActionAE.h](#)


10.338 gdcm::network::ULActionAE8 Class Reference

```
#include <gdcmULActionAE.h>
```

Inheritance diagram for gdcm::network::ULActionAE8:



Collaboration diagram for gdcm::network::ULActionAE8:



Public Member Functions

- [EStateID PerformAction](#) ([Subject](#) *s, [ULEvent](#) &inEvent, [ULConnection](#) &inConnection, bool &outWaitingForEvent, [EEventID](#) &outRaisedEvent) override

Public Member Functions inherited from [gdcm::network::ULAction](#)

- [ULAction](#) ()=default
- [ULAction](#) (const [ULAction](#) &inAction)=delete
- virtual [~ULAction](#) ()=default
- void [operator=](#) (const [ULAction](#) &)=delete

10.338.1 Member Function Documentation

10.338.1.1 PerformAction()

```
EStateID gdcmm::network::ULActionAE8::PerformAction (  
    Subject * s,  
    ULEvent & inEvent,  
    ULConnection & inConnection,  
    bool & outWaitingForEvent,  
    EEventID & outRaisedEvent) [override], [virtual]
```

Implements [gdcmm::network::ULAction](#).


The documentation for this class was generated from the following file:

- [gdcmmULActionAE.h](#)


10.339 gdcmm::network::ULActionAR1 Class Reference

```
#include <gdcmmULActionAR.h>
```

Inheritance diagram for gdcmm::network::ULActionAR1:



Collaboration diagram for gdcmm::network::ULActionAR1:



Public Member Functions

- [EStateID PerformAction](#) ([Subject](#) *s, [ULEvent](#) &inEvent, [ULConnection](#) &inConnection, bool &outWaitingForEvent, [EEventID](#) &outRaisedEvent) override

Public Member Functions inherited from [gdcm::network::ULAction](#)

- [ULAction](#) ()=default
- [ULAction](#) (const [ULAction](#) &inAction)=delete
- virtual [~ULAction](#) ()=default
- void [operator=](#) (const [ULAction](#) &)=delete

10.339.1 Member Function Documentation**10.339.1.1 PerformAction()**

```
EStateID gdcm::network::ULActionAR1::PerformAction (
    Subject * s,
    ULEvent & inEvent,
    ULConnection & inConnection,
    bool & outWaitingForEvent,
    EEventID & outRaisedEvent) [override], [virtual]
```

Implements [gdcm::network::ULAction](#).


The documentation for this class was generated from the following file:

- [gdcmULActionAR.h](#)


10.340 gdcm::network::ULActionAR10 Class Reference

```
#include <gdcmULActionAR.h>
```

Inheritance diagram for [gdcm::network::ULActionAR10](#):



Collaboration diagram for `gdcm::network::ULActionAR10`:



Public Member Functions

- [EStateID PerformAction](#) ([Subject](#) *s, [ULEvent](#) &inEvent, [ULConnection](#) &inConnection, bool &outWaitingForEvent, [EEventID](#) &outRaisedEvent) override

Public Member Functions inherited from [gdcm::network::ULAction](#)

- [ULAction](#) ()=default
- [ULAction](#) (const [ULAction](#) &inAction)=delete
- virtual [~ULAction](#) ()=default
- void [operator=](#) (const [ULAction](#) &)=delete

10.340.1 Member Function Documentation

10.340.1.1 PerformAction()

```

EStateID gdcm::network::ULActionAR10::PerformAction (
    Subject * s,
    ULEvent & inEvent,
    ULConnection & inConnection,
    bool & outWaitingForEvent,
    EEventID & outRaisedEvent) [override], [virtual]
  
```

Implements [gdcm::network::ULAction](#).


The documentation for this class was generated from the following file:

- [gdcmULActionAR.h](#)


10.341 gdcm::network::ULActionAR2 Class Reference

```
#include <gdcmULActionAR.h>
```

Inheritance diagram for gdcm::network::ULActionAR2:



Collaboration diagram for gdcm::network::ULActionAR2:



Public Member Functions

- [EStateID PerformAction](#) ([Subject](#) *s, [ULEvent](#) &inEvent, [ULConnection](#) &inConnection, bool &outWaitingForEvent, [EEventID](#) &outRaisedEvent) override

Public Member Functions inherited from [gdcm::network::ULAction](#)

- [ULAction](#) ()=default
- [ULAction](#) (const [ULAction](#) &inAction)=delete
- virtual [~ULAction](#) ()=default
- void [operator=](#) (const [ULAction](#) &)=delete

10.341.1 Member Function Documentation

10.341.1.1 PerformAction()

```
EStateID gdcmm::network::ULActionAR2::PerformAction (
    Subject * s,
    ULEvent & inEvent,
    ULConnection & inConnection,
    bool & outWaitingForEvent,
    EEventID & outRaisedEvent) [override], [virtual]
```

Implements [gdcmm::network::ULAction](#).


The documentation for this class was generated from the following file:

- [gdcmmULActionAR.h](#)


10.342 gdcmm::network::ULActionAR3 Class Reference

```
#include <gdcmmULActionAR.h>
```

Inheritance diagram for gdcmm::network::ULActionAR3:



Collaboration diagram for gdcmm::network::ULActionAR3:



Public Member Functions

- [EStateID PerformAction](#) ([Subject](#) *s, [ULEvent](#) &inEvent, [ULConnection](#) &inConnection, bool &outWaitingForEvent, [EEventID](#) &outRaisedEvent) override

Public Member Functions inherited from [gdcm::network::ULAction](#)

- [ULAction](#) ()=default
- [ULAction](#) (const [ULAction](#) &inAction)=delete
- virtual [~ULAction](#) ()=default
- void [operator=](#) (const [ULAction](#) &)=delete

10.342.1 Member Function Documentation**10.342.1.1 PerformAction()**

```
EStateID gdcm::network::ULActionAR3::PerformAction (
    Subject * s,
    ULEvent & inEvent,
    ULConnection & inConnection,
    bool & outWaitingForEvent,
    EEventID & outRaisedEvent) [override], [virtual]
```

Implements [gdcm::network::ULAction](#).


The documentation for this class was generated from the following file:

- [gdcmULActionAR.h](#)


10.343 gdcm::network::ULActionAR4 Class Reference

```
#include <gdcmULActionAR.h>
```

Inheritance diagram for [gdcm::network::ULActionAR4](#):



Collaboration diagram for `gdcm::network::ULActionAR4`:



Public Member Functions

- `EStateID PerformAction (Subject *s, ULEvent &inEvent, ULConnection &inConnection, bool &outWaitingForEvent, EEventID &outRaisedEvent)` override

Public Member Functions inherited from `gdcm::network::ULAction`

- `ULAction ()`=default
- `ULAction (const ULAction &inAction)`=delete
- virtual `~ULAction ()`=default
- void `operator= (const ULAction &)`=delete

10.343.1 Member Function Documentation

10.343.1.1 PerformAction()

```

EStateID gdcm::network::ULActionAR4::PerformAction (
    Subject * s,
    ULEvent & inEvent,
    ULConnection & inConnection,
    bool & outWaitingForEvent,
    EEventID & outRaisedEvent) [override], [virtual]
  
```

Implements `gdcm::network::ULAction`.


The documentation for this class was generated from the following file:

- `gdcmULActionAR.h`


10.344 gdcm::network::ULActionAR5 Class Reference

```
#include <gdcmULActionAR.h>
```

Inheritance diagram for gdcm::network::ULActionAR5:



Collaboration diagram for gdcm::network::ULActionAR5:



Public Member Functions

- [EStateID PerformAction](#) ([Subject](#) *s, [ULEvent](#) &inEvent, [ULConnection](#) &inConnection, bool &outWaitingForEvent, [EEventID](#) &outRaisedEvent) override

Public Member Functions inherited from [gdcm::network::ULAction](#)

- [ULAction](#) ()=default
- [ULAction](#) (const [ULAction](#) &inAction)=delete
- virtual [~ULAction](#) ()=default
- void [operator=](#) (const [ULAction](#) &)=delete

10.344.1 Member Function Documentation

10.344.1.1 PerformAction()

```
EStateID gdcmm::network::ULActionAR5::PerformAction (
    Subject * s,
    ULEvent & inEvent,
    ULConnection & inConnection,
    bool & outWaitingForEvent,
    EEventID & outRaisedEvent) [override], [virtual]
```

Implements [gdcmm::network::ULAction](#).


The documentation for this class was generated from the following file:

- [gdcmmULActionAR.h](#)


10.345 gdcmm::network::ULActionAR6 Class Reference

```
#include <gdcmmULActionAR.h>
```

Inheritance diagram for gdcmm::network::ULActionAR6:



Collaboration diagram for gdcmm::network::ULActionAR6:



Public Member Functions

- [EStateID PerformAction](#) ([Subject](#) *s, [ULEvent](#) &inEvent, [ULConnection](#) &inConnection, bool &outWaitingForEvent, [EEventID](#) &outRaisedEvent) override

Public Member Functions inherited from [gdcm::network::ULAction](#)

- [ULAction](#) ()=default
- [ULAction](#) (const [ULAction](#) &inAction)=delete
- virtual [~ULAction](#) ()=default
- void [operator=](#) (const [ULAction](#) &)=delete

10.345.1 Member Function Documentation**10.345.1.1 PerformAction()**

```
EStateID gdcm::network::ULActionAR6::PerformAction (
    Subject * s,
    ULEvent & inEvent,
    ULConnection & inConnection,
    bool & outWaitingForEvent,
    EEventID & outRaisedEvent) [override], [virtual]
```

Implements [gdcm::network::ULAction](#).


The documentation for this class was generated from the following file:

- [gdcmULActionAR.h](#)


10.346 gdcm::network::ULActionAR7 Class Reference

```
#include <gdcmULActionAR.h>
```

Inheritance diagram for [gdcm::network::ULActionAR7](#):



Collaboration diagram for `gdcm::network::ULActionAR7`:



Public Member Functions

- `EStateID PerformAction (Subject *s, ULEvent &inEvent, ULConnection &inConnection, bool &outWaitingForEvent, EEventID &outRaisedEvent)` override

Public Member Functions inherited from `gdcm::network::ULAction`

- `ULAction ()`=default
- `ULAction (const ULAction &inAction)`=delete
- virtual `~ULAction ()`=default
- void `operator= (const ULAction &)`=delete

10.346.1 Member Function Documentation

10.346.1.1 PerformAction()

```

EStateID gdcm::network::ULActionAR7::PerformAction (
    Subject * s,
    ULEvent & inEvent,
    ULConnection & inConnection,
    bool & outWaitingForEvent,
    EEventID & outRaisedEvent) [override], [virtual]
  
```

Implements `gdcm::network::ULAction`.


The documentation for this class was generated from the following file:

- `gdcmULActionAR.h`


10.347 gdcmm::network::ULActionAR8 Class Reference

```
#include <gdcmmULActionAR.h>
```

Inheritance diagram for gdcmm::network::ULActionAR8:



Collaboration diagram for gdcmm::network::ULActionAR8:



Public Member Functions

- [EStateID PerformAction](#) ([Subject](#) *s, [ULEvent](#) &inEvent, [ULConnection](#) &inConnection, bool &outWaitingForEvent, [EEventID](#) &outRaisedEvent) override

Public Member Functions inherited from [gdcmm::network::ULAction](#)

- [ULAction](#) ()=default
- [ULAction](#) (const [ULAction](#) &inAction)=delete
- virtual [~ULAction](#) ()=default
- void [operator=](#) (const [ULAction](#) &)=delete

10.347.1 Member Function Documentation

10.347.1.1 PerformAction()

```
EStateID gdcn::network::ULActionAR8::PerformAction (  
    Subject * s,  
    ULEvent & inEvent,  
    ULConnection & inConnection,  
    bool & outWaitingForEvent,  
    EEventID & outRaisedEvent) [override], [virtual]
```

Implements [gdcn::network::ULAction](#).


The documentation for this class was generated from the following file:

- [gdcnULActionAR.h](#)


10.348 gdcn::network::ULActionAR9 Class Reference

```
#include <gdcnULActionAR.h>
```

Inheritance diagram for gdcn::network::ULActionAR9:



Collaboration diagram for gdcn::network::ULActionAR9:



Public Member Functions

- [EStateID PerformAction](#) ([Subject](#) *s, [ULEvent](#) &inEvent, [ULConnection](#) &inConnection, bool &outWaitingForEvent, [EEventID](#) &outRaisedEvent) override

Public Member Functions inherited from [gdcm::network::ULAction](#)

- [ULAction](#) ()=default
- [ULAction](#) (const [ULAction](#) &inAction)=delete
- virtual [~ULAction](#) ()=default
- void [operator=](#) (const [ULAction](#) &)=delete

10.348.1 Member Function Documentation**10.348.1.1 PerformAction()**

```
EStateID gdcm::network::ULActionAR9::PerformAction (
    Subject * s,
    ULEvent & inEvent,
    ULConnection & inConnection,
    bool & outWaitingForEvent,
    EEventID & outRaisedEvent) [override], [virtual]
```

Implements [gdcm::network::ULAction](#).


The documentation for this class was generated from the following file:

- [gdcmULActionAR.h](#)


10.349 gdcm::network::ULActionDT1 Class Reference

```
#include <gdcmULActionDT.h>
```

Inheritance diagram for [gdcm::network::ULActionDT1](#):



Collaboration diagram for `gdcm::network::ULActionDT1`:



Public Member Functions

- [EStateID PerformAction](#) ([Subject](#) *s, [ULEvent](#) &inEvent, [ULConnection](#) &inConnection, bool &outWaitingForEvent, [EEventID](#) &outRaisedEvent) override

Public Member Functions inherited from [gdcm::network::ULAction](#)

- [ULAction](#) ()=default
- [ULAction](#) (const [ULAction](#) &inAction)=delete
- virtual [~ULAction](#) ()=default
- void [operator=](#) (const [ULAction](#) &)=delete

10.349.1 Member Function Documentation

10.349.1.1 PerformAction()

```

EStateID gdcm::network::ULActionDT1::PerformAction (
    Subject * s,
    ULEvent & inEvent,
    ULConnection & inConnection,
    bool & outWaitingForEvent,
    EEventID & outRaisedEvent) [override], [virtual]
  
```

Implements [gdcm::network::ULAction](#).


The documentation for this class was generated from the following file:

- [gdcmULActionDT.h](#)


10.350 gdcm::network::ULActionDT2 Class Reference

```
#include <gdcmULActionDT.h>
```

Inheritance diagram for gdcm::network::ULActionDT2:



Collaboration diagram for gdcm::network::ULActionDT2:



Public Member Functions

- [EStateID PerformAction](#) ([Subject](#) *s, [ULEvent](#) &inEvent, [ULConnection](#) &inConnection, bool &outWaitingForEvent, [EEventID](#) &outRaisedEvent) override

Public Member Functions inherited from [gdcm::network::ULAction](#)

- [ULAction](#) ()=default
- [ULAction](#) (const [ULAction](#) &inAction)=delete
- virtual [~ULAction](#) ()=default
- void [operator=](#) (const [ULAction](#) &)=delete

10.350.1 Member Function Documentation

10.350.1.1 PerformAction()

```
EStateID gdcn::network::ULActionDT2::PerformAction (  
    Subject * s,  
    ULEvent & inEvent,  
    ULConnection & inConnection,  
    bool & outWaitingForEvent,  
    EEventID & outRaisedEvent) [override], [virtual]
```

Implements [gdcn::network::ULAction](#).

The documentation for this class was generated from the following file:


- [gdcnULActionDT.h](#)

10.351 gdcn::network::ULBasicCallback Class Reference


[ULBasicCallback](#).

```
#include <gdcnULBasicCallback.h>
```

Inheritance diagram for `gdcn::network::ULBasicCallback`:



Collaboration diagram for gdcm::network::ULBasicCallback:



Public Member Functions

- [ULBasicCallback](#) ()=default
- [~ULBasicCallback](#) () override=default
- `std::vector< DataSet > const & GetDataSets () const`
- `std::vector< DataSet > const & GetResponses () const`
- `void HandleDataSet (const DataSet &inDataSet) override`
- `void HandleResponse (const DataSet &inDataSet) override`

Public Member Functions inherited from [gdcm::network::ULConnectionCallback](#)

- [ULConnectionCallback](#) ()
- `virtual ~ULConnectionCallback ()=default`
- `bool DataSetHandles () const`
- `void ResetHandledDataSet ()`
- `void SetImplicitFlag (const bool imp)`

Additional Inherited Members

Protected Member Functions inherited from [gdcm::network::ULConnectionCallback](#)

- `void DataSetHandled ()`

Protected Attributes inherited from [gdcm::network::ULConnectionCallback](#)

- `bool mImplicit`

10.351.1 Detailed Description

[ULBasicCallback](#).

This is the most basic of callbacks for how the [ULConnectionManager](#) handles incoming datasets. DataSets are just concatenated to the mDataSets vector, and the result can be pulled out of the vector by later code. Alternatives to this method include progress updates, saving to disk, etc. This class is NOT THREAD SAFE. Access the dataset vector after the entire set of datasets has been returned by the [ULConnectionManager](#).

10.351.2 Constructor & Destructor Documentation

10.351.2.1 [ULBasicCallback\(\)](#)

```
gdcmm::network::ULBasicCallback::ULBasicCallback () [default]
```

10.351.2.2 [~ULBasicCallback\(\)](#)

```
gdcmm::network::ULBasicCallback::~~ULBasicCallback () [override], [default]
```

10.351.3 Member Function Documentation

10.351.3.1 [GetDataSets\(\)](#)

```
std::vector< DataSet > const & gdcmm::network::ULBasicCallback::GetDataSets () const
```

10.351.3.2 [GetResponses\(\)](#)

```
std::vector< DataSet > const & gdcmm::network::ULBasicCallback::GetResponses () const
```

10.351.3.3 [HandleDataSet\(\)](#)

```
void gdcmm::network::ULBasicCallback::HandleDataSet (  
    const DataSet & inDataSet) [override], [virtual]
```

Implements [gdcmm::network::ULConnectionCallback](#).

10.351.3.4 [HandleResponse\(\)](#)

```
void gdcmm::network::ULBasicCallback::HandleResponse (  
    const DataSet & inDataSet) [override], [virtual]
```

Implements [gdcmm::network::ULConnectionCallback](#).

The documentation for this class was generated from the following file:

- [gdcmmULBasicCallback.h](#)

10.352 gdcm::network::ULConnection Class Reference

[ULConnection](#).

```
#include <gdcmULConnection.h>
```

Public Member Functions

- [ULConnection](#) (const [ULConnection](#) &)=delete
- [ULConnection](#) (const [ULConnectionInfo](#) &inUserInformation)
- virtual [~ULConnection](#) ()
- void [AddAcceptedPresentationContext](#) (const [PresentationContextAC](#) &inPC)
- [PresentationContextRQ](#) [FindContext](#) (const [DataElement](#) &de) const
- std::vector< [PresentationContextAC](#) > & [GetAcceptedPresentationContexts](#) ()
- std::vector< [PresentationContextAC](#) > const & [GetAcceptedPresentationContexts](#) () const
- const [ULConnectionInfo](#) & [GetConnectionInfo](#) () const
- uint32_t [GetMaxPDUSize](#) () const
- const [PresentationContextAC](#) * [GetPresentationContextACByID](#) (uint8_t id) const
- uint8_t [GetPresentationContextIDFromPresentationContext](#) ([PresentationContextRQ](#) const &pc) const
return 0 upon error
- const [PresentationContextRQ](#) * [GetPresentationContextRQByID](#) (uint8_t id) const
- std::vector< [PresentationContextRQ](#) > const & [GetPresentationContexts](#) () const
- std::iostream * [GetProtocol](#) ()
- [EStateID](#) [GetState](#) () const
- [ARTIMTimer](#) & [GetTimer](#) ()
- bool [InitializeConnection](#) ()
used to establish scu connections
- bool [InitializeIncomingConnection](#) ()
used to establish scp connections
- void [operator=](#) (const [ULConnection](#) &)=delete
- void [SetMaxPDUSize](#) (uint32_t inSize)
- void [SetPresentationContexts](#) (const std::vector< [PresentationContext](#) > &inContexts)
- void [SetPresentationContexts](#) (const std::vector< [PresentationContextRQ](#) > &inContexts)
- void [SetState](#) (const [EStateID](#) &inState)
- void [StopProtocol](#) ()

Friends

- class [ULActionAE6](#)
- class [ULConnectionManager](#)

10.352.1 Detailed Description

[ULConnection](#).

This is the class that contains the socket to another machine, and passes data through itself, as well as maintaining a sense of state.

The [ULConnectionManager](#) tells the [ULConnection](#) what data can actually be sent.

This class is done this way so that it can be eventually be replaced with a [ULSecureConnection](#), if such a protocol is warranted, so that all data that passes through can be managed through a secure connection. For now, this class provides a simple pass-through mechanism to the socket itself.

So, for instance, a [gdcm](#) object will be passes to this object, and it will then get passed along the connection, if that connection is in the proper state to do so.

For right now, this class is not directly intended to be inherited from, but the potential for future [ULSecureConnection](#) warrants the addition, rather than having everything be managed from within the [ULConnectionManager](#) (or this class) without a wrapper.

10.352.2 Constructor & Destructor Documentation

10.352.2.1 [ULConnection\(\)](#) [1/2]

```
gdcm::network::ULConnection::ULConnection (
    const ULConnectionInfo & inUserInformation)
```

Referenced by [ULConnection\(\)](#), and [operator=\(\)](#).

10.352.2.2 [~ULConnection\(\)](#)

```
virtual gdcm::network::ULConnection::~~ULConnection () [virtual]
```

10.352.2.3 [ULConnection\(\)](#) [2/2]

```
gdcm::network::ULConnection::ULConnection (
    const ULConnection & ) [delete]
```

References [ULConnection\(\)](#).

10.352.3 Member Function Documentation

10.352.3.1 [AddAcceptedPresentationContext\(\)](#)

```
void gdcm::network::ULConnection::AddAcceptedPresentationContext (
    const PresentationContextAC & inPC)
```


10.352.3.2 FindContext()

```
PresentationContextRQ gdcm::network::ULConnection::FindContext (
    const DataElement & de) const
```

10.352.3.3 GetAcceptedPresentationContexts() [1/2]

```
std::vector< PresentationContextAC > & gdcm::network::ULConnection::GetAcceptedPresentation←
Contexts ()
```

10.352.3.4 GetAcceptedPresentationContexts() [2/2]

```
std::vector< PresentationContextAC > const & gdcm::network::ULConnection::GetAcceptedPresentation←
Contexts () const
```

10.352.3.5 GetConnectionInfo()

```
const ULConnectionInfo & gdcm::network::ULConnection::GetConnectionInfo () const
```

10.352.3.6 GetMaxPDUSize()

```
uint32_t gdcm::network::ULConnection::GetMaxPDUSize () const
```

10.352.3.7 GetPresentationContextACByID()

```
const PresentationContextAC * gdcm::network::ULConnection::GetPresentationContextACByID (
    uint8_t id) const
```

10.352.3.8 GetPresentationContextIDFromPresentationContext()

```
uint8_t gdcm::network::ULConnection::GetPresentationContextIDFromPresentationContext (
    PresentationContextRQ const & pc) const
```

return 0 upon error

10.352.3.9 GetPresentationContextRQByID()

```
const PresentationContextRQ * gdcm::network::ULConnection::GetPresentationContextRQByID (
    uint8_t id) const
```

10.352.3.10 GetPresentationContexts()

```
std::vector< PresentationContextRQ > const & gdcM::network::ULConnection::GetPresentationContexts  
( ) const
```

10.352.3.11 GetProtocol()

```
std::iostream * gdcM::network::ULConnection::GetProtocol ( )
```

10.352.3.12 GetState()

```
EStateID gdcM::network::ULConnection::GetState ( ) const
```

10.352.3.13 GetTimer()

```
ARTIMTimer & gdcM::network::ULConnection::GetTimer ( )
```

10.352.3.14 InitializeConnection()

```
bool gdcM::network::ULConnection::InitializeConnection ( )
```

used to establish scu connections

10.352.3.15 InitializeIncomingConnection()

```
bool gdcM::network::ULConnection::InitializeIncomingConnection ( )
```

used to establish scp connections

10.352.3.16 operator=()

```
void gdcM::network::ULConnection::operator= (   
    const ULConnection & ) [delete]
```

References [ULConnection\(\)](#).

10.352.3.17 SetMaxPDUSize()

```
void gdcM::network::ULConnection::SetMaxPDUSize (   
    uint32_t inSize)
```

10.352.3.18 SetPresentationContexts() [1/2]

```
void gdcm::network::ULConnection::SetPresentationContexts (
    const std::vector< PresentationContext > & inContexts)
```

10.352.3.19 SetPresentationContexts() [2/2]

```
void gdcm::network::ULConnection::SetPresentationContexts (
    const std::vector< PresentationContextRQ > & inContexts)
```

10.352.3.20 SetState()

```
void gdcm::network::ULConnection::SetState (
    const EStateID & inState)
```

10.352.3.21 StopProtocol()

```
void gdcm::network::ULConnection::StopProtocol ()
```

10.352.4 Friends And Related Symbol Documentation**10.352.4.1 ULActionAE6**

```
friend class ULActionAE6 [friend]
```

References [ULActionAE6](#).

Referenced by [ULActionAE6](#).

10.352.4.2 ULConnectionManager

```
friend class ULConnectionManager [friend]
```

References [ULConnectionManager](#).

Referenced by [ULConnectionManager](#).


The documentation for this class was generated from the following file:

- [gdcmULConnection.h](#)

10.353 gdcm::network::ULConnectionCallback Class Reference

```
#include <gdcmULConnectionCallback.h>
```

Inheritance diagram for gdcm::network::ULConnectionCallback:



Public Member Functions

- [ULConnectionCallback](#) ()
- virtual [~ULConnectionCallback](#) ()=default
- bool [DataSetHandles](#) () const
- virtual void [HandleDataSet](#) (const [DataSet](#) &inDataSet)=0
- virtual void [HandleResponse](#) (const [DataSet](#) &inDataSet)=0
- void [ResetHandledDataSet](#) ()
- void [SetImplicitFlag](#) (const bool imp)

Protected Member Functions

- void [DataSetHandled](#) ()

Protected Attributes

- bool [mImplicit](#)

10.353.1 Detailed Description

When a dataset comes back from a query/move/etc, the result can either be stored entirely in memory, or could be stored on disk. This class provides a mechanism to indicate what the [ULConnectionManager](#) should do with datasets that are produced through query results. The [ULConnectionManager](#) will call the [HandleDataSet](#) function during the course of receiving datasets. Particular implementations should fill in what that function does, including updating progress, etc. NOTE: since cmove requires that multiple event loops be employed, the callback function MUST set `mHandledDataSet` to true. otherwise, the cmove event loop handler will not know data was received, and proceed to end the loop prematurely.

10.353.2 Constructor & Destructor Documentation

10.353.2.1 ULConnectionCallback()

```
gdcm::network::ULConnectionCallback::ULConnectionCallback () [inline]
```

References [mImplicit](#).

10.353.2.2 ~ULConnectionCallback()

```
virtual gdcm::network::ULConnectionCallback::~~ULConnectionCallback () [virtual], [default]
```

10.353.3 Member Function Documentation

10.353.3.1 DataSetHandled()

```
void gdcm::network::ULConnectionCallback::DataSetHandled () [inline], [protected]
```

10.353.3.2 DataSetHandles()

```
bool gdcm::network::ULConnectionCallback::DataSetHandles () const [inline]
```

10.353.3.3 HandleDataSet()

```
virtual void gdcm::network::ULConnectionCallback::HandleDataSet (  
    const DataSet & inDataSet) [pure virtual]
```

Implemented in [gdcm::network::ULBasicCallback](#), and [gdcm::network::ULWritingCallback](#).

10.353.3.4 HandleResponse()

```
virtual void gdcm::network::ULConnectionCallback::HandleResponse (  
    const DataSet & inDataSet) [pure virtual]
```

Implemented in [gdcm::network::ULBasicCallback](#), and [gdcm::network::ULWritingCallback](#).

10.353.3.5 ResetHandledDataSet()

```
void gdcm::network::ULConnectionCallback::ResetHandledDataSet () [inline]
```

10.353.3.6 SetImplicitFlag()

```
void gdcmm::network::ULConnectionCallback::SetImplicitFlag (  
    const bool imp) [inline]
```

References [mImplicit](#).

10.353.4 Member Data Documentation

10.353.4.1 mImplicit

```
bool gdcmm::network::ULConnectionCallback::mImplicit [protected]
```

Referenced by [ULConnectionCallback\(\)](#), and [SetImplicitFlag\(\)](#).

The documentation for this class was generated from the following file:

- [gdcmmULConnectionCallback.h](#)

10.354 gdcmm::network::ULConnectionInfo Class Reference

[ULConnectionInfo](#).

```
#include <gdcmmULConnectionInfo.h>
```

Public Member Functions

- [ULConnectionInfo](#) ()
- const char * [GetCalledAETitle](#) () const
- std::string [GetCalledComputerName](#) () const
- unsigned long [GetCalledIPAddress](#) () const
- int [GetCalledIPPort](#) () const
- const char * [GetCallingAETitle](#) () const
- unsigned long [GetMaxPDULength](#) () const
- bool [Initialize](#) ([UserInfo](#) const &inUserInfo, const char *inCalledAETitle, const char *inCallingAETitle, unsigned long inCalledIPAddress, int inCalledIPPort, std::string inCalledComputerName)
- void [SetMaxPDULength](#) (unsigned long inMaxPDULength)

10.354.1 Detailed Description

[ULConnectionInfo](#).

this class contains all the information about a particular connection as established by the user. That is, it's: User Information Calling AE Title Called AE Title IP address/computer name IP Port A connection must be established with this information, that's subsequently placed into various primitives for actual communication.

10.354.2 Constructor & Destructor Documentation

10.354.2.1 ULConnectionInfo()

```
gdcm::network::ULConnectionInfo::ULConnectionInfo ()
```

10.354.3 Member Function Documentation

10.354.3.1 GetCalledAETitle()

```
const char * gdcm::network::ULConnectionInfo::GetCalledAETitle () const
```

10.354.3.2 GetCalledComputerName()

```
std::string gdcm::network::ULConnectionInfo::GetCalledComputerName () const
```

10.354.3.3 GetCalledIPAddress()

```
unsigned long gdcm::network::ULConnectionInfo::GetCalledIPAddress () const
```

10.354.3.4 GetCalledIPPort()

```
int gdcm::network::ULConnectionInfo::GetCalledIPPort () const
```

10.354.3.5 GetCallingAETitle()

```
const char * gdcm::network::ULConnectionInfo::GetCallingAETitle () const
```

10.354.3.6 GetMaxPDULength()

```
unsigned long gdcm::network::ULConnectionInfo::GetMaxPDULength () const
```

10.354.3.7 Initialize()

```
bool gdcm::network::ULConnectionInfo::Initialize (  
    UserInformation const & inUserInformation,  
    const char * inCalledAETitle,  
    const char * inCallingAETitle,  
    unsigned long inCalledIPAddress,  
    int inCalledIPPort,  
    std::string inCalledComputerName)
```

10.354.3.8 SetMaxPDULength()

```
void gdcmm::network::ULConnectionInfo::SetMaxPDULength (
    unsigned long inMaxPDULength)
```

The documentation for this class was generated from the following file:


- [gdcmmULConnectionInfo.h](#)

10.355 gdcmm::network::ULConnectionManager Class Reference


[ULConnectionManager](#).

```
#include <gdcmmULConnectionManager.h>
```

Inheritance diagram for gdcmm::network::ULConnectionManager:



Collaboration diagram for gdcn::network::ULConnectionManager:



Public Member Functions

- [ULConnectionManager](#) ()
- [~ULConnectionManager](#) () override
- bool [BreakConnection](#) (const double &inTimeout)
- void [BreakConnectionNow](#) ()
- bool [EstablishConnection](#) (const std::string &inAETitle, const std::string &inConnectAETitle, const std::string &inComputerName, long inIPAddress, uint16_t inConnectPort, double inTimeout, std::vector< [PresentationContext](#) > const &pcVector)
- bool [EstablishConnectionMove](#) (const std::string &inAETitle, const std::string &inConnectAETitle, const std::string &inComputerName, long inIPAddress, uint16_t inConnectPort, double inTimeout, uint16_t inReturnPort, std::vector< [PresentationContext](#) > const &pcVector)
- std::vector< [PresentationDataValue](#) > [SendEcho](#) ()
- std::vector< [DataSet](#) > [SendFind](#) (const [BaseRootQuery](#) *inRootQuery)
- void [SendFind](#) (const [BaseRootQuery](#) *inRootQuery, [ULConnectionCallback](#) *inCallback)
- std::vector< [DataSet](#) > [SendMove](#) (const [BaseRootQuery](#) *inRootQuery)
- bool [SendMove](#) (const [BaseRootQuery](#) *inRootQuery, [ULConnectionCallback](#) *inCallback)
return false upon error
- std::vector< [DataSet](#) > [SendNAction](#) (const [BaseQuery](#) *inQuery)
- void [SendNAction](#) (const [BaseQuery](#) *inQuery, [ULConnectionCallback](#) *inCallback)
- std::vector< [DataSet](#) > [SendNCreate](#) (const [BaseQuery](#) *inQuery)
- void [SendNCreate](#) (const [BaseQuery](#) *inQuery, [ULConnectionCallback](#) *inCallback)
- std::vector< [DataSet](#) > [SendNDelete](#) (const [BaseQuery](#) *inQuery)
- void [SendNDelete](#) (const [BaseQuery](#) *inQuery, [ULConnectionCallback](#) *inCallback)
- std::vector< [DataSet](#) > [SendNEventReport](#) (const [BaseQuery](#) *inQuery)
- void [SendNEventReport](#) (const [BaseQuery](#) *inQuery, [ULConnectionCallback](#) *inCallback)
- std::vector< [DataSet](#) > [SendNGet](#) (const [BaseQuery](#) *inQuery)
- void [SendNGet](#) (const [BaseQuery](#) *inQuery, [ULConnectionCallback](#) *inCallback)
- std::vector< [DataSet](#) > [SendNSet](#) (const [BaseQuery](#) *inQuery)
- void [SendNSet](#) (const [BaseQuery](#) *inQuery, [ULConnectionCallback](#) *inCallback)
- std::vector< [DataSet](#) > [SendStore](#) (const [File](#) &file, std::istream *pStream=nullptr, std::streampos dataSetOffset=0)

- void [SendStore](#) (const [File](#) &file, [ULConnectionCallback](#) *inCallback, std::istream *pStream=nullptr, std::streampos dataSetOffset=0)
callback based API

Public Member Functions inherited from [gdcm::Subject](#)

- [Subject](#) ()
- [~Subject](#) () override
- unsigned long [AddObserver](#) (const [Event](#) &event, [Command](#) *)
- unsigned long [AddObserver](#) (const [Event](#) &event, [Command](#) *) const
- [Command](#) * [GetCommand](#) (unsigned long tag)
- bool [HasObserver](#) (const [Event](#) &event) const
- void [InvokeEvent](#) (const [Event](#) &)
- void [InvokeEvent](#) (const [Event](#) &) const
- void [RemoveAllObservers](#) ()
- void [RemoveObserver](#) (unsigned long tag)

Public Member Functions inherited from [gdcm::Object](#)

- [Object](#) ()
- [Object](#) (const [Object](#) &)
Special requirement for copy/cstor, assignment operator.
- virtual [~Object](#) ()
- void [operator=](#) (const [Object](#) &)
- virtual void [Print](#) (std::ostream &) const

Protected Member Functions

- [ULConnectionManager](#) (const [ULConnectionManager](#) &inCM)
- [EStateID](#) [RunEventLoop](#) ([ULEvent](#) &inEvent, [ULConnection](#) *inWhichConnection, [ULConnectionCallback](#) *inCallback, const bool &startWaiting)
- [EStateID](#) [RunMoveEventLoop](#) ([ULEvent](#) &inEvent, [ULConnectionCallback](#) *inCallback)

Protected Member Functions inherited from [gdcm::Object](#)

- void [Register](#) ()
- void [UnRegister](#) ()

Protected Attributes

- [ULConnection](#) * [mConnection](#)
- [ULConnection](#) * [mSecondaryConnection](#)
- [ULTransitionTable](#) [mTransitions](#)

10.355.1 Detailed Description

[ULConnectionManager](#).

The [ULConnectionManager](#) performs actions on the [ULConnection](#) given inputs from the user and from the state of what's going on around the connection (ie, timeouts of the ARTIM timer, responses from the peer across the connection, etc).

Its inputs are ULEvents, and it performs ULActions.

10.355.2 Constructor & Destructor Documentation

10.355.2.1 ULConnectionManager() [1/2]

```
gdcm::network::ULConnectionManager::ULConnectionManager (  
    const ULConnectionManager & inCM) [protected]
```

References [ULConnectionManager\(\)](#).

Referenced by [ULConnectionManager\(\)](#).

10.355.2.2 ULConnectionManager() [2/2]

```
gdcm::network::ULConnectionManager::ULConnectionManager ()
```

10.355.2.3 ~ULConnectionManager()

```
gdcm::network::ULConnectionManager::~~ULConnectionManager () [override]
```

10.355.3 Member Function Documentation

10.355.3.1 BreakConnection()

```
bool gdcm::network::ULConnectionManager::BreakConnection (  
    const double & inTimeout)
```

10.355.3.2 BreakConnectionNow()

```
void gdcm::network::ULConnectionManager::BreakConnectionNow ()
```

10.355.3.3 EstablishConnection()

```
bool gdcmm::network::ULConnectionManager::EstablishConnection (
    const std::string & inAETitle,
    const std::string & inConnectAETitle,
    const std::string & inComputerName,
    long inIPAddress,
    uint16_t inConnectPort,
    double inTimeout,
    std::vector< PresentationContext > const & pcVector)
```

returns true if a connection of the given AETitle (ie, 'this' program) is able to connect to the given AETitle and Port in a certain amount of time providing the connection type will establish the proper exchange syntax with a server; if a different functionality is required, a different connection should be established. returns false if the connection type is 'move'— have to give a return port for move to work as specified.

10.355.3.4 EstablishConnectionMove()

```
bool gdcmm::network::ULConnectionManager::EstablishConnectionMove (
    const std::string & inAETitle,
    const std::string & inConnectAETitle,
    const std::string & inComputerName,
    long inIPAddress,
    uint16_t inConnectPort,
    double inTimeout,
    uint16_t inReturnPort,
    std::vector< PresentationContext > const & pcVector)
```

returns true for above reasons, but contains the special 'move' port

10.355.3.5 RunEventLoop()

```
EStateID gdcmm::network::ULConnectionManager::RunEventLoop (
    ULEvent & inEvent,
    ULConnection * inWhichConnection,
    ULConnectionCallback * inCallback,
    const bool & startWaiting) [protected]
```

10.355.3.6 RunMoveEventLoop()

```
EStateID gdcmm::network::ULConnectionManager::RunMoveEventLoop (
    ULEvent & inEvent,
    ULConnectionCallback * inCallback) [protected]
```

10.355.3.7 SendEcho()

```
std::vector< PresentationDataValue > gdcmm::network::ULConnectionManager::SendEcho ()
```

10.355.3.8 SendFind() [1/2]

```
std::vector< DataSet > gdcmm::network::ULConnectionManager::SendFind (
    const BaseRootQuery * inRootQuery)
```

10.355.3.9 SendFind() [2/2]

```
void gdcmm::network::ULConnectionManager::SendFind (
    const BaseRootQuery * inRootQuery,
    ULConnectionCallback * inCallback)
```

10.355.3.10 SendMove() [1/2]

```
std::vector< DataSet > gdcmm::network::ULConnectionManager::SendMove (
    const BaseRootQuery * inRootQuery)
```

10.355.3.11 SendMove() [2/2]

```
bool gdcmm::network::ULConnectionManager::SendMove (
    const BaseRootQuery * inRootQuery,
    ULConnectionCallback * inCallback)
```

return false upon error

10.355.3.12 SendNAction() [1/2]

```
std::vector< DataSet > gdcmm::network::ULConnectionManager::SendNAction (
    const BaseQuery * inQuery)
```

10.355.3.13 SendNAction() [2/2]

```
void gdcmm::network::ULConnectionManager::SendNAction (
    const BaseQuery * inQuery,
    ULConnectionCallback * inCallback)
```

10.355.3.14 SendNCreate() [1/2]

```
std::vector< DataSet > gdcmm::network::ULConnectionManager::SendNCreate (
    const BaseQuery * inQuery)
```

10.355.3.15 SendNCreate() [2/2]

```
void gdcm::network::ULConnectionManager::SendNCreate (
    const BaseQuery * inQuery,
    ULConnectionCallback * inCallback)
```

10.355.3.16 SendNDelete() [1/2]

```
std::vector< DataSet > gdcm::network::ULConnectionManager::SendNDelete (
    const BaseQuery * inQuery)
```

10.355.3.17 SendNDelete() [2/2]

```
void gdcm::network::ULConnectionManager::SendNDelete (
    const BaseQuery * inQuery,
    ULConnectionCallback * inCallback)
```

10.355.3.18 SendNEventReport() [1/2]

```
std::vector< DataSet > gdcm::network::ULConnectionManager::SendNEventReport (
    const BaseQuery * inQuery)
```

10.355.3.19 SendNEventReport() [2/2]

```
void gdcm::network::ULConnectionManager::SendNEventReport (
    const BaseQuery * inQuery,
    ULConnectionCallback * inCallback)
```

10.355.3.20 SendNGet() [1/2]

```
std::vector< DataSet > gdcm::network::ULConnectionManager::SendNGet (
    const BaseQuery * inQuery)
```

10.355.3.21 SendNGet() [2/2]

```
void gdcm::network::ULConnectionManager::SendNGet (
    const BaseQuery * inQuery,
    ULConnectionCallback * inCallback)
```

10.355.3.22 SendNSet() [1/2]

```
std::vector< DataSet > gdcm::network::ULConnectionManager::SendNSet (
    const BaseQuery * inQuery)
```

10.355.3.23 SendNSet() [2/2]

```
void gdcm::network::ULConnectionManager::SendNSet (
    const BaseQuery * inQuery,
    ULConnectionCallback * inCallback)
```

10.355.3.24 SendStore() [1/2]

```
std::vector< DataSet > gdcm::network::ULConnectionManager::SendStore (
    const File & file,
    std::istream * pStream = nullptr,
    std::streampos dataSetOffset = 0)
```

10.355.3.25 SendStore() [2/2]

```
void gdcm::network::ULConnectionManager::SendStore (
    const File & file,
    ULConnectionCallback * inCallback,
    std::istream * pStream = nullptr,
    std::streampos dataSetOffset = 0)
```

callback based API

10.355.4 Member Data Documentation

10.355.4.1 mConnection

`ULConnection*` gdcm::network::ULConnectionManager::mConnection [protected]

10.355.4.2 mSecondaryConnection

`ULConnection*` gdcm::network::ULConnectionManager::mSecondaryConnection [protected]

10.355.4.3 mTransitions

`ULTransitionTable` gdcm::network::ULConnectionManager::mTransitions [protected]

The documentation for this class was generated from the following file:

- [gdcmULConnectionManager.h](#)

10.356 gdcm::network::ULEvent Class Reference

[ULEvent.](#)

```
#include <gdcmULEvent.h>
```

Public Member Functions

- [ULEvent](#) (const [EEventID](#) &inEventID, [BasePDU](#) *inBasePDU, std::istream *iStream=nullptr, std::streampos posDataSet=0)
- [ULEvent](#) (const [EEventID](#) &inEventID, std::vector< [BasePDU](#) * > inBasePDU, std::istream *iStream=nullptr, std::streampos posDataSet=0)
- [~ULEvent](#) ()
- std::streampos [GetDataSetPos](#) () const
- [EEventID](#) [GetEvent](#) () const
- std::istream * [GetIStream](#) () const
- std::vector< [BasePDU](#) * > const & [GetPDUs](#) () const
- void [SetEvent](#) (const [EEventID](#) &inEvent)
- void [SetPDU](#) (std::vector< [BasePDU](#) * > const &inPDU)

10.356.1 Detailed Description

[ULEvent.](#)

base class for network events.

An event consists of the event ID and the data associated with that event.

Note that once a PDU is created, it is now the responsibility of the associated event to destroy it!

10.356.2 Constructor & Destructor Documentation

10.356.2.1 ULEvent() [1/2]

```
gdcm::network::ULEvent::ULEvent (
    const EEventID & inEventID,
    std::vector< BasePDU * > inBasePDU,
    std::istream * iStream = nullptr,
    std::streampos posDataSet = 0) [inline]
```

10.356.2.2 ULEvent() [2/2]

```
gdcm::network::ULEvent::ULEvent (
    const EEventID & inEventID,
    BasePDU * inBasePDU,
    std::istream * iStream = nullptr,
    std::streampos posDataSet = 0) [inline]
```


10.356.2.3 ~ULEvent()

```
gdcm::network::ULEvent::~~ULEvent () [inline]
```

10.356.3 Member Function Documentation

10.356.3.1 GetDataSetPos()

```
std::streampos gdcm::network::ULEvent::GetDataSetPos () const [inline]
```

10.356.3.2 GetEvent()

```
EEventID gdcm::network::ULEvent::GetEvent () const [inline]
```

10.356.3.3 GetIStream()

```
std::istream * gdcm::network::ULEvent::GetIStream () const [inline]
```

10.356.3.4 GetPDUs()

```
std::vector< BasePDU * > const & gdcm::network::ULEvent::GetPDUs () const [inline]
```

10.356.3.5 SetEvent()

```
void gdcm::network::ULEvent::SetEvent (  
    const EEventID & inEvent) [inline]
```

10.356.3.6 SetPDU()

```
void gdcm::network::ULEvent::SetPDU (  
    std::vector< BasePDU * > const & inPDU) [inline]
```

The documentation for this class was generated from the following file:

- [gdcmULEvent.h](#)

10.357 gdcm::network::ULTransitionTable Class Reference

[ULTransitionTable](#) The transition table of all the ULEvents, new ULActions, and ULStates.

```
#include <gdcmULTransitionTable.h>
```

Public Member Functions

- [ULTransitionTable](#) ()
- void [HandleEvent](#) ([Subject](#) *s, [ULEvent](#) &inEvent, [ULConnection](#) &inConnection, bool &outWaitingForEvent, [EEventID](#) &outRaisedEvent) const
- void [PrintTable](#) () const

10.357.1 Detailed Description

[ULTransitionTable](#) The transition table of all the ULEvents, new ULActions, and ULStates.

Based roughly on the solutions in player2.cpp in the boost examples and this so question: <http://stackoverflow.com/questions/1647631/c-state-machine-design>

The transition table is constructed of TableRows. Each row is based on an event, and an event handler in the TransitionTable object takes a given event, and then finds the given row.

Then, given the current state of the connection, determines the appropriate action to take and then the state to transition to next.

10.357.2 Constructor & Destructor Documentation

10.357.2.1 ULTransitionTable()

```
gdcmm::network::ULTransitionTable::ULTransitionTable ()
```

10.357.3 Member Function Documentation

10.357.3.1 HandleEvent()

```
void gdcmm::network::ULTransitionTable::HandleEvent (
    Subject * s,
    ULEvent & inEvent,
    ULConnection & inConnection,
    bool & outWaitingForEvent,
    EEventID & outRaisedEvent) const
```

10.357.3.2 PrintTable()

```
void gdcmm::network::ULTransitionTable::PrintTable () const
```


The documentation for this class was generated from the following file:

- [gdcmmULTransitionTable.h](#)


10.358 gdcm::network::ULWritingCallback Class Reference

```
#include <gdcmULWritingCallback.h>
```

Inheritance diagram for gdcm::network::ULWritingCallback:



Collaboration diagram for gdcm::network::ULWritingCallback:



Public Member Functions

- `ULWritingCallback()` = default
- `~ULWritingCallback()` override = default
- void `HandleDataSet` (const `DataSet` &inDataSet) override
- void `HandleResponse` (const `DataSet` &inDataSet) override
- void `SetDirectory` (const std::string &inDirectoryName)
provide the directory into which all files are written.

Public Member Functions inherited from [gdcm::network::ULConnectionCallback](#)

- [ULConnectionCallback](#) ()
- virtual [~ULConnectionCallback](#) ()=default
- bool [DataSetHandles](#) () const
- void [ResetHandledDataSet](#) ()
- void [SetImplicitFlag](#) (const bool imp)

Additional Inherited Members

Protected Member Functions inherited from [gdcm::network::ULConnectionCallback](#)

- void [DataSetHandled](#) ()

Protected Attributes inherited from [gdcm::network::ULConnectionCallback](#)

- bool [mImplicit](#)

10.358.1 Constructor & Destructor Documentation

10.358.1.1 [ULWritingCallback](#)()

```
gdcm::network::ULWritingCallback::ULWritingCallback () [default]
```

10.358.1.2 [~ULWritingCallback](#)()

```
gdcm::network::ULWritingCallback::~~ULWritingCallback () [override], [default]
```

10.358.2 Member Function Documentation

10.358.2.1 [HandleDataSet](#)()

```
void gdcm::network::ULWritingCallback::HandleDataSet (
    const DataSet & inDataSet) [override], [virtual]
```

Implements [gdcm::network::ULConnectionCallback](#).

10.358.2.2 [HandleResponse](#)()

```
void gdcm::network::ULWritingCallback::HandleResponse (
    const DataSet & inDataSet) [override], [virtual]
```

Implements [gdcm::network::ULConnectionCallback](#).

10.358.2.3 SetDirectory()

```
void gdcm::network::ULWritingCallback::SetDirectory (
    const std::string & inDirectoryName) [inline]
```

provide the directory into which all files are written.

The documentation for this class was generated from the following file:


- [gdcmULWritingCallback.h](#)

10.359 gdcm::UNExplicitDataElement Class Reference


Class to read/write a [DataElement](#) as UNExplicit Data [Element](#).

```
#include <gdcmUNExplicitDataElement.h>
```

Inheritance diagram for gdcm::UNExplicitDataElement:



Collaboration diagram for `gdcmm::UNExplicitDataElement`:



Public Member Functions

- [VL GetLength](#) () const
- template<typename TSwap>
std::istream & [Read](#) (std::istream &is)
- template<typename TSwap>
std::istream & [ReadPreValue](#) (std::istream &is)
- template<typename TSwap>
std::istream & [ReadValue](#) (std::istream &is, bool readvalues=true)
- template<typename TSwap>
std::istream & [ReadWithLength](#) (std::istream &is, [VL](#) &length)

Public Member Functions inherited from [gdcmm::DataElement](#)

- [DataElement](#) (const [DataElement](#) &_val)
- [DataElement](#) (const [Tag](#) &t=[Tag](#)(0), const [VL](#) &vl=0, const [VR](#) &vr=[VR::INVALID](#))
- void [Clear](#) ()
Clear Data [Element](#) (make [Value](#) empty and invalidate [Tag](#) & [VR](#))
- void [Empty](#) ()
Make Data [Element](#) empty (no [Value](#))
- const [ByteValue](#) * [GetByteValue](#) () const
- template<typename TDE>
[VL GetLength](#) () const
- [SequenceOfFragments](#) * [GetSequenceOfFragments](#) ()
- const [SequenceOfFragments](#) * [GetSequenceOfFragments](#) () const

- [Tag](#) & [GetTag](#) ()
- const [Tag](#) & [GetTag](#) () const
Get Tag.
- [Value](#) & [GetValue](#) ()
- [Value](#) const & [GetValue](#) () const
Set/Get Value (bytes array, SQ of items, SQ of fragments):
- [SmartPointer](#)< [SequenceOfItems](#) > [GetValueAsSQ](#) () const
- [VL](#) & [GetVL](#) ()
- const [VL](#) & [GetVL](#) () const
Get VL.
- [VR](#) const & [GetVR](#) () const
- bool [IsEmpty](#) () const
Check if Data Element is empty.
- bool [IsUndefinedLength](#) () const
return if Value Length if of undefined length
- bool [operator](#)< (const [DataElement](#) &de) const
- [DataElement](#) & [operator](#)= (const [DataElement](#) &)=default
- bool [operator](#)== (const [DataElement](#) &de) const
- template<typename TDE, typename TSwap>
std::istream & [Read](#) (std::istream &is)
- template<typename TDE, typename TSwap>
std::istream & [ReadOrSkip](#) (std::istream &is, std::set< [Tag](#) > const &skiptags)
- template<typename TDE, typename TSwap>
std::istream & [ReadPreValue](#) (std::istream &is, std::set< [Tag](#) > const &skiptags)
- template<typename TDE, typename TSwap>
std::istream & [ReadValue](#) (std::istream &is, std::set< [Tag](#) > const &skiptags)
- template<typename TDE, typename TSwap>
std::istream & [ReadValueWithLength](#) (std::istream &is, [VL](#) &length, std::set< [Tag](#) > const &skiptags)
- template<typename TDE, typename TSwap>
std::istream & [ReadWithLength](#) (std::istream &is, [VL](#) &length)
- void [SetByteValue](#) (const char *array, [VL](#) length)
- void [SetTag](#) (const [Tag](#) &t)
- void [SetValue](#) ([Value](#) const &vl)
- void [SetVL](#) (const [VL](#) &vl)
- void [SetVLToUndefined](#) ()
- void [SetVR](#) ([VR](#) const &vr)
- template<typename TDE, typename TSwap>
const std::ostream & [Write](#) (std::ostream &os) const

Additional Inherited Members

Protected Types inherited from [gdcm::DataElement](#)

- typedef [SmartPointer](#)< [Value](#) > [ValuePtr](#)

Protected Member Functions inherited from [gdcm::DataElement](#)

- void [SetValueFieldLength](#) ([VL](#) vl, bool readvalues)

Protected Attributes inherited from [gdcm::DataElement](#)

- [Tag](#) [TagField](#)
- [ValuePtr](#) [ValueField](#)
- [VL](#) [ValueLengthField](#)
- [VR](#) [VRField](#)

10.359.1 Detailed Description

Class to read/write a [DataElement](#) as UNExplicit Data [Element](#).

Note

bla

10.359.2 Member Function Documentation

10.359.2.1 GetLength()

```
VL gdcm::UNExplicitDataElement::GetLength () const
```

10.359.2.2 Read()

```
template<typename TSwap>
std::istream & gdcm::UNExplicitDataElement::Read (
    std::istream & is)
```

10.359.2.3 ReadPreValue()

```
template<typename TSwap>
std::istream & gdcm::UNExplicitDataElement::ReadPreValue (
    std::istream & is)
```

10.359.2.4 ReadValue()

```
template<typename TSwap>
std::istream & gdcm::UNExplicitDataElement::ReadValue (
    std::istream & is,
    bool readvalues = true)
```


10.359.2.5 ReadWithLength()

```
template<typename TSwap>
std::istream & gdcm::UNExplicitDataElement::ReadWithLength (
    std::istream & is,
    VL & length)
```

The documentation for this class was generated from the following file:


- [gdcmUNExplicitDataElement.h](#)

10.360 gdcm::UNExplicitImplicitDataElement Class Reference


Class to read/write a [DataElement](#) as ExplicitImplicit Data [Element](#).

```
#include <gdcmUNExplicitImplicitDataElement.h>
```

Inheritance diagram for gdcm::UNExplicitImplicitDataElement:



Collaboration diagram for `gdcm::UNExplicitImplicitDataElement`:



Public Member Functions

- [VL GetLength](#) () const
- template<typename TSwap>
std::istream & [Read](#) (std::istream &is)
- template<typename TSwap>
std::istream & [ReadPreValue](#) (std::istream &is)
- template<typename TSwap>
std::istream & [ReadValue](#) (std::istream &is)

Public Member Functions inherited from [gdcm::DataElement](#)

- [DataElement](#) (const [DataElement](#) &_val)
- [DataElement](#) (const [Tag](#) &t=[Tag](#)(0), const [VL](#) &vl=0, const [VR](#) &vr=[VR::INVALID](#))
- void [Clear](#) ()
Clear Data [Element](#) (make [Value](#) empty and invalidate [Tag](#) & [VR](#))
- void [Empty](#) ()
Make Data [Element](#) empty (no [Value](#))
- const [ByteValue](#) * [GetByteValue](#) () const
- template<typename TDE>
[VL GetLength](#) () const
- [SequenceOfFragments](#) * [GetSequenceOfFragments](#) ()
- const [SequenceOfFragments](#) * [GetSequenceOfFragments](#) () const
- [Tag](#) & [GetTag](#) ()
- const [Tag](#) & [GetTag](#) () const

- *Get Tag.*
- [Value](#) & [GetValue](#) ()
- [Value](#) const & [GetValue](#) () const
- *Set/Get Value (bytes array, SQ of items, SQ of fragments):*
- [SmartPointer](#)< [SequenceOfItems](#) > [GetValueAsSQ](#) () const
- [VL](#) & [GetVL](#) ()
- const [VL](#) & [GetVL](#) () const
- *Get VL.*
- [VR](#) const & [GetVR](#) () const
- bool [IsEmpty](#) () const
- *Check if Data Element is empty.*
- bool [IsUndefinedLength](#) () const
- *return if Value Length if of undefined length*
- bool [operator](#)< (const [DataElement](#) &de) const
- [DataElement](#) & [operator](#)= (const [DataElement](#) &)=default
- bool [operator](#)== (const [DataElement](#) &de) const
- template<typename TDE, typename TSwap>
std::istream & [Read](#) (std::istream &is)
- template<typename TDE, typename TSwap>
std::istream & [ReadOrSkip](#) (std::istream &is, std::set< [Tag](#) > const &skiptags)
- template<typename TDE, typename TSwap>
std::istream & [ReadPreValue](#) (std::istream &is, std::set< [Tag](#) > const &skiptags)
- template<typename TDE, typename TSwap>
std::istream & [ReadValue](#) (std::istream &is, std::set< [Tag](#) > const &skiptags)
- template<typename TDE, typename TSwap>
std::istream & [ReadValueWithLength](#) (std::istream &is, [VL](#) &length, std::set< [Tag](#) > const &skiptags)
- template<typename TDE, typename TSwap>
std::istream & [ReadWithLength](#) (std::istream &is, [VL](#) &length)
- void [SetByteValue](#) (const char *array, [VL](#) length)
- void [SetTag](#) (const [Tag](#) &t)
- void [SetValue](#) ([Value](#) const &vl)
- void [SetVL](#) (const [VL](#) &vl)
- void [SetVLToUndefined](#) ()
- void [SetVR](#) ([VR](#) const &vr)
- template<typename TDE, typename TSwap>
const std::ostream & [Write](#) (std::ostream &os) const

Additional Inherited Members

Protected Types inherited from [gdcm::DataElement](#)

- typedef [SmartPointer](#)< [Value](#) > [ValuePtr](#)

Protected Member Functions inherited from [gdcm::DataElement](#)

- void [SetValueFieldLength](#) ([VL](#) vl, bool readvalues)

Protected Attributes inherited from [gdcm::DataElement](#)

- [Tag TagField](#)
- [ValuePtr ValueField](#)
- [VL ValueLengthField](#)
- [VR VRField](#)

10.360.1 Detailed Description

Class to read/write a [DataElement](#) as ExplicitImplicit Data [Element](#).

This class gather two known bugs:

1. GDCM 1.2.0 would rewrite [VR=UN Value](#) Length on 2 bytes instead of 4 bytes
2. GDCM 1.2.0 would also rewrite [DataElement](#) as Implicit when the [VR](#) would not be known this would only happen in some very rare cases. gdcm 2.X design could handle bug #1 or #2 exclusively, this class can now handle file which have both issues. See: [gdcmData/TheralysGDCM120Bug.dcm](#)

10.360.2 Member Function Documentation

10.360.2.1 GetLength()

```
VL gdcm::UNExplicitImplicitDataElement::GetLength () const
```

10.360.2.2 Read()

```
template<typename TSwap>
std::istream & gdcm::UNExplicitImplicitDataElement::Read (
    std::istream & is)
```

10.360.2.3 ReadPreValue()

```
template<typename TSwap>
std::istream & gdcm::UNExplicitImplicitDataElement::ReadPreValue (
    std::istream & is)
```

10.360.2.4 ReadValue()

```
template<typename TSwap>
std::istream & gdcm::UNExplicitImplicitDataElement::ReadValue (
    std::istream & is)
```

The documentation for this class was generated from the following file:

- [gdcmUNExplicitImplicitDataElement.h](#)

10.361 gdcm::Unpacker12Bits Class Reference

Pack/Unpack 12 bits pixel into 16bits.

```
#include <gdcmUnpacker12Bits.h>
```

Static Public Member Functions

- static bool [Pack](#) (char *out, const char *in, size_t n)
- static bool [Unpack](#) (char *out, const char *in, size_t n)

10.361.1 Detailed Description

Pack/Unpack 12 bits pixel into 16bits.

- You can only pack an even number of 16bits, which means a multiple of 4 (expressed in bytes)
- You can only unpack a multiple of 3 bytes

This class has no purpose in general purpose DICOM implementation. However to be able to cope with some early ACR-NEMA file generated by a well-known private vendor, one would need to unpack 12bits Stored Pixel [Value](#) into a more standard 16bits Stored Pixel [Value](#).

See also

[Rescaler](#)

10.361.2 Member Function Documentation

10.361.2.1 Pack()

```
bool gdcm::Unpacker12Bits::Pack (  
    char * out,  
    const char * in,  
    size_t n) [static]
```

Pack an array of 16bits where all values are 12bits into a pack form. n is the length in bytes of array in, out will be a fake 8bits array of size $(n / 2) * 3$

10.361.2.2 Unpack()

```
bool gdcmm::Unpacker12Bits::Unpack (
    char * out,
    const char * in,
    size_t n) [static]
```

Unpack an array of 'packed' 12bits data into a more conventional 16bits array. n is the length in bytes of array in, out will be a 16bits array of size $(n / 3) * 2$

The documentation for this class was generated from the following file:

- [gdcmmUnpacker12Bits.h](#)

10.362 gdcmm::Usage Class Reference

[Usage.](#)

```
#include <gdcmmUsage.h>
```

Public Types

- enum [UsageType](#) {
 [Mandatory](#) ,
 [Conditional](#) ,
 [UserOption](#) ,
 [Invalid](#) }

Public Member Functions

- [Usage](#) ([UsageType](#) type=[Invalid](#))
- [operator UsageType](#) () const

Static Public Member Functions

- static const char * [GetUsageString](#) ([UsageType](#) type)
- static [UsageType](#) [GetUsageType](#) (const char *type)

Friends

- std::ostream & [operator<<](#) (std::ostream &os, const [Usage](#) &vr)

10.362.1 Detailed Description

Usage.

Note

A.1.3 IOD Module Table and Functional Group Macro Table This Section of each IOD defines in a tabular form the Modules comprising the IOD. The following information must be specified for each Module in the table:

- The name of the Module or Functional Group
 - A reference to the Section in Annex C which defines the Module or Functional Group
 - The usage of the Module or Functional Group; whether it is:
 - Mandatory (see A.1.3.1) , abbreviated M
 - Conditional (see A.1.3.2) , abbreviated C
 - User Option (see A.1.3.3) , abbreviated U
- The Modules referenced are defined in Annex C. A.1.3.1 MANDATORY MODULES For each IOD, Mandatory Modules shall be supported per the definitions, semantics and requirements defined in Annex C.

A.1.3.2 CONDITIONAL MODULES Conditional Modules are Mandatory Modules if specific conditions are met. If the specified conditions are not met, this Module shall not be supported; that is, no information defined in that Module shall be sent. A.1.3.3 USER OPTION MODULES User Option Modules may or may not be supported. If an optional Module is supported, the Attribute Types specified in the Modules in Annex C shall be supported.

10.362.2 Member Enumeration Documentation

10.362.2.1 UsageType

```
enum gdcm::Usage::UsageType
```

Enumerator

Mandatory	
Conditional	
UserOption	
Invalid	

10.362.3 Constructor & Destructor Documentation

10.362.3.1 Usage()

```
gdcm::Usage::Usage (
    UsageType type = Invalid) [inline]
```

References [Invalid](#).

Referenced by [operator<<](#).

10.362.4 Member Function Documentation

10.362.4.1 GetUsageString()

```
const char * gdcm::Usage::GetUsageString (  
    UsageType type) [static]
```

Referenced by [operator<<](#).

10.362.4.2 GetUsageType()

```
UsageType gdcm::Usage::GetUsageType (  
    const char * type) [static]
```

10.362.4.3 operator UsageType()

```
gdcm::Usage::operator UsageType () const [inline]
```

10.362.5 Friends And Related Symbol Documentation

10.362.5.1 operator<<

```
std::ostream & operator<< (  
    std::ostream & os,  
    const Usage & vr) [friend]
```

References [Usage\(\)](#), and [GetUsageString\(\)](#).


The documentation for this class was generated from the following file:

- [gdcmUsage.h](#)


10.363 gdcm::UserEvent Class Reference

```
#include <gdcmEvent.h>
```

Inheritance diagram for gdcm::UserEvent:



Collaboration diagram for gdcm::UserEvent:



Additional Inherited Members

Public Member Functions inherited from [gdcm::Event](#)

- [Event](#) ()

- [Event](#) (const [Event](#) &)
- virtual [~Event](#) ()
- virtual bool [CheckEvent](#) (const [Event](#) *) const =0
- virtual const char * [GetEventName](#) () const =0
- virtual [Event](#) * [MakeObject](#) () const =0
- void [operator=](#) (const [Event](#) &)=delete
- virtual void [Print](#) (std::ostream &os) const

The documentation for this class was generated from the following file:

- [gdcmEvent.h](#)

10.364 gdcm::network::UserInformation Class Reference

[UserInformation](#).

```
#include <gdcmUserInformation.h>
```

Public Member Functions

- [UserInformation](#) ()
- [UserInformation](#) (const [UserInformation](#) &)=delete
- [~UserInformation](#) ()
- void [AddRoleSelectionSub](#) ([RoleSelectionSub](#) const &r)
- void [AddSOPClassExtendedNegociationSub](#) ([SOPClassExtendedNegociationSub](#) const &s)
- [MaximumLengthSub](#) & [GetMaximumLengthSub](#) ()
- const [MaximumLengthSub](#) & [GetMaximumLengthSub](#) () const
- [UserInformation](#) & [operator=](#) (const [UserInformation](#) &)
- void [Print](#) (std::ostream &os) const
- std::istream & [Read](#) (std::istream &is)
- size_t [Size](#) () const
- const std::ostream & [Write](#) (std::ostream &os) const

10.364.1 Detailed Description

[UserInformation](#).

[Table 9-16](#) USER INFORMATION ITEM FIELDS

TODO what is the goal of :

[Table 9-20](#) USER INFORMATION ITEM FIELDS

10.364.2 Constructor & Destructor Documentation

10.364.2.1 UserInfo() [1/2]

```
gdcm::network::UserInfo::UserInfo ()
```

Referenced by [UserInfo\(\)](#), and [operator=\(\)](#).

10.364.2.2 ~UserInfo()

```
gdcm::network::UserInfo::~UserInfo ()
```

10.364.2.3 UserInfo() [2/2]

```
gdcm::network::UserInfo::UserInfo (  
    const UserInfo & ) [delete]
```

References [UserInfo\(\)](#).

10.364.3 Member Function Documentation

10.364.3.1 AddRoleSelectionSub()

```
void gdcm::network::UserInfo::AddRoleSelectionSub (  
    RoleSelectionSub const & r)
```

10.364.3.2 AddSOPClassExtendedNegociationSub()

```
void gdcm::network::UserInfo::AddSOPClassExtendedNegociationSub (  
    SOPClassExtendedNegociationSub const & s)
```

10.364.3.3 GetMaximumLengthSub() [1/2]

```
MaximumLengthSub & gdcm::network::UserInfo::GetMaximumLengthSub () [inline]
```

10.364.3.4 GetMaximumLengthSub() [2/2]

```
const MaximumLengthSub & gdcm::network::UserInfo::GetMaximumLengthSub () const [inline]
```

10.364.3.5 operator=()

```
UserInformation & gdcmm::network::UserInformation::operator= (
    const UserInformation & )
```

References [UserInformation\(\)](#).

10.364.3.6 Print()

```
void gdcmm::network::UserInformation::Print (
    std::ostream & os) const
```

10.364.3.7 Read()

```
std::istream & gdcmm::network::UserInformation::Read (
    std::istream & is)
```

10.364.3.8 Size()

```
size_t gdcmm::network::UserInformation::Size () const
```

10.364.3.9 Write()

```
const std::ostream & gdcmm::network::UserInformation::Write (
    std::ostream & os) const
```

The documentation for this class was generated from the following file:

- [gdcmmUserInformation.h](#)

10.365 gdcmm::UUIDGenerator Class Reference

Class for generating unique UUID.

```
#include <gdcmmUUIDGenerator.h>
```

Public Member Functions

- const char * [Generate](#) ()

Static Public Member Functions

- static bool [IsValid](#) (const char *uid)
Find out if the string is a valid UUID or not.

10.365.1 Detailed Description

Class for generating unique UUID.

generate DCE 1.1 uid

10.365.2 Member Function Documentation

10.365.2.1 Generate()

```
const char * gdcm::UUIDGenerator::Generate ()
```

Return the generated uuid NOT THREAD SAFE

10.365.2.2 IsValid()

```
bool gdcm::UUIDGenerator::IsValid (  
    const char * uid) [static]
```

Find out if the string is a valid UUID or not.

The documentation for this class was generated from the following file:


- [gdcmUUIDGenerator.h](#)

10.366 gdcm::Validate Class Reference

[Validate](#) class.

```
#include <gdcmValidate.h>
```

Collaboration diagram for `gdcM::Validate`:



Public Member Functions

- [Validate](#) ()
- [~Validate](#) ()
- const [File](#) & [GetValidatedFile](#) ()
- void [SetFile](#) ([File](#) const &f)
- void [Validation](#) ()

Protected Attributes

- const [File](#) * [F](#)
- [File](#) [V](#)

10.366.1 Detailed Description

[Validate](#) class.

10.366.2 Constructor & Destructor Documentation

10.366.2.1 Validate()

```
gdcM::Validate::Validate ()
```

10.366.2.2 ~Validate()

```
gdcm::Validate::~~Validate ()
```

10.366.3 Member Function Documentation

10.366.3.1 GetValidatedFile()

```
const File & gdcm::Validate::GetValidatedFile () [inline]
```

References [V](#).

10.366.3.2 SetFile()

```
void gdcm::Validate::SetFile (  
    File const & f) [inline]
```

References [F](#).

10.366.3.3 Validation()

```
void gdcm::Validate::Validation ()
```

10.366.4 Member Data Documentation

10.366.4.1 F

```
const File* gdcm::Validate::F [protected]
```

Referenced by [SetFile\(\)](#).

10.366.4.2 V

```
File gdcm::Validate::V [protected]
```

Referenced by [GetValidatedFile\(\)](#).

The documentation for this class was generated from the following file:


- [gdcmValidate.h](#)

10.367 gdcM::Value Class Reference


Class to represent the value of a Data [Element](#).

```
#include <gdcMValue.h>
```

Inheritance diagram for gdcM::Value:



Collaboration diagram for gdcM::Value:



Public Member Functions

- `Value()`=default
- `~Value()` override=default
- virtual void `Clear()`=0
- virtual `VL GetLength()` const =0
- virtual bool `operator==` (const `Value` &val) const =0
- virtual void `SetLength` (`VL l`)=0

Public Member Functions inherited from [gdcm::Object](#)

- [Object](#) ()
- [Object](#) (const [Object](#) &)
Special requirement for copy/cstor, assignment operator.
- virtual [~Object](#) ()
- void [operator=](#) (const [Object](#) &)
- virtual void [Print](#) (std::ostream &) const

Protected Member Functions

- virtual void [SetLengthOnly](#) (VL l)

Protected Member Functions inherited from [gdcm::Object](#)

- void [Register](#) ()
- void [UnRegister](#) ()

Friends

- class [DataElement](#)

10.367.1 Detailed Description

Class to represent the value of a Data [Element](#).

Note

VALUE: A component of a [Value](#) Field. A [Value](#) Field may consist of one or more of these components.

10.367.2 Constructor & Destructor Documentation

10.367.2.1 Value()

```
gdcm::Value::Value () [default]
```

Referenced by [gdcm::ByteValue::operator==\(\)](#), [gdcm::SequenceOfFragments::operator==\(\)](#), [gdcm::SequenceOfItems::operator==\(\)](#), and [operator==\(\)](#).

10.367.2.2 ~Value()

```
gdcm::Value::~~Value () [override], [default]
```

10.367.3 Member Function Documentation

10.367.3.1 Clear()

```
virtual void gdcm::Value::Clear () [pure virtual]
```

Implemented in [gdcm::ByteValue](#), [gdcm::SequenceOfFragments](#), and [gdcm::SequenceOfItems](#).

10.367.3.2 GetLength()

```
virtual VL gdcm::Value::GetLength () const [pure virtual]
```

Implemented in [gdcm::ByteValue](#), [gdcm::SequenceOfFragments](#), and [gdcm::SequenceOfItems](#).

Referenced by [gdcm::DataSet::InsertDataElement\(\)](#), and [gdcm::DataElement::SetValue\(\)](#).

10.367.3.3 operator==(

```
virtual bool gdcm::Value::operator== (  
    const Value & val) const [pure virtual]
```

Implemented in [gdcm::ByteValue](#), [gdcm::SequenceOfFragments](#), and [gdcm::SequenceOfItems](#).

References [Value\(\)](#).

10.367.3.4 SetLength()

```
virtual void gdcm::Value::SetLength (  
    VL l) [pure virtual]
```

Implemented in [gdcm::ByteValue](#), [gdcm::SequenceOfFragments](#), and [gdcm::SequenceOfItems](#).

10.367.3.5 SetLengthOnly()

```
virtual void gdcm::Value::SetLengthOnly (  
    VL l) [protected], [virtual]
```

Reimplemented in [gdcm::ByteValue](#).

10.367.4 Friends And Related Symbol Documentation

10.367.4.1 DataElement

friend class [DataElement](#) [friend]

References [DataElement](#).

Referenced by [DataElement](#).

The documentation for this class was generated from the following file:

- [gdcmValue.h](#)

10.368 gdcm::ValueIO< TDE, TSwap, TType > Class Template Reference

Class to dispatch template calls.

```
#include <gdcmValueIO.h>
```

Static Public Member Functions

- static std::istream & [Read](#) (std::istream &is, [Value](#) &v, bool readvalues)
- static const std::ostream & [Write](#) (std::ostream &os, const [Value](#) &v)

10.368.1 Detailed Description

```
template<typename TDE, typename TSwap, typename TType = uint8_t>  
class gdcm::ValueIO< TDE, TSwap, TType >
```

Class to dispatch template calls.

10.368.2 Member Function Documentation

10.368.2.1 Read()

```
template<typename TDE, typename TSwap, typename TType = uint8_t>  
std::istream & gdcm::ValueIO< TDE, TSwap, TType >::Read (  
    std::istream & is,  
    Value & v,  
    bool readvalues) [static]
```

10.368.2.2 Write()

```
template<typename TDE, typename TSwap, typename TType = uint8_t>
const std::ostream & gdcM::ValueIO< TDE, TSwap, TType >::Write (
    std::ostream & os,
    const Value & v) [static]
```

The documentation for this class was generated from the following file:

- [gdcMValueIO.h](#)

10.369 gdcM::MrProtocol::Vector3 Struct Reference

```
#include <gdcMMrProtocol.h>
```

Public Attributes

- double [dCor](#)
- double [dSag](#)
- double [dTra](#)

10.369.1 Member Data Documentation

10.369.1.1 dCor

```
double gdcM::MrProtocol::Vector3::dCor
```

10.369.1.2 dSag

```
double gdcM::MrProtocol::Vector3::dSag
```

10.369.1.3 dTra

```
double gdcM::MrProtocol::Vector3::dTra
```

The documentation for this struct was generated from the following file:

- [gdcMMrProtocol.h](#)

10.370 gdcm::Version Class Reference

major/minor and build version

```
#include <gdcmVersion.h>
```

Public Member Functions

- [Version](#) ()=default
- [~Version](#) ()=default
- void [Print](#) (std::ostream &os=std::cout) const

Static Public Member Functions

- static int [GetBuildVersion](#) ()
- static int [GetMajorVersion](#) ()
- static int [GetMinorVersion](#) ()
- static const char * [GetVersion](#) ()

Friends

- std::ostream & [operator<<](#) (std::ostream &_os, const [Version](#) &v)

10.370.1 Detailed Description

major/minor and build version

10.370.2 Constructor & Destructor Documentation

10.370.2.1 Version()

```
gdcm::Version::Version () [default]
```

Referenced by [operator<<](#).

10.370.2.2 ~Version()

```
gdcm::Version::~~Version () [default]
```

10.370.3 Member Function Documentation

10.370.3.1 GetBuildVersion()

```
int gdcm::Version::GetBuildVersion () [static]
```

10.370.3.2 GetMajorVersion()

```
int gdcm::Version::GetMajorVersion () [static]
```

10.370.3.3 GetMinorVersion()

```
int gdcm::Version::GetMinorVersion () [static]
```

10.370.3.4 GetVersion()

```
const char * gdcm::Version::GetVersion () [static]
```

10.370.3.5 Print()

```
void gdcm::Version::Print (  
    std::ostream & os = std::cout) const
```

Referenced by [operator<<](#).

10.370.4 Friends And Related Symbol Documentation

10.370.4.1 operator<<

```
std::ostream & operator<< (  
    std::ostream & _os,  
    const Version & v) [friend]
```

References [Version\(\)](#), and [Print\(\)](#).

The documentation for this class was generated from the following file:

- [gdcmVersion.h](#)

10.371 gdcm::VL Class Reference

Value Length.

```
#include <gdcmVL.h>
```

Public Types

- typedef uint32_t [Type](#)

Public Member Functions

- [VL](#) (uint32_t vl=0)
- [VL GetLength](#) () const
- bool [IsOdd](#) () const
Return whether or not the [VL](#) is odd or not.
- bool [IsUndefined](#) () const
- [operator uint32_t](#) () const
- [VL & operator++](#) ()
- [VL operator++](#) (int)
- [VL & operator+=](#) ([VL](#) const &vl)
+= operator
- template<typename TSwap>
std::istream & [Read](#) (std::istream &is)
- template<typename TSwap>
std::istream & [Read16](#) (std::istream &is)
- void [SetToUndefined](#) ()
- template<typename TSwap>
const std::ostream & [Write](#) (std::ostream &os) const
- template<typename TSwap>
const std::ostream & [Write16](#) (std::ostream &os) const

Static Public Member Functions

- static uint16_t [GetVL16Max](#) ()
- static uint32_t [GetVL32Max](#) ()

Friends

- std::ostream & [operator<<](#) (std::ostream &os, const [VL](#) &vl)

10.371.1 Detailed Description

[Value](#) Length.

Warning

this is a 4bytes value ! Do not try to use it for 2bytes value length

Examples

[BasicImageAnonymizer.cs](#), [DecompressImage.cs](#), [ReadAndDumpDICOMDIR2.cxx](#), and [rle2img.cxx](#).

10.371.2 Member Typedef Documentation

10.371.2.1 Type

```
typedef uint32_t gdcm::VL::Type
```

10.371.3 Constructor & Destructor Documentation

10.371.3.1 VL()

```
gdcm::VL::VL (  
    uint32_t vl = 0) [inline]
```

Referenced by [GetLength\(\)](#), [operator++\(\)](#), [operator++\(\)](#), [operator+=\(\)](#), and [operator<<](#).

10.371.4 Member Function Documentation

10.371.4.1 GetLength()

```
VL gdcm::VL::GetLength () const [inline]
```

Examples

[ReadAndDumpDICOMDIR2.cxx](#).

References [VL\(\)](#).

Referenced by [gdcm::FileMetaInformation::GetFullLength\(\)](#), and [gdcm::Item::Write\(\)](#).

10.371.4.2 GetVL16Max()

```
uint16_t gdcm::VL::GetVL16Max () [inline], [static]
```

10.371.4.3 GetVL32Max()

```
uint32_t gdcm::VL::GetVL32Max () [inline], [static]
```

10.371.4.4 IsOdd()

```
bool gdcm::VL::IsOdd () const [inline]
```

Return whether or not the [VL](#) is odd or not.

References [IsUndefined\(\)](#).

Referenced by [Write\(\)](#), and [Write16\(\)](#).

10.371.4.5 IsUndefined()

```
bool gdcm::VL::IsUndefined () const [inline]
```

Referenced by [IsOdd\(\)](#).

10.371.4.6 operator uint32_t()

```
gdcm::VL::operator uint32_t () const [inline]
```

10.371.4.7 operator++() [1/2]

```
VL & gdcm::VL::operator++ () [inline]
```

References [VL\(\)](#).

10.371.4.8 operator++() [2/2]

```
VL gdcm::VL::operator++ (  
    int ) [inline]
```

References [VL\(\)](#).

10.371.4.9 operator+=()

```
VL & gdcmm::VL::operator+= (
    VL const & vl) [inline]
```

+= operator

References [VL\(\)](#).

10.371.4.10 Read()

```
template<typename TSwap>
std::istream & gdcmm::VL::Read (
    std::istream & is) [inline]
```

10.371.4.11 Read16()

```
template<typename TSwap>
std::istream & gdcmm::VL::Read16 (
    std::istream & is) [inline]
```

References [gdcmm_assert](#).

10.371.4.12 SetToUndefined()

```
void gdcmm::VL::SetToUndefined () [inline]
```

10.371.4.13 Write()

```
template<typename TSwap>
const std::ostream & gdcmm::VL::Write (
    std::ostream & os) const [inline]
```

References [IsOdd\(\)](#).

Referenced by [gdcmm::Fragment::Write\(\)](#), [gdcmm::Item::Write\(\)](#), [gdcmm::SequenceOfFragments::Write\(\)](#), and [gdcmm::SequenceOfItems::Write\(\)](#).

10.371.4.14 Write16()

```
template<typename TSwap>
const std::ostream & gdcmm::VL::Write16 (
    std::ostream & os) const [inline]
```

References [gdcmm_assert](#), and [IsOdd\(\)](#).

10.371.5 Friends And Related Symbol Documentation

10.371.5.1 operator<<

```
std::ostream & operator<< (
    std::ostream & os,
    const VL & vl) [friend]
```

References [VL\(\)](#).

The documentation for this class was generated from the following file:

- [gdcmVL.h](#)

10.372 gdcm::VM Class Reference

[Value](#) Multiplicity Looking at the DICOMV3 dict only there is very few cases: 1 2 3 4 5 6 8 16 24 1-2 1-3 1-8 1-32 1-99 1-n 2-2n 2-n 3-3n 3-n.

```
#include <gdcmVM.h>
```

Public Types

- enum [VMType](#) {
 - [VM0](#) = 0 ,
 - [VM1](#) = 1 ,
 - [VM2](#) = 2 ,
 - [VM3](#) = 4 ,
 - [VM4](#) = 8 ,
 - [VM5](#) = 16 ,
 - [VM6](#) = 32 ,
 - [VM8](#) = 64 ,
 - [VM9](#) = 128 ,
 - [VM10](#) = 256 ,
 - [VM12](#) = 512 ,
 - [VM16](#) = 1024 ,
 - [VM18](#) = 2048 ,
 - [VM24](#) = 4096 ,
 - [VM28](#) = 8192 ,
 - [VM32](#) = 16384 ,
 - [VM35](#) = 32768 ,
 - [VM99](#) = 65536 ,
 - [VM256](#) = 131072 ,
 - [VM1_2](#) = VM1 | VM2 ,
 - [VM1_3](#) = VM1 | VM2 | VM3 ,
 - [VM1_4](#) = VM1 | VM2 | VM3 | VM4 ,
 - [VM1_5](#) = VM1 | VM2 | VM3 | VM4 | VM5 ,
 - [VM1_8](#) = VM1 | VM2 | VM3 | VM4 | VM5 | VM6 | VM8 ,
 - [VM1_32](#) = VM1 | VM2 | VM3 | VM4 | VM5 | VM6 | VM8 | VM9 | VM16 | VM24 | VM32 ,

```

VM1_99 = VM1 | VM2 | VM3 | VM4 | VM5 | VM6 | VM8 | VM9 | VM16 | VM24 | VM32 | VM99 ,
VM1_n = VM1 | VM2 | VM3 | VM4 | VM5 | VM6 | VM8 | VM9 | VM16 | VM24 | VM32 | VM99 | VM256 ,
VM2_2n = VM2 | VM4 | VM6 | VM8 | VM16 | VM24 | VM32 | VM256 ,
VM2_n = VM2 | VM3 | VM4 | VM5 | VM6 | VM8 | VM9 | VM16 | VM24 | VM32 | VM99 | VM256 ,
VM3_4 = VM3 | VM4 ,
VM3_3n = VM3 | VM6 | VM9 | VM24 | VM99 | VM256 ,
VM3_n = VM3 | VM4 | VM5 | VM6 | VM8 | VM9 | VM16 | VM24 | VM32 | VM99 | VM256 ,
VM4_4n = VM4 | VM16 | VM24 | VM32 | VM256 ,
VM6_6n = VM6 | VM12 | VM18 | VM24 ,
VM6_n = VM6 | VM8 | VM9 | VM16 | VM24 | VM32 | VM99 | VM256 ,
VM7_7n ,
VM30_30n ,
VM47_47n ,
VM_END = VM1_n + 1 }

```

Public Member Functions

- [VM](#) ([VMType](#) type=[VM0](#))
- bool [Compatible](#) ([VM](#) const &vm) const
- unsigned int [GetLength](#) () const
- [operator VMType](#) () const

Static Public Member Functions

- static size_t [GetNumberOfElementsFromArray](#) (const char *array, size_t length)
- static const char * [GetVMString](#) ([VMType](#) vm)
- static [VMType](#) [GetVMType](#) (const char *vm)
- static [VMType](#) [GetVMTypeFromLength](#) (size_t length, unsigned int size)
- static bool [IsValid](#) (int vm1, [VMType](#) vm2)

Static Protected Member Functions

- static unsigned int [GetIndex](#) ([VMType](#) vm)

Friends

- std::ostream & [operator<<](#) (std::ostream &os, const [VM](#) &vm)

10.372.1 Detailed Description

[Value](#) Multiplicity Looking at the DICOMV3 dict only there is very few cases: 1 2 3 4 5 6 8 16 24 1-2 1-3 1-8 1-32 1-99 1-n 2-2n 2-n 3-3n 3-n.

Some private dict define some more: 4-4n 1-4 1-5 256 9 3-4

even more:

7-7n 10 18 12 35 47_47n 30_30n 28

6-6n

10.372.2 Member Enumeration Documentation

10.372.2.1 VMType

enum [gdcm::VM::VMType](#)

Enumerator

VM0	
VM1	
VM2	
VM3	
VM4	
VM5	
VM6	
VM8	
VM9	
VM10	
VM12	
VM16	
VM18	
VM24	
VM28	
VM32	
VM35	
VM99	
VM256	
VM1_2	
VM1_3	
VM1_4	
VM1_5	
VM1_8	
VM1_32	
VM1_99	
VM1_n	
VM2_2n	
VM2_n	
VM3_4	
VM3_3n	
VM3_n	
VM4_4n	
VM6_6n	
VM6_n	
VM7_7n	
VM30_30n	
VM47_47n	
VM_END	

10.372.3 Constructor & Destructor Documentation

10.372.3.1 VM()

```
gdcmm::VM::VM (
    VMType type = VM0) [inline]
```

References [VM0](#).

Referenced by [Compatible\(\)](#), [GetLength\(\)](#), and [operator<<](#).

10.372.4 Member Function Documentation

10.372.4.1 Compatible()

```
bool gdcm::VM::Compatible (
    VM const & vm) const
```

WARNING: Implementation deficiency The Compatible function is poorly implemented, the reference vm should be coming from the dictionary, while the passed in value is the value guess from the file.

References [VM\(\)](#).

10.372.4.2 GetIndex()

```
unsigned int gdcm::VM::GetIndex (
    VMType vm) [static], [protected]
```

10.372.4.3 GetLength()

```
unsigned int gdcm::VM::GetLength () const
```

References [VM\(\)](#), and [operator<<](#).

10.372.4.4 GetNumberOfElementsFromArray()

```
size_t gdcm::VM::GetNumberOfElementsFromArray (
    const char * array,
    size_t length) [static]
```

10.372.4.5 GetVMString()

```
const char * gdcm::VM::GetVMString (
    VMType vm) [static]
```

Return the string as written in the official DICOM dict from a custom enum type

Referenced by [operator<<](#).

10.372.4.6 GetVMType()

```
VMType gdcM::VM::GetVMType (
    const char * vm) [static]
```

10.372.4.7 GetVMTypeFromLength()

```
VMType gdcM::VM::GetVMTypeFromLength (
    size_t length,
    unsigned int size) [static]
```

10.372.4.8 IsValid()

```
bool gdcM::VM::IsValid (
    int vm1,
    VMType vm2) [static]
```

Check if vm1 is valid compare to vm2, i.e vm1 is element of vm2 vm1 is typically deduce from counting in a ValueField

10.372.4.9 operator VMType()

```
gdcM::VM::operator VMType () const [inline]
```

10.372.5 Friends And Related Symbol Documentation

10.372.5.1 operator<<

```
std::ostream & operator<< (
    std::ostream & os,
    const VM & vm) [friend]
```

References [VM\(\)](#), [gdcM_assert](#), and [GetVMString\(\)](#).

Referenced by [GetLength\(\)](#).

The documentation for this class was generated from the following file:

- [gdcMVM.h](#)

10.373 gdcM::VMToLength< T > Struct Template Reference

The documentation for this struct was generated from the following file:

- [gdcMVM.h](#)

10.374 gdcm::VR Class Reference

VR class.

```
#include <gdcmVR.h>
```

Public Types

- enum [VRType](#) : long long {
[INVALID](#) = 0 ,
[AE](#) = 1 ,
[AS](#) = 2 ,
[AT](#) = 4 ,
[CS](#) = 8 ,
[DA](#) = 16 ,
[DS](#) = 32 ,
[DT](#) = 64 ,
[FD](#) = 128 ,
[FL](#) = 256 ,
[IS](#) = 512 ,
[LO](#) = 1024 ,
[LT](#) = 2048 ,
[OB](#) = 4096 ,
[OD](#) = 134217728 ,
[OF](#) = 8192 ,
[OL](#) = 268435456 ,
[OV](#) = 2147483648 ,
[OW](#) = 16384 ,
[PN](#) = 32768 ,
[SH](#) = 65536 ,
[SL](#) = 131072 ,
[SQ](#) = 262144 ,
[SS](#) = 524288 ,
[ST](#) = 1048576 ,
[SV](#) = 4294967296 ,
[TM](#) = 2097152 ,
[UC](#) = 536870912 ,
[UI](#) = 4194304 ,
[UL](#) = 8388608 ,
[UN](#) = 16777216 ,
[UR](#) = 1073741824 ,
[US](#) = 33554432 ,
[UT](#) = 67108864 ,
[UV](#) = 8589934592 ,
[OB_OW](#) = OB | OW ,
[US_SS](#) = US | SS ,
[US_SS_OW](#) = US | SS | OW ,
[US_OW](#) = US | OW ,
[VL16](#) = AE | AS | AT | CS | DA | DS | DT | FD | FL | IS | LO | LT | PN | SH | SL | SS | ST | TM | UI | UL | US ,
[VL32](#) = OB | OW | OD | OF | OL | OV | SQ | SV | UC | UN | UR | UT | UV ,
[VRASCII](#) = AE | AS | CS | DA | DS | DT | IS | LO | LT | PN | SH | ST | TM | UC | UI | UR | UT ,
[VRBINARY](#) = AT | FL | FD | OB | OD | OF | OL | OV | OW | SL | SQ | SS | SV | UL | UN | US | UV ,
[VR_VM1](#) = AS | LT | ST | UT | SQ | OF | OL | OV | OD | OW | OB | UN ,
[VRALL](#) = VRASCII | VRBINARY ,
[VR_END](#) = UV+1 }

Public Member Functions

- [VR](#) (VRType vr=INVALID)
- bool [Compatible](#) (VR const &vr) const
- int [GetLength](#) () const
- unsigned int [GetSize](#) () const
- unsigned int [GetSizeof](#) () const
- bool [IsDual](#) () const
- bool [IsVRFile](#) () const
- [operator VRType](#) () const
- std::istream & [Read](#) (std::istream &is)
- const std::ostream & [Write](#) (std::ostream &os) const

Static Public Member Functions

- static bool [CanDisplay](#) (VRType vr)
- static uint32_t [GetLength](#) (VRType vr)
- static const char * [GetVRString](#) (VRType vr)
- static const char * [GetVRStringFromFile](#) (VRType vr)
- static VRType [GetVRType](#) (const char *vr)
- static VRType [GetVRTypeFromFile](#) (const char *vr)
- static bool [IsASCII](#) (VRType vr)
- static bool [IsASCII2](#) (VRType vr)
- static bool [IsBinary](#) (VRType vr)
- static bool [IsBinary2](#) (VRType vr)
- static bool [IsSwap](#) (const char *vr)
- static bool [IsValid](#) (const char *vr)
- static bool [IsValid](#) (const char *vr1, VRType vr2)

Friends

- std::ostream & [operator<<](#) (std::ostream &os, const [VR](#) &vr)

10.374.1 Detailed Description

[VR](#) class.

This is adapted from DICOM standard The biggest difference is the INVALID [VR](#) and the composite one that differ from standard (more like an addition) This allow us to represent all the possible case express in the DICOMV3 dict

Note

VALUE REPRESENTATION ([VR](#)) Specifies the data type and format of the Value(s) contained in the [Value](#) Field of a Data [Element](#). VALUE REPRESENTATION FIELD: The field where the [Value](#) Representation of a Data [Element](#) is stored in the encoding of a Data [Element](#) structure with explicit [VR](#).

Examples

[GenAllVR.cxx](#), [GenFakeIdentifyFile.cxx](#), and [SimplePrint.cs](#).

10.374.2 Member Enumeration Documentation**10.374.2.1 VRType**

```
enum gdcm::VR::VRType : long long
```

Enumerator

INVALID	
AE	
AS	
AT	
CS	
DA	
DS	
DT	
FD	
FL	
IS	
LO	
LT	
OB	
OD	
OF	
OL	
OV	
OW	
PN	
SH	
SL	
SQ	
SS	
ST	
SV	
TM	
UC	
UI	
UL	
UN	
UR	
US	
UT	
UV	
OB_OW	
US_SS	
US_SS_OW	
US_OW	
VL16	
VL32	
VRASCII	
VRBINARY	
VR_VM1	
VRALL	
VR_END	

Examples

[NewSequence.cs](#), and [SimplePrint.cs](#).

10.374.3 Constructor & Destructor Documentation

10.374.3.1 VR()

```
gdcmm::VR::VR (
    VRType vr = INVALID) [inline]
```

References [INVALID](#).

Referenced by [Compatible\(\)](#), and [operator<<](#).

10.374.4 Member Function Documentation

10.374.4.1 CanDisplay()

```
bool gdcmm::VR::CanDisplay (
    VRType vr) [static]
```

10.374.4.2 Compatible()

```
bool gdcmm::VR::Compatible (
    VR const & vr) const
```

Examples

[SimplePrint.cs](#).

References [VR\(\)](#).

10.374.4.3 GetLength() [1/2]

```
int gdcmm::VR::GetLength () const [inline]
```

References [GetLength\(\)](#).

Referenced by [GetLength\(\)](#).

10.374.4.4 GetLength() [2/2]

```
uint32_t gdcm::VR::GetLength (
    VRType vr) [inline], [static]
```

References [VL32](#).

10.374.4.5 GetSize()

```
unsigned int gdcm::VR::GetSize () const [inline]
```

References [AE](#), [AS](#), [AT](#), [CS](#), [DA](#), [DS](#), [DT](#), [FD](#), [FL](#), [gdcm_assert](#), [INVALID](#), [IS](#), [LO](#), [LT](#), [OB](#), [OB_OW](#), [OD](#), [OF](#), [OL](#), [OV](#), [OW](#), [PN](#), [SH](#), [SL](#), [SQ](#), [SS](#), [ST](#), [SV](#), [TM](#), [UC](#), [UI](#), [UL](#), [UN](#), [UR](#), [US](#), [US_OW](#), [US_SS](#), [US_SS_OW](#), [UT](#), [UV](#), [VL16](#), [VL32](#), [VR_END](#), [VR_VM1](#), [VRALL](#), [VRASCII](#), [VRBINARY](#), and [VRTypeTemplateCase](#).

10.374.4.6 GetSizeof()

```
unsigned int gdcm::VR::GetSizeof () const
```

10.374.4.7 GetVRString()

```
const char * gdcm::VR::GetVRString (
    VRType vr) [static]
```

Referenced by [operator<<](#), and [Write\(\)](#).

10.374.4.8 GetVRStringFromFile()

```
const char * gdcm::VR::GetVRStringFromFile (
    VRType vr) [static]
```

10.374.4.9 GetVRType()

```
VRType gdcm::VR::GetVRType (
    const char * vr) [static]
```

10.374.4.10 GetVRTypeFromFile()

```
VRType gdcm::VR::GetVRTypeFromFile (
    const char * vr) [static]
```

Referenced by [Read\(\)](#).

10.374.4.11 IsASCII()

```
bool gdcm::VR::IsASCII (
    VRType vr) [static]
```

10.374.4.12 IsASCII2()

```
bool gdcm::VR::IsASCII2 (
    VRType vr) [static]
```

10.374.4.13 IsBinary()

```
bool gdcm::VR::IsBinary (
    VRType vr) [static]
```

10.374.4.14 IsBinary2()

```
bool gdcm::VR::IsBinary2 (
    VRType vr) [static]
```

10.374.4.15 IsDual()

```
bool gdcm::VR::IsDual () const
```

Referenced by [Write\(\)](#).

10.374.4.16 IsSwap()

```
bool gdcm::VR::IsSwap (
    const char * vr) [static]
```

10.374.4.17 IsValid() [1/2]

```
bool gdcm::VR::IsValid (
    const char * vr) [static]
```

10.374.4.18 IsValid() [2/2]

```
bool gdcm::VR::IsValid (
    const char * vr1,
    VRType vr2) [static]
```

10.374.4.19 IsVRFile()

```
bool gdcm::VR::IsVRFile () const
```

Referenced by [gdcm::DataElement::SetVR\(\)](#).

10.374.4.20 operator VRType()

```
gdcm::VR::operator VRType () const [inline]
```

10.374.4.21 Read()

```
std::istream & gdcm::VR::Read (  
    std::istream & is) [inline]
```

References [gdcm_assert](#), [gdcmDebugMacro](#), [GetVRTypeFromFile\(\)](#), [INVALID](#), [VL32](#), and [VR_END](#).

10.374.4.22 Write()

```
const std::ostream & gdcm::VR::Write (  
    std::ostream & os) const [inline]
```

References [gdcm_assert](#), [gdcmAssertAlwaysMacro](#), [GetVRString\(\)](#), [INVALID](#), [IsDual\(\)](#), and [VL32](#).

10.374.5 Friends And Related Symbol Documentation

10.374.5.1 operator<<

```
std::ostream & operator<< (  
    std::ostream & os,  
    const VR & vr) [friend]
```

References [VR\(\)](#), and [GetVRString\(\)](#).

The documentation for this class was generated from the following file:


- [gdcmVR.h](#)

10.375 gdcm::VR16ExplicitDataElement Class Reference


Class to read/write a [DataElement](#) as Explicit Data [Element](#).

```
#include <gdcmVR16ExplicitDataElement.h>
```

Inheritance diagram for gdcm::VR16ExplicitDataElement:



Collaboration diagram for gdcm::VR16ExplicitDataElement:



Public Member Functions

- [VL GetLength](#) () const

- template<typename TSwap>
std::istream & [Read](#) (std::istream &is)
- template<typename TSwap>
std::istream & [ReadPreValue](#) (std::istream &is)
- template<typename TSwap>
std::istream & [ReadValue](#) (std::istream &is, bool readvalues=true)
- template<typename TSwap>
std::istream & [ReadWithLength](#) (std::istream &is, [VL](#) &length)

Public Member Functions inherited from [gdcm::DataElement](#)

- [DataElement](#) (const [DataElement](#) &_val)
- [DataElement](#) (const [Tag](#) &t=[Tag](#)(0), const [VL](#) &vl=0, const [VR](#) &vr=[VR::INVALID](#))
- void [Clear](#) ()
Clear Data [Element](#) (make [Value](#) empty and invalidate [Tag](#) & [VR](#))
- void [Empty](#) ()
Make Data [Element](#) empty (no [Value](#))
- const [ByteValue](#) * [GetByteValue](#) () const
- template<typename TDE>
[VL](#) [GetLength](#) () const
- [SequenceOfFragments](#) * [GetSequenceOfFragments](#) ()
- const [SequenceOfFragments](#) * [GetSequenceOfFragments](#) () const
- [Tag](#) & [GetTag](#) ()
- const [Tag](#) & [GetTag](#) () const
Get [Tag](#).
- [Value](#) & [GetValue](#) ()
- [Value](#) const & [GetValue](#) () const
Set/Get [Value](#) (bytes array, SQ of items, SQ of fragments):
- [SmartPointer](#)< [SequenceOfItems](#) > [GetValueAsSQ](#) () const
- [VL](#) & [GetVL](#) ()
- const [VL](#) & [GetVL](#) () const
Get [VL](#).
- [VR](#) const & [GetVR](#) () const
- bool [IsEmpty](#) () const
Check if Data [Element](#) is empty.
- bool [IsUndefinedLength](#) () const
return if [Value](#) Length if of undefined length
- bool [operator<](#) (const [DataElement](#) &de) const
- [DataElement](#) & [operator=](#) (const [DataElement](#) &)=default
- bool [operator==](#) (const [DataElement](#) &de) const
- template<typename TDE, typename TSwap>
std::istream & [Read](#) (std::istream &is)
- template<typename TDE, typename TSwap>
std::istream & [ReadOrSkip](#) (std::istream &is, std::set< [Tag](#) > const &skiptags)
- template<typename TDE, typename TSwap>
std::istream & [ReadPreValue](#) (std::istream &is, std::set< [Tag](#) > const &skiptags)
- template<typename TDE, typename TSwap>
std::istream & [ReadValue](#) (std::istream &is, std::set< [Tag](#) > const &skiptags)

- `template<typename TDE, typename TSwap>`
`std::istream & ReadValueWithLength (std::istream &is, VL &length, std::set< Tag > const &skiptags)`
- `template<typename TDE, typename TSwap>`
`std::istream & ReadWithLength (std::istream &is, VL &length)`
- `void SetByteValue (const char *array, VL length)`
- `void SetTag (const Tag &t)`
- `void SetValue (Value const &vl)`
- `void SetVL (const VL &vl)`
- `void SetVLToUndefined ()`
- `void SetVR (VR const &vr)`
- `template<typename TDE, typename TSwap>`
`const std::ostream & Write (std::ostream &os) const`

Additional Inherited Members

Protected Types inherited from `gdcm::DataElement`

- `typedef SmartPointer< Value > ValuePtr`

Protected Member Functions inherited from `gdcm::DataElement`

- `void SetValueFieldLength (VL vl, bool readvalues)`

Protected Attributes inherited from `gdcm::DataElement`

- `Tag TagField`
- `ValuePtr ValueField`
- `VL ValueLengthField`
- `VR VRField`

10.375.1 Detailed Description

Class to read/write a `DataElement` as Explicit Data `Element`.

Note

This class support 16 bits when finding an unknown `VR`: For instance: Siemens_CT_Sensation64_has_VR_RT.↔
 dcm

10.375.2 Member Function Documentation

10.375.2.1 GetLength()

`VL gdcm::VR16ExplicitDataElement::GetLength () const`

10.375.2.2 Read()

```
template<typename TSwap>
std::istream & gdcm::VR16ExplicitDataElement::Read (
    std::istream & is)
```

10.375.2.3 ReadPreValue()

```
template<typename TSwap>
std::istream & gdcm::VR16ExplicitDataElement::ReadPreValue (
    std::istream & is)
```

10.375.2.4 ReadValue()

```
template<typename TSwap>
std::istream & gdcm::VR16ExplicitDataElement::ReadValue (
    std::istream & is,
    bool readvalues = true)
```

10.375.2.5 ReadWithLength()

```
template<typename TSwap>
std::istream & gdcm::VR16ExplicitDataElement::ReadWithLength (
    std::istream & is,
    VL & length)
```

The documentation for this class was generated from the following file:

- [gdcmVR16ExplicitDataElement.h](#)


10.376 gdcm::VRToEncoding< T > Struct Template Reference

The documentation for this struct was generated from the following file:

- [gdcmVR.h](#)

10.377 `gdcm::VRToType< T >` Struct Template Reference

Inheritance diagram for `gdcm::VRToType< T >`:



10.377.1 Detailed Description

```
template<long long T>
struct gdcm::VRToType< T >
```

Examples


[DumpGEMSMovieGroup.cxx](#).

The documentation for this struct was generated from the following file:

- [gdcmVR.h](#)

10.378 `gdcm::VRVLSIZE< T >` Class Template Reference

Inheritance diagram for `gdcm::VRVLSIZE< T >`:




The documentation for this class was generated from the following file:

- [gdcmAttribute.h](#)


10.379 gdcm::VRVLSIZE< 0 > Class Reference

```
#include <gdcmAttribute.h>
```

Inheritance diagram for gdcm::VRVLSIZE< 0 >:



Collaboration diagram for gdcm::VRVLSIZE< 0 >:



Static Public Member Functions

- static uint16_t [Read](#) (std::istream &_is)
- static void [Write](#) (std::ostream &os)

10.379.1 Member Function Documentation

10.379.1.1 Read()

```
uint16_t gdcm::VRVLSIZE< 0 >::Read (
    std::istream &_is) [inline], [static]
```

10.379.1.2 Write()

```
void gdcm::VRVLSize< 0 >::Write (
    std::ostream & os) [inline], [static]
```

The documentation for this class was generated from the following file:

- [gdcmAttribute.h](#)

10.380 gdcm::VRVLSize< 1 > Class Reference

```
#include <gdcmAttribute.h>
```

Inheritance diagram for gdcm::VRVLSize< 1 >:



Collaboration diagram for gdcm::VRVLSize< 1 >:



Static Public Member Functions

- static uint32_t [Read](#) (std::istream &_is)
- static void [Write](#) (std::ostream &os)

10.380.1 Member Function Documentation

10.380.1.1 Read()

```
uint32_t gdcM::VRVLSize< 1 >::Read (  
    std::istream & _is) [inline], [static]
```

10.380.1.2 Write()

```
void gdcM::VRVLSize< 1 >::Write (  
    std::ostream & os) [inline], [static]
```


The documentation for this class was generated from the following file:

- [gdcMAttribute.h](#)


10.381 vtkGDCMImageReader Class Reference

```
#include <vtkGDCMImageReader.h>
```

Inheritance diagram for vtkGDCMImageReader:



Collaboration diagram for vtkGDCMImageReader:



Public Member Functions

- virtual int [CanReadFile](#) (const char *fname)
- virtual const char * [GetDescriptiveName](#) ()
- virtual const char * [GetFileExtensions](#) ()
- vtkImageData * [GetIconImage](#) ()
- vtkImageData * [GetOverlay](#) (int i)
- virtual void [PrintSelf](#) (ostream &os, vtkIndent indent)
- virtual void [SetCurve](#) (vtkPolyData *pd)
- virtual void [SetFileNames](#) (vtkStringArray *)
- virtual void [SetMedicalImageProperties](#) (vtkMedicalImageProperties *pd)
- [vtkBooleanMacro](#) ([ApplyLookupTable](#), int)
- int [vtkBooleanMacro](#) ([ApplyYBRToRGB](#), int)
- [vtkBooleanMacro](#) ([LoadIconImage](#), int)
- [vtkBooleanMacro](#) ([LoadOverlays](#), int)
- [vtkBooleanMacro](#) ([LossyFlag](#), int)
- [vtkGetMacro](#) ([ApplyLookupTable](#), int)
- [vtkGetMacro](#) ([ApplyYBRToRGB](#), int) [vtkSetMacro](#)([ApplyYBRToRGB](#)
- [vtkGetMacro](#) ([ImageFormat](#), int)
- [vtkGetMacro](#) ([LoadIconImage](#), int)
- [vtkGetMacro](#) ([LoadOverlays](#), int)
- [vtkGetMacro](#) ([LossyFlag](#), int)
- [vtkGetMacro](#) ([NumberOfIconImages](#), int)
- [vtkGetMacro](#) ([NumberOfOverlays](#), int)
- [vtkGetMacro](#) ([PlanarConfiguration](#), int)
- [vtkGetMacro](#) ([Scale](#), double)
- [vtkGetMacro](#) ([Shift](#), double)
- [vtkGetObjectMacro](#) ([Curve](#), vtkPolyData)
- [vtkGetObjectMacro](#) ([DirectionCosines](#), vtkMatrix4x4)
- [vtkGetObjectMacro](#) ([FileNames](#), vtkStringArray)
- [vtkGetObjectMacro](#) ([MedicalImageProperties](#), vtkMedicalImageProperties)
- [vtkGetVector3Macro](#) ([ImagePositionPatient](#), double)
- [vtkGetVector6Macro](#) ([ImageOrientationPatient](#), double)
- [vtkSetMacro](#) ([ApplyLookupTable](#), int)

- [vtkSetMacro](#) ([LoadIconImage](#), int)
- [vtkSetMacro](#) ([LoadOverlays](#), int)
- [vtkSetMacro](#) ([LossyFlag](#), int)
- [vtkTypeMacro](#) ([vtkGDCMImageReader](#), [vtkMedicalImageReader2](#))

Static Public Member Functions

- static [vtkGDCMImageReader](#) * [New](#) ()

Protected Member Functions

- [vtkGDCMImageReader](#) ()
- [~vtkGDCMImageReader](#) ()
- void [ExecuteData](#) ([vtkDataObject](#) *out)
- void [ExecuteInformation](#) ()
- void [FillMedicalImageInformation](#) (const [gdcm::ImageReader](#) &reader)
- int [LoadSingleFile](#) (const char *filename, char *pointer, unsigned long &outlen)
- int [RequestDataCompat](#) ()
- int [RequestInformationCompat](#) ()
- void [SetFilePattern](#) (const char *)
- void [SetFilePrefix](#) (const char *)
- [vtkGetStringMacro](#) (FilePattern)
- [vtkGetStringMacro](#) (FilePrefix)
- [vtkSetVector6Macro](#) ([ImageOrientationPatient](#), double)

Protected Attributes

- int [ApplyInverseVideo](#)
- int [ApplyLookupTable](#)
- int [ApplyPlanarConfiguration](#)
- int [ApplyShiftScale](#)
- int [ApplyYBRTToRGB](#)
- [vtkPolyData](#) * [Curve](#)
- [vtkMatrix4x4](#) * [DirectionCosines](#)
- [vtkStringArray](#) * [FileNames](#)
- int [ForceRescale](#)
- int [IconDataScalarType](#)
- int [IconImageDataExtent](#) [6]
- int [IconNumberOfScalarComponents](#)
- int [ImageFormat](#)
- double [ImageOrientationPatient](#) [6]
- double [ImagePositionPatient](#) [3]
- int [LoadIconImage](#)
- int [LoadOverlays](#)
- int [LossyFlag](#)
- [vtkMedicalImageProperties](#) * [MedicalImageProperties](#)
- int [NumberOfIconImages](#)
- int [NumberOfOverlays](#)
- int [PlanarConfiguration](#)
- double [Scale](#)
- double [Shift](#)

10.381.1 Detailed Description

Examples

[AWTMedical3.java](#), [Convert16BitsTo8Bits.cxx](#), [ConvertMultiFrameToSingleFrame.cxx](#), [ConvertRGBToLuminance.cxx](#), [ConvertSingleBitTo8Bits.cxx](#), [HelloActiviz.cs](#), [HelloActiviz2.cs](#), [HelloActiviz3.cs](#), [HelloActiviz4.cs](#), [HelloActiviz5.cs](#), [HelloVTKWorld.cs](#), [HelloVTKWorld.java](#), [MIPViewer.java](#), [MPRViewer.java](#), [MPRViewer2.java](#), [MagnifyFile.cxx](#), [MetaImageMD5Activiz.cs](#), [ReadSeriesIntoVTK.java](#), [RefCounting.cs](#), [gdcmmorthoplanes.cxx](#), [gdcmmreslice.cxx](#), [gdcmmtexture.cxx](#), [gdcmmvolume.cxx](#), and [offscreenimage.cxx](#).

10.381.2 Constructor & Destructor Documentation

10.381.2.1 vtkGDCMImageReader()

```
vtkGDCMImageReader::vtkGDCMImageReader () [protected]
```

Examples

[HelloActiviz2.cs](#).

References [vtkGDCMImageReader\(\)](#).

Referenced by [vtkGDCMImageReader\(\)](#), [~vtkGDCMImageReader\(\)](#), [New\(\)](#), [vtkGetStringMacro\(\)](#), [vtkTypeMacro\(\)](#), and [vtkGDCMThreadedImageReader::vtkTypeMacro\(\)](#).

10.381.2.2 ~vtkGDCMImageReader()

```
vtkGDCMImageReader::~~vtkGDCMImageReader () [protected]
```

References [vtkGDCMImageReader\(\)](#).

10.381.3 Member Function Documentation

10.381.3.1 CanReadFile()

```
virtual int vtkGDCMImageReader::CanReadFile (  
    const char * fname) [virtual]
```

Examples

[AWTMedical3.java](#), and [MetaImageMD5Activiz.cs](#).

10.381.3.2 ExecuteData()

```
void vtkGDCMImageReader::ExecuteData (
    vtkDataObject * out) [protected]
```

10.381.3.3 ExecuteInformation()

```
void vtkGDCMImageReader::ExecuteInformation () [protected]
```

10.381.3.4 FillMedicalImageInformation()

```
void vtkGDCMImageReader::FillMedicalImageInformation (
    const gdcmm::ImageReader & reader) [protected]
```

References [FillMedicalImageInformation\(\)](#).

Referenced by [FillMedicalImageInformation\(\)](#).

10.381.3.5 GetDescriptiveName()

```
virtual const char * vtkGDCMImageReader::GetDescriptiveName () [inline], [virtual]
```

10.381.3.6 GetFileExtensions()

```
virtual const char * vtkGDCMImageReader::GetFileExtensions () [inline], [virtual]
```

10.381.3.7 GetIconImage()

```
vtkImageData * vtkGDCMImageReader::GetIconImage ()
```

10.381.3.8 GetOverlay()

```
vtkImageData * vtkGDCMImageReader::GetOverlay (
    int i)
```

10.381.3.9 LoadSingleFile()

```
int vtkGDCMImageReader::LoadSingleFile (
    const char * filename,
    char * pointer,
    unsigned long & outlen) [protected]
```

10.381.3.10 New()

```
vtkGDCMImageReader * vtkGDCMImageReader::New () [static]
```

Examples

[Convert16BitsTo8Bits.cxx](#), [ConvertMultiFrameToSingleFrame.cxx](#), [ConvertRGBToLuminance.cxx](#), [ConvertSingleBitTo8Bits.cxx](#), [HelloActiviz.cs](#), [HelloActiviz3.cs](#), [HelloActiviz4.cs](#), [HelloActiviz5.cs](#), [HelloVTKWorld.cs](#), [MagnifyFile.cxx](#), [MetaImageMD5Activiz.cs](#), [RefCounting.cs](#), [gdcmmorthoplanes.cxx](#), [gdcmlreslice.cxx](#), [gdcmltexture.cxx](#), [gdcmlvolume.cxx](#), [offscreenimage.cxx](#), and [reslicesphere.cxx](#).

References [vtkGDCMImageReader\(\)](#).

10.381.3.11 PrintSelf()

```
virtual void vtkGDCMImageReader::PrintSelf (
    ostream & os,
    vtkIndent indent) [virtual]
```

Reimplemented in [vtkGDCMThreadedImageReader](#).

10.381.3.12 RequestDataCompat()

```
int vtkGDCMImageReader::RequestDataCompat () [protected]
```

References [RequestDataCompat\(\)](#).

Referenced by [RequestDataCompat\(\)](#).

10.381.3.13 RequestInformationCompat()

```
int vtkGDCMImageReader::RequestInformationCompat () [protected]
```

References [RequestInformationCompat\(\)](#).

Referenced by [RequestInformationCompat\(\)](#).

10.381.3.14 SetCurve()

```
virtual void vtkGDCMImageReader::SetCurve (
    vtkPolyData * pd) [virtual]
```

References [SetCurve\(\)](#).

Referenced by [SetCurve\(\)](#).

10.381.3.15 SetFileNames()

```
virtual void vtkGDCMImageReader::SetFileNames (
    vtkStringArray * ) [virtual]
```

Examples

[AWTMedical3.java](#), [HelloActiviz3.cs](#), [HelloActiviz4.cs](#), [HelloActiviz5.cs](#), [MIPViewer.java](#), [MPRViewer.java](#), [MPRViewer2.java](#), [ReadSeriesIntoVTK.java](#), and [gdcmmorthoplanes.cxx](#).

10.381.3.16 SetFilePattern()

```
void vtkGDCMImageReader::SetFilePattern (
    const char * ) [inline], [protected]
```

10.381.3.17 SetFilePrefix()

```
void vtkGDCMImageReader::SetFilePrefix (
    const char * ) [inline], [protected]
```

10.381.3.18 SetMedicalImageProperties()

```
virtual void vtkGDCMImageReader::SetMedicalImageProperties (
    vtkMedicalImageProperties * pd) [virtual]
```

10.381.3.19 vtkBooleanMacro() [1/5]

```
vtkGDCMImageReader::vtkBooleanMacro (
    ApplyLookupTable ,
    int )
```

References [ApplyLookupTable](#).

10.381.3.20 vtkBooleanMacro() [2/5]

```
int vtkGDCMImageReader::vtkBooleanMacro (
    ApplyYBRToRGB ,
    int )
```

References [ApplyYBRToRGB](#), and [vtkBooleanMacro\(\)](#).

10.381.3.21 vtkBooleanMacro() [3/5]

```
vtkGDCMImageReader::vtkBooleanMacro (
    LoadIconImage ,
    int )
```

References [LoadIconImage](#).

10.381.3.22 vtkBooleanMacro() [4/5]

```
vtkGDCMImageReader::vtkBooleanMacro (
    LoadOverlays ,
    int )
```

References [LoadOverlays](#).

Referenced by [vtkBooleanMacro\(\)](#).

10.381.3.23 vtkBooleanMacro() [5/5]

```
vtkGDCMImageReader::vtkBooleanMacro (
    LossyFlag ,
    int )
```

References [LossyFlag](#).

10.381.3.24 vtkGetMacro() [1/11]

```
vtkGDCMImageReader::vtkGetMacro (
    ApplyLookupTable ,
    int )
```

References [ApplyLookupTable](#).

10.381.3.25 vtkGetMacro() [2/11]

```
vtkGDCMImageReader::vtkGetMacro (
    ApplyYBRToRGB ,
    int )
```

References [ApplyYBRToRGB](#), and [vtkSetMacro\(\)](#).

10.381.3.26 vtkGetMacro() [3/11]

```
vtkGDCMImageReader::vtkGetMacro (
    ImageFormat ,
    int )
```

References [ImageFormat](#), and [vtkGetMacro\(\)](#).

10.381.3.27 vtkGetMacro() [4/11]

```
vtkGDCMImageReader::vtkGetMacro (
    LoadIconImage ,
    int )
```

References [LoadIconImage](#).

10.381.3.28 vtkGetMacro() [5/11]

```
vtkGDCMImageReader::vtkGetMacro (
    LoadOverlays ,
    int )
```

References [LoadOverlays](#).

Referenced by [vtkGetMacro\(\)](#), [vtkGetMacro\(\)](#), [vtkGetMacro\(\)](#), and [vtkGetMacro\(\)](#).

10.381.3.29 vtkGetMacro() [6/11]

```
vtkGDCMImageReader::vtkGetMacro (
    LossyFlag ,
    int )
```

References [LossyFlag](#).

10.381.3.30 vtkGetMacro() [7/11]

```
vtkGDCMImageReader::vtkGetMacro (
    NumberOfIconImages ,
    int )
```

References [NumberOfIconImages](#).

10.381.3.31 vtkGetMacro() [8/11]

```
vtkGDCMImageReader::vtkGetMacro (
    NumberOfOverlays ,
    int )
```

References [NumberOfOverlays](#).

10.381.3.32 vtkGetMacro() [9/11]

```
vtkGDCMImageReader::vtkGetMacro (
    PlanarConfiguration ,
    int )
```

References [PlanarConfiguration](#), and [vtkGetMacro\(\)](#).

10.381.3.33 vtkGetMacro() [10/11]

```
vtkGDCMImageReader::vtkGetMacro (
    Scale ,
    double )
```

References [Scale](#), and [vtkGetMacro\(\)](#).

10.381.3.34 vtkGetMacro() [11/11]

```
vtkGDCMImageReader::vtkGetMacro (
    Shift ,
    double )
```

References [Shift](#), and [vtkGetMacro\(\)](#).

10.381.3.35 vtkGetObjectMacro() [1/4]

```
vtkGDCMImageReader::vtkGetObjectMacro (
    Curve ,
    vtkPolyData )
```

References [Curve](#), and [vtkGetObjectMacro\(\)](#).

10.381.3.36 vtkGetObjectMacro() [2/4]

```
vtkGDCMImageReader::vtkGetObjectMacro (
    DirectionCosines ,
    vtkMatrix4x4 )
```

References [DirectionCosines](#).

Referenced by [vtkGetObjectMacro\(\)](#).

10.381.3.37 vtkGetObjectMacro() [3/4]

```
vtkGDCMImageReader::vtkGetObjectMacro (
    FileNames ,
    vtkStringArray )
```

References [FileNames](#).

10.381.3.38 vtkGetObjectMacro() [4/4]

```
vtkGDCMImageReader::vtkGetObjectMacro (
    MedicalImageProperties ,
    vtkMedicalImageProperties )
```

References [MedicalImageProperties](#).

10.381.3.39 vtkGetStringMacro() [1/2]

```
vtkGDCMImageReader::vtkGetStringMacro (
    FilePattern ) [protected]
```

References [vtkGDCMImageReader\(\)](#).

10.381.3.40 vtkGetStringMacro() [2/2]

```
vtkGDCMImageReader::vtkGetStringMacro (
    FilePrefix ) [protected]
```

10.381.3.41 vtkGetVector3Macro()

```
vtkGDCMImageReader::vtkGetVector3Macro (
    ImagePositionPatient ,
    double )
```

References [ImagePositionPatient](#), and [vtkGetVector3Macro\(\)](#).

Referenced by [vtkGetVector3Macro\(\)](#).

10.381.3.42 vtkGetVector6Macro()

```
vtkGDCMImageReader::vtkGetVector6Macro (
    ImageOrientationPatient ,
    double )
```

References [ImageOrientationPatient](#), and [vtkGetVector6Macro\(\)](#).

Referenced by [vtkGetVector6Macro\(\)](#).

10.381.3.43 vtkSetMacro() [1/4]

```
vtkGDCMImageReader::vtkSetMacro (
    ApplyLookupTable ,
    int )
```

References [ApplyLookupTable](#).

10.381.3.44 vtkSetMacro() [2/4]

```
vtkGDCMImageReader::vtkSetMacro (
    LoadIconImage ,
    int )
```

References [LoadIconImage](#).

10.381.3.45 vtkSetMacro() [3/4]

```
vtkGDCMImageReader::vtkSetMacro (
    LoadOverlays ,
    int )
```

References [LoadOverlays](#).

Referenced by [vtkGetMacro\(\)](#).

10.381.3.46 vtkSetMacro() [4/4]

```
vtkGDCMImageReader::vtkSetMacro (
    LossyFlag ,
    int )
```

References [LossyFlag](#).

10.381.3.47 vtkSetVector6Macro()

```
vtkGDCMImageReader::vtkSetVector6Macro (
    ImageOrientationPatient ,
    double ) [protected]
```

References [ImageOrientationPatient](#), and [vtkSetVector6Macro\(\)](#).

Referenced by [vtkSetVector6Macro\(\)](#).

10.381.3.48 vtkTypeMacro()

```
vtkGDCMImageReader::vtkTypeMacro (
    vtkGDCMImageReader ,
    vtkMedicalImageReader2 )
```

References [vtkGDCMImageReader\(\)](#).

10.381.4 Member Data Documentation

10.381.4.1 ApplyInverseVideo

```
int vtkGDCMImageReader::ApplyInverseVideo [protected]
```

10.381.4.2 ApplyLookupTable

```
int vtkGDCMImageReader::ApplyLookupTable [protected]
```

Referenced by [vtkBooleanMacro\(\)](#), [vtkGetMacro\(\)](#), and [vtkSetMacro\(\)](#).

10.381.4.3 ApplyPlanarConfiguration

```
int vtkGDCMImageReader::ApplyPlanarConfiguration [protected]
```

10.381.4.4 ApplyShiftScale

```
int vtkGDCMImageReader::ApplyShiftScale [protected]
```

10.381.4.5 ApplyYBRToRGB

```
int vtkGDCMImageReader::ApplyYBRToRGB [protected]
```

Referenced by [vtkBooleanMacro\(\)](#), and [vtkGetMacro\(\)](#).

10.381.4.6 Curve

```
vtkPolyData* vtkGDCMImageReader::Curve [protected]
```

Referenced by [vtkGetObjectMacro\(\)](#).

10.381.4.7 DirectionCosines

`vtkMatrix4x4* vtkGDCMImageReader::DirectionCosines [protected]`

Referenced by [vtkGetObjectMacro\(\)](#).

10.381.4.8 FileNames

`vtkStringArray* vtkGDCMImageReader::FileNames [protected]`

Referenced by [vtkGetObjectMacro\(\)](#).

10.381.4.9 ForceRescale

`int vtkGDCMImageReader::ForceRescale [protected]`

10.381.4.10 IconDataScalarType

`int vtkGDCMImageReader::IconDataScalarType [protected]`

10.381.4.11 IconImageDataExtent

`int vtkGDCMImageReader::IconImageDataExtent[6] [protected]`

10.381.4.12 IconNumberOfScalarComponents

`int vtkGDCMImageReader::IconNumberOfScalarComponents [protected]`

10.381.4.13 ImageFormat

`int vtkGDCMImageReader::ImageFormat [protected]`

Referenced by [vtkGetMacro\(\)](#).

10.381.4.14 ImageOrientationPatient

`double vtkGDCMImageReader::ImageOrientationPatient[6] [protected]`

Referenced by [vtkGetVector6Macro\(\)](#), and [vtkSetVector6Macro\(\)](#).

10.381.4.15 ImagePositionPatient

```
double vtkGDCMImageReader::ImagePositionPatient[3] [protected]
```

Referenced by [vtkGetVector3Macro\(\)](#).

10.381.4.16 LoadIconImage

```
int vtkGDCMImageReader::LoadIconImage [protected]
```

Referenced by [vtkBooleanMacro\(\)](#), [vtkGetMacro\(\)](#), and [vtkSetMacro\(\)](#).

10.381.4.17 LoadOverlays

```
int vtkGDCMImageReader::LoadOverlays [protected]
```

Referenced by [vtkBooleanMacro\(\)](#), [vtkGetMacro\(\)](#), and [vtkSetMacro\(\)](#).

10.381.4.18 LossyFlag

```
int vtkGDCMImageReader::LossyFlag [protected]
```

Referenced by [vtkBooleanMacro\(\)](#), [vtkGetMacro\(\)](#), and [vtkSetMacro\(\)](#).

10.381.4.19 MedicalImageProperties

```
vtkMedicalImageProperties* vtkGDCMImageReader::MedicalImageProperties [protected]
```

Referenced by [vtkGetObjectMacro\(\)](#).

10.381.4.20 NumberOfIconImages

```
int vtkGDCMImageReader::NumberOfIconImages [protected]
```

Referenced by [vtkGetMacro\(\)](#).

10.381.4.21 NumberOfOverlays

```
int vtkGDCMImageReader::NumberOfOverlays [protected]
```

Referenced by [vtkGetMacro\(\)](#).

10.381.4.22 PlanarConfiguration

```
int vtkGDCMImageReader::PlanarConfiguration [protected]
```

Referenced by [vtkGetMacro\(\)](#).

10.381.4.23 Scale

```
double vtkGDCMImageReader::Scale [protected]
```

Referenced by [vtkGetMacro\(\)](#), and [vtkGDCMThreadedImageReader::vtkSetMacro\(\)](#).

10.381.4.24 Shift

```
double vtkGDCMImageReader::Shift [protected]
```

Referenced by [vtkGetMacro\(\)](#), and [vtkGDCMThreadedImageReader::vtkSetMacro\(\)](#).


The documentation for this class was generated from the following file:

- [vtkGDCMImageReader.h](#)


10.382 vtkGDCMImageReader2 Class Reference

```
#include <vtkGDCMImageReader2.h>
```

Inheritance diagram for vtkGDCMImageReader2:



Collaboration diagram for vtkGDCMImageReader2:



Public Member Functions

- virtual int [CanReadFile](#) (const char *fname)
- virtual const char * [GetDescriptiveName](#) ()
- virtual const char * [GetFileExtensions](#) ()
- vtkImageData * [GetIconImage](#) ()
- vtkAlgorithmOutput * [GetIconImagePort](#) ()
- vtkImageData * [GetOverlay](#) (int i)
- vtkAlgorithmOutput * [GetOverlayPort](#) (int index)
- virtual void [PrintSelf](#) (ostream &os, vtkIndent indent)
- virtual void [SetCurve](#) (vtkPolyData *pd)
- virtual void [SetMedicalImageProperties](#) (vtkMedicalImageProperties *pd)
- [vtkBooleanMacro](#) ([ApplyLookupTable](#), int)
- int [vtkBooleanMacro](#) ([ApplyYBRToRGB](#), int)
- [vtkBooleanMacro](#) ([LoadIconImage](#), int)
- [vtkBooleanMacro](#) ([LoadOverlays](#), int)
- [vtkBooleanMacro](#) ([LossyFlag](#), int)
- [vtkGetMacro](#) ([ApplyLookupTable](#), int)
- [vtkGetMacro](#) ([ApplyYBRToRGB](#), int) [vtkSetMacro](#)([ApplyYBRToRGB](#)
- [vtkGetMacro](#) ([ImageFormat](#), int)
- [vtkGetMacro](#) ([LoadIconImage](#), int)
- [vtkGetMacro](#) ([LoadOverlays](#), int)
- [vtkGetMacro](#) ([LossyFlag](#), int)
- [vtkGetMacro](#) ([NumberOfIconImages](#), int)
- [vtkGetMacro](#) ([NumberOfOverlays](#), int)
- [vtkGetMacro](#) ([PlanarConfiguration](#), int)
- [vtkGetMacro](#) ([Scale](#), double)
- [vtkGetMacro](#) ([Shift](#), double)
- [vtkGetObjectMacro](#) ([Curve](#), vtkPolyData)
- [vtkGetObjectMacro](#) ([DirectionCosines](#), vtkMatrix4x4)
- [vtkGetVector3Macro](#) ([ImagePositionPatient](#), double)
- [vtkGetVector6Macro](#) ([ImageOrientationPatient](#), double)
- [vtkSetMacro](#) ([ApplyLookupTable](#), int)
- [vtkSetMacro](#) ([LoadIconImage](#), int)
- [vtkSetMacro](#) ([LoadOverlays](#), int)
- [vtkSetMacro](#) ([LossyFlag](#), int)
- [vtkTypeMacro](#) (vtkGDCMImageReader2, vtkMedicalImageReader2)

Static Public Member Functions

- static [vtkGDCMImageReader2](#) * [New](#) ()

Protected Member Functions

- [vtkGDCMImageReader2](#) ()
- [~vtkGDCMImageReader2](#) ()
- void [FillMedicalImageInformation](#) (const [gdcmm::ImageReader](#) &reader)
- int [LoadSingleFile](#) (const char *filename, char *pointer, unsigned long &outlen)
- int [ProcessRequest](#) (vtkInformation *request, vtkInformationVector **inputVector, vtkInformationVector *outputVector)
- int [RequestData](#) (vtkInformation *request, vtkInformationVector **inputVector, vtkInformationVector *outputVector)
- int [RequestDataCompat](#) ()
- int [RequestInformation](#) (vtkInformation *request, vtkInformationVector **inputVector, vtkInformationVector *outputVector)
- int [RequestInformationCompat](#) ()
- void [SetFilePattern](#) (const char *)
- void [SetFilePrefix](#) (const char *)
- [vtkGetStringMacro](#) (FilePattern)
- [vtkGetStringMacro](#) (FilePrefix)
- [vtkSetVector6Macro](#) (ImageOrientationPatient, double)

Protected Attributes

- int [ApplyInverseVideo](#)
- int [ApplyLookupTable](#)
- int [ApplyPlanarConfiguration](#)
- int [ApplyShiftScale](#)
- int [ApplyYBRToRGB](#)
- vtkPolyData * [Curve](#)
- vtkMatrix4x4 * [DirectionCosines](#)
- int [ForceRescale](#)
- int [IconDataScalarType](#)
- int [IconImageDataExtent](#) [6]
- int [IconNumberOfScalarComponents](#)
- int [ImageFormat](#)
- double [ImageOrientationPatient](#) [6]
- double [ImagePositionPatient](#) [3]
- int [LoadIconImage](#)
- int [LoadOverlays](#)
- int [LossyFlag](#)
- int [NumberOfIconImages](#)
- int [NumberOfOverlays](#)
- int [PlanarConfiguration](#)
- double [Scale](#)
- double [Shift](#)

10.382.1 Detailed Description

Examples

[Compute3DSpacing.cxx](#).

10.382.2 Constructor & Destructor Documentation

10.382.2.1 vtkGDCMImageReader2()

```
vtkGDCMImageReader2::vtkGDCMImageReader2 () [protected]
```

References [vtkGDCMImageReader2\(\)](#).

Referenced by [vtkGDCMImageReader2\(\)](#), [~vtkGDCMImageReader2\(\)](#), [New\(\)](#), [vtkGetStringMacro\(\)](#), and [vtkTypeMacro\(\)](#).

10.382.2.2 ~vtkGDCMImageReader2()

```
vtkGDCMImageReader2::~~vtkGDCMImageReader2 () [protected]
```

References [vtkGDCMImageReader2\(\)](#).

10.382.3 Member Function Documentation

10.382.3.1 CanReadFile()

```
virtual int vtkGDCMImageReader2::CanReadFile (
    const char * fname) [virtual]
```

10.382.3.2 FillMedicalImageInformation()

```
void vtkGDCMImageReader2::FillMedicalImageInformation (
    const gdcm::ImageReader & reader) [protected]
```

References [FillMedicalImageInformation\(\)](#).

Referenced by [FillMedicalImageInformation\(\)](#).

10.382.3.3 GetDescriptiveName()

```
virtual const char * vtkGDCMImageReader2::GetDescriptiveName () [inline], [virtual]
```

10.382.3.4 GetFileExtensions()

```
virtual const char * vtkGDCMImageReader2::GetFileExtensions () [inline], [virtual]
```

10.382.3.5 GetIconImage()

```
vtkImageData * vtkGDCMImageReader2::GetIconImage ()
```

10.382.3.6 GetIconImagePort()

```
vtkAlgorithmOutput * vtkGDCMImageReader2::GetIconImagePort ()
```

10.382.3.7 GetOverlay()

```
vtkImageData * vtkGDCMImageReader2::GetOverlay (
    int i)
```

10.382.3.8 GetOverlayPort()

```
vtkAlgorithmOutput * vtkGDCMImageReader2::GetOverlayPort (
    int index)
```

10.382.3.9 LoadSingleFile()

```
int vtkGDCMImageReader2::LoadSingleFile (
    const char * filename,
    char * pointer,
    unsigned long & outlen) [protected]
```

References [LoadSingleFile\(\)](#).

Referenced by [LoadSingleFile\(\)](#).

10.382.3.10 New()

```
vtkGDCMImageReader2 * vtkGDCMImageReader2::New () [static]
```

Examples

[Compute3DSpacing.cxx](#).

References [vtkGDCMImageReader2\(\)](#).

10.382.3.11 PrintSelf()

```
virtual void vtkGDCMImageReader2::PrintSelf (
    ostream & os,
    vtkIndent indent) [virtual]
```

10.382.3.12 ProcessRequest()

```
int vtkGDCMImageReader2::ProcessRequest (
    vtkInformation * request,
    vtkInformationVector ** inputVector,
    vtkInformationVector * outputVector) [protected]
```

References [ProcessRequest\(\)](#).

Referenced by [ProcessRequest\(\)](#).

10.382.3.13 RequestData()

```
int vtkGDCMImageReader2::RequestData (
    vtkInformation * request,
    vtkInformationVector ** inputVector,
    vtkInformationVector * outputVector) [protected]
```

References [RequestData\(\)](#).

Referenced by [RequestData\(\)](#).

10.382.3.14 RequestDataCompat()

```
int vtkGDCMImageReader2::RequestDataCompat () [protected]
```

References [RequestDataCompat\(\)](#).

Referenced by [RequestDataCompat\(\)](#).

10.382.3.15 RequestInformation()

```
int vtkGDCMImageReader2::RequestInformation (
    vtkInformation * request,
    vtkInformationVector ** inputVector,
    vtkInformationVector * outputVector) [protected]
```

References [RequestInformation\(\)](#).

Referenced by [RequestInformation\(\)](#).

10.382.3.16 RequestInformationCompat()

```
int vtkGDCMImageReader2::RequestInformationCompat () [protected]
```

References [RequestInformationCompat\(\)](#).

Referenced by [RequestInformationCompat\(\)](#).

10.382.3.17 SetCurve()

```
virtual void vtkGDCMImageReader2::SetCurve (
    vtkPolyData * pd) [virtual]
```

References [SetCurve\(\)](#).

Referenced by [SetCurve\(\)](#).

10.382.3.18 SetFilePattern()

```
void vtkGDCMImageReader2::SetFilePattern (
    const char * ) [inline], [protected]
```

10.382.3.19 SetFilePrefix()

```
void vtkGDCMImageReader2::SetFilePrefix (
    const char * ) [inline], [protected]
```

References [SetFilePrefix\(\)](#).

Referenced by [SetFilePrefix\(\)](#).

10.382.3.20 SetMedicalImageProperties()

```
virtual void vtkGDCMImageReader2::SetMedicalImageProperties (
    vtkMedicalImageProperties * pd) [virtual]
```

10.382.3.21 vtkBooleanMacro() [1/5]

```
vtkGDCMImageReader2::vtkBooleanMacro (
    ApplyLookupTable ,
    int )
```

References [ApplyLookupTable](#).

10.382.3.22 vtkBooleanMacro() [2/5]

```
int vtkGDCMImageReader2::vtkBooleanMacro (
    ApplyYBRToRGB ,
    int )
```

References [ApplyYBRToRGB](#), and [vtkBooleanMacro\(\)](#).

10.382.3.23 vtkBooleanMacro() [3/5]

```
vtkGDCMImageReader2::vtkBooleanMacro (
    LoadIconImage ,
    int )
```

References [LoadIconImage](#).

10.382.3.24 vtkBooleanMacro() [4/5]

```
vtkGDCMImageReader2::vtkBooleanMacro (
    LoadOverlays ,
    int )
```

References [LoadOverlays](#).

Referenced by [vtkBooleanMacro\(\)](#).

10.382.3.25 vtkBooleanMacro() [5/5]

```
vtkGDCMImageReader2::vtkBooleanMacro (
    LossyFlag ,
    int )
```

References [LossyFlag](#).

10.382.3.26 vtkGetMacro() [1/11]

```
vtkGDCMImageReader2::vtkGetMacro (
    ApplyLookupTable ,
    int )
```

References [ApplyLookupTable](#).

10.382.3.27 vtkGetMacro() [2/11]

```
vtkGDCMImageReader2::vtkGetMacro (
    ApplyYBRToRGB ,
    int )
```

References [ApplyYBRToRGB](#), and [vtkSetMacro\(\)](#).

10.382.3.28 vtkGetMacro() [3/11]

```
vtkGDCMImageReader2::vtkGetMacro (
    ImageFormat ,
    int )
```

References [ImageFormat](#), and [vtkGetMacro\(\)](#).

10.382.3.29 vtkGetMacro() [4/11]

```
vtkGDCMImageReader2::vtkGetMacro (
    LoadIconImage ,
    int )
```

References [LoadIconImage](#).

10.382.3.30 vtkGetMacro() [5/11]

```
vtkGDCMImageReader2::vtkGetMacro (
    LoadOverlays ,
    int )
```

References [LoadOverlays](#).

Referenced by [vtkGetMacro\(\)](#), [vtkGetMacro\(\)](#), [vtkGetMacro\(\)](#), and [vtkGetMacro\(\)](#).

10.382.3.31 vtkGetMacro() [6/11]

```
vtkGDCMImageReader2::vtkGetMacro (
    LossyFlag ,
    int )
```

References [LossyFlag](#).

10.382.3.32 vtkGetMacro() [7/11]

```
vtkGDCMImageReader2::vtkGetMacro (
    NumberOfIconImages ,
    int )
```

References [NumberOfIconImages](#).

10.382.3.33 vtkGetMacro() [8/11]

```
vtkGDCMImageReader2::vtkGetMacro (
    NumberOfOverlays ,
    int )
```

References [NumberOfOverlays](#).

10.382.3.34 vtkGetMacro() [9/11]

```
vtkGDCMImageReader2::vtkGetMacro (
    PlanarConfiguration ,
    int )
```

References [PlanarConfiguration](#), and [vtkGetMacro\(\)](#).

10.382.3.35 vtkGetMacro() [10/11]

```
vtkGDCMImageReader2::vtkGetMacro (
    Scale ,
    double )
```

References [Scale](#), and [vtkGetMacro\(\)](#).

10.382.3.36 vtkGetMacro() [11/11]

```
vtkGDCMImageReader2::vtkGetMacro (
    Shift ,
    double )
```

References [Shift](#), and [vtkGetMacro\(\)](#).

10.382.3.37 vtkGetObjectMacro() [1/2]

```
vtkGDCMImageReader2::vtkGetObjectMacro (
    Curve ,
    vtkPolyData )
```

References [Curve](#), and [vtkGetObjectMacro\(\)](#).

10.382.3.38 vtkGetObjectMacro() [2/2]

```
vtkGDCMImageReader2::vtkGetObjectMacro (
    DirectionCosines ,
    vtkMatrix4x4 )
```

References [DirectionCosines](#).

Referenced by [vtkGetObjectMacro\(\)](#).

10.382.3.39 vtkGetStringMacro() [1/2]

```
vtkGDCMImageReader2::vtkGetStringMacro (
    FilePattern ) [protected]
```

References [vtkGDCMImageReader2\(\)](#).

10.382.3.40 vtkGetStringMacro() [2/2]

```
vtkGDCMImageReader2::vtkGetStringMacro (
    FilePrefix ) [protected]
```

10.382.3.41 vtkGetVector3Macro()

```
vtkGDCMImageReader2::vtkGetVector3Macro (
    ImagePositionPatient ,
    double )
```

References [ImagePositionPatient](#), and [vtkGetVector3Macro\(\)](#).

Referenced by [vtkGetVector3Macro\(\)](#).

10.382.3.42 vtkGetVector6Macro()

```
vtkGDCMImageReader2::vtkGetVector6Macro (
    ImageOrientationPatient ,
    double )
```

References [ImageOrientationPatient](#), and [vtkGetVector6Macro\(\)](#).

Referenced by [vtkGetVector6Macro\(\)](#).

10.382.3.43 vtkSetMacro() [1/4]

```
vtkGDCMImageReader2::vtkSetMacro (
    ApplyLookupTable ,
    int )
```

References [ApplyLookupTable](#).

10.382.3.44 vtkSetMacro() [2/4]

```
vtkGDCMImageReader2::vtkSetMacro (
    LoadIconImage ,
    int )
```

References [LoadIconImage](#).

10.382.3.45 vtkSetMacro() [3/4]

```
vtkGDCMImageReader2::vtkSetMacro (
    LoadOverlays ,
    int )
```

References [LoadOverlays](#).

Referenced by [vtkGetMacro\(\)](#).

10.382.3.46 vtkSetMacro() [4/4]

```
vtkGDCMImageReader2::vtkSetMacro (
    LossyFlag ,
    int )
```

References [LossyFlag](#).

10.382.3.47 vtkSetVector6Macro()

```
vtkGDCMImageReader2::vtkSetVector6Macro (
    ImageOrientationPatient ,
    double ) [protected]
```

References [ImageOrientationPatient](#), and [vtkSetVector6Macro\(\)](#).

Referenced by [vtkSetVector6Macro\(\)](#).

10.382.3.48 vtkTypeMacro()

```
vtkGDCMImageReader2::vtkTypeMacro (
    vtkGDCMImageReader2 ,
    vtkMedicalImageReader2 )
```

References [vtkGDCMImageReader2\(\)](#).

10.382.4 Member Data Documentation

10.382.4.1 ApplyInverseVideo

```
int vtkGDCMImageReader2::ApplyInverseVideo [protected]
```

10.382.4.2 ApplyLookupTable

```
int vtkGDCMImageReader2::ApplyLookupTable [protected]
```

Referenced by [vtkBooleanMacro\(\)](#), [vtkGetMacro\(\)](#), and [vtkSetMacro\(\)](#).

10.382.4.3 ApplyPlanarConfiguration

```
int vtkGDCMImageReader2::ApplyPlanarConfiguration [protected]
```

10.382.4.4 ApplyShiftScale

```
int vtkGDCMImageReader2::ApplyShiftScale [protected]
```

10.382.4.5 ApplyYBRToRGB

```
int vtkGDCMImageReader2::ApplyYBRToRGB [protected]
```

Referenced by [vtkBooleanMacro\(\)](#), and [vtkGetMacro\(\)](#).

10.382.4.6 Curve

```
vtkPolyData* vtkGDCMImageReader2::Curve [protected]
```

Referenced by [vtkGetObjectMacro\(\)](#).

10.382.4.7 DirectionCosines

`vtkMatrix4x4* vtkGDCMImageReader2::DirectionCosines` [protected]

Referenced by [vtkGetObjectMacro\(\)](#).

10.382.4.8 ForceRescale

`int vtkGDCMImageReader2::ForceRescale` [protected]

10.382.4.9 IconDataScalarType

`int vtkGDCMImageReader2::IconDataScalarType` [protected]

10.382.4.10 IconImageDataExtent

`int vtkGDCMImageReader2::IconImageDataExtent[6]` [protected]

10.382.4.11 IconNumberOfScalarComponents

`int vtkGDCMImageReader2::IconNumberOfScalarComponents` [protected]

10.382.4.12 ImageFormat

`int vtkGDCMImageReader2::ImageFormat` [protected]

Referenced by [vtkGetMacro\(\)](#).

10.382.4.13 ImageOrientationPatient

`double vtkGDCMImageReader2::ImageOrientationPatient[6]` [protected]

Referenced by [vtkGetVector6Macro\(\)](#), and [vtkSetVector6Macro\(\)](#).

10.382.4.14 ImagePositionPatient

`double vtkGDCMImageReader2::ImagePositionPatient[3]` [protected]

Referenced by [vtkGetVector3Macro\(\)](#).

10.382.4.15 LoadIconImage

```
int vtkGDCMImageReader2::LoadIconImage [protected]
```

Referenced by [vtkBooleanMacro\(\)](#), [vtkGetMacro\(\)](#), and [vtkSetMacro\(\)](#).

10.382.4.16 LoadOverlays

```
int vtkGDCMImageReader2::LoadOverlays [protected]
```

Referenced by [vtkBooleanMacro\(\)](#), [vtkGetMacro\(\)](#), and [vtkSetMacro\(\)](#).

10.382.4.17 LossyFlag

```
int vtkGDCMImageReader2::LossyFlag [protected]
```

Referenced by [vtkBooleanMacro\(\)](#), [vtkGetMacro\(\)](#), and [vtkSetMacro\(\)](#).

10.382.4.18 NumberOfIconImages

```
int vtkGDCMImageReader2::NumberOfIconImages [protected]
```

Referenced by [vtkGetMacro\(\)](#).

10.382.4.19 NumberOfOverlays

```
int vtkGDCMImageReader2::NumberOfOverlays [protected]
```

Referenced by [vtkGetMacro\(\)](#).

10.382.4.20 PlanarConfiguration

```
int vtkGDCMImageReader2::PlanarConfiguration [protected]
```

Referenced by [vtkGetMacro\(\)](#).

10.382.4.21 Scale

```
double vtkGDCMImageReader2::Scale [protected]
```

Referenced by [vtkGetMacro\(\)](#).

10.382.4.22 Shift

```
double vtkGDCMImageReader2::Shift [protected]
```

Referenced by [vtkGetMacro\(\)](#).


The documentation for this class was generated from the following file:

- [vtkGDCMImageReader2.h](#)


10.383 vtkGDCMImageWriter Class Reference

```
#include <vtkGDCMImageWriter.h>
```

Inheritance diagram for vtkGDCMImageWriter:



Collaboration diagram for vtkGDCMImageWriter:



Public Types

- enum [CompressionTypes](#) {
 [NO_COMPRESSION](#) = 0 ,
 [JPEG_COMPRESSION](#) ,
 [JPEG2000_COMPRESSION](#) ,
 [JPEGLS_COMPRESSION](#) ,
 [RLE_COMPRESSION](#) }

Public Member Functions

- virtual const char * [GetDescriptiveName](#) ()
- virtual const char * [GetFileExtensions](#) ()
- virtual void [PrintSelf](#) (ostream &os, vtkIndent indent)
- virtual void [SetDirectionCosines](#) (vtkMatrix4x4 *matrix)
- virtual void [SetDirectionCosinesFromImageOrientationPatient](#) (const double dircos[6])
- virtual void [SetFileNames](#) (vtkStringArray *)
- virtual void [SetMedicalImageProperties](#) (vtkMedicalImageProperties *)
- [vtkBooleanMacro](#) (FileLowerLeft, int)
- [vtkBooleanMacro](#) (LossyFlag, int)
- [vtkGetMacro](#) (CompressionType, int)
- [vtkGetMacro](#) (FileLowerLeft, int)
- [vtkGetMacro](#) (ImageFormat, int)
- [vtkGetMacro](#) (LossyFlag, int)
- [vtkGetMacro](#) (PlanarConfiguration, int)
- [vtkGetMacro](#) (Scale, double)
- [vtkGetMacro](#) (Shift, double)
- [vtkGetObjectMacro](#) (DirectionCosines, vtkMatrix4x4)
- [vtkGetObjectMacro](#) (FileNames, vtkStringArray)
- [vtkGetObjectMacro](#) (MedicalImageProperties, vtkMedicalImageProperties)
- [vtkGetStringMacro](#) (SeriesUID)
- [vtkGetStringMacro](#) (StudyUID)
- [vtkSetMacro](#) (CompressionType, int)
- [vtkSetMacro](#) (FileLowerLeft, int)
- [vtkSetMacro](#) (ImageFormat, int)
- [vtkSetMacro](#) (LossyFlag, int)
- [vtkSetMacro](#) (PlanarConfiguration, int)
- [vtkSetMacro](#) (Scale, double)
- [vtkSetMacro](#) (Shift, double)
- [vtkSetStringMacro](#) (SeriesUID)
- [vtkSetStringMacro](#) (StudyUID)
- [vtkTypeMacro](#) ([vtkGDCMImageWriter](#), vtkImageWriter)
- virtual void [Write](#) ()

Static Public Member Functions

- static [vtkGDCMImageWriter](#) * [New](#) ()

Protected Member Functions

- [vtkGDCMImageWriter \(\)](#)
- [~vtkGDCMImageWriter \(\)](#)
- virtual char * [GetFileName \(\)](#)
- int [WriteGDCMData](#) (vtkImageData *data, int timeStep)
- void [WriteSlice](#) (vtkImageData *data)

10.383.1 Detailed Description**Examples**

[Convert16BitsTo8Bits.cxx](#), [ConvertMultiFrameToSingleFrame.cxx](#), [ConvertRGBToLuminance.cxx](#), [ConvertSingleBitTo8Bits.cxx](#), [CreateFakePET.cxx](#), [CreateFakeRTDOSE.cxx](#), [HelloActiviz.cs](#), [HelloActiviz2.cs](#), [HelloVTKWorld.cs](#), [HelloVTKWorld.java](#), [HelloVTKWorld2.cs](#), [MagnifyFile.cxx](#), [RefCounting.cs](#), and [gdcmmorthoplanes.cxx](#).

10.383.2 Member Enumeration Documentation**10.383.2.1 CompressionTypes**

```
enum vtkGDCMImageWriter::CompressionTypes
```

Enumerator

NO_COMPRESSION	
JPEG_COMPRESSION	
JPEG2000_COMPRESSION	
JPEGLS_COMPRESSION	
RLE_COMPRESSION	

10.383.3 Constructor & Destructor Documentation**10.383.3.1 vtkGDCMImageWriter()**

```
vtkGDCMImageWriter::vtkGDCMImageWriter () [protected]
```

Referenced by [GetFileName\(\)](#), [New\(\)](#), and [vtkTypeMacro\(\)](#).

10.383.3.2 ~vtkGDCMImageWriter()

```
vtkGDCMImageWriter::~vtkGDCMImageWriter () [protected]
```

10.383.4 Member Function Documentation

10.383.4.1 GetDescriptiveName()

```
virtual const char * vtkGDCMImageWriter::GetDescriptiveName () [inline], [virtual]
```

10.383.4.2 GetFileExtensions()

```
virtual const char * vtkGDCMImageWriter::GetFileExtensions () [inline], [virtual]
```

10.383.4.3 GetFileName()

```
virtual char * vtkGDCMImageWriter::GetFileName () [protected], [virtual]
```

References [vtkGDCMImageWriter\(\)](#).

10.383.4.4 New()

```
vtkGDCMImageWriter * vtkGDCMImageWriter::New () [static]
```

Examples

[Convert16BitsTo8Bits.cxx](#), [ConvertMultiFrameToSingleFrame.cxx](#), [ConvertRGBToLuminance.cxx](#), [ConvertSingleBitTo8Bits.cxx](#), [CreateFakePET.cxx](#), [CreateFakeRTDOSE.cxx](#), [HelloActiviz.cs](#), [HelloVTKWorld.cs](#), [HelloVTKWorld2.cs](#), [MagnifyFile.cxx](#), [RefCounting.cs](#), and [gdcmorphoplanes.cxx](#).

References [vtkGDCMImageWriter\(\)](#).

10.383.4.5 PrintSelf()

```
virtual void vtkGDCMImageWriter::PrintSelf (
    ostream & os,
    vtkIndent indent) [virtual]
```

10.383.4.6 SetDirectionCosines()

```
virtual void vtkGDCMImageWriter::SetDirectionCosines (
    vtkMatrix4x4 * matrix) [virtual]
```

Examples

[Convert16BitsTo8Bits.cxx](#), [ConvertRGBToLuminance.cxx](#), [ConvertSingleBitTo8Bits.cxx](#), [HelloActiviz2.cs](#), [HelloVTKWorld.cs](#), [HelloVTKWorld.java](#), [MagnifyFile.cxx](#), and [gdcmorphoplanes.cxx](#).

10.383.4.7 SetDirectionCosinesFromImageOrientationPatient()

```
virtual void vtkGDCMImageWriter::SetDirectionCosinesFromImageOrientationPatient (
    const double dircos[6]) [virtual]
```

10.383.4.8 SetFileNames()

```
virtual void vtkGDCMImageWriter::SetFileNames (
    vtkStringArray * ) [virtual]
```

Examples

[ConvertMultiFrameToSingleFrame.cxx](#), and [CreateFakePET.cxx](#).

10.383.4.9 SetMedicalImageProperties()

```
virtual void vtkGDCMImageWriter::SetMedicalImageProperties (
    vtkMedicalImageProperties * ) [virtual]
```

Examples

[Convert16BitsTo8Bits.cxx](#), [ConvertRGBToLuminance.cxx](#), [ConvertSingleBitTo8Bits.cxx](#), [HelloActiviz.cs](#), [HelloActiviz2.cs](#), [HelloVTKWorld.cs](#), [HelloVTKWorld.java](#), [MagnifyFile.cxx](#), and [gdcmmorthoplanes.cxx](#).

10.383.4.10 vtkBooleanMacro() [1/2]

```
vtkGDCMImageWriter::vtkBooleanMacro (
    FileLowerLeft ,
    int )
```

10.383.4.11 vtkBooleanMacro() [2/2]

```
vtkGDCMImageWriter::vtkBooleanMacro (
    LossyFlag ,
    int )
```

10.383.4.12 vtkGetMacro() [1/7]

```
vtkGDCMImageWriter::vtkGetMacro (
    CompressionType ,
    int )
```

10.383.4.13 vtkGetMacro() [2/7]

```
vtkGDCMImageWriter::vtkGetMacro (
    FileLowerLeft ,
    int )
```

10.383.4.14 vtkGetMacro() [3/7]

```
vtkGDCMImageWriter::vtkGetMacro (
    ImageFormat ,
    int )
```

10.383.4.15 vtkGetMacro() [4/7]

```
vtkGDCMImageWriter::vtkGetMacro (
    LossyFlag ,
    int )
```

10.383.4.16 vtkGetMacro() [5/7]

```
vtkGDCMImageWriter::vtkGetMacro (
    PlanarConfiguration ,
    int )
```

10.383.4.17 vtkGetMacro() [6/7]

```
vtkGDCMImageWriter::vtkGetMacro (
    Scale ,
    double )
```

10.383.4.18 vtkGetMacro() [7/7]

```
vtkGDCMImageWriter::vtkGetMacro (
    Shift ,
    double )
```

10.383.4.19 vtkGetObjectMacro() [1/3]

```
vtkGDCMImageWriter::vtkGetObjectMacro (
    DirectionCosines ,
    vtkMatrix4x4 )
```

10.383.4.20 vtkGetObjectMacro() [2/3]

```
vtkGDCMImageWriter::vtkGetObjectMacro (
    FileNames ,
    vtkStringArray )
```

10.383.4.21 vtkGetObjectMacro() [3/3]

```
vtkGDCMImageWriter::vtkGetObjectMacro (
    MedicalImageProperties ,
    vtkMedicalImageProperties )
```

10.383.4.22 vtkGetStringMacro() [1/2]

```
vtkGDCMImageWriter::vtkGetStringMacro (
    SeriesUID )
```

10.383.4.23 vtkGetStringMacro() [2/2]

```
vtkGDCMImageWriter::vtkGetStringMacro (
    StudyUID )
```

10.383.4.24 vtkSetMacro() [1/7]

```
vtkGDCMImageWriter::vtkSetMacro (
    CompressionType ,
    int )
```

10.383.4.25 vtkSetMacro() [2/7]

```
vtkGDCMImageWriter::vtkSetMacro (
    FileLowerLeft ,
    int )
```

10.383.4.26 vtkSetMacro() [3/7]

```
vtkGDCMImageWriter::vtkSetMacro (
    ImageFormat ,
    int )
```

10.383.4.27 vtkSetMacro() [4/7]

```
vtkGDCMImageWriter::vtkSetMacro (
    LossyFlag ,
    int )
```

10.383.4.28 vtkSetMacro() [5/7]

```
vtkGDCMImageWriter::vtkSetMacro (
    PlanarConfiguration ,
    int )
```

10.383.4.29 vtkSetMacro() [6/7]

```
vtkGDCMImageWriter::vtkSetMacro (
    Scale ,
    double )
```

10.383.4.30 vtkSetMacro() [7/7]

```
vtkGDCMImageWriter::vtkSetMacro (
    Shift ,
    double )
```

10.383.4.31 vtkSetStringMacro() [1/2]

```
vtkGDCMImageWriter::vtkSetStringMacro (
    SeriesUID )
```

10.383.4.32 vtkSetStringMacro() [2/2]

```
vtkGDCMImageWriter::vtkSetStringMacro (
    StudyUID )
```

10.383.4.33 vtkTypeMacro()

```
vtkGDCMImageWriter::vtkTypeMacro (
    vtkGDCMImageWriter ,
    vtkImageWriter )
```

References [vtkGDCMImageWriter\(\)](#).

10.383.4.34 Write()

```
virtual void vtkGDCMImageWriter::Write () [virtual]
```

Examples

[Convert16BitsTo8Bits.cxx](#), [ConvertMultiFrameToSingleFrame.cxx](#), [ConvertRGBToLuminance.cxx](#), [ConvertSingleBitTo8Bits.cxx](#), [CreateFakePET.cxx](#), [CreateFakeRTDOSE.cxx](#), [HelloActiviz.cs](#), [HelloActiviz2.cs](#), [HelloVTKWorld.cs](#), [HelloVTKWorld.java](#), [HelloVTKWorld2.cs](#), [MagnifyFile.cxx](#), and [gdcmmorthoplanes.cxx](#).

10.383.4.35 WriteGDCMData()

```
int vtkGDCMImageWriter::WriteGDCMData (  
    vtkImageData * data,  
    int timeStep) [protected]
```

10.383.4.36 WriteSlice()

```
void vtkGDCMImageWriter::WriteSlice (  
    vtkImageData * data) [protected]
```


The documentation for this class was generated from the following file:

- [vtkGDCMImageWriter.h](#)


10.384 vtkGDCMMedicalImageProperties Class Reference

```
#include <vtkGDCMMedicalImageProperties.h>
```

Inheritance diagram for vtkGDCMMedicalImageProperties:



Collaboration diagram for vtkGDCMMedicalImageProperties:



Public Member Functions

- virtual void [Clear](#) ()
- void [PrintSelf](#) (ostream &os, vtkIndent indent)
- [vtkTypeMacro](#) ([vtkGDCMMedicalImageProperties](#), vtkMedicalImageProperties)

Static Public Member Functions

- static [vtkGDCMMedicalImageProperties](#) * [New](#) ()

Protected Member Functions

- [vtkGDCMMedicalImageProperties](#) ()
- [~vtkGDCMMedicalImageProperties](#) ()
- [gdcmm::File](#) const & [GetFile](#) (unsigned int t)
- void [PushBackFile](#) ([gdcmm::File](#) const &f)

Friends

- class [vtkGDCMImageReader](#)
- class [vtkGDCMImageReader2](#)
- class [vtkGDCMImageWriter](#)

10.384.1 Constructor & Destructor Documentation

10.384.1.1 vtkGDCMMedicalImageProperties()

```
vtkGDCMMedicalImageProperties::vtkGDCMMedicalImageProperties () [protected]
```

Referenced by [GetFile\(\)](#), [New\(\)](#), and [vtkTypeMacro\(\)](#).

10.384.1.2 ~vtkGDCMMedicalImageProperties()

```
vtkGDCMMedicalImageProperties::~~vtkGDCMMedicalImageProperties () [protected]
```

10.384.2 Member Function Documentation

10.384.2.1 Clear()

```
virtual void vtkGDCMMedicalImageProperties::Clear () [virtual]
```

10.384.2.2 GetFile()

```
gdcmm::File const & vtkGDCMMedicalImageProperties::GetFile (
    unsigned int t) [protected]
```

References [vtkGDCMMedicalImageProperties\(\)](#).

10.384.2.3 New()

```
vtkGDCMMedicalImageProperties * vtkGDCMMedicalImageProperties::New () [static]
```

References [vtkGDCMMedicalImageProperties\(\)](#).

10.384.2.4 PrintSelf()

```
void vtkGDCMMedicalImageProperties::PrintSelf (
    ostream & os,
    vtkIndent indent)
```

10.384.2.5 PushBackFile()

```
void vtkGDCMMedicalImageProperties::PushBackFile (
    gdcmm::File const & f) [protected]
```

10.384.2.6 vtkTypeMacro()

```
vtkGDCMMedicalImageProperties::vtkTypeMacro (
    vtkGDCMMedicalImageProperties ,
    vtkMedicalImageProperties )
```

References [vtkGDCMMedicalImageProperties\(\)](#).

10.384.3 Friends And Related Symbol Documentation

10.384.3.1 vtkGDCMImageReader

friend class [vtkGDCMImageReader](#) [friend]

References [vtkGDCMImageReader](#).

Referenced by [vtkGDCMImageReader](#).

10.384.3.2 vtkGDCMImageReader2

friend class [vtkGDCMImageReader2](#) [friend]

References [vtkGDCMImageReader2](#).

Referenced by [vtkGDCMImageReader2](#).

10.384.3.3 vtkGDCMImageWriter

friend class [vtkGDCMImageWriter](#) [friend]

References [vtkGDCMImageWriter](#).

Referenced by [vtkGDCMImageWriter](#).


The documentation for this class was generated from the following file:

- [vtkGDCMMedicalImageProperties.h](#)


10.385 vtkGDCMPolyDataReader Class Reference

```
#include <vtkGDCMPolyDataReader.h>
```

Inheritance diagram for vtkGDCMPolyDataReader:



Collaboration diagram for vtkGDCMPolyDataReader:



Public Member Functions

- virtual void [PrintSelf](#) (ostream &os, vtkIndent indent)
- [vtkGetObjectMacro](#) (MedicalImageProperties, vtkMedicalImageProperties)
- [vtkGetObjectMacro](#) (RTStructSetProperties, vtkRTStructSetProperties)
- [vtkGetStringMacro](#) (FileName)
- [vtkSetStringMacro](#) (FileName)
- [vtkTypeMacro](#) (vtkGDCMPolyDataReader, vtkPolyDataAlgorithm)

Static Public Member Functions

- static [vtkGDCMPolyDataReader * New](#) ()

Protected Member Functions

- [vtkGDCMPolyDataReader](#) ()
- [~vtkGDCMPolyDataReader](#) ()
- void [FillMedicalImageInformation](#) (const [gdcmm::Reader](#) &reader)
- int [RequestData](#) (vtkInformation *, vtkInformationVector **, vtkInformationVector *)
- int [RequestData_HemodynamicWaveformStorage](#) ([gdcmm::Reader](#) const &reader, vtkInformationVector *outputVector)
- int [RequestData_RTStructureSetStorage](#) ([gdcmm::Reader](#) const &reader, vtkInformationVector *outputVector)
- int [RequestInformation](#) (vtkInformation *vtkNotUsed(request), vtkInformationVector **vtkNotUsed(inputVector), vtkInformationVector *outputVector)
- int [RequestInformation_HemodynamicWaveformStorage](#) ([gdcmm::Reader](#) const &reader)
- int [RequestInformation_RTStructureSetStorage](#) ([gdcmm::Reader](#) const &reader)

Protected Attributes

- char * [FileName](#)
- vtkMedicalImageProperties * [MedicalImageProperties](#)
- vtkRTStructSetProperties * [RTStructSetProperties](#)

10.385.1 Detailed Description

Examples

[GenerateRTSTRUCT.cxx](#), [gdcmscene.cxx](#), and [rtstructapp.cxx](#).

10.385.2 Constructor & Destructor Documentation

10.385.2.1 vtkGDCMPolyDataReader()

```
vtkGDCMPolyDataReader::vtkGDCMPolyDataReader () [protected]
```

Referenced by [New\(\)](#), [RequestData_HemodynamicWaveformStorage\(\)](#), and [vtkTypeMacro\(\)](#).

10.385.2.2 ~vtkGDCMPolyDataReader()

```
vtkGDCMPolyDataReader::~vtkGDCMPolyDataReader () [protected]
```

10.385.3 Member Function Documentation

10.385.3.1 FillMedicalImageInformation()

```
void vtkGDCMPolyDataReader::FillMedicalImageInformation (
    const gdcm::Reader & reader) [protected]
```

10.385.3.2 New()

```
vtkGDCMPolyDataReader * vtkGDCMPolyDataReader::New () [static]
```

Examples

[GenerateRTSTRUCT.cxx](#), [gdcmscene.cxx](#), and [rtstructapp.cxx](#).

References [vtkGDCMPolyDataReader\(\)](#).

10.385.3.3 PrintSelf()

```
virtual void vtkGDCMPolyDataReader::PrintSelf (
    ostream & os,
    vtkIndent indent) [virtual]
```

10.385.3.4 RequestData()

```
int vtkGDCMPolyDataReader::RequestData (
    vtkInformation * ,
    vtkInformationVector ** ,
    vtkInformationVector * ) [protected]
```

10.385.3.5 RequestData_HemodynamicWaveformStorage()

```
int vtkGDCMPolyDataReader::RequestData_HemodynamicWaveformStorage (
    gdcM::Reader const & reader,
    vtkInformationVector * outputVector) [protected]
```

References [vtkGDCMPolyDataReader\(\)](#).

10.385.3.6 RequestData_RTStructureSetStorage()

```
int vtkGDCMPolyDataReader::RequestData_RTStructureSetStorage (
    gdcM::Reader const & reader,
    vtkInformationVector * outputVector) [protected]
```

10.385.3.7 RequestInformation()

```
int vtkGDCMPolyDataReader::RequestInformation (
    vtkInformation * vtkNotUsedrequest,
    vtkInformationVector ** vtkNotUsedinputVector,
    vtkInformationVector * outputVector) [protected]
```

10.385.3.8 RequestInformation_HemodynamicWaveformStorage()

```
int vtkGDCMPolyDataReader::RequestInformation_HemodynamicWaveformStorage (
    gdcM::Reader const & reader) [protected]
```

10.385.3.9 RequestInformation_RTStructureSetStorage()

```
int vtkGDCMPolyDataReader::RequestInformation_RTStructureSetStorage (
    gdcM::Reader const & reader) [protected]
```

10.385.3.10 vtkGetObjectMacro() [1/2]

```
vtkGDCMPolyDataReader::vtkGetObjectMacro (
    MedicalImageProperties ,
    vtkMedicalImageProperties )
```

References [MedicalImageProperties](#).

10.385.3.11 vtkGetObjectMacro() [2/2]

```
vtkGDCMPolyDataReader::vtkGetObjectMacro (
    RTStructSetProperties ,
    vtkRTStructSetProperties )
```

References [RTStructSetProperties](#).

10.385.3.12 vtkGetStringMacro()

```
vtkGDCMPolyDataReader::vtkGetStringMacro (
    FileName )
```

References [FileName](#).

10.385.3.13 vtkSetStringMacro()

```
vtkGDCMPolyDataReader::vtkSetStringMacro (
    FileName )
```

References [FileName](#).

10.385.3.14 vtkTypeMacro()

```
vtkGDCMPolyDataReader::vtkTypeMacro (
    vtkGDCMPolyDataReader ,
    vtkPolyDataAlgorithm )
```

References [vtkGDCMPolyDataReader\(\)](#).

10.385.4 Member Data Documentation**10.385.4.1 FileName**

```
char* vtkGDCMPolyDataReader::FileName [protected]
```

Referenced by [vtkGetStringMacro\(\)](#), and [vtkSetStringMacro\(\)](#).

10.385.4.2 MedicalImageProperties

```
vtkMedicalImageProperties* vtkGDCMPolyDataReader::MedicalImageProperties [protected]
```

Referenced by [vtkGetObjectMacro\(\)](#).

10.385.4.3 RTStructSetProperties

```
vtkRTStructSetProperties* vtkGDCMPolyDataReader::RTStructSetProperties [protected]
```

Referenced by [vtkGetObjectMacro\(\)](#).


The documentation for this class was generated from the following file:

- [vtkGDCMPolyDataReader.h](#)


10.386 vtkGDCMPolyDataWriter Class Reference

```
#include <vtkGDCMPolyDataWriter.h>
```

Inheritance diagram for vtkGDCMPolyDataWriter:



Collaboration diagram for vtkGDCMPolyDataWriter:



Public Member Functions

- void [InitializeRTStructSet](#) (vtkStdString inDirectory, vtkStdString inStructLabel, vtkStdString inStructName, vtkStringArray *inROINames, vtkStringArray *inROIAlgorithmName, vtkStringArray *inROIType)
- virtual void [PrintSelf](#) (ostream &os, vtkIndent indent)
- virtual void [SetMedicalImageProperties](#) (vtkMedicalImageProperties *pd)
- void [SetNumberOfInputPorts](#) (int n)
- virtual void [SetRTStructSetProperties](#) (vtkRTStructSetProperties *pd)
- [vtkTypeMacro](#) (vtkGDCMPolyDataWriter, vtkPolyDataWriter)

Static Public Member Functions

- static [vtkGDCMPolyDataWriter * New](#) ()

Protected Member Functions

- [vtkGDCMPolyDataWriter](#) ()
- [~vtkGDCMPolyDataWriter](#) ()
- void [WriteData](#) ()
- void [WriteRTSTRUCTData](#) (gdcmm::File &file, int num)
- void [WriteRTSTRUCTInfo](#) (gdcmm::File &file)

Protected Attributes

- vtkMedicalImageProperties * [MedicalImageProperties](#)
- [vtkRTStructSetProperties](#) * [RTStructSetProperties](#)

10.386.1 Detailed Description

Examples

[GenerateRTSTRUCT.cxx](#), and [rtstructapp.cxx](#).

10.386.2 Constructor & Destructor Documentation

10.386.2.1 vtkGDCMPolyDataWriter()

```
vtkGDCMPolyDataWriter::vtkGDCMPolyDataWriter () [protected]
```

Referenced by [New\(\)](#), [vtkTypeMacro\(\)](#), and [WriteRTSTRUCTData\(\)](#).

10.386.2.2 ~vtkGDCMPolyDataWriter()

```
vtkGDCMPolyDataWriter::~~vtkGDCMPolyDataWriter () [protected]
```

10.386.3 Member Function Documentation

10.386.3.1 InitializeRTStructSet()

```
void vtkGDCMPolyDataWriter::InitializeRTStructSet (  
    vtkStdString inDirectory,  
    vtkStdString inStructLabel,  
    vtkStdString inStructName,  
    vtkStringArray * inROINames,  
    vtkStringArray * inROIAlgorithmName,  
    vtkStringArray * inROIType)
```

Examples

[GenerateRTSTRUCT.cxx](#).

10.386.3.2 New()

```
vtkGDCMPolyDataWriter * vtkGDCMPolyDataWriter::New () [static]
```

Examples

[GenerateRTSTRUCT.cxx](#), and [rtstructapp.cxx](#).

References [vtkGDCMPolyDataWriter\(\)](#).

10.386.3.3 PrintSelf()

```
virtual void vtkGDCMPolyDataWriter::PrintSelf (
    ostream & os,
    vtkIndent indent) [virtual]
```

10.386.3.4 SetMedicalImageProperties()

```
virtual void vtkGDCMPolyDataWriter::SetMedicalImageProperties (
    vtkMedicalImageProperties * pd) [virtual]
```

Examples

[GenerateRTSTRUCT.cxx](#), and [rtstructapp.cxx](#).

10.386.3.5 SetNumberOfInputPorts()

```
void vtkGDCMPolyDataWriter::SetNumberOfInputPorts (
    int n)
```

Examples

[GenerateRTSTRUCT.cxx](#), and [rtstructapp.cxx](#).

10.386.3.6 SetRTStructSetProperties()

```
virtual void vtkGDCMPolyDataWriter::SetRTStructSetProperties (
    vtkRTStructSetProperties * pd) [virtual]
```

Examples

[GenerateRTSTRUCT.cxx](#), and [rtstructapp.cxx](#).

10.386.3.7 vtkTypeMacro()

```
vtkGDCMPolyDataWriter::vtkTypeMacro (
    vtkGDCMPolyDataWriter ,
    vtkPolyDataWriter )
```

References [vtkGDCMPolyDataWriter\(\)](#).

10.386.3.8 WriteData()

```
void vtkGDCMPolyDataWriter::WriteData () [protected]
```

10.386.3.9 WriteRTSTRUCTData()

```
void vtkGDCMPolyDataWriter::WriteRTSTRUCTData (  
    gdcM::File & file,  
    int num) [protected]
```

References [vtkGDCMPolyDataWriter\(\)](#).

10.386.3.10 WriteRTSTRUCTInfo()

```
void vtkGDCMPolyDataWriter::WriteRTSTRUCTInfo (  
    gdcM::File & file) [protected]
```

10.386.4 Member Data Documentation

10.386.4.1 MedicalImageProperties

```
vtkMedicalImageProperties* vtkGDCMPolyDataWriter::MedicalImageProperties [protected]
```

10.386.4.2 RTStructSetProperties

```
vtkRTStructSetProperties* vtkGDCMPolyDataWriter::RTStructSetProperties [protected]
```


The documentation for this class was generated from the following file:

- [vtkGDCMPolyDataWriter.h](#)


10.387 vtkGDCMTesting Class Reference

```
#include <vtkGDCMTesting.h>
```

Inheritance diagram for vtkGDCMTesting:



Collaboration diagram for vtkGDCMTesting:



Public Types

- typedef const char *const (* [MD5MetalImagesType](#))[3]

Public Member Functions

- void [PrintSelf](#) (ostream &os, vtkIndent indent)
- [vtkTypeMacro](#) ([vtkGDCMTesting](#), vtkObject)

Static Public Member Functions

- static const char * [GetGDCMDataRoot](#) ()
- static const char *const * [GetMD5MetaImage](#) (unsigned int file)
- static const char * [GetMHDMD5FromFile](#) (const char *filepath)
- static unsigned int [GetNumberOfMD5MetaImages](#) ()
- static const char * [GetRAWMD5FromFile](#) (const char *filepath)
- static const char * [GetVTKDataRoot](#) ()
- static [vtkGDCMTesting](#) * [New](#) ()

Protected Member Functions

- [vtkGDCMTesting](#) ()
- [~vtkGDCMTesting](#) ()

10.387.1 Detailed Description

Examples

[HelloActiviz5.cs](#), [HelloVTKWorld2.cs](#), [MetaImageMD5Activiz.cs](#), [ReadSeriesIntoVTK.java](#), and [RefCounting.cs](#).

10.387.2 Member Typedef Documentation

10.387.2.1 MD5MetaImagesType

```
typedef const char* const(* vtkGDCMTesting::MD5MetaImagesType) [3]
```

10.387.3 Constructor & Destructor Documentation

10.387.3.1 vtkGDCMTesting()

```
vtkGDCMTesting::vtkGDCMTesting () [protected]
```

Referenced by [~vtkGDCMTesting\(\)](#), [New\(\)](#), and [vtkTypeMacro\(\)](#).

10.387.3.2 ~vtkGDCMTesting()

```
vtkGDCMTesting::~~vtkGDCMTesting () [protected]
```

References [vtkGDCMTesting\(\)](#).

10.387.4 Member Function Documentation

10.387.4.1 GetGDCMDataRoot()

```
const char * vtkGDCMTesting::GetGDCMDataRoot () [static]
```

Examples

[HelloActiviz5.cs](#), and [ReadSeriesIntoVTK.java](#).

10.387.4.2 GetMD5MetaImage()

```
const char *const * vtkGDCMTesting::GetMD5MetaImage (
    unsigned int file) [static]
```

10.387.4.3 GetMHDMD5FromFile()

```
const char * vtkGDCMTesting::GetMHDMD5FromFile (
    const char * filepath) [static]
```

Examples

[MetaImageMD5Activiz.cs](#).

10.387.4.4 GetNumberOfMD5MetaImages()

```
unsigned int vtkGDCMTesting::GetNumberOfMD5MetaImages () [static]
```

10.387.4.5 GetRAWMD5FromFile()

```
const char * vtkGDCMTesting::GetRAWMD5FromFile (
    const char * filepath) [static]
```

Examples

[MetaImageMD5Activiz.cs](#).

10.387.4.6 GetVTKDataRoot()

```
const char * vtkGDCMTesting::GetVTKDataRoot () [static]
```

Examples

[HelloActiviz5.cs](#), and [HelloVTKWorld2.cs](#).

10.387.4.7 New()

```
vtkGDCMTesting * vtkGDCMTesting::New () [static]
```

Examples

[RefCounting.cs](#).

References [vtkGDCMTesting\(\)](#).

10.387.4.8 PrintSelf()

```
void vtkGDCMTesting::PrintSelf (
    ostream & os,
    vtkIndent indent)
```

10.387.4.9 vtkTypeMacro()

```
vtkGDCMTesting::vtkTypeMacro (
    vtkGDCMTesting ,
    vtkObject )
```

References [vtkGDCMTesting\(\)](#).


The documentation for this class was generated from the following file:

- [vtkGDCMTesting.h](#)


10.388 vtkGDCMThreadedImageReader Class Reference

```
#include <vtkGDCMThreadedImageReader.h>
```

Inheritance diagram for vtkGDCMThreadedImageReader:



Collaboration diagram for vtkGDCMThreadedImageReader:



Public Member Functions

- virtual void [PrintSelf](#) (ostream &os, vtkIndent indent)
- [vtkBooleanMacro](#) (UseShiftScale, int)
- [vtkGetMacro](#) (UseShiftScale, int)
- [vtkSetMacro](#) (Scale, double)
- [vtkSetMacro](#) (Shift, double)
- [vtkSetMacro](#) (UseShiftScale, int)
- [vtkTypeMacro](#) (vtkGDCMThreadedImageReader, vtkGDCMImageReader)

Public Member Functions inherited from [vtkGDCMImageReader](#)

- virtual int [CanReadFile](#) (const char *fname)
- virtual const char * [GetDescriptiveName](#) ()
- virtual const char * [GetFileExtensions](#) ()
- vtkImageData * [GetIconImage](#) ()
- vtkImageData * [GetOverlay](#) (int i)
- virtual void [SetCurve](#) (vtkPolyData *pd)
- virtual void [SetFileNames](#) (vtkStringArray *)
- virtual void [SetMedicalImageProperties](#) (vtkMedicalImageProperties *pd)
- [vtkBooleanMacro](#) (ApplyLookupTable, int)
- int [vtkBooleanMacro](#) (ApplyYBRToRGB, int)
- [vtkBooleanMacro](#) (LoadIconImage, int)
- [vtkBooleanMacro](#) (LoadOverlays, int)
- [vtkBooleanMacro](#) (LossyFlag, int)
- [vtkGetMacro](#) (ApplyLookupTable, int)
- [vtkGetMacro](#) (ApplyYBRToRGB, int) [vtkSetMacro](#) (ApplyYBRToRGB
- [vtkGetMacro](#) (ImageFormat, int)
- [vtkGetMacro](#) (LoadIconImage, int)

- [vtkGetMacro](#) ([LoadOverlays](#), int)
- [vtkGetMacro](#) ([LossyFlag](#), int)
- [vtkGetMacro](#) ([NumberOfIconImages](#), int)
- [vtkGetMacro](#) ([NumberOfOverlays](#), int)
- [vtkGetMacro](#) ([PlanarConfiguration](#), int)
- [vtkGetMacro](#) ([Scale](#), double)
- [vtkGetMacro](#) ([Shift](#), double)
- [vtkGetObjectMacro](#) ([Curve](#), vtkPolyData)
- [vtkGetObjectMacro](#) ([DirectionCosines](#), vtkMatrix4x4)
- [vtkGetObjectMacro](#) ([FileNames](#), vtkStringArray)
- [vtkGetObjectMacro](#) ([MedicalImageProperties](#), vtkMedicalImageProperties)
- [vtkGetVector3Macro](#) ([ImagePositionPatient](#), double)
- [vtkGetVector6Macro](#) ([ImageOrientationPatient](#), double)
- [vtkSetMacro](#) ([ApplyLookupTable](#), int)
- [vtkSetMacro](#) ([LoadIconImage](#), int)
- [vtkSetMacro](#) ([LoadOverlays](#), int)
- [vtkSetMacro](#) ([LossyFlag](#), int)
- [vtkTypeMacro](#) ([vtkGDCMImageReader](#), vtkMedicalImageReader2)

Static Public Member Functions

- static [vtkGDCMThreadedImageReader](#) * [New](#) ()

Static Public Member Functions inherited from [vtkGDCMImageReader](#)

- static [vtkGDCMImageReader](#) * [New](#) ()

Protected Member Functions

- [vtkGDCMThreadedImageReader](#) ()
- [~vtkGDCMThreadedImageReader](#) ()
- void [ExecuteData](#) (vtkDataObject *out)
- void [ExecuteInformation](#) ()
- void [ReadFiles](#) (unsigned int nfiles, const char *filenames[])
- void [RequestDataCompat](#) ()

Protected Member Functions inherited from [vtkGDCMImageReader](#)

- [vtkGDCMImageReader](#) ()
- [~vtkGDCMImageReader](#) ()
- void [ExecuteData](#) (vtkDataObject *out)
- void [ExecuteInformation](#) ()
- void [FillMedicalImageInformation](#) (const [gdcm::ImageReader](#) &reader)
- int [LoadSingleFile](#) (const char *filename, char *pointer, unsigned long &outlen)
- int [RequestDataCompat](#) ()
- int [RequestInformationCompat](#) ()
- void [SetFilePattern](#) (const char *)
- void [SetFilePrefix](#) (const char *)
- [vtkGetStringMacro](#) (FilePattern)
- [vtkGetStringMacro](#) (FilePrefix)
- [vtkSetVector6Macro](#) ([ImageOrientationPatient](#), double)

Additional Inherited Members

Protected Attributes inherited from [vtkGDCMImageReader](#)

- int [ApplyInverseVideo](#)
- int [ApplyLookupTable](#)
- int [ApplyPlanarConfiguration](#)
- int [ApplyShiftScale](#)
- int [ApplyYBRTToRGB](#)
- vtkPolyData * [Curve](#)
- vtkMatrix4x4 * [DirectionCosines](#)
- vtkStringArray * [FileNames](#)
- int [ForceRescale](#)
- int [IconDataScalarType](#)
- int [IconImageDataExtent](#) [6]
- int [IconNumberOfScalarComponents](#)
- int [ImageFormat](#)
- double [ImageOrientationPatient](#) [6]
- double [ImagePositionPatient](#) [3]
- int [LoadIconImage](#)
- int [LoadOverlays](#)
- int [LossyFlag](#)
- vtkMedicalImageProperties * [MedicalImageProperties](#)
- int [NumberOfIconImages](#)
- int [NumberOfOverlays](#)
- int [PlanarConfiguration](#)
- double [Scale](#)
- double [Shift](#)

10.388.1 Constructor & Destructor Documentation

10.388.1.1 [vtkGDCMThreadedImageReader\(\)](#)

`vtkGDCMThreadedImageReader::vtkGDCMThreadedImageReader ()` [protected]

Referenced by [New\(\)](#), [RequestDataCompat\(\)](#), and [vtkTypeMacro\(\)](#).

10.388.1.2 [~vtkGDCMThreadedImageReader\(\)](#)

`vtkGDCMThreadedImageReader::~~vtkGDCMThreadedImageReader ()` [protected]

10.388.2 Member Function Documentation

10.388.2.1 [ExecuteData\(\)](#)

`void vtkGDCMThreadedImageReader::ExecuteData (`
`vtkDataObject * out) [protected]`

10.388.2.2 ExecuteInformation()

```
void vtkGDCMThreadedImageReader::ExecuteInformation () [protected]
```

10.388.2.3 New()

```
vtkGDCMThreadedImageReader * vtkGDCMThreadedImageReader::New () [static]
```

References [vtkGDCMThreadedImageReader\(\)](#).

10.388.2.4 PrintSelf()

```
virtual void vtkGDCMThreadedImageReader::PrintSelf (
    ostream & os,
    vtkIndent indent) [virtual]
```

Reimplemented from [vtkGDCMImageReader](#).

10.388.2.5 ReadFiles()

```
void vtkGDCMThreadedImageReader::ReadFiles (
    unsigned int nfiles,
    const char * filenames[]) [protected]
```

10.388.2.6 RequestDataCompat()

```
void vtkGDCMThreadedImageReader::RequestDataCompat () [protected]
```

References [vtkGDCMThreadedImageReader\(\)](#).

10.388.2.7 vtkBooleanMacro()

```
vtkGDCMThreadedImageReader::vtkBooleanMacro (
    UseShiftScale ,
    int )
```

10.388.2.8 vtkGetMacro()

```
vtkGDCMThreadedImageReader::vtkGetMacro (
    UseShiftScale ,
    int )
```

10.388.2.9 vtkSetMacro() [1/3]

```
vtkGDCMThreadedImageReader::vtkSetMacro (
    Scale ,
    double )
```

References [vtkGDCMImageReader::Scale](#).

10.388.2.10 vtkSetMacro() [2/3]

```
vtkGDCMThreadedImageReader::vtkSetMacro (
    Shift ,
    double )
```

References [vtkGDCMImageReader::Shift](#).

10.388.2.11 vtkSetMacro() [3/3]

```
vtkGDCMThreadedImageReader::vtkSetMacro (
    UseShiftScale ,
    int )
```

10.388.2.12 vtkTypeMacro()

```
vtkGDCMThreadedImageReader::vtkTypeMacro (
    vtkGDCMThreadedImageReader ,
    vtkGDCMImageReader )
```

References [vtkGDCMImageReader::vtkGDCMImageReader\(\)](#), and [vtkGDCMThreadedImageReader\(\)](#).


The documentation for this class was generated from the following file:

- [vtkGDCMThreadedImageReader.h](#)


10.389 vtkGDCMThreadedImageReader2 Class Reference

```
#include <vtkGDCMThreadedImageReader2.h>
```

Inheritance diagram for vtkGDCMThreadedImageReader2:



Collaboration diagram for vtkGDCMThreadedImageReader2:



Public Member Functions

- virtual const char * [GetFileName](#) (int i=0)
- virtual void [PrintSelf](#) (ostream &os, vtkIndent indent)
- virtual void [SetFileName](#) (const char *filename)
- virtual void [SetFileNames](#) (vtkStringArray *)
- int [SplitExtent](#) (int splitExt[6], int startExt[6], int num, int total)
- [vtkBooleanMacro](#) (FileLowerLeft, int)
- [vtkBooleanMacro](#) (LoadOverlays, int)
- [vtkBooleanMacro](#) (UseShiftScale, int)
- [vtkGetMacro](#) (DataScalarType, int)
- [vtkGetMacro](#) (FileLowerLeft, int)
- [vtkGetMacro](#) (LoadOverlays, int)

- [vtkGetMacro](#) (NumberOfOverlays, int)
- [vtkGetMacro](#) (NumberOfScalarComponents, int)
- [vtkGetMacro](#) (Scale, double)
- [vtkGetMacro](#) (Shift, double)
- [vtkGetMacro](#) (UseShiftScale, int)
- [vtkGetObjectMacro](#) (FileNames, vtkStringArray)
- [vtkGetVector3Macro](#) (DataOrigin, double)
- [vtkGetVector3Macro](#) (DataSpacing, double)
- [vtkGetVector6Macro](#) (DataExtent, int)
- [vtkSetMacro](#) (DataScalarType, int)
- [vtkSetMacro](#) (FileLowerLeft, int)
- [vtkSetMacro](#) (LoadOverlays, int)
- [vtkSetMacro](#) (NumberOfScalarComponents, int)
- [vtkSetMacro](#) (Scale, double)
- [vtkSetMacro](#) (Shift, double)
- [vtkSetMacro](#) (UseShiftScale, int)
- [vtkSetVector3Macro](#) (DataOrigin, double)
- [vtkSetVector3Macro](#) (DataSpacing, double)
- [vtkSetVector6Macro](#) (DataExtent, int)
- [vtkTypeMacro](#) ([vtkGDCMThreadedImageReader2](#), [vtkThreadedImageAlgorithm](#))

Static Public Member Functions

- static [vtkGDCMThreadedImageReader2](#) * [New](#) ()

Protected Member Functions

- [vtkGDCMThreadedImageReader2](#) ()
- [~vtkGDCMThreadedImageReader2](#) ()
- int [RequestInformation](#) (vtkInformation *request, vtkInformationVector **inputVector, vtkInformationVector *outputVector)
- void [ThreadedRequestData](#) (vtkInformation *request, vtkInformationVector **inputVector, vtkInformationVector *outputVector, vtkImageData ***inData, vtkImageData **outData, int outExt[6], int id)

10.389.1 Constructor & Destructor Documentation

10.389.1.1 [vtkGDCMThreadedImageReader2\(\)](#)

`vtkGDCMThreadedImageReader2::vtkGDCMThreadedImageReader2 ()` [protected]

Referenced by [New\(\)](#), [ThreadedRequestData\(\)](#), and [vtkTypeMacro\(\)](#).

10.389.1.2 [~vtkGDCMThreadedImageReader2\(\)](#)

`vtkGDCMThreadedImageReader2::~~vtkGDCMThreadedImageReader2 ()` [protected]

10.389.2 Member Function Documentation

10.389.2.1 GetFileName()

```
virtual const char * vtkGDCMThreadedImageReader2::GetFileName (
    int i = 0) [virtual]
```

10.389.2.2 New()

```
vtkGDCMThreadedImageReader2 * vtkGDCMThreadedImageReader2::New () [static]
```

References [vtkGDCMThreadedImageReader2\(\)](#).

10.389.2.3 PrintSelf()

```
virtual void vtkGDCMThreadedImageReader2::PrintSelf (
    ostream & os,
    vtkIndent indent) [virtual]
```

10.389.2.4 RequestInformation()

```
int vtkGDCMThreadedImageReader2::RequestInformation (
    vtkInformation * request,
    vtkInformationVector ** inputVector,
    vtkInformationVector * outputVector) [protected]
```

10.389.2.5 SetFileName()

```
virtual void vtkGDCMThreadedImageReader2::SetFileName (
    const char * filename) [virtual]
```

10.389.2.6 SetFileNames()

```
virtual void vtkGDCMThreadedImageReader2::SetFileNames (
    vtkStringArray * ) [virtual]
```

10.389.2.7 SplitExtent()

```
int vtkGDCMThreadedImageReader2::SplitExtent (
    int splitExt[6],
    int startExt[6],
    int num,
    int total)
```

10.389.2.8 ThreadedRequestData()

```
void vtkGDCMThreadedImageReader2::ThreadedRequestData (
    vtkInformation * request,
    vtkInformationVector ** inputVector,
    vtkInformationVector * outputVector,
    vtkImageData *** inData,
    vtkImageData ** outData,
    int outExt[6],
    int id) [protected]
```

References [vtkGDCMThreadedImageReader2\(\)](#).

10.389.2.9 vtkBooleanMacro() [1/3]

```
vtkGDCMThreadedImageReader2::vtkBooleanMacro (
    FileLowerLeft ,
    int )
```

10.389.2.10 vtkBooleanMacro() [2/3]

```
vtkGDCMThreadedImageReader2::vtkBooleanMacro (
    LoadOverlays ,
    int )
```

10.389.2.11 vtkBooleanMacro() [3/3]

```
vtkGDCMThreadedImageReader2::vtkBooleanMacro (
    UseShiftScale ,
    int )
```

10.389.2.12 vtkGetMacro() [1/8]

```
vtkGDCMThreadedImageReader2::vtkGetMacro (
    DataScalarType ,
    int )
```

10.389.2.13 vtkGetMacro() [2/8]

```
vtkGDCMThreadedImageReader2::vtkGetMacro (
    FileLowerLeft ,
    int )
```

10.389.2.14 vtkGetMacro() [3/8]

```
vtkGDCMThreadedImageReader2::vtkGetMacro (
    LoadOverlays ,
    int )
```

10.389.2.15 vtkGetMacro() [4/8]

```
vtkGDCMThreadedImageReader2::vtkGetMacro (
    NumberOfOverlays ,
    int )
```

10.389.2.16 vtkGetMacro() [5/8]

```
vtkGDCMThreadedImageReader2::vtkGetMacro (
    NumberOfScalarComponents ,
    int )
```

10.389.2.17 vtkGetMacro() [6/8]

```
vtkGDCMThreadedImageReader2::vtkGetMacro (
    Scale ,
    double )
```

10.389.2.18 vtkGetMacro() [7/8]

```
vtkGDCMThreadedImageReader2::vtkGetMacro (
    Shift ,
    double )
```

10.389.2.19 vtkGetMacro() [8/8]

```
vtkGDCMThreadedImageReader2::vtkGetMacro (
    UseShiftScale ,
    int )
```

10.389.2.20 vtkGetObjectMacro()

```
vtkGDCMThreadedImageReader2::vtkGetObjectMacro (
    FileNames ,
    vtkStringArray )
```

10.389.2.21 vtkGetVector3Macro() [1/2]

```
vtkGDCMThreadedImageReader2::vtkGetVector3Macro (
    DataOrigin ,
    double )
```

10.389.2.22 vtkGetVector3Macro() [2/2]

```
vtkGDCMThreadedImageReader2::vtkGetVector3Macro (
    DataSpacing ,
    double )
```

10.389.2.23 vtkGetVector6Macro()

```
vtkGDCMThreadedImageReader2::vtkGetVector6Macro (
    DataExtent ,
    int )
```

10.389.2.24 vtkSetMacro() [1/7]

```
vtkGDCMThreadedImageReader2::vtkSetMacro (
    DataScalarType ,
    int )
```

10.389.2.25 vtkSetMacro() [2/7]

```
vtkGDCMThreadedImageReader2::vtkSetMacro (
    FileLowerLeft ,
    int )
```

10.389.2.26 vtkSetMacro() [3/7]

```
vtkGDCMThreadedImageReader2::vtkSetMacro (
    LoadOverlays ,
    int )
```

10.389.2.27 vtkSetMacro() [4/7]

```
vtkGDCMThreadedImageReader2::vtkSetMacro (
    NumberOfScalarComponents ,
    int )
```


10.389.2.28 vtkSetMacro() [5/7]

```
vtkGDCMThreadedImageReader2::vtkSetMacro (
    Scale ,
    double )
```

10.389.2.29 vtkSetMacro() [6/7]

```
vtkGDCMThreadedImageReader2::vtkSetMacro (
    Shift ,
    double )
```

10.389.2.30 vtkSetMacro() [7/7]

```
vtkGDCMThreadedImageReader2::vtkSetMacro (
    UseShiftScale ,
    int )
```

10.389.2.31 vtkSetVector3Macro() [1/2]

```
vtkGDCMThreadedImageReader2::vtkSetVector3Macro (
    DataOrigin ,
    double )
```

10.389.2.32 vtkSetVector3Macro() [2/2]

```
vtkGDCMThreadedImageReader2::vtkSetVector3Macro (
    DataSpacing ,
    double )
```

10.389.2.33 vtkSetVector6Macro()

```
vtkGDCMThreadedImageReader2::vtkSetVector6Macro (
    DataExtent ,
    int )
```

10.389.2.34 vtkTypeMacro()

```
vtkGDCMThreadedImageReader2::vtkTypeMacro (
    vtkGDCMThreadedImageReader2 ,
    vtkThreadedImageAlgorithm )
```

References [vtkGDCMThreadedImageReader2\(\)](#).


The documentation for this class was generated from the following file:

- [vtkGDCMThreadedImageReader2.h](#)


10.390 vtkImageColorViewer Class Reference

```
#include <vtkImageColorViewer.h>
```

Inheritance diagram for vtkImageColorViewer:



Collaboration diagram for vtkImageColorViewer:



Public Types

- enum {
 SLICE_ORIENTATION_YZ = 0 ,
 SLICE_ORIENTATION_XZ = 1 ,
 SLICE_ORIENTATION_XY = 2 }

Public Member Functions

- virtual void [AddInput](#) (vtkImageData *input)
- virtual void [AddInputConnection](#) (vtkAlgorithmOutput *input)
- virtual double [GetColorLevel](#) ()
- virtual double [GetColorWindow](#) ()
- virtual vtkImageData * [GetInput](#) ()
- virtual int [GetOffScreenRendering](#) ()
- double [GetOverlayVisibility](#) ()
- virtual int * [GetPosition](#) ()
- virtual int * [GetSize](#) ()
- virtual int [GetSliceMax](#) ()
- virtual int [GetSliceMin](#) ()
- virtual int * [GetSliceRange](#) ()
- virtual void [GetSliceRange](#) (int &min, int &max)
- virtual void [GetSliceRange](#) (int range[2])
- virtual const char * [GetWindowName](#) ()
- void [PrintSelf](#) (ostream &os, vtkIndent indent)
- virtual void [Render](#) (void)
- virtual void [SetColorLevel](#) (double s)
- virtual void [SetColorWindow](#) (double s)
- virtual void [SetDisplayId](#) (void *a)
- virtual void [SetInput](#) (vtkImageData *in)
- virtual void [SetInputConnection](#) (vtkAlgorithmOutput *input)
- virtual void [SetOffScreenRendering](#) (int)
- void [SetOverlayVisibility](#) (double vis)
- virtual void [SetParentId](#) (void *a)
- virtual void [SetPosition](#) (int a, int b)
- virtual void [SetPosition](#) (int a[2])
- virtual void [SetRenderer](#) (vtkRenderer *arg)
- virtual void [SetRenderWindow](#) (vtkRenderWindow *arg)
- virtual void [SetSize](#) (int a, int b)
- virtual void [SetSize](#) (int a[2])
- virtual void [SetSlice](#) (int s)
- virtual void [SetSliceOrientation](#) (int orientation)
- virtual void [SetSliceOrientationToXY](#) ()
- virtual void [SetSliceOrientationToXZ](#) ()
- virtual void [SetSliceOrientationToYZ](#) ()
- virtual void [SetupInteractor](#) (vtkRenderWindowInteractor *)
- virtual void [SetWindowId](#) (void *a)
- virtual void [UpdateDisplayExtent](#) ()
- [vtkBooleanMacro](#) (OffScreenRendering, int)
- [vtkGetMacro](#) (Slice, int)
- [vtkGetMacro](#) (SliceOrientation, int)
- [vtkGetObjectMacro](#) (ImageActor, vtkImageActor)
- [vtkGetObjectMacro](#) (InteractorStyle, vtkInteractorStyleImage)
- [vtkGetObjectMacro](#) (Renderer, vtkRenderer)
- [vtkGetObjectMacro](#) (RenderWindow, vtkRenderWindow)
- [vtkGetObjectMacro](#) (WindowLevel, vtkImageMapToWindowLevelColors2)
- [vtkTypeMacro](#) (vtkImageColorViewer, vtkObject)

Static Public Member Functions

- static [vtkImageColorViewer](#) * [New](#) ()

Protected Member Functions

- [vtkImageColorViewer](#) ()
- [~vtkImageColorViewer](#) ()
- virtual void [InstallPipeline](#) ()
- virtual void [UnInstallPipeline](#) ()
- virtual void [UpdateOrientation](#) ()

Protected Attributes

- int [FirstRender](#)
- [vtkImageActor](#) * [ImageActor](#)
- [vtkRenderWindowInteractor](#) * [Interactor](#)
- [vtkInteractorStyleImage](#) * [InteractorStyle](#)
- [vtkImageActor](#) * [OverlayImageActor](#)
- [vtkRenderer](#) * [Renderer](#)
- [vtkRenderWindow](#) * [RenderWindow](#)
- int [Slice](#)
- int [SliceOrientation](#)
- [vtkImageMapToWindowLevelColors2](#) * [WindowLevel](#)

Friends

- class [vtkImageColorViewerCallback](#)

10.390.1 Detailed Description

Examples

[gdcmrtnionplan.cxx](#), and [gdcmrtpplan.cxx](#).

10.390.2 Member Enumeration Documentation

10.390.2.1 anonymous enum

anonymous enum

Enumerator

SLICE_ORIENTATION_YZ	
SLICE_ORIENTATION_XZ	
SLICE_ORIENTATION_XY	

10.390.3 Constructor & Destructor Documentation

10.390.3.1 vtkImageColorViewer()

```
vtkImageColorViewer::vtkImageColorViewer () [protected]
```

Referenced by [New\(\)](#), [vtkImageColorViewerCallback](#), and [vtkTypeMacro\(\)](#).

10.390.3.2 ~vtkImageColorViewer()

```
vtkImageColorViewer::~vtkImageColorViewer () [protected]
```

10.390.4 Member Function Documentation

10.390.4.1 AddInput()

```
virtual void vtkImageColorViewer::AddInput (  
    vtkImageData * input) [virtual]
```

10.390.4.2 AddInputConnection()

```
virtual void vtkImageColorViewer::AddInputConnection (  
    vtkAlgorithmOutput * input) [virtual]
```

10.390.4.3 GetColorLevel()

```
virtual double vtkImageColorViewer::GetColorLevel () [virtual]
```

10.390.4.4 GetColorWindow()

```
virtual double vtkImageColorViewer::GetColorWindow () [virtual]
```

10.390.4.5 GetInput()

```
virtual vtkImageData * vtkImageColorViewer::GetInput () [virtual]
```

10.390.4.6 GetOffScreenRendering()

```
virtual int vtkImageColorViewer::GetOffScreenRendering () [virtual]
```

10.390.4.7 GetOverlayVisibility()

```
double vtkImageColorViewer::GetOverlayVisibility ()
```

10.390.4.8 GetPosition()

```
virtual int * vtkImageColorViewer::GetPosition () [virtual]
```

10.390.4.9 GetSize()

```
virtual int * vtkImageColorViewer::GetSize () [virtual]
```

10.390.4.10 GetSliceMax()

```
virtual int vtkImageColorViewer::GetSliceMax () [virtual]
```

10.390.4.11 GetSliceMin()

```
virtual int vtkImageColorViewer::GetSliceMin () [virtual]
```

10.390.4.12 GetSliceRange() [1/3]

```
virtual int * vtkImageColorViewer::GetSliceRange () [virtual]
```

10.390.4.13 GetSliceRange() [2/3]

```
virtual void vtkImageColorViewer::GetSliceRange (  
    int & min,  
    int & max) [virtual]
```

10.390.4.14 GetSliceRange() [3/3]

```
virtual void vtkImageColorViewer::GetSliceRange (  
    int range[2]) [inline], [virtual]
```

References [GetSliceRange\(\)](#).

Referenced by [GetSliceRange\(\)](#).

10.390.4.15 GetWindowName()

```
virtual const char * vtkImageColorViewer::GetWindowName () [virtual]
```

10.390.4.16 InstallPipeline()

```
virtual void vtkImageColorViewer::InstallPipeline () [protected], [virtual]
```

10.390.4.17 New()

```
vtkImageColorViewer * vtkImageColorViewer::New () [static]
```

Examples

[gdcmrptionplan.cxx](#), and [gdcmrtpplan.cxx](#).

References [vtkImageColorViewer\(\)](#).

10.390.4.18 PrintSelf()

```
void vtkImageColorViewer::PrintSelf (  
    ostream & os,  
    vtkIndent indent)
```

10.390.4.19 Render()

```
virtual void vtkImageColorViewer::Render (  
    void ) [virtual]
```

Examples

[gdcmrptionplan.cxx](#), and [gdcmrtpplan.cxx](#).

10.390.4.20 SetColorLevel()

```
virtual void vtkImageColorViewer::SetColorLevel (  
    double s) [virtual]
```

10.390.4.21 SetColorWindow()

```
virtual void vtkImageColorViewer::SetColorWindow (  
    double s) [virtual]
```

10.390.4.22 SetDisplayId()

```
virtual void vtkImageColorViewer::SetDisplayId (  
    void * a) [virtual]
```

10.390.4.23 SetInput()

```
virtual void vtkImageColorViewer::SetInput (  
    vtkImageData * in) [virtual]
```

Examples

[gdcmrtonplan.cxx](#), and [gdcmrtpplan.cxx](#).

10.390.4.24 SetInputConnection()

```
virtual void vtkImageColorViewer::SetInputConnection (  
    vtkAlgorithmOutput * input) [virtual]
```

10.390.4.25 SetOffScreenRendering()

```
virtual void vtkImageColorViewer::SetOffScreenRendering (  
    int ) [virtual]
```

10.390.4.26 SetOverlayVisibility()

```
void vtkImageColorViewer::SetOverlayVisibility (  
    double vis)
```

10.390.4.27 SetParentId()

```
virtual void vtkImageColorViewer::SetParentId (  
    void * a) [virtual]
```

10.390.4.28 SetPosition() [1/2]

```
virtual void vtkImageColorViewer::SetPosition (  
    int a,  
    int b) [virtual]
```


10.390.4.29 SetPosition() [2/2]

```
virtual void vtkImageColorViewer::SetPosition (  
    int a[2]) [inline], [virtual]
```

References [SetPosition\(\)](#).

Referenced by [SetPosition\(\)](#).

10.390.4.30 SetRenderer()

```
virtual void vtkImageColorViewer::SetRenderer (  
    vtkRenderer * arg) [virtual]
```

10.390.4.31 SetRenderWindow()

```
virtual void vtkImageColorViewer::SetRenderWindow (  
    vtkRenderWindow * arg) [virtual]
```

10.390.4.32 SetSize() [1/2]

```
virtual void vtkImageColorViewer::SetSize (  
    int a,  
    int b) [virtual]
```

Examples

[gdcmrtonplan.cxx](#), and [gdcmrtpplan.cxx](#).

10.390.4.33 SetSize() [2/2]

```
virtual void vtkImageColorViewer::SetSize (  
    int a[2]) [inline], [virtual]
```

References [SetSize\(\)](#).

Referenced by [SetSize\(\)](#).

10.390.4.34 SetSlice()

```
virtual void vtkImageColorViewer::SetSlice (  
    int s) [virtual]
```

10.390.4.35 SetSliceOrientation()

```
virtual void vtkImageColorViewer::SetSliceOrientation (
    int orientation) [virtual]
```

Referenced by [SetSliceOrientationToXY\(\)](#), [SetSliceOrientationToXZ\(\)](#), and [SetSliceOrientationToYZ\(\)](#).

10.390.4.36 SetSliceOrientationToXY()

```
virtual void vtkImageColorViewer::SetSliceOrientationToXY () [inline], [virtual]
```

References [SetSliceOrientation\(\)](#), and [SLICE_ORIENTATION_XY](#).

10.390.4.37 SetSliceOrientationToXZ()

```
virtual void vtkImageColorViewer::SetSliceOrientationToXZ () [inline], [virtual]
```

References [SetSliceOrientation\(\)](#), and [SLICE_ORIENTATION_XZ](#).

10.390.4.38 SetSliceOrientationToYZ()

```
virtual void vtkImageColorViewer::SetSliceOrientationToYZ () [inline], [virtual]
```

References [SetSliceOrientation\(\)](#), and [SLICE_ORIENTATION_YZ](#).

10.390.4.39 SetupInteractor()

```
virtual void vtkImageColorViewer::SetupInteractor (
    vtkRenderWindowInteractor * ) [virtual]
```

Examples

[gdcmrptionplan.cxx](#), and [gdcmrtpian.cxx](#).

10.390.4.40 SetWindowId()

```
virtual void vtkImageColorViewer::SetWindowId (
    void * a) [virtual]
```

10.390.4.41 UnInstallPipeline()

```
virtual void vtkImageColorViewer::UnInstallPipeline () [protected], [virtual]
```

10.390.4.42 UpdateDisplayExtent()

```
virtual void vtkImageColorViewer::UpdateDisplayExtent () [virtual]
```

10.390.4.43 UpdateOrientation()

```
virtual void vtkImageColorViewer::UpdateOrientation () [protected], [virtual]
```

10.390.4.44 vtkBooleanMacro()

```
vtkImageColorViewer::vtkBooleanMacro (
    OffScreenRendering ,
    int )
```

10.390.4.45 vtkGetMacro() [1/2]

```
vtkImageColorViewer::vtkGetMacro (
    Slice ,
    int )
```

References [Slice](#).

10.390.4.46 vtkGetMacro() [2/2]

```
vtkImageColorViewer::vtkGetMacro (
    SliceOrientation ,
    int )
```

References [SliceOrientation](#).

10.390.4.47 vtkGetObjectMacro() [1/5]

```
vtkImageColorViewer::vtkGetObjectMacro (
    ImageActor ,
    vtkImageActor )
```

References [ImageActor](#).

10.390.4.48 vtkGetObjectMacro() [2/5]

```
vtkImageColorViewer::vtkGetObjectMacro (
    InteractorStyle ,
    vtkInteractorStyleImage )
```

References [InteractorStyle](#).

10.390.4.49 vtkGetObjectMacro() [3/5]

```
vtkImageColorViewer::vtkGetObjectMacro (
    Renderer ,
    vtkRenderer )
```

References [Renderer](#).

10.390.4.50 vtkGetObjectMacro() [4/5]

```
vtkImageColorViewer::vtkGetObjectMacro (
    RenderWindow ,
    vtkRenderWindow )
```

References [RenderWindow](#).

10.390.4.51 vtkGetObjectMacro() [5/5]

```
vtkImageColorViewer::vtkGetObjectMacro (
    WindowLevel ,
    vtkImageMapToWindowLevelColors2 )
```

References [WindowLevel](#).

10.390.4.52 vtkTypeMacro()

```
vtkImageColorViewer::vtkTypeMacro (
    vtkImageColorViewer ,
    vtkObject )
```

References [vtkImageColorViewer\(\)](#).

10.390.5 Friends And Related Symbol Documentation**10.390.5.1 vtkImageColorViewerCallback**

```
friend class vtkImageColorViewerCallback [friend]
```

References [vtkImageColorViewer\(\)](#), and [vtkImageColorViewerCallback](#).

Referenced by [vtkImageColorViewerCallback](#).

10.390.6 Member Data Documentation

10.390.6.1 FirstRender

`int vtkImageColorViewer::FirstRender` [protected]

10.390.6.2 ImageActor

`vtkImageActor* vtkImageColorViewer::ImageActor` [protected]

Referenced by [vtkGetObjectMacro\(\)](#).

10.390.6.3 Interactor

`vtkRenderWindowInteractor* vtkImageColorViewer::Interactor` [protected]

10.390.6.4 InteractorStyle

`vtkInteractorStyleImage* vtkImageColorViewer::InteractorStyle` [protected]

Referenced by [vtkGetObjectMacro\(\)](#).

10.390.6.5 OverlayImageActor

`vtkImageActor* vtkImageColorViewer::OverlayImageActor` [protected]

10.390.6.6 Renderer

`vtkRenderer* vtkImageColorViewer::Renderer` [protected]

Referenced by [vtkGetObjectMacro\(\)](#).

10.390.6.7 RenderWindow

`vtkRenderWindow* vtkImageColorViewer::RenderWindow` [protected]

Referenced by [vtkGetObjectMacro\(\)](#).

10.390.6.8 Slice

```
int vtkImageColorViewer::Slice [protected]
```

Referenced by [vtkGetMacro\(\)](#).

10.390.6.9 SliceOrientation

```
int vtkImageColorViewer::SliceOrientation [protected]
```

Referenced by [vtkGetMacro\(\)](#).

10.390.6.10 WindowLevel

```
vtkImageMapToWindowLevelColors2* vtkImageColorViewer::WindowLevel [protected]
```

Referenced by [vtkGetObjectMacro\(\)](#).


The documentation for this class was generated from the following file:

- [vtkImageColorViewer.h](#)


10.391 vtkImageMapToColors16 Class Reference

```
#include <vtkImageMapToColors16.h>
```

Inheritance diagram for vtkImageMapToColors16:



Collaboration diagram for vtkImageMapToColors16:



Public Member Functions

- virtual unsigned long [GetMTime](#) ()
- void [PrintSelf](#) (ostream &os, vtkIndent indent)
- virtual void [SetLookupTable](#) (vtkScalarsToColors *)
- void [SetOutputFormatToLuminance](#) ()
- void [SetOutputFormatToLuminanceAlpha](#) ()
- void [SetOutputFormatToRGB](#) ()
- void [SetOutputFormatToRGBA](#) ()
- [vtkBooleanMacro](#) ([PassAlphaToOutput](#), int)
- [vtkGetMacro](#) ([ActiveComponent](#), int)
- [vtkGetMacro](#) ([OutputFormat](#), int)
- [vtkGetMacro](#) ([PassAlphaToOutput](#), int)
- [vtkGetObjectMacro](#) ([LookupTable](#), vtkScalarsToColors)
- [vtkSetMacro](#) ([ActiveComponent](#), int)
- [vtkSetMacro](#) ([OutputFormat](#), int)
- [vtkSetMacro](#) ([PassAlphaToOutput](#), int)
- [vtkTypeMacro](#) (vtkImageMapToColors16, vtkThreadedImageAlgorithm)

Static Public Member Functions

- static [vtkImageMapToColors16 * New](#) ()

Protected Member Functions

- [vtkImageMapToColors16](#) ()
- [~vtkImageMapToColors16](#) ()
- virtual int [RequestData](#) (vtkInformation *request, vtkInformationVector **inputVector, vtkInformationVector *outputVector)
- virtual int [RequestInformation](#) (vtkInformation *, vtkInformationVector **, vtkInformationVector *)
- void [ThreadedRequestData](#) (vtkInformation *request, vtkInformationVector **inputVector, vtkInformationVector *outputVector, vtkImageData ***inData, vtkImageData **outData, int extent[6], int id)

Protected Attributes

- int [ActiveComponent](#)
- int [DataWasPassed](#)
- vtkScalarsToColors * [LookupTable](#)
- int [OutputFormat](#)
- int [PassAlphaToOutput](#)

10.391.1 Constructor & Destructor Documentation

10.391.1.1 vtkImageMapToColors16()

```
vtkImageMapToColors16::vtkImageMapToColors16 () [protected]
```

Referenced by [New\(\)](#), and [vtkTypeMacro\(\)](#).

10.391.1.2 ~vtkImageMapToColors16()

```
vtkImageMapToColors16::~~vtkImageMapToColors16 () [protected]
```

10.391.2 Member Function Documentation

10.391.2.1 GetMTime()

```
virtual unsigned long vtkImageMapToColors16::GetMTime () [virtual]
```

Referenced by [vtkGetMacro\(\)](#).

10.391.2.2 New()

```
vtkImageMapToColors16 * vtkImageMapToColors16::New () [static]
```

References [vtkImageMapToColors16\(\)](#).

10.391.2.3 PrintSelf()

```
void vtkImageMapToColors16::PrintSelf (  
    ostream & os,  
    vtkIndent indent)
```


10.391.2.4 RequestData()

```
virtual int vtkImageMapToColors16::RequestData (
    vtkInformation * request,
    vtkInformationVector ** inputVector,
    vtkInformationVector * outputVector) [protected], [virtual]
```

10.391.2.5 RequestInformation()

```
virtual int vtkImageMapToColors16::RequestInformation (
    vtkInformation * ,
    vtkInformationVector ** ,
    vtkInformationVector * ) [protected], [virtual]
```

10.391.2.6 SetLookupTable()

```
virtual void vtkImageMapToColors16::SetLookupTable (
    vtkScalarsToColors * ) [virtual]
```

10.391.2.7 SetOutputFormatToLuminance()

```
void vtkImageMapToColors16::SetOutputFormatToLuminance () [inline]
```

References [OutputFormat](#).

10.391.2.8 SetOutputFormatToLuminanceAlpha()

```
void vtkImageMapToColors16::SetOutputFormatToLuminanceAlpha () [inline]
```

References [OutputFormat](#).

10.391.2.9 SetOutputFormatToRGB()

```
void vtkImageMapToColors16::SetOutputFormatToRGB () [inline]
```

References [OutputFormat](#).

10.391.2.10 SetOutputFormatToRGBA()

```
void vtkImageMapToColors16::SetOutputFormatToRGBA () [inline]
```

References [OutputFormat](#).

10.391.2.11 ThreadedRequestData()

```
void vtkImageMapToColors16::ThreadedRequestData (
    vtkInformation * request,
    vtkInformationVector ** inputVector,
    vtkInformationVector * outputVector,
    vtkImageData *** inData,
    vtkImageData ** outData,
    int extent[6],
    int id) [protected]
```

10.391.2.12 vtkBooleanMacro()

```
vtkImageMapToColors16::vtkBooleanMacro (
    PassAlphaToOutput ,
    int )
```

References [PassAlphaToOutput](#).

10.391.2.13 vtkGetMacro() [1/3]

```
vtkImageMapToColors16::vtkGetMacro (
    ActiveComponent ,
    int )
```

References [ActiveComponent](#).

10.391.2.14 vtkGetMacro() [2/3]

```
vtkImageMapToColors16::vtkGetMacro (
    OutputFormat ,
    int )
```

References [OutputFormat](#).

10.391.2.15 vtkGetMacro() [3/3]

```
vtkImageMapToColors16::vtkGetMacro (
    PassAlphaToOutput ,
    int )
```

References [GetMTime\(\)](#), and [PassAlphaToOutput](#).

10.391.2.16 vtkGetObjectMacro()

```
vtkImageMapToColors16::vtkGetObjectMacro (
    LookupTable ,
    vtkScalarsToColors )
```

References [LookupTable](#).

10.391.2.17 vtkSetMacro() [1/3]

```
vtkImageMapToColors16::vtkSetMacro (
    ActiveComponent ,
    int )
```

References [ActiveComponent](#).

10.391.2.18 vtkSetMacro() [2/3]

```
vtkImageMapToColors16::vtkSetMacro (
    OutputFormat ,
    int )
```

References [OutputFormat](#).

10.391.2.19 vtkSetMacro() [3/3]

```
vtkImageMapToColors16::vtkSetMacro (
    PassAlphaToOutput ,
    int )
```

References [PassAlphaToOutput](#).

10.391.2.20 vtkTypeMacro()

```
vtkImageMapToColors16::vtkTypeMacro (
    vtkImageMapToColors16 ,
    vtkThreadedImageAlgorithm )
```

References [vtkImageMapToColors16\(\)](#).

10.391.3 Member Data Documentation

10.391.3.1 ActiveComponent

```
int vtkImageMapToColors16::ActiveComponent [protected]
```

Referenced by [vtkGetMacro\(\)](#), and [vtkSetMacro\(\)](#).

10.391.3.2 DataWasPassed

```
int vtkImageMapToColors16::DataWasPassed [protected]
```

10.391.3.3 LookupTable

```
vtkScalarsToColors* vtkImageMapToColors16::LookupTable [protected]
```

Referenced by [vtkGetObjectMacro\(\)](#).

10.391.3.4 OutputFormat

```
int vtkImageMapToColors16::OutputFormat [protected]
```

Referenced by [SetOutputFormatToLuminance\(\)](#), [SetOutputFormatToLuminanceAlpha\(\)](#), [SetOutputFormatToRGB\(\)](#), [SetOutputFormatToRGBA\(\)](#), [vtkGetMacro\(\)](#), and [vtkSetMacro\(\)](#).

10.391.3.5 PassAlphaToOutput

```
int vtkImageMapToColors16::PassAlphaToOutput [protected]
```

Referenced by [vtkBooleanMacro\(\)](#), [vtkGetMacro\(\)](#), and [vtkSetMacro\(\)](#).


The documentation for this class was generated from the following file:

- [vtkImageMapToColors16.h](#)


10.392 vtkImageMapToWindowLevelColors2 Class Reference

```
#include <vtkImageMapToWindowLevelColors2.h>
```

Inheritance diagram for vtkImageMapToWindowLevelColors2:



Collaboration diagram for vtkImageMapToWindowLevelColors2:



Public Member Functions

- void [PrintSelf](#) (ostream &os, vtkIndent indent)
- [vtkGetMacro](#) (Level, double)
- [vtkGetMacro](#) (Window, double)
- [vtkSetMacro](#) (Level, double)
- [vtkSetMacro](#) (Window, double)
- [vtkTypeMacro](#) (vtkImageMapToWindowLevelColors2, vtkImageMapToColors)

Static Public Member Functions

- static [vtkImageMapToWindowLevelColors2 * New](#) ()

Protected Member Functions

- [vtkImageMapToWindowLevelColors2](#) ()
- [~vtkImageMapToWindowLevelColors2](#) ()
- virtual int [RequestData](#) (vtkInformation *request, vtkInformationVector **inputVector, vtkInformationVector *outputVector)
- virtual int [RequestInformation](#) (vtkInformation *, vtkInformationVector **, vtkInformationVector *)
- void [ThreadedRequestData](#) (vtkInformation *request, vtkInformationVector **inputVector, vtkInformationVector *outputVector, vtkImageData ***inData, vtkImageData **outData, int extent[6], int id)

Protected Attributes

- double [Level](#)
- double [Window](#)

10.392.1 Constructor & Destructor Documentation

10.392.1.1 vtkImageMapToWindowLevelColors2()

`vtkImageMapToWindowLevelColors2::vtkImageMapToWindowLevelColors2 () [protected]`

Referenced by [New\(\)](#), and [vtkTypeMacro\(\)](#).

10.392.1.2 ~vtkImageMapToWindowLevelColors2()

`vtkImageMapToWindowLevelColors2::~~vtkImageMapToWindowLevelColors2 () [protected]`

10.392.2 Member Function Documentation

10.392.2.1 New()

`vtkImageMapToWindowLevelColors2 * vtkImageMapToWindowLevelColors2::New () [static]`

References [vtkImageMapToWindowLevelColors2\(\)](#).

10.392.2.2 PrintSelf()

```
void vtkImageMapToWindowLevelColors2::PrintSelf (
    ostream & os,
    vtkIndent indent)
```

10.392.2.3 RequestData()

```
virtual int vtkImageMapToWindowLevelColors2::RequestData (
    vtkInformation * request,
    vtkInformationVector ** inputVector,
    vtkInformationVector * outputVector) [protected], [virtual]
```

10.392.2.4 RequestInformation()

```
virtual int vtkImageMapToWindowLevelColors2::RequestInformation (
    vtkInformation * ,
    vtkInformationVector ** ,
    vtkInformationVector * ) [protected], [virtual]
```

10.392.2.5 ThreadedRequestData()

```
void vtkImageMapToWindowLevelColors2::ThreadedRequestData (
    vtkInformation * request,
    vtkInformationVector ** inputVector,
    vtkInformationVector * outputVector,
    vtkImageData *** inData,
    vtkImageData ** outData,
    int extent[6],
    int id) [protected]
```

10.392.2.6 vtkGetMacro() [1/2]

```
vtkImageMapToWindowLevelColors2::vtkGetMacro (
    Level ,
    double )
```

References [Level](#).

10.392.2.7 vtkGetMacro() [2/2]

```
vtkImageMapToWindowLevelColors2::vtkGetMacro (
    Window ,
    double )
```

References [Window](#).

10.392.2.8 vtkSetMacro() [1/2]

```
vtkImageMapToWindowLevelColors2::vtkSetMacro (
    Level ,
    double )
```

References [Level](#).

10.392.2.9 vtkSetMacro() [2/2]

```
vtkImageMapToWindowLevelColors2::vtkSetMacro (
    Window ,
    double )
```

References [Window](#).

10.392.2.10 vtkTypeMacro()

```
vtkImageMapToWindowLevelColors2::vtkTypeMacro (
    vtkImageMapToWindowLevelColors2 ,
    vtkImageMapToColors )
```

References [vtkImageMapToWindowLevelColors2\(\)](#).

10.392.3 Member Data Documentation

10.392.3.1 Level

```
double vtkImageMapToWindowLevelColors2::Level [protected]
```

Referenced by [vtkGetMacro\(\)](#), and [vtkSetMacro\(\)](#).

10.392.3.2 Window

```
double vtkImageMapToWindowLevelColors2::Window [protected]
```

Referenced by [vtkGetMacro\(\)](#), and [vtkSetMacro\(\)](#).


The documentation for this class was generated from the following file:

- [vtkImageMapToWindowLevelColors2.h](#)


10.393 vtkImagePlanarComponentsToComponents Class Reference

```
#include <vtkImagePlanarComponentsToComponents.h>
```

Inheritance diagram for vtkImagePlanarComponentsToComponents:



Collaboration diagram for vtkImagePlanarComponentsToComponents:



Public Member Functions

- void [PrintSelf](#) (ostream &os, vtkIndent indent)
- [vtkTypeMacro](#) ([vtkImagePlanarComponentsToComponents](#), vtkImageAlgorithm)

Static Public Member Functions

- static [vtkImagePlanarComponentsToComponents](#) * [New](#) ()

Protected Member Functions

- [vtkImagePlanarComponentsToComponents](#) ()
- [~vtkImagePlanarComponentsToComponents](#) ()
- virtual int [RequestData](#) (vtkInformation *, vtkInformationVector **, vtkInformationVector *)

10.393.1 Constructor & Destructor Documentation

10.393.1.1 vtkImagePlanarComponentsToComponents()

```
vtkImagePlanarComponentsToComponents::vtkImagePlanarComponentsToComponents () [protected]
```

Referenced by [New\(\)](#), [RequestData\(\)](#), and [vtkTypeMacro\(\)](#).

10.393.1.2 ~vtkImagePlanarComponentsToComponents()

```
vtkImagePlanarComponentsToComponents::~~vtkImagePlanarComponentsToComponents () [inline], [protected]
```

10.393.2 Member Function Documentation

10.393.2.1 New()

[vtkImagePlanarComponentsToComponents](#) * [vtkImagePlanarComponentsToComponents::New](#) () [static]

References [vtkImagePlanarComponentsToComponents\(\)](#).

10.393.2.2 PrintSelf()

```
void vtkImagePlanarComponentsToComponents::PrintSelf (
    ostream & os,
    vtkIndent indent)
```

10.393.2.3 RequestData()

```
virtual int vtkImagePlanarComponentsToComponents::RequestData (
    vtkInformation * ,
    vtkInformationVector ** ,
    vtkInformationVector * ) [protected], [virtual]
```

References [vtkImagePlanarComponentsToComponents\(\)](#).

10.393.2.4 vtkTypeMacro()

```
vtkImagePlanarComponentsToComponents::vtkTypeMacro (
    vtkImagePlanarComponentsToComponents ,
    vtkImageAlgorithm )
```

References [vtkImagePlanarComponentsToComponents\(\)](#).


The documentation for this class was generated from the following file:

- [vtkImagePlanarComponentsToComponents.h](#)


10.394 vtkImageRGBToYBR Class Reference

```
#include <vtkImageRGBToYBR.h>
```

Inheritance diagram for vtkImageRGBToYBR:



Collaboration diagram for vtkImageRGBToYBR:



Public Member Functions

- void [PrintSelf](#) (ostream &os, vtkIndent indent)
- [vtkTypeMacro](#) (vtkImageRGBToYBR, vtkThreadedImageAlgorithm)

Static Public Member Functions

- static [vtkImageRGBToYBR](#) * [New](#) ()

Protected Member Functions

- [vtkImageRGBToYBR \(\)](#)
- [~vtkImageRGBToYBR \(\)](#)
- void [ThreadedExecute](#) (vtkImageData *inData, vtkImageData *outData, int ext[6], int id)

10.394.1 Constructor & Destructor Documentation

10.394.1.1 vtkImageRGBToYBR()

```
vtkImageRGBToYBR::vtkImageRGBToYBR () [protected]
```

Referenced by [New\(\)](#), [ThreadedExecute\(\)](#), and [vtkTypeMacro\(\)](#).

10.394.1.2 ~vtkImageRGBToYBR()

```
vtkImageRGBToYBR::~vtkImageRGBToYBR () [inline], [protected]
```

10.394.2 Member Function Documentation

10.394.2.1 New()

```
vtkImageRGBToYBR * vtkImageRGBToYBR::New () [static]
```

References [vtkImageRGBToYBR\(\)](#).

10.394.2.2 PrintSelf()

```
void vtkImageRGBToYBR::PrintSelf (
    ostream & os,
    vtkIndent indent)
```

10.394.2.3 ThreadedExecute()

```
void vtkImageRGBToYBR::ThreadedExecute (
    vtkImageData * inData,
    vtkImageData * outData,
    int ext[6],
    int id) [protected]
```

References [vtkImageRGBToYBR\(\)](#).

10.394.2.4 vtkTypeMacro()

```
vtkImageRGBToYBR::vtkTypeMacro (
    vtkImageRGBToYBR ,
    vtkThreadedImageAlgorithm )
```

References [vtkImageRGBToYBR\(\)](#).


The documentation for this class was generated from the following file:

- [vtkImageRGBToYBR.h](#)


10.395 vtkImageYBRToRGB Class Reference

```
#include <vtkImageYBRToRGB.h>
```

Inheritance diagram for vtkImageYBRToRGB:



Collaboration diagram for vtkImageYBRToRGB:



Public Member Functions

- void [PrintSelf](#) (ostream &os, vtkIndent indent)
- [vtkTypeMacro](#) ([vtkImageYBRTToRGB](#), vtkThreadedImageAlgorithm)

Static Public Member Functions

- static [vtkImageYBRTToRGB](#) * [New](#) ()

Protected Member Functions

- [vtkImageYBRTToRGB](#) ()
- [~vtkImageYBRTToRGB](#) ()
- void [ThreadedExecute](#) (vtkImageData *inData, vtkImageData *outData, int ext[6], int id)

10.395.1 Constructor & Destructor Documentation

10.395.1.1 [vtkImageYBRTToRGB](#)()

`vtkImageYBRTToRGB::vtkImageYBRTToRGB () [protected]`

Referenced by [New\(\)](#), [ThreadedExecute\(\)](#), and [vtkTypeMacro\(\)](#).

10.395.1.2 [~vtkImageYBRTToRGB](#)()

`vtkImageYBRTToRGB::~~vtkImageYBRTToRGB () [inline], [protected]`

10.395.2 Member Function Documentation

10.395.2.1 [New](#)()

`vtkImageYBRTToRGB * vtkImageYBRTToRGB::New () [static]`

References [vtkImageYBRTToRGB\(\)](#).

10.395.2.2 [PrintSelf](#)()

```
void vtkImageYBRTToRGB::PrintSelf (
    ostream & os,
    vtkIndent indent)
```

10.395.2.3 ThreadedExecute()

```
void vtkImageYBRToRGB::ThreadedExecute (
    vtkImageData * inData,
    vtkImageData * outData,
    int ext[6],
    int id) [protected]
```

References [vtkImageYBRToRGB\(\)](#).

10.395.2.4 vtkTypeMacro()

```
vtkImageYBRToRGB::vtkTypeMacro (
    vtkImageYBRToRGB ,
    vtkThreadedImageAlgorithm )
```

References [vtkImageYBRToRGB\(\)](#).


The documentation for this class was generated from the following file:

- [vtkImageYBRToRGB.h](#)


10.396 vtkLookupTable16 Class Reference

```
#include <vtkLookupTable16.h>
```

Inheritance diagram for vtkLookupTable16:



Collaboration diagram for vtkLookupTable16:



Public Member Functions

- void [Build](#) ()
- unsigned short * [GetPointer](#) (const vtkIdType id)
- void [PrintSelf](#) (ostream &os, vtkIndent indent)
- void [SetNumberOfTableValues](#) (vtkIdType number)
- [vtkTypeMacro](#) ([vtkLookupTable16](#), vtkLookupTable)
- unsigned char * [WritePointer](#) (const vtkIdType id, const int number)

Static Public Member Functions

- static [vtkLookupTable16](#) * [New](#) ()

Protected Member Functions

- [vtkLookupTable16](#) (int size=256, int ext=256)
- [~vtkLookupTable16](#) ()
- void [MapScalarsThroughTable2](#) (void *input, unsigned char *output, int inputDataType, int numberOfValues, int inputIncrement, int outputFormat)

Protected Attributes

- vtkUnsignedShortArray * [Table16](#)

10.396.1 Constructor & Destructor Documentation

10.396.1.1 vtkLookupTable16()

```

vtkLookupTable16::vtkLookupTable16 (
    int size = 256,
    int ext = 256) [protected]
  
```

Referenced by [MapScalarsThroughTable2\(\)](#), [New\(\)](#), and [vtkTypeMacro\(\)](#).

10.396.1.2 ~vtkLookupTable16()

```
vtkLookupTable16::~vtkLookupTable16 () [protected]
```

10.396.2 Member Function Documentation

10.396.2.1 Build()

```
void vtkLookupTable16::Build ()
```

10.396.2.2 GetPointer()

```
unsigned short * vtkLookupTable16::GetPointer (
    const vtkIdType id) [inline]
```

References [Table16](#).

10.396.2.3 MapScalarsThroughTable2()

```
void vtkLookupTable16::MapScalarsThroughTable2 (
    void * input,
    unsigned char * output,
    int inputDataType,
    int numberOfValues,
    int inputIncrement,
    int outputFormat) [protected]
```

References [vtkLookupTable16\(\)](#).

10.396.2.4 New()

```
vtkLookupTable16 * vtkLookupTable16::New () [static]
```

References [vtkLookupTable16\(\)](#).

10.396.2.5 PrintSelf()

```
void vtkLookupTable16::PrintSelf (
    ostream & os,
    vtkIndent indent)
```

10.396.2.6 SetNumberOfTableValues()

```
void vtkLookupTable16::SetNumberOfTableValues (
    vtkIdType number)
```

References [WritePointer\(\)](#).

10.396.2.7 vtkTypeMacro()

```
vtkLookupTable16::vtkTypeMacro (
    vtkLookupTable16 ,
    vtkLookupTable )
```

References [vtkLookupTable16\(\)](#).

10.396.2.8 WritePointer()

```
unsigned char * vtkLookupTable16::WritePointer (
    const vtkIdType id,
    const int number) [inline]
```

References [Table16](#).

Referenced by [SetNumberOfTableValues\(\)](#).

10.396.3 Member Data Documentation

10.396.3.1 Table16

```
vtkUnsignedShortArray* vtkLookupTable16::Table16 [protected]
```

Referenced by [GetPointer\(\)](#), and [WritePointer\(\)](#).


The documentation for this class was generated from the following file:

- [vtkLookupTable16.h](#)


10.397 vtkRTStructSetProperties Class Reference

```
#include <vtkRTStructSetProperties.h>
```

Inheritance diagram for vtkRTStructSetProperties:



Collaboration diagram for vtkRTStructSetProperties:



Public Member Functions

- void [AddContourReferencedFrameOfReference](#) (vtkIdType pdnum, const char *classuid, const char *instanceuid)
- void [AddReferencedFrameOfReference](#) (const char *classuid, const char *instanceuid)
- void [AddStructureSetROI](#) (int roinumber, const char *refframerefid, const char *roiname, const char *ROIGenerationAlgorithm, const char *ROIDescription=0)
- void [AddStructureSetROIObservation](#) (int refnumber, int observationnumber, const char *rtroiinterpretedtype, const char *roiinterpreter, const char *roiobservationlabel=0)
- virtual void [Clear](#) ()
- virtual void [DeepCopy](#) (vtkRTStructSetProperties *p)
- const char * [GetContourReferencedFrameOfReferenceClassUID](#) (vtkIdType pdnum, vtkIdType id)
- const char * [GetContourReferencedFrameOfReferenceInstanceUID](#) (vtkIdType pdnum, vtkIdType id)
- vtkIdType [GetNumberOfContourReferencedFrameOfReferences](#) ()

- vtkIdType [GetNumberOfContourReferencedFrameOfReferences](#) (vtkIdType pdnum)
- vtkIdType [GetNumberOfReferencedFrameOfReferences](#) ()
- vtkIdType [GetNumberOfStructureSetROIs](#) ()
- const char * [GetReferencedFrameOfReferenceClassUID](#) (vtkIdType id)
- const char * [GetReferencedFrameOfReferenceInstanceUID](#) (vtkIdType id)
- int [GetStructureSetObservationNumber](#) (vtkIdType id)
- const char * [GetStructureSetROIDescription](#) (vtkIdType id)
- const char * [GetStructureSetROIGenerationAlgorithm](#) (vtkIdType)
- const char * [GetStructureSetROIName](#) (vtkIdType)
- int [GetStructureSetROINumber](#) (vtkIdType id)
- const char * [GetStructureSetROIObservationLabel](#) (vtkIdType id)
- const char * [GetStructureSetROIRefFrameRefUID](#) (vtkIdType)
- const char * [GetStructureSetRTROIInterpretedType](#) (vtkIdType id)
- void [PrintSelf](#) (ostream &os, vtkIndent indent)
- [vtkGetStringMacro](#) (ReferenceFrameOfReferenceUID)
- [vtkGetStringMacro](#) (ReferenceSeriesInstanceUID)
- [vtkGetStringMacro](#) (SeriesInstanceUID)
- [vtkGetStringMacro](#) (SOPInstanceUID)
- [vtkGetStringMacro](#) (StructureSetDate)
- [vtkGetStringMacro](#) (StructureSetLabel)
- [vtkGetStringMacro](#) (StructureSetName)
- [vtkGetStringMacro](#) (StructureSetTime)
- [vtkGetStringMacro](#) (StudyInstanceUID)
- [vtkSetStringMacro](#) (ReferenceFrameOfReferenceUID)
- [vtkSetStringMacro](#) (ReferenceSeriesInstanceUID)
- [vtkSetStringMacro](#) (SeriesInstanceUID)
- [vtkSetStringMacro](#) (SOPInstanceUID)
- [vtkSetStringMacro](#) (StructureSetDate)
- [vtkSetStringMacro](#) (StructureSetLabel)
- [vtkSetStringMacro](#) (StructureSetName)
- [vtkSetStringMacro](#) (StructureSetTime)
- [vtkSetStringMacro](#) (StudyInstanceUID)
- [vtkTypeMacro](#) (vtkRTStructSetProperties, vtkObject)

Static Public Member Functions

- static [vtkRTStructSetProperties](#) * [New](#) ()

Protected Member Functions

- [vtkRTStructSetProperties](#) ()
- [~vtkRTStructSetProperties](#) ()

Protected Attributes

- vtkRTStructSetPropertiesInternals * [Internals](#)
- char * [ReferenceFrameOfReferenceUID](#)
- char * [ReferenceSeriesInstanceUID](#)
- char * [SeriesInstanceUID](#)
- char * [SOPInstanceUID](#)
- char * [StructureSetDate](#)
- char * [StructureSetLabel](#)
- char * [StructureSetName](#)
- char * [StructureSetTime](#)
- char * [StudyInstanceUID](#)

10.397.1 Detailed Description**Examples**

[GenerateRTSTRUCT.cxx](#).

10.397.2 Constructor & Destructor Documentation**10.397.2.1 vtkRTStructSetProperties()**

```
vtkRTStructSetProperties::vtkRTStructSetProperties () [protected]
```

Referenced by [DeepCopy\(\)](#), [New\(\)](#), and [vtkTypeMacro\(\)](#).

10.397.2.2 ~vtkRTStructSetProperties()

```
vtkRTStructSetProperties::~~vtkRTStructSetProperties () [protected]
```

10.397.3 Member Function Documentation**10.397.3.1 AddContourReferencedFrameOfReference()**

```
void vtkRTStructSetProperties::AddContourReferencedFrameOfReference (
    vtkIdType pdnum,
    const char * classuid,
    const char * instanceuid)
```

10.397.3.2 AddReferencedFrameOfReference()

```
void vtkRTStructSetProperties::AddReferencedFrameOfReference (
    const char * classuid,
    const char * instanceuid)
```

10.397.3.3 AddStructureSetROI()

```
void vtkRTStructSetProperties::AddStructureSetROI (
    int roinumber,
    const char * refframerefuid,
    const char * roiname,
    const char * ROIGenerationAlgorithm,
    const char * ROIDescription = 0)
```

10.397.3.4 AddStructureSetROIObservation()

```
void vtkRTStructSetProperties::AddStructureSetROIObservation (
    int refnumber,
    int observationnumber,
    const char * rtroiinterpretedtype,
    const char * roiinterpreter,
    const char * roiobservationlabel = 0)
```

10.397.3.5 Clear()

```
virtual void vtkRTStructSetProperties::Clear () [virtual]
```

10.397.3.6 DeepCopy()

```
virtual void vtkRTStructSetProperties::DeepCopy (
    vtkRTStructSetProperties * p) [virtual]
```

References [vtkRTStructSetProperties\(\)](#).

10.397.3.7 GetContourReferencedFrameOfReferenceClassUID()

```
const char * vtkRTStructSetProperties::GetContourReferencedFrameOfReferenceClassUID (
    vtkIdType pdnum,
    vtkIdType id)
```

10.397.3.8 GetContourReferencedFrameOfReferenceInstanceUID()

```
const char * vtkRTStructSetProperties::GetContourReferencedFrameOfReferenceInstanceUID (
    vtkIdType pdnum,
    vtkIdType id)
```

10.397.3.9 GetNumberOfContourReferencedFrameOfReferences() [1/2]

```
vtkIdType vtkRTStructSetProperties::GetNumberOfContourReferencedFrameOfReferences ()
```

10.397.3.10 GetNumberOfContourReferencedFrameOfReferences() [2/2]

```
vtkIdType vtkRTStructSetProperties::GetNumberOfContourReferencedFrameOfReferences (
    vtkIdType pdnum)
```

10.397.3.11 GetNumberOfReferencedFrameOfReferences()

```
vtkIdType vtkRTStructSetProperties::GetNumberOfReferencedFrameOfReferences ()
```

10.397.3.12 GetNumberOfStructureSetROIs()

```
vtkIdType vtkRTStructSetProperties::GetNumberOfStructureSetROIs ()
```

10.397.3.13 GetReferencedFrameOfReferenceClassUID()

```
const char * vtkRTStructSetProperties::GetReferencedFrameOfReferenceClassUID (
    vtkIdType id)
```

10.397.3.14 GetReferencedFrameOfReferenceInstanceUID()

```
const char * vtkRTStructSetProperties::GetReferencedFrameOfReferenceInstanceUID (
    vtkIdType id)
```

10.397.3.15 GetStructureSetObservationNumber()

```
int vtkRTStructSetProperties::GetStructureSetObservationNumber (
    vtkIdType id)
```

10.397.3.16 GetStructureSetROIDescription()

```
const char * vtkRTStructSetProperties::GetStructureSetROIDescription (
    vtkIdType id)
```

10.397.3.17 GetStructureSetROIGenerationAlgorithm()

```
const char * vtkRTStructSetProperties::GetStructureSetROIGenerationAlgorithm (
    vtkIdType )
```

10.397.3.18 GetStructureSetROIName()

```
const char * vtkRTStructSetProperties::GetStructureSetROIName (
    vtkIdType )
```

10.397.3.19 GetStructureSetROINumber()

```
int vtkRTStructSetProperties::GetStructureSetROINumber (
    vtkIdType id)
```

10.397.3.20 GetStructureSetROIObservationLabel()

```
const char * vtkRTStructSetProperties::GetStructureSetROIObservationLabel (
    vtkIdType id)
```

10.397.3.21 GetStructureSetROIRefFrameRefUID()

```
const char * vtkRTStructSetProperties::GetStructureSetROIRefFrameRefUID (
    vtkIdType )
```

10.397.3.22 GetStructureSetRTROIInterpretedType()

```
const char * vtkRTStructSetProperties::GetStructureSetRTROIInterpretedType (
    vtkIdType id)
```

10.397.3.23 New()

```
vtkRTStructSetProperties * vtkRTStructSetProperties::New () [static]
```

Examples

[GenerateRTSTRUCT.cxx](#).

References [vtkRTStructSetProperties\(\)](#).

10.397.3.24 PrintSelf()

```
void vtkRTStructSetProperties::PrintSelf (
    ostream & os,
    vtkIndent indent)
```


10.397.3.25 vtkGetStringMacro() [1/9]

```
vtkRTStructSetProperties::vtkGetStringMacro (
    ReferenceFrameOfReferenceUID )
```

References [ReferenceFrameOfReferenceUID](#).

10.397.3.26 vtkGetStringMacro() [2/9]

```
vtkRTStructSetProperties::vtkGetStringMacro (
    ReferenceSeriesInstanceUID )
```

References [ReferenceSeriesInstanceUID](#).

10.397.3.27 vtkGetStringMacro() [3/9]

```
vtkRTStructSetProperties::vtkGetStringMacro (
    SeriesInstanceUID )
```

References [SeriesInstanceUID](#).

10.397.3.28 vtkGetStringMacro() [4/9]

```
vtkRTStructSetProperties::vtkGetStringMacro (
    SOPInstanceUID )
```

References [SOPInstanceUID](#).

10.397.3.29 vtkGetStringMacro() [5/9]

```
vtkRTStructSetProperties::vtkGetStringMacro (
    StructureSetDate )
```

References [StructureSetDate](#).

10.397.3.30 vtkGetStringMacro() [6/9]

```
vtkRTStructSetProperties::vtkGetStringMacro (
    StructureSetLabel )
```

References [StructureSetLabel](#).

10.397.3.31 vtkGetStringMacro() [7/9]

```
vtkRTStructSetProperties::vtkGetStringMacro (
    StructureSetName )
```

References [StructureSetName](#).

10.397.3.32 vtkGetStringMacro() [8/9]

```
vtkRTStructSetProperties::vtkGetStringMacro (
    StructureSetTime )
```

References [StructureSetTime](#).

10.397.3.33 vtkGetStringMacro() [9/9]

```
vtkRTStructSetProperties::vtkGetStringMacro (
    StudyInstanceUID )
```

References [StudyInstanceUID](#).

10.397.3.34 vtkSetStringMacro() [1/9]

```
vtkRTStructSetProperties::vtkSetStringMacro (
    ReferenceFrameOfReferenceUID )
```

References [ReferenceFrameOfReferenceUID](#).

10.397.3.35 vtkSetStringMacro() [2/9]

```
vtkRTStructSetProperties::vtkSetStringMacro (
    ReferenceSeriesInstanceUID )
```

References [ReferenceSeriesInstanceUID](#).

10.397.3.36 vtkSetStringMacro() [3/9]

```
vtkRTStructSetProperties::vtkSetStringMacro (
    SeriesInstanceUID )
```

References [SeriesInstanceUID](#).

10.397.3.37 vtkSetStringMacro() [4/9]

```
vtkRTStructSetProperties::vtkSetStringMacro (
    SOPInstanceUID )
```

References [SOPInstanceUID](#).

10.397.3.38 vtkSetStringMacro() [5/9]

```
vtkRTStructSetProperties::vtkSetStringMacro (
    StructureSetDate )
```

References [StructureSetDate](#).

10.397.3.39 vtkSetStringMacro() [6/9]

```
vtkRTStructSetProperties::vtkSetStringMacro (
    StructureSetLabel )
```

References [StructureSetLabel](#).

10.397.3.40 vtkSetStringMacro() [7/9]

```
vtkRTStructSetProperties::vtkSetStringMacro (
    StructureSetName )
```

References [StructureSetName](#).

10.397.3.41 vtkSetStringMacro() [8/9]

```
vtkRTStructSetProperties::vtkSetStringMacro (
    StructureSetTime )
```

References [StructureSetTime](#).

10.397.3.42 vtkSetStringMacro() [9/9]

```
vtkRTStructSetProperties::vtkSetStringMacro (
    StudyInstanceUID )
```

References [StudyInstanceUID](#).

10.397.3.43 vtkTypeMacro()

```
vtkRTStructSetProperties::vtkTypeMacro (
    vtkRTStructSetProperties ,
    vtkObject )
```

References [vtkRTStructSetProperties\(\)](#).

10.397.4 Member Data Documentation

10.397.4.1 Internals

```
vtkRTStructSetPropertiesInternals* vtkRTStructSetProperties::Internals [protected]
```

10.397.4.2 ReferenceFrameOfReferenceUID

```
char* vtkRTStructSetProperties::ReferenceFrameOfReferenceUID [protected]
```

Referenced by [vtkGetStringMacro\(\)](#), and [vtkSetStringMacro\(\)](#).

10.397.4.3 ReferenceSeriesInstanceUID

```
char* vtkRTStructSetProperties::ReferenceSeriesInstanceUID [protected]
```

Referenced by [vtkGetStringMacro\(\)](#), and [vtkSetStringMacro\(\)](#).

10.397.4.4 SeriesInstanceUID

```
char* vtkRTStructSetProperties::SeriesInstanceUID [protected]
```

Referenced by [vtkGetStringMacro\(\)](#), and [vtkSetStringMacro\(\)](#).

10.397.4.5 SOPInstanceUID

```
char* vtkRTStructSetProperties::SOPInstanceUID [protected]
```

Referenced by [vtkGetStringMacro\(\)](#), and [vtkSetStringMacro\(\)](#).

10.397.4.6 StructureSetDate

```
char* vtkRTStructSetProperties::StructureSetDate [protected]
```

Referenced by [vtkGetStringMacro\(\)](#), and [vtkSetStringMacro\(\)](#).

10.397.4.7 StructureSetLabel

```
char* vtkRTStructSetProperties::StructureSetLabel [protected]
```

Referenced by [vtkGetStringMacro\(\)](#), and [vtkSetStringMacro\(\)](#).

10.397.4.8 StructureSetName

```
char* vtkRTStructSetProperties::StructureSetName [protected]
```

Referenced by [vtkGetStringMacro\(\)](#), and [vtkSetStringMacro\(\)](#).

10.397.4.9 StructureSetTime

```
char* vtkRTStructSetProperties::StructureSetTime [protected]
```

Referenced by [vtkGetStringMacro\(\)](#), and [vtkSetStringMacro\(\)](#).

10.397.4.10 StudyInstanceUID

```
char* vtkRTStructSetProperties::StudyInstanceUID [protected]
```

Referenced by [vtkGetStringMacro\(\)](#), and [vtkSetStringMacro\(\)](#).

The documentation for this class was generated from the following file:

- [vtkRTStructSetProperties.h](#)

10.398 gdcm::Waveform Class Reference

[Waveform](#) class.

```
#include <gdcmWaveform.h>
```

Public Member Functions

- [Waveform](#) ()=default

10.398.1 Detailed Description

[Waveform](#) class.

10.398.2 Constructor & Destructor Documentation

10.398.2.1 Waveform()

```
gdcm::Waveform::Waveform () [default]
```

The documentation for this class was generated from the following file:


- [gdcmWaveform.h](#)

10.399 gdcm::WLMFindQuery Class Reference


PatientRootQuery.

```
#include <gdcmWLMFindQuery.h>
```

Inheritance diagram for gdcm::WLMFindQuery:



Collaboration diagram for gdcm::WLMFindQuery:



Public Member Functions

- [WLMFindQuery](#) ()
- [UIDs::TSName GetAbstractSyntaxUID](#) () const override
- [std::vector< Tag > GetTagListByLevel](#) (const [EQueryLevel](#) &inQueryLevel) override
- void [InitializeDataSet](#) (const [EQueryLevel](#) &inQueryLevel) override
- bool [ValidateQuery](#) (bool inStrict=true) const override

Public Member Functions inherited from [gdcm::BaseRootQuery](#)

- [~BaseRootQuery](#) () override=default
- [EQueryLevel GetQueryLevelFromQueryRoot](#) ([ERootType](#) roottype)

Public Member Functions inherited from [gdcm::BaseQuery](#)

- [~BaseQuery](#) () override
- void [AddQueryDataSet](#) (const [DataSet](#) &ds)
- [DataSet & GetQueryDataSet](#) ()
- [DataSet](#) const & [GetQueryDataSet](#) () const
Set/Get the internal representation of the query as a DataSet.
- [std::string GetSOPInstanceUID](#) () const
- void [Print](#) ([std::ostream](#) &os) const override
- void [SetSearchParameter](#) (const [std::string](#) &inKeyword, const [std::string](#) &inValue)
- void [SetSearchParameter](#) (const [Tag](#) &inTag, const [std::string](#) &inValue)
- void [SetSOPInstanceUID](#) (const [std::string](#) &iSopInstanceUID)
- const [std::ostream](#) & [WriteHelpFile](#) ([std::ostream](#) &os)
- bool [WriteQuery](#) (const [std::string](#) &inFileName)

Public Member Functions inherited from [gdcm::Object](#)

- [Object](#) ()
- [Object](#) (const [Object](#) &)
Special requirement for copy/cstor, assignment operator.
- virtual [~Object](#) ()
- void [operator=](#) (const [Object](#) &)

Protected Member Functions

- [DataSet](#) [GetValidDataSet](#) () const

Protected Member Functions inherited from [gdcm::BaseRootQuery](#)

- [BaseRootQuery](#) ()

Protected Member Functions inherited from [gdcm::BaseQuery](#)

- [BaseQuery](#) ()
- void [SetSearchParameter](#) (const [Tag](#) &inTag, const [DictEntry](#) &inDictEntry, const std::string &inValue)
- bool [ValidDataSet](#) (const [DataSet](#) &dataSetToValid, const [DataSet](#) &dataSetReference) const

Protected Member Functions inherited from [gdcm::Object](#)

- void [Register](#) ()
- void [UnRegister](#) ()

Friends

- class [QueryFactory](#)

Additional Inherited Members

Static Public Member Functions inherited from [gdcm::BaseRootQuery](#)

- static [QueryBase](#) * [Construct](#) ([ERootType](#) inRootType, [EQueryLevel](#) qllevel)
- static int [GetQueryLevelFromString](#) (const char *str)
- static const char * [GetQueryLevelString](#) ([EQueryLevel](#) ql)

Protected Attributes inherited from [gdcm::BaseRootQuery](#)

- std::string [mHelpDescription](#)
- [QueryImage](#) [mImage](#)
- [QueryPatient](#) [mPatient](#)
- [ERootType](#) [mRootType](#)
- [QuerySeries](#) [mSeries](#)
- [QueryStudy](#) [mStudy](#)

Protected Attributes inherited from [gdcm::BaseQuery](#)

- [DataSet](#) [mDataSet](#)
- std::string [mSopInstanceUID](#)

10.399.1 Detailed Description

PatientRootQuery.

contains: the class which will produce a dataset for c-find with patient root

10.399.2 Constructor & Destructor Documentation

10.399.2.1 WLMFindQuery()

```
gdcm::WLMFindQuery::WLMFindQuery ()
```

10.399.3 Member Function Documentation

10.399.3.1 GetAbstractSyntaxUID()

```
UIDs::TSName gdcm::WLMFindQuery::GetAbstractSyntaxUID () const [override], [virtual]
```

Implements [gdcm::BaseQuery](#).

10.399.3.2 GetTagListByLevel()

```
std::vector< Tag > gdcm::WLMFindQuery::GetTagListByLevel (
    const EQueryLevel & inQueryLevel) [override], [virtual]
```

this function will return all tags at a given query level, so that they maybe selected for searching. The boolean forFind is true if the query is a find query, or false for a move query.

Implements [gdcm::BaseRootQuery](#).

10.399.3.3 GetValidDataSet()

```
DataSet gdcm::WLMFindQuery::GetValidDataSet () const [protected]
```

10.399.3.4 InitializeDataSet()

```
void gdcm::WLMFindQuery::InitializeDataSet (
    const EQueryLevel & inQueryLevel) [override], [virtual]
```

this function sets tag 8,52 to the appropriate value based on query level also fills in the right unique tags, as per the standard's requirements should allow for connection with dcmTk

Implements [gdcm::BaseRootQuery](#).

10.399.3.5 ValidateQuery()

```
bool gdcm::WLMFindQuery::ValidateQuery (
    bool inStrict = true) const [override], [virtual]
```

have to be able to ensure that 0x8,0x52 is set (which will be true if InitializeDataSet is called...) that the level is appropriate (ie, not setting PATIENT for a study query that the tags in the query match the right level (either required, unique, optional) by default, this function checks to see if the query is for finding, which is more permissive than for moving. For moving, only the unique tags are allowed. 10 Jan 2011: adding in the 'strict' mode. according to the standard (at least, how I've read it), only tags for a particular level should be allowed in a particular query (ie, just series level tags in a series level query). However, it seems that dcm4chee doesn't share that interpretation. So, if 'inStrict' is false, then tags from the current level and all higher levels are now considered valid. So, if you're doing a non-strict series-level query, tags from the patient and study level can be passed along as well.

Implements [gdcm::BaseRootQuery](#).

10.399.4 Friends And Related Symbol Documentation

10.399.4.1 QueryFactory

```
friend class QueryFactory [friend]
```

References [QueryFactory](#).

Referenced by [QueryFactory](#).

The documentation for this class was generated from the following file:


- [gdcmWLMFindQuery.h](#)

10.400 gdcm::Writer Class Reference


[Writer](#) ala DOM (Document [Object](#) Model)

```
#include <gdcmWriter.h>
```

Inheritance diagram for gdcm::Writer:



Collaboration diagram for gdcm::Writer:



Public Member Functions

- [Writer](#) ()
- virtual [~Writer](#) ()
- void [CheckFileMetaInformationOff](#) ()
- void [CheckFileMetaInformationOn](#) ()
- [File](#) & [GetFile](#) ()
- void [SetCheckFileMetaInformation](#) (bool b)
Undocumented function, do not use (= leave default)
- void [SetFile](#) (const [File](#) &f)
Set/Get the DICOM file ([DataSet](#) + Header)
- void [SetFileName](#) (const char *filename_native)

Set the filename of DICOM file to write:

- void [SetStream](#) (std::ostream &output_stream)

Set user ostream buffer.

- virtual bool [Write](#) ()

Main function to tell the writer to write.

Protected Member Functions

- bool [GetCheckFileMetaInformation](#) () const
- std::ostream * [GetStreamPtr](#) () const
- void [SetWriteDataSetOnly](#) (bool b)

Protected Attributes

- std::ofstream * [Ofstream](#)
- std::ostream * [Stream](#)

Friends

- class [StreamImageWriter](#)

10.400.1 Detailed Description

[Writer](#) ala DOM (Document [Object](#) Model)

This class is a non-validating writer, it will only performs well- formedness check only.

Detailed description here To avoid GDCM being yet another broken DICOM lib we try to be user level and avoid writing illegal stuff (odd length, non-zero value for [Item](#) start/end length ...) Therefore you cannot (well unless you are really smart) write DICOM with even length tag. All the checks are consider basics:

- Correct Meta Information Header (see [gdcm::FileMetaInformation](#))
- Zero value for [Item](#) Length (0xfffe, 0xe00d/0xe0dd)
- Even length for any elements
- Alphabetical order for elements (guaranteed by design of internals)
- 32bits [VR](#) will be rewritten with 00

Warning

[gdcm::Writer](#) cannot write a [DataSet](#) if no SOP Instance UID (0008,0018) is found, unless a [DICOMDIR](#) is being written out

See also

[Reader DataSet File](#)

Examples

[ChangePrivateTags.cxx](#), [ChangeSequenceUltrasound.cxx](#), [ClinicalTrialAnnotate.cxx](#), [CreateFakeRTDOSE.cxx](#), [CreateJPIPDataSet.cxx](#), [DeriveSeries.cxx](#), [DuplicatePCDE.cxx](#), [EncapsulateFileInRawData.cxx](#), [Extracting_All_Resolution.cxx](#), [Fake_Image_Using_Stream_Image_Writer.cxx](#), [FixBrokenJ2K.cxx](#), [FixJAIBugJPEGLS.cxx](#), [FixOrientation.cxx](#), [GenAllVR.cxx](#), [GenFakeIdentifyFile.cxx](#), [GenLongSeqs.cxx](#), [GenSeqs.cxx](#), [GenerateDICOMDIR.cs](#), [HelloWorld.cxx](#), [LargeVRDSExplicit.cxx](#), [MakeTemplate.cxx](#), [ManipulateFile.cs](#), [NewSequence.cs](#), [PatchFile.cxx](#), [QIDO-RS.cxx](#), [ReformatFile.cs](#), [StreamImageReaderTest.cxx](#), [pmsct_rgb1.cxx](#), and [rle2img.cxx](#).

10.400.2 Constructor & Destructor Documentation

10.400.2.1 Writer()

```
gdcm::Writer::Writer ()
```

10.400.2.2 ~Writer()

```
virtual gdcm::Writer::~Writer () [virtual]
```

10.400.3 Member Function Documentation

10.400.3.1 CheckFileMetaInformationOff()

```
void gdcm::Writer::CheckFileMetaInformationOff () [inline]
```

Examples

[CreateFakeRTDOSE.cxx](#), [FixBrokenJ2K.cxx](#), and [HelloWorld.cxx](#).

10.400.3.2 CheckFileMetaInformationOn()

```
void gdcm::Writer::CheckFileMetaInformationOn () [inline]
```

10.400.3.3 GetCheckFileMetaInformation()

```
bool gdcm::Writer::GetCheckFileMetaInformation () const [inline], [protected]
```

10.400.3.4 GetFile()

```
File & gdcm::Writer::GetFile () [inline]
```

Examples

[CreateJPIPDataSet.cxx](#), [EncapsulateFileInRawData.cxx](#), [Extracting_All_Resolution.cxx](#), [Fake_Image_Using_Stream_Image_Writer](#), [GenAllVR.cxx](#), [GenFakeIdentifyFile.cxx](#), [GetSubSequenceData.cxx](#), [MpegVideoInfo.cs](#), [QIDO-RS.cxx](#), [StreamImageReaderTest.cxx](#), [TemplateEmptyImage.cxx](#), [iU22tomultisc.cxx](#), [pmsct_rgb1.cxx](#), and [rle2img.cxx](#).

10.400.3.5 GetStreamPtr()

```
std::ostream * gdcmm::Writer::GetStreamPtr () const [inline], [protected]
```

References [Stream](#).

10.400.3.6 SetCheckFileMetaInformation()

```
void gdcmm::Writer::SetCheckFileMetaInformation (
    bool b) [inline]
```

Undocumented function, do not use (= leave default)

Examples

[GenAllVR.cxx](#), [GenFakeIdentifyFile.cxx](#), and [PatchFile.cxx](#).

10.400.3.7 SetFile()

```
void gdcmm::Writer::SetFile (
    const File & f) [inline]
```

Set/Get the DICOM file ([DataSet](#) + Header)

Examples

[BasicAnonymizer.cs](#), [BasicImageAnonymizer.cs](#), [ChangePrivateTags.cxx](#), [ChangeSequenceUltrasound.cxx](#), [Cleaner.cs](#), [ClinicalTrialAnnotate.cxx](#), [ClinicalTrialIdentificationWorkflow.cs](#), [CompressImage.cxx](#), [CompressLossyJPEG.cs](#), [CreateFakeRTDOSE.cxx](#), [DecompressImage.cs](#), [DeriveSeries.cxx](#), [DuplicatePCDE.cxx](#), [FixBrokenJ2K.cxx](#), [FixJAIBugJPEGLS.cxx](#), [FixOrientation.cxx](#), [GenFakeImage.cxx](#), [GenLongSeqs.cxx](#), [GenSeqs.cxx](#), [GenerateDICOMDIR.cs](#), [HelloWorld.cxx](#), [LargeVRDSExplicit.cxx](#), [MakeTemplate.cxx](#), [ManipulateFile.cs](#), [MergeTwoFiles.cxx](#), [NewSequence.cs](#), [PatchFile.cxx](#), [ReformatFile.cs](#), [StandardizeFiles.cs](#), [pmsct_rgb1.cxx](#), and [rle2img.cxx](#).

10.400.3.8 SetFileName()

```
void gdcmm::Writer::SetFileName (
    const char * filename_native)
```

Set the filename of DICOM file to write:

Examples

[BasicAnonymizer.cs](#), [BasicImageAnonymizer.cs](#), [ChangePrivateTags.cxx](#), [ChangeSequenceUltrasound.cxx](#), [Cleaner.cs](#), [ClinicalTrialAnnotate.cxx](#), [ClinicalTrialIdentificationWorkflow.cs](#), [CompressImage.cxx](#), [CompressLossyJPEG.cs](#), [CreateARGBImage.cxx](#), [CreateCMYKImage.cxx](#), [CreateFakeRTDOSE.cxx](#), [CreateJPIPDataSet.cxx](#), [DecompressImage.cs](#), [DeriveSeries.cxx](#), [DuplicatePCDE.cxx](#), [EncapsulateFileInRawData.cxx](#), [FixBrokenJ2K.cxx](#), [FixJAIBugJPEGLS.cxx](#), [FixOrientation.cxx](#), [GenAllVR.cxx](#), [GenFakeIdentifyFile.cxx](#), [GenFakeImage.cxx](#), [GenLongSeqs.cxx](#), [GenSeqs.cxx](#), [GenerateDICOMDIR.cs](#), [GetSubSequenceData.cxx](#), [HelloVizWorld.cxx](#), [HelloWorld.cxx](#), [LargeVRDSExplicit.cxx](#), [MakeTemplate.cxx](#), [ManipulateFile.cs](#), [MergeTwoFiles.cxx](#), [MpegVideoInfo.cs](#), [NewSequence.cs](#), [PatchFile.cxx](#), [QIDO-RS.cxx](#), [ReformatFile.cs](#), [StandardizeFiles.cs](#), [TemplateEmptyImage.cxx](#), [csa2img.cxx](#), [iU22tomultisc.cxx](#), [pmsct_rgb1.cxx](#), and [rle2img.cxx](#).

10.400.3.9 SetStream()

```
void gdcmm::Writer::SetStream (
    std::ostream & output_stream) [inline]
```

Set user ostream buffer.

References [Stream](#).

10.400.3.10 SetWriteDataSetOnly()

```
void gdcmm::Writer::SetWriteDataSetOnly (
    bool b) [inline], [protected]
```

10.400.3.11 Write()

```
virtual bool gdcmm::Writer::Write () [virtual]
```

Main function to tell the writer to write.

Reimplemented in [gdcmm::ImageWriter](#), [gdcmm::PixmapWriter](#), [gdcmm::SegmentWriter](#), and [gdcmm::SurfaceWriter](#).

Examples

[BasicAnonymizer.cs](#), [ChangePrivateTags.cxx](#), [ChangeSequenceUltrasound.cxx](#), [Cleaner.cs](#), [ClinicalTrialAnnotate.cxx](#), [ClinicalTrialIdentificationWorkflow.cs](#), [CreateFakeRTDOSE.cxx](#), [CreateJPIPDataSet.cxx](#), [DeriveSeries.cxx](#), [DuplicatePCDE.cxx](#), [EncapsulateFileInRawData.cxx](#), [FixBrokenJ2K.cxx](#), [FixJAI BugJPEGLS.cxx](#), [FixOrientation.cxx](#), [GenAllVR.cxx](#), [GenFakeIdentifyFile.cxx](#), [GenLongSeqs.cxx](#), [GenSeqs.cxx](#), [GenerateDICOMDIR.cs](#), [HelloWorld.cxx](#), [LargeVRDSExplicit.cxx](#), [MakeTemplate.cxx](#), [ManipulateFile.cs](#), [NewSequence.cs](#), [PatchFile.cxx](#), [QIDO-RS.cxx](#), [ReformatFile.cs](#), [pmsct_rgb1.cxx](#), and [rle2img.cxx](#).

10.400.4 Friends And Related Symbol Documentation

10.400.4.1 StreamImageWriter

```
friend class StreamImageWriter [friend]
```

References [StreamImageWriter](#).

Referenced by [StreamImageWriter](#).

10.400.5 Member Data Documentation

10.400.5.1 Ofstream

```
std::ofstream* gdcmm::Writer::Ofstream [protected]
```

10.400.5.2 Stream

```
std::ostream* gdcM::Writer::Stream [protected]
```

Referenced by [GetStreamPtr\(\)](#), and [SetStream\(\)](#).

The documentation for this class was generated from the following file:


- [gdcMWriter.h](#)

10.401 gdcM::XMLDictReader Class Reference


Class for representing a [XMLDictReader](#).

```
#include <gdcMXMLDictReader.h>
```

Inheritance diagram for gdcM::XMLDictReader:



Collaboration diagram for gdcM::XMLDictReader:



Public Member Functions

- [XMLDictReader](#) ()
- [~XMLDictReader](#) ()
- void [CharacterDataHandler](#) (const char *data, int length)
- void [EndElement](#) (const char *name)
- const [Dict](#) & [GetDict](#) ()
- void [StartElement](#) (const char *name, const char **atts)

Public Member Functions inherited from [gdcm::TableReader](#)

- [TableReader](#) (Defs &defs)
- virtual [~TableReader](#) ()=default
- const [Defs](#) & [GetDefs](#) () const
- const char * [GetFilename](#) ()
- void [HandleIOD](#) (const char **atts)
- void [HandleIODEntry](#) (const char **atts)
- void [HandleMacro](#) (const char **atts)
- void [HandleMacroEntry](#) (const char **atts)
- void [HandleMacroEntryDescription](#) (const char **atts)
- void [HandleModule](#) (const char **atts)
- void [HandleModuleEntry](#) (const char **atts)
- void [HandleModuleEntryDescription](#) (const char **atts)
- void [HandleModuleInclude](#) (const char **atts)
- int [Read](#) ()
- void [SetFilename](#) (const char *filename)

Protected Member Functions

- void [HandleDescription](#) (const char **atts)
- void [HandleEntry](#) (const char **atts)

10.401.1 Detailed Description

Class for representing a [XMLDictReader](#).

Note

bla Will read the DICOMV3.xml file

10.401.2 Constructor & Destructor Documentation

10.401.2.1 XMLDictReader()

```
gdcm::XMLDictReader::XMLDictReader ()
```

10.401.2.2 ~XMLDictReader()

```
gdcM::XMLDictReader::~XMLDictReader () [inline]
```

10.401.3 Member Function Documentation

10.401.3.1 CharacterDataHandler()

```
void gdcM::XMLDictReader::CharacterDataHandler (
    const char * data,
    int length) [virtual]
```

Reimplemented from [gdcM::TableReader](#).

10.401.3.2 EndElement()

```
void gdcM::XMLDictReader::EndElement (
    const char * name) [virtual]
```

Reimplemented from [gdcM::TableReader](#).

10.401.3.3 GetDict()

```
const Dict & gdcM::XMLDictReader::GetDict () [inline]
```

10.401.3.4 HandleDescription()

```
void gdcM::XMLDictReader::HandleDescription (
    const char ** atts) [protected]
```

10.401.3.5 HandleEntry()

```
void gdcM::XMLDictReader::HandleEntry (
    const char ** atts) [protected]
```

10.401.3.6 StartElement()

```
void gdcM::XMLDictReader::StartElement (
    const char * name,
    const char ** atts) [virtual]
```

Reimplemented from [gdcM::TableReader](#).


The documentation for this class was generated from the following file:

- [gdcMXMLDictReader.h](#)

10.402 gdcm::XMLPrinter Class Reference

```
#include <gdcmXMLPrinter.h>
```

Collaboration diagram for gdcm::XMLPrinter:



Public Types

- enum `PrintStyles` {
`OnlyUUID = 0` ,
`LOADBULKDATA = 1` }

Public Member Functions

- `XMLPrinter ()`
- virtual `~XMLPrinter ()`
- `PrintStyles GetPrintStyle () const`
- virtual void `HandleBulkData` (const char *uuid, const `TransferSyntax` &ts, const char *bulkdata, size_t bulklen)
- void `Print` (std::ostream &os)
- void `PrintDataSet` (const `DataSet` &ds, const `TransferSyntax` &ts, std::ostream &os)
- void `SetFile` (`File` const &f)
- void `SetStyle` (`PrintStyles` ps)

Protected Member Functions

- VR `PrintDataElement` (std::ostream &os, const `Dicts` &dicts, const `DataSet` &ds, const `DataElement` &de, const `TransferSyntax` &ts)
- void `PrintSQ` (const `SequenceOfItems` *sqi, const `TransferSyntax` &ts, std::ostream &os)

Protected Attributes

- const [File](#) * `F`
- [PrintStyles](#) `PrintStyle`

10.402.1 Member Enumeration Documentation

10.402.1.1 PrintStyles

```
enum gdcm::XMLPrinter::PrintStyles
```

Enumerator

OnlyUUID	
LOADBULKDATA	

10.402.2 Constructor & Destructor Documentation

10.402.2.1 XMLPrinter()

```
gdcm::XMLPrinter::XMLPrinter ()
```

10.402.2.2 ~XMLPrinter()

```
virtual gdcm::XMLPrinter::~~XMLPrinter () [virtual]
```

10.402.3 Member Function Documentation

10.402.3.1 GetPrintStyle()

```
PrintStyles gdcm::XMLPrinter::GetPrintStyle () const [inline]
```

References [PrintStyle](#).

10.402.3.2 HandleBulkData()

```
virtual void gdcm::XMLPrinter::HandleBulkData (  
    const char * uuid,  
    const TransferSyntax & ts,  
    const char * bulkdata,  
    size_t bulklen) [virtual]
```

Virtual function mechanism to allow application programmer to override the default mechanism for BulkData handling. By default GDCM will simply discard the BulkData and only write the UUID

10.402.3.3 Print()

```
void gdcm::XMLPrinter::Print (
    std::ostream & os)
```

10.402.3.4 PrintDataElement()

```
VR gdcm::XMLPrinter::PrintDataElement (
    std::ostream & os,
    const Dicts & dicts,
    const DataSet & ds,
    const DataElement & de,
    const TransferSyntax & ts) [protected]
```

10.402.3.5 PrintDataSet()

```
void gdcm::XMLPrinter::PrintDataSet (
    const DataSet & ds,
    const TransferSyntax & ts,
    std::ostream & os)
```

10.402.3.6 PrintSQ()

```
void gdcm::XMLPrinter::PrintSQ (
    const SequenceOfItems * sqi,
    const TransferSyntax & ts,
    std::ostream & os) [protected]
```

10.402.3.7 SetFile()

```
void gdcm::XMLPrinter::SetFile (
    File const & f) [inline]
```

References [F](#).

10.402.3.8 SetStyle()

```
void gdcm::XMLPrinter::SetStyle (
    PrintStyles ps) [inline]
```

References [PrintStyle](#).

10.402.4 Member Data Documentation

10.402.4.1 F

```
const File* gdcm::XMLPrinter::F [protected]
```

Referenced by [SetFile\(\)](#).

10.402.4.2 PrintStyle

```
PrintStyles gdcm::XMLPrinter::PrintStyle [protected]
```

Referenced by [GetPrintStyle\(\)](#), and [SetStyle\(\)](#).

The documentation for this class was generated from the following file:


- [gdcmXMLPrinter.h](#)

10.403 gdcm::XMLPrivateDictReader Class Reference


Class for representing a [XMLPrivateDictReader](#).

```
#include <gdcmXMLPrivateDictReader.h>
```

Inheritance diagram for gdcm::XMLPrivateDictReader:



Collaboration diagram for gdcm::XMLPrivateDictReader:



Public Member Functions

- [XMLPrivateDictReader](#) ()
- [~XMLPrivateDictReader](#) ()
- void [CharacterDataHandler](#) (const char *data, int length)
- void [EndElement](#) (const char *name)
- const [PrivateDict](#) & [GetPrivateDict](#) ()
- void [StartElement](#) (const char *name, const char **atts)

Public Member Functions inherited from [gdcm::TableReader](#)

- [TableReader](#) (Defs &defs)
- virtual [~TableReader](#) ()=default
- const [Defs](#) & [GetDefs](#) () const
- const char * [GetFilename](#) ()
- void [HandleIOD](#) (const char **atts)
- void [HandleIODEntry](#) (const char **atts)
- void [HandleMacro](#) (const char **atts)
- void [HandleMacroEntry](#) (const char **atts)
- void [HandleMacroEntryDescription](#) (const char **atts)
- void [HandleModule](#) (const char **atts)
- void [HandleModuleEntry](#) (const char **atts)
- void [HandleModuleEntryDescription](#) (const char **atts)
- void [HandleModuleInclude](#) (const char **atts)
- int [Read](#) ()
- void [SetFilename](#) (const char *filename)

Protected Member Functions

- void [HandleDescription](#) (const char **atts)
- void [HandleEntry](#) (const char **atts)

10.403.1 Detailed Description

Class for representing a [XMLPrivateDictReader](#).

Note

bla Will read the Private.xml file

10.403.2 Constructor & Destructor Documentation

10.403.2.1 XMLPrivateDictReader()

```
gdcM::XMLPrivateDictReader::XMLPrivateDictReader ()
```

10.403.2.2 ~XMLPrivateDictReader()

```
gdcM::XMLPrivateDictReader::~~XMLPrivateDictReader () [inline]
```

10.403.3 Member Function Documentation

10.403.3.1 CharacterDataHandler()

```
void gdcM::XMLPrivateDictReader::CharacterDataHandler (
    const char * data,
    int length) [virtual]
```

Reimplemented from [gdcM::TableReader](#).

10.403.3.2 EndElement()

```
void gdcM::XMLPrivateDictReader::EndElement (
    const char * name) [virtual]
```

Reimplemented from [gdcM::TableReader](#).

10.403.3.3 GetPrivateDict()

```
const PrivateDict & gdcM::XMLPrivateDictReader::GetPrivateDict () [inline]
```


10.403.3.4 HandleDescription()

```
void gdcm::XMLPrivateDictReader::HandleDescription (  
    const char ** atts) [protected]
```

10.403.3.5 HandleEntry()

```
void gdcm::XMLPrivateDictReader::HandleEntry (  
    const char ** atts) [protected]
```

10.403.3.6 StartElement()

```
void gdcm::XMLPrivateDictReader::StartElement (  
    const char * name,  
    const char ** atts) [virtual]
```

Reimplemented from [gdcm::TableReader](#).

The documentation for this class was generated from the following file:

- [gdcmXMLPrivateDictReader.h](#)

Chapter 11


File Documentation

11.1 README.txt File Reference

11.2 TestsList.txt File Reference

11.3 gdc ASN1.h File Reference

```
#include "gdcTypes.h"
Include dependency graph for gdc ASN1.h:
```



Classes

- class `gdc::ASN1`
Class for `ASN1`.

Namespaces

- namespace [gdcm](#)

11.4 gdcmASN1.h

[Go to the documentation of this file.](#)

```


00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMASN1_H
00015 #define GDCMASN1_H
00016
00017 #include "gdcmTypes.h"
00018
00019 namespace gdcm
00020 {
00021 {
00022 //-----
00023 class ASN1Internals;
00024 class GDCM_EXPORT ASN1
00025 {
00026 public :
00027     ASN1();
00028     ~ASN1();
00029
00030     static bool ParseDumpFile(const char *filename);
00031
00032     static bool ParseDump(const char *array, size_t length);
00033
00034     ASN1(const ASN1&) = delete;
00035     void operator=(const ASN1&) = delete;
00036 protected:
00037     int TestPBKDF2();
00038 private:
00039     ASN1Internals *Internals;
00040 };
00041 } // end namespace gdcm
00042 //-----
00043 #endif //GDCMASN1_H

```

11.5 gdcmBase64.h File Reference

```
#include "gdcmTypes.h"
```

Include dependency graph for gdcmBase64.h:



Classes

- class [gdcm::Base64](#)
Class for [Base64](#).

Namespaces

- namespace [gdcm](#)

11.6 gdcmBase64.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013  =====*/
00014 #ifndef GDCMBASE64_H
00015 #define GDCMBASE64_H
00016
00017 #include "gdcmTypes.h"
00018
00019 namespace gdcm
00020 {
00021
00025   class GDCM_EXPORT Base64

```

```


00026 {
00027 public:
00028
00032     static size_t GetEncodeLength(const char *src, size_t srclen );
00033
00045     static size_t Encode( char *dst, size_t dlen, const char *src, size_t slen );
00046
00050     static size_t GetDecodeLength( const char *src, size_t len );
00051
00062     static size_t Decode( char *dst, size_t dlen, const char *src, size_t slen );
00063
00064     Base64(const Base64&) = delete;
00065     void operator=(const Base64&) = delete;
00066 };
00067
00068 } // end namespace gdcM
00069
00070 #endif // GDCMBASE64_H

```

11.7 gdcMBoxRegion.h File Reference

```
#include "gdcMRegion.h"
```

Include dependency graph for gdcMBoxRegion.h:



Classes

- class `gdcM::BoxRegion`
Class for manipulation box region.

Namespaces

- namespace `gdcM`

11.8 gdcmBoxRegion.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMBOXREGION_H
00015 #define GDCMBOXREGION_H
00016
00017 #include "gdcmRegion.h"
00018
00019 namespace gdcm
00020 {
00021   class BoxRegionInternals;
00022
00023   //-----
00024   class GDCM_EXPORT BoxRegion : public Region
00025   {
00026   public :
00027     BoxRegion();
00028     ~BoxRegion() override;
00029
00030     void SetDomain(unsigned int xmin, unsigned int xmax,
00031                   unsigned int ymin, unsigned int ymax,
00032                   unsigned int zmin, unsigned int zmax);
00033
00034     unsigned int GetXMin() const;
00035     unsigned int GetXMax() const;
00036     unsigned int GetYMin() const;
00037     unsigned int GetYMax() const;
00038     unsigned int GetZMin() const;
00039     unsigned int GetZMax() const;
00040
00041     // Satisfy pure virtual parent class
00042     Region *Clone() const override;
00043     bool Empty() const override;
00044     bool IsValid() const override;
00045     size_t Area() const override;
00046     BoxRegion ComputeBoundingBox() override;
00047
00048     void Print(std::ostream &os = std::cout) const override;
00049
00050     static BoxRegion BoundingBox(BoxRegion const & b1, BoxRegion const & b2 );
00051
00052     BoxRegion(const BoxRegion&);
00053     void operator=(const BoxRegion&);
00054 private:
00055     BoxRegionInternals *Internals;
00056   };
00057
00058 } // end namespace gdcm
00059 //-----
00060 #endif //GDCMREGION_H

```

11.9 gdcmByteSwap.h File Reference


```

#include "gdcmTypes.h"
#include "gdcmSwapCode.h"

```

```
#include "gdcmByteSwap.txx"
```

Include dependency graph for gdcmByteSwap.h:



Classes

- class [gdcm::ByteSwap< T >](#)
ByteSwap.

Namespaces

- namespace [gdcm](#)

11.10 gdcmByteSwap.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013   =====*/
00014 #ifndef GDCMBYTESWAP_H
00015 #define GDCMBYTESWAP_H
00016
00017 #include "gdcmTypes.h"
00018 #include "gdcmSwapCode.h"
00019
00020 namespace gdcm
00021 {
00022
00029 template<class T>

```



```


00030 class ByteSwap
00031 {
00032 public:
00034     static bool SystemIsBigEndian ();
00035     static bool SystemIsLittleEndian ();
00036
00037     static void Swap(T &p);
00038     static void SwapFromSwapCodeIntoSystem(T &p, SwapCode const &sc);
00039     static void SwapRange(T *p, unsigned int num);
00040     static void SwapRangeFromSwapCodeIntoSystem(T *p, SwapCode const &sc,
00041         std::streamoff num);
00042
00043 protected:
00044     // ByteSwap() {}
00045     // ~ByteSwap() {}
00046
00047 private:
00048
00049 };
00050
00055
00056 } // end namespace gdcm
00057
00058 #include "gdcmByteSwap.txx"
00059
00060 #endif //GDCMBYTESWAP_H

```

11.11 gdcmCAPICryptoFactory.h File Reference

```
#include "gdcmCryptoFactory.h"
```

Include dependency graph for gdcmCAPICryptoFactory.h:



Classes

- class `gdcm::CAPICryptoFactory`

Namespaces

- namespace [gdcm](#)

11.12 gdcmCAPICryptoFactory.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMCAPICRYPTOFACTORY_H
00015 #define GDCMCAPICRYPTOFACTORY_H
00016
00017 #include "gdcmCryptoFactory.h"
00018
00019 namespace gdcm
00020 {
00021
00022 class GDCM_EXPORT CAPICryptoFactory : public CryptoFactory
00023 {
00024 public:
00025     CAPICryptoFactory(CryptoLib id);
00026     CryptographicMessageSyntax* CreateCMSProvider();
00027
00028 private:
00029     CAPICryptoFactory() {}
00030 };
00031
00032 } // end namespace gdcm
00033
00034 #endif //GDCMCAPICRYPTOFACTORY_H

```


11.13 gdcmCAPICryptographicMessageSyntax.h File Reference

```

#include "gdcmCryptographicMessageSyntax.h"
#include <windows.h>
#include <wincrypt.h>
#include <vector>

```

Include dependency graph for gdcmCAPICryptographicMessageSyntax.h:



Classes

- class [gdcm::CAPICryptographicMessageSyntax](#)

Namespaces

- namespace [gdcm](#)

11.14 gdcmCAPICryptographicMessageSyntax.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013  =====*/
00014 #ifndef GDCMCAPICRYPTOGRAPHICMESSAGESYNTAX_H
00015 #define GDCMCAPICRYPTOGRAPHICMESSAGESYNTAX_H
00016
00017 #include "gdcmCryptographicMessageSyntax.h"
00018 #include <windows.h>
00019 #include <wincrypt.h>
00020 #include <vector>
00021
00022 namespace gdcm
00023 {
00024
00025   class GDCM_EXPORT CAPICryptographicMessageSyntax : public CryptographicMessageSyntax
00026   {
00027   public:


```

```
00028  CAPICryptographicMessageSyntax();
00029  ~CAPICryptographicMessageSyntax();
00030
00031  // X.509
00032  bool ParseCertificateFile( const char *filename );
00033  bool ParseKeyFile( const char *filename );
00034
00035  // PBE
00036  bool SetPassword(const char * pass, size_t passLen);
00037
00038  void SetCipherType(CipherTypes type);
00039
00040  CipherTypes GetCipherType() const;
00041
00042  bool Encrypt(char *output, size_t &outlen, const char *array, size_t len) const;
00043  bool Decrypt(char *output, size_t &outlen, const char *array, size_t len) const;
00044
00045  bool GetInitialized() const
00046  {
00047      return initialized;
00048  }
00049
00050 private:
00051  bool Initialize();
00052  static ALG_ID GetAlgIdByObjId(const char * pszObjId);
00053  static const char *GetCipherObjId() const;
00054  static void ReverseBytes(unsigned char* data, DWORD len);
00055  static bool LoadFile(const char * filename, unsigned char* & buffer, DWORD & bufLen);
00056
00057 private:
00058  bool initialized;
00059  HCRYPTPROV hProv;
00060  std::vector<PCCERT_CONTEXT> certifList;
00061  HCRYPTKEY hRsaPrivK;
00062  CipherTypes cipherType;
00063 };
00064
00065 } // end namespace gdc
00066
00067 #endif // GDCMCAPICRYPTOGRAPHICMESSAGESYNTAX_H
```


11.15 gdcmCommand.h File Reference

```
#include "gdcmSubject.h"
```

Include dependency graph for gdcmCommand.h:



This graph shows which files directly or indirectly include this file:



Classes

- class `gdcm::Command`
Command superclass for callback/observer methods.
- class `gdcm::MemberCommand< T >`
Command subclass that calls a pointer to a member function.
- class `gdcm::SimpleMemberCommand< T >`
Command subclass that calls a pointer to a member function.

Namespaces

- namespace `gdcm`

11.16 `gdcmCommand.h`

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMCOMMAND_H
00015 #define GDCMCOMMAND_H
00016
00017 #include "gdcmSubject.h"
00018
00019 namespace gdcm
00020 {
00021   class Event;
00022
00023   class GDCM_EXPORT Command : public Subject
00024   {
00025   public :
00026     Command(const Command&) = delete;
00027     void operator=(const Command&) = delete;
00028
00029     virtual void Execute(Subject *caller, const Event & event ) = 0;
00030     virtual void Execute(const Subject *caller, const Event & event ) = 0;
00031
00032   protected:
00033     Command();
00034     ~Command() override;
00035   };
00036
00037   template <class T>
00038   class MemberCommand : public Command
00039   {
00040   public:
00041     typedef void (T::*TMemberFunctionPointer)(Subject*, const Event &);
00042     typedef void (T::*TConstMemberFunctionPointer)(const Subject*,
00043                                                     const Event &);
00044
00045     typedef MemberCommand      Self;
00046     //typedef SmartPointer<Self> Pointer;
00047
00048     MemberCommand(const Self&) = delete;
00049     void operator=(const Self&) = delete;
00050
00051     static SmartPointer<MemberCommand> New()
00052     {
00053       return new MemberCommand;
00054     }
00055
00056     //gdcmTypeMacro(MemberCommand,Command);
00057
00058     void SetCallbackFunction(T* object,
00059                             TMemberFunctionPointer memberFunction)
00060     {
00061       m_This = object;
00062       m_MemberFunction = memberFunction;
00063     }
00064     void SetCallbackFunction(T* object,

```

```

00089             TConstMemberFunctionPointer memberFunction)
00090     {
00091         m_This = object;
00092         m_ConstMemberFunction = memberFunction;
00093     }
00094
00096 void Execute(Subject *caller, const Event & event ) override
00097 {
00098     if( m_MemberFunction )
00099     {
00100         ((*m_This).*(m_MemberFunction))(caller, event);
00101     }
00102 }
00103
00105 void Execute( const Subject *caller, const Event & event ) override
00106 {
00107     if( m_ConstMemberFunction )
00108     {
00109         ((*m_This).*(m_ConstMemberFunction))(caller, event);
00110     }
00111 }
00112
00113 protected:
00114
00115     T* m_This;
00116     TMemberFunctionPointer m_MemberFunction;
00117     TConstMemberFunctionPointer m_ConstMemberFunction;
00118     MemberCommand():m_This(nullptr),m_MemberFunction(nullptr),m_ConstMemberFunction(nullptr) {}
00119     ~MemberCommand() override= default;
00120
00121 };
00122
00129 template <typename T>
00130 class SimpleMemberCommand : public Command
00131 {
00132 public:
00133
00135     typedef void (T::*TMemberFunctionPointer) ();
00136
00138     typedef SimpleMemberCommand Self;
00139     //typedef SmartPointer<Self> Pointer;
00140
00141     SimpleMemberCommand(const Self&) = delete;
00142     void operator=(const Self&) = delete;
00143
00145     //gdcmTypeMacro(SimpleMemberCommand,Command);
00146
00148     static SmartPointer<SimpleMemberCommand> New()
00149     {
00150         return new SimpleMemberCommand;
00151     }
00152
00154     void SetCallbackFunction(T* object,
00155                             TMemberFunctionPointer memberFunction)
00156     {
00157         m_This = object;
00158         m_MemberFunction = memberFunction;
00159     }
00160
00162     void Execute(Subject *,const Event & ) override
00163     {
00164         if( m_MemberFunction )
00165         {
00166             ((*m_This).*(m_MemberFunction)) ();
00167         }
00168     }
00169     void Execute(const Subject *,const Event & ) override
00170     {
00171         if( m_MemberFunction )
00172         {
00173             ((*m_This).*(m_MemberFunction)) ();
00174         }
00175     }
00176
00177 protected:
00178     T* m_This;
00179     TMemberFunctionPointer m_MemberFunction;
00180     SimpleMemberCommand():m_This(nullptr),m_MemberFunction(nullptr) {}
00181     ~SimpleMemberCommand() override = default;
00182 };
00183

```

```

00184 } // end namespace gdcm
00185 //-----
00186 #endif //GDCMCOMMAND_H


```

11.17 gdcmCryptoFactory.h File Reference


```
#include "gdcmCryptographicMessageSyntax.h"
```

```
#include <map>
```

Include dependency graph for gdcmCryptoFactory.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::CryptoFactory](#)
Class to do handle the crypto factory.

Namespaces

- namespace [gdcm](#)

11.18 gdcmCryptoFactory.h

[Go to the documentation of this file.](#)

```


00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMCRYPTOFACTORY_H
00015 #define GDCMCRYPTOFACTORY_H
00016
00017 #include "gdcmCryptographicMessageSyntax.h"
00018 #include <map>
00019
00020 namespace gdcm
00021 {
00022
00023     class GDCM_EXPORT CryptoFactory
00024     {
00025     public:
00026         enum CryptoLib {DEFAULT = 0, OPENSSL = 1, CAPI = 2, OPENSSL7 = 3};
00027
00028         virtual CryptographicMessageSyntax* CreateCMSProvider() = 0;
00029         static CryptoFactory* GetFactoryInstance(CryptoLib id = DEFAULT);
00030
00031     protected:
00032         CryptoFactory(CryptoLib id)
00033         {
00034             AddLib(id, this);
00035         }
00036
00037     private:
00038         static std::map<CryptoLib, CryptoFactory*> getInstanceMap()
00039         {
00040             static std::map<CryptoLib, CryptoFactory*> libs;
00041             return libs;
00042         }
00043
00044         static void AddLib(CryptoLib id, CryptoFactory* f)
00045         {
00046             if (getInstanceMap().insert(std::pair<CryptoLib, CryptoFactory*>(id, f)).second == false)
00047             {
00048                 gdcmErrorMacro( "Library already registered under id " « (int)id );
00049             }
00050         }
00051
00052     protected:
00053         CryptoFactory()= default;
00054         ~CryptoFactory()= default;
00055     };
00056
00057 } // end namespace gdcm
00058
00059 #endif // GDCMCRYPTOFACTORY_H

```


11.19 gdcmCryptographicMessageSyntax.h File Reference

```
#include "gdcmTypes.h"
```

Include dependency graph for gdcmCryptographicMessageSyntax.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::CryptographicMessageSyntax](#)

Namespaces

- namespace [gdcm](#)

11.20 gdcmCryptographicMessageSyntax.h

[Go to the documentation of this file.](#)

```


00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMCRYPTOGRAPHICMESSAGESYNTAX_H
00015 #define GDCMCRYPTOGRAPHICMESSAGESYNTAX_H
00016
00017 #include "gdcmTypes.h"
00018
00019 namespace gdcm
00020 {
00021
00022 class GDCM_EXPORT CryptographicMessageSyntax
00023 {
00024 public:
00025     CryptographicMessageSyntax() = default;
00026
00027     virtual ~CryptographicMessageSyntax() = default;
00028     CryptographicMessageSyntax(const CryptographicMessageSyntax&) = delete;
00029     void operator=(const CryptographicMessageSyntax&) = delete;
00030
00031     typedef enum {
00032         DES3_CIPHER, // Triple DES
00033         AES128_CIPHER, // CBC AES
00034         AES192_CIPHER, // ' '
00035         AES256_CIPHER // ' '
00036     } CipherTypes;
00037
00038     // X.509
00039     virtual bool ParseCertificateFile( const char *filename ) = 0;
00040     virtual bool ParseKeyFile( const char *filename ) = 0;
00041
00042     // PBE
00043     virtual bool SetPassword(const char * pass, size_t passLen) = 0;
00044
00046     virtual bool Encrypt(char *output, size_t &outlen, const char *array, size_t len) const = 0;
00048     virtual bool Decrypt(char *output, size_t &outlen, const char *array, size_t len) const = 0;
00049
00050     virtual void SetCipherType(CipherTypes type) = 0;
00051
00052     virtual CipherTypes GetCipherType() const = 0;
00053 };
00054
00055 } // end namespace gdcm
00056
00057 #endif //GDCMCRYPTOGRAPHICMESSAGESYNTAX_H

```


11.21 gdcmDataEvent.h File Reference

```
#include "gdcmEvent.h"
```

Include dependency graph for gdcmDataEvent.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::DataEvent](#)
DataEvent.

Namespaces

- namespace [gdcm](#)

11.22 gdcmDataEvent.h

[Go to the documentation of this file.](#)

```


00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMDATAEVENT_H
00015 #define GDCMDATAEVENT_H
00016
00017 #include "gdcmEvent.h"
00018
00019 namespace gdcm
00020 {
00021
00022 class DataEvent : public AnyEvent
00023 {
00024 public:
00025     typedef DataEvent Self;
00026     typedef AnyEvent Superclass;
00027     DataEvent(const char *bytes = nullptr, size_t len = 0):Bytes(bytes),Length(len) {}
00028     ~DataEvent() override = default;
00029     DataEvent(const Self&s) : AnyEvent(s), Bytes(nullptr), Length(0) {}
00030     void operator=(const Self&) = delete;
00031
00032     const char * GetEventName() const override { return "DataEvent"; }
00033     bool CheckEvent(const ::gdcm::Event* e) const override
00034     { return (dynamic_cast<const Self*>(e) == nullptr ? false : true) ; }
00035     ::gdcm::Event* MakeObject() const override
00036     { return new Self; }
00037
00038     void SetData(const char *bytes, size_t len) {
00039         Bytes = bytes;
00040         Length = len;
00041     }
00042     size_t GetDataLength() const { return Length; }
00043     const char *GetData() const { return Bytes; }
00044
00045     //std::string GetValueAsString() const { return; }
00046
00047 private:
00048     const char *Bytes;
00049     size_t Length;
00050 };
00051
00052 } // end namespace gdcm
00053
00054 #endif //GDCMDATAEVENT_H

```

11.23 gdcmDeflateStream.h File Reference

```
#include "zipstreamimpl.h"
```

Include dependency graph for gdcmDeflateStream.h:



11.24 gdcmDeflateStream.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012   =====*/
00013
00014 #ifndef GDCMDEFLATESTREAM_H
00015 #define GDCMDEFLATESTREAM_H
00016
00017 #include "zipstreamimpl.h"
00018
00019 #endif //GDCMDEFLATESTREAM_H
  
```


11.25 gdcmDirectory.h File Reference

```

#include "gdcmTypes.h"
#include <string>
#include <vector>
#include <iostream>
  
```

```
#include <assert.h>
```

Include dependency graph for gdcmDirectory.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::Directory](#)
Class for manipulation directories.

Namespaces

- namespace [gdcm](#)

Functions

- `std::ostream & gdcm::operator<< (std::ostream &os, const Directory &d)`

11.26 gdcmDirectory.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even

```

```


00010     the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011     PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMDIRECTORY_H
00015 #define GDCMDIRECTORY_H
00016
00017 #include "gdcmTypes.h"
00018
00019 #include <string>
00020 #include <vector>
00021 #include <iostream>
00022 #include <assert.h>
00023
00024 namespace gdcm
00025 {
00041 //-----
00042 class GDCM_EXPORT Directory
00043 {
00044     friend std::ostream& operator<<(std::ostream &_os, const Directory &d);
00045 public :
00046     Directory() = default;
00047     ~Directory() = default;
00048     typedef std::string FilenameType;
00049     typedef std::vector<FilenameType> FilenamesType;
00050
00052     void Print(std::ostream &os = std::cout) const;
00053
00055     FilenameType const &GetToplevel() const { return Toplevel; }
00056
00058     FilenamesType const &GetFilenames() const {
00059         gdcm_assert( !(Toplevel.empty()) && "Need to call Explore first" );
00060         return Filenames; }
00061
00063     FilenamesType const &GetDirectories() const { return Directories; }
00064
00067     unsigned int Load(FilenameType const &name, bool recursive = false);
00068
00069     // \todo later: GLOB
00070     // The glob() function searches for all the pathnames matching pattern according to
00071     // the rules used by the shell (see glob(7)). No tilde expansion or parameter
00072     // substitution is done; if you want these, use wordexp(3).
00073     // int Glob(...);
00074
00075 protected:
00077     unsigned int Explore(FilenameType const &name, bool recursive);
00078
00079 private :
00081     FilenamesType Filenames;
00082     FilenamesType Directories;
00083
00085     FilenameType Toplevel;
00086 };
00087 //-----
00088 inline std::ostream& operator<<(std::ostream &os, const Directory &d)
00089 {
00090     d.Print( os );
00091     return os;
00092 }
00093
00094 } // end namespace gdcm
00095 //-----
00096 #endif //GDCMDIRECTORY_H

```


11.27 gdcmDummyValueGenerator.h File Reference

```
#include "gdcmTypes.h"
```

Include dependency graph for gdcmDummyValueGenerator.h:



Classes

- class [gdcm::DummyValueGenerator](#)
Class for generating dummy value.

Namespaces

- namespace [gdcm](#)

11.28 gdcmDummyValueGenerator.h

[Go to the documentation of this file.](#)

```

00001  /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013  =====*/
00014  #ifndef GDCMDUMMYVALUEGENERATOR_H
00015  #define GDCMDUMMYVALUEGENERATOR_H
00016
00017  #include "gdcmTypes.h"
00018
00019  namespace gdcm
00020  {
00021

```

```


00026 class GDCM_EXPORT DummyValueGenerator
00027 {
00028 public:
00029
00035     static const char* Generate(const char *input);
00036
00037 private:
00038 };
00039
00040
00041 } // end namespace gdcmm
00042
00043 #endif //GDCMDUMMYVALUEGENERATOR_H

```


11.29 gdcmmEvent.h File Reference

```
#include "gdcmmTypes.h"
```

Include dependency graph for gdcmmEvent.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcmm::AbortEvent](#)
- class [gdcmm::AnyEvent](#)
- class [gdcmm::EndEvent](#)
- class [gdcmm::Event](#)

superclass for callback/observer methods

- class [gdcm::ExitEvent](#)
- class [gdcm::InitializeEvent](#)
- class [gdcm::IterationEvent](#)
- class [gdcm::ModifiedEvent](#)
- class [gdcm::NoEvent](#)
- class [gdcm::StartEvent](#)
- class [gdcm::UserEvent](#)

Namespaces

- namespace [gdcm](#)

Macros

- `#define gdcmEventMacro(classname, super)`

Functions

- `std::ostream & gdcm::operator<< (std::ostream &os, const Event &e)`
Generic inserter operator for [Event](#) and its subclasses.

11.29.1 Macro Definition Documentation

11.29.1.1 gdcmEventMacro

```
#define gdcmEventMacro(
    classname,
    super)
```

Value:

```
\
class classname : public super { \
public: \
    typedef classname Self; \
    typedef super Superclass; \
    classname() {} \
    virtual ~classname() override = default; \
    virtual const char * GetEventName() const override { return #classname; } \
    virtual bool CheckEvent(const ::gdcm::Event* e) const override \
    { return dynamic_cast<const Self*>(e) ? true : false; } \
    virtual ::gdcm::Event* MakeObject() const override \
    { return new Self; } \
    classname(const Self&s) : super(s){} \
private: \
    void operator=(const Self&); \
}
```

11.30 gdcmEvent.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMEVENT_H
00015 #define GDCMEVENT_H
00016
00017 #include "gdcmTypes.h"
00018
00019 namespace gdcm
00020 {
00021 //-----
00022 class GDCM_EXPORT Event
00023 {
00024 public :
00025     Event();
00026     virtual ~Event();
00027     Event(const Event&);
00028     void operator=(const Event&) = delete;
00029
00030     virtual Event* MakeObject() const = 0;
00031
00032     virtual void Print(std::ostream& os) const;
00033
00034     virtual const char * GetEventName() const = 0;
00035
00036     virtual bool CheckEvent(const Event*) const = 0;
00037 };
00038
00039 inline std::ostream& operator<<(std::ostream& os, const Event &e)
00040 {
00041     e.Print(os);
00042     return os;
00043 }
00044
00045 /*
00046  * Macro for creating new Events
00047  */
00048 #define gdcmEventMacro( classname , super ) \
00049 \
00050 class classname : public super { \
00051 public: \
00052     typedef classname Self; \
00053     typedef super Superclass; \
00054     classname() {} \
00055     virtual ~classname() override = default; \
00056     virtual const char * GetEventName() const override { return #classname; } \
00057     virtual bool CheckEvent(const ::gdcm::Event* e) const override \
00058     { return dynamic_cast<const Self*>(e) ? true : false; } \
00059     virtual ::gdcm::Event* MakeObject() const override \
00060     { return new Self; } \
00061     classname(const Self&s) : super(s){} \
00062 private: \
00063     void operator=(const Self&); \
00064 }
00065
00066 gdcmEventMacro( NoEvent , Event );
00067 gdcmEventMacro( AnyEvent , Event );
00068 gdcmEventMacro( StartEvent , AnyEvent );
00069 gdcmEventMacro( EndEvent , AnyEvent );
00070 //gdcmEventMacro( ProgressEvent , AnyEvent );
00071 gdcmEventMacro( ExitEvent , AnyEvent );
00072 gdcmEventMacro( AbortEvent , AnyEvent );
00073 gdcmEventMacro( ModifiedEvent , AnyEvent );
00074 gdcmEventMacro( InitializeEvent , AnyEvent );

```

```

00091 gdcmEventMacro( IterationEvent      , AnyEvent );
00092 //gdcmEventMacro( AnonymizeEvent    , AnyEvent );
00093 gdcmEventMacro( UserEvent            , AnyEvent );
00094
00095
00096 } // end namespace gdcm
00097 //-----
00098 #endif //GDCMEVENT_H

```


11.31 gdcmException.h File Reference

```

#include <cassert>
#include <cstdlib>
#include <exception>
#include <sstream>
#include <stdexcept>
#include <string>

```

Include dependency graph for gdcmException.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::Exception](#)
Exception.

Namespaces

- namespace [gdcm](#)

Macros

- #define [gdcm_assert](#)(cond)
- #define [gdcm_debug_assert](#)(cond)
- #define [gdcm_forced_assert](#)(cond)

11.31.1 Macro Definition Documentation

11.31.1.1 gdcm_assert

```
#define gdcm_assert(  
    cond)
```

Value:

```
if (!cond) throw gdcm::Exception("An invalid logic behavior occurred" #cond, __FILE__ , __LINE__)
```

Examples

CStoreQtProgress.cxx, CheckBigEndianBug.cxx, DiscriminateVolume.cxx, DumpADAC.cxx, DumpExamCard.cxx, DumpGEMSMovieGroup.cxx, DumpImageHeaderInfo.cxx, DumpPhilipsECHO.cxx, DumpSiemensBase64.cxx, ELSCINT1WaveToText.cxx, ExtractIconFromFile.cxx, Extracting_All_Resolution.cxx, Fake_Image_Using_Stream_Image_Writer.cxx, GenAllVR.cxx, GenFakeIdentifyFile.cxx, GetSubSequenceData.cxx, LargeVRDSExplicit.cxx, ReadAndPrintAttributes.cxx, StreamImageReaderTest.cxx, VolumeSorter.cxx, and pmsct_rgb1.cxx.

Referenced by [gdcm::network::AAssociateRQPDU::AAssociateRQPDU\(\)](#), [gdcm::CSAHeaderDict::CSAHeaderDict\(\)](#), [gdcm::Dict::Dict\(\)](#), [gdcm::LookupTable::LookupTable\(\)](#), [gdcm::CSAHeaderDict::AddCSAHeaderDictEntry\(\)](#), [gdcm::Dict::AddDictEntry\(\)](#), [gdcm::PrivateDict::AddDictEntry\(\)](#), [gdcm::Macros::AddMacro\(\)](#), [gdcm::Modules::AddModule\(\)](#), [gdcm::network::PDataTFPDU::AddPresent](#), [gdcm::Clamp\(\)](#), [gdcm::DataSet::Clear\(\)](#), [gdcm::DataSet::ComputeGroupLength\(\)](#), [gdcm::ByteBuffer::Get\(\)](#), [gdcm::Attribute< Group, Elem](#), [gdcm::Attribute< Group, Element, TVR, VM::VM1 >::GetAsDataElement\(\)](#), [gdcm::Attribute< Group, Element, TVR, VM::VM1_n >::GetA](#), [gdcm::Element< TVR, TVM >::GetAsDataElement\(\)](#), [gdcm::PixelFormat::GetBitsStored\(\)](#), [gdcm::Pixmap::GetCurve\(\)](#), [gdcm::Pixmap::GetCurve\(\)](#), [gdcm::Dict::GetDictEntry\(\)](#), [gdcm::PrivateDict::GetDictEntry\(\)](#), [gdcm::Dict::GetDictEntryByKeyword\(\)](#), [gdcm::Dict::GetDictEntryByName\(\)](#), [gdcm::Directory::GetFileNames\(\)](#), [gdcm::FilenameGenerator::GetFileNames\(\)](#), [gdcm::PixelFormat::GetHighBit\(\)](#), [gdcm::IODs::GetIOD\(\)](#), [gdcm::Dict::GetKeywordFromTag\(\)](#), [gdcm::DataSet::GetLength\(\)](#), [gdcm::Macros::GetMacro\(\)](#), [gdcm::network::PresentationDataValue::GetMessageHeader\(\)](#), [gdcm::Modules::GetModule\(\)](#), [gdcm::Pixmap::GetOverlay\(\)](#), [gdcm::Pixmap::GetOverlay\(\)](#), [gdcm::network::AAssociateRQPDU::GetPresentationContext\(\)](#), [gdcm::network::AAssociateACPDU::GetPresentationContextAC\(\)](#), [gdcm::network::PDataTFPDU::GetPresentationDataValue\(\)](#), [gdcm::VR::GetSize\(\)](#), [gdcm::Table::GetTableEntry\(\)](#), [gdcm::Attribute< Group, Element, TVR, TVM >::GetValue\(\)](#), [gdcm::Attribute< Group, Element, TVR, TVM >::GetValue\(\)](#), [gdcm::Attribute< Group, Element, TVR, VM::VM1_n >::GetValue\(\)](#), [gdcm::Attribute< Group, Element, TVR, VM::VM1_n >::GetValue\(\)](#), [gdcm::Element< TVR, TVM >::GetValue\(\)](#), [gdcm::Element< TVR, TVM >::GetValue\(\)](#), [gdcm::DataSet::InsertDataElement\(\)](#), [gdcm::Item::InsertDataElement\(\)](#), [gdcm::Table::InsertEntry\(\)](#), [gdcm::ByteValue::IsEmpty\(\)](#), [gdcm::ByteValue::IsPrintable\(\)](#), [gdcm::Scanner2::Itstr::operator\(\)\(\)](#), [gdcm::Scanner::Itstr::operator\(\)\(\)](#), [gdcm::StrictScanner2::Itstr::operator\(\)\(\)](#), [gdcm::StrictScanner::Itstr::operator\(\)\(\)](#), [gdcm::SmartPointer< Value >::operator*\(\)](#), [gdcm::BasicOffsetTable::operator<<\(\)](#), [gdcm::CSAElement::operator<<\(\)](#), [gdcm::File::operator<<\(\)](#), [gdcm::VM::operator<<\(\)](#), [gdcm::network::PresentationContextRQ::operator==\(\)](#), [gdcm::PresentationContext::ope](#), [gdcm::Tag::operator\[\]\(\)](#), [gdcm::Tag::operator\[\]\(\)](#), [gdcm::ApplicationEntity::Print\(\)](#), [gdcm::SequenceOfFragments::Print\(\)](#), [gdcm::ByteValue::PrintGroupLength\(\)](#), [gdcm::BasicOffsetTable::Read\(\)](#), [gdcm::ByteValue::Read\(\)](#), [gdcm::EncodingImplementation< VR::VR](#), [gdcm::EncodingImplementation< VR::VRBINARY >::Read\(\)](#), [gdcm::Item::Read\(\)](#), [gdcm::SequenceOfFragments::Read\(\)](#), [gdcm::SequenceOfItems::Read\(\)](#), [gdcm::VR::Read\(\)](#), [gdcm::VL::Read16\(\)](#), [gdcm::Fragment::ReadBacktrack\(\)](#), [gdcm::EncodingImplementation< VR::VRASCII >::ReadComputeLength\(\)](#), [gdcm::EncodingImplementation< VR::VRBINARY >::ReadC](#), [gdcm::EncodingImplementation< VR::VRBINARY >::ReadNoSwap\(\)](#), [gdcm::SequenceOfFragments::ReadValue\(\)](#), [gdcm::SurfaceHelper::RecommendedDisplayCIELabToRGB\(\)](#), [gdcm::Object::Register\(\)](#), [gdcm::DataSet::Remove\(\)](#), [gdcm::PrivateDict::RemoveDictEntry\(\)](#), [gdcm::Pixmap::RemoveOverlay\(\)](#), [gdcm::ImageChangePhotometricInterpretation::RGB2YBR\(\)](#), [gdcm::ImageChangePlanarConfiguration::RGBPixelsToRGBPlanes\(\)](#), [gdcm::ImageChangePlanarConfiguration::RGBPlanesToRGBPixels](#), [gdcm::SurfaceHelper::RGBToRecommendedDisplayCIELab\(\)](#), [gdcm::SurfaceHelper::RGBToRecommendedDisplayGrayscale\(\)](#), [gdcm::ApplicationEntity::SetBlob\(\)](#), [gdcm::Attribute< Group, Element, TVR, TVM >::SetByteValue\(\)](#), [gdcm::Attribute< Group, Element, T](#), [gdcm::Attribute< Group, Element, TVR, VM::VM1_n >::SetByteValue\(\)](#), [gdcm::Attribute< Group, Element, TVR, TVM >::SetByteValueN](#), [gdcm::Attribute< Group, Element, TVR, VM::VM1 >::SetByteValueNoSwap\(\)](#), [gdcm::PersonName::SetComponents\(\)](#), [gdcm::Attribute< Group, Element, TVR, TVM >::SetFromDataElement\(\)](#), [gdcm::Attribute< Group, Element, TVR, VM::VM1 >::SetFromD](#)

```

gdcm::Attribute< Group, Element, TVR, VM::VM1_n >::SetFromDataElement(), gdcm::network::PresentationDataValue::SetMessageHeader(),
gdcm::Element< TVR, TVM >::SetNoSwap(), gdcm::ImageCodec::SetPlanarConfiguration(), gdcm::network::PresentationDataValue::SetPlanarConfiguration(),
gdcm::Tag::SetPrivateCreator(), gdcm::PixelFormat::SetSamplesPerPixel(), gdcm::Attribute< Group, Element, TVR, TVM >::SetValue(),
gdcm::Attribute< Group, Element, TVR, VM::VM1_n >::SetValue(),          gdcm::Element< TVR, TVM >::SetValue(),
gdcm::Attribute< Group, Element, TVR, TVM >::SetValues(), gdcm::Attribute< Group, Element, TVR, VM::VM1_n >::SetValues(),
gdcm::GroupDict::Size(), gdcm::Object::UnRegister(), gdcm::ByteValue::Write(), gdcm::EncodingImplementation< VR::VRASCII >::Write(),
gdcm::EncodingImplementation< VR::VRASCII >::Write(), gdcm::EncodingImplementation< VR::VRBINARY >::Write(),
gdcm::Fragment::Write(), gdcm::Item::Write(), gdcm::SequenceOfFragments::Write(), gdcm::VR::Write(), gdcm::VL::Write16(),
gdcm::ByteValue::WriteBuffer(), and gdcm::ImageChangePhotometricInterpretation::YBR2RGB().

```

11.31.1.2 gdcm_debug_assert

```

#define gdcm_debug_assert (
    cond)

```

Value:

```
gdcm_assert (cond)
```

11.31.1.3 gdcm_forced_assert

```

#define gdcm_forced_assert (
    cond)

```

Value:

```
assert (cond)
```

Referenced by [gdcm::Object::~~Object\(\)](#).

11.32 gdcmException.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013  =====*/
00014 #ifndef GDCMEXCEPTION_H
00015 #define GDCMEXCEPTION_H
00016
00017 #include <cassert>
00018 #include <cstdlib> // NULL
00019 #include <exception>
00020 #include <sstream> // ostringstream
00021 #include <stdexcept> // logic_error
00022 #include <string>
00023
00024 // Disable clang warning "dynamic exception specifications are deprecated".
00025 // We need to be C++03 and C++11 compatible, and if we remove the 'throw()'

```

```

00026 // specifier we'll get an error in C++03 by not matching the superclass.
00027 #if defined(__clang__) && defined(__has_warning)
00028 # if __has_warning("-Wdeprecated")
00029 #   pragma clang diagnostic push
00030 #   pragma clang diagnostic ignored "-Wdeprecated"
00031 # endif
00032 #endif
00033
00034 #define gdcmm_forced_assert(cond) assert(cond)
00035
00036 namespace gdcmm
00037 {
00038
00039     class Exception : public std::exception
00040     {
00041     public:
00042         typedef std::logic_error StringHolder;
00043
00044         static StringHolder CreateWhat(const char* const desc,
00045                                       const char* const file,
00046                                       const unsigned int lineNumber,
00047                                       const char* const func)
00048         {
00049             gdcmm_forced_assert(desc != nullptr);
00050             gdcmm_forced_assert(file != nullptr);
00051             gdcmm_forced_assert(func != nullptr);
00052             std::ostringstream oswhat;
00053             oswhat << file << ":" << lineNumber << " (" << func << "):\n";
00054             oswhat << desc;
00055             return StringHolder( oswhat.str() );
00056         }
00057
00058     public:
00059         explicit Exception(const char *desc = "None",
00060                           const char *file = __FILE__,
00061                           unsigned int lineNumber = __LINE__,
00062                           // FIXME: __PRETTY_FUNCTION__ is the non-mangled version for __GNUC__ compiler
00063                           const char *func = "" /*__FUNCTION__*/)
00064             : What( CreateWhat(desc, file, lineNumber, func) ),
00065               Description(desc)
00066         {
00067         }
00068
00069         ~Exception() throw() override {}
00070
00071         const char* what() const throw() override
00072         {
00073             return What.what();
00074         }
00075
00076         const char * GetDescription() const { return Description.what(); }
00077
00078     private:
00079         StringHolder What;
00080         StringHolder Description;
00081     };
00082 }
00083
00084 // end namespace gdcmm
00085
00086 // Always defined
00087 #define gdcmm_assert(cond) \
00088     if (!(cond)) throw gdcmm::Exception("An invalid logic behavior occurred" #cond, __FILE__ , __LINE__)
00089
00090 /* Asserts that should only exist in debug builds. */
00091 #ifndef NDEBUG // checks in debug builds and elision in release builds (like assert)
00092 #define gdcmm_debug_assert(cond) gdcmm_assert(cond)
00093 #else
00094 #define gdcmm_debug_assert(cond) ((void)0)
00095 #endif
00096
00097 // Undo warning suppression.
00098 #if defined(__clang__) && defined(__has_warning)
00099 # if __has_warning("-Wdeprecated")
00100 #   pragma clang diagnostic pop
00101 # endif
00102 #endif
00103
00104 #endif


```


11.33 gdcmFilename.h File Reference

```
#include "gdcmTypes.h"
```

```
#include <string>
```

Include dependency graph for gdcmFilename.h:



Classes

- class [gdcm::Filename](#)
Class to manipulate file name's.

Namespaces

- namespace [gdcm](#)

11.34 gdcmFilename.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013  =====*/
00014 #ifndef GDCMFILENAME_H
00015 #define GDCMFILENAME_H
00016
00017 #include "gdcmTypes.h"
00018
00019 #include <string>
00020
00021 namespace gdcm

```

```

00022 {
00027 class GDCM_EXPORT Filename
00028 {
00029 public:
00030     Filename(const char* filename = ""):FileName(filename ? filename : ""),Path(),Conversion() {}
00031
00033     const char *GetFileName() const { return FileName.c_str(); }
00035     const char *GetPath();
00037     const char *GetName();
00039     const char *GetExtension();
00041     const char *ToUnixSlashes();
00043     const char *ToWindowsSlashes();
00044
00047     static const char *Join(const char *path, const char *filename);
00048
00050     bool IsEmpty() const { return FileName.empty(); }
00051
00055     operator const char * () const { return GetFileName(); }
00056
00057     // FIXME: I don't like this function
00058     // It hides the realpath call (maybe useful)
00059     // and it forces file to exist on the disk whereas FileName
00060     // should be independent from file existence.
00061     bool IsIdentical(Filename const &fn) const;
00062
00064     bool EndWith(const char ending[]) const;
00065
00066 private:
00067     std::string FileName;
00068     std::string Path;
00069     std::string Conversion;
00070 };
00071
00072 } // end namespace gdcmm
00073
00074 #endif //GDCMFILENAME_H


```

11.35 gdcmmFileNameEvent.h File Reference

```
#include "gdcmmEvent.h"
```

```
#include "gdcmmTag.h"
```

Include dependency graph for gdcmmFileNameEvent.h:



Classes

- class `gdcm::FileNameEvent`
FileNameEvent.

Namespaces

- namespace `gdcm`

11.36 gdcmFileNameEvent.h

[Go to the documentation of this file.](#)

```


00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013   =====*/
00014 #ifndef GDCMFILENAMEEVENT_H
00015 #define GDCMFILENAMEEVENT_H
00016
00017 #include "gdcmEvent.h"
00018 #include "gdcmTag.h"
00019
00020 namespace gdcm
00021 {
00022
00023   class FileNameEvent : public AnyEvent
00024   {
00025   public:
00026     typedef FileNameEvent Self;
00027     typedef AnyEvent Superclass;
00028     FileNameEvent(const char *s = "") : m_FileName(s) {}
00029     ~FileNameEvent() override = default;
00030
00031     FileNameEvent(const Self&s) : AnyEvent(s){}
00032     void operator=(const Self&) = delete;
00033
00034     const char * GetEventName() const override { return "FileNameEvent"; }
00035     bool CheckEvent(const ::gdcm::Event* e) const override
00036     { return dynamic_cast<const Self*>(e) ? true : false; }
00037     ::gdcm::Event* MakeObject() const override
00038     { return new Self; }
00039
00040     void SetFileName(const char *f) { m_FileName = f; }
00041     const char *GetFileName() const { return m_FileName.c_str(); }
00042   private:
00043     std::string m_FileName;
00044   };
00045
00046 } // end namespace gdcm
00047
00048 #endif //GDCMFILENAMEEVENT_H

```

11.37 gdcmFilenameGenerator.h File Reference

```
#include "gdcmTypes.h"
#include <string>
#include <vector>
```

Include dependency graph for gdcmFilenameGenerator.h:



Classes

- class [gdcm::FilenameGenerator](#)
FilenameGenerator.

Namespaces

- namespace [gdcm](#)

11.38 gdcmFilenameGenerator.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013   =====*/
00014 #ifndef GDCMFILENAMEGENERATOR_H
00015 #define GDCMFILENAMEGENERATOR_H
00016
00017 #include "gdcmTypes.h"
00018 #include <string>
00019 #include <vector>
00020
```

```

00021
00022 namespace gdcm
00023 {
00035
00036 class GDCM_EXPORT FilenameGenerator
00037 {
00038 public:
00039   FilenameGenerator():Pattern(),Prefix(),FileNames() {}
00040   ~FilenameGenerator() = default;
00041   // FIXME: already defines in gdcm::Directory
00042   typedef std::string FilenameType;
00043   typedef std::vector<FilenameType> FileNamesType;
00044   typedef FileNamesType::size_type SizeType;
00045
00047   void SetPattern(const char *pattern) { Pattern = pattern; }
00048   const char *GetPattern() const { return Pattern.c_str(); }
00049
00051   void SetPrefix(const char *prefix) { Prefix = prefix; }
00052   const char *GetPrefix() const { return Prefix.c_str(); }
00053
00055   bool Generate();
00056
00058   void SetNumberOfFileNames(SizeType nfiles);
00059   SizeType GetNumberOfFileNames() const;
00060
00062   const char * GetFilename(SizeType n) const;
00063
00065   FileNamesType const & GetFileNames() const { gdcm_assert( !Pattern.empty() ); return FileNames; }
00066 private:
00067   FilenameType Pattern;
00068   FilenameType Prefix;
00069   FileNamesType FileNames;
00071 };
00072
00073 } // end namespace gdcm
00074
00075 #endif //GDCMFILENAMEGENERATOR_H


```

11.39 gdcmLegacyMacro.h File Reference

```
#include "gdcmException.h"
```

```
#include "gdcmTrace.h"
```

Include dependency graph for gdcmLegacyMacro.h:



This graph shows which files directly or indirectly include this file:



Macros

- `#define GDCM_LEGACY(method)`
- `#define GDCM_LEGACY_BODY(method, version)`
- `#define GDCM_LEGACY_REPLACED_BODY(method, version, replace)`
- `#define GDCM_NOOP_STATEMENT static_assert(true, "")`

11.39.1 Macro Definition Documentation

11.39.1.1 GDCM_LEGACY

```
#define GDCM_LEGACY(  
    method)
```

Value:

```
method;
```

11.39.1.2 GDCM_LEGACY_BODY

```
#define GDCM_LEGACY_BODY(  
    method,  
    version)
```

Value:

```
gdcmWarningMacro(#method " was deprecated for " version " and will be removed in a future version.")
```

11.39.1.3 GDCM_LEGACY_REPLACED_BODY

```
#define GDCM_LEGACY_REPLACED_BODY(  
    method,  
    version,  
    replace)
```

Value:

```
gdcmWarningMacro(#method " was deprecated for " version " and will be removed in a future version. Use "  
#replace " instead.")
```

11.39.1.4 GDCM_NOOP_STATEMENT

```
#define GDCM_NOOP_STATEMENT static_assert(true, "")
```

The `static_assert(true, "")` idiom is commonly employed for C++11 or greater to ensure that it is compile-time only check that can not be part of the binary file. This allows a macro to be used anywhere that a statement is expected, and to enforce consistent use of `;` after a macro. The `static_assert` is a `constexpr` that can be used in places where raw statements (i.e. `'do{} while(0)'`) are not allowed (i.e. after class member function definitions).

11.40 gdcmLegacyMacro.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMLEGACYMACRO_H
00015 #define GDCMLEGACYMACRO_H
00016
00017 #if !defined(GDCMTYPES_H) && !defined(SWIG)
00018 #error you need to include gdcmTypes.h instead
00019 #endif
00020
00021 #include "gdcmException.h"
00022
00023 //-----
00024 // Setup legacy code policy.
00025
00026 // Define GDCM_LEGACY macro to mark legacy methods where they are
00027 // declared in their class. Example usage:
00028 //
00029 //   // @deprecated Replaced by MyOtherMethod() as of GDCM 2.0.
00030 //   GDCM_LEGACY(void MyMethod());
00031 #if defined(GDCM_LEGACY_REMOVE)
00032 # define GDCM_LEGACY(method)
00033 #elif defined(GDCM_LEGACY_SILENT) || defined(SWIG)
00034 // Provide legacy methods with no warnings.
00035 # define GDCM_LEGACY(method) method;
00036 #else
00037 // Setup compile-time warnings for uses of deprecated methods if
00038 // possible on this compiler.
00039 # if defined(__GNUC__) && !defined(__INTEL_COMPILER) && (__GNUC__ > 3 || (__GNUC__ == 3 && __GNUC_MINOR__
00040 >= 1))
00041 #   define GDCM_LEGACY(method) method __attribute__((deprecated));
00042 #   elif defined(_MSC_VER) && _MSC_VER >= 1300
00043 #   define GDCM_LEGACY(method) __declspec(deprecated) method;
00044 #   else
00045 #   define GDCM_LEGACY(method) method;
00046 #   endif
00047 #endif
00048
00049 # define GDCM_NOOP_STATEMENT static_assert(true, "")
00050
00051 // Macros to create runtime deprecation warning messages in function
00052 // bodies. Example usage:
00053 //
00054 //   #if !defined(GDCM_LEGACY_REMOVE)
00055 //   void gdcm::MyClass::MyOldMethod()
00056 //   {
00057 //       GDCM_LEGACY_BODY(gdcm::MyClass::MyOldMethod, "GDCM 2.0");
00058 //   }
00059 //   #endif
00060 //
00061 //   #if !defined(GDCM_LEGACY_REMOVE)
00062 //   void gdcm::MyClass::MyMethod()
00063 //   {
00064 //       GDCM_LEGACY_REPLACED_BODY(gdcm::MyClass::MyMethod, "GDCM 2.0",
00065 //                                   gdcm::MyClass::MyOtherMethod);
00066 //   }
00067 //   #endif
00068 //
00069 //   #if !defined(GDCM_LEGACY_REMOVE) || defined(GDCM_LEGACY_SILENT)
00070 //   # define GDCM_LEGACY_BODY(method, version)
00071 //   # define GDCM_LEGACY_REPLACED_BODY(method, version, replace)
00072 //   #else
00073 //   # define GDCM_LEGACY_BODY(method, version) \
00074 //       gdcmWarningMacro(#method " was deprecated for " version " and will be removed in a future version.")
00075 //   # define GDCM_LEGACY_REPLACED_BODY(method, version, replace) \
00076 //       gdcmWarningMacro(#method " was deprecated for " version " and will be removed in a future version. Use
00077 //       " #replace " instead.")

```

```


00084 #endif
00085
00086 #include "gdcmTrace.h"
00087
00088 #endif // GDCMLEGACYMACRO_H

```

11.41 gdcmMD5.h File Reference

```
#include "gdcmTypes.h"
```

Include dependency graph for gdcmMD5.h:



Classes

- class [gdcm::MD5](#)
Class for *MD5*.

Namespaces

- namespace [gdcm](#)

11.42 gdcmMD5.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003 Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005 Copyright (c) 2006-2011 Mathieu Malaterre
00006 All rights reserved.
00007 See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009 This software is distributed WITHOUT ANY WARRANTY; without even
00010 the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011 PURPOSE. See the above copyright notice for more information.

```



```

00012
00013 =====*/
00014 #ifndef GDCMMD5_H
00015 #define GDCMMD5_H
00016
00017 #include "gdcmTypes.h"
00018
00019 namespace gdcm
00020 {
00021 //-----
00022 class GDCM_EXPORT MD5
00023 {
00024 public :
00025     // Compute md5 from memory pointed by `pointer` of size `buf_len`
00026     static bool Compute(const char *buffer, size_t buf_len, char digest_str[33]);
00027
00028     static bool ComputeFile(const char *filename, char digest_str[33]);
00029 };
00030 //-----
00031 #endif //GDCMMD5_H

```


11.43 gdcmObject.h File Reference

```
#include "gdcmTypes.h"
```

```
#include <assert.h>
```

```
#include <iostream>
```

Include dependency graph for gdcmObject.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::Object](#)
Object.

Namespaces

- namespace `gdcm`

Functions

- `std::ostream & gdcm::operator<< (std::ostream &os, const Object &obj)`

11.44 gdcmObject.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003     Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005     Copyright (c) 2006-2011 Mathieu Malaterre
00006     All rights reserved.
00007     See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009     This software is distributed WITHOUT ANY WARRANTY; without even
00010     the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011     PURPOSE. See the above copyright notice for more information.
00012
00013     =====*/
00014 #ifndef GDCMOBJECT_H
00015 #define GDCMOBJECT_H
00016
00017 #include "gdcmTypes.h"
00018
00019 #include <assert.h>
00020 #include <iostream> // grrrrr
00021
00022 //namespace std { class ostream; }
00023 namespace gdcm
00024 {
00025
00026     template<class ObjectType> class SmartPointer;
00027
00036     class GDCM_EXPORT Object
00037     {
00038     public:
00039         template <class ObjectType> friend class SmartPointer;
00040         friend std::ostream& operator<<(std::ostream &os, const Object &obj);
00041
00042         Object():ReferenceCount(0) {}
00043
00044         // Implementation note:
00045         // If I move ~Object in the protected section I can prevent people
00046         // from writing:
00047         // SmartPointer<Object> p = new Object;
00048         // delete p; // due to SmartPointer::operator ObjectType * () const
00049         // but on the other hand one could not define an Object on the stack
00050         // Object obj;
00051         // Furthermore it would not prevent anyone from doing:
00052         // class MyObject : public Object {};
00053         // SmartPointer<MyObject> o = new MyObject;
00054         // delete o; // grrrrrr
00055         virtual ~Object() {
00056             // If your debugger reach here it means you are doing something silly
00057             // like using SmartPointer on object allocated on the stack (vs heap)
00058             gdcm_forced_assert(ReferenceCount == 0);
00059         }
00060
00061         // http://www.parashift.com/c++-faq-lite/freestore-mgmt.html#faq-16.24
00062         // Set the ref count to 0
00063         // Do NOT copy the reference count !
00064         Object(const Object&):ReferenceCount(0){}
00065         void operator=(const Object&){}
00066
00067         //static Object* New() { return new Object; }

```

```

00069
00070 protected:
00071     // For the purpose of the invasive SmartPointer implementation
00072     void Register() {
00073         ReferenceCount++;
00074         gdcm_assert( ReferenceCount > 0 );
00075     }
00076     void UnRegister() {
00077         gdcm_assert( ReferenceCount > 0 );
00078         ReferenceCount--;
00079         if (!ReferenceCount)
00080         {
00081             delete this;
00082         }
00083     }
00084
00085 public:
00086     // For dealing with printing of object and polymorphism
00087     virtual void Print(std::ostream &) const {}
00088
00089 private:
00090     long ReferenceCount;
00091 };
00092
00093 //-----
00094 // function do not carry vtable. Thus define in the base class the operator
00095 // and use the member function ->Print() to call the appropriate function
00096 // NOTE: All subclass of Object needs to implement the Print function
00097 inline std::ostream& operator<<(std::ostream &os, const Object &obj)
00098 {
00099     obj.Print(os);
00100     return os;
00101 }
00102
00103 } // end namespace gdc
00104
00105 #endif //GDCMOBJECT_H

```


11.45 gdcOpenSSLCryptoFactory.h File Reference

```

#include "gdcmCryptoFactory.h"
#include "gdcOpenSSLCryptographicMessageSyntax.h"

```

Include dependency graph for gdcOpenSSLCryptoFactory.h:



Classes

- class [gdcm::OpenSSLCryptoFactory](#)

Namespaces

- namespace [gdcm](#)

11.46 gdcmOpenSSLCryptoFactory.h

[Go to the documentation of this file.](#)

```

00001  /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013  =====*/
00014  #ifndef GDCMOPENSSLCRYPTOFACTORY_H
00015  #define GDCMOPENSSLCRYPTOFACTORY_H
00016
00017  #include "gdcmCryptoFactory.h"
00018  #include "gdcmOpenSSLCryptographicMessageSyntax.h"
00019
00020  namespace gdcm
00021  {
00022
00023  class GDCM_EXPORT OpenSSLCryptoFactory : public CryptoFactory
00024  {
00025  public:
00026      OpenSSLCryptoFactory(CryptoLib id) : CryptoFactory(id)
00027      {
00028          gdcmDebugMacro( "OpenSSL Factory registered." );
00029      }
00030
00031  public:
00032      CryptographicMessageSyntax* CreateCMSProvider()
00033      {
00034          InitOpenSSL();
00035          return new OpenSSLCryptographicMessageSyntax();
00036      }
00037
00038  protected:
00039      void InitOpenSSL();
00040
00041  private:
00042      OpenSSLCryptoFactory() {}
00043  };
00044
00045  } // end namespace gdcm
00046
00047  #endif //GDCMOPENSSLCRYPTOFACTORY_H

```

11.47 gdcmOpenSSLCryptographicMessageSyntax.h File Reference


```

#include "gdcmCryptographicMessageSyntax.h"
#include <openssl/cms.h>


```

```
#include <openssl/evp.h>
```

Include dependency graph for gdcmlOpenSSLCryptographicMessageSyntax.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcml::OpenSSLCryptographicMessageSyntax](#)

Namespaces

- namespace [gdcml](#)

11.48 gdcmOpenSSLCryptographicMessageSyntax.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMOPENSSLCRYPTOGRAPHICMESSAGESYNTAX_H
00015 #define GDCMOPENSSLCRYPTOGRAPHICMESSAGESYNTAX_H
00016
00017 #include "gdcmCryptographicMessageSyntax.h"
00018 #include <openssl/cms.h>
00019 #include <openssl/evp.h>
00020
00021 namespace gdcm
00022 {
00023
00024   class GDCM_EXPORT OpenSSLCryptographicMessageSyntax : public CryptographicMessageSyntax
00025   {
00026   public:
00027     OpenSSLCryptographicMessageSyntax();
00028     ~OpenSSLCryptographicMessageSyntax();
00029
00030     // X.509
00031     bool ParseCertificateFile( const char *filename );
00032     bool ParseKeyFile( const char *filename );
00033
00034     // PBE
00035     bool SetPassword(const char * pass, size_t passLen);
00036
00037     void SetCipherType(CipherTypes type);
00038     CipherTypes GetCipherType() const;
00039     bool Encrypt(char *output, size_t &outlen, const char *array, size_t len) const;
00040     bool Decrypt(char *output, size_t &outlen, const char *array, size_t len) const;
00041
00042   private:
00043     // #ifdef GDCM_HAVE_CMS_RECIPIENT_PASSWORD
00044     //   ::stack_st_X509 *recips;
00045     // #else
00046     STACK_OF(X509) *recips;
00047     // #endif
00048     ::EVP_PKEY *pkey;
00049     const EVP_CIPHER *internalCipherType;
00050     char * password;
00051     size_t passwordLength;
00052     CipherTypes cipherType;
00053
00054   private:
00055     OpenSSLCryptographicMessageSyntax(const OpenSSLCryptographicMessageSyntax&); // Not implemented.
00056     void operator=(const OpenSSLCryptographicMessageSyntax&); // Not implemented.
00057     const EVP_CIPHER *CreateCipher( CryptographicMessageSyntax::CipherTypes ciphertype);
00058
00059   };
00060
00061 } // end namespace gdcm
00062
00063 #endif //GDCMOPENSSLCRYPTOGRAPHICMESSAGESYNTAX_H

```


11.49 gdcmOpenSSLP7CryptoFactory.h File Reference

```

#include "gdcmCryptoFactory.h"
#include "gdcmOpenSSLP7CryptographicMessageSyntax.h"

```

Include dependency graph for gdcOpenSSL7CryptoFactory.h:



Classes

- class [gdc::OpenSSL7CryptoFactory](#)

Namespaces

- namespace [gdc](#)

11.50 gdcOpenSSL7CryptoFactory.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdc.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013   =====*/
00014 #ifndef GDCMOPENSSL7CRYPTOFACTORY_H
00015 #define GDCMOPENSSL7CRYPTOFACTORY_H
00016
00017 #include "gdcCryptoFactory.h"
00018 #include "gdcOpenSSL7CryptographicMessageSyntax.h"
00019
00020 namespace gdc

```

```

00021 {
00022 class GDCM_EXPORT OpenSSL7CryptoFactory : public CryptoFactory
00023 {
00024 public:
00025     OpenSSL7CryptoFactory(CryptoLib id) : CryptoFactory(id)
00026     {
00027         gdcmDebugMacro( "OpenSSL (PKCS7) Factory registered." );
00028     }
00029
00030 public:
00031     CryptographicMessageSyntax* CreateCMSProvider()
00032     {
00033         return new OpenSSL7CryptographicMessageSyntax();
00034     }
00035
00036 private:
00037     OpenSSL7CryptoFactory() {}
00038 };
00039 }
00040
00041 #endif //GDCMOPENSSL7CRYPTOFACTORY_H


```

11.51 gdcmOpenSSL7CryptographicMessageSyntax.h File Reference


```
#include "gdcmCryptographicMessageSyntax.h"
```

```
#include "gdcmTypes.h"
```

Include dependency graph for gdcmOpenSSL7CryptographicMessageSyntax.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::OpenSSLP7CryptographicMessageSyntax](#)

Namespaces

- namespace [gdcm](#)

11.52 gdcmOpenSSLP7CryptographicMessageSyntax.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMOPENSSLP7CRYPTOGRAPHICMESSAGESYNTAX_H
00015 #define GDCMOPENSSLP7CRYPTOGRAPHICMESSAGESYNTAX_H
00016
00017 #include "gdcmCryptographicMessageSyntax.h"
00018 #include "gdcmTypes.h"
00019
00020 namespace gdcm
00021 {
00022   class CryptographicMessageSyntaxInternals;
00023   //-----
00024
00034   class GDCM_EXPORT OpenSSLP7CryptographicMessageSyntax : public CryptographicMessageSyntax
00035   {
00036   public:
00037     OpenSSLP7CryptographicMessageSyntax();
00038     ~OpenSSLP7CryptographicMessageSyntax();
00039

```

```

00040     // X.509
00041     bool ParseCertificateFile( const char *filename );
00042     bool ParseKeyFile( const char *filename );
00043
00044     // PBE
00045     bool SetPassword(const char * /*pass*/, size_t /*passLen*/)
00046     {
00047         gdcWarningMacro( "Openssl using PKCS7 does not support Password Based Encryption." );
00048         return false;
00049     }
00050
00053     void SetCipherType(CipherTypes type);
00054     CipherTypes GetCipherType() const;
00055
00057     bool Encrypt(char *output, size_t &outlen, const char *array, size_t len) const;
00058
00060     bool Decrypt(char *output, size_t &outlen, const char *array, size_t len) const;
00061
00062 private:
00063     CryptographicMessageSyntaxInternals *Internals;
00064 private:
00065     OpenSSLP7CryptographicMessageSyntax(const OpenSSLP7CryptographicMessageSyntax&); // Not implemented.
00066     void operator=(const OpenSSLP7CryptographicMessageSyntax&); // Not implemented.
00067 };
00068 } // end namespace gdc
00069 //-----
00070 #endif //GDCMOPENSLLP7CRYPTOGRAPHICMESSAGESYNTAX_H


```

11.53 gdcProgressEvent.h File Reference

```
#include "gdcEvent.h"
```

```
#include "gdcTag.h"
```

Include dependency graph for gdcProgressEvent.h:



Classes

- class [gdc::ProgressEvent](#)
ProgressEvent.

Namespaces

- namespace [gdcm](#)

11.54 gdcmProgressEvent.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMPROGRESSEVENT_H
00015 #define GDCMPROGRESSEVENT_H
00016
00017 #include "gdcmEvent.h"
00018 #include "gdcmTag.h"
00019
00020 namespace gdcm
00021 {
00022
00023   class ProgressEvent : public AnyEvent
00024   {
00025   public:
00026     typedef ProgressEvent Self;
00027     typedef AnyEvent Superclass;
00028     ProgressEvent(double p = 0):m_Progress(p) {}
00029     ~ProgressEvent() override = default;
00030
00031     ProgressEvent(const Self&s) : AnyEvent(s), m_Progress(0.0) {}
00032     void operator=(const Self&) = delete;
00033
00034     const char * GetEventName() const override { return "ProgressEvent"; }
00035     bool CheckEvent(const ::gdcm::Event* e) const override
00036     { return dynamic_cast<const Self*>(e) ? true : false; }
00037     ::gdcm::Event* MakeObject() const override
00038     { return new Self; }
00039
00040     void SetProgress(double p) { m_Progress = p; }
00041     double GetProgress() const { return m_Progress; }
00042   private:
00043     double m_Progress;
00044   };
00045
00046 } // end namespace gdcm
00047
00048 #endif //GDCMPROGRESSEVENT_H

```

11.55 gdcmRegion.h File Reference


```

#include "gdcmTypes.h"
#include <vector>


```

```
#include <iostream>
```

Include dependency graph for `gdcmRegion.h`:



This graph shows which files directly or indirectly include this file:



Classes

- class `gdcm::Region`
Class for manipulation region.

Namespaces

- namespace `gdcm`

Functions

- `std::ostream & gdcm::operator<< (std::ostream &os, const Region &r)`

11.56 gdcmRegion.h

[Go to the documentation of this file.](#)

```


00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMREGION_H
00015 #define GDCMREGION_H
00016
00017 #include "gdcmTypes.h"
00018 #include <vector>
00019 #include <iostream>
00020
00021 namespace gdcm
00022 {
00023   class BoxRegion;
00027   //-----
00028   class GDCM_EXPORT Region
00029   {
00030   public :
00031     Region();
00032     virtual ~Region();
00033
00035     virtual void Print(std::ostream &os = std::cout) const;
00036
00038     virtual bool Empty() const = 0;
00039
00041     virtual bool IsValid() const = 0;
00042
00044     virtual size_t Area() const = 0;
00045
00046     // implementation detail of heterogeneous container in C++
00047     virtual Region *Clone() const = 0;
00048
00050     virtual BoxRegion ComputeBoundingBox() = 0;
00051 private:
00052 };
00053 //-----
00054 inline std::ostream& operator<<(std::ostream &os, const Region&r)
00055 {
00056   r.Print( os );
00057   return os;
00058 }
00059
00060 } // end namespace gdcm
00061 //-----
00062 #endif //GDCMREGION_H

```

11.57 gdcmSHA1.h File Reference

```
#include "gdcmTypes.h"
```

Include dependency graph for gdcmSHA1.h:



Classes

- class [gdcm::SHA1](#)
Class for [SHA1](#).

Namespaces

- namespace [gdcm](#)

11.58 gdcmSHA1.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013  =====*/
00014 #ifndef GDCMSHA1_H
00015 #define GDCMSHA1_H
00016
00017 #include "gdcmTypes.h"
00018
00019 namespace gdcm
00020 {
00021 //-----

```

```


00022 class SHA1Internals;
00032 class GDCM_EXPORT SHA1
00033 {
00034 public :
00035     SHA1();
00036     ~SHA1();
00037     SHA1(const SHA1&) = delete;
00038     void operator=(const SHA1&) = delete;
00039
00040     static bool Compute(const char *buffer, unsigned long buf_len, char digest_str[20*2+1]);
00041
00042     static bool ComputeFile(const char *filename, char digest_str[20*2+1]);
00043 private:
00044     SHA1Internals *Internals;
00045 };
00046 } // end namespace gdcm
00047 //-----
00048 #endif //GDCMSHA1_H

```

11.59 gdcmSmartPointer.h File Reference

```
#include "gdcmObject.h"
```

Include dependency graph for gdcmSmartPointer.h:



This graph shows which files directly or indirectly include this file:



Classes

- class `gdcm::SmartPointer< ObjectType >`
Class for Smart Pointer.

Namespaces

- namespace [gdcm](#)

11.60 gdcmSmartPointer.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMSMARTPOINTER_H
00015 #define GDCMSMARTPOINTER_H
00016
00017 #include "gdcmObject.h"
00018
00019 namespace gdcm
00020 {
00021     template<class ObjectType>
00022     class SmartPointer
00023     {
00024     public:
00025         SmartPointer():Pointer(nullptr) {}
00026         SmartPointer(const SmartPointer<ObjectType>& p):Pointer(p.Pointer)
00027         { Register(); }
00028         SmartPointer(ObjectType* p):Pointer(p)
00029         { Register(); }
00030         SmartPointer(ObjectType const & p)
00031         {
00032             Pointer = const_cast<ObjectType*>(&p);
00033             Register();
00034         }
00035         ~SmartPointer() {
00036             UnRegister();
00037             Pointer = nullptr;
00038         }
00039
00040         ObjectType *operator -> () const
00041         { return Pointer; }
00042
00043         ObjectType& operator * () const
00044         {
00045             gdcm_assert( Pointer );
00046             return *Pointer;
00047         }
00048
00049         operator ObjectType * () const
00050         { return Pointer; }
00051
00052         SmartPointer &operator = (SmartPointer const &r)
00053         { return operator = (r.Pointer); }
00054
00055         SmartPointer &operator = (ObjectType *r)
00056         {
00057             // http://www.parashift.com/c++-faq-lite/freestore-mgmt.html#faq-16.22
00058             // DO NOT CHANGE THE ORDER OF THESE STATEMENTS!
00059             // (This order properly handles self-assignment)
00060             // (This order also properly handles recursion, e.g., if a ObjectType contains
00061             SmartPointer<ObjectType>s)
00062             if( Pointer != r )
00063             {
00064                 ObjectType* old = Pointer;
00065                 Pointer = r;
00066                 Register();
00067             }
00068         }
00069     };

```



```

00087         if ( old ) { old->UnRegister(); }
00088     }
00089     return *this;
00090 }
00091
00092 SmartPointer &operator = (ObjectType const &r)
00093 {
00094     ObjectType* tmp = const_cast<ObjectType*>(&r);
00095     return operator = (tmp);
00096 }
00097
00099 ObjectType *GetPointer() const
00100 { return Pointer; }
00101
00102 private:
00103 void Register()
00104 {
00105     if(Pointer) Pointer->Register();
00106 }
00107
00108 void UnRegister()
00109 {
00110     if(Pointer) Pointer->UnRegister();
00111 }
00112
00113 ObjectType* Pointer;
00114 };
00115
00116 } // end namespace gdcm
00117
00118 #endif //GDCMSMARTPOINTER_H

```

11.61 gdcmStaticAssert.h File Reference

This graph shows which files directly or indirectly include this file:



Classes

- struct [gdcm::static_assert_test< x >](#)
- struct [gdcm::STATIC_ASSERTION_FAILURE< true >](#)

Namespaces

- namespace [gdcm](#)

Macros

- #define [GDCM_DO_JOIN\(X, Y\)](#)
 - #define [GDCM_DO_JOIN2\(X, Y\)](#)
 - #define [GDCM_JOIN\(X, Y\)](#)
 - #define [GDCM_STATIC_ASSERT\(B\)](#)
- The GDCM_JOIN + **LINE** is needed to create a uniq identifier.*

11.61.1 Macro Definition Documentation

11.61.1.1 GDCM_DO_JOIN

```
#define GDCM_DO_JOIN(  
    X,  
    Y)
```

Value:

`GDCM_DO_JOIN2 (X, Y)`

11.61.1.2 GDCM_DO_JOIN2

```
#define GDCM_DO_JOIN2(  
    X,  
    Y)
```

Value:

`X##Y`

11.61.1.3 GDCM_JOIN

```
#define GDCM_JOIN(  
    X,  
    Y)
```

Value:

`GDCM_DO_JOIN (X, Y)`

11.61.1.4 GDCM_STATIC_ASSERT

```
#define GDCM_STATIC_ASSERT(  
    B)
```

Value:

```
typedef ::gdcml::static_assert_test<\n    sizeof(::gdcml::STATIC_ASSERTION_FAILURE< (bool) ( B ) >)>\n    GDCM_JOIN(gdcml_static_assert_typedef_, __LINE__)
```

The `GDCM_JOIN + LINE` is needed to create a uniq identifier.

11.62 gdcmStaticAssert.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMSTATICASSERT_H
00015 #define GDCMSTATICASSERT_H
00016
00017
00018 // the following was shamelessly borrowed from BOOST static assert:
00019 namespace gdcm
00020 {
00021     template <bool x>
00022     struct STATIC_ASSERTION_FAILURE;
00023
00024     template <>
00025     struct STATIC_ASSERTION_FAILURE<true> { enum { value = 1 }; };
00026
00027     template <int x>
00028     struct static_assert_test {};
00029 }
00030
00031 #define GDCM_JOIN( X, Y ) GDCM_DO_JOIN( X, Y )
00032 #define GDCM_DO_JOIN( X, Y ) GDCM_DO_JOIN2(X,Y)
00033 #define GDCM_DO_JOIN2( X, Y ) X##Y
00034
00035 #define GDCM_STATIC_ASSERT( B ) \
00036     typedef ::gdcm::static_assert_test<\
00037         sizeof(::gdcm::STATIC_ASSERTION_FAILURE< (bool) ( B ) >)>\
00038         GDCM_JOIN(gdcm_static_assert_typedef_, __LINE__)\
00039
00040
00041
00042 /* Example of use:
00043 *
00044 * template <class T>
00045 * struct must_not_be_instantiated
00046 * {
00047 * // this will be triggered if this type is instantiated
00048 * GDCM_STATIC_ASSERT(sizeof(T) == 0);
00049 * };
00050 *
00051 */
00052 #endif // GDCMSTATICASSERT_H

```


11.63 gdcmString.h File Reference

```

#include "gdcmTypes.h"
#include "gdcmStaticAssert.h"

```

Include dependency graph for `gdcmString.h`:



This graph shows which files directly or indirectly include this file:



Classes

- class `gdcm::String< TDelimiter, TMaxLength, TPadChar >`
String.

Namespaces

- namespace `gdcm`

Functions

- template<char TDelimiter, unsigned int TMaxLength, char TPadChar>
`std::istream & gdcm::operator>> (std::istream &is, String< TDelimiter, TMaxLength, TPadChar > &ms)`

11.64 gdcmString.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMSTRING_H
00015 #define GDCMSTRING_H
00016
00017 #include "gdcmTypes.h"
00018 #include "gdcmStaticAssert.h"
00019
00020 namespace gdcm
00021 {
00022
00023   template <char TDelimiter = '\\', unsigned int TMaxLength = 64, char TPadChar = ' '>
00031   class /*GDCM_EXPORT*/ String : public std::string /* PLEASE do not export me */
00032   {
00033   // UI wants \0 for pad character, while ASCII ones wants space char... do not allow anything else
00034   GDCM_STATIC_ASSERT( TPadChar == ' ' || TPadChar == 0 );
00035
00036   public:
00037   // typedef are not inherited:
00038   typedef std::string::value_type      value_type;
00039   typedef std::string::pointer         pointer;
00040   typedef std::string::reference       reference;
00041   typedef std::string::const_reference const_reference;
00042   typedef std::string::size_type       size_type;
00043   typedef std::string::difference_type difference_type;
00044   typedef std::string::iterator        iterator;
00045   typedef std::string::const_iterator  const_iterator;
00046   typedef std::string::reverse_iterator reverse_iterator;
00047   typedef std::string::const_reverse_iterator const_reverse_iterator;
00048
00050   String(): std::string() {}
00051   String(const value_type* s): std::string(s)
00052   {
00053   if( size() % 2 )
00054   {
00055     push_back( TPadChar );
00056   }
00057   }
00058   String(const value_type* s, size_type n): std::string(s, n)
00059   {
00060   // We are being passed a const char* pointer, so s[n] == 0 (guaranteed!)
00061   if( n % 2 )
00062   {
00063     push_back( TPadChar );
00064   }
00065   }
00066   String(const std::string& s, size_type pos=0, size_type n=npos):
00067   std::string(s, pos, n)
00068   {
00069   // FIXME: some users might already have padded the string 's' with a trailing \0...
00070   if( size() % 2 )
00071   {
00072     push_back( TPadChar );
00073   }
00074   }
00075
00077   operator const char *() const { return this->c_str(); }
00078
00080   bool IsValid() const {
00081   // Check Length:
00082   size_type l = size();
00083   if( l > TMaxLength ) return false;
00084   return true;
00085   }

```

```


00086
00087 gdcM::String<TDelimiter, TMaxLength, TPadChar> Truncate() const {
00088     if( !IsValid() ) return *this;
00089     std::string str = *this; // copy
00090     str.resize( TMaxLength );
00091     return str;
00092 }
00093
00096 std::string Trim() const {
00097     std::string str = *this; // copy
00098     std::string::size_type pos1 = str.find_first_not_of(' ');
00099     std::string::size_type pos2 = str.find_last_not_of(' ');
00100     str = str.substr( (pos1 == std::string::npos) ? 0 : pos1,
00101         (pos2 == std::string::npos) ? (str.size() - 1) : (pos2 - pos1 + 1));
00102     return str;
00103 }
00104
00105 static std::string Trim(const char *input) {
00106     if( !input ) return "";
00107     std::string str = input;
00108     std::string::size_type pos1 = str.find_first_not_of(' ');
00109     std::string::size_type pos2 = str.find_last_not_of(' ');
00110     str = str.substr( (pos1 == std::string::npos) ? 0 : pos1,
00111         (pos2 == std::string::npos) ? (str.size() - 1) : (pos2 - pos1 + 1));
00112     return str;
00113 }
00114 };
00115 template <char TDelimiter, unsigned int TMaxLength, char TPadChar>
00116 inline std::istream& operator>>(std::istream &is, String<TDelimiter,TMaxLength,TPadChar> &ms)
00117 {
00118     if(is)
00119     {
00120         std::getline(is, ms, TDelimiter);
00121         // no such thing as std::get where the delim char would be left, so I need to manually add it back...
00122         // hopefully this is the right thing to do (no overhead)
00123         if( !is.eof() ) is.putback( TDelimiter );
00124     }
00125     return is;
00126 }
00127 //template <char TDelimiter = EOF, unsigned int TMaxLength = 64, char TPadChar = ' '>
00128 //String String::Trim() const
00129 //{
00130 //    String s;
00131 //    return s;
00132 //}
00133
00134 } // end namespace gdcM
00135
00136 #endif //GDCMSTRING_H

```


11.65 gdcmSubject.h File Reference

```
#include "gdcmObject.h"
```

Include dependency graph for gdcmSubject.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::Subject](#)
Subject.

Namespaces

- namespace [gdcm](#)

11.66 gdcmSubject.h

[Go to the documentation of this file.](#)

```

00001  /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
  
```

```

00006 All rights reserved.
00007 See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009 This software is distributed WITHOUT ANY WARRANTY; without even
00010 the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011 PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMSUBJECT_H
00015 #define GDCMSUBJECT_H
00016
00017 #include "gdcmObject.h"
00018
00019 namespace gdcm
00020 {
00021 class Event;
00022 class Command;
00023 class SubjectInternals;
00028 class GDCM_EXPORT Subject : public Object
00029 {
00030 public:
00031 Subject();
00032 ~Subject() override;
00033
00042 unsigned long AddObserver(const Event & event, Command *);
00043 unsigned long AddObserver(const Event & event, Command *) const;
00044
00050 Command* GetCommand(unsigned long tag);
00051
00053 void InvokeEvent( const Event & );
00054
00057 void InvokeEvent( const Event & ) const;
00058
00060 void RemoveObserver(unsigned long tag);
00061
00063 void RemoveAllObservers();
00064
00066 bool HasObserver( const Event & event ) const;
00067
00068 protected:
00069
00070 private:
00071 SubjectInternals *Internals;
00072 private:
00073 };
00074
00075 } // end namespace gdcm
00076
00077 #endif //GDCMSUBJECT_H

```


11.67 gdcmSwapCode.h File Reference

```

#include "gdcmTypes.h"
#include <iostream>

```


Include dependency graph for gdcmSwapCode.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::SwapCode](#)
SwapCode representation.

Namespaces

- namespace [gdcm](#)

Functions

- `std::ostream & gdcm::operator<< (std::ostream &os, const SwapCode &sc)`

11.68 gdcmSwapCode.h

[Go to the documentation of this file.](#)

```

00001  /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

```

```

00008
00009     This software is distributed WITHOUT ANY WARRANTY; without even
00010     the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011     PURPOSE. See the above copyright notice for more information.
00012
00013     =====*/
00014 #ifndef GDCMSWAPCODE_H
00015 #define GDCMSWAPCODE_H
00016
00017 #include "gdcmTypes.h"
00018 #include <iostream>
00019
00020 namespace gdcm
00021 {
00022
00026 class GDCM_EXPORT SwapCode
00027 {
00028 public:
00029     typedef enum {
00030         Unknown          = 0,
00031         LittleEndian     = 1234,
00032         BigEndian        = 4321,
00033         BadLittleEndian  = 3412,
00034         BadBigEndian     = 2143
00035     } SwapCodeType;
00036
00037     operator SwapCodeType() const { return SwapCodeValue; }
00038     SwapCode(SwapCodeType sc = Unknown):SwapCodeValue(sc) { }
00039     static const char* GetSwapCodeString(SwapCode const & sc);
00040
00041     friend std::ostream& operator<<(std::ostream& os, const SwapCode& sc);
00042 protected:
00043     static int GetIndex(SwapCode const & sc);
00044
00045 private:
00046     SwapCodeType SwapCodeValue;
00047 };
00048 //-----
00049 inline std::ostream& operator<<(std::ostream& os, const SwapCode& sc)
00050 {
00051     os << SwapCode::GetSwapCodeString(sc);
00052     return os;
00053 }
00054
00055 } // end namespace gdcm
00056
00057 #endif //GDCMSWAPCODE_H

```


11.69 gdcmSwapper.h File Reference

```

#include "gdcmSwapCode.h"
#include "gdcmSwapper.txx"

```

Include dependency graph for gdcmSwapper.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::SwapperDoOp](#)
- class [gdcm::SwapperNoOp](#)

Namespaces

- namespace [gdcm](#)

11.70 gdcmSwapper.h

[Go to the documentation of this file.](#)

```

00001  /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012


```

```
00013 =====*/
00014 #ifndef GDCMSWAPPER_H
00015 #define GDCMSWAPPER_H
00016
00017 #include "gdcmswapCode.h"
00018
00019 namespace gdcmswap
00020 {
00021
00022 #ifdef GDCM_WORDS_BIGENDIAN
00023 class SwapperDoOp
00024 {
00025 public:
00026     template <typename T> static T Swap(T val) {return val;}
00027     template <typename T> static void SwapArray(T *, size_t ) {}
00028 };
00029
00030 class SwapperNoOp
00031 {
00032 public:
00033     template <typename T> static T Swap(T val);
00034     template <typename T>
00035     static void SwapArray(T *array, size_t n)
00036     {
00037         // TODO: need to unroll loop:
00038         for(size_t i = 0; i < n; ++i)
00039         {
00040             array[i] = Swap<T>(array[i]);
00041         }
00042     }
00043 };
00044 #else
00045 class SwapperNoOp
00046 {
00047 public:
00048     template <typename T> static T Swap(T val) {return val;}
00049     template <typename T> static void SwapArray(T *, size_t ) {}
00050 };
00051
00052 class SwapperDoOp
00053 {
00054 public:
00055     template <typename T> static T Swap(T val);
00056     template <typename T>
00057     static void SwapArray(T *array, size_t n)
00058     {
00059         // TODO: need to unroll loop:
00060         for(size_t i = 0; i < n; ++i)
00061         {
00062             array[i] = Swap<T>(array[i]);
00063         }
00064     }
00065 };
00066 #endif
00067
00068 } // end namespace gdcmswap
00069
00070 #include "gdcmswapCode.txx"
00071
00072 #endif //GDCMSWAPPER_H
```

11.71 gdcmSystem.h File Reference

```
#include "gdcmTypes.h"
```

Include dependency graph for gdcmSystem.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::System](#)
Class to do system operation.

Namespaces

- namespace [gdcm](#)

11.72 gdcmSystem.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008

```

```

00009      This software is distributed WITHOUT ANY WARRANTY; without even
00010      the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011      PURPOSE. See the above copyright notice for more information.
00012
00013      =====*/
00014      #ifndef GDCMSYSTEM_H
00015      #define GDCMSYSTEM_H
00016
00017      #include "gdcmTypes.h"
00018
00019      namespace gdcm
00020      {
00021
00022      class GDCM_EXPORT System
00023      {
00024      public:
00025          static bool MakeDirectory(const char *path);
00026          static bool FileExists(const char* filename);
00027          static bool FileIsDirectory(const char* name);
00028          static bool FileIsSymlink(const char* name);
00029          static bool RemoveFile(const char* source);
00030          static bool DeleteDirectory(const char *source);
00031
00032          static std::wstring ConvertToUNC(const char *utf8path);
00033
00034          static const char *GetLastSystemError();
00035
00036          static size_t FileSize(const char* filename);
00037
00038          static time_t FileTime(const char* filename);
00039
00040          static const char *GetCurrentProcessFileName();
00041
00042          static const char *GetCurrentModuleFileName();
00043
00044          static const char *GetCurrentResourcesDirectory();
00045
00046          // TODO some system calls
00047          // Chdir
00048          // copy a file
00049
00050          static bool GetHostName(char hostname[255]);
00051
00052          // In the following the size '22' is explicitly listed. You need to pass in
00053          // at least 22bytes of array. If the string is an output it will be
00054          // automatically padded ( array[21] == 0 ) for you.
00055          // Those functions: GetCurrentDateTime / FormatDateTime / ParseDateTime do
00056          // not return the &YYZZ part of the DT structure as defined in DICOM PS 3.5 -
00057          // 2008 In this case it is simple to split the date[22] into a DA and TM
00058          // structure
00059
00060          static bool GetCurrentDateTime(char date[22]);
00061
00062          static bool FormatDateTime(char date[22], time_t t, long milliseconds = 0);
00063
00064          static bool ParseDateTime(time_t &timep, const char date[22]);
00065
00066          static bool ParseDateTime(time_t &timep, long &milliseconds, const char date[22]);
00067
00068          static const char *GetTimezoneOffsetFromUTC();
00069
00070          static size_t EncodeBytes(char *out, const unsigned char *data, int size);
00071
00072          static int StrCaseCmp(const char *s1, const char *s2);
00073          static int StrNCaseCmp(const char *s1, const char *s2, size_t n);
00074
00075          static const char * GetCWD();
00076
00077          static char *StrTokR(char *ptr, const char *sep, char **end);
00078
00079          static char *StrSep(char **stringp, const char *delim);
00080
00081          static const char *GetLocaleCharset();
00082
00083          /*
00084          static void SetArgv0(const char *);
00085          static const char* GetArgv0();
00086          */
00087
00088      protected:
00089          static bool GetPermissions(const char* file, unsigned short& mode);

```

```


00144     static bool SetPermissions(const char* file, unsigned short mode);
00145
00146 private:
00147 };
00148
00149 } // end namespace gdc
00150
00151 #endif //GDCMSYSTEM_H

```

11.73 gdcTerminal.h File Reference

```
#include "gdcTypes.h"
```

Include dependency graph for gdcTerminal.h:



Namespaces

- namespace [gdc](#)
- namespace [gdc::terminal](#)

Class for Terminal.

Enumerations

- enum [gdc::terminal::Attribute](#) {
[gdc::terminal::reset](#) = 0 ,
[gdc::terminal::bright](#) = 1 ,
[gdc::terminal::dim](#) = 2 ,
[gdc::terminal::underline](#) = 3 ,
[gdc::terminal::blink](#) = 5 ,
[gdc::terminal::reverse](#) = 7 ,
[gdc::terminal::hidden](#) = 8 }

- enum `gdcm::terminal::Color` {
`gdcm::terminal::black` = 0 ,
`gdcm::terminal::red` ,
`gdcm::terminal::green` ,
`gdcm::terminal::yellow` ,
`gdcm::terminal::blue` ,
`gdcm::terminal::magenta` ,
`gdcm::terminal::cyan` ,
`gdcm::terminal::white` }
- enum `gdcm::terminal::Mode` {
`gdcm::terminal::CONSOLE` = 0 ,
`gdcm::terminal::VT100` }

Functions

- `GDCM_EXPORT std::string gdcm::terminal::setAttribute (Attribute att)`
- `GDCM_EXPORT std::string gdcm::terminal::setbgcolor (Color c)`
- `GDCM_EXPORT std::string gdcm::terminal::setfgcolor (Color c)`
- `GDCM_EXPORT void gdcm::terminal::setmode (Mode m)`

11.74 gdcmTerminal.h

[Go to the documentation of this file.](#)

```

00001  /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013  =====*/
00014  #ifndef GDCMTERMINAL_H
00015  #define GDCMTERMINAL_H
00016
00017  #include "gdcmTypes.h"
00018
00019
00020  namespace gdcm
00021  {
00022  //-----
00023
00024  namespace terminal
00025  {
00026      typedef enum
00027      {
00028          CONSOLE = 0,
00029          VT100
00030      } Mode;
00031
00032      typedef enum
00033      {
00034          black = 0,
00035          red,
00036          green,
00037          yellow, // brown ??
00038          blue,
00039          magenta,
00040          cyan,
00041          white
00042      } Color;
00043  }
00044  }

```



```

00047     } Color;
00048     typedef enum
00049     {
00050         reset      = 0,
00051         bright     = 1, // bold
00052         dim        = 2,
00053         underline  = 3,
00054         blink      = 5,
00055         reverse    = 7,
00056         hidden     = 8
00057     } Attribute;
00058     GDCM_EXPORT std::string setattribute( Attribute att );
00059     GDCM_EXPORT std::string setfgcolor( Color c );
00060     GDCM_EXPORT std::string setbgcolor( Color c );
00061     GDCM_EXPORT void setmode( Mode m);
00062 }
00063
00064 } // end namespace gdcm
00065 //-----
00066 #endif //GDCMTERMINAL_H

```


11.75 gdcmTestDriver.h File Reference

```

#include <clocale>
#include <locale>

```

Include dependency graph for gdcmTestDriver.h:



11.76 gdcmTestDriver.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003     Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005     Copyright (c) 2006-2011 Mathieu Malaterre
00006     All rights reserved.
00007     See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009     This software is distributed WITHOUT ANY WARRANTY; without even
00010     the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011     PURPOSE. See the above copyright notice for more information.
00012
00013     =====*/
00014 // This header is included by all the C++ test drivers in GDCM.
00015 #ifndef GDCMTESTDRIVER_H

```

```

00016 #define GDCMTESTDRIVER_H
00017
00018 // CREATE_TEST_SOURCELIST supports the flag EXTRA_INCLUDE but only one per call.
00019 // So there is no way to specify we want to include two files... instead
00020 // gather the #include in a single file and include that one...
00021 #include <clocale> // C setlocale()
00022 #include <locale> // C++ locale
00023
00024 #endif // GDCMTESTDRIVER_H


```

11.77 gdcmTesting.h File Reference

```
#include "gdcmTypes.h"
```

```
#include <iostream>
```

Include dependency graph for gdcmTesting.h:



Classes

- class [gdcm::Testing](#)
class for testing

Namespaces

- namespace [gdcm](#)

11.78 gdcmTesting.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003 Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005 Copyright (c) 2006-2011 Mathieu Malaterre
00006 All rights reserved.

```

```


00007 See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009 This software is distributed WITHOUT ANY WARRANTY; without even
00010 the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011 PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMTESTING_H
00015 #define GDCMTESTING_H
00016
00017 #include "gdcmTypes.h"
00018
00019 #include <iostream>
00020
00021 namespace gdcm
00022 {
00023 //-----
00024 class GDCM_EXPORT Testing
00025 {
00026 public :
00027     Testing() = default;
00028     ~Testing() = default;
00029
00030     static bool ComputeMD5(const char *buffer, size_t buf_len,
00031         char digest_str[33]);
00032     static bool ComputeFileMD5(const char *filename, char digest_str[33]);
00033
00034     void Print(std::ostream &os = std::cout);
00035
00036     static const char * const * GetFileNames();
00037     static unsigned int GetNumberOfFileNames();
00038     static const char * GetFileName(unsigned int file);
00039
00040     typedef const char* const (*MediaStorageDataFilesType) [2];
00041     static MediaStorageDataFilesType GetMediaStorageDataFiles();
00042     static unsigned int GetNumberOfMediaStorageDataFiles();
00043     static const char * const * GetMediaStorageDataFile(unsigned int file);
00044     static const char * GetMediaStorageFromFile(const char *filepath);
00045
00046     typedef const char* const (*MD5DataImagesType) [2];
00047     static MD5DataImagesType GetMD5DataImages();
00048     static unsigned int GetNumberOfMD5DataImages();
00049     static const char * const * GetMD5DataImage(unsigned int file);
00050     static const char * GetMD5FromFile(const char *filepath);
00051
00052     static const char * GetMD5FromBrokenFile(const char *filepath);
00053
00054     static std::streamoff GetStreamOffsetFromFile(const char *filepath);
00055
00056     static std::streamoff GetSelectedTagsOffsetFromFile(const char *filepath);
00057
00058     static std::streamoff GetSelectedPrivateGroupOffsetFromFile(const char *filepath);
00059
00060     static int GetLossyFlagFromFile(const char *filepath);
00061
00062     static const char * GetDataRoot();
00063
00064     static const char * GetDataExtraRoot();
00065
00066     static const char * GetPixelSpacingDataRoot();
00067
00068     static const char * GetTempDirectory(const char * subdir = nullptr);
00069
00070     static const wchar_t * GetTempDirectoryW(const wchar_t * subdir = nullptr);
00071
00072     static const char * GetTempFilename(const char *filename, const char * subdir = nullptr);
00073
00074     static const wchar_t* GetTempFilenameW(const wchar_t *filename, const wchar_t* subdir = nullptr);
00075
00076     static const char *GetSourceDirectory();
00077 };
00078 } // end namespace gdcm
00079 //-----
00080 #endif //GDCMTESTING_H

```

11.79 gdcmTrace.h File Reference

```
#include "gdcmTypes.h"
#include "gdcmSystem.h"
#include <iosfwd>
#include <cassert>
```

Include dependency graph for gdcmTrace.h:



This graph shows which files directly or indirectly include this file:



Classes

- class `gdcm::Trace`
Trace.

Namespaces

- namespace `gdcm`

Macros

- #define [GDCM_FUNCTION](#) "<unknown>"
- #define [gdcmAssertAlwaysMacro](#)(arg)
AssertAlways.
- #define [gdcmAssertMacro](#)(arg)
Assert.
- #define [gdcmDebugMacro](#)(msg)
Debug.
- #define [gdcmErrorMacro](#)(msg)
Error this is pretty bad, more than just warning It could mean lost of data, something not handle...
- #define [gdcmWarningMacro](#)(msg)
Warning.

11.79.1 Macro Definition Documentation

11.79.1.1 GDCM_FUNCTION

```
#define GDCM_FUNCTION "<unknown>"
```

11.79.1.2 gdcmAssertAlwaysMacro

```
#define gdcmAssertAlwaysMacro(  
    arg)
```

Value:

[gdcmAssertMacro](#)(arg)

AssertAlways.

Parameters

<i>arg</i>	argument to test An easy solution to pass also a message is to do: <code>gdcmAssertMacro("my message" && 2 < 3)</code>
------------	---

Referenced by [gdcm::DataElement::GetValue\(\)](#), [gdcm::DataElement::GetValue\(\)](#), [gdcm::BasicOffsetTable::Read\(\)](#), [gdcm::SequenceOfFragments::ReadValue\(\)](#), [gdcm::DataSet::Replace\(\)](#), [gdcm::DataSet::ReplaceEmpty\(\)](#), and [gdcm::VR::Write\(\)](#).

11.79.1.3 gdcmAssertMacro

```
#define gdcmAssertMacro(  
    arg)
```

Value:

```
{  
    if( !(arg) )  
    {  
        std::ostringstream osmacro;  
        osmacro << "Assert: In " __FILE__ ", line " << __LINE__  
            << ", function " << GDCM_FUNCTION  
            << "\n\n";  
        std::ostream &_os = gdcm::Trace::GetErrorStream();  
        _os << osmacro.str() << std::endl;  
        assert ( arg );  
    }  
}  
GDCM_NOOP_STATEMENT
```

Assert.

Parameters

<i>arg</i>	argument to test An easy solution to pass also a message is to do: <code>gdcmAssertMacro("my message" && 2 < 3)</code>
------------	---

Referenced by [gdcm::PixelFormat::SetSamplesPerPixel\(\)](#).

11.79.1.4 gdcmDebugMacro

```
#define gdcmDebugMacro(  
    msg)
```

Value:

```
{  
    if( gdcm::Trace::GetDebugFlag() )  
    {  
        std::ostringstream osmacro;  
        osmacro << "Debug: In " __FILE__ ", line " << __LINE__  
            << ", function " << GDCM_FUNCTION << '\n'  
            << "Last system error was: "  
            << gdcm::System::GetLastSystemError() << '\n' << msg;  
        std::ostream &_os = gdcm::Trace::GetDebugStream();  
        _os << osmacro.str() << "\n\n" << std::endl;  
    }  
}  
GDCM_NOOP_STATEMENT
```

Debug.

Parameters

<i>msg</i>	message part
------------	--------------

Referenced by [gdcm::OpenSSLCryptoFactory::OpenSSLCryptoFactory\(\)](#), [gdcm::OpenSSLP7CryptoFactory::OpenSSLP7CryptoFactory\(\)](#), [gdcm::Item::Read\(\)](#), [gdcm::SequenceOfItems::Read\(\)](#), [gdcm::VR::Read\(\)](#), [gdcm::SequenceOfFragments::ReadPreValue\(\)](#), and [gdcm::SequenceOfFragments::ReadValue\(\)](#).

11.79.1.5 gdcmErrorMacro

```
#define gdcmErrorMacro(  
    msg)
```

Value:

```
{  
    if( gdcm::Trace::GetErrorFlag() )  
    {  
        std::ostringstream osmacro;  
        osmacro << "Error: In " __FILE__ ", line " << __LINE__  
            << ", function " << GDCM_FUNCTION << '\n'  
            << msg << "\n\n";  
        std::ostream &_os = gdcm::Trace::GetErrorStream();  
        _os << osmacro.str() << std::endl;  
    }  
}  
GDCM_NOOP_STATEMENT
```

Error this is pretty bad, more than just warning It could mean lost of data, something not handle...

Parameters

<i>msg</i>	second message part
------------	---------------------

Referenced by [gdcm::CommandDataSet::Insert\(\)](#), [gdcm::DataSet::Insert\(\)](#), [gdcm::FileMetaInformation::Insert\(\)](#), [gdcm::Item::Read\(\)](#), and [gdcm::Fragment::ReadBacktrack\(\)](#).

11.79.1.6 gdcmWarningMacro

```
#define gdcmWarningMacro(  
    msg)
```

Value:

```
{  
    if( gdcm::Trace::GetWarningFlag() )  
    {  
        std::ostringstream osmacro;  
        osmacro << "Warning: In " __FILE__ ", line " << __LINE__  
            << ", function " << GDCM_FUNCTION << "\n"  
            << msg << "\n\n";  
        std::ostream &_os = gdcm::Trace::GetWarningStream();  
        _os << osmacro.str() << std::endl;  
    }  
}  
GDCM_NOOP_STATEMENT
```

Warning.

Parameters

<i>msg</i>	message part
------------	--------------

Referenced by [gdcm::DataSet::InsertDataElement\(\)](#), [gdcm::Item::Read\(\)](#), [gdcm::SequenceOfItems::Read\(\)](#), [gdcm::Fragment::ReadBacktrack\(\)](#), [gdcm::Fragment::ReadValue\(\)](#), [gdcm::SequenceOfFragments::ReadValue\(\)](#), [gdcm::OpenSSL7CryptographicMessageSyntax::SetPassw](#) and [gdcm::Item::Write\(\)](#).

11.80 gdcmTrace.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMTRACE_H
00015 #define GDCMTRACE_H
00016
00017 #include "gdcmTypes.h"
00018 #include "gdcmSystem.h"
00019
00020 #include <iosfwd>
00021 #include <cassert>
00022
00023 namespace gdcm
00024 {
00025
00041 class GDCM_EXPORT Trace
00042 {
00043 public :
00044   Trace();
00045   ~Trace();
00046
00049   static void SetStream(std::ostream &os);
00050   static std::ostream &GetStream();
00051
00053   static void SetDebugStream(std::ostream &os);
00054   static std::ostream &GetDebugStream();
00055
00057   static void SetWarningStream(std::ostream &os);
00058   static std::ostream &GetWarningStream();
00059
00061   static void SetErrorStream(std::ostream &os);
00062   static std::ostream &GetErrorStream();
00063
00066   static void SetStreamToFile( const char *filename );
00067
00069   static void SetDebug(bool debug);
00070   static void DebugOn();
00071   static void DebugOff();
00072   static bool GetDebugFlag();
00073
00075   static void SetWarning(bool debug);
00076   static void WarningOn();
00077   static void WarningOff();
00078   static bool GetWarningFlag();
00079
00081   static void SetError(bool debug);
00082   static void ErrorOn();
00083   static void ErrorOff();
00084   static bool GetErrorFlag();
00085
00086 protected:
00087 private:
00088 };
00089
00090 // Here we define function this is the only way to be able to pass
00091 // stuff with indirection like:
00092 // gdcmDebug( "my message:" « i « '\t' );
00093 // You cannot use function unless you use vnsprintf ...
00094
00095 // __FUNCTION__ is not always defined by preprocessor
00096 // In c++ we should use __PRETTY_FUNCTION__ instead...
00097 #ifdef GDCM_CXX_HAS_FUNCTION
00098 // Handle particular case for GNU C++ which also defines __PRETTY_FUNCTION__
00099 // which is a lot nice in C++
00100 #ifdef __BORLANDC__

```



```

00101 # define __FUNCTION__ __FUNC__
00102 #endif
00103 #ifdef __GNUC__
00104 # define GDCM_FUNCTION __PRETTY_FUNCTION__
00105 #else
00106 # define GDCM_FUNCTION __FUNCTION__
00107 #endif //__GNUC__
00108 #else
00109 # define GDCM_FUNCTION "<unknown>"
00110 #endif //GDCM_CXX_HAS_FUNCTION
00111
00116 #if defined(NDEBUG) && !defined(GDCM_ALWAYS_TRACE_MACRO)
00117 #define gdcDebugMacro(msg) GDCM_NOOP_STATEMENT
00118 #else
00119 #define gdcDebugMacro(msg)
00120 {
00121     if( gdc::Trace::GetDebugFlag() )
00122     {
00123         std::ostringstream osmacro;
00124         osmacro < "Debug: In " __FILE__ ", line " < __LINE__
00125             < ", function " < GDCM_FUNCTION < '\n'
00126             < "Last system error was: "
00127             < gdc::System::GetLastSystemError() < '\n' < msg;
00128         std::ostream &_os = gdc::Trace::GetDebugStream();
00129         _os < osmacro.str() < "\n\n" < std::endl;
00130     }
00131 }
00132 GDCM_NOOP_STATEMENT
00133 #endif //NDEBUG
00134
00139 #if defined(NDEBUG) && !defined(GDCM_ALWAYS_TRACE_MACRO)
00140 #define gdcWarningMacro(msg) GDCM_NOOP_STATEMENT
00141 #else
00142 #define gdcWarningMacro(msg)
00143 {
00144     if( gdc::Trace::GetWarningFlag() )
00145     {
00146         std::ostringstream osmacro;
00147         osmacro < "Warning: In " __FILE__ ", line " < __LINE__
00148             < ", function " < GDCM_FUNCTION < "\n"
00149             < msg < "\n\n";
00150         std::ostream &_os = gdc::Trace::GetWarningStream();
00151         _os < osmacro.str() < std::endl;
00152     }
00153 }
00154 GDCM_NOOP_STATEMENT
00155 #endif //NDEBUG
00156
00162 #if defined(NDEBUG) && !defined(GDCM_ALWAYS_TRACE_MACRO)
00163 #define gdcErrorMacro(msg) GDCM_NOOP_STATEMENT
00164 #else
00165 #define gdcErrorMacro(msg)
00166 {
00167     if( gdc::Trace::GetErrorFlag() )
00168     {
00169         std::ostringstream osmacro;
00170         osmacro < "Error: In " __FILE__ ", line " < __LINE__
00171             < ", function " < GDCM_FUNCTION < '\n'
00172             < msg < "\n\n";
00173         std::ostream &_os = gdc::Trace::GetErrorStream();
00174         _os < osmacro.str() < std::endl;
00175     }
00176 }
00177 GDCM_NOOP_STATEMENT
00178 #endif //NDEBUG
00179
00186 #if defined(NDEBUG) && !defined(GDCM_ALWAYS_TRACE_MACRO)
00187 #define gdcAssertMacro(arg) GDCM_NOOP_STATEMENT
00188 #else
00189 #define gdcAssertMacro(arg)
00190 {
00191     if( !(arg) )
00192     {
00193         std::ostringstream osmacro;
00194         osmacro < "Assert: In " __FILE__ ", line " < __LINE__
00195             < ", function " < GDCM_FUNCTION
00196             < "\n\n";
00197         std::ostream &_os = gdc::Trace::GetErrorStream();
00198         _os < osmacro.str() < std::endl;
00199         assert ( arg );
00200     }

```

```

00201 }
00202 GDCM_NOOP_STATEMENT
00203 #endif //NDEBUG
00204
00211 #if defined(NDEBUG)
00212 // User asked for release compilation, but still need to report
00213 // if grave issue.
00214 #define gdcmAssertAlwaysMacro(arg) \
00215 {
00216     if( !(arg) )
00217     {
00218         std::ostringstream osmacro;
00219         osmacro < "Assert: In " __FILE__ ", line " << __LINE__
00220             < ", function " << GDCM_FUNCTION
00221             < "\n\n";
00222         throw osmacro.str();
00223     }
00224 }
00225 GDCM_NOOP_STATEMENT
00226 #else
00227 // Simply reproduce gdcmAssertMacro behavior:
00228 #define gdcmAssertAlwaysMacro(arg) gdcmAssertMacro(arg)
00229 #endif //NDEBUG
00230
00231 } // end namespace gdc
00232 //-----
00233 #endif //GDCMTRACE_H

```


11.81 gdcTypes.h File Reference

```

#include "gdcConfigure.h"
#include "gdcWin32.h"
#include "gdcLegacyMacro.h"
#include <stdint>

```

Include dependency graph for gdcTypes.h:



11.82 gdcTypes.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003     Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005     Copyright (c) 2006-2011 Mathieu Malaterre
00006     All rights reserved.

```

```


00007  See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009      This software is distributed WITHOUT ANY WARRANTY; without even
00010      the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011      PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMTYPES_H
00015 #define GDCMTYPES_H
00016
00017 #include "gdcmConfigure.h"
00018 #include "gdcmWin32.h"
00019 #include "gdcmLegacyMacro.h"
00020
00021 //-----
00022 #include <stdint>
00023
00024 //-----
00025 #endif //GDCMTYPES_H

```

11.83 gdcmUnpacker12Bits.h File Reference

```
#include "gdcmTypes.h"
```

Include dependency graph for gdcmUnpacker12Bits.h:



Classes

- class [gdcm::Unpacker12Bits](#)
Pack/Unpack 12 bits pixel into 16bits.

Namespaces

- namespace [gdcm](#)

11.84 gdcmUnpacker12Bits.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013   =====*/
00014 #ifndef GDCMUNPACKER12BITS_H
00015 #define GDCMUNPACKER12BITS_H
00016
00017 #include "gdcmTypes.h"
00018
00019 namespace gdcm
00020 {
00034   class GDCM_EXPORT Unpacker12Bits
00035   {
00036   public:
00040     static bool Pack(char *out, const char *in, size_t n);
00041
00045     static bool Unpack(char *out, const char *in, size_t n);
00046   };
00047
00048 } // end namespace gdcm
00049
00050 #endif //GDCMUNPACKER12BITS_H

```


11.85 gdcmVersion.h File Reference

```

#include "gdcmTypes.h"
#include <iostream>

```

Include dependency graph for gdcmVersion.h:



Classes

- class [gdcm::Version](#)
major/minor and build version

Namespaces

- namespace `gdcm`

Functions

- `std::ostream & gdcm::operator<< (std::ostream &os, const Version &v)`

11.86 gdcmVersion.h

[Go to the documentation of this file.](#)

```

00001  /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013  =====*/
00014  #ifndef GDCMVERSION_H
00015  #define GDCMVERSION_H
00016
00017  #include "gdcmTypes.h"
00018  #include <iostream>
00019
00020  namespace gdcm
00021  {
00022  //-----
00023  class GDCM_EXPORT Version
00024  {
00025  {
00026      friend std::ostream& operator<<(std::ostream &os, const Version &v);
00027  public :
00028      static const char *GetVersion();
00029      static int GetMajorVersion();
00030      static int GetMinorVersion();
00031      static int GetBuildVersion();
00032
00033      void Print(std::ostream &os = std::cout) const;
00034
00035  //protected:
00036      Version() = default;
00037      ~Version() = default;
00038  };
00039  //-----
00040  inline std::ostream& operator<<(std::ostream &os, const Version &v)
00041  {
00042      v.Print( os );
00043      return os;
00044  }
00045  } // end namespace gdcm
00046  //-----
00047  #endif //GDCMVERSION_H

```

11.87 gdcmWin32.h File Reference

This graph shows which files directly or indirectly include this file:



Macros

- `#define GDCM_EXPORT`

11.87.1 Macro Definition Documentation

11.87.1.1 GDCM_EXPORT

```
#define GDCM_EXPORT
```

Referenced by `gdcm::terminal::setAttribute()`, `gdcm::terminal::setbgcolor()`, `gdcm::terminal::setfgcolor()`, and `gdcm::terminal::setmode()`.

11.88 gdcmWin32.h

[Go to the documentation of this file.](#)

```
00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013   =====*/
00014
00015 #ifndef GDCMWIN32_H
00016 #define GDCMWIN32_H
00017
00018 #if !defined(GDCMTYPES_H)
00019 #error you need to include gdcmTypes.h instead
00020 #endif
00021 //-----
00022 // http://gcc.gnu.org/wiki/Visibility
00023 #if defined(_WIN32) && defined(GDCM_BUILD_SHARED_LIBS)
00024   #if (defined(gdcmCommon_EXPORTS) || defined(gdcmDICT_EXPORTS) || defined(gdcmDSED_EXPORTS) ||
00025        defined(gdcmIOD_EXPORTS) || defined(gdcmMSFF_EXPORTS) || defined(gdcmMEXD_EXPORTS) ||
00026        defined(_gdcmswig_EXPORTS)) || defined(vtkgdcM_EXPORTS)
00027     #define GDCM_EXPORT __declspec( dllexport )
00028   #else
00029     #define GDCM_EXPORT __declspec( dllimport )
00030   #endif
00031 #else
00032   #if __GNUC__ >= 4 && defined(GDCM_BUILD_SHARED_LIBS)
00033     #define GDCM_EXPORT __attribute__ ((visibility ("default")))
00034   #define GDCM_LOCAL __attribute__ ((visibility ("hidden")))
00035   #else
00036     #define GDCM_EXPORT
00037   #endif
00038 #endif
00039 #undef GDCM_EXPORT
00040 #define GDCM_EXPORT
00041 #endif
00042
00043 // In VTK 4.2 vtkWrapPython does not like anything other than VTK_*EXPORT
00044 // [ 86%] Generating vtkGDCMImageReaderPython.cxx
00045 // syntax error
```

```

00046 // *** SYNTAX ERROR found in parsing the header file
00047 //usr/local/src/gdcm2/tags/gdcm-2-0-11/Utilities/VTK/vtkGDCMImageReader.h before line 128***
00047 // make[2]: *** [Utilities/VTK/vtkGDCMImageReaderPython.cxx] Error 1
00048 // make[1]: *** [Utilities/VTK/CMakeFiles/vtkgdcmPythonD.dir/all] Error 2
00049 // make: *** [all] Error 2
00050
00051 #if defined(VTK_MAJOR_VERSION) && ( VTK_MAJOR_VERSION == 4 )
00052 #undef VTK_EXPORT
00053 #define VTK_EXPORT GDCM_EXPORT
00054 #endif
00055
00056 //-----
00057 //This is needed when compiling in debug mode
00058 #ifdef _MSC_VER
00059 // to allow construct such as: std::numeric_limits<int>::max() we need the following:
00060 // warning C4003: not enough actual parameters for macro 'max'
00061 #ifndef NOMINMAX
00062 #define NOMINMAX
00063 #endif
00064 #pragma warning ( default : 4263 ) /* no override, call convention differs */
00065 // 'identifier' : class 'type' needs to have dll-interface to be used by
00066 // clients of class 'type2'
00067 #pragma warning ( disable : 4251 )
00068 // non dll-interface class 'type' used as base for dll-interface class 'type2'
00069 #pragma warning ( disable : 4275 )
00070 // 'identifier' : identifier was truncated to 'number' characters in the
00071 // debug information
00072 #pragma warning ( disable : 4786 )
00073 // 'identifier' : decorated name length exceeded, name was truncated
00074 #pragma warning ( disable : 4503 )
00075 #endif // _MSC_VER
00076
00077 //-----
00078 #endif //GDCMWIN32_H

```


11.89 gdcmCSAHeaderDict.h File Reference

```


#include "gdcmTypes.h"
#include "gdcmTag.h"
#include "gdcmCSAHeaderDictEntry.h"
#include <iostream>
#include <iomanip>
#include <set>
#include <exception>

```

Include dependency graph for gdcmCSAHeaderDict.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcml::CSAHeaderDict](#)
Class to represent a map of [CSAHeaderDictEntry](#).
- class [gdcml::CSAHeaderDictException](#)

Namespaces

- namespace [gdcml](#)

Functions

- `std::ostream & gdcml::operator<< (std::ostream &os, const CSAHeaderDict &val)`

11.90 gdcmlCSAHeaderDict.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcml.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012   =====*/
00013
00014 #ifndef GDCMLCSAHEADERDICT_H

```



```

00015 #define GDCMCSAHEADERDICT_H
00016
00017 #include "gdcmTypes.h"
00018 #include "gdcmTag.h"
00019 #include "gdcmCSAHeaderDictEntry.h"
00020
00021 #include <iostream>
00022 #include <iomanip>
00023 #include <set>
00024 #include <exception>
00025
00026 namespace gdcm
00027 {
00028
00029 class GDCM_EXPORT CSAHeaderDictException : public std::exception {};
00030
00031 class GDCM_EXPORT CSAHeaderDict
00032 {
00033 public:
00034     typedef std::set<CSAHeaderDictEntry> MapCSAHeaderDictEntry;
00035     typedef MapCSAHeaderDictEntry::iterator Iterator;
00036     typedef MapCSAHeaderDictEntry::const_iterator ConstIterator;
00037     //static CSAHeaderDictEntry GroupLengthCSAHeaderDictEntry; // = CSAHeaderDictEntry("Group
    Length",VR::UL,VM::VM1);
00041
00042     CSAHeaderDict():CSAHeaderDictInternal() {
00043         gdcm_assert( CSAHeaderDictInternal.empty() );
00044     }
00045     CSAHeaderDict &operator=(const CSAHeaderDict &_val) = delete;
00046     CSAHeaderDict(const CSAHeaderDict &_val) = delete;
00047
00048     friend std::ostream& operator<<(std::ostream& _os, const CSAHeaderDict &_val);
00049
00050     ConstIterator Begin() const { return CSAHeaderDictInternal.begin(); }
00051     ConstIterator End() const { return CSAHeaderDictInternal.end(); }
00052
00053     bool IsEmpty() const { return CSAHeaderDictInternal.empty(); }
00054     void AddCSAHeaderDictEntry(const CSAHeaderDictEntry &de)
00055     {
00056 #ifndef NDEBUG
00057         MapCSAHeaderDictEntry::size_type s = CSAHeaderDictInternal.size();
00058 #endif
00059         CSAHeaderDictInternal.insert( de );
00060 #ifndef NDEBUG
00061         gdcm_assert( s < CSAHeaderDictInternal.size() );
00062 #endif
00063     }
00064
00065     const CSAHeaderDictEntry &GetCSAHeaderDictEntry(const char *name) const
00066     {
00067         MapCSAHeaderDictEntry::const_iterator it = CSAHeaderDictInternal.find( name );
00068         if( it != CSAHeaderDictInternal.end() )
00069         {
00070             return *it;
00071         }
00072         throw CSAHeaderDictException();
00073     }
00074
00075 protected:
00076     friend class Dicts;
00077     void LoadDefault();
00078
00079 private:
00080
00081     MapCSAHeaderDictEntry CSAHeaderDictInternal;
00082 };
00083 //-----
00084 inline std::ostream& operator<<(std::ostream& os, const CSAHeaderDict &val)
00085 {
00086     CSAHeaderDict::MapCSAHeaderDictEntry::const_iterator it = val.CSAHeaderDictInternal.begin();
00087     for(;it != val.CSAHeaderDictInternal.end(); ++it)
00088     {
00089         const CSAHeaderDictEntry &de = *it;
00090         os << de << '\n';
00091     }
00092
00093     return os;
00094 }
00095
00096
00097

```

```

00098 } // end namespace gdcm
00099
00100 #endif //GDCMCSAHEADERDICT_H

```


11.91 gdcmCSAHeaderDictEntry.h File Reference

```


#include "gdcmVR.h"
#include "gdcmVM.h"
#include <string>
#include <iostream>
#include <iomanip>
#include <cstring>

```

Include dependency graph for gdcmCSAHeaderDictEntry.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::CSAHeaderDictEntry](#)
Class to represent an Entry in the [Dict](#).

Namespaces

- namespace [gdcm](#)

Functions

- `std::ostream & gdcm::operator<< (std::ostream &os, const CSAHeaderDictEntry &val)`

11.92 gdcmCSAHeaderDictEntry.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008

```

```


00009      This software is distributed WITHOUT ANY WARRANTY; without even
00010      the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011      PURPOSE. See the above copyright notice for more information.
00012
00013      =====*/
00014 #ifndef GDCMCSAHEADERDICTENTRY_H
00015 #define GDCMCSAHEADERDICTENTRY_H
00016
00017 #include "gdcmVR.h"
00018 #include "gdcmVM.h"
00019
00020 #include <string>
00021 #include <iostream>
00022 #include <iomanip>
00023
00024 #include <cstring>
00025
00026 namespace gdcm
00027 {
00028     class GDCM_EXPORT CSAHeaderDictEntry
00029     {
00030     public:
00031         CSAHeaderDictEntry(const char *name = "", VR const &vr = VR::INVALID, VM const &vm = VM::VM0, const char
00032         *desc = ""):Name(name),ValueRepresentation(vr),ValueMultiplicity(vm),Description(desc) {
00033         }
00034
00035         friend std::ostream& operator<<(std::ostream& _os, const CSAHeaderDictEntry &_val);
00036
00037         const VR &GetVR() const { return ValueRepresentation; }
00038         void SetVR(const VR &vr) { ValueRepresentation = vr; }
00039
00040         const VM &GetVM() const { return ValueMultiplicity; }
00041         void SetVM(VM const &vm) { ValueMultiplicity = vm; }
00042
00043         const char *GetName() const { return Name.c_str(); }
00044         void SetName(const char* name) { Name = name; }
00045
00046         const char *GetDescription() const { return Description.c_str(); }
00047         void SetDescription(const char* desc) { Description = desc; }
00048
00049         bool operator<(const CSAHeaderDictEntry &entry) const
00050         {
00051             return strcmp(GetName(),entry.GetName()) < 0;
00052         }
00053
00054     private:
00055         std::string Name;
00056         VR ValueRepresentation;
00057         VM ValueMultiplicity;
00058         std::string Description;
00059         std::string Type; // TODO
00060     };
00061
00062 //-----
00063 inline std::ostream& operator<<(std::ostream& os, const CSAHeaderDictEntry &val)
00064 {
00065     if( val.Name.empty() )
00066     {
00067         os << "[No name]";
00068     }
00069     else
00070     {
00071         os << val.Name;
00072     }
00073     os << "\t" << val.ValueRepresentation << "\t" << val.ValueMultiplicity;
00074     if( !val.Description.empty() )
00075     {
00076         os << "\t" << val.Description;
00077     }
00078     return os;
00079 }
00080
00081 // end namespace gdcm
00082
00083 #endif //GDCMCSAHEADERDICTENTRY_H

```


11.93 gdcmDict.h File Reference

```
#include "gdcmTypes.h"
#include "gdcmTag.h"
#include "gdcmPrivateTag.h"
#include "gdcmDictEntry.h"
#include "gdcmSystem.h"
#include <iostream>
#include <iomanip>
#include <map>
```

Include dependency graph for gdcDict.h:



This graph shows which files directly or indirectly include this file:



Classes

- class `gdcm::Dict`
Class to represent a map of `DictEntry`.
- class `gdcm::PrivateDict`
Private `Dict`.

Namespaces

- namespace [gdcm](#)

Functions

- `std::ostream & gdcm::operator<< (std::ostream &os, const Dict &val)`
- `std::ostream & gdcm::operator<< (std::ostream &os, const PrivateDict &val)`

11.94 gdcmDict.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013   =====*/
00014 #ifndef GDCMDICT_H
00015 #define GDCMDICT_H
00016
00017 #include "gdcmTypes.h"
00018 #include "gdcmTag.h"
00019 #include "gdcmPrivateTag.h"
00020 #include "gdcmDictEntry.h"
00021 #include "gdcmSystem.h"
00022
00023 #include <iostream>
00024 #include <iomanip>
00025 #include <map>
00026
00027 /*
00028  * FIXME / TODO
00029  * I need to seriously rewrite this mess. a class template should work for both a public
00030  * and a private dict
00031  */
00032
00033 namespace gdcm
00034 {
00035   // Data Element Tag
00044   class GDCM_EXPORT Dict
00045   {
00046   public:
00047     typedef std::map<Tag, DictEntry> MapDictEntry;
00048     typedef MapDictEntry::iterator Iterator;
00049     typedef MapDictEntry::const_iterator ConstIterator;
00050     //static DictEntry GroupLengthDictEntry; // = DictEntry("Group Length",VR::UL,VM::VM1);
00051
00052     Dict():DictInternal() {
00053       gdcm_assert( DictInternal.empty() );
00054     }
00055     Dict &operator=(const Dict &_val) = delete;
00056     Dict(const Dict &_val) = delete;
00057
00058
00059     friend std::ostream& operator<<(std::ostream& _os, const Dict &_val);
00060
00061     ConstIterator Begin() const { return DictInternal.begin(); }
00062     ConstIterator End() const { return DictInternal.end(); }
00063
00064     bool IsEmpty() const { return DictInternal.empty(); }
00065     void AddDictEntry(const Tag &tag, const DictEntry &de)

```

```

00066     {
00067 #ifndef NDEBUG
00068     MapDictEntry::size_type s = DictInternal.size();
00069 #endif
00070     DictInternal.insert(
00071         MapDictEntry::value_type(tag, de));
00072 #ifndef NDEBUG
00073     gdcm_assert( s < DictInternal.size() );
00074 #endif
00075     }
00076
00077     const DictEntry &GetDictEntry(const Tag &tag) const
00078     {
00079     MapDictEntry::const_iterator it =
00080         DictInternal.find(tag);
00081     if (it == DictInternal.end())
00082     {
00083 #ifdef UNKNOWNPUBLICTAG
00084         // test.acr
00085         if ( tag != Tag(0x28,0x15)
00086             && tag != Tag(0x28,0x16)
00087             && tag != Tag(0x28,0x199)
00088             // gdcmData/TherapysGDCM1.dcm
00089             && tag != Tag(0x20,0x1)
00090             // gdcmData/0019004_Baseline_IMG1.dcm
00091             && tag != Tag(0x8348,0x339)
00092             && tag != Tag(0xb5e8,0x338)
00093             // gdcmData/dicomdir_Acusson_WithPrivate_WithSR
00094             && tag != Tag(0x40,0xa125)
00095         )
00096         {
00097             gdcm_assert( 0 && "Impossible" );
00098         }
00099 #endif
00100         it = DictInternal.find( Tag(0xffff,0xffff) );
00101         return it->second;
00102     }
00103     gdcm_assert( DictInternal.count(tag) == 1 );
00104     return it->second;
00105     }
00106
00107     const char *GetKeywordFromTag(Tag const & tag) const
00108     {
00109     MapDictEntry::const_iterator it =
00110         DictInternal.find(tag);
00111     if (it == DictInternal.end())
00112     {
00113         return nullptr;
00114     }
00115     gdcm_assert( DictInternal.count(tag) == 1 );
00116     return it->second.GetKeyword();
00117     }
00118
00119     const DictEntry &GetDictEntryByKeyword(const char *keyword, Tag & tag) const
00120     {
00121     MapDictEntry::const_iterator it =
00122         DictInternal.begin();
00123     if( keyword )
00124     {
00125         for(; it != DictInternal.end(); ++it)
00126         {
00127             if( strcmp( keyword, it->second.GetKeyword() ) == 0 )
00128             {
00129                 // Found a match !
00130                 tag = it->first;
00131                 break;
00132             }
00133         }
00134     }
00135     else
00136     {
00137         it = DictInternal.end();
00138     }
00139     if (it == DictInternal.end())
00140     {
00141         tag = Tag(0xffff,0xffff);
00142         it = DictInternal.find( tag );
00143         return it->second;
00144     }
00145     gdcm_assert( DictInternal.count(tag) == 1 );
00146     return it->second;

```

```

00152     }
00153
00157     const DictEntry &GetDictEntryByName(const char *name, Tag & tag) const
00158     {
00159         MapDictEntry::const_iterator it =
00160             DictInternal.begin();
00161         if( name )
00162         {
00163             for(; it != DictInternal.end(); ++it)
00164             {
00165                 if( strcmp( name, it->second.GetName() ) == 0 )
00166                 {
00167                     // Found a match !
00168                     tag = it->first;
00169                     break;
00170                 }
00171             }
00172         }
00173         else
00174         {
00175             it = DictInternal.end();
00176         }
00177         if (it == DictInternal.end())
00178         {
00179             tag = Tag(0xffff,0xffff);
00180             it = DictInternal.find( tag );
00181             return it->second;
00182         }
00183         gdcmm_assert( DictInternal.count(tag) == 1 );
00184         return it->second;
00185     }
00186
00187 protected:
00188     friend class Dicts;
00189     void LoadDefault();
00190
00191 private:
00192     MapDictEntry DictInternal;
00193 };
00194 //-----
00195 inline std::ostream& operator<<(std::ostream& os, const Dict &val)
00196 {
00197     Dict::MapDictEntry::const_iterator it = val.DictInternal.begin();
00198     for(; it != val.DictInternal.end(); ++it)
00199     {
00200         const Tag &t = it->first;
00201         const DictEntry &de = it->second;
00202         os << t << " " << de << '\n';
00203     }
00204     return os;
00205 }
00206
00207 // TODO
00208 // For private dict, element < 0x10 should automatically defined:
00209 // Name = "Private Creator"
00210 // ValueRepresentation = LO
00211 // ValueMultiplicity = 1
00212 // Owner = ""
00213
00214 class GDCM_EXPORT PrivateDict
00215 {
00220     typedef std::map<PrivateTag, DictEntry> MapDictEntry;
00221     friend std::ostream& operator<<(std::ostream& os, const PrivateDict &val);
00222 public:
00223     PrivateDict() = default;
00224     ~PrivateDict() = default;
00225     void AddDictEntry(const PrivateTag &tag, const DictEntry &de)
00226     {
00227 #ifndef NDEBBUG
00228         MapDictEntry::size_type s = DictInternal.size();
00229 #endif
00230         DictInternal.insert(
00231             MapDictEntry::value_type(tag, de));
00232         // The following code should only be used when manually constructing a Private.xml file by hand
00233         // it will get rid of VR::UN duplicate (ie. if a VR != VR::Un can be found)
00234 #if defined(NDEBBUG) && 0
00235         if( s == DictInternal.size() )
00236         {
00237             MapDictEntry::iterator it =
00238                 DictInternal.find(tag);

```



```

00239     gdcm_assert( it != DictInternal.end() );
00240     DictEntry &duplicate = it->second;
00241     gdcm_assert( de.GetVR() == VR::UN || duplicate.GetVR() == VR::UN );
00242     gdcm_assert( de.GetVR() != duplicate.GetVR() );
00243     if( duplicate.GetVR() == VR::UN )
00244     {
00245         gdcm_assert( de.GetVR() != VR::UN );
00246         duplicate.SetVR( de.GetVR() );
00247         duplicate.SetVM( de.GetVM() );
00248         gdcm_assert( GetDictEntry(tag).GetVR() != VR::UN );
00249         gdcm_assert( GetDictEntry(tag).GetVR() == de.GetVR() );
00250         gdcm_assert( GetDictEntry(tag).GetVM() == de.GetVM() );
00251     }
00252     return;
00253 }
00254 #endif
00255 #ifndef NDEBUG
00256     gdcm_assert( s < DictInternal.size() /*&& std::cout << tag << ", " << de << std::endl*/ );
00257 #endif
00258 }
00261 bool RemoveDictEntry(const PrivateTag &tag)
00262 {
00263     MapDictEntry::size_type s =
00264         DictInternal.erase(tag);
00265     gdcm_assert( s == 1 || s == 0 );
00266     return s == 1;
00267 }
00268 bool FindDictEntry(const PrivateTag &tag) const
00269 {
00270     MapDictEntry::const_iterator it =
00271         DictInternal.find(tag);
00272     if (it == DictInternal.end())
00273     {
00274         return false;
00275     }
00276     return true;
00277 }
00278 const DictEntry &GetDictEntry(const PrivateTag &tag) const
00279 {
00280     // if 0x10 -> return Private Creator
00281     MapDictEntry::const_iterator it =
00282         DictInternal.find(tag);
00283     if (it == DictInternal.end())
00284     {
00285         //gdcm_assert( 0 && "Impossible" );
00286         it = DictInternal.find( PrivateTag(0xffff,0xffff,"GDCM Private Sentinel" ) );
00287         assert (it != DictInternal.end());
00288         return it->second;
00289     }
00290     gdcm_assert( DictInternal.count(tag) == 1 );
00291     return it->second;
00292 }
00293
00294
00295 void PrintXML() const
00296 {
00297     MapDictEntry::const_iterator it = DictInternal.begin();
00298     std::cout << "<dict edition=\"2008\">\n";
00299     for(;it != DictInternal.end(); ++it)
00300     {
00301         const PrivateTag &t = it->first;
00302         const DictEntry &de = it->second;
00303         std::cout << "  <entry group=\"" << std::hex << std::setw(4)
00304             << std::setfill('0') << t.GetGroup() << "\" " <<
00305             " element=\"" << std::setw(2) << std::setfill('0') << t.GetElement() << "\" " << " vr=\""
00306             << de.GetVR() << "\" vm=\"" << de.GetVM() << "\" owner=\""
00307             << t.GetOwner();
00308         const char *name = de.GetName();
00309         if( *name == 0 )
00310         {
00311             std::cout << "\"/>\n";
00312         }
00313         else
00314         {
00315             std::cout << "\" name=\"" << de.GetName() << "\"/>\n";
00316         }
00317     }
00318     std::cout << "</dict>\n";
00319 }
00320
00321 bool IsEmpty() const { return DictInternal.empty(); }

```

```

00322 protected:
00323     friend class Dicts;
00324     void LoadDefault();
00325
00326 private:
00327     PrivateDict &operator=(const PrivateDict &_val) = delete;
00328     PrivateDict(const PrivateDict &_val) = delete;
00329
00330     MapDictEntry DictInternal;
00331 };
00332 //-----
00333 inline std::ostream& operator<<(std::ostream& os, const PrivateDict &val)
00334 {
00335     PrivateDict::MapDictEntry::const_iterator it = val.DictInternal.begin();
00336     for(; it != val.DictInternal.end(); ++it)
00337     {
00338         const PrivateTag &t = it->first;
00339         const DictEntry &de = it->second;
00340         os << t << " " << de << '\n';
00341     }
00342
00343     return os;
00344 }
00345
00346 } // end namespace gdc
00347
00348 #endif //GDCMDICT_H

```


11.95 gdcDictConverter.h File Reference

```

#include "gdcTypes.h"
#include "gdcVR.h"
#include "gdcVM.h"
#include <string>

```

Include dependency graph for gdcDictConverter.h:



Classes

- class [gdc::DictConverter](#)

Class to convert a .dic file into something else:

Namespaces

- namespace `gdcm`

11.96 gdcmDictConverter.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014
00015 #ifndef GDCMDICTCONVERTER_H
00016 #define GDCMDICTCONVERTER_H
00017
00018 #include "gdcmTypes.h"
00019 #include "gdcmVR.h"
00020 #include "gdcmVM.h"
00021
00022 #include <string>
00023
00024 namespace gdcm
00025 {
00026
00027   class DictConverterInternal;
00036   class GDCM_EXPORT DictConverter
00037   {
00038   public:
00039     DictConverter();
00040     ~DictConverter();
00041     void SetInputFileName(const char* filename);
00042     const std::string &GetInputFilename() const;
00043     void SetOutputFileName(const char* filename);
00044     const std::string &GetOutputFilename() const;
00045
00046     int GetOutputType() const {
00047         return OutputType;
00048     }
00049     void SetOutputType(int type) {
00050         OutputType = type;
00051     }
00052     const std::string &GetDictName() const;
00053     void SetDictName(const char *name);
00054
00055     void Convert();
00056
00057     // Leaving them public for now. Not really user oriented but may be
00058     // useful
00059     static bool ReadVR(const char *raw, VR::VRType &type);
00060     static bool ReadVM(const char *raw, VM::VMType &type);
00061     static bool Readuint16(const char *raw, uint16_t &ov);
00062
00063     enum OutputTypes {
00064         DICT_DEFAULT = 0,
00065         DICT_DEBUG,
00066         DICT_XML
00067     };
00068
00069   protected:
00070     void WriteHeader();
00071     void WriteFooter();
00072     bool ConvertToXML(const char *raw, std::string &cxx);
00073     bool ConvertToCXX(const char *raw, std::string &cxx);
00074     void AddGroupLength();

```

```

00075
00076 private:
00077     DictConverterInternal *Internal;
00078
00079     int OutputType;
00080 };
00081
00082 } // end namespace gdcM
00083
00084 #endif //GDCMDICTCONVERTER_H

```


11.97 gdcMDictEntry.h File Reference

```


#include "gdcMVR.h"
#include "gdcMVM.h"
#include <string>
#include <iostream>
#include <iomanip>

```

Include dependency graph for gdcMDictEntry.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::DictEntry](#)
Class to represent an Entry in the Dict.

Namespaces

- namespace [gdcm](#)

Functions

- `std::ostream & gdcm::operator<< (std::ostream &os, const DictEntry &val)`

11.98 gdcmDictEntry.h

[Go to the documentation of this file.](#)

```

00001  /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013  =====*/
00014  #ifndef GDCMDICTENTRY_H
00015  #define GDCMDICTENTRY_H
00016
00017  #include "gdcmVR.h"
00018  #include "gdcmVM.h"
00019
00020  #include <string>
00021  #include <iostream>
00022  #include <iomanip>
00023
00024  namespace gdcm
00025  {
00026  class GDCM_EXPORT DictEntry
00027  {
00028  public:
00029      DictEntry(const char *name = "", const char *keyword = "", VR const &vr = VR::INVALID, VM const &vm =
VM::VM0, bool ret = false):
00030          Name(name),
00031          Keyword(keyword),
00032          ValueRepresentation(vr),
00033          ValueMultiplicity(vm),
00034          Retired(ret),
00035          GroupXX(false),
00036          ElementXX(false)
00037      {
00038      }
00039
00040      friend std::ostream& operator<<(std::ostream& _os, const DictEntry &_val);
00041
00042      const VR &GetVR() const { return ValueRepresentation; }
00043      void SetVR(const VR &vr) { ValueRepresentation = vr; }
00044      // bool IsValid() const { return ValueRepresentation != VR::VR_END; }
00045      // !Name.empty() /*&& ValueRepresentation && ValueMultiplicity*/; }
00046
00047      const VM &GetVM() const { return ValueMultiplicity; }
00048      void SetVM(VM const &vm) { ValueMultiplicity = vm; }

```

```


00061
00063     const char *GetName() const { return Name.c_str(); }
00064     void SetName(const char* name) { Name = name; }
00065
00067     const char *GetKeyword() const { return Keyword.c_str(); }
00068     void SetKeyword(const char* keyword) { Keyword = keyword; }
00069
00071     bool GetRetired() const { return Retired; }
00072     void SetRetired(bool retired) { Retired = retired; }
00073
00074     // <entry group="50xx" element="0005" vr="US" vm="1" retired="true" version="3">
00076     void SetGroupXX(bool v) { GroupXX = v; }
00077
00078     // <entry group="0020" element="3lxx" vr="CS" vm="1-n" retired="true" version="2">
00080     void SetElementXX(bool v) { ElementXX = v; }
00081
00084     bool IsUnique() const { return ElementXX == false && GroupXX == false; }
00085
00086 private:
00087     //
00088     friend class Dict;
00089     static bool CheckKeywordAgainstName(const char *name, const char *keyword);
00090
00091 private:
00092     std::string Name;
00093     std::string Keyword;
00094     VR ValueRepresentation;
00095     VM ValueMultiplicity;
00096     bool Retired : 1;
00097     bool GroupXX : 1;
00098     bool ElementXX : 1;
00099 };
00100
00101 #if 0
00102 class GDCM_EXPORT PrivateDictEntry : public DictEntry
00103 {
00104 public:
00105     PrivateDictEntry(const char *name = "", VR::VRType const &vr = VR::INVALID, VM::VMType const &vm =
VM::VM0, bool ret = false, const char *owner = ""):DictEntry(name,vr,vm,ret),Owner(owner) {}
00106     PrivateDictEntry(const char *name, const char *vr, const char *vm):DictEntry(name,vr,vm) {}
00107
00108     const char *GetOwner() const { return Owner.c_str(); }
00109     void SetOwner(const char *owner) { Owner = owner; }
00110
00111 private:
00112     // SIEMENS MED, GEMS_PETD_01 ...
00113     std::string Owner;
00114 };
00115 #endif
00116
00117 //-----
00118 inline std::ostream& operator<<(std::ostream& os, const DictEntry &val)
00119 {
00120     if( val.Name.empty() )
00121     {
00122         os << "[No name]";
00123     }
00124     else
00125     {
00126         os << val.Name;
00127     }
00128     if( val.Keyword.empty() )
00129     {
00130         os << "[No keyword]";
00131     }
00132     else
00133     {
00134         os << val.Keyword;
00135     }
00136     os << "\t" << val.ValueRepresentation << "\t" << val.ValueMultiplicity;
00137     if( val.Retired )
00138     {
00139         os << "\t(RET)";
00140     }
00141     return os;
00142 }
00143
00144 } // end namespace gdcms
00145
00146 #endif //GDCMDICTENTRY_H

```


11.99 gdcmDicts.h File Reference

```
#include "gdcmDict.h"
#include "gdcmCSAHeaderDict.h"
#include <string>
```

Include dependency graph for gdcmDicts.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::Dicts](#)
Class to manipulate the sum of knowledge (all the dict user load)

Namespaces

- namespace [gdcm](#)

Functions

- std::ostream & [gdcm::operator<<](#) (std::ostream &os, const [Dicts](#) &d)

11.100 gdcmDicts.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMDICTS_H
00015 #define GDCMDICTS_H
00016
00017 #include "gdcmDict.h"
00018 #include "gdcmCSAHeaderDict.h"
00019
00020 #include <string>
00021
00022 namespace gdcm
00023 {
00024     class GDCM_EXPORT Dicts
00025     {
00026     public:
00027         Dicts();
00028         ~Dicts();
00029         Dicts &operator=(const Dicts &_val) = delete;
00030         Dicts(const Dicts &_val) = delete;
00031
00032         // DataSet::GetPrivateCreator
00033         const DictEntry &GetDictEntry(const Tag& tag, const char *owner = nullptr) const;
00034
00035         const DictEntry &GetDictEntry(const PrivateTag& tag) const;
00036
00037         //enum PublicTypes {
00038         //    DICOMV3_DICT,
00039         //    ACRNEMA_DICT,
00040         //    NIH_DICT
00041         //};
00042         const Dict &GetPublicDict() const;
00043
00044         const PrivateDict &GetPrivateDict() const;
00045         PrivateDict &GetPrivateDict();
00046
00047         const CSAHeaderDict &GetCSAHeaderDict() const;
00048
00049         bool IsEmpty() const { return GetPublicDict().IsEmpty(); }
00050
00051 protected:
00052         typedef enum {
00053             PHILIPS,
00054             GEMS,
00055             SIEMENS
00056         } ConstructorType;
00057         static const char *GetConstructorString(ConstructorType type);
00058
00059         friend class Global;
00060         void LoadDefaults();
00061
00062 private:
00063         // Public dict:
00064         Dict PublicDict;
00065
00066         // Private Dicts:
00067         PrivateDict ShadowDict;
00068
00069         CSAHeaderDict CSADict;
00070     };
00071
00072 //-----
00073 inline std::ostream& operator<<(std::ostream &os, const Dicts &d)
00074 {

```



```


00084     (void)d;
00085     return os;
00086 }
00087
00088
00089 } // end namespace gdcm
00090
00091 #endif //GDCMDICTS_H

```

11.101 gdcmGlobal.h File Reference

```
#include "gdcmTypes.h"
```

Include dependency graph for gdcmGlobal.h:



Classes

- class `gdcm::Global`
Global.

Namespaces

- namespace `gdcm`

Functions

- `std::ostream & gdcm::operator<< (std::ostream &os, const Global &g)`

Variables

- static `Global gdcm::GlobalInstance`

11.102 gdcmGlobal.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013   =====*/
00014 // Implementation detail was shamelessly borrowed from the VTK excellent
00015 // implementation of debug leak manager singleton:
00016 /*=====
00017
00018   Program:   Visualization Toolkit
00019   Module:    $RCSfile: vtkDebugLeaks.cxx,v $
00020
00021   Copyright (c) Ken Martin, Will Schroeder, Bill Lorensen
00022   All rights reserved.
00023   See Copyright.txt or http://www.kitware.com/Copyright.htm for details.
00024
00025   This software is distributed WITHOUT ANY WARRANTY; without even
00026   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00027   PURPOSE. See the above copyright notice for more information.
00028
00029   =====*/
00030 #ifndef GDCMGLOBAL_H
00031 #define GDCMGLOBAL_H
00032
00033 #include "gdcmTypes.h"
00034
00035 namespace gdcm
00036 {
00037   class GlobalInternal;
00038   class Dicts;
00039   class Defs;
00040   class GDCM_EXPORT Global // why expose the symbol I think I only need to expose the instance...
00041   {
00042   friend std::ostream& operator<<(std::ostream &_os, const Global &g);
00043   public:
00044     Global();
00045     ~Global();
00046     Global &operator=(const Global &_val) = delete;
00047     Global(const Global &_val) = delete;
00048
00049     Dicts const &GetDicts() const;
00050     Dicts &GetDicts();
00051
00052     Defs const &GetDefs() const;
00053
00054     static Global& GetInstance();
00055
00056     bool LoadResourcesFiles();
00057
00058     bool Append(const char *path);
00059
00060     bool Prepend(const char *path);
00061
00062   protected:
00063     const char *Locate(const char *resfile) const;
00064
00065   private:
00066     // PIMPL:
00067     // but we could have also directly exposed a Dicts *Internals;
00068     static GlobalInternal *Internals;
00069   };
00070 //-----
00071 inline std::ostream& operator<<(std::ostream &os, const Global &g)
00072 {
00073   (void)g;
00074   return os;
00075 }

```

```

00098
00099 // This instance will show up in any translation unit that uses
00100 // Global or that has a singleton. It will make sure
00101 // Global is initialized before it is used and is the last
00102 // static object destroyed.
00103 static Global GlobalInstance;
00104
00105 } // end namespace gdcm
00106
00107 #endif //GDCMGLOBAL_H

```


11.103 gdcmGroupDict.h File Reference

```

#include "gdcmTypes.h"
#include <assert.h>
#include <vector>
#include <string>
#include <iostream>
#include <iomanip>

```

Include dependency graph for gdcmGroupDict.h:



Classes

- class [gdcm::GroupDict](#)
Class to represent the mapping from group number to its abbreviation and name.

Namespaces

- namespace [gdcm](#)

Functions

- `std::ostream & gdcm::operator<< (std::ostream &_os, const GroupDict &_val)`

11.104 gdcmGroupDict.h

[Go to the documentation of this file.](#)

```


00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014
00015 #ifndef GDCMGROUPDICT_H
00016 #define GDCMGROUPDICT_H
00017
00018 #include "gdcmTypes.h"
00019
00020 #include <assert.h>
00021 #include <vector>
00022 #include <string>
00023 #include <iostream>
00024 #include <iomanip>
00025
00026 namespace gdcm
00027 {
00033 class GDCM_EXPORT GroupDict
00034 {
00035 public:
00036     typedef std::vector<std::string> GroupStringVector;
00037     GroupDict() { FillDefaultGroupName(); }
00038     ~GroupDict() = default;
00039
00040     friend std::ostream& operator<<(std::ostream& _os, const GroupDict &_val);
00041
00042     size_t Size() const
00043     {
00044         gdcm_assert( Names.size() == Abbreviations.size() );
00045         return Names.size(); }
00046
00047     std::string const &GetAbbreviation(uint16_t num) const;
00048
00049     std::string const &GetName(uint16_t num) const;
00050
00051 protected:
00052     void Add(std::string const &abbreviation, std::string const &name);
00053     void Insert(uint16_t num, std::string const &abbreviation, std::string const &name);
00054
00055 private:
00056     // Generated implementation, see gdcmDefaultGroupNames
00057     void FillDefaultGroupName();
00058
00059     GroupDict &operator=(const GroupDict &_val); // purposely not implemented
00060     GroupDict(const GroupDict &_val); // purposely not implemented
00061
00062     GroupStringVector Abbreviations;
00063     GroupStringVector Names;
00064 };
00065 //-----
00066 inline std::ostream& operator<<(std::ostream& _os, const GroupDict &_val)
00067 {
00068     size_t size = _val.Size();
00069     for(size_t i=0; i<size; ++i)
00070     {
00071         _os << std::hex << std::setw(4) << std::setfill( '0' ) << i << ", "
00072         << _val.GetAbbreviation((uint16_t)i) << ", " << _val.GetName((uint16_t)i) << "\n";
00073     }
00074     return _os;
00075 }
00076
00077 } // end namespace gdcm
00078
00079 #endif //GDCMGROUPDICT_H

```

11.105 gdcmSOPClassUIDToIOD.h File Reference

```
#include "gdcmUIDs.h"
```

Include dependency graph for gdcmSOPClassUIDToIOD.h:



Classes

- class [gdcm::SOPClassUIDToIOD](#)
Class convert a class SOP Class UID into *IOD*.

Namespaces

- namespace [gdcm](#)

11.106 gdcmSOPClassUIDToIOD.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013   =====*/
00014
00015 #ifndef GDCMSOPCLASSUIDTOIOD_H
00016 #define GDCMSOPCLASSUIDTOIOD_H
00017

```

```


00018 #include "gdcmUIDs.h"
00019
00020 namespace gdcm
00021 {
00022
00028 class GDCM_EXPORT SOPClassUIDToIOD
00029 {
00030 public:
00033     static const char *GetIOD(UIDs const & uid);
00034
00036     static unsigned int GetNumberOfSOPClassToIOD();
00037
00038     typedef const char* const (SOPClassUIDToIODType)[2];
00039     static SOPClassUIDToIODType* GetSOPClassUIDToIODs();
00040
00041     static SOPClassUIDToIODType& GetSOPClassUIDToIOD(unsigned int i);
00042
00043     static const char *GetSOPClassUIDFromIOD(const char *iod);
00044     static const char *GetIODFromSOPClassUID(const char *sopclassuid);
00045 };
00046
00047 } // end namespace gdcm
00048
00049 #endif //GDCMSOPCLASSUIDTOIOD_H

```

11.107 gdcmUIDs.h File Reference

#include "gdcmTypes.h"

Include dependency graph for gdcmUIDs.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::UIDs](#)
all known uids

Namespaces

- namespace `gdcml`

Functions

- `std::ostream & gdcml::operator<< (std::ostream &_os, const UIDs &uid)`

11.108 gdcmlUIDs.h

[Go to the documentation of this file.](#)

```

00001
00002 // GENERATED FILE DO NOT EDIT
00003 // $ xsltproc UIDToC++.xsl Part6.xml > gdcmlUIDs.h
00004
00005 /*=====
00006
00007 Program: GDCM (Grassroots DICOM). A DICOM library
00008
00009 Copyright (c) 2006-2011 Mathieu Malaterre
00010 All rights reserved.
00011 See Copyright.txt or http://gdcml.sourceforge.net/Copyright.html for details.
00012
00013 This software is distributed WITHOUT ANY WARRANTY; without even
00014 the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00015 PURPOSE. See the above copyright notice for more information.
00016
00017 =====*/
00018
00019 #ifndef GDCMLUIDS_H
00020 #define GDCMLUIDS_H
00021
00022 #include "gdcmlTypes.h"
00023
00024 namespace gdcml
00025 {
00026
00027 class GDCM_EXPORT UIDs
00028 {
00029 public:
00030     typedef enum {
00031         uid_1_2_840_10008_1_1 = 1, // Verification SOP Class
00032         uid_1_2_840_10008_1_2 = 2, // Implicit VR Little Endian: Default Transfer Syntax for DICOM
00033         uid_1_2_840_10008_1_2_1 = 3, // Explicit VR Little Endian
00034         uid_1_2_840_10008_1_2_1_99 = 4, // Deflated Explicit VR Little Endian
00035         uid_1_2_840_10008_1_2_2 = 5, // Explicit VR Big Endian
00036         uid_1_2_840_10008_1_2_4_50 = 6, // JPEG Baseline (Process 1): Default Transfer Syntax for Lossy JPEG 8 Bit
00037         uid_1_2_840_10008_1_2_4_51 = 7, // JPEG Extended (Process 2 & 4): Default Transfer Syntax for Lossy JPEG
00038         uid_1_2_840_10008_1_2_4_52 = 8, // JPEG Extended (Process 3 & 5)
00039         uid_1_2_840_10008_1_2_4_53 = 9, // JPEG Spectral Selection, Non-Hierarchical (Process 6 & 8)
00040         uid_1_2_840_10008_1_2_4_54 = 10, // JPEG Spectral Selection, Non-Hierarchical (Process 7 & 9)
00041         uid_1_2_840_10008_1_2_4_55 = 11, // JPEG Full Progression, Non-Hierarchical (Process 10 & 12)
00042         uid_1_2_840_10008_1_2_4_56 = 12, // JPEG Full Progression, Non-Hierarchical (Process 11 & 13)
00043         uid_1_2_840_10008_1_2_4_57 = 13, // JPEG Lossless, Non-Hierarchical (Process 14)
00044         uid_1_2_840_10008_1_2_4_58 = 14, // JPEG Lossless, Non-Hierarchical (Process 15)
00045         uid_1_2_840_10008_1_2_4_59 = 15, // JPEG Extended, Hierarchical (Process 16 & 18)
00046         uid_1_2_840_10008_1_2_4_60 = 16, // JPEG Extended, Hierarchical (Process 17 & 19)
00047         uid_1_2_840_10008_1_2_4_61 = 17, // JPEG Spectral Selection, Hierarchical (Process 20 & 22)
00048         uid_1_2_840_10008_1_2_4_62 = 18, // JPEG Spectral Selection, Hierarchical (Process 21 & 23)
00049         uid_1_2_840_10008_1_2_4_63 = 19, // JPEG Full Progression, Hierarchical (Process 24 & 26)
00050         uid_1_2_840_10008_1_2_4_64 = 20, // JPEG Full Progression, Hierarchical (Process 25 & 27)
00051         uid_1_2_840_10008_1_2_4_65 = 21, // JPEG Lossless, Hierarchical (Process 28)
00052         uid_1_2_840_10008_1_2_4_66 = 22, // JPEG Lossless, Hierarchical (Process 29)
00053         uid_1_2_840_10008_1_2_4_70 = 23, // JPEG Lossless, Non-Hierarchical, First-Order Prediction (Process 14
00054         [Selection Value 1]): Default Transfer Syntax for Lossless JPEG Image Compression
00055         uid_1_2_840_10008_1_2_4_80 = 24, // JPEG-LS Lossless Image Compression
00056         uid_1_2_840_10008_1_2_4_81 = 25, // JPEG-LS Lossy (Near-Lossless) Image Compression
00057         uid_1_2_840_10008_1_2_4_90 = 26, // JPEG 2000 Image Compression (Lossless Only)
00058
00059     };

```

```
00060 uid_1_2_840_10008_1_2_4_91 = 27, // JPEG 2000 Image Compression
00061 uid_1_2_840_10008_1_2_4_92 = 28, // JPEG 2000 Part 2 Multi-component Image Compression (Lossless Only)
00062 uid_1_2_840_10008_1_2_4_93 = 29, // JPEG 2000 Part 2 Multi-component Image Compression
00063 uid_1_2_840_10008_1_2_4_94 = 30, // JPIP Referenced
00064 uid_1_2_840_10008_1_2_4_95 = 31, // JPIP Referenced Deflate
00065 uid_1_2_840_10008_1_2_4_100 = 32, // MPEG2 Main Profile @ Main Level
00066 uid_1_2_840_10008_1_2_5 = 33, // RLE Lossless
00067 uid_1_2_840_10008_1_2_6_1 = 34, // RFC 2557 MIME encapsulation
00068 uid_1_2_840_10008_1_2_6_2 = 35, // XML Encoding
00069 uid_1_2_840_10008_1_3_10 = 36, // Media Storage Directory Storage
00070 uid_1_2_840_10008_1_4_1_1 = 37, // Talairach Brain Atlas Frame of Reference
00071 uid_1_2_840_10008_1_4_1_2 = 38, // SPM2 T1 Frame of Reference
00072 uid_1_2_840_10008_1_4_1_3 = 39, // SPM2 T2 Frame of Reference
00073 uid_1_2_840_10008_1_4_1_4 = 40, // SPM2 PD Frame of Reference
00074 uid_1_2_840_10008_1_4_1_5 = 41, // SPM2 EPI Frame of Reference
00075 uid_1_2_840_10008_1_4_1_6 = 42, // SPM2 FIL T1 Frame of Reference
00076 uid_1_2_840_10008_1_4_1_7 = 43, // SPM2 PET Frame of Reference
00077 uid_1_2_840_10008_1_4_1_8 = 44, // SPM2 TRANSM Frame of Reference
00078 uid_1_2_840_10008_1_4_1_9 = 45, // SPM2 SPECT Frame of Reference
00079 uid_1_2_840_10008_1_4_1_10 = 46, // SPM2 GRAY Frame of Reference
00080 uid_1_2_840_10008_1_4_1_11 = 47, // SPM2 WHITE Frame of Reference
00081 uid_1_2_840_10008_1_4_1_12 = 48, // SPM2 CSF Frame of Reference
00082 uid_1_2_840_10008_1_4_1_13 = 49, // SPM2 BRAINMASK Frame of Reference
00083 uid_1_2_840_10008_1_4_1_14 = 50, // SPM2 AVG305T1 Frame of Reference
00084 uid_1_2_840_10008_1_4_1_15 = 51, // SPM2 AVG152T1 Frame of Reference
00085 uid_1_2_840_10008_1_4_1_16 = 52, // SPM2 AVG152T2 Frame of Reference
00086 uid_1_2_840_10008_1_4_1_17 = 53, // SPM2 AVG152PD Frame of Reference
00087 uid_1_2_840_10008_1_4_1_18 = 54, // SPM2 SINGLESUBJT1 Frame of Reference
00088 uid_1_2_840_10008_1_4_2_1 = 55, // ICBM 452 T1 Frame of Reference
00089 uid_1_2_840_10008_1_4_2_2 = 56, // ICBM Single Subject MRI Frame of Reference
00090 uid_1_2_840_10008_1_9 = 57, // Basic Study Content Notification SOP Class
00091 uid_1_2_840_10008_1_20_1 = 58, // Storage Commitment Push Model SOP Class
00092 uid_1_2_840_10008_1_20_1_1 = 59, // Storage Commitment Push Model SOP Instance
00093 uid_1_2_840_10008_1_20_2 = 60, // Storage Commitment Pull Model SOP Class
00094 uid_1_2_840_10008_1_20_2_1 = 61, // Storage Commitment Pull Model SOP Instance
00095 uid_1_2_840_10008_1_40 = 62, // Procedural Event Logging SOP Class
00096 uid_1_2_840_10008_1_40_1 = 63, // Procedural Event Logging SOP Instance
00097 uid_1_2_840_10008_1_42 = 64, // Substance Administration Logging SOP Class
00098 uid_1_2_840_10008_1_42_1 = 65, // Substance Administration Logging SOP Instance
00099 uid_1_2_840_10008_2_6_1 = 66, // DICOM UID Registry
00100 uid_1_2_840_10008_2_16_4 = 67, // DICOM Controlled Terminology
00101 uid_1_2_840_10008_3_1_1_1 = 68, // DICOM Application Context Name
00102 uid_1_2_840_10008_3_1_2_1_1 = 69, // Detached Patient Management SOP Class
00103 uid_1_2_840_10008_3_1_2_1_4 = 70, // Detached Patient Management Meta SOP Class
00104 uid_1_2_840_10008_3_1_2_2_1 = 71, // Detached Visit Management SOP Class
00105 uid_1_2_840_10008_3_1_2_3_1 = 72, // Detached Study Management SOP Class
00106 uid_1_2_840_10008_3_1_2_3_2 = 73, // Study Component Management SOP Class
00107 uid_1_2_840_10008_3_1_2_3_3 = 74, // Modality Performed Procedure Step SOP Class
00108 uid_1_2_840_10008_3_1_2_3_4 = 75, // Modality Performed Procedure Step Retrieve SOP Class
00109 uid_1_2_840_10008_3_1_2_3_5 = 76, // Modality Performed Procedure Step Notification SOP Class
00110 uid_1_2_840_10008_3_1_2_5_1 = 77, // Detached Results Management SOP Class
00111 uid_1_2_840_10008_3_1_2_5_4 = 78, // Detached Results Management Meta SOP Class
00112 uid_1_2_840_10008_3_1_2_5_5 = 79, // Detached Study Management Meta SOP Class
00113 uid_1_2_840_10008_3_1_2_6_1 = 80, // Detached Interpretation Management SOP Class
00114 uid_1_2_840_10008_4_2 = 81, // Storage Service Class
00115 uid_1_2_840_10008_5_1_1_1 = 82, // Basic Film Session SOP Class
00116 uid_1_2_840_10008_5_1_1_2 = 83, // Basic Film Box SOP Class
00117 uid_1_2_840_10008_5_1_1_4 = 84, // Basic Grayscale Image Box SOP Class
00118 uid_1_2_840_10008_5_1_1_4_1 = 85, // Basic Color Image Box SOP Class
00119 uid_1_2_840_10008_5_1_1_4_2 = 86, // Referenced Image Box SOP Class
00120 uid_1_2_840_10008_5_1_1_9 = 87, // Basic Grayscale Print Management Meta SOP Class
00121 uid_1_2_840_10008_5_1_1_9_1 = 88, // Referenced Grayscale Print Management Meta SOP Class
00122 uid_1_2_840_10008_5_1_1_14 = 89, // Print Job SOP Class
00123 uid_1_2_840_10008_5_1_1_15 = 90, // Basic Annotation Box SOP Class
00124 uid_1_2_840_10008_5_1_1_16 = 91, // Printer SOP Class
00125 uid_1_2_840_10008_5_1_1_16_376 = 92, // Printer Configuration Retrieval SOP Class
00126 uid_1_2_840_10008_5_1_1_17 = 93, // Printer SOP Instance
00127 uid_1_2_840_10008_5_1_1_17_376 = 94, // Printer Configuration Retrieval SOP Instance
00128 uid_1_2_840_10008_5_1_1_18 = 95, // Basic Color Print Management Meta SOP Class
00129 uid_1_2_840_10008_5_1_1_18_1 = 96, // Referenced Color Print Management Meta SOP Class
00130 uid_1_2_840_10008_5_1_1_22 = 97, // VOI LUT Box SOP Class
00131 uid_1_2_840_10008_5_1_1_23 = 98, // Presentation LUT SOP Class
00132 uid_1_2_840_10008_5_1_1_24 = 99, // Image Overlay Box SOP Class
00133 uid_1_2_840_10008_5_1_1_24_1 = 100, // Basic Print Image Overlay Box SOP Class
00134 uid_1_2_840_10008_5_1_1_25 = 101, // Print Queue SOP Instance
00135 uid_1_2_840_10008_5_1_1_26 = 102, // Print Queue Management SOP Class
00136 uid_1_2_840_10008_5_1_1_27 = 103, // Stored Print Storage SOP Class
00137 uid_1_2_840_10008_5_1_1_29 = 104, // Hardcopy Grayscale Image Storage SOP Class
00138 uid_1_2_840_10008_5_1_1_30 = 105, // Hardcopy Color Image Storage SOP Class
00139 uid_1_2_840_10008_5_1_1_31 = 106, // Pull Print Request SOP Class
00140 uid_1_2_840_10008_5_1_1_32 = 107, // Pull Stored Print Management Meta SOP Class
```



```
00141 uid_1_2_840_10008_5_1_1_33 = 108, // Media Creation Management SOP Class UID
00142 uid_1_2_840_10008_5_1_4_1_1_1 = 109, // Computed Radiography Image Storage
00143 uid_1_2_840_10008_5_1_4_1_1_1_1 = 110, // Digital X-Ray Image Storage - For Presentation
00144 uid_1_2_840_10008_5_1_4_1_1_1_1_1 = 111, // Digital X-Ray Image Storage - For Processing
00145 uid_1_2_840_10008_5_1_4_1_1_1_2 = 112, // Digital Mammography X-Ray Image Storage - For Presentation
00146 uid_1_2_840_10008_5_1_4_1_1_1_2_1 = 113, // Digital Mammography X-Ray Image Storage - For Processing
00147 uid_1_2_840_10008_5_1_4_1_1_1_3 = 114, // Digital Intra-oral X-Ray Image Storage - For Presentation
00148 uid_1_2_840_10008_5_1_4_1_1_1_3_1 = 115, // Digital Intra-oral X-Ray Image Storage - For Processing
00149 uid_1_2_840_10008_5_1_4_1_1_2 = 116, // CT Image Storage
00150 uid_1_2_840_10008_5_1_4_1_1_2_1 = 117, // Enhanced CT Image Storage
00151 uid_1_2_840_10008_5_1_4_1_1_3 = 118, // Ultrasound Multi-frame Image Storage
00152 uid_1_2_840_10008_5_1_4_1_1_3_1 = 119, // Ultrasound Multi-frame Image Storage
00153 uid_1_2_840_10008_5_1_4_1_1_4 = 120, // MR Image Storage
00154 uid_1_2_840_10008_5_1_4_1_1_4_1 = 121, // Enhanced MR Image Storage
00155 uid_1_2_840_10008_5_1_4_1_1_4_2 = 122, // MR Spectroscopy Storage
00156 uid_1_2_840_10008_5_1_4_1_1_5 = 123, // Nuclear Medicine Image Storage
00157 uid_1_2_840_10008_5_1_4_1_1_6 = 124, // Ultrasound Image Storage
00158 uid_1_2_840_10008_5_1_4_1_1_6_1 = 125, // Ultrasound Image Storage
00159 uid_1_2_840_10008_5_1_4_1_1_7 = 126, // Secondary Capture Image Storage
00160 uid_1_2_840_10008_5_1_4_1_1_7_1 = 127, // Multi-frame Single Bit Secondary Capture Image Storage
00161 uid_1_2_840_10008_5_1_4_1_1_7_2 = 128, // Multi-frame Grayscale Byte Secondary Capture Image Storage
00162 uid_1_2_840_10008_5_1_4_1_1_7_3 = 129, // Multi-frame Grayscale Word Secondary Capture Image Storage
00163 uid_1_2_840_10008_5_1_4_1_1_7_4 = 130, // Multi-frame True Color Secondary Capture Image Storage
00164 uid_1_2_840_10008_5_1_4_1_1_8 = 131, // Standalone Overlay Storage
00165 uid_1_2_840_10008_5_1_4_1_1_9 = 132, // Standalone Curve Storage
00166 uid_1_2_840_10008_5_1_4_1_1_9_1 = 133, // Waveform Storage - Trial
00167 uid_1_2_840_10008_5_1_4_1_1_9_1_1 = 134, // 12-lead ECG Waveform Storage
00168 uid_1_2_840_10008_5_1_4_1_1_9_1_2 = 135, // General ECG Waveform Storage
00169 uid_1_2_840_10008_5_1_4_1_1_9_1_3 = 136, // Ambulatory ECG Waveform Storage
00170 uid_1_2_840_10008_5_1_4_1_1_9_2_1 = 137, // Hemodynamic Waveform Storage
00171 uid_1_2_840_10008_5_1_4_1_1_9_3_1 = 138, // Cardiac Electrophysiology Waveform Storage
00172 uid_1_2_840_10008_5_1_4_1_1_9_4_1 = 139, // Basic Voice Audio Waveform Storage
00173 uid_1_2_840_10008_5_1_4_1_1_10 = 140, // Standalone Modality LUT Storage
00174 uid_1_2_840_10008_5_1_4_1_1_11 = 141, // Standalone VOI LUT Storage
00175 uid_1_2_840_10008_5_1_4_1_1_11_1 = 142, // Grayscale Softcopy Presentation State Storage SOP Class
00176 uid_1_2_840_10008_5_1_4_1_1_11_2 = 143, // Color Softcopy Presentation State Storage SOP Class
00177 uid_1_2_840_10008_5_1_4_1_1_11_3 = 144, // Pseudo-Color Softcopy Presentation State Storage SOP Class
00178 uid_1_2_840_10008_5_1_4_1_1_11_4 = 145, // Blending Softcopy Presentation State Storage SOP Class
00179 uid_1_2_840_10008_5_1_4_1_1_12_1 = 146, // X-Ray Angiographic Image Storage
00180 uid_1_2_840_10008_5_1_4_1_1_12_1_1 = 147, // Enhanced XA Image Storage
00181 uid_1_2_840_10008_5_1_4_1_1_12_2 = 148, // X-Ray Radiofluoroscopic Image Storage
00182 uid_1_2_840_10008_5_1_4_1_1_12_2_1 = 149, // Enhanced XRF Image Storage
00183 uid_1_2_840_10008_5_1_4_1_1_13_1_1 = 150, // X-Ray 3D Angiographic Image Storage
00184 uid_1_2_840_10008_5_1_4_1_1_13_1_2 = 151, // X-Ray 3D Craniofacial Image Storage
00185 uid_1_2_840_10008_5_1_4_1_1_12_3 = 152, // X-Ray Angiographic Bi-Plane Image Storage
00186 uid_1_2_840_10008_5_1_4_1_1_20 = 153, // Nuclear Medicine Image Storage
00187 uid_1_2_840_10008_5_1_4_1_1_66 = 154, // Raw Data Storage
00188 uid_1_2_840_10008_5_1_4_1_1_66_1 = 155, // Spatial Registration Storage
00189 uid_1_2_840_10008_5_1_4_1_1_66_2 = 156, // Spatial Fiducials Storage
00190 uid_1_2_840_10008_5_1_4_1_1_66_3 = 157, // Deformable Spatial Registration Storage
00191 uid_1_2_840_10008_5_1_4_1_1_66_4 = 158, // Segmentation Storage
00192 uid_1_2_840_10008_5_1_4_1_1_67 = 159, // Real World Value Mapping Storage
00193 uid_1_2_840_10008_5_1_4_1_1_77_1 = 160, // VL Image Storage - Trial
00194 uid_1_2_840_10008_5_1_4_1_1_77_2 = 161, // VL Multi-frame Image Storage - Trial
00195 uid_1_2_840_10008_5_1_4_1_1_77_1_1 = 162, // VL Endoscopic Image Storage
00196 uid_1_2_840_10008_5_1_4_1_1_77_1_1_1 = 163, // Video Endoscopic Image Storage
00197 uid_1_2_840_10008_5_1_4_1_1_77_1_2 = 164, // VL Microscopic Image Storage
00198 uid_1_2_840_10008_5_1_4_1_1_77_1_2_1 = 165, // Video Microscopic Image Storage
00199 uid_1_2_840_10008_5_1_4_1_1_77_1_3 = 166, // VL Slide-Coordinates Microscopic Image Storage
00200 uid_1_2_840_10008_5_1_4_1_1_77_1_4 = 167, // VL Photographic Image Storage
00201 uid_1_2_840_10008_5_1_4_1_1_77_1_4_1 = 168, // Video Photographic Image Storage
00202 uid_1_2_840_10008_5_1_4_1_1_77_1_5_1 = 169, // Ophthalmic Photography 8 Bit Image Storage
00203 uid_1_2_840_10008_5_1_4_1_1_77_1_5_2 = 170, // Ophthalmic Photography 16 Bit Image Storage
00204 uid_1_2_840_10008_5_1_4_1_1_77_1_5_3 = 171, // Stereometric Relationship Storage
00205 uid_1_2_840_10008_5_1_4_1_1_77_1_5_4 = 172, // Ophthalmic Tomography Image Storage
00206 uid_1_2_840_10008_5_1_4_1_1_88_1 = 173, // Text SR Storage - Trial
00207 uid_1_2_840_10008_5_1_4_1_1_88_2 = 174, // Audio SR Storage - Trial
00208 uid_1_2_840_10008_5_1_4_1_1_88_3 = 175, // Detail SR Storage - Trial
00209 uid_1_2_840_10008_5_1_4_1_1_88_4 = 176, // Comprehensive SR Storage - Trial
00210 uid_1_2_840_10008_5_1_4_1_1_88_11 = 177, // Basic Text SR Storage
00211 uid_1_2_840_10008_5_1_4_1_1_88_22 = 178, // Enhanced SR Storage
00212 uid_1_2_840_10008_5_1_4_1_1_88_33 = 179, // Comprehensive SR Storage
00213 uid_1_2_840_10008_5_1_4_1_1_88_40 = 180, // Procedure Log Storage
00214 uid_1_2_840_10008_5_1_4_1_1_88_50 = 181, // Mammography CAD SR Storage
00215 uid_1_2_840_10008_5_1_4_1_1_88_59 = 182, // Key Object Selection Document Storage
00216 uid_1_2_840_10008_5_1_4_1_1_88_65 = 183, // Chest CAD SR Storage
00217 uid_1_2_840_10008_5_1_4_1_1_88_67 = 184, // X-Ray Radiation Dose SR Storage
00218 uid_1_2_840_10008_5_1_4_1_1_104_1 = 185, // Encapsulated PDF Storage
00219 uid_1_2_840_10008_5_1_4_1_1_104_2 = 186, // Encapsulated CDA Storage
00220 uid_1_2_840_10008_5_1_4_1_1_128 = 187, // Positron Emission Tomography Image Storage
00221 uid_1_2_840_10008_5_1_4_1_1_129 = 188, // Standalone PET Curve Storage
```

```
00222 uid_1_2_840_10008_5_1_4_1_1_481_1 = 189, // RT Image Storage
00223 uid_1_2_840_10008_5_1_4_1_1_481_2 = 190, // RT Dose Storage
00224 uid_1_2_840_10008_5_1_4_1_1_481_3 = 191, // RT Structure Set Storage
00225 uid_1_2_840_10008_5_1_4_1_1_481_4 = 192, // RT Beams Treatment Record Storage
00226 uid_1_2_840_10008_5_1_4_1_1_481_5 = 193, // RT Plan Storage
00227 uid_1_2_840_10008_5_1_4_1_1_481_6 = 194, // RT Brachy Treatment Record Storage
00228 uid_1_2_840_10008_5_1_4_1_1_481_7 = 195, // RT Treatment Summary Record Storage
00229 uid_1_2_840_10008_5_1_4_1_1_481_8 = 196, // RT Ion Plan Storage
00230 uid_1_2_840_10008_5_1_4_1_1_481_9 = 197, // RT Ion Beams Treatment Record Storage
00231 uid_1_2_840_10008_5_1_4_1_2_1_1 = 198, // Patient Root Query/Retrieve Information Model - FIND
00232 uid_1_2_840_10008_5_1_4_1_2_1_2 = 199, // Patient Root Query/Retrieve Information Model - MOVE
00233 uid_1_2_840_10008_5_1_4_1_2_1_3 = 200, // Patient Root Query/Retrieve Information Model - GET
00234 uid_1_2_840_10008_5_1_4_1_2_2_1 = 201, // Study Root Query/Retrieve Information Model - FIND
00235 uid_1_2_840_10008_5_1_4_1_2_2_2 = 202, // Study Root Query/Retrieve Information Model - MOVE
00236 uid_1_2_840_10008_5_1_4_1_2_2_3 = 203, // Study Root Query/Retrieve Information Model - GET
00237 uid_1_2_840_10008_5_1_4_1_2_3_1 = 204, // Patient/Study Only Query/Retrieve Information Model - FIND
00238 uid_1_2_840_10008_5_1_4_1_2_3_2 = 205, // Patient/Study Only Query/Retrieve Information Model - MOVE
00239 uid_1_2_840_10008_5_1_4_1_2_3_3 = 206, // Patient/Study Only Query/Retrieve Information Model - GET
00240 uid_1_2_840_10008_5_1_4_31 = 207, // Modality Worklist Information Model - FIND
00241 uid_1_2_840_10008_5_1_4_32_1 = 208, // General Purpose Worklist Information Model - FIND
00242 uid_1_2_840_10008_5_1_4_32_2 = 209, // General Purpose Scheduled Procedure Step SOP Class
00243 uid_1_2_840_10008_5_1_4_32_3 = 210, // General Purpose Performed Procedure Step SOP Class
00244 uid_1_2_840_10008_5_1_4_32 = 211, // General Purpose Worklist Management Meta SOP Class
00245 uid_1_2_840_10008_5_1_4_33 = 212, // Instance Availability Notification SOP Class
00246 uid_1_2_840_10008_5_1_4_34_1 = 213, // RT Beams Delivery Instruction Storage (Supplement 74 Frozen Draft)
00247 uid_1_2_840_10008_5_1_4_34_2 = 214, // RT Conventional Machine Verification (Supplement 74 Frozen Draft)
00248 uid_1_2_840_10008_5_1_4_34_3 = 215, // RT Ion Machine Verification (Supplement 74 Frozen Draft)
00249 uid_1_2_840_10008_5_1_4_34_4 = 216, // Unified Worklist and Procedure Step Service Class
00250 uid_1_2_840_10008_5_1_4_34_4_1 = 217, // Unified Procedure Step - Push SOP Class
00251 uid_1_2_840_10008_5_1_4_34_4_2 = 218, // Unified Procedure Step - Watch SOP Class
00252 uid_1_2_840_10008_5_1_4_34_4_3 = 219, // Unified Procedure Step - Pull SOP Class
00253 uid_1_2_840_10008_5_1_4_34_4_4 = 220, // Unified Procedure Step - Event SOP Class
00254 uid_1_2_840_10008_5_1_4_34_5 = 221, // Unified Worklist and Procedure Step SOP Instance
00255 uid_1_2_840_10008_5_1_4_37_1 = 222, // General Relevant Patient Information Query
00256 uid_1_2_840_10008_5_1_4_37_2 = 223, // Breast Imaging Relevant Patient Information Query
00257 uid_1_2_840_10008_5_1_4_37_3 = 224, // Cardiac Relevant Patient Information Query
00258 uid_1_2_840_10008_5_1_4_38_1 = 225, // Hanging Protocol Storage
00259 uid_1_2_840_10008_5_1_4_38_2 = 226, // Hanging Protocol Information Model - FIND
00260 uid_1_2_840_10008_5_1_4_38_3 = 227, // Hanging Protocol Information Model - MOVE
00261 uid_1_2_840_10008_5_1_4_41 = 228, // Product Characteristics Query SOP Class
00262 uid_1_2_840_10008_5_1_4_42 = 229, // Substance Approval Query SOP Class
00263 uid_1_2_840_10008_15_0_3_1 = 230, // dicomDeviceName
00264 uid_1_2_840_10008_15_0_3_2 = 231, // dicomDescription
00265 uid_1_2_840_10008_15_0_3_3 = 232, // dicomManufacturer
00266 uid_1_2_840_10008_15_0_3_4 = 233, // dicomManufacturerModelName
00267 uid_1_2_840_10008_15_0_3_5 = 234, // dicomSoftwareVersion
00268 uid_1_2_840_10008_15_0_3_6 = 235, // dicomVendorData
00269 uid_1_2_840_10008_15_0_3_7 = 236, // dicomAETitle
00270 uid_1_2_840_10008_15_0_3_8 = 237, // dicomNetworkConnectionReference
00271 uid_1_2_840_10008_15_0_3_9 = 238, // dicomApplicationCluster
00272 uid_1_2_840_10008_15_0_3_10 = 239, // dicomAssociationInitiator
00273 uid_1_2_840_10008_15_0_3_11 = 240, // dicomAssociationAcceptor
00274 uid_1_2_840_10008_15_0_3_12 = 241, // dicomHostname
00275 uid_1_2_840_10008_15_0_3_13 = 242, // dicomPort
00276 uid_1_2_840_10008_15_0_3_14 = 243, // dicomSOPClass
00277 uid_1_2_840_10008_15_0_3_15 = 244, // dicomTransferRole
00278 uid_1_2_840_10008_15_0_3_16 = 245, // dicomTransferSyntax
00279 uid_1_2_840_10008_15_0_3_17 = 246, // dicomPrimaryDeviceType
00280 uid_1_2_840_10008_15_0_3_18 = 247, // dicomRelatedDeviceReference
00281 uid_1_2_840_10008_15_0_3_19 = 248, // dicomPreferredCalledAETitle
00282 uid_1_2_840_10008_15_0_3_20 = 249, // dicomTLCSCyphersuite
00283 uid_1_2_840_10008_15_0_3_21 = 250, // dicomAuthorizedNodeCertificateReference
00284 uid_1_2_840_10008_15_0_3_22 = 251, // dicomThisNodeCertificateReference
00285 uid_1_2_840_10008_15_0_3_23 = 252, // dicomInstalled
00286 uid_1_2_840_10008_15_0_3_24 = 253, // dicomStationName
00287 uid_1_2_840_10008_15_0_3_25 = 254, // dicomDeviceSerialNumber
00288 uid_1_2_840_10008_15_0_3_26 = 255, // dicomInstitutionName
00289 uid_1_2_840_10008_15_0_3_27 = 256, // dicomInstitutionAddress
00290 uid_1_2_840_10008_15_0_3_28 = 257, // dicomInstitutionDepartmentName
00291 uid_1_2_840_10008_15_0_3_29 = 258, // dicomIssuerOfPatientID
00292 uid_1_2_840_10008_15_0_3_30 = 259, // dicomPreferredCallingAETitle
00293 uid_1_2_840_10008_15_0_3_31 = 260, // dicomSupportedCharacterSet
00294 uid_1_2_840_10008_15_0_4_1 = 261, // dicomConfigurationRoot
00295 uid_1_2_840_10008_15_0_4_2 = 262, // dicomDevicesRoot
00296 uid_1_2_840_10008_15_0_4_3 = 263, // dicomUniqueAETitlesRegistryRoot
00297 uid_1_2_840_10008_15_0_4_4 = 264, // dicomDevice
00298 uid_1_2_840_10008_15_0_4_5 = 265, // dicomNetworkAE
00299 uid_1_2_840_10008_15_0_4_6 = 266, // dicomNetworkConnection
00300 uid_1_2_840_10008_15_0_4_7 = 267, // dicomUniqueAETitle
00301 uid_1_2_840_10008_15_0_4_8 = 268, // dicomTransferCapability
00302 //
```

```
00303 uid_1_2_840_10008_5_1_4_1_1_77_1_6 = 269, // VL Whole Slide Microscopy
00304 uid_1_2_840_10008_5_1_4_1_1_6_2 = 270, // Enhanced US Volume Storage
00305 uid_1_2_840_10008_5_1_4_1_1_66_5 = 271, // Surface Segmentation Storage
00306 uid_1_2_840_10008_5_1_4_1_1_13_1_3 = 272, // Breast Tomosynthesis Image Storage
00307 uid_1_2_840_10008_5_1_4_1_1_2_2 = 273, // Legacy Converted Enhanced CT
00308 uid_1_2_840_10008_5_1_4_1_1_4_4 = 274, // Legacy Converted Enhanced MR
00309 uid_1_2_840_10008_5_1_4_1_1_128_1 = 275, // Legacy Converted Enhanced PET
00310 uid_1_2_840_10008_1_2_4_101 = 276, // MPEG2 Main Profile High Level
00311 uid_1_2_840_10008_1_2_4_102 = 277, // MPEG-4 AVC/H.264 High Profile Lev. 4.1
00312 uid_1_2_840_10008_1_2_4_103 = 278, // MPEG-4 AVC/H.264 BD-comp High Profile Lev. 4.1
00313
00315 //
00316 // 2019b
00317 //
00318 uid_1_2_840_10008_1_5_2 = 279,
00319 uid_1_2_840_10008_1_5_3 = 280,
00320 uid_1_2_840_10008_1_5_4 = 281,
00321 uid_1_2_840_10008_1_5_5 = 282,
00322 uid_1_2_840_10008_1_5_6 = 283,
00323 uid_1_2_840_10008_1_5_7 = 284,
00324 uid_1_2_840_10008_1_5_8 = 285,
00325 uid_1_2_840_10008_1_20 = 286,
00326 uid_1_2_840_10008_2_16_5 = 287,
00327 uid_1_2_840_10008_2_16_6 = 288,
00328 uid_1_2_840_10008_2_16_7 = 289,
00329 uid_1_2_840_10008_2_16_8 = 290,
00330 uid_1_2_840_10008_2_16_9 = 291,
00331 uid_1_2_840_10008_2_16_10 = 292,
00332 uid_1_2_840_10008_2_16_11 = 293,
00333 uid_1_2_840_10008_2_16_12 = 294,
00334 uid_1_2_840_10008_2_16_13 = 295,
00335 uid_1_2_840_10008_2_16_14 = 296,
00336 uid_1_2_840_10008_5_1_1_40 = 297,
00337 uid_1_2_840_10008_5_1_1_40_1 = 298,
00338 uid_1_2_840_10008_5_1_4_1_1_9_4_2 = 299,
00339 uid_1_2_840_10008_5_1_4_1_1_9_5_1 = 300,
00340 uid_1_2_840_10008_5_1_4_1_1_9_6_1 = 301,
00341 uid_1_2_840_10008_5_1_4_1_1_11_5 = 302,
00342 uid_1_2_840_10008_5_1_4_1_1_11_6 = 303,
00343 uid_1_2_840_10008_1_2_4_104 = 304,
00344 uid_1_2_840_10008_1_2_4_105 = 305,
00345 uid_1_2_840_10008_1_2_4_106 = 306,
00346 uid_1_2_840_10008_1_2_4_107 = 307,
00347 uid_1_2_840_10008_1_2_4_108 = 308,
00348 uid_1_2_840_10008_1_5_1 = 309,
00349 uid_1_2_840_10008_5_1_4_1_1_11_7 = 310,
00350 uid_1_2_840_10008_5_1_4_1_1_11_8 = 311,
00351 uid_1_2_840_10008_5_1_4_1_1_11_9 = 312,
00352 uid_1_2_840_10008_5_1_4_1_1_11_10 = 313,
00353 uid_1_2_840_10008_5_1_4_1_1_11_11 = 314,
00354 uid_1_2_840_10008_5_1_4_1_1_12_77 = 315,
00355 uid_1_2_840_10008_5_1_4_1_1_13_1_4 = 316,
00356 uid_1_2_840_10008_5_1_4_1_1_13_1_5 = 317,
00357 uid_1_2_840_10008_5_1_4_1_1_14_1 = 318,
00358 uid_1_2_840_10008_5_1_4_1_1_14_2 = 319,
00359 uid_1_2_840_10008_5_1_4_1_1_30 = 320,
00360 uid_1_2_840_10008_5_1_4_1_1_40 = 321,
00361 uid_1_2_840_10008_5_1_4_1_1_66_6 = 322,
00362 uid_1_2_840_10008_5_1_4_1_1_68_1 = 323,
00363 uid_1_2_840_10008_5_1_4_1_1_68_2 = 324,
00364 uid_1_2_840_10008_5_1_4_1_1_77_1_5_5 = 325,
00365 uid_1_2_840_10008_5_1_4_1_1_77_1_5_6 = 326,
00366 uid_1_2_840_10008_5_1_4_1_1_77_1_5_7 = 327,
00367 uid_1_2_840_10008_5_1_4_1_1_77_1_5_8 = 328,
00368 uid_1_2_840_10008_5_1_4_1_1_78_1 = 329,
00369 uid_1_2_840_10008_5_1_4_1_1_78_2 = 330,
00370 uid_1_2_840_10008_5_1_4_1_1_78_3 = 331,
00371 uid_1_2_840_10008_5_1_4_1_1_78_4 = 332,
00372 uid_1_2_840_10008_5_1_4_1_1_78_5 = 333,
00373 uid_1_2_840_10008_5_1_4_1_1_78_6 = 334,
00374 uid_1_2_840_10008_5_1_4_1_1_78_7 = 335,
00375 uid_1_2_840_10008_5_1_4_1_1_78_8 = 336,
00376 uid_1_2_840_10008_5_1_4_1_1_79_1 = 337,
00377 uid_1_2_840_10008_5_1_4_1_1_80_1 = 338,
00378 uid_1_2_840_10008_5_1_4_1_1_81_1 = 339,
00379 uid_1_2_840_10008_5_1_4_1_1_82_1 = 340,
00380 uid_1_2_840_10008_5_1_4_1_1_88_34 = 341,
00381 uid_1_2_840_10008_5_1_4_1_1_88_35 = 342,
00382 uid_1_2_840_10008_5_1_4_1_1_88_68 = 343,
00383 uid_1_2_840_10008_5_1_4_1_1_88_69 = 344,
00384 uid_1_2_840_10008_5_1_4_1_1_88_70 = 345,
```

```

00385 uid_1_2_840_10008_5_1_4_1_1_88_71 = 346,
00386 uid_1_2_840_10008_5_1_4_1_1_88_72 = 347,
00387 uid_1_2_840_10008_5_1_4_1_1_88_73 = 348,
00388 uid_1_2_840_10008_5_1_4_1_1_88_74 = 349,
00389 uid_1_2_840_10008_5_1_4_1_1_88_75 = 350,
00390 uid_1_2_840_10008_5_1_4_1_1_90_1 = 351,
00391 uid_1_2_840_10008_5_1_4_1_1_104_3 = 352,
00392 uid_1_2_840_10008_5_1_4_1_1_130 = 353,
00393 uid_1_2_840_10008_5_1_4_1_1_131 = 354,
00394 uid_1_2_840_10008_5_1_4_1_1_200_1 = 355,
00395 uid_1_2_840_10008_5_1_4_1_1_200_2 = 356,
00396 uid_1_2_840_10008_5_1_4_1_1_200_3 = 357,
00397 uid_1_2_840_10008_5_1_4_1_1_200_4 = 358,
00398 uid_1_2_840_10008_5_1_4_1_1_200_5 = 359,
00399 uid_1_2_840_10008_5_1_4_1_1_200_6 = 360,
00400 uid_1_2_840_10008_5_1_4_1_1_481_10 = 361,
00401 uid_1_2_840_10008_5_1_4_1_1_481_11 = 362,
00402 uid_1_2_840_10008_5_1_4_1_1_501_1 = 363,
00403 uid_1_2_840_10008_5_1_4_1_1_501_2_1 = 364,
00404 uid_1_2_840_10008_5_1_4_1_1_501_2_2 = 365,
00405 uid_1_2_840_10008_5_1_4_1_1_501_3 = 366,
00406 uid_1_2_840_10008_5_1_4_1_1_501_4 = 367,
00407 uid_1_2_840_10008_5_1_4_1_1_501_5 = 368,
00408 uid_1_2_840_10008_5_1_4_1_1_501_6 = 369,
00409 uid_1_2_840_10008_5_1_4_1_1_601_1 = 370,
00410 uid_1_2_840_10008_5_1_4_1_1_601_2 = 371,
00411 uid_1_2_840_10008_5_1_4_1_2_4_2 = 372,
00412 uid_1_2_840_10008_5_1_4_1_2_4_3 = 373,
00413 uid_1_2_840_10008_5_1_4_1_2_5_3 = 374,
00414 uid_1_2_840_10008_5_1_4_20_1 = 375,
00415 uid_1_2_840_10008_5_1_4_20_2 = 376,
00416 uid_1_2_840_10008_5_1_4_20_3 = 377,
00417 uid_1_2_840_10008_5_1_4_34_5_1 = 378,
00418 uid_1_2_840_10008_5_1_4_34_6 = 379,
00419 uid_1_2_840_10008_5_1_4_34_6_1 = 380,
00420 uid_1_2_840_10008_5_1_4_34_6_2 = 381,
00421 uid_1_2_840_10008_5_1_4_34_6_3 = 382,
00422 uid_1_2_840_10008_5_1_4_34_6_4 = 383,
00423 uid_1_2_840_10008_5_1_4_34_7 = 384,
00424 uid_1_2_840_10008_5_1_4_34_8 = 385,
00425 uid_1_2_840_10008_5_1_4_34_9 = 386,
00426 uid_1_2_840_10008_5_1_4_34_10 = 387,
00427 uid_1_2_840_10008_5_1_4_38_4 = 388,
00428 uid_1_2_840_10008_5_1_4_39_1 = 389,
00429 uid_1_2_840_10008_5_1_4_39_2 = 390,
00430 uid_1_2_840_10008_5_1_4_39_3 = 391,
00431 uid_1_2_840_10008_5_1_4_39_4 = 392,
00432 uid_1_2_840_10008_5_1_4_43_1 = 393,
00433 uid_1_2_840_10008_5_1_4_43_2 = 394,
00434 uid_1_2_840_10008_5_1_4_43_3 = 395,
00435 uid_1_2_840_10008_5_1_4_43_4 = 396,
00436 uid_1_2_840_10008_5_1_4_44_1 = 397,
00437 uid_1_2_840_10008_5_1_4_44_2 = 398,
00438 uid_1_2_840_10008_5_1_4_44_3 = 399,
00439 uid_1_2_840_10008_5_1_4_44_4 = 400,
00440 uid_1_2_840_10008_5_1_4_45_1 = 401,
00441 uid_1_2_840_10008_5_1_4_45_2 = 402,
00442 uid_1_2_840_10008_5_1_4_45_3 = 403,
00443 uid_1_2_840_10008_5_1_4_45_4 = 404,
00444 uid_1_2_840_10008_7_1_1 = 405,
00445 uid_1_2_840_10008_7_1_2 = 406,
00446 uid_1_2_840_10008_8_1_1 = 407,
00447 uid_1_2_840_10008_5_1_4_1_1_4_3 = 408,
00448 uid_1_2_840_10008_15_1_1 = 409
00449 //
00450 //
00452 //
00454 //
00455 // Optionally private UIDs
00456 //
00457 #if 0
00458 uid_1_2_840_113619_4_2,
00459 uid_1_2_840_113619_4_3,
00460 uid_1_3_12_2_1107_5_9_1,
00461 uid_1_2_840_113619_4_26,
00462 uid_1_2_840_113619_4_30,
00463 uid_2_16_840_1_113709_1_5_1,
00464 uid_2_16_840_1_113709_1_2_2,
00465 uid_1_2_840_113543_6_6_1_3_10002,
00466 uid_1_2_392_200036_9116_7_8_1_1_1,
00467 uid_1_2_392_200036_9125_1_1_2,

```

```
00468 uid_1_2_840_113619_4_27,
00469 uid_1_3_46_670589_11_0_0_12_1,
00470 uid_1_3_46_670589_11_0_0_12_2,
00471 uid_1_3_46_670589_11_0_0_12_4,
00472 uid_1_3_46_670589_2_3_1_1,
00473 uid_1_3_46_670589_2_4_1_1,
00474 uid_1_3_46_670589_2_5_1_1,
00475 uid_1_3_46_670589_5_0_1,
00476 uid_1_3_46_670589_5_0_1_1,
00477 uid_1_3_46_670589_5_0_10,
00478 uid_1_3_46_670589_5_0_11,
00479 uid_1_3_46_670589_5_0_11_1,
00480 uid_1_3_46_670589_5_0_12,
00481 uid_1_3_46_670589_5_0_13,
00482 uid_1_3_46_670589_5_0_14,
00483 uid_1_3_46_670589_5_0_2,
00484 uid_1_3_46_670589_5_0_2_1,
00485 uid_1_3_46_670589_5_0_3,
00486 uid_1_3_46_670589_5_0_3_1,
00487 uid_1_3_46_670589_5_0_4,
00488 uid_1_3_46_670589_5_0_7,
00489 uid_1_3_46_670589_5_0_8,
00490 uid_1_3_46_670589_5_0_9,
00491 uid_1_2_752_24_3_7_6,
00492 uid_1_2_752_24_3_7_7,
00493 uid_1_2_840_113619_5_2,
00494 uid_1_3_46_670589_33_1_4_1
00495 #endif
00496 //
00497 //
00499
00500 } TSType;
00501 typedef enum {
00502 VerificationSOPClass = 1, // Verification SOP Class
00503 ImplicitVRLittleEndianDefaultTransferSyntaxforDICOM = 2, // Implicit VR Little Endian: Default Transfer
    Syntax for DICOM
00504 ExplicitVRLittleEndian = 3, // Explicit VR Little Endian
00505 DeflatedExplicitVRLittleEndian = 4, // Deflated Explicit VR Little Endian
00506 ExplicitVRBigEndian = 5, // Explicit VR Big Endian
00507 JPEGBaselineProcess1DefaultTransferSyntaxforLossyJPEG8BitImageCompression = 6, // JPEG Baseline (Process
    1): Default Transfer Syntax for Lossy JPEG 8 Bit Image Compression
00508 JPEGExtendedProcess24DefaultTransferSyntaxforLossyJPEG12BitImageCompressionProcess4only = 7, // JPEG
    Extended (Process 2 & 4): Default Transfer Syntax for Lossy JPEG 12 Bit Image Compression (Process 4 only)
00509 JPEGExtendedProcess35Retired = 8, // JPEG Extended (Process 3 & 5)
00510 JPEGSpectralSelectionNonHierarchicalProcess68Retired = 9, // JPEG Spectral Selection, Non-Hierarchical
    (Process 6 & 8)
00511 JPEGSpectralSelectionNonHierarchicalProcess79Retired = 10, // JPEG Spectral Selection, Non-Hierarchical
    (Process 7 & 9)
00512 JPEGFullProgressionNonHierarchicalProcess1012Retired = 11, // JPEG Full Progression, Non-Hierarchical
    (Process 10 & 12)
00513 JPEGFullProgressionNonHierarchicalProcess1113Retired = 12, // JPEG Full Progression, Non-Hierarchical
    (Process 11 & 13)
00514 JPEGLosslessNonHierarchicalProcess14 = 13, // JPEG Lossless, Non-Hierarchical (Process 14)
00515 JPEGLosslessNonHierarchicalProcess15Retired = 14, // JPEG Lossless, Non-Hierarchical (Process 15)
00516 JPEGExtendedHierarchicalProcess1618Retired = 15, // JPEG Extended, Hierarchical (Process 16 & 18)
00517 JPEGExtendedHierarchicalProcess1719Retired = 16, // JPEG Extended, Hierarchical (Process 17 & 19)
00518 JPEGSpectralSelectionHierarchicalProcess2022Retired = 17, // JPEG Spectral Selection, Hierarchical
    (Process 20 & 22)
00519 JPEGSpectralSelectionHierarchicalProcess2123Retired = 18, // JPEG Spectral Selection, Hierarchical
    (Process 21 & 23)
00520 JPEGFullProgressionHierarchicalProcess2426Retired = 19, // JPEG Full Progression, Hierarchical (Process 24
    & 26)
00521 JPEGFullProgressionHierarchicalProcess2527Retired = 20, // JPEG Full Progression, Hierarchical (Process 25
    & 27)
00522 JPEGLosslessHierarchicalProcess28Retired = 21, // JPEG Lossless, Hierarchical (Process 28)
00523 JPEGLosslessHierarchicalProcess29Retired = 22, // JPEG Lossless, Hierarchical (Process 29)
00524
    JPEGLosslessNonHierarchicalFirstOrderPredictionProcess14SelectionValue1DefaultTransferSyntaxforLosslessJPEGImageCompression
    = 23, // JPEG Lossless, Non-Hierarchical, First-Order Prediction (Process 14 [Selection Value 1]): Default
    Transfer Syntax for Lossless JPEG Image Compression
00525 JPEGLSLosslessImageCompression = 24, // JPEG-LS Lossless Image Compression
00526 JPEGLSLossyNearLosslessImageCompression = 25, // JPEG-LS Lossy (Near-Lossless) Image Compression
00527 JPEG2000ImageCompressionLosslessOnly = 26, // JPEG 2000 Image Compression (Lossless Only)
00528 JPEG2000ImageCompression = 27, // JPEG 2000 Image Compression
00529 JPEG2000Part2MultiComponentImageCompressionLosslessOnly = 28, // JPEG 2000 Part 2 Multi-component Image
    Compression (Lossless Only)
00530 JPEG2000Part2MultiComponentImageCompression = 29, // JPEG 2000 Part 2 Multi-component Image Compression
00531 JPIPReferenced = 30, // JPIP Referenced
00532 JPIPReferencedDeflate = 31, // JPIP Referenced Deflate
00533 MPEG2MainProfileMainLevel = 32, // MPEG2 Main Profile @ Main Level
00534 RLELossless = 33, // RLE Lossless
```

```
00535 RFC2557MIMEencapsulation = 34, // RFC 2557 MIME encapsulation
00536 XMLEncoding = 35, // XML Encoding
00537 MediaStorageDirectoryStorage = 36, // Media Storage Directory Storage
00538 TalairachBrainAtlasFrameofReference = 37, // Talairach Brain Atlas Frame of Reference
00539 SPM2T1FrameofReference = 38, // SPM2 T1 Frame of Reference
00540 SPM2T2FrameofReference = 39, // SPM2 T2 Frame of Reference
00541 SPM2PDFFrameofReference = 40, // SPM2 PD Frame of Reference
00542 SPM2EPIFrameofReference = 41, // SPM2 EPI Frame of Reference
00543 SPM2FILTI1FrameofReference = 42, // SPM2 FIL T1 Frame of Reference
00544 SPM2PETFrameofReference = 43, // SPM2 PET Frame of Reference
00545 SPM2TRANSMFrameofReference = 44, // SPM2 TRANSM Frame of Reference
00546 SPM2SPECTFrameofReference = 45, // SPM2 SPECT Frame of Reference
00547 SPM2GRAYFrameofReference = 46, // SPM2 GRAY Frame of Reference
00548 SPM2WHITEFrameofReference = 47, // SPM2 WHITE Frame of Reference
00549 SPM2CSFFFrameofReference = 48, // SPM2 CSF Frame of Reference
00550 SPM2BRAINMASKFrameofReference = 49, // SPM2 BRAINMASK Frame of Reference
00551 SPM2AVG305T1FrameofReference = 50, // SPM2 AVG305T1 Frame of Reference
00552 SPM2AVG152T1FrameofReference = 51, // SPM2 AVG152T1 Frame of Reference
00553 SPM2AVG152T2FrameofReference = 52, // SPM2 AVG152T2 Frame of Reference
00554 SPM2AVG152PDFrameofReference = 53, // SPM2 AVG152PD Frame of Reference
00555 SPM2SINGLESUBJT1FrameofReference = 54, // SPM2 SINGLESUBJT1 Frame of Reference
00556 ICBM452T1FrameofReference = 55, // ICBM 452 T1 Frame of Reference
00557 ICBMSingleSubjectMRIFrameofReference = 56, // ICBM Single Subject MRI Frame of Reference
00558 BasicStudyContentNotificationSOPClassRetired = 57, // Basic Study Content Notification SOP Class
00559 StorageCommitmentPushModelSOPClass = 58, // Storage Commitment Push Model SOP Class
00560 StorageCommitmentPushModelSOPInstance = 59, // Storage Commitment Push Model SOP Instance
00561 StorageCommitmentPullModelSOPClassRetired = 60, // Storage Commitment Pull Model SOP Class
00562 StorageCommitmentPullModelSOPInstanceRetired = 61, // Storage Commitment Pull Model SOP Instance
00563 ProceduralEventLoggingSOPClass = 62, // Procedural Event Logging SOP Class
00564 ProceduralEventLoggingSOPInstance = 63, // Procedural Event Logging SOP Instance
00565 SubstanceAdministrationLoggingSOPClass = 64, // Substance Administration Logging SOP Class
00566 SubstanceAdministrationLoggingSOPInstance = 65, // Substance Administration Logging SOP Instance
00567 DICOMUIDRegistry = 66, // DICOM UID Registry
00568 DICOMControlledTerminology = 67, // DICOM Controlled Terminology
00569 DICOMApplicationContextName = 68, // DICOM Application Context Name
00570 DetachedPatientManagementSOPClassRetired = 69, // Detached Patient Management SOP Class
00571 DetachedPatientManagementMetaSOPClassRetired = 70, // Detached Patient Management Meta SOP Class
00572 DetachedVisitManagementSOPClassRetired = 71, // Detached Visit Management SOP Class
00573 DetachedStudyManagementSOPClassRetired = 72, // Detached Study Management SOP Class
00574 StudyComponentManagementSOPClassRetired = 73, // Study Component Management SOP Class
00575 ModalityPerformedProcedureStepSOPClass = 74, // Modality Performed Procedure Step SOP Class
00576 ModalityPerformedProcedureStepRetrieveSOPClass = 75, // Modality Performed Procedure Step Retrieve SOP
    Class
00577 ModalityPerformedProcedureStepNotificationSOPClass = 76, // Modality Performed Procedure Step Notification
    SOP Class
00578 DetachedResultsManagementSOPClassRetired = 77, // Detached Results Management SOP Class
00579 DetachedResultsManagementMetaSOPClassRetired = 78, // Detached Results Management Meta SOP Class
00580 DetachedStudyManagementMetaSOPClassRetired = 79, // Detached Study Management Meta SOP Class
00581 DetachedInterpretationManagementSOPClassRetired = 80, // Detached Interpretation Management SOP Class
00582 StorageServiceClass = 81, // Storage Service Class
00583 BasicFilmSessionSOPClass = 82, // Basic Film Session SOP Class
00584 BasicFilmBoxSOPClass = 83, // Basic Film Box SOP Class
00585 BasicGrayscaleImageBoxSOPClass = 84, // Basic Grayscale Image Box SOP Class
00586 BasicColorImageBoxSOPClass = 85, // Basic Color Image Box SOP Class
00587 ReferencedImageBoxSOPClassRetired = 86, // Referenced Image Box SOP Class
00588 BasicGrayscalePrintManagementMetaSOPClass = 87, // Basic Grayscale Print Management Meta SOP Class
00589 ReferencedGrayscalePrintManagementMetaSOPClassRetired = 88, // Referenced Grayscale Print Management Meta
    SOP Class
00590 PrintJobSOPClass = 89, // Print Job SOP Class
00591 BasicAnnotationBoxSOPClass = 90, // Basic Annotation Box SOP Class
00592 PrinterSOPClass = 91, // Printer SOP Class
00593 PrinterConfigurationRetrievalSOPClass = 92, // Printer Configuration Retrieval SOP Class
00594 PrinterSOPInstance = 93, // Printer SOP Instance
00595 PrinterConfigurationRetrievalSOPInstance = 94, // Printer Configuration Retrieval SOP Instance
00596 BasicColorPrintManagementMetaSOPClass = 95, // Basic Color Print Management Meta SOP Class
00597 ReferencedColorPrintManagementMetaSOPClassRetired = 96, // Referenced Color Print Management Meta SOP
    Class
00598 VOILUTBoxSOPClass = 97, // VOI LUT Box SOP Class
00599 PresentationLUTSOPClass = 98, // Presentation LUT SOP Class
00600 ImageOverlayBoxSOPClassRetired = 99, // Image Overlay Box SOP Class
00601 BasicPrintImageOverlayBoxSOPClassRetired = 100, // Basic Print Image Overlay Box SOP Class
00602 PrintQueueSOPInstanceRetired = 101, // Print Queue SOP Instance
00603 PrintQueueManagementSOPClassRetired = 102, // Print Queue Management SOP Class
00604 StoredPrintStorageSOPClassRetired = 103, // Stored Print Storage SOP Class
00605 HardcopyGrayscaleImageStorageSOPClassRetired = 104, // Hardcopy Grayscale Image Storage SOP Class
00606 HardcopyColorImageStorageSOPClassRetired = 105, // Hardcopy Color Image Storage SOP Class
00607 PullPrintRequestSOPClassRetired = 106, // Pull Print Request SOP Class
00608 PullStoredPrintManagementMetaSOPClassRetired = 107, // Pull Stored Print Management Meta SOP Class
00609 MediaCreationManagementSOPClassUID = 108, // Media Creation Management SOP Class UID
00610 ComputedRadiographyImageStorage = 109, // Computed Radiography Image Storage
00611 DigitalXRayImageStorageForPresentation = 110, // Digital X-Ray Image Storage - For Presentation
```



```
00612 DigitalXRayImageStorageForProcessing = 111, // Digital X-Ray Image Storage - For Processing
00613 DigitalMammographyXRayImageStorageForPresentation = 112, // Digital Mammography X-Ray Image Storage - For
Presentation
00614 DigitalMammographyXRayImageStorageForProcessing = 113, // Digital Mammography X-Ray Image Storage - For
Processing
00615 DigitalIntraoralXRayImageStorageForPresentation = 114, // Digital Intra-oral X-Ray Image Storage - For
Presentation
00616 DigitalIntraoralXRayImageStorageForProcessing = 115, // Digital Intra-oral X-Ray Image Storage - For
Processing
00617 CTImageStorage = 116, // CT Image Storage
00618 EnhancedCTImageStorage = 117, // Enhanced CT Image Storage
00619 UltrasoundMultiframeImageStorageRetired = 118, // Ultrasound Multi-frame Image Storage
00620 UltrasoundMultiframeImageStorage = 119, // Ultrasound Multi-frame Image Storage
00621 MRImageStorage = 120, // MR Image Storage
00622 EnhancedMRImageStorage = 121, // Enhanced MR Image Storage
00623 MRSpectroscopyStorage = 122, // MR Spectroscopy Storage
00624 NuclearMedicineImageStorageRetired = 123, // Nuclear Medicine Image Storage
00625 UltrasoundImageStorageRetired = 124, // Ultrasound Image Storage
00626 UltrasoundImageStorage = 125, // Ultrasound Image Storage
00627 SecondaryCaptureImageStorage = 126, // Secondary Capture Image Storage
00628 MultiframeSingleBitSecondaryCaptureImageStorage = 127, // Multi-frame Single Bit Secondary Capture Image
Storage
00629 MultiframeGrayscaleByteSecondaryCaptureImageStorage = 128, // Multi-frame Grayscale Byte Secondary Capture
Image Storage
00630 MultiframeGrayscaleWordSecondaryCaptureImageStorage = 129, // Multi-frame Grayscale Word Secondary Capture
Image Storage
00631 MultiframeTrueColorSecondaryCaptureImageStorage = 130, // Multi-frame True Color Secondary Capture Image
Storage
00632 StandaloneOverlayStorageRetired = 131, // Standalone Overlay Storage
00633 StandaloneCurveStorageRetired = 132, // Standalone Curve Storage
00634 WaveformStorageTrialRetired = 133, // Waveform Storage - Trial
00635 ECG12leadWaveformStorage = 134, // 12-lead ECG Waveform Storage
00636 GeneralECGWaveformStorage = 135, // General ECG Waveform Storage
00637 AmbulatoryECGWaveformStorage = 136, // Ambulatory ECG Waveform Storage
00638 HemodynamicWaveformStorage = 137, // Hemodynamic Waveform Storage
00639 CardiacElectrophysiologyWaveformStorage = 138, // Cardiac Electrophysiology Waveform Storage
00640 BasicVoiceAudioWaveformStorage = 139, // Basic Voice Audio Waveform Storage
00641 StandaloneModalityLUTStorageRetired = 140, // Standalone Modality LUT Storage
00642 StandaloneVOILUTStorageRetired = 141, // Standalone VOI LUT Storage
00643 GrayscaleSoftcopyPresentationStateStorageSOPClass = 142, // Grayscale Softcopy Presentation State Storage
SOP Class
00644 ColorSoftcopyPresentationStateStorageSOPClass = 143, // Color Softcopy Presentation State Storage SOP
Class
00645 PseudoColorSoftcopyPresentationStateStorageSOPClass = 144, // Pseudo-Color Softcopy Presentation State
Storage SOP Class
00646 BlendingSoftcopyPresentationStateStorageSOPClass = 145, // Blending Softcopy Presentation State Storage
SOP Class
00647 XRayAngiographicImageStorage = 146, // X-Ray Angiographic Image Storage
00648 EnhancedXAImageStorage = 147, // Enhanced XA Image Storage
00649 XRayRadiofluoroscopicImageStorage = 148, // X-Ray Radiofluoroscopic Image Storage
00650 EnhancedXRFImageStorage = 149, // Enhanced XRF Image Storage
00651 XRay3DAngiographicImageStorage = 150, // X-Ray 3D Angiographic Image Storage
00652 XRay3DCraniofacialImageStorage = 151, // X-Ray 3D Craniofacial Image Storage
00653 XRayAngiographicBiPlaneImageStorageRetired = 152, // X-Ray Angiographic Bi-Plane Image Storage
00654 NuclearMedicineImageStorage = 153, // Nuclear Medicine Image Storage
00655 RawDataStorage = 154, // Raw Data Storage
00656 SpatialRegistrationStorage = 155, // Spatial Registration Storage
00657 SpatialFiducialsStorage = 156, // Spatial Fiducials Storage
00658 DeformableSpatialRegistrationStorage = 157, // Deformable Spatial Registration Storage
00659 SegmentationStorage = 158, // Segmentation Storage
00660 RealWorldValueMappingStorage = 159, // Real World Value Mapping Storage
00661 VLImageStorageTrialRetired = 160, // VL Image Storage - Trial
00662 VLMultiframeImageStorageTrialRetired = 161, // VL Multi-frame Image Storage - Trial
00663 VLEndoscopicImageStorage = 162, // VL Endoscopic Image Storage
00664 VideoEndoscopicImageStorage = 163, // Video Endoscopic Image Storage
00665 VLMicroscopicImageStorage = 164, // VL Microscopic Image Storage
00666 VideoMicroscopicImageStorage = 165, // Video Microscopic Image Storage
00667 VLSlideCoordinatesMicroscopicImageStorage = 166, // VL Slide-Coordinates Microscopic Image Storage
00668 VLPhotographicImageStorage = 167, // VL Photographic Image Storage
00669 VideoPhotographicImageStorage = 168, // Video Photographic Image Storage
00670 OphthalmicPhotography8BitImageStorage = 169, // Ophthalmic Photography 8 Bit Image Storage
00671 OphthalmicPhotography16BitImageStorage = 170, // Ophthalmic Photography 16 Bit Image Storage
00672 StereometricRelationshipStorage = 171, // Stereometric Relationship Storage
00673 OphthalmicTomographyImageStorage = 172, // Ophthalmic Tomography Image Storage
00674 TextSRStorageTrialRetired = 173, // Text SR Storage - Trial
00675 AudioSRStorageTrialRetired = 174, // Audio SR Storage - Trial
00676 DetailSRStorageTrialRetired = 175, // Detail SR Storage - Trial
00677 ComprehensiveSRStorageTrialRetired = 176, // Comprehensive SR Storage - Trial
00678 BasicTextSRStorage = 177, // Basic Text SR Storage
00679 EnhancedSRStorage = 178, // Enhanced SR Storage
00680 ComprehensiveSRStorage = 179, // Comprehensive SR Storage
```

```
00681 ProcedureLogStorage = 180, // Procedure Log Storage
00682 MammographyCADSRStorage = 181, // Mammography CAD SR Storage
00683 KeyObjectSelectionDocumentStorage = 182, // Key Object Selection Document Storage
00684 ChestCADSRStorage = 183, // Chest CAD SR Storage
00685 XRayRadiationDoseSRStorage = 184, // X-Ray Radiation Dose SR Storage
00686 EncapsulatedPDFStorage = 185, // Encapsulated PDF Storage
00687 EncapsulatedCDAStorage = 186, // Encapsulated CDA Storage
00688 PositronEmissionTomographyImageStorage = 187, // Positron Emission Tomography Image Storage
00689 StandalonePETCurveStorageRetired = 188, // Standalone PET Curve Storage
00690 RTImageStorage = 189, // RT Image Storage
00691 RTDoseStorage = 190, // RT Dose Storage
00692 RTStructureSetStorage = 191, // RT Structure Set Storage
00693 RTBeamsTreatmentRecordStorage = 192, // RT Beams Treatment Record Storage
00694 RTPlanStorage = 193, // RT Plan Storage
00695 RTBrachyTreatmentRecordStorage = 194, // RT Brachy Treatment Record Storage
00696 RTTreatmentSummaryRecordStorage = 195, // RT Treatment Summary Record Storage
00697 RTIonPlanStorage = 196, // RT Ion Plan Storage
00698 RTIonBeamsTreatmentRecordStorage = 197, // RT Ion Beams Treatment Record Storage
00699 PatientRootQueryRetrieveInformationModelFIND = 198, // Patient Root Query/Retrieve Information Model -
    FIND
00700 PatientRootQueryRetrieveInformationModelMOVE = 199, // Patient Root Query/Retrieve Information Model -
    MOVE
00701 PatientRootQueryRetrieveInformationModelGET = 200, // Patient Root Query/Retrieve Information Model - GET
00702 StudyRootQueryRetrieveInformationModelFIND = 201, // Study Root Query/Retrieve Information Model - FIND
00703 StudyRootQueryRetrieveInformationModelMOVE = 202, // Study Root Query/Retrieve Information Model - MOVE
00704 StudyRootQueryRetrieveInformationModelGET = 203, // Study Root Query/Retrieve Information Model - GET
00705 PatientStudyOnlyQueryRetrieveInformationModelFINDRetired = 204, // Patient/Study Only Query/Retrieve
    Information Model - FIND
00706 PatientStudyOnlyQueryRetrieveInformationModelMOVERetired = 205, // Patient/Study Only Query/Retrieve
    Information Model - MOVE
00707 PatientStudyOnlyQueryRetrieveInformationModelGETRetired = 206, // Patient/Study Only Query/Retrieve
    Information Model - GET
00708 ModalityWorklistInformationModelFIND = 207, // Modality Worklist Information Model - FIND
00709 GeneralPurposeWorklistInformationModelFIND = 208, // General Purpose Worklist Information Model - FIND
00710 GeneralPurposeScheduledProcedureStepSOPClass = 209, // General Purpose Scheduled Procedure Step SOP Class
00711 GeneralPurposePerformedProcedureStepSOPClass = 210, // General Purpose Performed Procedure Step SOP Class
00712 GeneralPurposeWorklistManagementMetaSOPClass = 211, // General Purpose Worklist Management Meta SOP Class
00713 InstanceAvailabilityNotificationSOPClass = 212, // Instance Availability Notification SOP Class
00714 RTBeamsDeliveryInstructionStorageSupplement74FrozenDraft = 213, // RT Beams Delivery Instruction Storage
    (Supplement 74 Frozen Draft)
00715 RTConventionalMachineVerificationSupplement74FrozenDraft = 214, // RT Conventional Machine Verification
    (Supplement 74 Frozen Draft)
00716 RTIonMachineVerificationSupplement74FrozenDraft = 215, // RT Ion Machine Verification (Supplement 74
    Frozen Draft)
00717 UnifiedWorklistandProcedureStepServiceClass = 216, // Unified Worklist and Procedure Step Service Class
00718 UnifiedProcedureStepPushSOPClass = 217, // Unified Procedure Step - Push SOP Class
00719 UnifiedProcedureStepWatchSOPClass = 218, // Unified Procedure Step - Watch SOP Class
00720 UnifiedProcedureStepPullSOPClass = 219, // Unified Procedure Step - Pull SOP Class
00721 UnifiedProcedureStepEventSOPClass = 220, // Unified Procedure Step - Event SOP Class
00722 UnifiedWorklistandProcedureStepSOPInstance = 221, // Unified Worklist and Procedure Step SOP Instance
00723 GeneralRelevantPatientInformationQuery = 222, // General Relevant Patient Information Query
00724 BreastImagingRelevantPatientInformationQuery = 223, // Breast Imaging Relevant Patient Information Query
00725 CardiacRelevantPatientInformationQuery = 224, // Cardiac Relevant Patient Information Query
00726 HangingProtocolStorage = 225, // Hanging Protocol Storage
00727 HangingProtocolInformationModelFIND = 226, // Hanging Protocol Information Model - FIND
00728 HangingProtocolInformationModelMOVE = 227, // Hanging Protocol Information Model - MOVE
00729 ProductCharacteristicsQuerySOPClass = 228, // Product Characteristics Query SOP Class
00730 SubstanceApprovalQuerySOPClass = 229, // Substance Approval Query SOP Class
00731 dicomDeviceName = 230, // dicomDeviceName
00732 dicomDescription = 231, // dicomDescription
00733 dicomManufacturer = 232, // dicomManufacturer
00734 dicomManufacturerModelName = 233, // dicomManufacturerModelName
00735 dicomSoftwareVersion = 234, // dicomSoftwareVersion
00736 dicomVendorData = 235, // dicomVendorData
00737 dicomAETitle = 236, // dicomAETitle
00738 dicomNetworkConnectionReference = 237, // dicomNetworkConnectionReference
00739 dicomApplicationCluster = 238, // dicomApplicationCluster
00740 dicomAssociationInitiator = 239, // dicomAssociationInitiator
00741 dicomAssociationAcceptor = 240, // dicomAssociationAcceptor
00742 dicomHostname = 241, // dicomHostname
00743 dicomPort = 242, // dicomPort
00744 dicomSOPClass = 243, // dicomSOPClass
00745 dicomTransferRole = 244, // dicomTransferRole
00746 dicomTransferSyntax = 245, // dicomTransferSyntax
00747 dicomPrimaryDeviceType = 246, // dicomPrimaryDeviceType
00748 dicomRelatedDeviceReference = 247, // dicomRelatedDeviceReference
00749 dicomPreferredCalledAETitle = 248, // dicomPreferredCalledAETitle
00750 dicomTLSCyphersuite = 249, // dicomTLSCyphersuite
00751 dicomAuthorizedNodeCertificateReference = 250, // dicomAuthorizedNodeCertificateReference
00752 dicomThisNodeCertificateReference = 251, // dicomThisNodeCertificateReference
00753 dicomInstalled = 252, // dicomInstalled
```



```
00754 dicomStationName = 253, // dicomStationName
00755 dicomDeviceSerialNumber = 254, // dicomDeviceSerialNumber
00756 dicomInstitutionName = 255, // dicomInstitutionName
00757 dicomInstitutionAddress = 256, // dicomInstitutionAddress
00758 dicomInstitutionDepartmentName = 257, // dicomInstitutionDepartmentName
00759 dicomIssuerOfPatientID = 258, // dicomIssuerOfPatientID
00760 dicomPreferredCallingAETitle = 259, // dicomPreferredCallingAETitle
00761 dicomSupportedCharacterSet = 260, // dicomSupportedCharacterSet
00762 dicomConfigurationRoot = 261, // dicomConfigurationRoot
00763 dicomDevicesRoot = 262, // dicomDevicesRoot
00764 dicomUniqueAETitlesRegistryRoot = 263, // dicomUniqueAETitlesRegistryRoot
00765 dicomDevice = 264, // dicomDevice
00766 dicomNetworkAE = 265, // dicomNetworkAE
00767 dicomNetworkConnection = 266, // dicomNetworkConnection
00768 dicomUniqueAETitle = 267, // dicomUniqueAETitle
00769 dicomTransferCapability = 268, // dicomTransferCapability
00770 //
00771 VLWholeSlideMicroscopyImageStorage = 269,
00772 EnhancedUSVolumeStorage = 270,
00773 SurfaceSegmentationStorage = 271,
00774 BreastTomosynthesisImageStorage = 272,
00775 LegacyConvertedEnhancedCTImageStorage = 273,
00776 LegacyConvertedEnhancedMRImageStorage = 274,
00777 LegacyConvertedEnhancedPETImageStorage = 275,
00778 MPEG2MainProfileHighLevel = 276,
00779 MPEG4AVCH_264HighProfileLevel4_1 = 277,
00780 MPEG4AVCH_264BDcompatibleHighProfileLevel4_1 = 278,
00781
00783 //
00784 // 2019b
00785 //
00786 PETColorPaletteSOPInstance = 279,
00787 HotMetalBlueColorPaletteSOPInstance = 280,
00788 PET20StepColorPaletteSOPInstance = 281,
00789 SpringColorPaletteSOPInstance = 282,
00790 SummerColorPaletteSOPInstance = 283,
00791 FallColorPaletteSOPInstance = 284,
00792 WinterColorPaletteSOPInstance = 285,
00793 Papyrus3ImplicitVRLittleEndian = 286,
00794 AdultMouseAnatomyOntology = 287,
00795 UberonOntology = 288,
00796 IntegratedTaxonomicInformationSystemITISTaxonomicSerialNumberTSN = 289,
00797 MouseGenomeInitiativeMGI = 290,
00798 PubChemCompoundCID = 291,
00799 ICD11 = 292,
00800 NewYorkUniversityMelanomaClinicalCooperativeGroup = 293,
00801 MayoClinicNonradiologicalImagesSBSAnatomicalSurfaceRegionGuide = 294,
00802 ImageBiomarkerStandardisationInitiative = 295,
00803 RadiomicsOntology = 296,
00804 DisplaySystemSOPClass = 297,
00805 DisplaySystemSOPInstance = 298,
00806 GeneralAudioWaveformStorage = 299,
00807 ArterialPulseWaveformStorage = 300,
00808 RespiratoryWaveformStorage = 301,
00809 XAXRFGrayscaleSoftcopyPresentationStateStorage = 302,
00810 GrayscalePlanarMPRVolumetricPresentationStateStorage = 303,
00811 MPEG4AVCH_264HighProfileLevel4_2For2DVideo = 304,
00812 MPEG4AVCH_264HighProfileLevel4_2For3DVideo = 305,
00813 MPEG4AVCH_264StereoHighProfileLevel4_2 = 306,
00814 HEVCH_265MainProfileLevel5_1 = 307,
00815 HEVCH_265Main10ProfileLevel5_1 = 308,
00816 HotIronColorPaletteSOPInstance = 309,
00817 CompositingPlanarMPRVolumetricPresentationStateStorage = 310,
00818 AdvancedBlendingPresentationStateStorage = 311,
00819 VolumeRenderingVolumetricPresentationStateStorage = 312,
00820 SegmentedVolumeRenderingVolumetricPresentationStateStorage = 313,
00821 MultipleVolumeRenderingVolumetricPresentationStateStorage = 314,
00822 Null0 = 315,
00823 BreastProjectionXRayImageStorageForPresentation = 316,
00824 BreastProjectionXRayImageStorageForProcessing = 317,
00825 IntravascularOpticalCoherenceTomographyImageStorageForPresentation = 318,
00826 IntravascularOpticalCoherenceTomographyImageStorageForProcessing = 319,
00827 ParametricMapStorage = 320,
00828 Null1 = 321,
00829 TractographyResultsStorage = 322,
00830 SurfaceScanMeshStorage = 323,
00831 SurfaceScanPointCloudStorage = 324,
00832 WideFieldOphthalmicPhotographyStereographicProjectionImageStorage = 325,
00833 WideFieldOphthalmicPhotography3DCoordinatesImageStorage = 326,
00834 OphthalmicOpticalCoherenceTomographyEnFaceImageStorage = 327,
00835 OphthalmicOpticalCoherenceTomographyBscanVolumeAnalysisStorage = 328,
```

00836	LensometryMeasurementsStorage	= 329,
00837	AutorefractometryMeasurementsStorage	= 330,
00838	KeratometryMeasurementsStorage	= 331,
00839	SubjectiveRefractionMeasurementsStorage	= 332,
00840	VisualAcuityMeasurementsStorage	= 333,
00841	SpectaclePrescriptionReportStorage	= 334,
00842	OphthalmicAxialMeasurementsStorage	= 335,
00843	IntraocularLensCalculationsStorage	= 336,
00844	MacularGridThicknessandVolumeReportStorage	= 337,
00845	OphthalmicVisualFieldStaticPerimetryMeasurementsStorage	= 338,
00846	OphthalmicThicknessMapStorage	= 339,
00847	CornealTopographyMapStorage	= 340,
00848	Comprehensive3DSRStorage	= 341,
00849	ExtensibleSRStorage	= 342,
00850	RadiopharmaceuticalRadiationDoseSRStorage	= 343,
00851	ColonCADSRStorage	= 344,
00852	ImplantationPlanSRStorage	= 345,
00853	AcquisitionContextSRStorage	= 346,
00854	SimplifiedAdultEchoSRStorage	= 347,
00855	PatientRadiationDoseSRStorage	= 348,
00856	PlannedImagingAgentAdministrationSRStorage	= 349,
00857	PerformedImagingAgentAdministrationSRStorage	= 350,
00858	ContentAssessmentResultsStorage	= 351,
00859	EncapsulatedSTLStorage	= 352,
00860	EnhancedPETImageStorage	= 353,
00861	BasicStructuredDisplayStorage	= 354,
00862	CTDefinedProcedureProtocolStorage	= 355,
00863	CTPerformedProcedureProtocolStorage	= 356,
00864	ProtocolApprovalStorage	= 357,
00865	ProtocolApprovalInformationModelFIND	= 358,
00866	ProtocolApprovalInformationModelMOVE	= 359,
00867	ProtocolApprovalInformationModelGET	= 360,
00868	RTPhysicianIntentStorage	= 361,
00869	RTSegmentAnnotationStorage	= 362,
00870	DICOSCTImageStorage	= 363,
00871	DICOSDigitalXRayImageStorageForPresentation	= 364,
00872	DICOSDigitalXRayImageStorageForProcessing	= 365,
00873	DICOSThreatDetectionReportStorage	= 366,
00874	DICOS2DAITStorage	= 367,
00875	DICOS3DAITStorage	= 368,
00876	DICOSQuadrupoleResonanceQRStorage	= 369,
00877	EddyCurrentImageStorage	= 370,
00878	EddyCurrentMultiframeImageStorage	= 371,
00879	CompositeInstanceRootRetrieveMOVE	= 372,
00880	CompositeInstanceRootRetrieveGET	= 373,
00881	CompositeInstanceRetrieveWithoutBulkDataGET	= 374,
00882	DefinedProcedureProtocolInformationModelFIND	= 375,
00883	DefinedProcedureProtocolInformationModelMOVE	= 376,
00884	DefinedProcedureProtocolInformationModelGET	= 377,
00885	UPSFilteredGlobalSubscriptionSOPInstance	= 378,
00886	UnifiedWorklistandProcedureStepServiceClass1	= 379,
00887	UnifiedProcedureStepPushSOPClass1	= 380,
00888	UnifiedProcedureStepWatchSOPClass1	= 381,
00889	UnifiedProcedureStepPullSOPClass1	= 382,
00890	UnifiedProcedureStepEventSOPClass1	= 383,
00891	RTBeamsDeliveryInstructionStorage	= 384,
00892	RTConventionalMachineVerification	= 385,
00893	RTIonMachineVerification	= 386,
00894	RTBrachyApplicationSetupDeliveryInstructionStorage	= 387,
00895	HangingProtocolInformationModelGET	= 388,
00896	ColorPaletteStorage	= 389,
00897	ColorPaletteQueryRetrieveInformationModelFIND	= 390,
00898	ColorPaletteQueryRetrieveInformationModelMOVE	= 391,
00899	ColorPaletteQueryRetrieveInformationModelGET	= 392,
00900	GenericImplantTemplateStorage	= 393,
00901	GenericImplantTemplateInformationModelFIND	= 394,
00902	GenericImplantTemplateInformationModelMOVE	= 395,
00903	GenericImplantTemplateInformationModelGET	= 396,
00904	ImplantAssemblyTemplateStorage	= 397,
00905	ImplantAssemblyTemplateInformationModelFIND	= 398,
00906	ImplantAssemblyTemplateInformationModelMOVE	= 399,
00907	ImplantAssemblyTemplateInformationModelGET	= 400,
00908	ImplantTemplateGroupStorage	= 401,
00909	ImplantTemplateGroupInformationModelFIND	= 402,
00910	ImplantTemplateGroupInformationModelMOVE	= 403,
00911	ImplantTemplateGroupInformationModelGET	= 404,
00912	NativeDICOMModel	= 405,
00913	AbstractMultiDimensionalImageModel	= 406,
00914	DICOMContentMappingResource	= 407,
00915	EnhancedMRColorImageStorage	= 408,
00916	UniversalCoordinatedTime	= 409

```

00917 //
00918 //
00920
00922 //
00923 // Optionally private UIDs
00924 //
00925 #if 0
00926 Private_1_2_840_113619_4_2,
00927 Private_1_2_840_113619_4_3,
00928 Private_1_3_12_2_1107_5_9_1,
00929 Private_1_2_840_113619_4_26,
00930 Private_1_2_840_113619_4_30,
00931 Private_2_16_840_1_113709_1_5_1,
00932 Private_2_16_840_1_113709_1_2_2,
00933 Private_1_2_840_113543_6_6_1_3_10002,
00934 Private_1_2_392_200036_9116_7_8_1_1_1,
00935 Private_1_2_392_200036_9125_1_1_2,
00936 Private_1_2_840_113619_4_27,
00937 Private_1_3_46_670589_11_0_0_12_1,
00938 Private_1_3_46_670589_11_0_0_12_2,
00939 Private_1_3_46_670589_11_0_0_12_4,
00940 Private_1_3_46_670589_2_3_1_1,
00941 Private_1_3_46_670589_2_4_1_1,
00942 Private_1_3_46_670589_2_5_1_1,
00943 Private_1_3_46_670589_5_0_1,
00944 Private_1_3_46_670589_5_0_1_1,
00945 Private_1_3_46_670589_5_0_10,
00946 Private_1_3_46_670589_5_0_11,
00947 Private_1_3_46_670589_5_0_11_1,
00948 Private_1_3_46_670589_5_0_12,
00949 Private_1_3_46_670589_5_0_13,
00950 Private_1_3_46_670589_5_0_14,
00951 Private_1_3_46_670589_5_0_2,
00952 Private_1_3_46_670589_5_0_2_1,
00953 Private_1_3_46_670589_5_0_3,
00954 Private_1_3_46_670589_5_0_3_1,
00955 Private_1_3_46_670589_5_0_4,
00956 Private_1_3_46_670589_5_0_7,
00957 Private_1_3_46_670589_5_0_8,
00958 Private_1_3_46_670589_5_0_9,
00959 Private_1_2_752_24_3_7_6,
00960 Private_1_2_752_24_3_7_7,
00961 Private_1_2_840_113619_5_2,
00962 Private_1_3_46_670589_33_1_4_1
00963 #endif
00964 //
00965 //
00967
00968 } TSName;
00969
00970
00971 typedef const char* const (*TransferSyntaxStringsType)[2];
00972 static TransferSyntaxStringsType GetTransferSyntaxStrings();
00973 static const char * const *GetTransferSyntaxString(unsigned int ts);
00974 static unsigned int GetNumberOfTransferSyntaxStrings();
00975
00976
00977 // TODO: Because I would like a dual signature for TSType and TSName, C++ won't let me do it...
00978 static const char* GetUIDString(/*TSType*/ unsigned int ts);
00979 static const char* GetUIDName(/*TSType*/ unsigned int ts);
00980
00981 bool SetFromUID(const char *str);
00982
00983 const char *GetName() const;
00984
00985 const char *GetString() const;
00986
00987 operator TSType () const { return TSField; }
00988 UIDs() = default;
00989
00990 private:
00991     TSType TSField;
00992 };
00993 //-----
01000 inline std::ostream &operator<<(std::ostream &_os, const UIDs &uid)
01001 {
01002     _os << uid.GetString() << " -> " << uid.GetName();
01003     return _os;
01004 }
01005 }
01006

```

```

01007 } // end namespace gdcm
01008
01009 #endif //GDCMUIDS_H

```


11.109 gdcmAttribute.h File Reference

```


#include "gdcmTypes.h"
#include "gdcmVR.h"
#include "gdcmTagToType.h"
#include "gdcmVM.h"
#include "gdcmElement.h"
#include "gdcmDataElement.h"
#include "gdcmDataSet.h"
#include "gdcmStaticAssert.h"
#include <string>
#include <vector>
#include <sstream>

```

Include dependency graph for gdcmAttribute.h:



This graph shows which files directly or indirectly include this file:



Classes

- class `gdcm::Attribute< Group, Element, TVR, TVM >`
Attribute class This class use template metaprograming tricks to let the user know when the template instantiation does not match the public dictionary.
- class `gdcm::Attribute< Group, Element, TVR, VM::VM1 >`
- class `gdcm::Attribute< Group, Element, TVR, VM::VM1_3 >`
- class `gdcm::Attribute< Group, Element, TVR, VM::VM1_8 >`
- class `gdcm::Attribute< Group, Element, TVR, VM::VM1_n >`
- class `gdcm::Attribute< Group, Element, TVR, VM::VM2_2n >`
- class `gdcm::Attribute< Group, Element, TVR, VM::VM2_n >`
- class `gdcm::Attribute< Group, Element, TVR, VM::VM3_3n >`
- class `gdcm::Attribute< Group, Element, TVR, VM::VM3_n >`
- class `gdcm::VRVLSize< 0 >`
- class `gdcm::VRVLSize< 1 >`

Namespaces

- namespace `gdcm`

11.110 gdcmAttribute.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMATATTRIBUTE_H
00015 #define GDCMATATTRIBUTE_H
00016
00017 #include "gdcmTypes.h"
00018 #include "gdcmVR.h"
00019 #include "gdcmTagToType.h"
00020 #include "gdcmVM.h"
00021 #include "gdcmElement.h"
00022 #include "gdcmDataElement.h"
00023 #include "gdcmDataSet.h"
00024 #include "gdcmStaticAssert.h"
00025
00026 #include <string>
00027 #include <vector>
00028 #include <sstream>
00029
00030 namespace gdcm_ns
00031 {
00032
00033   struct void_;
00034
00035   // Declaration, also serve as forward declaration
00036   template<int T> class VRVLSize;
00037
00038   // Implementation when VL is coded on 16 bits:
00039   template<> class VRVLSize<0> {

```

```

00040 public:
00041     static inline uint16_t Read(std::istream &_is) {
00042         uint16_t l;
00043         _is.read((char*)&l, 2);
00044         return l;
00045     }
00046
00047     static inline void Write(std::ostream &os) { (void)os;
00048     }
00049 };
00050 // Implementation when VL is coded on 32 bits:
00051 template<> class VRVLSize<1> {
00052 public:
00053     static inline uint32_t Read(std::istream &_is) {
00054         char dummy[2];
00055         _is.read(dummy, 2);
00056
00057         uint32_t l;
00058         _is.read((char*)&l, 4);
00059         return l;
00060     }
00061
00062     static inline void Write(std::ostream &os) { (void)os;
00063     }
00064 };
00065
00081 template<uint16_t Group, uint16_t Element,
00082         long long TVR = TagToType<Group, Element>::VRType, // can the user override this value ?
00083         int TVM = TagToType<Group, Element>::VMType // can the user override this value ?
00084         /*typename SQAttribute = void*/ > // if only I had variadic template...
00085 class Attribute
00086 {
00087 public:
00088     typedef typename VRToType<TVR>::Type ArrayType;
00089     enum { VMType = VMToLength<TVM>::Length };
00090     ArrayType Internal[VMToLength<TVM>::Length];
00091
00092     // Make sure that user specified VR/VM are compatible with the public dictionary:
00093     GDCM_STATIC_ASSERT( ((VR::VRType)TVR & (VR::VRType)(TagToType<Group, Element>::VRType)) );
00094     GDCM_STATIC_ASSERT( ((VM::VMType)TVM & (VM::VMType)(TagToType<Group, Element>::VMType)) );
00095     GDCM_STATIC_ASSERT( (((VR::VRType)TVR & VR::VR_VM1) && ((VM::VMType)TVM == VM::VM1) )
00096         || !((VR::VRType)TVR & VR::VR_VM1) );
00097
00098     static Tag GetTag() { return Tag(Group,Element); }
00099     static VR GetVR() { return (VR::VRType)TVR; }
00100     static VM GetVM() { return (VM::VMType)TVM; }
00101
00102     // The following two methods do make sense only in case of public element,
00103     // when the template is intanciated with private element the VR/VM are simply
00104     // defaulted to allow everything (see gdcmtagToType.h default template for TagToType)
00105     static VR GetDictVR() { return (VR::VRType)(TagToType<Group, Element>::VRType); }
00106     static VM GetDictVM() { return (VM::VMType)(TagToType<Group, Element>::VMType); }
00107
00108     // Some extra dummy checks:
00109     // Data Elements with a VR of SQ, OF, OW, OB or UN shall always have a Value Multiplicity of one.
00110
00111     unsigned int GetNumberOfValues() const {
00112         return VMToLength<TVM>::Length;
00113     }
00114     // Implementation of Print is common to all Mode (ASCII/Binary)
00115     // TODO: Can we print a \ when in ASCII...well I don't think so
00116     // it would mean we used a bad VM then, right ?
00117     void Print(std::ostream &os) const {
00118         os << GetTag() << " ";
00119         os << TagToType<Group,Element>::GetVRString() << " ";
00120         os << TagToType<Group,Element>::GetVMString() << " ";
00121         os << Internal[0]; // VM is at least guarantee to be one
00122         for(unsigned int i=1; i<GetNumberOfValues(); ++i)
00123             os << "," << Internal[i];
00124     }
00125
00126     // copy:
00127     //ArrayType GetValue(unsigned int idx = 0) {
00128     //    gdcmt_assert( idx < GetNumberOfValues() );
00129     //    return Internal[idx];
00130     //}
00131     //ArrayType operator[] (unsigned int idx) {
00132     //    return GetValue(idx);
00133     //}
00134     // FIXME: is this always a good idea ?
00135     // I do not think so, I prefer operator

```

```

00136 //operator ArrayType () const { return Internal[0]; }
00137
00138 bool operator==(const Attribute &att) const
00139 {
00140     return std::equal(Internal, Internal+GetNumberOfValues(),
00141         att.GetValues());
00142 }
00143 bool operator!=(const Attribute &att) const
00144 {
00145     return !std::equal(Internal, Internal+GetNumberOfValues(),
00146         att.GetValues());
00147 }
00148 bool operator<(const Attribute &att) const
00149 {
00150     return std::lexicographical_compare(Internal, Internal+GetNumberOfValues(),
00151         att.GetValues(), att.GetValues() + att.GetNumberOfValues() );
00152 }
00153
00154 ArrayType &GetValue(unsigned int idx = 0) {
00155     gdcm_assert( idx < GetNumberOfValues() );
00156     return Internal[idx];
00157 }
00158 ArrayType & operator[] (unsigned int idx) {
00159     return GetValue(idx);
00160 }
00161 // const reference
00162 ArrayType const &GetValue(unsigned int idx = 0) const {
00163     gdcm_assert( idx < GetNumberOfValues() );
00164     return Internal[idx];
00165 }
00166 ArrayType const & operator[] (unsigned int idx) const {
00167     return GetValue(idx);
00168 }
00169 void SetValue(ArrayType v, unsigned int idx = 0) {
00170     gdcm_assert( idx < GetNumberOfValues() );
00171     Internal[idx] = v;
00172 }
00173 void SetValues(const ArrayType* array, unsigned int numel = VMType ) {
00174     gdcm_assert( array && numel && numel == GetNumberOfValues() );
00175     // std::copy is smarter than a memcpy, and will call memcpy when POD type
00176     std::copy(array, array+numel, Internal);
00177 }
00178 const ArrayType* GetValues() const {
00179     return Internal;
00180 }
00181
00182 // API to talk to the run-time layer: gdcm::DataElement
00183 DataElement GetAsDataElement() const {
00184     DataElement ret( GetTag() );
00185     std::ostringstream os;
00186     // os.imbue(std::locale::classic()); // This is not required AFAIK
00187     EncodingImplementation<VRToEncoding<TVR>::Mode>::Write(Internal,
00188         GetNumberOfValues(), os);
00189     ret.SetVR( GetVR() );
00190     gdcm_assert( ret.GetVR() != VR::SQ );
00191     if( (VR::VRType)VRToEncoding<TVR>::Mode == VR::VRASCII )
00192     {
00193         if( GetVR() != VR::UI )
00194         {
00195             if( os.str().size() % 2 )
00196             {
00197                 os << " ";
00198             }
00199         }
00200     }
00201     VL::Type osStrSize = (VL::Type)os.str().size();
00202     ret.SetByteValue( os.str().c_str(), osStrSize );
00203     return ret;
00204 }
00205
00206 void SetFromDataElement(DataElement const &de) {
00207     // This is kind of hackish but since I do not generate other element than the first one: 0x6000 I
    should be ok:
00208     gdcm_assert( Tag(Group,Element) == de.GetTag() || Group == 0x6000 || Group == 0x5000 );
00209     gdcm_assert( GetVR() != VR::INVALID );
00210     gdcm_assert( GetVR().Compatible( de.GetVR() ) || de.GetVR() == VR::INVALID ); // In case of
    VR::INVALID cannot use the & operator
00211     if( de.IsEmpty() ) return;
00212     const ByteValue *bv = de.GetByteValue();
00213 #ifdef GDCM_WORDS_BIGENDIAN
00214     if( de.GetVR() == VR::UN /*|| de.GetVR() == VR::INVALID*/ )

```

```

00215 #else
00216     if( de.GetVR() == VR::UN || de.GetVR() == VR::INVALID )
00217 #endif
00218     {
00219         SetByteValue(bv);
00220     }
00221     else
00222     {
00223         SetByteValueNoSwap(bv);
00224     }
00225 }
00226 void Set(DataSet const &ds) {
00227     SetFromDataElement( ds.GetDataElement( Tag(Group,Element) ) );
00228 }
00229 void SetFromDataSet(DataSet const &ds) {
00230     if( ds.FindDataElement( Tag(Group,Element) ) &&
00231         !ds.GetDataElement( Tag(Group,Element) ).IsEmpty() )
00232     {
00233         SetFromDataElement( ds.GetDataElement( Tag(Group,Element) ) );
00234     }
00235 }
00236 protected:
00237 void SetByteValueNoSwap(const ByteValue *bv) {
00238     if( !bv ) return; // That would be bad...
00239     gdcm_assert( bv->GetPointer() && bv->GetLength() ); // [123]C element can be empty
00240     //if( VRToEncoding<TVR>::Mode == VR::VRBINARY )
00241     // {
00242     // // always do a copy !
00243     // SetValues(bv->GetPointer(), bv->GetLength());
00244     // }
00245     //else
00246     {
00247         std::stringstream ss;
00248         std::string s = std::string( bv->GetPointer(), bv->GetLength() );
00249         ss.str( s );
00250         EncodingImplementation<VRToEncoding<TVR>::Mode>::ReadNoSwap(Internal,
00251             GetNumberOfValues(),ss);
00252     }
00253 }
00254 void SetByteValue(const ByteValue *bv) {
00255     if( !bv ) return; // That would be bad...
00256     gdcm_assert( bv->GetPointer() && bv->GetLength() ); // [123]C element can be empty
00257     //if( VRToEncoding<TVR>::Mode == VR::VRBINARY )
00258     // {
00259     // // always do a copy !
00260     // SetValues(bv->GetPointer(), bv->GetLength());
00261     // }
00262     //else
00263     {
00264         std::stringstream ss;
00265         std::string s = std::string( bv->GetPointer(), bv->GetLength() );
00266         ss.str( s );
00267         EncodingImplementation<VRToEncoding<TVR>::Mode>::Read(Internal,
00268             GetNumberOfValues(),ss);
00269     }
00270 }
00271 #if 0 // TODO FIXME the implicit way:
00272 // explicit:
00273 void Read(std::istream &_is) {
00274     const uint16_t cref[] = { Group, Element };
00275     uint16_t c[2];
00276     _is.read((char*)&c, sizeof(c));
00277     gdcm_assert( c[0] == cref[0] && c[1] == cref[1] );
00278     char vr[2];
00279     _is.read(vr, 2); // Check consistency ?
00280     const uint32_t lref = GetLength() * sizeof( typename VRToType<TVR>::Type );
00281     uint32_t l = VRVLSize< (TVR & VR::VL32) >::Read(_is);
00282     l /= sizeof( typename VRToType<TVR>::Type );
00283     return EncodingImplementation<VRToEncoding<TVR>::Mode>::Read(Internal,
00284         l,_is);
00285 }
00286 void Write(std::ostream &_os) const {
00287     uint16_t c[] = { Group, Element };
00288     _os.write((char*)&c, 4);
00289     uint32_t l = GetLength() * sizeof( typename VRToType<TVR>::Type );
00290     _os.write((char*)&l, 4);
00291     return EncodingImplementation<VRToEncoding<TVR>::Mode>::Write(Internal,
00292         GetLength(),_os);
00293 }
00294 void Read(std::istream &_is) {
00295     uint16_t cref[] = { Group, Element };

```



```

00296     uint16_t c[2];
00297     _is.read((char*)&c, 4);
00298     const uint32_t lref = GetLength() * sizeof( typename VRToType<TVR>::Type );
00299     uint32_t l;
00300     _is.read((char*)&l, 4);
00301     l /= sizeof( typename VRToType<TVR>::Type );
00302     return EncodingImplementation<VRToEncoding<TVR>::Mode>::Read(Internal,
00303         l,_is);
00304 }
00305 void Write(std::ostream &_os) const {
00306     uint16_t c[] = { Group, Element };
00307     _os.write((char*)&c, 4);
00308     uint32_t l = GetLength() * sizeof( typename VRToType<TVR>::Type );
00309     _os.write((char*)&l, 4);
00310     return EncodingImplementation<VRToEncoding<TVR>::Mode>::Write(Internal,
00311         GetLength(),_os);
00312 }
00313 #endif
00314 };
00315 };
00316
00317 template<uint16_t Group, uint16_t Element, long long TVR >
00318 class Attribute<Group,Element,TVR,VM::VM1>
00319 {
00320 public:
00321     typedef typename VRToType<TVR>::Type ArrayType;
00322     enum { VMType = VMToLength<VM::VM1>::Length };
00323     //ArrayType Internal[VMToLength<TVM>::Length];
00324     ArrayType Internal;
00325     GDCM_STATIC_ASSERT( VMToLength<VM::VM1>::Length == 1 );
00326
00327     // Make sure that user specified VR/VM are compatible with the public dictionary:
00328     GDCM_STATIC_ASSERT( ((VR::VRType)TVR & (VR::VRType)(TagToType<Group, Element>::VRType)) );
00329     GDCM_STATIC_ASSERT( ((VM::VMType)VM::VM1 & (VM::VMType)(TagToType<Group, Element>::VMType)) );
00330     GDCM_STATIC_ASSERT( (((VR::VRType)TVR & VR::VR_VM1) && ((VM::VMType)VM::VM1 == VM::VM1) )
00331         || !((VR::VRType)TVR & VR::VR_VM1) );
00332
00333     static Tag GetTag() { return Tag(Group,Element); }
00334     static VR GetVR() { return (VR::VRType)TVR; }
00335     static VM GetVM() { return (VM::VMType)VM::VM1; }
00336
00337     // The following two methods do make sense only in case of public element,
00338     // when the template is intanciated with private element the VR/VM are simply
00339     // defaulted to allow everything (see gdcmTagToType.h default template for TagToType)
00340     static VR GetDictVR() { return (VR::VRType)(TagToType<Group, Element>::VRType); }
00341     static VM GetDictVM() { return (VM::VMType)(TagToType<Group, Element>::VMType); }
00342
00343     // Some extra dummy checks:
00344     // Data Elements with a VR of SQ, OF, OW, OB or UN shall always have a Value Multiplicity of one.
00345
00346     unsigned int GetNumberOfValues() const {
00347         return VMToLength<VM::VM1>::Length;
00348     }
00349     // Implementation of Print is common to all Mode (ASCII/Binary)
00350     // TODO: Can we print a \ when in ASCII...well I don't think so
00351     // it would mean we used a bad VM then, right ?
00352     void Print(std::ostream &os) const {
00353         os << GetTag() << " ";
00354         os << TagToType<Group,Element>::GetVRString() << " ";
00355         os << TagToType<Group,Element>::GetVMString() << " ";
00356         os << Internal; // VM is at least guarantee to be one
00357     }
00358     // copy:
00359     //ArrayType GetValue(unsigned int idx = 0) {
00360     //    gdcm_assert( idx < GetNumberOfValues() );
00361     //    return Internal[idx];
00362     //}
00363     //ArrayType operator[] (unsigned int idx) {
00364     //    return GetValue(idx);
00365     //}
00366     // FIXME: is this always a good idea ?
00367     // I do not think so, I prefer operator
00368     //operator ArrayType () const { return Internal[0]; }
00369
00370     bool operator==(const Attribute &att) const
00371     {
00372         return std::equal(&Internal, &Internal+GetNumberOfValues(),
00373             att.GetValues());
00374     }
00375     bool operator!=(const Attribute &att) const
00376     {

```

```

00377     return !std::equal(&Internal, &Internal+GetNumberOfValues(),
00378         att.GetValues());
00379     }
00380     bool operator<(const Attribute &att) const
00381     {
00382         return std::lexicographical_compare(&Internal, &Internal+GetNumberOfValues(),
00383             att.GetValues(), att.GetValues() + att.GetNumberOfValues() );
00384     }
00385
00386     ArrayType &GetValue() {
00387         // gdcmm_assert( idx < GetNumberOfValues() );
00388         return Internal;
00389     }
00390     // ArrayType & operator[] (unsigned int idx) {
00391     //     return GetValue(idx);
00392     // }
00393     // const reference
00394     ArrayType const &GetValue() const {
00395         //gdcmm_assert( idx < GetNumberOfValues() );
00396         return Internal;
00397     }
00398     //ArrayType const & operator[] () const {
00399     //     return GetValue();
00400     //}
00401     void SetValue(ArrayType v) {
00402         // gdcmm_assert( idx < GetNumberOfValues() );
00403         Internal = v;
00404     }
00405     /* void SetValues(const ArrayType* array, unsigned int numel = VMType ) {
00406         gdcmm_assert( array && numel && numel == GetNumberOfValues() );
00407         // std::copy is smarter than a memcpy, and will call memcpy when POD type
00408         std::copy(array, array+numel, Internal);
00409     }
00410     */
00411
00412     // FIXME Should we remove this function ?
00413     const ArrayType* GetValues() const {
00414         return &Internal;
00415     }
00416
00417     // API to talk to the run-time layer: gdcmm::DataElement
00418     DataElement GetAsDataElement() const {
00419         DataElement ret( Tag(Group,Element) );
00420         std::ostream os;
00421         // os.imbue(std::locale::classic()); // This is not required AFAIK
00422         EncodingImplementation<VRToEncoding<TVR>::Mode>::Write(&Internal,
00423             GetNumberOfValues(),os);
00424         ret.SetVR( GetVR() );
00425         gdcmm_assert( ret.GetVR() != VR::SQ );
00426         if( (VR::VRType)VRToEncoding<TVR>::Mode == VR::VRASCII )
00427         {
00428             if( GetVR() != VR::UI )
00429             {
00430                 if( os.str().size() % 2 )
00431                 {
00432                     os << " ";
00433                 }
00434             }
00435         }
00436         VL::Type osStrSize = (VL::Type)os.str().size();
00437         ret.SetByteValue( os.str().c_str(), osStrSize );
00438         return ret;
00439     }
00440
00441     void SetFromDataElement(DataElement const &de) {
00442         // This is kind of hackish but since I do not generate other element than the first one: 0x6000 I
00443         // should be ok:
00444         gdcmm_assert( Tag(Group,Element) == de.GetTag() || Group == 0x6000 || Group == 0x5000 );
00445         gdcmm_assert( GetVR() != VR::INVALID );
00446         gdcmm_assert( GetVR().Compatible( de.GetVR() ) || de.GetVR() == VR::INVALID ); // In case of
00447         VR::INVALID cannot use the & operator
00448         if( de.IsEmpty() ) return;
00449         const ByteValue *bv = de.GetByteValue();
00450         #ifdef GDCM_WORDS_BIGENDIAN
00451         if( de.GetVR() == VR::UN /*|| de.GetVR() == VR::INVALID*/ )
00452         #else
00453         if( de.GetVR() == VR::UN || de.GetVR() == VR::INVALID )
00454         #endif
00455         {
00456             SetByteValue(bv);
00457         }

```

```

00456     else
00457     {
00458         SetByteValueNoSwap(bv);
00459     }
00460 }
00461 void Set(DataSet const &ds) {
00462     SetFromDataElement( ds.GetDataElement( Tag(Group,Element) ) );
00463 }
00464 void SetFromDataSet(DataSet const &ds) {
00465     if( ds.FindDataElement( Tag(Group,Element) ) &&
00466         !ds.GetDataElement( Tag(Group,Element) ).IsEmpty() )
00467     {
00468         SetFromDataElement( ds.GetDataElement( Tag(Group,Element) ) );
00469     }
00470 }
00471 protected:
00472 void SetByteValueNoSwap(const ByteValue *bv) {
00473     if( !bv ) return; // That would be bad...
00474     gdcm_assert( bv->GetPointer() && bv->GetLength() ); // [123]C element can be empty
00475     //if( VRToEncoding<TVR>::Mode == VR::VRBINARY )
00476     // {
00477     //     // always do a copy !
00478     //     SetValues(bv->GetPointer(), bv->GetLength());
00479     // }
00480     //else
00481     {
00482         std::stringstream ss;
00483         std::string s = std::string( bv->GetPointer(), bv->GetLength() );
00484         ss.str( s );
00485         EncodingImplementation<VRToEncoding<TVR>::Mode>::ReadNoSwap(&Internal,
00486             GetNumberOfValues(),ss);
00487     }
00488 }
00489 void SetByteValue(const ByteValue *bv) {
00490     if( !bv ) return; // That would be bad...
00491     gdcm_assert( bv->GetPointer() && bv->GetLength() ); // [123]C element can be empty
00492     //if( VRToEncoding<TVR>::Mode == VR::VRBINARY )
00493     // {
00494     //     // always do a copy !
00495     //     SetValues(bv->GetPointer(), bv->GetLength());
00496     // }
00497     //else
00498     {
00499         std::stringstream ss;
00500         std::string s = std::string( bv->GetPointer(), bv->GetLength() );
00501         ss.str( s );
00502         EncodingImplementation<VRToEncoding<TVR>::Mode>::Read(&Internal,
00503             GetNumberOfValues(),ss);
00504     }
00505 }
00506 #if 0 // TODO FIXME the implicit way:
00507 // explicit:
00508 void Read(std::istream &_is) {
00509     const uint16_t cref[] = { Group, Element };
00510     uint16_t c[2];
00511     _is.read((char*)&c, sizeof(c));
00512     gdcm_assert( c[0] == cref[0] && c[1] == cref[1] );
00513     char vr[2];
00514     _is.read(vr, 2); // Check consistency ?
00515     const uint32_t lref = GetLength() * sizeof( typename VRToType<TVR>::Type );
00516     uint32_t l = VRVLSize< (TVR & VR::VL32) >::Read(_is);
00517     l /= sizeof( typename VRToType<TVR>::Type );
00518     return EncodingImplementation<VRToEncoding<TVR>::Mode>::Read(Internal,
00519         l,_is);
00520 }
00521 void Write(std::ostream &_os) const {
00522     uint16_t c[] = { Group, Element };
00523     _os.write((char*)&c, 4);
00524     uint32_t l = GetLength() * sizeof( typename VRToType<TVR>::Type );
00525     _os.write((char*)&l, 4);
00526     return EncodingImplementation<VRToEncoding<TVR>::Mode>::Write(Internal,
00527         GetLength(),_os);
00528 }
00529 void Read(std::istream &_is) {
00530     uint16_t cref[] = { Group, Element };
00531     uint16_t c[2];
00532     _is.read((char*)&c, 4);
00533     const uint32_t lref = GetLength() * sizeof( typename VRToType<TVR>::Type );
00534     uint32_t l;
00535     _is.read((char*)&l, 4);
00536     l /= sizeof( typename VRToType<TVR>::Type );

```

```

00537         return EncodingImplementation<VRToEncoding<TVR>::Mode>::Read(Internal,
00538             l,_is);
00539     }
00540     void Write(std::ostream &_os) const {
00541         uint16_t c[] = { Group, Element };
00542         _os.write((char*)&c, 4);
00543         uint32_t l = GetLength() * sizeof( typename VRToType<TVR>::Type );
00544         _os.write((char*)&l, 4);
00545         return EncodingImplementation<VRToEncoding<TVR>::Mode>::Write(Internal,
00546             GetLength(),_os);
00547     }
00548 #endif
00549 };
00550 };
00551
00552 // No need to repeat default template arg, since primary template
00553 // will be used to generate the default arguments
00554 template<uint16_t Group, uint16_t Element, long long TVR >
00555 class Attribute<Group,Element,TVR,VM::VM1_n>
00556 {
00557 public:
00558     typedef typename VRToType<TVR>::Type ArrayType;
00559
00560     // Make sure that user specified VR/VM are compatible with the public dictionary:
00561     GDCM_STATIC_ASSERT( ((VR::VRType)TVR & (VR::VRType)(TagToType<Group, Element>::VRType)) );
00562     GDCM_STATIC_ASSERT( (VM::VM1_n & (VM::VMType)(TagToType<Group, Element>::VMType)) );
00563     GDCM_STATIC_ASSERT( (((VR::VRType)TVR & VR::VR_VM1) && ((VM::VMType)TagToType<Group,Element>::VMType ==
VM::VM1) )
00564         || !((VR::VRType)TVR & VR::VR_VM1) ) );
00565
00566     static Tag GetTag() { return Tag(Group,Element); }
00567     static VR GetVR() { return (VR::VRType)TVR; }
00568     static VM GetVM() { return VM::VM1_n; }
00569
00570     static VR GetDictVR() { return (VR::VRType)(TagToType<Group, Element>::VRType); }
00571     static VM GetDictVM() { return GetVM(); }
00572
00573     // This the way to prevent default initialization
00574     explicit Attribute() { Internal=nullptr; Length=0; Own = true; }
00575     ~Attribute() {
00576         if( Own ) {
00577             delete[] Internal;
00578         }
00579         Internal = nullptr; // paranoid
00580     }
00581
00582     unsigned int GetNumberOfValues() const { return Length; }
00583
00584     void SetNumberOfValues(unsigned int numel)
00585     {
00586         SetValues(nullptr, numel, true);
00587     }
00588
00589     const ArrayType* GetValues() const {
00590         return Internal;
00591     }
00592     void Print(std::ostream &os) const {
00593         os << GetTag() << " ";
00594         os << GetVR() << " ";
00595         os << GetVM() << " ";
00596         os << Internal[0]; // VM is at least guarantee to be one
00597         for(unsigned int i=1; i<GetNumberOfValues(); ++i)
00598             os << "," << Internal[i];
00599     }
00600     ArrayType &GetValue(unsigned int idx = 0) {
00601         gdcml_assert( idx < GetNumberOfValues() );
00602         return Internal[idx];
00603     }
00604     ArrayType &operator[] (unsigned int idx) {
00605         return GetValue(idx);
00606     }
00607     // const reference
00608     ArrayType const &GetValue(unsigned int idx = 0) const {
00609         gdcml_assert( idx < GetNumberOfValues() );
00610         return Internal[idx];
00611     }
00612     ArrayType const &operator[] (unsigned int idx) const {
00613         return GetValue(idx);
00614     }
00615     void SetValue(unsigned int idx, ArrayType v) {
00616         gdcml_assert( idx < GetNumberOfValues() );

```

```

00617     Internal[idx] = v;
00618 }
00619 void SetValue(ArrayType v) { SetValue(0, v); }
00620
00621 void SetValues(const ArrayType *array, unsigned int numel, bool own = false)
00622 {
00623     if( Internal ) // were we used before ?
00624     {
00625         // yes !
00626         if( Own ) delete[] Internal;
00627         Internal = nullptr;
00628     }
00629     Own = own;
00630     Length = numel;
00631     gdcm_assert( Internal == nullptr );
00632     if( own ) // make a copy:
00633     {
00634         Internal = new ArrayType[numel];
00635         if( array && numel )
00636             std::copy(array, array+numel, Internal);
00637     }
00638     else // pass pointer
00639     {
00640         Internal = const_cast<ArrayType*>(array);
00641     }
00642     // postcondition
00643     gdcm_assert( numel == GetNumberOfValues() );
00644 }
00645
00646 DataElement GetAsDataElement() const {
00647     DataElement ret( GetTag() );
00648     std::ostringstream os;
00649     if( Internal )
00650     {
00651         EncodingImplementation<VRToEncoding<TVR>::Mode>::Write(Internal,
00652             GetNumberOfValues(),os);
00653         if( (VR::VRType)VRToEncoding<TVR>::Mode == VR::VRASCII )
00654         {
00655             if( GetVR() != VR::UI )
00656             {
00657                 if( os.str().size() % 2 )
00658                 {
00659                     os << " ";
00660                 }
00661             }
00662         }
00663     }
00664     ret.SetVR( GetVR() );
00665     gdcm_assert( ret.GetVR() != VR::SQ );
00666     VL::Type osStrSize = (VL::Type) os.str().size();
00667     ret.SetByteValue( os.str().c_str(), osStrSize);
00668     return ret;
00669 }
00670 void SetFromDataElement(DataElement const &de) {
00671     // This is kind of hackish but since I do not generate other element than the first one: 0x6000 I
00672     // should be ok:
00673     gdcm_assert( GetTag() == de.GetTag() || GetTag().GetGroup() == 0x6000
00674         || GetTag().GetGroup() == 0x5000 );
00675     gdcm_assert( GetVR().Compatible( de.GetVR() ) ); // In case of VR::INVALID cannot use the & operator
00676     gdcm_assert( !de.IsEmpty() );
00677     const ByteValue *bv = de.GetByteValue();
00678     SetByteValue(bv);
00679 }
00680 void Set(DataSet const &ds) {
00681     SetFromDataElement( ds.GetDataElement( GetTag() ) );
00682 }
00683 void SetFromDataSet(DataSet const &ds) {
00684     if( ds.FindDataElement( GetTag() ) &&
00685         !ds.GetDataElement( GetTag() ).IsEmpty() )
00686     {
00687         SetFromDataElement( ds.GetDataElement( GetTag() ) );
00688     }
00689 }
00690 protected:
00691 void SetByteValue(const ByteValue *bv) {
00692     gdcm_assert( bv ); // FIXME
00693     std::stringstream ss;
00694     std::string s = std::string( bv->GetPointer(), bv->GetLength() );
00695     Length = bv->GetLength(); // HACK FIXME
00696     ss.str( s );
00697     ArrayType *internal;

```

```

00697     ArrayType buffer[256];
00698     if( bv->GetLength() < 256 )
00699     {
00700         internal = buffer;
00701     }
00702     else
00703     {
00704         internal = new ArrayType[ (VL::Type)bv->GetLength() ]; // over allocation
00705     }
00706     EncodingImplementation<VRTToEncoding<TVR>::Mode>::ReadComputeLength(internal, Length, ss);
00707     SetValues( internal, Length, true );
00708     if( !(bv->GetLength() < 256) )
00709     {
00710         delete[] internal;
00711     }
00712     //EncodingImplementation<VRTToEncoding<TVR>::Mode>::Read(Internal,
00713     // GetNumberOfValues(),ss);
00714 }
00715
00716 private:
00717     ArrayType *Internal;
00718     unsigned int Length;
00719     bool Own : 1;
00720 };
00721
00722 template<uint16_t Group, uint16_t Element, long long TVR>
00723 class Attribute<Group,Element,TVR,VM::VM1_3> : public Attribute<Group,Element,TVR,VM::VM1_n>
00724 {
00725 public:
00726     VM GetVM() const { return VM::VM1_3; }
00727 };
00728
00729 template<uint16_t Group, uint16_t Element, long long TVR>
00730 class Attribute<Group,Element,TVR,VM::VM1_8> : public Attribute<Group,Element,TVR,VM::VM1_n>
00731 {
00732 public:
00733     VM GetVM() const { return VM::VM1_8; }
00734 };
00735
00736 template<uint16_t Group, uint16_t Element, long long TVR>
00737 class Attribute<Group,Element,TVR,VM::VM2_n> : public Attribute<Group,Element,TVR,VM::VM1_n>
00738 {
00739 public:
00740     VM GetVM() const { return VM::VM2_n; }
00741 };
00742
00743 template<uint16_t Group, uint16_t Element, long long TVR>
00744 class Attribute<Group,Element,TVR,VM::VM2_2n> : public Attribute<Group,Element,TVR,VM::VM2_n>
00745 {
00746 public:
00747     static VM GetVM() { return VM::VM2_2n; }
00748 };
00749
00750 template<uint16_t Group, uint16_t Element, long long TVR>
00751 class Attribute<Group,Element,TVR,VM::VM3_n> : public Attribute<Group,Element,TVR,VM::VM1_n>
00752 {
00753 public:
00754     static VM GetVM() { return VM::VM3_n; }
00755 };
00756
00757 template<uint16_t Group, uint16_t Element, long long TVR>
00758 class Attribute<Group,Element,TVR,VM::VM3_3n> : public Attribute<Group,Element,TVR,VM::VM3_n>
00759 {
00760 public:
00761     static VM GetVM() { return VM::VM3_3n; }
00762 };
00763
00764
00765 // For particular case for ASCII string
00766 // WARNING: This template explicitly instantiates a particular
00767 // EncodingImplementation THEREFORE it is required to be declared after the
00768 // EncodingImplementation is needs (doh!)
00769 #if 0
00770 template<int TVM>
00771 class Attribute<TVM>
00772 {
00773 public:
00774     Attribute(const char array[])
00775     {
00776         unsigned int i = 0;
00777         const char sep = '\\';

```

```

00778     std::string sarray = array;
00779     std::string::size_type pos1 = 0;
00780     std::string::size_type pos2 = sarray.find(sep, pos1+1);
00781     while(pos2 != std::string::npos)
00782     {
00783         Internal[i++] = sarray.substr(pos1, pos2-pos1);
00784         pos1 = pos2+1;
00785         pos2 = sarray.find(sep, pos1+1);
00786     }
00787     Internal[i] = sarray.substr(pos1, pos2-pos1);
00788     // Shouldn't we do the contrary, since we know how many separators
00789     // (and default behavior is to discard anything after the VM declared
00790     gdcm_assert( GetLength()-1 == i );
00791 }
00792
00793 unsigned long GetLength() const {
00794     return VMToLength<TVM>::Length;
00795 }
00796 // Implementation of Print is common to all Mode (ASCII/Binary)
00797 void Print(std::ostream &_os) const {
00798     _os << Internal[0]; // VM is at least guarantee to be one
00799     for(int i=1; i<VMToLength<TVM>::Length; ++i)
00800         _os << "," << Internal[i];
00801 }
00802
00803 void Read(std::istream &_is) {
00804     EncodingImplementation<VR::VRASCII>::Read(Internal, GetLength(), _is);
00805 }
00806 void Write(std::ostream &_os) const {
00807     EncodingImplementation<VR::VRASCII>::Write(Internal, GetLength(), _os);
00808 }
00809 private:
00810     typename String Internal[VMToLength<TVM>::Length];
00811 };
00812
00813 template< int TVM>
00814 class Attribute<VR::PN, TVM> : public StringAttribute<TVM>
00815 {
00816 };
00817 #endif
00818
00819 #if 0
00820
00821 // Implementation for the undefined length (dynamically allocated array)
00822 template<int TVR>
00823 class Attribute<TVR, VM::VM1_n>
00824 {
00825 public:
00826     // This the way to prevent default initialization
00827     explicit Attribute() { Internal=0; Length=0; }
00828     ~Attribute() {
00829         delete[] Internal;
00830         Internal = 0;
00831     }
00832
00833     // Length manipulation
00834     // SetLength should really be protected anyway...all operation
00835     // should go through SetArray
00836     unsigned long GetLength() const { return Length; }
00837     typedef typename VRToType<TVR>::Type ArrayType;
00838     void SetLength(unsigned long len) {
00839         const unsigned int size = sizeof(ArrayType);
00840         if( len ) {
00841             if( len > Length ) {
00842                 // perform realloc
00843                 gdcm_assert( (len / size) * size == len );
00844                 ArrayType *internal = new ArrayType[len / size];
00845                 memcpy(internal, Internal, Length * size);
00846                 delete[] Internal;
00847                 Internal = internal;
00848             }
00849         }
00850         Length = len / size;
00851     }
00852
00853     // If save is set to zero user should not delete the pointer
00854     //void SetArray(const typename VRToType<TVR>::Type *array, int len, bool save = false)
00855     void SetArray(const ArrayType *array, unsigned long len,
00856         bool save = false) {
00857         if( save ) {
00858             SetLength(len); // realloc

```

```

00859     memcpy(Internal, array, len/*sizeof(ArrayType)*/);
00860 }
00861 else {
00862     // TODO rewrite this stupid code:
00863     Length = len;
00864     //Internal = array;
00865     gdcmm_assert(0);
00866 }
00867 }
00868 // Implementation of Print is common to all Mode (ASCII/Binary)
00869 void Print(std::ostream &_os) const {
00870     gdcmm_assert(Length);
00871     gdcmm_assert(Internal);
00872     _os << Internal[0]; // VM is at least guarantee to be one
00873     const unsigned long length = GetLength() < 25 ? GetLength() : 25;
00874     for(unsigned long i=1; i<length; ++i)
00875         _os << ", " << Internal[i];
00876 }
00877 void Read(std::istream &_is) {
00878     EncodingImplementation<VRToEncoding<TVR>::Mode>::Read(Internal,
00879         GetLength(), _is);
00880 }
00881 void Write(std::ostream &_os) const {
00882     EncodingImplementation<VRToEncoding<TVR>::Mode>::Write(Internal,
00883         GetLength(), _os);
00884 }
00885
00886 Attribute(const Attribute&_val) {
00887     if( this != &_amp;_val) {
00888         *_this = _val;
00889     }
00890 }
00891
00892 Attribute &operator=(const Attribute &_val) {
00893     Length = 0; // SYITF
00894     Internal = 0;
00895     SetArray(_val.Internal, _val.Length, true);
00896     return *_this;
00897 }
00898
00899 private:
00900     typename VRTToType<TVR>::Type *Internal;
00901     unsigned long Length; // unsigned int ??
00902 };
00903
00904 //template <int TVM = VM::VM1_n>
00905 //class Attribute<VR::OB, TVM > : public Attribute<VR::OB, VM::VM1_n> {};
00906
00907 // Partial specialization for derivatives of 1-n : 2-n, 3-n ...
00908 template<int TVR>
00909 class Attribute<TVR, VM::VM2_n> : public Attribute<TVR, VM::VM1_n>
00910 {
00911 public:
00912     typedef Attribute<TVR, VM::VM1_n> Parent;
00913     void SetLength(int len) {
00914         if( len <= 1 ) return;
00915         Parent::SetLength(len);
00916     }
00917 };
00918 template<int TVR>
00919 class Attribute<TVR, VM::VM2_2n> : public Attribute<TVR, VM::VM2_n>
00920 {
00921 public:
00922     typedef Attribute<TVR, VM::VM2_n> Parent;
00923     void SetLength(int len) {
00924         if( len % 2 ) return;
00925         Parent::SetLength(len);
00926     }
00927 };
00928 template<int TVR>
00929 class Attribute<TVR, VM::VM3_n> : public Attribute<TVR, VM::VM1_n>
00930 {
00931 public:
00932     typedef Attribute<TVR, VM::VM1_n> Parent;
00933     void SetLength(int len) {
00934         if( len <= 2 ) return;
00935         Parent::SetLength(len);
00936     }
00937 };
00938 template<int TVR>
00939 class Attribute<TVR, VM::VM3_3n> : public Attribute<TVR, VM::VM3_n>

```



```

00940 {
00941 public:
00942     typedef Attribute<TVR, VM::VM3_n> Parent;
00943     void SetLength(int len) {
00944         if( len % 3 ) return;
00945         Parent::SetLength(len);
00946     }
00947 };
00948
00949
00950 //template<int T> struct VRToLength;
00951 //template<> struct VRToLength<VR::AS>
00952 //{ enum { Length = VM::VM1 }; }
00953 //template<>
00954 //class Attribute<VR::AS> : public Attribute<VR::AS, VRToLength<VR::AS>::Length >
00955
00956 // only 0010 1010 AS 1 Patient's Age
00957 template<>
00958 class Attribute<VR::AS, VM::VM5>
00959 {
00960 public:
00961     char Internal[VRToLength<VM::VM5>::Length];
00962     void Print(std::ostream &_os) const {
00963         _os << Internal;
00964     }
00965 };
00966
00967 template<>
00968 class Attribute<VR::OB, VM::VM1> : public Attribute<VR::OB, VM::VM1_n> {};
00969 // Make it impossible to compile any other cases:
00970 template<int TVM> class Attribute<VR::OB, TVM>;
00971
00972 // Same for OW:
00973 template<>
00974 class Attribute<VR::OW, VM::VM1> : public Attribute<VR::OW, VM::VM1_n> {};
00975 // Make it impossible to compile any other cases:
00976 template<int TVM> class Attribute<VR::OW, TVM>;
00977 #endif
00978
00979 #if 0
00980 template<>
00981 class Attribute<0x7fe0,0x0010, VR::OW, VM::VM1>
00982 {
00983 public:
00984     char *Internal;
00985     unsigned long Length; // unsigned int ??
00986
00987     void Print(std::ostream &_os) const {
00988         _os << Internal[0];
00989     }
00990     void SetBytes(char *bytes, unsigned long length) {
00991         Internal = bytes;
00992         Length = length;
00993     }
00994     void Read(std::istream &_is) {
00995         uint16_t c[2];
00996         _is.read((char*)&c, 4);
00997         uint32_t l;
00998         _is.read((char*)&l, 4);
00999         Length = l;
01000         _is.read( Internal, Length );
01001     }
01002     void Write(std::ostream &_os) const {
01003         uint16_t c[] = {0x7fe0, 0x0010};
01004         _os.write((char*)&c, 4);
01005         _os.write((char*)&Length, 4);
01006         _os.write( Internal, Length );
01007     }
01008 };
01009 #endif
01010
01011 /*
01012 // Removing Attribute for SQ for now...
01013 template<uint16_t Group, uint16_t Element, typename SQA>
01014 class Attribute<Group,Element, VR::SQ, VM::VM1, SQA>
01015 {
01016 public:
01017     SQA sqa;
01018     void Print(std::ostream &_os) const {
01019         _os << Tag(Group,Element);
01020         sqa.Print(_os << std::endl << '\t');

```

```


01021     }
01022     void Write(std::ostream &_os) const {
01023         uint16_t c[] = {Group, Element};
01024         _os.write((char*)&c, 4);
01025         uint32_t undef = 0xffffffff;
01026         _os.write((char*)&undef, 4);
01027         uint16_t item_beg[] = {0xfffe, 0xe000};
01028         _os.write((char*)&item_beg, 4);
01029         _os.write((char*)&undef, 4);
01030         sqa.Write(_os);
01031         uint16_t item_end[] = {0xfffe, 0xe00d};
01032         _os.write((char*)&item_end, 4);
01033         uint32_t zero = 0x0;
01034         _os.write((char*)&zero, 4);
01035         uint16_t seq_end[] = {0xfffe, 0xe0dd};
01036         _os.write((char*)&seq_end, 4);
01037         _os.write((char*)&zero, 4);
01038     }
01039 };
01040 */
01041
01046
01047 } // namespace gdcmm_ns
01048
01049 #endif //GDCMATRIBUTE_H

```


11.111 gdcmmBasicOffsetTable.h File Reference

#include "gdcmmFragment.h"

Include dependency graph for gdcmmBasicOffsetTable.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::BasicOffsetTable](#)
Class to represent a *BasicOffsetTable*.

Namespaces

- namespace [gdcm](#)

Functions

- `std::ostream & gdcm::operator<< (std::ostream &os, const BasicOffsetTable &val)`

11.112 gdcmBasicOffsetTable.h

[Go to the documentation of this file.](#)

```

00001  /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012  =====*/
00013
00014
00015  #ifndef GDCMBASICOFFSETTABLE_H
00016  #define GDCMBASICOFFSETTABLE_H
00017
00018  #include "gdcmFragment.h"
00019
00020  namespace gdcm_ns
00021  {
00025

```

```

00026 class GDCM_EXPORT BasicOffsetTable : public Fragment
00027 {
00028 //protected:
00029 // void SetTag(const Tag &t);
00030 public:
00031 BasicOffsetTable() : Fragment() {}
00032 friend std::ostream &operator<<(std::ostream &os, const BasicOffsetTable &val);
00033
00034 /*
00035 VL GetLength() const {
00036     gdcml_assert( !ValueLengthField.IsUndefined() );
00037     gdcml_assert( !ValueField || ValueField->GetLength() == ValueLengthField );
00038     return TagField.GetLength() + ValueLengthField.GetLength()
00039         + ValueLengthField;
00040 }
00041 */
00042
00043 template <typename TSwap>
00044 std::istream &Read(std::istream &is) {
00045     // Superclass
00046     const Tag itemStart(0xffff, 0xe000);
00047     if( !TagField.Read<TSwap>(is) )
00048     {
00049         gdcml_assert(0 && "Should not happen");
00050         return is;
00051     }
00052     //gdcml_assert( TagField == itemStart );
00053     if( TagField != itemStart )
00054     {
00055         // Bug_Siemens_PrivateIconNoItem.dcm
00056         //gdcml_debugMacro( "Could be Bug_Siemens_PrivateIconNoItem.dcm" );
00057         ParseException pe;
00058         pe.SetLastElement(*this);
00059         //throw "SIEMENS Icon thingy";
00060         throw pe;
00061     }
00062     if( !ValueLengthField.Read<TSwap>(is) )
00063     {
00064         gdcml_assert(0 && "Should not happen");
00065         return is;
00066     }
00067     // Self
00068     SmartPointer<ByteValue> bv = new ByteValue;
00069     bv->SetLength(ValueLengthField);
00070     if( !bv->Read<TSwap>(is) )
00071     {
00072         gdcmlAssertAlwaysMacro(0 && "Should not happen");
00073         return is;
00074     }
00075     ValueField = bv;
00076     return is;
00077 }
00078
00079 /*
00080 template <typename TSwap>
00081 std::ostream &Write(std::ostream &os) const {
00082     const Tag itemStart(0xffff, 0xe000);
00083     const Tag seqDelItem(0xffff, 0xe0dd);
00084     if( !TagField.Write<TSwap>(os) )
00085     {
00086         gdcml_assert(0 && "Should not happen");
00087         return os;
00088     }
00089     gdcml_assert( TagField == itemStart );
00090     if( !ValueLengthField.Write<TSwap>(os) )
00091     {
00092         gdcml_assert(0 && "Should not happen");
00093         return os;
00094     }
00095     if( ValueLengthField )
00096     {
00097         // Self
00098         const ByteValue *bv = GetByteValue();
00099         gdcml_assert( bv );
00100         gdcml_assert( bv->GetLength() == ValueLengthField );
00101         if( !bv->Write<TSwap>(os) )
00102         {
00103             gdcml_assert(0 && "Should not happen");
00104             return os;
00105         }
00106     }

```

```

00107     return os;
00108 }
00109 */
00110 };
00111 //-----
00112 inline std::ostream &operator<<(std::ostream &os, const BasicOffsetTable &val)
00113 {
00114     os << " BasicOffsetTable Length=" << val.ValueLengthField << std::endl;
00115     if( val.ValueField )
00116     {
00117         const ByteValue *bv = val.GetByteValue();
00118         gdcm_assert( bv );
00119         os << *bv;
00120     }
00121 }
00122 return os;
00123 }
00124
00125
00126 } // end namespace gdcm_ns
00127
00128 #endif //GDCMBASICOFFSETTABLE_H

```

11.113 gdcmByteBuffer.h File Reference


```
#include "gdcmTypes.h"
```

```
#include <vector>
```


```
#include <assert.h>
```

```
#include <string.h>
```

Include dependency graph for gdcmByteBuffer.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcml::ByteBuffer](#)
ByteBuffer.

Namespaces

- namespace [gdcml](#)

11.114 gdcmlByteBuffer.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcml.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMBYTEBUFFER_H
00015 #define GDCMBYTEBUFFER_H
00016
00017 #include "gdcmlTypes.h"
00018 #include <vector>
00019 #include <assert.h>
00020 #include <string.h> // memmove
00021
00022 #error should not be used
00023
00024 namespace gdcml
00025 {
00034   class ByteBuffer
00035   {
00036   public:
00037     static const int InitBufferSize = 1024;
00038     ByteBuffer() : Start(0), End(0), Limit(0) {}
  
```

```

00039 char *Get(int len)
00040 {
00041     char *buffer = &Internal[0];
00042     if (len > Limit - End)
00043     {
00044         // FIXME avoid integer overflow
00045         int neededSize = len + (End - Start);
00046         if (neededSize <= Limit - buffer)
00047         {
00048             memmove(buffer, Start, End - Start);
00049             End = buffer + (End - Start);
00050             Start = buffer;
00051         }
00052     else
00053     {
00054         char *newBuf;
00055         int bufferSize = Limit - Start;
00056         if ( bufferSize == 0 )
00057         {
00058             bufferSize = InitBufferSize;
00059         }
00060         do
00061         {
00062             bufferSize *= 2;
00063         } while (bufferSize < neededSize);
00064         //newBuf = malloc(bufferSize);
00065         try
00066         {
00067             Internal.reserve(bufferSize);
00068             newBuf = &Internal[0];
00069         }
00070         catch(...)
00071         {
00072             //errorCode = NoMemoryError;
00073             return 0;
00074         }
00075         Limit = newBuf + bufferSize;
00076
00077         if (Start)
00078         {
00079             memcpy(newBuf, Start, End - Start);
00080         }
00081         End = newBuf + (End - Start);
00082         Start = /*buffer =*/ newBuf;
00083     }
00084 }
00085 gdcm_assert( (int)Internal.capacity() >= len );
00086 return End;
00087 }
00088
00089 void UpdatePosition() {}
00090 void ShiftEnd(int len) {
00091     End += len;
00092 }
00093 const char *GetStart() const {
00094     return Start;
00095 }
00096
00097 private:
00098     typedef std::vector<char> CharVector;
00099     const char *Start;
00100     char *End;
00101     const char *Limit;
00102     CharVector Internal;
00103 };
00104
00105 } // end namespace gdcm
00106
00107 #endif //GDCMBYTEBUFFER_H

```



```

00028 {
00029 public:
00030     ByteSwapFilter(DataSet& ds):DS(ds),ByteSwapTag(false) {}
00031     ~ByteSwapFilter() = default;
00032     ByteSwapFilter(const ByteSwapFilter &) = delete;
00033     ByteSwapFilter& operator=(const ByteSwapFilter &) = delete;
00034
00035     bool ByteSwap();
00036     void SetByteSwapTag(bool b) { ByteSwapTag = b; }
00037
00038 private:
00039     DataSet &DS;
00040     bool ByteSwapTag;
00041 };
00042
00043
00044 } // end namespace gdcm
00045
00046 #endif //GDCMBYTESWAPFILTER_H

```


11.117 gdcmByteValue.h File Reference

```

#include "gdcmValue.h"
#include "gdcmTrace.h"
#include "gdcmVL.h"
#include <vector>
#include <iterator>
#include <iomanip>
#include <algorithm>
#include <cstring>

```

Include dependency graph for gdcmByteValue.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::ByteValue](#)
Class to represent binary value (array of bytes)

Namespaces

- namespace [gdcm](#)

11.118 gdcmByteValue.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003 Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005 Copyright (c) 2006-2011 Mathieu Malaterre
00006 All rights reserved.
00007 See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009 This software is distributed WITHOUT ANY WARRANTY; without even
00010 the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011 PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMBYTEVALUE_H
00015 #define GDCMBYTEVALUE_H
00016
00017 #include "gdcmValue.h"
00018 #include "gdcmTrace.h"
00019 #include "gdcmVL.h"
00020
00021 #include <vector>
00022 #include <iterator>
00023 #include <iomanip>
00024 #include <algorithm>
00025 #include <cstring>
00026
00027 namespace gdcm_ns
00028 {
00029 #if !defined(SWIGPYTHON) && !defined(SWIGSHARP) && !defined(SWIGJAVA) && !defined(SWIGPHP)
00030 using namespace gdcm;
00031 #endif
00032 class GDCM_EXPORT ByteValue : public Value
00033 {
00034 public:
00035     ByteValue(const char* array = nullptr, VL const &vl = 0): Length(vl) {
00036         VL bytes_count_to_copy = Length;
00037         if( vl.IsOdd() )
00038         {
00039             gdcmDebugMacro( "Odd length" );
00040             Internal.resize(vl+1);
00041             ++Length;
00042         }
00043         Internal.resize(Length);
00044         if( array )
00045             std::memcpy(Internal.data(), array, bytes_count_to_copy);
00046     }
00047
00048     ByteValue(std::vector<char> &v): Internal(v), Length((uint32_t)v.size()) {}
00049     //ByteValue(std::ostringstream const &os) {
00050     //    (void)os;
00051     //    gdcm_assert(0); // TODO
00052     //}
00053     ~ByteValue() override {
00054         Internal.clear();
00055     }
00056
00057     // When 'dumping' dicom file we still have some information from

```

```

00062 // Either the VR: eg LO (private tag)
00063 void PrintASCII(std::ostream &os, VL maxlength) const;
00064
00065 void PrintHex(std::ostream &os, VL maxlength) const;
00066
00067 // Either from Element Number (== 0x0000)
00068 void PrintGroupLength(std::ostream &os) {
00069     gdcm_assert( Length == 2 );
00070     (void)os;
00071 }
00072
00073 bool IsEmpty() const {
00074 #if 0
00075     if( Internal.empty() ) gdcm_assert( Length == 0 );
00076     return Internal.empty();
00077 #else
00078     return Length == 0;
00079 #endif
00080 }
00081 VL GetLength() const override { return Length; }
00082
00083 VL ComputeLength() const { return Length + Length % 2; }
00084 // Does a reallocation
00085 void SetLength(VL vl) override;
00086
00087 operator const std::vector<char>& () const { return Internal; }
00088
00089 ByteValue &operator=(const ByteValue &val) {
00090     Internal = val.Internal;
00091     Length = val.Length;
00092     return *this;
00093 }
00094
00095 bool operator==(const ByteValue &val) const {
00096     if( Length != val.Length )
00097         return false;
00098     if( Internal == val.Internal )
00099         return true;
00100     return false;
00101 }
00102 bool operator==(const Value &val) const override
00103 {
00104     const ByteValue &bv = dynamic_cast<const ByteValue&>(val);
00105     return Length == bv.Length && Internal == bv.Internal;
00106 }
00107
00108 void Append(ByteValue const &bv);
00109
00110 void Clear() override {
00111     Internal.clear();
00112 }
00113 // Use that only if you understand what you are doing
00114 const char *GetPointer() const {
00115     if(!Internal.empty()) return &Internal[0];
00116     return nullptr;
00117 }
00118 // Use that only if you really understand what you are doing
00119 const void *GetVoidPointer() const {
00120     if(!Internal.empty()) return &Internal[0];
00121     return nullptr;
00122 }
00123 void *GetVoidPointer() {
00124     if(!Internal.empty()) return &Internal[0];
00125     return nullptr;
00126 }
00127 void Fill(char c) {
00128     //if( Internal.empty() ) return;
00129     std::vector<char>::iterator it = Internal.begin();
00130     for(; it != Internal.end(); ++it) *it = c;
00131 }
00132 bool GetBuffer(char *buffer, unsigned long length) const;
00133 bool WriteBuffer(std::ostream &os) const {
00134     if( Length ) {
00135         //gdcm_assert( Internal.size() <= Length );
00136         gdcm_assert( !(Internal.size() % 2) );
00137         os.write(&Internal[0], Internal.size() );
00138     }
00139     return true;
00140 }
00141
00142 template <typename TSwap, typename TType>

```

```

00143 std::istream &Read(std::istream &is, bool readvalues = true) {
00144     // If Length is odd we have detected that in SetLength
00145     // and calling std::vector::resize make sure to allocate *AND*
00146     // initialize values to 0 so we are sure to have a \0 at the end
00147     // even in this case
00148     if(Length)
00149     {
00150         if( readvalues )
00151         {
00152             is.read(&Internal[0], Length);
00153             gdcm_assert( Internal.size() == Length || Internal.size() == Length + 1 );
00154             TSwap::SwapArray((TType*)GetVoidPointer(), Internal.size() / sizeof(TType) );
00155         }
00156         else
00157         {
00158             is.seekg(Length, std::ios::cur);
00159         }
00160     }
00161     return is;
00162 }
00163
00164 template <typename TSwap>
00165 std::istream &Read(std::istream &is) {
00166     return Read<TSwap,uint8_t>(is);
00167 }
00168
00169
00170 template <typename TSwap, typename TType>
00171 std::ostream const &Write(std::ostream &os) const {
00172     gdcm_assert( !(Internal.size() % 2) );
00173     if( !Internal.empty() ) {
00174         //os.write(&Internal[0], Internal.size());
00175         std::vector<char> copy = Internal;
00176         TSwap::SwapArray((TType*)(void*)&copy[0], Internal.size() / sizeof(TType) );
00177         os.write(&copy[0], copy.size());
00178     }
00179     return os;
00180 }
00181
00182 template <typename TSwap>
00183 std::ostream const &Write(std::ostream &os) const {
00184     return Write<TSwap,uint8_t>(os);
00185 }
00186
00193 bool IsPrintable(VL length) const {
00194     gdcm_assert( length <= Length );
00195     for(unsigned int i=0; i<length; i++)
00196     {
00197         if ( i == (length-1) && Internal[i] == '\0' ) continue;
00198         if ( !( isprint((unsigned char)Internal[i]) || isspace((unsigned char)Internal[i]) ) )
00199         {
00200             //gdcmWarningMacro( "Cannot print : " « i );
00201             return false;
00202         }
00203     }
00204     return true;
00205 }
00206
00208 void PrintPNXML(std::ostream &os) const;
00209 void PrintASCIIXML(std::ostream &os) const;
00210 void PrintHexXML(std::ostream &os) const;
00211 protected:
00212 void Print(std::ostream &os) const override {
00213     // This is perfectly valid to have a Length = 0 , so we cannot check
00214     // the length for printing
00215     if( !Internal.empty() )
00216     {
00217         if( IsPrintable(Length) )
00218         {
00219             // WARNING: Internal.end() != Internal.begin()+Length
00220             std::vector<char>::size_type length = Length;
00221             if( Internal.back() == 0 ) --length;
00222             std::copy(Internal.begin(), Internal.begin()+length,
00223                 std::ostream_iterator<char>(os));
00224         }
00225         else
00226             os << "Loaded:" « Internal.size();
00227     }
00228     else
00229     {
00230         //os << "Not Loaded";

```

```


00231     os << "(no value available)";
00232   }
00233 }
00234 /*
00235 //Introduce check for invalid XML characters
00236 friend std::ostream& operator<<(std::ostream &os,const char c);
00237 */
00238
00239 void SetLengthOnly(VL vl) override {
00240     Length = vl;
00241 }
00242
00243 private:
00244     std::vector<char> Internal;
00245
00246 // WARNING Length IS NOT Internal.size() some *featured* DICOM
00247 // implementation define odd length, we always load them as even number
00248 // of byte, so we need to keep the right Length
00249 VL Length;
00250 };
00251
00252 } // end namespace gdcm_ns
00253
00254 #endif //GDCMBYTEVALUE_H

```

11.119 gdcmCodeString.h File Reference

```
#include "gdcmString.h"
```

Include dependency graph for gdcmCodeString.h:



Classes

- class `gdcm::CodeString`
CodeString.

Namespaces

- namespace `gdcm`

Functions

- bool `gdcm::operator!=` (const `CodeString` &ref, const `CodeString` &cs)
- `std::ostream` & `gdcm::operator<<` (`std::ostream` &os, const `CodeString` &str)
- bool `gdcm::operator==` (const `CodeString` &ref, const `CodeString` &cs)

11.120 gdcmCodeString.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003     Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005     Copyright (c) 2006-2011 Mathieu Malaterre
00006     All rights reserved.
00007     See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009     This software is distributed WITHOUT ANY WARRANTY; without even
00010     the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011     PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMCODESTRING_H
00015 #define GDCMCODESTRING_H
00016
00017 #include "gdcmString.h"
00018
00019 namespace gdcm
00020 {
00021
00039 // Note to myself: because not all wrapped language support exception
00040 // we could not support throwing an exception during object construction.
00041 class GDCM_EXPORT CodeString
00042 {
00043     friend std::ostream& operator<< (std::ostream& os, const CodeString& str);
00044     friend bool operator==(const CodeString &ref, const CodeString &cs);
00045     friend bool operator!=(const CodeString &ref, const CodeString &cs);
00046     typedef String<'\\',16> InternalClass;
00047 public:
00048     typedef InternalClass::value_type      value_type;
00049     typedef InternalClass::pointer         pointer;
00050     typedef InternalClass::reference       reference;
00051     typedef InternalClass::const_reference const_reference;
00052     typedef InternalClass::size_type      size_type;
00053     typedef InternalClass::difference_type difference_type;
00054     typedef InternalClass::iterator        iterator;
00055     typedef InternalClass::const_iterator  const_iterator;
00056     typedef InternalClass::reverse_iterator reverse_iterator;
00057     typedef InternalClass::const_reverse_iterator const_reverse_iterator;
00058
00060     CodeString(): Internal() {}
00061     CodeString(const value_type* s): Internal(s) { Internal = Internal.Trim(); }
00062     CodeString(const value_type* s, size_type n): Internal(s, n) {
00063         Internal = Internal.Trim(); }
00064     CodeString(const InternalClass& s, size_type pos=0, size_type n=InternalClass::npos):
00065         Internal(s, pos, n) { Internal = Internal.Trim(); }
00066
00068     bool IsValid() const;
00069
00071     std::string GetAsString() const {
00072         return Internal;
00073     }
00074
00076     size_type Size() const { return Internal.size(); }
00077
00078 protected:
00079     std::string TrimInternal() const {
00080         return Internal.Trim();
00081     }
00082
00083 private:
00084     String<'\\',16> Internal;

```

```

00085 };
00086
00087 inline std::ostream& operator<< (std::ostream& os, const CodeString& str)
00088 {
00089     os << str.Internal;
00090     return os;
00091 }
00092
00093 inline bool operator==(const CodeString &ref, const CodeString& cs)
00094 {
00095     return ref.Internal == cs.Internal;
00096 }
00097 inline bool operator!=(const CodeString &ref, const CodeString& cs)
00098 {
00099     return ref.Internal != cs.Internal;
00100 }
00101
00102
00103 } // end namespace gdcm
00104
00105 #endif //GDCMCODESTRING_H

```


11.121 gdcmCP246ExplicitDataElement.h File Reference

```

#include "gdcmDataElement.h"
#include "gdcmCP246ExplicitDataElement.txx"

```

Include dependency graph for gdcmCP246ExplicitDataElement.h:



Classes

- class [gdcm::CP246ExplicitDataElement](#)
Class to read/write a [DataElement](#) as CP246Explicit Data [Element](#).

Namespaces

- namespace [gdcm](#)

11.122 gdcmCP246ExplicitDataElement.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMCP246EXPLICITDATAELEMENT_H
00015 #define GDCMCP246EXPLICITDATAELEMENT_H
00016
00017 #include "gdcmDataElement.h"
00018
00019 namespace gdcm
00020 {
00021   // Data Element (CP246Explicit)
00022   class GDCM_EXPORT CP246ExplicitDataElement : public DataElement
00023   {
00024   public:
00025     VL GetLength() const;
00026
00027     template <typename TSwap>
00028     std::istream &Read(std::istream &is);
00029
00030     template <typename TSwap>
00031     std::istream &ReadPreValue(std::istream &is);
00032
00033     template <typename TSwap>
00034     std::istream &ReadValue(std::istream &is, bool readvalues = true);
00035
00036     template <typename TSwap>
00037     std::istream &ReadWithLength(std::istream &is, VL & length);
00038
00039     // PURPOSELY do not provide an implementation for writing !
00040     //template <typename TSwap>
00041     //const std::ostream &Write(std::ostream &os) const;
00042   };
00043
00044 } // end namespace gdcm
00045
00046 #include "gdcmCP246ExplicitDataElement.txx"
00047
00048 #endif //GDCMCP246EXPLICITDATAELEMENT_H

```


11.123 gdcmCSAElement.h File Reference

```


#include "gdcmTag.h"
#include "gdcmVM.h"
#include "gdcmVR.h"
#include "gdcmByteValue.h"
#include "gdcmSmartPointer.h"

```


Include dependency graph for gdcmCSAElement.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::CSAElement](#)
Class to represent a CSA [Element](#).

Namespaces

- namespace [gdcm](#)

Functions

- `std::ostream & gdcm::operator<< (std::ostream &os, const CSAElement &val)`

11.124 gdcmCSAElement.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMCSAELEMENT_H
00015 #define GDCMCSAELEMENT_H
00016
00017 #include "gdcmTag.h"
00018 #include "gdcmVM.h"
00019 #include "gdcmVR.h"
00020 #include "gdcmByteValue.h"
00021 #include "gdcmSmartPointer.h"
00022
00023 namespace gdcm
00024 {
00025     class GDCM_EXPORT CSAElement
00026     {
00027     public:
00028         CSAElement(unsigned int kf = 0):KeyField(kf),SyngoDTField(0),NoOfItemsField(0) {}
00029
00030         friend std::ostream& operator<<(std::ostream &os, const CSAElement &val);
00031
00032         unsigned int GetKey() const { return KeyField; }
00033         void SetKey(unsigned int key) { KeyField = key; }
00034
00035         const char *GetName() const { return NameField.c_str(); }
00036         void SetName(const char *name) { NameField = name; }
00037
00038         const VM& GetVM() const { return ValueMultiplicityField; }
00039         void SetVM(const VM &vm) { ValueMultiplicityField = vm; }
00040
00041         VR const &GetVR() const { return VRField; }
00042         void SetVR(VR const &vr) { VRField = vr; }
00043
00044         unsigned int GetSyngoDT() const { return SyngoDTField; }
00045         void SetSyngoDT(unsigned int syngodt) { SyngoDTField = syngodt; }
00046
00047         unsigned int GetNoOfItems() const { return NoOfItemsField; }
00048         void SetNoOfItems(unsigned int items) { NoOfItemsField = items; }
00049
00050         Value const &GetValue() const { return *DataField; }
00051         Value &GetValue() { return *DataField; }
00052         void SetValue(Value const &vl) {
00053             //gdcm_assert( DataField == 0 );
00054             DataField = vl;
00055         }
00056         bool IsEmpty() const { return DataField == nullptr; }
00057
00058         void SetByteValue(const char *array, VL length)
00059         {
00060             ByteValue *bv = new ByteValue(array,length);
00061             SetValue( *bv );
00062         }
00063         const ByteValue* GetByteValue() const {
00064             // Get the raw pointer from the gdcm::SmartPointer
00065             const ByteValue *bv = dynamic_cast<const ByteValue*>(DataField.GetPointer());
00066             return bv; // Will return NULL if not ByteValue
00067         }
00068
00069         CSAElement(const CSAElement &_val)
00070         {
00071             if( this != &_amp;_val)
00072             {
00073                 *this = _val;
00074             }
00075         }
00076     };

```

```

00091
00092 bool operator<(const CSAElement &de) const
00093 {
00094     return GetKey() < de.GetKey();
00095 }
00096 CSAElement &operator=(const CSAElement &de)
00097     = default;
00098
00099 bool operator==(const CSAElement &de) const
00100 {
00101     return KeyField == de.KeyField
00102         && NameField == de.NameField
00103         && ValueMultiplicityField == de.ValueMultiplicityField
00104         && VRField == de.VRField
00105         && SyngoDTField == de.SyngoDTField
00106         //&& ValueField == de.ValueField;
00107     ;
00108 }
00109
00110 protected:
00111     unsigned int KeyField;
00112     std::string NameField;
00113     VM ValueMultiplicityField;
00114     VR VRField;
00115     unsigned int SyngoDTField;
00116     unsigned int NoOfItemsField;
00117     typedef SmartPointer<Value> DataPtr;
00118     DataPtr DataField;
00119 };
00120 //-----
00121 inline std::ostream& operator<(std::ostream &os, const CSAElement &val)
00122 {
00123     os << val.KeyField;
00124     os << " - '" << val.NameField;
00125     os << "' VM " << val.ValueMultiplicityField;
00126     os << ", VR " << val.VRField;
00127     os << ", SyngoDT " << val.SyngoDTField;
00128     os << ", NoOfItems " << val.NoOfItemsField;
00129     os << ", Data ";
00130     if( val.DataField )
00131     {
00132         //val.DataField->Print( os << "' " );
00133         const ByteValue * bv = dynamic_cast<ByteValue*>(&*val.DataField);
00134         gdcm_assert( bv );
00135         const char * p = bv->GetPointer();
00136         std::string str(p, p + bv->GetLength() );
00137         if( val.ValueMultiplicityField == VM::VM1 )
00138         {
00139             os << "' " << str.c_str() << "' ";
00140         }
00141         else
00142         {
00143             std::istringstream is( str );
00144             std::string s;
00145             bool sep = false;
00146             while( std::getline(is, s, '\\') )
00147             {
00148                 if( sep )
00149                 {
00150                     os << '\\';
00151                 }
00152                 sep = true;
00153                 os << "' " << s.c_str() << "' ";
00154             }
00155             //bv->Print( os << "' " );
00156             //os << "' ";
00157         }
00158     }
00159     return os;
00160 }
00161
00162 } // end namespace gdcm
00163
00164 #endif //GDCMCSAELEMENT_H

```



```

00010     the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011     PURPOSE. See the above copyright notice for more information.
00012
00013     =====*/
00014 #ifndef GDCMCSAHEADER_H
00015 #define GDCMCSAHEADER_H
00016
00017 #include "gdcmTypes.h"
00018 #include "gdcmDataSet.h"
00019 #include "gdcmCSAElement.h"
00020 #include "gdcmMrProtocol.h"
00021
00022 namespace gdcm
00023 {
00024 /*
00025  * Everything done in this code is for the sole purpose of writing interoperable
00026  * software under Sect. 1201 (f) Reverse Engineering exception of the DMCA.
00027  * If you believe anything in this code violates any law or any of your rights,
00028  * please contact us (gdcm-developers@lists.sourceforge.net) so that we can
00029  * find a solution.
00030  */
00031 //-----
00032
00033 class DataElement;
00034 class PrivateTag;
00063 class GDCM_EXPORT CSAHeader
00064 {
00065     friend std::ostream& operator<(std::ostream &_os, const CSAHeader &d);
00066 public :
00067     CSAHeader():InternalDataSet(),InternalType(UNKNOWN),InterfileData(nullptr) {}
00068     ~CSAHeader() = default;
00069
00071     typedef enum {
00072         UNKNOWN = 0,
00073         SV10,
00074         NOMAGIC,
00075         DATASET_FORMAT,
00076         INTERFILE,
00077         ZEROED_OUT
00078     } CSAHeaderType;
00079
00081     bool LoadFromDataElement(DataElement const &de);
00082
00084     void Print(std::ostream &os) const;
00085
00087     const DataSet& GetDataSet() const { return InternalDataSet; }
00088
00090     const char * GetInterfile() const { return InterfileData; }
00091
00094     CSAHeaderType GetFormat() const;
00095
00098     static const PrivateTag & GetCSAImageHeaderInfoTag();
00099
00102     static const PrivateTag & GetCSASeriesHeaderInfoTag();
00103
00106     static const PrivateTag & GetCSADataInfo();
00107
00110     const CSAElement &GetCSAElementByName(const char *name);
00111
00114     bool FindCSAElementByName(const char *name);
00115
00117     bool GetMrProtocol( const DataSet &ds, MrProtocol &mrProtocol );
00118
00119 protected:
00120     const CSAElement& GetCSAEnd() const;
00121
00122 private:
00123     std::set<CSAElement> InternalCSADataSet;
00124     DataSet InternalDataSet;
00125     CSAHeaderType InternalType;
00126     Tag DataElementTag;
00127     static CSAElement CSAEEnd;
00128     const char *InterfileData;
00129 };
00130 //-----
00131 inline std::ostream& operator<(std::ostream &os, const CSAHeader &d)
00132 {
00133     d.Print( os );
00134     return os;
00135 }
00136

```

```

00137 } // end namespace gdcm
00138 //-----
00139 #endif //GDCMCSAHEADER_H

```


11.127 gdcmDataElement.h File Reference

```

#include "gdcmTag.h"
#include "gdcmVL.h"
#include "gdcmVR.h"
#include "gdcmByteValue.h"
#include "gdcmSmartPointer.h"
#include <set>

```

Include dependency graph for gdcmDataElement.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::DataElement](#)
Class to represent a Data [Element](#) either Implicit or Explicit.

Namespaces

- namespace [gdcm](#)

Functions

- bool `gdcm::operator!=` (const `DataElement` &lhs, const `DataElement` &rhs)
- `std::ostream` & `gdcm::operator<<` (`std::ostream` &os, const `DataElement` &val)

11.128 gdcmDataElement.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003     Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005     Copyright (c) 2006-2011 Mathieu Malaterre
00006     All rights reserved.
00007     See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009     This software is distributed WITHOUT ANY WARRANTY; without even
00010     the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011     PURPOSE. See the above copyright notice for more information.
00012
00013     =====*/
00014 #ifndef GDCMDATAELEMENT_H
00015 #define GDCMDATAELEMENT_H
00016
00017 #include "gdcmTag.h"
00018 #include "gdcmVL.h"
00019 #include "gdcmVR.h"
00020 #include "gdcmByteValue.h"
00021 #include "gdcmSmartPointer.h"
00022
00023 #include <set>
00024
00025 namespace gdcm_ns
00026 {
00027     // Data Element
00028     // Contains multiple fields:
00029     // -> Tag
00030     // -> Optional VR (Explicit Transfer Syntax)
00031     // -> ValueLength
00032     // -> Value
00033     // TODO: This class SHOULD be pure virtual. I don't want a user
00034     // to shoot himself in the foot.
00035
00036     class SequenceOfItems;
00037     class SequenceOfFragments;
00038     class GDCM_EXPORT DataElement
00039     {
00040     public:
00041         DataElement(const Tag& t = Tag(0), const VL& vl = 0, const VR &vr =
VR::INVALID):TagField(t),ValueLengthField(vl),VRField(vr),ValueField(nullptr) {}
00042         //DataElement( Attribute const &att );
00043
00044         friend std::ostream& operator<<(std::ostream &_os, const DataElement &_val);
00045
00046         const Tag& GetTag() const { return TagField; }
00047         Tag& GetTag() { return TagField; }
00048         void SetTag(const Tag &t) { TagField = t; }
00049
00050         const VL& GetVL() const { return ValueLengthField; }
00051         VL& GetVL() { return ValueLengthField; }
00052         void SetVL(const VL &vl) { ValueLengthField = vl; }
00053         void SetVLToUndefined();
00054
00055         VR const &GetVR() const { return VRField; }
00056         void SetVR(VR const &vr) {
00057             if( vr.IsVRFile() )
00058                 VRField = vr;
00059         }
00060
00061         Value const &GetValue() const { gdcmAssertAlwaysMacro(ValueField); return *ValueField; }
00062         Value &GetValue() {
00063             gdcmAssertAlwaysMacro(ValueField);
00064             return *ValueField;
00065         }
00066     };
00067
00068 }
00069
00070 #endif

```

```

00098     }
00100     void SetValue(Value const & vl) {
00101         //gdc assert( ValueField == 0 );
00102         ValueField = vl;
00103         ValueLengthField = vl.GetLength();
00104     }
00106     bool IsEmpty() const { return ValueField == nullptr || (GetByteValue() && GetByteValue()->IsEmpty()); }
00107
00109     void Empty() { ValueField = nullptr; ValueLengthField = 0; }
00110
00112     void Clear()
00113     {
00114         TagField = 0;
00115         VRField = VR::INVALID;
00116         ValueField = nullptr;
00117         ValueLengthField = 0;
00118     }
00119
00120     // Helper:
00126     void SetByteValue(const char *array, VL length)
00127     {
00128         ByteValue *bv = new ByteValue(array,length);
00129         SetValue( *bv );
00130     }
00133     const ByteValue* GetByteValue() const {
00134         // Get the raw pointer from the gdc::SmartPointer
00135         const ByteValue *bv = dynamic_cast<const ByteValue*>(ValueField.GetPointer());
00136         return bv; // Will return NULL if not ByteValue
00137     }
00138
00145     SmartPointer<SequenceOfItems> GetValueAsSQ() const;
00146
00149     const SequenceOfFragments* GetSequenceOfFragments() const;
00150     SequenceOfFragments* GetSequenceOfFragments();
00151
00153     bool IsUndefinedLength() const {
00154         return ValueLengthField.IsUndefined();
00155     }
00156
00157     DataElement(const DataElement &_val)
00158     {
00159         if( this != &_amp;_val)
00160         {
00161             *this = _val;
00162         }
00163     }
00164
00165     bool operator<(const DataElement &de) const
00166     {
00167         return GetTag() < de.GetTag();
00168     }
00169     DataElement &operator=(const DataElement &)
00170     = default;
00171
00172     bool operator==(const DataElement &de) const
00173     {
00174         bool b = TagField == de.TagField
00175             && ValueLengthField == de.ValueLengthField
00176             && VRField == de.VRField;
00177         if( !ValueField && !de.ValueField )
00178         {
00179             return b;
00180         }
00181         if( ValueField && de.ValueField )
00182         {
00183             return b && (*ValueField == *de.ValueField);
00184         }
00185         // ValueField != de.ValueField
00186         return false;
00187     }
00188
00189     // The following functionalities are dependent on:
00190     // # The Transfer Syntax: Explicit or Implicit
00191     // # The Byte encoding: Little Endian / Big Endian
00192
00193     /*
00194     * The following was inspired by a C++ idiom: Curiously Recurring Template Pattern
00195     * Ref: http://en.wikipedia.org/wiki/Curiously\_Recurring\_Template\_Pattern
00196     * The typename TDE is typically a derived class *without* any data
00197     * while TSwap is a simple template parameter to achieve byteswapping (and allow factorization of
00198     * highly identical code)

```




```

00199     */
00200     template <typename TDE>
00201     VL GetLength() const {
00202         return static_cast<const TDE*>(this)->GetLength();
00203     }
00204
00205     template <typename TDE, typename TSwap>
00206     std::istream &Read(std::istream &is) {
00207         return static_cast<TDE*>(this)->template Read<TSwap>(is);
00208     }
00209
00210     template <typename TDE, typename TSwap>
00211     std::istream &ReadOrSkip(std::istream &is, std::set<Tag> const &skiptags) {
00212         (void)skiptags;
00213         return static_cast<TDE*>(this)->template Read<TSwap>(is);
00214     }
00215
00216     template <typename TDE, typename TSwap>
00217     std::istream &ReadPreValue(std::istream &is, std::set<Tag> const &skiptags) {
00218         (void)skiptags;
00219         return static_cast<TDE*>(this)->template ReadPreValue<TSwap>(is);
00220     }
00221     template <typename TDE, typename TSwap>
00222     std::istream &ReadValue(std::istream &is, std::set<Tag> const &skiptags) {
00223         (void)skiptags;
00224         return static_cast<TDE*>(this)->template ReadValue<TSwap>(is);
00225     }
00226     template <typename TDE, typename TSwap>
00227     std::istream &ReadValueWithLength(std::istream &is, VL &length, std::set<Tag> const &skiptags) {
00228         (void)skiptags;
00229         return static_cast<TDE*>(this)->template ReadValueWithLength<TSwap>(is, length);
00230     }
00231
00232     template <typename TDE, typename TSwap>
00233     std::istream &ReadWithLength(std::istream &is, VL &length) {
00234         return static_cast<TDE*>(this)->template ReadWithLength<TSwap>(is, length);
00235     }
00236
00237     template <typename TDE, typename TSwap>
00238     const std::ostream &Write(std::ostream &os) const {
00239         return static_cast<const TDE*>(this)->template Write<TSwap>(os);
00240     }
00241
00242 protected:
00243     Tag TagField;
00244     // This is the value read from the file, might be different from the length of Value Field
00245     VL ValueLengthField; // Can be 0xFFFFFFFF
00246
00247     // Value Representation
00248     VR VRField;
00249     typedef SmartPointer<Value> ValuePtr;
00250     ValuePtr ValueField;
00251
00252     void SetValueFieldLength( VL vl, bool readvalues );
00253 };
00254 //-----
00255 inline std::ostream& operator<<(std::ostream &os, const DataElement &val)
00256 {
00257     os << val.TagField;
00258     os << "\t" << val.VRField;
00259     os << "\t" << val.ValueLengthField;
00260     if( val.ValueField )
00261     {
00262         val.ValueField->Print( os << "\t" );
00263     }
00264     return os;
00265 }
00266
00267 inline bool operator!=(const DataElement& lhs, const DataElement& rhs)
00268 {
00269     return ! ( lhs == rhs );
00270 }
00271
00272 } // end namespace gdcm_ns
00273
00274 #endif //GDCMDATAELEMENT_H

```

11.129 gdcmDataSet.h File Reference

```
#include "gdcmDataElement.h"
#include "gdcmTag.h"
#include "gdcmVR.h"
#include "gdcmElement.h"
#include "gdcmMediaStorage.h"
#include <set>
#include <iterator>
#include "gdcmDataSet.txx"
Include dependency graph for gdcmDataSet.h:
```



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::DataElementException](#)
- class [gdcm::DataSet](#)

Class to represent a Data Set (which contains Data Elements)

Namespaces

- namespace [gdcm](#)

Functions

- `std::ostream & gdcm::operator<< (std::ostream &os, const DataSet &val)`

11.130 gdcmDataSet.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMDATASET_H
00015 #define GDCMDATASET_H
00016
00017 #include "gdcmDataElement.h"
00018 #include "gdcmTag.h"
00019 #include "gdcmVR.h"
00020 #include "gdcmElement.h"
00021 #include "gdcmMediaStorage.h"
00022
00023 #include <set>
00024 #include <iterator>
00025
00026 namespace gdcm_ns
00027 {
00028   class GDCM_EXPORT DataElementException : public std::exception {};
00029
00030   class PrivateTag;
00031   class GDCM_EXPORT DataSet
00032   {
00033   public:
00034     friend class CSAHeader;
00035     typedef std::set<DataElement> DataElementSet;
00036     typedef DataElementSet::const_iterator ConstIterator;
00037     typedef DataElementSet::iterator Iterator;
00038     typedef DataElementSet::size_type SizeType;
00039     //typedef typename DataElementSet::iterator iterator;
00040     ConstIterator Begin() const { return DES.begin(); }
00041     Iterator Begin() { return DES.begin(); }
00042     ConstIterator End() const { return DES.end(); }
00043     Iterator End() { return DES.end(); }
00044     const DataElementSet &GetDES() const { return DES; }
00045     DataElementSet &GetDES() { return DES; }
00046     void Clear() {
00047       DES.clear();
00048       gdcm_assert( DES.empty() );
00049     }
00050
00051     SizeType Size() const {
00052       return DES.size();
00053     }
00054
00055     void Print(std::ostream &os, std::string const &indent = "") const {
00056       // CT_Phillips_JPEG2K_Decompr_Problem.dcm has a SQ of length == 0
00057       //int s = DES.size();
00058       //gdcm_assert( s );
00059       //std::copy(DES.begin(), DES.end(),
00060       //  std::ostream_iterator<DataElement>(os, "\n"));
00061       ConstIterator it = DES.begin();
00062       for( ; it != DES.end(); ++it)
00063       {
00064         os << indent << *it << "\n";
00065       }
00066     }
00067
00068     template <typename TDE>
00069     unsigned int ComputeGroupLength(Tag const &tag) const
00070     {
00071       gdcm_assert( tag.GetElement() == 0x0 );
00072       const DataElement r(tag);
00073       ConstIterator it = DES.find(r);
00074       unsigned int res = 0;
00075       for( ++it; it != DES.end()

```

```

00100         && it->GetTag().GetGroup() == tag.GetGroup(); ++it)
00101     {
00102         gdcmm_assert( it->GetTag().GetElement() != 0x0 );
00103         gdcmm_assert( it->GetTag().GetGroup() == tag.GetGroup() );
00104         res += it->GetLength<TDE>();
00105     }
00106     return res;
00107 }
00108
00109 template <typename TDE>
00110 VL GetLength() const {
00111     if( DES.empty() ) return 0;
00112     gdcmm_assert( !DES.empty() );
00113     VL ll = 0;
00114     gdcmm_assert( ll == 0 );
00115     ConstIterator it = DES.begin();
00116     for( ; it != DES.end(); ++it )
00117     {
00118         gdcmm_assert( !(it->GetLength<TDE>().IsUndefined()) );
00119         if ( it->GetTag() != Tag(0xfffe,0xe00d) )
00120         {
00121             ll += it->GetLength<TDE>();
00122         }
00123     }
00124     return ll;
00125 }
00126 void Insert(const DataElement& de) {
00127     // FIXME: there is a special case where a dataset can have value < 0x8, see:
00128     // $ gdcmdump --csa gdcmmData/SIEMENS-JPEG-CorruptFrag.dcm
00129     if( de.GetTag().GetGroup() >= 0x0008 || de.GetTag().GetGroup() == 0x4 )
00130     {
00131         // prevent user error:
00132         if( de.GetTag() == Tag(0xfffe,0xe00d)
00133            || de.GetTag() == Tag(0xfffe,0xe0dd)
00134            || de.GetTag() == Tag(0xfffe,0xe000) )
00135         {
00136             // do nothing
00137         }
00138         else
00139         {
00140             InsertDataElement( de );
00141         }
00142     }
00143     else
00144     {
00145         gdcmmErrorMacro( "Cannot add element with group < 0x0008 and != 0x4 in the dataset: " « de.GetTag()
00146     );
00147     }
00148 }
00149 void Replace(const DataElement& de) {
00150     ConstIterator it = DES.find(de);
00151     if( it != DES.end() )
00152     {
00153         // detect loop:
00154         gdcmmAssertAlwaysMacro( &*it != &de );
00155         DES.erase(it);
00156     }
00157     DES.insert(de);
00158 }
00159 void ReplaceEmpty(const DataElement& de) {
00160     ConstIterator it = DES.find(de);
00161     if( it != DES.end() && it->IsEmpty() )
00162     {
00163         // detect loop:
00164         gdcmmAssertAlwaysMacro( &*it != &de );
00165         DES.erase(it);
00166     }
00167     DES.insert(de);
00168 }
00169 SizeType Remove(const Tag& tag) {
00170     DataElementSet::size_type count = DES.erase(tag);
00171     gdcmm_assert( count == 0 || count == 1 );
00172     return count;
00173 }
00174 //DataElement& GetDataElement(const Tag &t) {
00175 //    DataElement r(t);
00176 //    Iterator it = DES.find(r);
00177 //    if( it != DES.end() )
00178 //        return *it;
00179 //    return GetDEEnd();
00180 // }

```

```

00188     const DataElement& GetDataElement(const Tag &t) const {
00189         const DataElement r(t);
00190         ConstIterator it = DES.find(r);
00191         if( it != DES.end() )
00192             return *it;
00193         return GetDEEnd();
00194     }
00195     const DataElement& operator[] (const Tag &t) const { return GetDataElement(t); }
00196     const DataElement& operator() (uint16_t group, uint16_t element) const { return GetDataElement(
Tag(group,element) ); }
00197
00200     std::string GetPrivateCreator(const Tag &t) const;
00201
00202     PrivateTag GetPrivateTag(const Tag &t) const;
00203
00204
00206     bool FindDataElement(const PrivateTag &t) const;
00208     const DataElement& GetDataElement(const PrivateTag &t) const;
00209
00210     // DUMB: this only search within the level of the current DataSet
00211     bool FindDataElement(const Tag &t) const {
00212         const auto it = GetDataElement(t);
00213         // Return if tag is found
00214         return it != GetDEEnd();
00215     }
00216
00217     // WARNING:
00218     // This only search at the same level as the DataSet is !
00219     const DataElement& FindNextDataElement(const Tag &t) const {
00220         const DataElement r(t);
00221         ConstIterator it = DES.lower_bound(r);
00222         if( it != DES.end() )
00223             return *it;
00224         return GetDEEnd();
00225     }
00226
00228     bool IsEmpty() const { return DES.empty(); }
00229
00230     DataSet& operator=(DataSet const &)
00231     = default;
00232
00233     template <typename TDE, typename TSwap>
00234     std::istream &ReadNested(std::istream &is);
00235
00236     template <typename TDE, typename TSwap>
00237     std::istream &Read(std::istream &is);
00238
00239     template <typename TDE, typename TSwap>
00240     std::istream &ReadUpToTag(std::istream &is, const Tag &t, std::set<Tag> const &skiptags);
00241
00242     template <typename TDE, typename TSwap>
00243     std::istream &ReadUpToTagWithLength(std::istream &is, const Tag &t, std::set<Tag> const &skiptags, VL &
length);
00244
00245     template <typename TDE, typename TSwap>
00246     std::istream &ReadSelectedTags(std::istream &is, const std::set<Tag> &tags, bool readvalues = true);
00247     template <typename TDE, typename TSwap>
00248     std::istream &ReadSelectedTagsWithLength(std::istream &is, const std::set<Tag> &tags, VL &length, bool
readvalues = true);
00249
00250     template <typename TDE, typename TSwap>
00251     std::istream &ReadSelectedPrivateTags(std::istream &is, const std::set<PrivateTag> &tags, bool
readvalues = true);
00252     template <typename TDE, typename TSwap>
00253     std::istream &ReadSelectedPrivateTagsWithLength(std::istream &is, const std::set<PrivateTag> &tags, VL
&length, bool readvalues = true);
00254
00255     template <typename TDE, typename TSwap>
00256     std::ostream const &Write(std::ostream &os) const;
00257
00258     template <typename TDE, typename TSwap>
00259     std::istream &ReadWithLength(std::istream &is, VL &length);
00260
00261     MediaStorage GetMediaStorage() const;
00262
00263 protected:
00264     /* GetDEEnd is a Win32 only issue, one cannot use a dllexported
00265      * static member data in an inline function, otherwise symbol
00266      * will get reported as missing in any dll using the inlined function
00267      */
00268     const DataElement& GetDEEnd() const;
00269

```

```

00270 // This function is not safe, it does not check for the value of the tag
00271 // so depending whether we are getting called from a dataset or file meta header
00272 // the condition is different
00273 void InsertDataElement(const DataElement& de) {
00274     //if( de.GetTag() == Tag(0xffff,0xe00d) ) return;
00275     //if( de.GetTag() == Tag(0xffff,0xe0dd) ) return;
00276 #ifndef NDEBUB
00277     std::pair<Iterator,bool> pr = DES.insert(de);
00278     if( pr.second == false )
00279     {
00280         gdcmWarningMacro( "DataElement: " « de « " was already found, skipping duplicate entry.\n"
00281             "Original entry kept is: " « *pr.first );
00282     }
00283 #else
00284     DES.insert(de);
00285 #endif
00286     gdcm_assert( de.IsEmpty() || de.GetVL() == de.GetValue().GetLength() );
00287 }
00288
00289 protected:
00290 // Internal function, that will compute the actual Tag (if found) of
00291 // a requested Private Tag (XXXX,YY,"PRIVATE")
00292 Tag ComputeDataElement(const PrivateTag & t) const;
00293
00294 private:
00295     DataElementSet DES;
00296     static DataElement DEEnd;
00297     friend std::ostream& operator<<(std::ostream &_os, const DataSet &);
00298 };
00299 //-----
00300 inline std::ostream& operator<<(std::ostream &os, const DataSet &val)
00301 {
00302     val.Print(os);
00303     return os;
00304 }
00305
00306 #if defined(SWIGPYTHON) || defined(SWIGCSHARP) || defined(SWIGJAVA) || defined(SWIGPHP)
00307 /*
00308  * HACK: I need this temp class to be able to manipulate a std::set from python,
00309  * swig does not support wrapping of simple class like std::set...
00310  */
00311 class SWIGDataSet
00312 {
00313 public:
00314     SWIGDataSet(DataSet &des):Internal(des),it(des.Begin()) {}
00315     const DataElement& GetCurrent() const { return *it; }
00316     void Start() { it = Internal.Begin(); }
00317     bool IsAtEnd() const { return it == Internal.End(); }
00318     void Next() { ++it; }
00319 private:
00320     DataSet & Internal;
00321     DataSet::ConstIterator it;
00322 };
00323 #endif /* SWIG */
00324
00325 } // end namespace gdcm_ns
00326
00327 #include "gdcmDataSet.txx"
00328
00329 #endif //GDCMDATASET_H

```

11.131 gdcmDataSetEvent.h File Reference

```

#include "gdcmEvent.h"
#include "gdcmDataSet.h"

```

[illegible]

- class `gdcm::DataSetEvent`
DataSetEvent.

- namespace **gdcm**

[Go to the documentation of this file.](#)

Generated by Doxygen

Classes

- class [gdcm::Element< TVR, TVM >](#)
Element class.
- class [gdcm::Element< TVR, VM::VM1_2 >](#)
- class [gdcm::Element< TVR, VM::VM1_n >](#)
- class [gdcm::Element< TVR, VM::VM2_2n >](#)
- class [gdcm::Element< TVR, VM::VM2_n >](#)
- class [gdcm::Element< TVR, VM::VM3_3n >](#)
- class [gdcm::Element< TVR, VM::VM3_4 >](#)
- class [gdcm::Element< TVR, VM::VM3_n >](#)
- class [gdcm::Element< VR::AS, VM::VM5 >](#)
- class [gdcm::Element< VR::OB, VM::VM1 >](#)
- class [gdcm::Element< VR::OW, VM::VM1 >](#)
- class [gdcm::ElementDisableCombinations< TVR, TVM >](#)
A class which is used to produce compile errors for an invalid combination of template parameters.
- class [gdcm::ElementDisableCombinations< VR::OB, VM::VM1_n >](#)
- class [gdcm::ElementDisableCombinations< VR::OW, VM::VM1_n >](#)
- class [gdcm::EncodingImplementation< VR::VRASCII >](#)
- class [gdcm::EncodingImplementation< VR::VRBINARY >](#)
- struct [gdcm::ignore_char](#)

Namespaces

- namespace [gdcm](#)

Functions

- static int [gdcm::add1](#) (char *buf, int n)
- [ignore_char](#) const [gdcm::backslash](#) ("\\")
- static void [gdcm::clean](#) (char *mant)
- static int [gdcm::doround](#) (char *buf, unsigned int n)
- std::istream & [gdcm::operator>>](#) (std::istream &in, [ignore_char](#) const &ic)
- static int [gdcm::roundat](#) (char *buf, size_t bufLen, unsigned int i, int iexp)
- template<typename Float>
static void [gdcm::x16printf](#) (char *buf, int size, Float f)

11.134 gdcmElement.h

[Go to the documentation of this file.](#)

```

00001  /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR

```

```

00011     PURPOSE.  See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMELEMENT_H
00015 #define GDCMELEMENT_H
00016
00017 #include "gdcmTypes.h"
00018 #include "gdcmVR.h"
00019 #include "gdcmTag.h"
00020 #include "gdcmVM.h"
00021 #include "gdcmByteValue.h"
00022 #include "gdcmDataElement.h"
00023 #include "gdcmSwapper.h"
00024
00025 #include <string>
00026 #include <vector>
00027 #include <sstream>
00028 #include <limits>
00029 #include <cmath>
00030 #include <cstring>
00031
00032 namespace gdcm_ns
00033 {
00034
00035 // Forward declaration
00041 template<long long T> class EncodingImplementation;
00042
00043
00051 template <long long TVR, int TVM>
00052 class ElementDisableCombinations {};
00053 template <>
00054 class ElementDisableCombinations<VR::OB, VM::VMI_n> {};
00055 template <>
00056 class ElementDisableCombinations<VR::OW, VM::VMI_n> {};
00057 // Make it impossible to compile these other cases
00058 template <int TVM>
00059 class ElementDisableCombinations<VR::OB, TVM>;
00060 template <int TVM>
00061 class ElementDisableCombinations<VR::OW, TVM>;
00062
00068 template<long long TVR, int TVM>
00069 class Element
00070 {
00071     enum { ElementDisableCombinationsCheck = sizeof ( ElementDisableCombinations<TVR, TVM> ) };
00072 public:
00073     typename VRToType<TVR>::Type Internal[VMToLength<TVM>::Length];
00074     typedef typename VRToType<TVR>::Type Type;
00075
00076     static VR GetVR() { return (VR::VRType)TVR; }
00077     static VM GetVM() { return (VM::VMType)TVM; }
00078
00079     unsigned long GetLength() const {
00080         return VMToLength<TVM>::Length;
00081     }
00082     // Implementation of Print is common to all Mode (ASCII/Binary)
00083     // TODO: Can we print a \ when in ASCII...well I don't think so
00084     // it would mean we used a bad VM then, right?
00085     void Print(std::ostream &_os) const {
00086         _os << Internal[0]; // VM is at least guarantee to be one
00087         for(int i=1; i<VMToLength<TVM>::Length; ++i)
00088             _os << ", " << Internal[i];
00089     }
00090
00091     const typename VRToType<TVR>::Type *GetValues() const {
00092         return Internal;
00093     }
00094     const typename VRToType<TVR>::Type &GetValue(unsigned int idx = 0) const {
00095         gdcm_assert( idx < VMToLength<TVM>::Length );
00096         return Internal[idx];
00097     }
00098     typename VRToType<TVR>::Type &GetValue(unsigned int idx = 0) {
00099         gdcm_assert( idx < VMToLength<TVM>::Length );
00100         return Internal[idx];
00101     }
00102     typename VRToType<TVR>::Type operator[] (unsigned int idx) const {
00103         return GetValue(idx);
00104     }
00105     void SetValue(typename VRToType<TVR>::Type v, unsigned int idx = 0) {
00106         gdcm_assert( idx < VMToLength<TVM>::Length );
00107         Internal[idx] = v;
00108     }

```

```

00109
00110 void SetFromDataElement(DataElement const &de) {
00111     const ByteValue *bv = de.GetByteValue();
00112     if( !bv ) return;
00113 #ifdef GDCM_WORDS_BIGENDIAN
00114     if( de.GetVR() == VR::UN /*|| de.GetVR() == VR::INVALID*/ )
00115 #else
00116     if( de.GetVR() == VR::UN || de.GetVR() == VR::INVALID )
00117 #endif
00118     {
00119         Set( de.GetValue() );
00120     }
00121     else
00122     {
00123         SetNoSwap( de.GetValue() );
00124     }
00125 }
00126
00127 DataElement GetAsDataElement() const {
00128     DataElement ret;
00129     std::ostringstream os;
00130     EncodingImplementation<VRToEncoding<TVR>::Mode>::Write(Internal,
00131         GetLength(), os);
00132     ret.SetVR( (VR::VRType)TVR );
00133     gdcm_assert( ret.GetVR() != VR::SQ );
00134     if( (VR::VRType)VRToEncoding<TVR>::Mode == VR::VRASCII )
00135     {
00136         if( GetVR() != VR::UI )
00137         {
00138             if( os.str().size() % 2 )
00139             {
00140                 os << " ";
00141             }
00142         }
00143     }
00144     VL::Type osStrSize = (VL::Type)os.str().size();
00145     ret.SetByteValue( os.str().c_str(), osStrSize );
00146
00147     return ret;
00148 }
00149
00150 void Read(std::istream &_is) {
00151     return EncodingImplementation<VRToEncoding<TVR>::Mode>::Read(Internal,
00152         GetLength(), _is);
00153 }
00154 void Write(std::ostream &_os) const {
00155     return EncodingImplementation<VRToEncoding<TVR>::Mode>::Write(Internal,
00156         GetLength(), _os);
00157 }
00158
00159 // FIXME: remove this function
00160 // this is only used in gdcm::SplitMosaicFilter / to pass value of a CSAElement
00161 void Set(Value const &v) {
00162     const ByteValue *bv = dynamic_cast<const ByteValue*>(&v);
00163     if( bv ) {
00164         //memcpy(Internal, bv->GetPointer(), bv->GetLength());
00165         std::stringstream ss;
00166         std::string s = std::string( bv->GetPointer(), bv->GetLength() );
00167         ss.str( s );
00168         EncodingImplementation<VRToEncoding<TVR>::Mode>::Read(Internal,
00169             GetLength(), ss);
00170     }
00171 }
00172 protected:
00173 void SetNoSwap(Value const &v) {
00174     const ByteValue *bv = dynamic_cast<const ByteValue*>(&v);
00175     gdcm_assert( bv ); // That would be bad...
00176     //memcpy(Internal, bv->GetPointer(), bv->GetLength());
00177     std::stringstream ss;
00178     std::string s = std::string( bv->GetPointer(), bv->GetLength() );
00179     ss.str( s );
00180     EncodingImplementation<VRToEncoding<TVR>::Mode>::ReadNoSwap(Internal,
00181         GetLength(), ss);
00182 }
00183 };
00184
00185 struct ignore_char {
00186     ignore_char(char c): m_char(c) {}
00187     char m_char;
00188 };
00189 ignore_char const backslash('\\');

```

```

00190
00191 inline std::istream& operator> (std::istream& in, ignore_char const& ic) {
00192     if (!in.eof())
00193         in.clear(in.rdstate() & ~std::ios_base::failbit);
00194     if (in.get() != ic.m_char)
00195         in.setstate(std::ios_base::failbit);
00196     return in;
00197 }
00198
00199
00200 // Implementation to perform formatted read and write
00201 template<> class EncodingImplementation<VR::VRASCII> {
00202 public:
00203     template<typename T> // FIXME this should be VRToType<TVR>::Type
00204     static inline void ReadComputeLength(T* data, unsigned int &length,
00205                                         std::istream &_is) {
00206         gdcmm_assert( data );
00207         //gdcmm_assert( length ); // != 0
00208         length = 0;
00209         gdcmm_assert( !_is );
00210 #if 0
00211         char sep;
00212         while( !_is >> data[length++] )
00213         {
00214             // Get the separator in between the values
00215             gdcmm_assert( !_is );
00216             _is.get(sep);
00217             gdcmm_assert( sep == '\\\\' || sep == ' ' ); // FIXME: Bad use of assert
00218             if( sep == ' ' ) length--; // FIXME
00219         }
00220 #else
00221         while( !_is >> std::ws >> data[length++] >> std::ws >> backslash )
00222         {
00223         }
00224 #endif
00225     }
00226
00227     template<typename T> // FIXME this should be VRToType<TVR>::Type
00228     static inline void Read(T* data, unsigned long length,
00229                             std::istream &_is) {
00230         gdcmm_assert( data );
00231         gdcmm_assert( length ); // != 0
00232         gdcmm_assert( !_is );
00233         // FIXME BUG: what if >> operation fails ?
00234         // gdcmmData/MR00010001.dcm / SpacingBetweenSlices
00235         _is >> std::ws >> data[0];
00236         char sep;
00237         //std::cout << "GetLength: " << af->GetLength() << std::endl;
00238         for(unsigned long i=1; i<length;++i) {
00239             //gdcmm_assert( !_is );
00240             // Get the separator in between the values
00241             _is >> std::ws >> sep; // _is.get(sep);
00242             //gdcmm_assert( sep == '\\\\' ); // FIXME: Bad use of assert
00243             _is >> std::ws >> data[i];
00244         }
00245     }
00246
00247     template<typename T>
00248     static inline void ReadNoSwap(T* data, unsigned long length,
00249                                   std::istream &_is) {
00250         Read(data,length,_is);
00251     }
00252     template<typename T>
00253     static inline void Write(const T* data, unsigned long length,
00254                             std::ostream &_os) {
00255         gdcmm_assert( data );
00256         gdcmm_assert( length );
00257         gdcmm_assert( !_os );
00258         _os << data[0];
00259         for(unsigned long i=1; i<length; ++i) {
00260             gdcmm_assert( !_os );
00261             _os << "\\\" << data[i];
00262         }
00263     }
00264 };
00265
00266 //define VRDS16ILLEGAL
00267
00268 #ifdef VRDS16ILLEGAL
00269 template < typename Float >
00270 std::string to_string ( Float data ) {

```

```

00271     std::stringstream in;
00272     // in.imbue(std::locale::classic()); // This is not required AFAIK
00273     int const digits =
00274         static_cast< int >(
00275             - std::log( std::numeric_limits<Float>::epsilon() )
00276             / static_cast< Float >( std::log( 10.0 ) ) );
00277     if ( in << std::dec << std::setprecision( /*2*/digits) << data ) {
00278         return ( in.str() );
00279     } else {
00280         throw "Impossible Conversion"; // should not happen ...
00281     }
00282 }
00283 #else
00284 //
00285 http://stackoverflow.com/questions/32631178/writing-ieee-754-1985-double-as-ascii-on-a-limited-16-bytes-string
00286 static inline void clean(char *mant) {
00287     char *ix = mant + strlen(mant) - 1;
00288     while (('0' == *ix) && (ix > mant)) {
00289         *ix-- = '\0';
00290     }
00291     if ('.' == *ix) {
00292         *ix = '\0';
00293     }
00294 }
00295
00296 static int add1(char *buf, int n) {
00297     if (n < 0) return 1;
00298     if (buf[n] == '9') {
00299         buf[n] = '0';
00300         return add1(buf, n-1);
00301     }
00302     else {
00303         buf[n] = (char)(buf[n] + 1);
00304     }
00305     return 0;
00306 }
00307
00308 static int doround(char *buf, unsigned int n) {
00309     char c;
00310     if (n >= strlen(buf)) return 0;
00311     c = buf[n];
00312     buf[n] = 0;
00313     if ((c >= '5') && (c <= '9')) return add1(buf, n-1);
00314     return 0;
00315 }
00316
00317 #if defined(_MSC_VER) && (_MSC_VER < 1900)
00318 #define snprintf _snprintf
00319 #endif
00320
00321 static int roundat(char *buf, size_t bufLen, unsigned int i, int iexp) {
00322     if (doround(buf, i) != 0) {
00323         iexp += 1;
00324         switch(iexp) {
00325             case -2:
00326                 strcpy(buf, ".01");
00327                 break;
00328             case -1:
00329                 strcpy(buf, ".1");
00330                 break;
00331             case 0:
00332                 strcpy(buf, "1.");
00333                 break;
00334             case 1:
00335                 strcpy(buf, "10");
00336                 break;
00337             case 2:
00338                 strcpy(buf, "100");
00339                 break;
00340             default:
00341                 snprintf(buf, bufLen, "1e%d", iexp);
00342         }
00343         return 1;
00344     }
00345     return 0;
00346 }
00347
00348 template < typename Float >
00349 static void x16printf(char *buf, int size, Float f) {
00350     char line[40];

```

```

00351 char *mant = line + 1;
00352 int iexp, lexp, i;
00353 char exp[6];
00354
00355 if (f < 0) {
00356     f = -f;
00357     size -= 1;
00358     *buf++ = '-';
00359 }
00360 snprintf(line, sizeof(line), "%1.16e", f);
00361 if (line[0] == '-') {
00362     f = -f;
00363     size -= 1;
00364     *buf++ = '-';
00365     snprintf(line, sizeof(line), "%1.16e", f);
00366 }
00367 *mant = line[0];
00368 i = (int)strcspn(mant, "eE");
00369 mant[i] = '\0';
00370 iexp = (int)strtol(mant + i + 1, nullptr, 10);
00371 lexp = snprintf(exp, sizeof(exp), "%d", iexp);
00372 if ((iexp >= size) || (iexp < -3)) {
00373     i = roundat(mant, sizeof(line) - 1, size - 1 - lexp, iexp);
00374     if (i == 1) {
00375         strcpy(buf, mant);
00376         return;
00377     }
00378     buf[0] = mant[0];
00379     buf[1] = '.';
00380     strncpy(buf + i + 2, mant + 1, size - 2 - lexp);
00381     buf[size - lexp] = 0;
00382     clean(buf);
00383     strcat(buf, exp);
00384 }
00385 else if (iexp >= size - 2) {
00386     roundat(mant, sizeof(line) - 1, iexp + 1, iexp);
00387     strcpy(buf, mant);
00388 }
00389 else if (iexp >= 0) {
00390     i = roundat(mant, sizeof(line) - 1, size - 1, iexp);
00391     if (i == 1) {
00392         strcpy(buf, mant);
00393         return;
00394     }
00395     memcpy(buf, mant, iexp + 1);
00396     buf[iexp + 1] = '.';
00397     strncpy(buf + iexp + 2, mant + iexp + 1, size - iexp - 1);
00398     buf[size] = 0;
00399     clean(buf);
00400 }
00401 else {
00402     int j;
00403     i = roundat(mant, sizeof(line) - 1, size + 1 + iexp, iexp);
00404     if (i == 1) {
00405         strcpy(buf, mant);
00406         return;
00407     }
00408     buf[0] = '.';
00409     for (j=0; j< -1 - iexp; j++) {
00410         buf[j+1] = '0';
00411     }
00412     memcpy(buf - iexp, mant, size + 1 + iexp);
00413     buf[size] = 0;
00414     clean(buf);
00415 }
00416 }
00417 #if defined(_MSC_VER) && (_MSC_VER < 1900)
00418 #undef snprintf
00419 #endif
00420
00421 #endif
00422
00423 template<> inline void EncodingImplementation<VR::VRASCII>::Write(const double* data, unsigned long
length, std::ostream &_os) {
00424     gdcmm_assert( data );
00425     gdcmm_assert( length );
00426     gdcmm_assert( _os );
00427 #ifdef VRDS16ILLEGAL
00428     _os << to_string(data[0]);
00429 #else
00430     char buf[16+1];

```

```

00431     x16printf(buf, 16, data[0]);
00432     _os « buf;
00433 #endif
00434     for(unsigned long i=1; i<length; ++i) {
00435         gdcm_assert( _os );
00436 #ifdef VRDS16ILLEGAL
00437         _os « "\\\" « to_string(data[i]);
00438 #else
00439         x16printf(buf, 16, data[i]);
00440         _os « "\\\" « buf;
00441 #endif
00442     }
00443 }
00444
00445
00446 // Implementation to perform binary read and write
00447 // TODO rewrite operation so that either:
00448 // #1. dummy implementation use a pointer to Internal and do ++p (faster)
00449 // #2. Actually do some meta programming to unroll the loop
00450 // (no notion of order in VM ...)
00451 template<> class EncodingImplementation<VR::VRBINARY> {
00452 public:
00453     template<typename T> // FIXME this should be VRToType<TVR>::Type
00454         static inline void ReadComputeLength(T* data, unsigned int &length,
00455             std::istream &_is) {
00456             const unsigned int type_size = sizeof(T);
00457             gdcm_assert( data ); // Can we read from pointer ?
00458             //gdcm_assert( length );
00459             length /= type_size;
00460             gdcm_assert( _is ); // Is stream valid ?
00461             _is.read( reinterpret_cast<char*>(data+0), type_size);
00462             for(unsigned long i=1; i<length; ++i) {
00463                 gdcm_assert( _is );
00464                 _is.read( reinterpret_cast<char*>(data+i), type_size );
00465             }
00466         }
00467     template<typename T>
00468     static inline void ReadNoSwap(T* data, unsigned long length,
00469         std::istream &_is) {
00470         const unsigned int type_size = sizeof(T);
00471         gdcm_assert( data ); // Can we read from pointer ?
00472         gdcm_assert( length );
00473         gdcm_assert( _is ); // Is stream valid ?
00474         _is.read( reinterpret_cast<char*>(data+0), type_size);
00475         for(unsigned long i=1; i<length; ++i) {
00476             if( _is )
00477                 _is.read( reinterpret_cast<char*>(data+i), type_size );
00478         }
00479         //ByteSwap<T>::SwapRangeFromSwapCodeIntoSystem(data,
00480         // _is.GetSwapCode(), length);
00481         //SwapperNoOp::SwapArray(data,length);
00482     }
00483     template<typename T>
00484     static inline void Read(T* data, unsigned long length,
00485         std::istream &_is) {
00486         const unsigned int type_size = sizeof(T);
00487         gdcm_assert( data ); // Can we read from pointer ?
00488         gdcm_assert( length );
00489         gdcm_assert( _is ); // Is stream valid ?
00490         _is.read( reinterpret_cast<char*>(data+0), type_size);
00491         for(unsigned long i=1; i<length; ++i) {
00492             if( _is )
00493                 _is.read( reinterpret_cast<char*>(data+i), type_size );
00494         }
00495         //ByteSwap<T>::SwapRangeFromSwapCodeIntoSystem(data,
00496         // _is.GetSwapCode(), length);
00497         SwapperNoOp::SwapArray(data,length);
00498     }
00499     template<typename T>
00500     static inline void Write(const T* data, unsigned long length,
00501         std::ostream &_os) {
00502         const unsigned int type_size = sizeof(T);
00503         gdcm_assert( data ); // Can we write into pointer ?
00504         gdcm_assert( length );
00505         gdcm_assert( _os ); // Is stream valid ?
00506         //ByteSwap<T>::SwapRangeFromSwapCodeIntoSystem((T*)data,
00507         // _os.GetSwapCode(), length);
00508         T swappedData = SwapperNoOp::Swap(data[0]);
00509         _os.write( reinterpret_cast<const char*>(&swappedData), type_size);
00510         for(unsigned long i=1; i<length; ++i) {
00511             gdcm_assert( _os );

```

```

00512         swappedData = SwapperNoOp::Swap(data[i]);
00513         _os.write( reinterpret_cast<const char*>(&swappedData), type_size );
00514     }
00515     //ByteSwap<T>::SwapRangeFromSwapCodeIntoSystem((T*)data,
00516     // _os.GetSwapCode(), length);
00517 }
00518 };
00519
00520 // For particular case for ASCII string
00521 // WARNING: This template explicitly instantiates a particular
00522 // EncodingImplementation THEREFORE it is required to be declared after the
00523 // EncodingImplementation is needs (doh!)
00524 #if 0
00525 template<int TVM>
00526 class Element<TVM>
00527 {
00528 public:
00529     Element(const char array[])
00530     {
00531         unsigned int i = 0;
00532         const char sep = '\\';
00533         std::string sarray = array;
00534         std::string::size_type pos1 = 0;
00535         std::string::size_type pos2 = sarray.find(sep, pos1+1);
00536         while(pos2 != std::string::npos)
00537         {
00538             Internal[i++] = sarray.substr(pos1, pos2-pos1);
00539             pos1 = pos2+1;
00540             pos2 = sarray.find(sep, pos1+1);
00541         }
00542         Internal[i] = sarray.substr(pos1, pos2-pos1);
00543         // Shouldn't we do the contrary, since we know how many separators
00544         // (and default behavior is to discard anything after the VM declared
00545         gdcmm_assert( GetLength()-1 == i );
00546     }
00547
00548     unsigned long GetLength() const {
00549         return VMToLength<TVM>::Length;
00550     }
00551     // Implementation of Print is common to all Mode (ASCII/Binary)
00552     void Print(std::ostream &_os) const {
00553         _os << Internal[0]; // VM is at least guarantee to be one
00554         for(int i=1; i<VMToLength<TVM>::Length; ++i)
00555             _os << ", " << Internal[i];
00556     }
00557
00558     void Read(std::istream &_is) {
00559         EncodingImplementation<VR::VRASCII>::Read(Internal, GetLength(), _is);
00560     }
00561     void Write(std::ostream &_os) const {
00562         EncodingImplementation<VR::VRASCII>::Write(Internal, GetLength(), _os);
00563     }
00564 private:
00565     typename String Internal[VMToLength<TVM>::Length];
00566 };
00567
00568 template< int TVM>
00569 class Element<VR::PN, TVM> : public StringElement<TVM>
00570 {
00571     enum { ElementDisableCombinationsCheck = sizeof ( ElementDisableCombinations<VR::PN, TVM> ) };
00572 };
00573 #endif
00574
00575 // Implementation for the undefined length (dynamically allocated array)
00576 template<long long TVR>
00577 class Element<TVR, VM::VM1_n>
00578 {
00579     enum { ElementDisableCombinationsCheck = sizeof ( ElementDisableCombinations<TVR, VM::VM1_n> ) };
00580 public:
00581     // This the way to prevent default initialization
00582     explicit Element() { Internal=nullptr; Length=0; Save = false; }
00583     ~Element() {
00584         if( Save ) {
00585             delete[] Internal;
00586         }
00587         Internal = nullptr;
00588     }
00589
00590     static VR GetVR() { return (VR::VRType)TVR; }
00591     static VM GetVM() { return VM::VM1_n; }
00592

```



```

00593 // Length manipulation
00594 // SetLength should really be protected anyway...all operation
00595 // should go through SetArray
00596 unsigned long GetLength() const { return Length; }
00597 typedef typename VRToType<TVR>::Type Type;
00598
00599 void SetLength(unsigned long len) {
00600     const unsigned int size = sizeof(Type);
00601     if( len ) {
00602         if( len > Length ) {
00603             // perform realloc
00604             gdcm_assert( (len / size) * size == len );
00605             Type *internal = new Type[len / size];
00606             gdcm_assert( Save == false );
00607             Save = true; // ???
00608             if( Internal )
00609             {
00610                 memcpy(internal, Internal, len);
00611                 delete[] Internal;
00612             }
00613             Internal = internal;
00614         }
00615     }
00616     Length = len / size;
00617 }
00618
00619 // If save is set to zero user should not delete the pointer
00620 //void SetArray(const typename VRToType<TVR>::Type *array, int len, bool save = false)
00621 void SetArray(const Type *array, unsigned long len,
00622     bool save = false) {
00623     if( save ) {
00624         SetLength(len); // realloc
00625         memcpy(Internal, array, len/*sizeof(Type)*/);
00626         gdcm_assert( Save == false );
00627     }
00628     else {
00629         // TODO rewrite this stupid code:
00630         gdcm_assert( Length == 0 );
00631         gdcm_assert( Internal == nullptr );
00632         gdcm_assert( Save == false );
00633         Length = len / sizeof(Type);
00634         //gdcm_assert( (len / sizeof(Type)) * sizeof(Type) == len );
00635         // MR00010001.dcm is a tough kid: 0019,105a is supposed to be VR::FL, VM::VM3 but
00636         // length is 14 bytes instead of 12 bytes. Simply consider value is total garbage.
00637         if( (len / sizeof(Type)) * sizeof(Type) != len ) { Internal = nullptr; Length = 0; }
00638         else Internal = const_cast<Type*>(array);
00639     }
00640     Save = save;
00641 }
00642 void SetValue(typename VRToType<TVR>::Type v, unsigned int idx = 0) {
00643     gdcm_assert( idx < Length );
00644     Internal[idx] = v;
00645 }
00646 const typename VRToType<TVR>::Type &GetValue(unsigned int idx = 0) const {
00647     gdcm_assert( idx < Length );
00648     return Internal[idx];
00649 }
00650 typename VRToType<TVR>::Type &GetValue(unsigned int idx = 0) {
00651     //gdcm_assert( idx < Length );
00652     return Internal[idx];
00653 }
00654 typename VRToType<TVR>::Type operator[] (unsigned int idx) const {
00655     return GetValue(idx);
00656 }
00657 void Set(Value const &v) {
00658     const ByteValue *bv = dynamic_cast<const ByteValue*>(&v);
00659     gdcm_assert( bv ); // That would be bad...
00660     if( (VR::VRType) (VRToEncoding<TVR>::Mode) == VR::VRBINARY )
00661     {
00662         const Type* array = (const Type*)bv->GetVoidPointer();
00663         if( array ) {
00664             gdcm_assert( array ); // That would be bad...
00665             gdcm_assert( Internal == nullptr );
00666             SetArray(array, bv->GetLength() ); }
00667     }
00668     else
00669     {
00670         std::stringstream ss;
00671         std::string s = std::string( bv->GetPointer(), bv->GetLength() );
00672         ss.str( s );
00673         EncodingImplementation<VRToEncoding<TVR>::Mode>::Read(Internal,

```

```

00674         GetLength(),ss);
00675     }
00676 }
00677 void SetFromDataElement(DataElement const &de) {
00678     const ByteValue *bv = de.GetByteValue();
00679     if( !bv ) return;
00680 #ifdef GDCM_WORDS_BIGENDIAN
00681     if( de.GetVR() == VR::UN /*|| de.GetVR() == VR::INVALID*/ )
00682 #else
00683     if( de.GetVR() == VR::UN || de.GetVR() == VR::INVALID )
00684 #endif
00685     {
00686         Set(de.GetValue());
00687     }
00688     else
00689     {
00690         SetNoSwap(de.GetValue());
00691     }
00692 }
00693
00694
00695 // Need to be placed after definition of EncodingImplementation<VR::VRASCII>
00696 void WriteASCII(std::ostream &os) const {
00697     return EncodingImplementation<VR::VRASCII>::Write(Internal, GetLength(), os);
00698 }
00699
00700 // Implementation of Print is common to all Mode (ASCII/Binary)
00701 void Print(std::ostream &_os) const {
00702     gdcml_assert( Length );
00703     gdcml_assert( Internal );
00704     _os << Internal[0]; // VM is at least guarantee to be one
00705     const unsigned long length = GetLength() < 25 ? GetLength() : 25;
00706     for(unsigned long i=1; i<length; ++i)
00707         _os << ", " << Internal[i];
00708 }
00709 void Read(std::istream &_is) {
00710     if( !Internal ) return;
00711     EncodingImplementation<VRToEncoding<TVR>::Mode>::Read(Internal,
00712         GetLength(),_is);
00713 }
00714 //void ReadComputeLength(std::istream &_is) {
00715 //    if( !Internal ) return;
00716 //    EncodingImplementation<VRToEncoding<TVR>::Mode>::ReadComputeLength(Internal,
00717 //        Length,_is);
00718 // }
00719 void Write(std::ostream &_os) const {
00720     EncodingImplementation<VRToEncoding<TVR>::Mode>::Write(Internal,
00721         GetLength(),_os);
00722 }
00723
00724 DataElement GetAsDataElement() const {
00725     DataElement ret;
00726     ret.SetVR( (VR::VRType)TVR );
00727     gdcml_assert( ret.GetVR() != VR::SQ );
00728     if( Internal )
00729     {
00730         std::ostringstream os;
00731         EncodingImplementation<VRToEncoding<TVR>::Mode>::Write(Internal,
00732             GetLength(),os);
00733         if( (VR::VRType)VRToEncoding<TVR>::Mode == VR::VRASCII )
00734         {
00735             if( GetVR() != VR::UI )
00736             {
00737                 if( os.str().size() % 2 )
00738                 {
00739                     os << " ";
00740                 }
00741             }
00742         }
00743         VL::Type osStrSize = (VL::Type)os.str().size();
00744         ret.SetByteValue( os.str().c_str(), osStrSize );
00745     }
00746     return ret;
00747 }
00748
00749 Element(const Element&_val) {
00750     if( this != &_amp;_val ) {
00751         *this = _val;
00752     }
00753 }
00754

```

```

00755 Element &operator=(const Element &_val) {
00756     Length = 0; // SYITF
00757     Internal = 0;
00758     SetArray(_val.Internal, _val.Length, true);
00759     return *this;
00760 }
00761 protected:
00762 void SetNoSwap(Value const &v) {
00763     const ByteValue *bv = dynamic_cast<const ByteValue*>(&v);
00764     gdcassert( bv ); // That would be bad...
00765     if( (VR::VRType) (VRToEncoding<TVR>::Mode) == VR::VRBINARY )
00766     {
00767         const Type* array = (const Type*)bv->GetPointer();
00768         if( array ) {
00769             gdcassert( array ); // That would be bad...
00770             gdcassert( Internal == nullptr );
00771             SetArray(array, bv->GetLength() ); }
00772     }
00773     else
00774     {
00775         std::stringstream ss;
00776         std::string s = std::string( bv->GetPointer(), bv->GetLength() );
00777         ss.str( s );
00778         EncodingImplementation<VRToEncoding<TVR>::Mode>::ReadNoSwap(Internal,
00779             GetLength(), ss);
00780     }
00781 }
00782
00783 private:
00784     typename VRToType<TVR>::Type *Internal;
00785     unsigned long Length; // unsigned int ??
00786     bool Save;
00787 };
00788
00789 //template <int TVM = VM::VM1_n>
00790 //class Element<VR::OB, TVM > : public Element<VR::OB, VM::VM1_n> {};
00791
00792 // Partial specialization for derivatives of 1-n : 2-n, 3-n ...
00793 template<long long TVR>
00794 class Element<TVR, VM::VM1_2> : public Element<TVR, VM::VM1_n>
00795 {
00796 public:
00797     typedef Element<TVR, VM::VM1_n> Parent;
00798     void SetLength(int len) {
00799         if( len != 1 && len != 2 ) return;
00800         Parent::SetLength(len);
00801     }
00802 };
00803 template<long long TVR>
00804 class Element<TVR, VM::VM2_n> : public Element<TVR, VM::VM1_n>
00805 {
00806     enum { ElementDisableCombinationsCheck = sizeof ( ElementDisableCombinations<TVR, VM::VM2_n> ) };
00807 public:
00808     typedef Element<TVR, VM::VM1_n> Parent;
00809     void SetLength(int len) {
00810         if( len <= 1 ) return;
00811         Parent::SetLength(len);
00812     }
00813 };
00814 template<long long TVR>
00815 class Element<TVR, VM::VM2_2n> : public Element<TVR, VM::VM2_n>
00816 {
00817     enum { ElementDisableCombinationsCheck = sizeof ( ElementDisableCombinations<TVR, VM::VM2_2n> ) };
00818 public:
00819     typedef Element<TVR, VM::VM2_n> Parent;
00820     void SetLength(int len) {
00821         if( len % 2 ) return;
00822         Parent::SetLength(len);
00823     }
00824 };
00825 template<long long TVR>
00826 class Element<TVR, VM::VM3_n> : public Element<TVR, VM::VM1_n>
00827 {
00828     enum { ElementDisableCombinationsCheck = sizeof ( ElementDisableCombinations<TVR, VM::VM3_n> ) };
00829 public:
00830     typedef Element<TVR, VM::VM1_n> Parent;
00831     void SetLength(int len) {
00832         if( len <= 2 ) return;
00833         Parent::SetLength(len);
00834     }
00835 };

```

```

00836 template<long long TVR>
00837 class Element<TVR, VM::VM3_3n> : public Element<TVR, VM::VM3_n>
00838 {
00839     enum { ElementDisableCombinationsCheck = sizeof ( ElementDisableCombinations<TVR, VM::VM3_3n> ) };
00840 public:
00841     typedef Element<TVR, VM::VM3_n> Parent;
00842     void SetLength(int len) {
00843         if( len % 3 ) return;
00844         Parent::SetLength(len);
00845     }
00846 };
00847 template<long long TVR>
00848 class Element<TVR, VM::VM3_4> : public Element<TVR, VM::VM1_n>
00849 {
00850 public:
00851     typedef Element<TVR, VM::VM1_n> Parent;
00852     void SetLength(int len) {
00853         if( len != 3 && len != 4 ) return;
00854         Parent::SetLength(len);
00855     }
00856 };
00857
00858
00859 //template<int T> struct VRToLength;
00860 //template<> struct VRToLength<VR::AS>
00861 //{ enum { Length = VM::VM1 }; }
00862 //template<>
00863 //class Element<VR::AS> : public Element<VR::AS, VRToLength<VR::AS>::Length >
00864
00865 // only 0010 1010 AS 1 Patient's Age
00866 template<>
00867 class Element<VR::AS, VM::VM5>
00868 {
00869     enum { ElementDisableCombinationsCheck = sizeof ( ElementDisableCombinations<VR::AS, VM::VM5> ) };
00870 public:
00871     char Internal[VMToLength<VM::VM5>::Length * sizeof( VRToType<VR::AS>::Type )];
00872     void Print(std::ostream &_os) const {
00873         _os << Internal;
00874     }
00875     unsigned long GetLength() const {
00876         return VMToLength<VM::VM5>::Length;
00877     }
00878 };
00879
00880
00881 template<>
00882 class Element<VR::OB, VM::VM1> : public Element<VR::OB, VM::VM1_n> {};
00883
00884 // Same for OW:
00885 template<>
00886 class Element<VR::OW, VM::VM1> : public Element<VR::OW, VM::VM1_n> {};
00887
00888
00889 } // namespace gdcms
00890
00891 #endif //GDCMELEMENT_H

```


11.135 gdcmsExplicitDataElement.h File Reference

```

#include "gdcmsDataElement.h"
#include "gdcmsExplicitDataElement.txx"

```

Include dependency graph for gdcmExplicitDataElement.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::ExplicitDataElement](#)
Class to read/write a *DataElement* as *Explicit Data Element*.

Namespaces

- namespace [gdcm](#)

11.136 gdcmExplicitDataElement.h

[Go to the documentation of this file.](#)

```

00001  /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008

```

```

00009      This software is distributed WITHOUT ANY WARRANTY; without even
00010      the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011      PURPOSE. See the above copyright notice for more information.
00012
00013      =====*/
00014      #ifndef GDCMEXPLICITDATAELEMENT_H
00015      #define GDCMEXPLICITDATAELEMENT_H
00016
00017      #include "gdcmDataElement.h"
00018
00019      namespace gdcm_ns
00020      {
00021      class GDCM_EXPORT ExplicitDataElement : public DataElement
00022      {
00023      public:
00024          VL GetLength() const;
00025
00026          template <typename TSwap>
00027          std::istream &Read(std::istream &is);
00028
00029          template <typename TSwap>
00030          std::istream &ReadPreValue(std::istream &is);
00031
00032          template <typename TSwap>
00033          std::istream &ReadValue(std::istream &is, bool readvalues = true);
00034
00035          template <typename TSwap>
00036          std::istream &ReadWithLength(std::istream &is, VL & length);
00037
00038          template <typename TSwap>
00039          const std::ostream &Write(std::ostream &os) const;
00040      };
00041
00042      } // end namespace gdcm_ns
00043
00044      #include "gdcmExplicitDataElement.txx"
00045
00046      #endif //GDCMEXPLICITDATAELEMENT_H

```


11.137 gdcmExplicitImplicitDataElement.h File Reference

```

#include "gdcmDataElement.h"
#include "gdcmExplicitImplicitDataElement.txx"

```

Include dependency graph for gdcmExplicitImplicitDataElement.h:



Classes

- class [gdcm::ExplicitImplicitDataElement](#)
Class to read/write a [DataElement](#) as [ExplicitImplicit Data Element](#).

Namespaces

- namespace [gdcm](#)

11.138 gdcmExplicitImplicitDataElement.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013   =====*/
00014 #ifndef GDCMEXPLICITIMPLICITDATAELEMENT_H
00015 #define GDCMEXPLICITIMPLICITDATAELEMENT_H
00016
00017 #include "gdcmDataElement.h"
00018
00019 namespace gdcm
00020 {
00021   // Data Element (ExplicitImplicit)
00022   class GDCM_EXPORT ExplicitImplicitDataElement : public DataElement
00023   {
00024   public:
00025     VL GetLength() const;
00026
00027     template <typename TSwap>
00028     std::istream &Read(std::istream &is);
00029
00030     template <typename TSwap>
00031     std::istream &ReadPreValue(std::istream &is);
00032
00033     template <typename TSwap>
00034     std::istream &ReadValue(std::istream &is, bool readvalues = true);
00035
00036     template <typename TSwap>
00037     std::istream &ReadWithLength(std::istream &is, VL & length)
00038     {
00039       (void)length;
00040       return Read<TSwap>(is);
00041     }
00042
00043     // PURPOSELY do not provide an implementation for writing !
00044     template <typename TSwap>
00045     //const std::ostream &Write(std::ostream &os) const;
00046   };
00047
00048 } // end namespace gdcm
00049
00050 #include "gdcmExplicitImplicitDataElement.txx"
00051
00052 #endif //GDCMEXPLICITIMPLICITDATAELEMENT_H

```


11.140 gdcmFile.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMFILE_H
00015 #define GDCMFILE_H
00016
00017 #include "gdcmObject.h"
00018 #include "gdcmDataSet.h"
00019 #include "gdcmFileMetaInformation.h"
00020
00021 namespace gdcm_ns
00022 {
00023
00024   class GDCM_EXPORT File : public Object
00025   {
00026   public:
00027     File();
00028     ~File() override;
00029
00030     friend std::ostream &operator<<(std::ostream &os, const File &val);
00031
00032     std::istream &Read(std::istream &is);
00033
00034     std::ostream const &Write(std::ostream &os) const;
00035
00036     const FileMetaInformation &GetHeader() const { return Header; }
00037
00038     FileMetaInformation &GetHeader() { return Header; }
00039
00040     void SetHeader( const FileMetaInformation &fmi ) { Header = fmi; }
00041
00042     const DataSet &GetDataSet() const { return DS; }
00043
00044     DataSet &GetDataSet() { return DS; }
00045
00046     void SetDataSet( const DataSet &ds ) { DS = ds; }
00047
00048   private:
00049     FileMetaInformation Header;
00050     DataSet DS;
00051   };
00052
00053   //-----
00054   inline std::ostream& operator<<(std::ostream &os, const File &val)
00055   {
00056     os << val.GetHeader() << std::endl;
00057     //os << val.GetDataSet() << std::endl; // FIXME
00058     gdcm_assert(0);
00059     return os;
00060   }
00061
00062 } // end namespace gdcm_ns
00063
00064 #endif //GDCMFILE_H

```

11.141 gdcmFileMetaInformation.h File Reference

```

#include "gdcmPreamble.h"
#include "gdcmDataSet.h"

```

Include dependency graph for `gdcmFileMetaInformation.h`:



- Class to represent a **File** Meta Information.*

- namespace **gdcm**

- `std::ostream & gdcm::operator<< (std::ostream &os, const FileMetaInformation &val)`

11.142 gdcmFileMetaInformation.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMFILEMETAINFORMATION_H
00015 #define GDCMFILEMETAINFORMATION_H
00016
00017 #include "gdcmPreamble.h"
00018 #include "gdcmDataSet.h"
00019 #include "gdcmDataElement.h"
00020 #include "gdcmMediaStorage.h"
00021 #include "gdcmTransferSyntax.h"
00022 #include "gdcmExplicitDataElement.h"
00023
00024 namespace gdcm_ns
00025 {
00040 class GDCM_EXPORT FileMetaInformation : public DataSet
00041 {
00042 public:
00043   // FIXME: TransferSyntax::TS_END -> TransferSyntax::ImplicitDataElement
00044   FileMetaInformation();
00045   ~FileMetaInformation();
00046
00047   friend std::ostream &operator<<(std::ostream &_os, const FileMetaInformation &_val);
00048
00049   bool IsValid() const { return true; }
00050
00051   TransferSyntax::NegociatedType GetMetaInformationTS() const { return MetaInformationTS; }
00052   void SetDataSetTransferSyntax(const TransferSyntax &ts);
00053   const TransferSyntax &GetDataSetTransferSyntax() const { return DataSetTS; }
00054   MediaStorage GetMediaStorage() const;
00055   std::string GetMediaStorageAsString() const;
00056
00057   // FIXME: no virtual function means: duplicate code...
00058   void Insert(const DataElement& de) {
00059     if( de.GetTag().GetGroup() == 0x0002 )
00060     {
00061       InsertDataElement( de );
00062     }
00063     else
00064     {
00065       gdcmErrorMacro( "Cannot add element with group != 0x0002 in the file meta header: " << de );
00066     }
00067   }
00068   void Replace(const DataElement& de) {
00069     Remove(de.GetTag());
00070     Insert(de);
00071   }
00072
00074   std::istream &Read(std::istream &is);
00075   std::istream &ReadCompat(std::istream &is);
00076
00078   std::ostream &Write(std::ostream &os) const;
00079
00081   void FillFromDataSet(DataSet const &ds);
00082
00084   const Preamble &GetPreamble() const { return P; }
00085   Preamble &GetPreamble() { return P; }
00086   void SetPreamble(const Preamble &p) { P = p; }
00087
00089   static void SetImplementationClassUID(const char * imp);
00090   static void AppendImplementationClassUID(const char * imp);
00091   static const char *GetImplementationClassUID();
00092   static void SetImplementationVersionName(const char * version);
00093   static const char *GetImplementationVersionName();
00094   static void SetSourceApplicationEntityTitle(const char * title);

```

```

00095     static const char *GetSourceApplicationEntityTitle();
00096
00097     FileMetaInformation(FileMetaInformation const& fmi) = default;
00098     FileMetaInformation& operator=(const FileMetaInformation& fmi) = default;
00099
00100     VL GetFullLength() const {
00101         return P.GetLength() + DataSet::GetLength<ExplicitDataElement>();
00102     }
00103
00104 protected:
00105     void ComputeDataSetTransferSyntax(); // FIXME
00106
00107     template <typename TSwap>
00108     std::istream &ReadCompatInternal(std::istream &is);
00109
00110     void Default();
00111     void ComputeDataSetMediaStorageSOPClass();
00112
00113     TransferSyntax DataSetTS;
00114     TransferSyntax::NegociatedType MetaInformationTS;
00115     MediaStorage::MSType DataSetMS;
00116
00117 protected:
00118     static const char * GetFileMetaInformationVersion();
00119     static const char * GetGDCMImplementationClassUID();
00120     static const char * GetGDCMImplementationVersionName();
00121     static const char * GetGDCMSourceApplicationEntityTitle();
00122
00123 private:
00124     Preamble P;
00125
00126 //static stuff:
00127     static const char GDCM_FILE_META_INFORMATION_VERSION[];
00128     static const char GDCM_IMPLEMENTATION_CLASS_UID[];
00129     static const char GDCM_IMPLEMENTATION_VERSION_NAME[];
00130     static const char GDCM_SOURCE_APPLICATION_ENTITY_TITLE[];
00131     static std::string ImplementationClassUID;
00132     static std::string ImplementationVersionName;
00133     static std::string SourceApplicationEntityTitle;
00134 };
00135 //-----
00136 inline std::ostream& operator<<(std::ostream &os, const FileMetaInformation &val)
00137 {
00138     os << val.GetPreamble() << std::endl;
00139     val.Print( os );
00140     return os;
00141 }
00142
00143 } // end namespace gdcms
00144
00145 #endif //GDCMFILEMETAINFORMATION_H

```


11.143 gdcmsFileSet.h File Reference

```


#include "gdcmsFile.h"
#include <vector>

```

Include dependency graph for `gdcmFileSet.h`:



This graph shows which files directly or indirectly include this file:



Classes

- class `gdcm::FileSet`

Namespaces

- namespace **gdcm**

Functions

- `std::ostream & gdcmm::operator<< (std::ostream &os, const FileSet &f)`

11.144 gdcmFileSet.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMFILESET_H
00015 #define GDCMFILESET_H
00016
00017 #include "gdcmFile.h"
00018 #include <vector>
00019
00020 namespace gdcm
00021 {
00022     class GDCM_EXPORT FileSet
00023     {
00024     public:
00025         FileSet():Files() {}
00026         typedef std::string FileType;
00027         typedef std::vector<FileType> FilesType;
00028
00029         void AddFile(File const & ) {}
00030
00031         bool AddFile(const char *filename);
00032
00033         void SetFiles(FilesType const &files);
00034         FilesType const &GetFiles() const {
00035             return Files;
00036         }
00037     private:
00038         FilesType Files;
00039     };
00040
00041 //-----
00042 inline std::ostream& operator<<(std::ostream &os, const FileSet &f)
00043 {
00044     (void)f; // FIXME
00045     return os;
00046 }
00047
00048 } // end namespace gdcm
00049
00050 #endif //GDCMFILESET_H

```

11.145 gdcmFragment.h File Reference

```

#include "gdcmDataElement.h"
#include "gdcmByteValue.h"
#include "gdcmSmartPointer.h"
#include "gdcmParseException.h"

```

```

graph TD
    gdcmFragment.h --> gdcmDataElement.h
    gdcmFragment.h --> gdcmParseException.h
    gdcmDataElement.h --> gdcmByteValue.h
    gdcmDataElement.h --> set
    gdcmDataElement.h --> gdcmSmartPointer.h
    gdcmByteValue.h --> vector
    gdcmByteValue.h --> iterator
    gdcmByteValue.h --> algorithm
    gdcmByteValue.h --> cstring
    gdcmByteValue.h --> gdcmValue.h
    gdcmSmartPointer.h --> gdcmVRL.h
    gdcmVRL.h --> gdcmValue.txx
    gdcmVRL.h --> gdcmVL.h
    gdcmVRL.h --> gdcmTag.h
    gdcmVRL.h --> gdcmObject.h
    gdcmVRL.h --> fstream
    gdcmVRL.h --> gdcmString.h
    gdcmObject.h --> gdcmTypes.h
    gdcmObject.h --> assert.h
    gdcmObject.h --> gdcmStaticAssert.h
    gdcmTypes.h --> gdcmConfigure.h
    gdcmTypes.h --> gdcmWir32.h
    gdcmTypes.h --> gdcmLegacyMacro.h
    gdcmLegacyMacro.h --> gdcmTrace.h
    gdcmLegacyMacro.h --> gdcmException.h
    gdcmException.h --> gdcmSystem.h
    gdcmException.h --> iofwd
    gdcmException.h --> cassert
    gdcmException.h --> cstdlib
    gdcmException.h --> exception
    gdcmException.h --> sstream
    gdcmException.h --> stdexcept
    gdcmException.h --> string
    gdcmTrace.h --> gdcmSystem.h
    gdcmTrace.h --> iofwd
    gdcmTrace.h --> cassert
    gdcmTrace.h --> cstdlib
    gdcmTrace.h --> exception
    gdcmTrace.h --> sstream
    gdcmTrace.h --> stdexcept
    gdcmTrace.h --> string
    gdcmSystem.h --> iofwd
    gdcmSystem.h --> cassert
    gdcmSystem.h --> cstdlib
    gdcmSystem.h --> exception
    gdcmSystem.h --> sstream
    gdcmSystem.h --> stdexcept
    gdcmSystem.h --> string
    iofwd --> cassert
    iofwd --> cstdlib
    iofwd --> exception
    iofwd --> sstream
    iofwd --> stdexcept
    iofwd --> string
    cassert --> cstdlib
    cassert --> exception
    cassert --> sstream
    cassert --> stdexcept
    cassert --> string
    cstdlib --> exception
    cstdlib --> sstream
    cstdlib --> stdexcept
    cstdlib --> string
    exception --> sstream
    exception --> stdexcept
    exception --> string
    sstream --> stdexcept
    sstream --> string
    stdexcept --> string
    string --> string
  
```

```
graph TD; gdcmFragment.h --> gdcmBasicOffsetTable.h; gdcmBasicOffsetTable.h --> gdcmSequenceOfFragments.h; gdcmSequenceOfFragments.h --> gdcmFragment.h;
```

- class `gdcm::Fragment`
Class to represent a `Fragment`.

- namespace **gdcm**

Functions

- `std::ostream & gdcmm::operator<< (std::ostream &os, const Fragment &val)`

11.146 gdcmmFragment.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcmm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMMFRAGMENT_H
00015 #define GDCMMFRAGMENT_H
00016
00017 #include "gdcmmDataElement.h"
00018 #include "gdcmmByteValue.h"
00019 #include "gdcmmSmartPointer.h"
00020 #include "gdcmmParseException.h"
00021
00022 namespace gdcmm_ns
00023 {
00024
00025   // Implementation detail:
00026   // I think Fragment should be a protected subclass of DataElement:
00027   // looking somewhat like this:
00028   /*
00029   class GDCM_EXPORT Fragment : protected DataElement
00030   {
00031   public:
00032     using DataElement::GetTag;
00033     using DataElement::GetVL;
00034     using DataElement::SetByteValue;
00035     using DataElement::GetByteValue;
00036     using DataElement::GetValue;
00037   */
00038   // Instead I am only hiding the SetTag member...
00039
00040   class GDCM_EXPORT Fragment : public DataElement
00041   {
00042   //protected:
00043   // void SetTag(const Tag &t);
00044   public:
00045     Fragment() : DataElement(Tag(0xffff, 0xe000), 0) {}
00046     friend std::ostream &operator<<(std::ostream &os, const Fragment &val);
00047
00048     VL GetLength() const;
00049
00050     VL ComputeLength() const;
00051
00052     template <typename TSwap>
00053     std::istream &Read(std::istream &is)
00054     {
00055       ReadPreValue<TSwap>(is);
00056       return ReadValue<TSwap>(is);
00057     }
00058
00059     template <typename TSwap>
00060     std::istream &ReadPreValue(std::istream &is)
00061     {
00062       TagField.Read<TSwap>(is);
00063       if( !is )
00064       {
00065         // BogusItemStartItemEnd.dcm
00066         throw Exception( "Problem #1" );
00067       }
00068     }
00069

```



```

00070     }
00071     if( !ValueLengthField.Read<TSwap>(is) )
00072     {
00073         // GENESIS_SIGNA-JPEG-CorruptFrag.dcm
00074         // JPEG fragment is declared to have 61902, but in fact really is only 61901
00075         // so we end up reading 0xddff,0x00e0, and VL = 0x0 (1 byte)
00076         throw Exception( "Problem #2" );
00077     }
00078 #ifndef GDCM_SUPPORT_BROKEN_IMPLEMENTATION
00079     const Tag itemStart(0xffff, 0xe000);
00080     const Tag seqDelItem(0xffff,0xe0dd);
00081     if( TagField != itemStart && TagField != seqDelItem )
00082     {
00083         throw Exception( "Problem #3" );
00084     }
00085 #endif
00086     return is;
00087 }
00088
00089 template <typename TSwap>
00090 std::istream &ReadValue(std::istream &is)
00091 {
00092     // Self
00093     SmartPointer<ByteValue> bv = new ByteValue;
00094     bv->SetLength(ValueLengthField);
00095     if( !bv->Read<TSwap>(is) )
00096     {
00097         // Fragment is incomplete, but is a itemStart, let's try to push it anyway...
00098         gdcmWarningMacro( "Fragment could not be read" );
00099         //bv->SetLength(is.gcount());
00100         ValueField = bv;
00101         ParseException pe;
00102         pe.SetLastElement( *this );
00103         throw pe;
00104     }
00105     ValueField = bv;
00106     return is;
00107 }
00108
00109 template <typename TSwap>
00110 std::istream &ReadBacktrack(std::istream &is)
00111 {
00112     const Tag itemStart(0xffff, 0xe000);
00113     const Tag seqDelItem(0xffff,0xe0dd);
00114
00115     bool cont = true;
00116     const std::streampos start = is.tellg();
00117     const int max = 10;
00118     int offset = 0;
00119     while( cont )
00120     {
00121         TagField.Read<TSwap>(is);
00122         gdcm_assert( is );
00123         if( TagField != itemStart && TagField != seqDelItem )
00124         {
00125             ++offset;
00126             is.seekg( (std::streampos)((size_t)start - offset) );
00127             gdcmWarningMacro( "Fuzzy Search, backtrack: " « (start - is.tellg()) « " Offset: " « is.tellg() );
00128             if( offset > max )
00129             {
00130                 gdcmErrorMacro( "Giving up" );
00131                 throw "Impossible to backtrack";
00132             }
00133         }
00134         else
00135         {
00136             cont = false;
00137         }
00138     }
00139     gdcm_assert( TagField == itemStart || TagField == seqDelItem );
00140     if( !ValueLengthField.Read<TSwap>(is) )
00141     {
00142         return is;
00143     }
00144
00145     // Self
00146     SmartPointer<ByteValue> bv = new ByteValue;
00147     bv->SetLength(ValueLengthField);
00148     if( !bv->Read<TSwap>(is) )
00149     {
00150         // Fragment is incomplete, but is a itemStart, let's try to push it anyway...

```

```

00151         gdcMWarningMacro( "Fragment could not be read" );
00152         //bv->SetLength(is.gcount());
00153         ValueField = bv;
00154         ParseException pe;
00155         pe.SetLastElement( *this );
00156         throw pe;
00157     }
00158     ValueField = bv;
00159     return is;
00160 }
00161
00162
00163 template <typename TSwap>
00164 std::ostream &Write(std::ostream &os) const {
00165     const Tag itemStart(0xfffe, 0xe000);
00166     const Tag seqDelItem(0xfffe, 0xe0dd);
00167     if( !TagField.Write<TSwap>(os) )
00168     {
00169         gdcM_assert(0 && "Should not happen");
00170         return os;
00171     }
00172     gdcM_assert( TagField == itemStart
00173         || TagField == seqDelItem );
00174     const ByteValue *bv = GetByteValue();
00175     // VL
00176     // The following piece of code is hard to read in order to support such broken file as:
00177     // CompressedLossy.dcm
00178     if( IsEmpty() )
00179     {
00180         //gdcM_assert( bv );
00181         VL zero = 0;
00182         if( !zero.Write<TSwap>(os) )
00183         {
00184             gdcM_assert(0 && "Should not happen");
00185             return os;
00186         }
00187     }
00188     else
00189     {
00190         gdcM_assert( ValueLengthField );
00191         gdcM_assert( !ValueLengthField.IsUndefined() );
00192         const VL actualLen = bv->ComputeLength();
00193         gdcM_assert( actualLen == ValueLengthField || actualLen == ValueLengthField + 1 );
00194         if( !actualLen.Write<TSwap>(os) )
00195         {
00196             gdcM_assert(0 && "Should not happen");
00197             return os;
00198         }
00199     }
00200     // Value
00201     if( ValueLengthField && bv )
00202     {
00203         // Self
00204         gdcM_assert( bv );
00205         gdcM_assert( bv->GetLength() == ValueLengthField );
00206         if( !bv->Write<TSwap>(os) )
00207         {
00208             gdcM_assert(0 && "Should not happen");
00209             return os;
00210         }
00211     }
00212     return os;
00213 }
00214 };
00215 //-----
00216 inline std::ostream &operator<<(std::ostream &os, const Fragment &val)
00217 {
00218     os << "Tag: " << val.TagField;
00219     os << "\tVL: " << val.ValueLengthField;
00220     if( val.ValueField )
00221     {
00222         os << "\t" << *(val.ValueField);
00223     }
00224     return os;
00225 }
00226 }
00227
00228 } // end namespace gdcM_ns
00229
00230 #endif //GDCMFRAGMENT_H


```


11.149 gdcmltem.h File Reference

Include dependency graph for gdcmlItem.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::Item](#)
Class to represent an *Item*.

Namespaces

- namespace [gdcm](#)

Functions

- `std::ostream & gdcm::operator<< (std::ostream &os, const Item &val)`

11.150 gdcmItem.h

[Go to the documentation of this file.](#)

```

00001  /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012  =====*/
00013
00014
00015  #ifndef GDCMITEM_H
00016  #define GDCMITEM_H
00017
00018  #include "gdcmDataElement.h"
00019  #include "gdcmDataSet.h"
00020  #include "gdcmParseException.h"
00021  #include "gdcmSwapper.h"
00022

```

```

00023 #ifdef GDCM_SUPPORT_BROKEN_IMPLEMENTATION
00024 #include "gdcmByteSwapFilter.h"
00025 #endif
00026
00027 namespace gdcm_ns
00028 {
00029
00030 class DataSet;
00045 class GDCM_EXPORT Item : public DataElement
00046 {
00047 public:
00048     Item() : DataElement(Tag(0xfffe, 0xe000), 0xFFFFFFFF), NestedDataSet() {}
00049     friend std::ostream& operator<< (std::ostream &os, const Item &val);
00050
00051     void Clear() {
00052         this->DataElement::Clear();
00053         NestedDataSet.Clear();
00054     }
00055
00056     template <typename TDE>
00057     VL GetLength() const;
00058
00059     void InsertDataElement(const DataElement & de) {
00060         NestedDataSet.Insert(de);
00061         // Update the length
00062         if( !IsUndefinedLength() )
00063         {
00064             gdcml_assert( 0 && "InsertDataElement" );
00065             //ValueLengthField += de.GetLength();
00066         }
00067     }
00068     const DataElement& GetDataElement(const Tag& t) const
00069     {
00070         return NestedDataSet.GetDataElement(t);
00071     }
00072
00073     // Completely defines it with the nested dataset
00074     // destroy anything present
00075     void SetNestedDataSet(const DataSet& nested)
00076     {
00077         NestedDataSet = nested;
00078     }
00079     // Return a const ref to the Nested Data Set
00080     const DataSet &GetNestedDataSet() const
00081     {
00082         return NestedDataSet;
00083     }
00084     DataSet &GetNestedDataSet()
00085     {
00086         return NestedDataSet;
00087     }
00088
00089     //Value const & GetValue() const { return *NestedDataSet; }
00090
00091     Item(Item const &val):DataElement(val)
00092     {
00093         NestedDataSet = val.NestedDataSet;
00094     }
00095
00096     template <typename TDE, typename TSwap>
00097     std::istream &Read(std::istream &is) {
00098         // Superclass
00099         {
00100             DataSet &nested = NestedDataSet;
00101             nested.Clear();
00102             gdcml_assert( nested.IsEmpty() );
00103         }
00104         if( !TagField.Read<TSwap>(is) )
00105         {
00106             throw Exception("Should not happen (item)");
00107             return is;
00108         }
00109     #ifdef GDCM_SUPPORT_BROKEN_IMPLEMENTATION
00110         // MR_Philips_Intera_SwitchIndianess_noLgtSQItem_in_trueLgtSeq.dcm
00111         if( TagField == Tag(0xfeff, 0x00e0)
00112             || TagField == Tag(0xfeff, 0xdde0) )
00113         {
00114             gdcmlWarningMacro( "ByteSwaping Private SQ: " << TagField );
00115             // Invert previously read TagField since wrong endianness:
00116             TagField = Tag( SwapperDoOp::Swap( TagField.GetGroup() ), SwapperDoOp::Swap( TagField.GetElement() )
);

```

```

00117     assert ( TagField == Tag(0xfffe, 0xe000)
00118             || TagField == Tag(0xfffe, 0xe0dd) );
00119
00120     if( !ValueLengthField.Read<SwapperDoOp>(is) )
00121     {
00122         gdcm_assert(0 && "Should not happen");
00123         return is;
00124     }
00125     // Self
00126     // Some file written by GDCM 1.0 we write 0xFFFFFFFF instead of 0x0
00127     if( TagField == Tag(0xfffe,0xe0dd) )
00128     {
00129         if( ValueLengthField )
00130         {
00131             gdcmErrorMacro( "ValueLengthField is not 0" );
00132         }
00133     }
00134     //else if( ValueLengthField == 0 )
00135     // {
00136     //     gdcm_assert( TagField == Tag( 0xfffe, 0xe0dd) );
00137     //     if( TagField != Tag( 0xfffe, 0xe0dd) )
00138     //     {
00139     //         gdcmErrorMacro( "SQ: " << TagField << " has a length of 0" );
00140     //     }
00141     // }
00142     else if( ValueLengthField.IsUndefined() )
00143     {
00144         DataSet &nested = NestedDataSet;
00145         nested.Clear();
00146         gdcm_assert( nested.IsEmpty() );
00147         std::streampos start = is.tellg();
00148         try
00149         {
00150             nested.template ReadNested<TDE,SwapperDoOp>(is);
00151             ByteSwapFilter bsf(nested);
00152             bsf.ByteSwap();
00153         }
00154         catch(ParseException &pe)
00155         {
00156             (void)pe;
00157             //
00158             MR_Philips_Intera_PrivateSequenceExplicitVR_in_SQ_2001_e05f_item_wrong_lgt_use_NOSHADOWSEQ.dcm
00159             // You have to byteswap the length but not the tag...sigh
00160             gdcmWarningMacro( "Attempt to read nested Item without byteswapping the Value Length." );
00161             start -= is.tellg();
00162             gdcm_assert( start < 0 );
00163             is.seekg( start, std::ios::cur );
00164             nested.Clear();
00165             nested.template ReadNested<TDE,SwapperNoOp>(is);
00166             ByteSwapFilter bsf(nested);
00167             // Tag are read in big endian, need to byteswap them back...
00168             bsf.SetByteSwapTag(true);
00169             bsf.ByteSwap();
00170         }
00171         catch(Exception &e)
00172         {
00173             // MR_Philips_Intera_No_PrivateSequenceImplicitVR.dcm
00174             throw e;
00175         }
00176         catch(...)
00177         {
00178             gdcm_assert(0);
00179         }
00180     }
00181     else /* if( ValueLengthField.IsUndefined() ) */
00182     {
00183         DataSet &nested = NestedDataSet;
00184         nested.Clear();
00185         gdcm_assert( nested.IsEmpty() );
00186         nested.template ReadWithLength<TDE,SwapperDoOp>(is, ValueLengthField);
00187         ByteSwapFilter bsf(nested);
00188         bsf.ByteSwap();
00189     }
00190     return is;
00191 }
00192 // http://groups.google.com/group/comp.protocols.dicom/msg/c07efcf5e759fc83
00193 // Bug_Philips_ItemTag_3F3F.dcm
00194 if( TagField == Tag(0x3f3f, 0x3f00) )
00195 {
00196     //TagField = Tag(0xfffe, 0xe000);
00197 }

```

```

00197 #endif
00198     if( TagField != Tag(0xffff, 0xe000) && TagField != Tag(0xffff, 0xe0dd) )
00199     {
00200         gdcmlDebugMacro( "Invalid Item, found tag: " << TagField);
00201         throw Exception( "Not a valid Item" );
00202     }
00203     gdcml_assert( TagField == Tag(0xffff, 0xe000) || TagField == Tag(0xffff, 0xe0dd) );
00204
00205     if( !ValueLengthField.Read<TSwap>(is) )
00206     {
00207         gdcml_assert(0 && "Should not happen");
00208         return is;
00209     }
00210     // Self
00211     if( TagField == Tag(0xffff,0xe0dd) )
00212     {
00213         // Some file written by GDCM 1.0 were written with 0xFFFFFFFF instead of 0x0
00214         if( ValueLengthField )
00215         {
00216             gdcmlDebugMacro( "ValueLengthField is not 0 but " << ValueLengthField );
00217         }
00218     }
00219     else if( ValueLengthField.IsUndefined() )
00220     {
00221         DataSet &nested = NestedDataSet;
00222         nested.Clear();
00223         gdcml_assert( nested.IsEmpty() );
00224         nested.template ReadNested<TDE,TSwap>(is);
00225     }
00226     else /* if( ValueLengthField.IsUndefined() ) */
00227     {
00228         gdcml_assert( !ValueLengthField.IsUndefined() );
00229         DataSet &nested = NestedDataSet;
00230         nested.Clear();
00231         gdcml_assert( nested.IsEmpty() );
00232         nested.template ReadWithLength<TDE,TSwap>(is, ValueLengthField);
00233     }
00234
00235     return is;
00236 }
00237
00238 template <typename TDE, typename TSwap>
00239 const std::ostream &Write(std::ostream &os) const {
00240 #ifdef GDCM_SUPPORT_BROKEN_IMPLEMENTATION
00241     if( TagField == Tag(0x3f3f,0x3f00) && false )
00242     {
00243         Tag t(0xffff, 0xe000);
00244         t.Write<TSwap>(os);
00245     }
00246     else
00247 #endif
00248     {
00249         assert ( TagField == Tag(0xffff, 0xe000)
00250             || TagField == Tag(0xffff, 0xe0dd) );
00251         // Not sure how this happen
00252         if( TagField == Tag(0xffff, 0xe0dd) )
00253         {
00254             gdcmlWarningMacro( "SeqDelItem found in defined length Sequence" );
00255             gdcml_assert( ValueLengthField == 0 );
00256             gdcml_assert( NestedDataSet.Size() == 0 );
00257         }
00258         if( !TagField.Write<TSwap>(os) )
00259         {
00260             gdcml_assert(0 && "Should not happen");
00261             return os;
00262         }
00263     }
00264     if( ValueLengthField.IsUndefined() )
00265     {
00266         if( !ValueLengthField.Write<TSwap>(os) )
00267         {
00268             gdcml_assert(0 && "Should not happen");
00269             return os;
00270         }
00271     }
00272     else
00273     {
00274         const VL dummy = NestedDataSet.GetLength<TDE>();
00275         gdcml_assert( dummy % 2 == 0 );
00276         //gdcml_assert( ValueLengthField == dummy );
00277         if( !dummy.Write<TSwap>(os) )

```



```


00278     {
00279         gdcm_assert(0 && "Should not happen");
00280         return os;
00281     }
00282 }
00283 // Self
00284 NestedDataSet.Write<TDE,TSwap>(os);
00285 if( ValueLengthField.IsUndefined() )
00286 {
00287     const Tag itemDelItem(0xffff,0xe00d);
00288     itemDelItem.Write<TSwap>(os);
00289     VL zero = 0;
00290     zero.Write<TSwap>(os);
00291 }
00292
00293 return os;
00294 }
00295
00296 /*
00297 There are three special SQ related Data Elements that are not ruled by the VR encoding rules conveyed
00298 by the Transfer Syntax. They shall be encoded as Implicit VR. These special Data Elements are Item
00299 (FFFE,E000), Item Delimitation Item (FFFE,E00D), and Sequence Delimitation Item (FFFE,E0DD).
00300 However, the Data Set within the Value Field of the Data Element Item (FFFE,E000) shall be encoded
00301 according to the rules conveyed by the Transfer Syntax.
00302 */
00303 bool FindDataElement(const Tag &t) const {
00304     return NestedDataSet.FindDataElement( t );
00305 }
00306
00307 private:
00308     /* NESTED DATA SET a Data Set contained within a Data Element of an other Data Set.
00309      * May be nested recursively.
00310      * Only Data Elements with VR = SQ may, themselves, contain Data Sets
00311      */
00312     DataSet NestedDataSet;
00313 };
00314 //-----
00315 inline std::ostream& operator<<(std::ostream& os, const Item &val)
00316 {
00317     os << val.TagField;
00318     os << "\t" << val.ValueLengthField << "\n";
00319     val.NestedDataSet.Print( os, "\t" );
00320
00321     return os;
00322 }
00323
00324 } // end namespace gdcm_ns
00325
00326 #include "gdcmItem.txx"
00327
00328 #endif //GDCMITEM_H

```

11.151 gdcmLO.h File Reference

```
#include "gdcmString.h"
```

Include dependency graph for gdcmLO.h:



Classes

- class [gdcm::LO](#)
[LO](#).

Namespaces

- namespace [gdcm](#)

11.152 gdcmLO.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013   =====*/
00014 #ifndef GDCMLO_H
00015 #define GDCMLO_H
00016
00017 #include "gdcmString.h"

```

```


00018
00019 namespace gdcm
00020 {
00021
00027 class /*GDCM_EXPORT*/ LO : public String<'\\',64> /* PLEASE do not export me */
00028 {
00029 public:
00030     // typedef are not inherited:
00031     typedef String<'\\',64> Superclass;
00032     typedef Superclass::value_type      value_type;
00033     typedef Superclass::pointer         pointer;
00034     typedef Superclass::reference       reference;
00035     typedef Superclass::const_reference const_reference;
00036     typedef Superclass::size_type      size_type;
00037     typedef Superclass::difference_type difference_type;
00038     typedef Superclass::iterator       iterator;
00039     typedef Superclass::const_iterator const_iterator;
00040     typedef Superclass::reverse_iterator reverse_iterator;
00041     typedef Superclass::const_reverse_iterator const_reverse_iterator;
00042
00043     // LO constructors.
00044     LO(): Superclass() {}
00045     LO(const value_type* s): Superclass(s) {}
00046     LO(const value_type* s, size_type n): Superclass(s, n) {}
00047     LO(const Superclass& s, size_type pos=0, size_type n=npos):
00048         Superclass(s, pos, n) {}
00049
00050     bool IsValid() const {
00051         if( !Superclass::IsValid() ) return false;
00052         // Implementation specific:
00053         return true;
00054     }
00055 };
00056
00057 } // end namespace gdcm
00058
00059 #endif //GDCMLO_H

```


11.153 gdcmMediaStorage.h File Reference

#include "gdcmTransferSyntax.h"

Include dependency graph for gdcmMediaStorage.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::MediaStorage](#)
MediaStorage.

Namespaces

- namespace [gdcm](#)

Functions

- `std::ostream & gdcm::operator<< (std::ostream &_os, const MediaStorage &ms)`

11.154 gdcmMediaStorage.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003     Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005     Copyright (c) 2006-2011 Mathieu Malaterre
00006     All rights reserved.
00007     See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009     This software is distributed WITHOUT ANY WARRANTY; without even
00010     the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011     PURPOSE. See the above copyright notice for more information.
00012
00013     =====*/
00014 #ifndef GDCMMEDIASTORAGE_H
00015 #define GDCMMEDIASTORAGE_H
00016
00017 #include "gdcmTransferSyntax.h"
00018
00019 namespace gdcm { class Tag; }
00020 namespace gdcm_ns
00021 {
00022     #if !defined(SWIGPYTHON) && !defined(SWIGCSHARP) && !defined(SWIGJAVA) && !defined(SWIGPHP)
00023     using namespace gdcm;
00024     #endif
00025     class DataSet;
00026     class FileMetaInformation;
00027     class File;
00028
00029     // WARNING: This class will be deprecated in the future. There is no reason to extend this class.
00030     // Please check the gdcm::UIDs class if adding new well known UID.
00031
00043     class GDCM_EXPORT MediaStorage
00044     {
00045     public:
00046         typedef enum {
00047             MediaStorageDirectoryStorage = 0,
00048             ComputedRadiographyImageStorage,
00049             DigitalXRayImageStorageForPresentation,

```


```
00050     DigitalXRayImageStorageForProcessing,
00051     DigitalMammographyImageStorageForPresentation,
00052     DigitalMammographyImageStorageForProcessing,
00053     DigitalIntraoralXrayImageStorageForPresentation,
00054     DigitalIntraoralXRayImageStorageForProcessing,
00055     CTImageStorage,
00056     EnhancedCTImageStorage,
00057     UltrasoundImageStorageRetired,
00058     UltrasoundImageStorage,
00059     UltrasoundMultiFrameImageStorageRetired,
00060     UltrasoundMultiFrameImageStorage,
00061     MRImageStorage,
00062     EnhancedMRImageStorage,
00063     MRSpectroscopyStorage,
00064     NuclearMedicineImageStorageRetired,
00065     SecondaryCaptureImageStorage,
00066     MultiframeSingleBitSecondaryCaptureImageStorage,
00067     MultiframeGrayscaleByteSecondaryCaptureImageStorage,
00068     MultiframeGrayscaleWordSecondaryCaptureImageStorage,
00069     MultiframeTrueColorSecondaryCaptureImageStorage,
00070     StandaloneOverlayStorage,
00071     StandaloneCurveStorage,
00072     LeadECGWaveformStorage, // 12-
00073     GeneralECGWaveformStorage,
00074     AmbulatoryECGWaveformStorage,
00075     HemodynamicWaveformStorage,
00076     CardiacElectrophysiologyWaveformStorage,
00077     BasicVoiceAudioWaveformStorage,
00078     StandaloneModalityLUTStorage,
00079     StandaloneVOILUTStorage,
00080     GrayscaleSoftcopyPresentationStateStorageSOPClass,
00081     XRayAngiographicImageStorage,
00082     XRayRadiofluoroscopicImageStorage,
00083     XRayAngiographicBiPlaneImageStorageRetired,
00084     NuclearMedicineImageStorage,
00085     RawDataStorage,
00086     SpacialRegistrationStorage, // Spatial
00087     SpacialFiducialsStorage, // Spatial..
00088     PETImageStorage,
00089     RTImageStorage,
00090     RTDoseStorage,
00091     RTStructureSetStorage,
00092     RTPlanStorage,
00093     CSANonImageStorage,
00094     Philips3D,
00095     EnhancedSR,
00096     BasicTextSR,
00097     HardcopyGrayscaleImageStorage,
00098     ComprehensiveSR,
00099     DetachedStudyManagementSOPClass,
00100     EncapsulatedPDFStorage,
00101     EncapsulatedCDASStorage,
00102     StudyComponentManagementSOPClass,
00103     DetachedVisitManagementSOPClass,
00104     DetachedPatientManagementSOPClass,
00105     VideoEndoscopicImageStorage,
00106     GeneralElectricMagneticResonanceImageStorage,
00107     GEPrivate3DModelStorage,
00108     ToshibaPrivateDataStorage,
00109     MammographyCADSR,
00110     KeyObjectSelectionDocument,
00111     HangingProtocolStorage,
00112     ModalityPerformedProcedureStepSOPClass,
00113     PhilipsPrivateMRSyntheticImageStorage,
00114     VLPhotographicImageStorage,
00115     SegmentationStorage, // "1.2.840.10008.5.1.4.1.1.66.4"
00116     RTIonPlanStorage, // 1.2.840.10008.5.1.4.1.1.481.8
00117     XRay3DAngiographicImageStorage, // 1.2.840.10008.5.1.4.1.1.13.1.1
00118     EnhancedXAImageStorage,
00119     RTIonBeamsTreatmentRecordStorage, // 1.2.840.10008.5.1.4.1.1.481.9
00120     SurfaceSegmentationStorage, // "1.2.840.10008.5.1.4.1.1.66.5"
00121     VLWholeSlideMicroscopyImageStorage, // 1.2.840.10008.5.1.4.1.1.77.1.6
00122     RTTreatmentSummaryRecordStorage, // 1.2.840.10008.5.1.4.1.1.481.7
00123     EnhancedUSVolumeStorage, // 1.2.840.10008.5.1.4.1.1.6.2
00124     XRayRadiationDoseSR, // 1.2.840.10008.5.1.4.1.1.88.67
00125     VLEndoscopicImageStorage, // 1.2.840.10008.5.1.4.1.1.77.1.1
00126     BreastTomosynthesisImageStorage, // 1.2.840.10008.5.1.4.1.1.13.1.3
00127     FujiPrivateCRImageStorage, // 1.2.392.200036.9125.1.1.2
00128     OphthalmicPhotography8BitImageStorage, // 1.2.840.10008.5.1.4.1.1.77.1.5.1
00129     OphthalmicTomographyImageStorage, // 1.2.840.10008.5.1.4.1.1.77.1.5.4
00130     VLMicroscopicImageStorage,
```

```


00131     EnhancedPETImageStorage,
00132     VideoPhotographicImageStorage,
00133     XRay3DCraniofacialImageStorage,
00134     IVOCForPresentation,
00135     IVOCForProcessing,
00136     LegacyConvertedEnhancedCTImageStorage,
00137     LegacyConvertedEnhancedMRImageStorage,
00138     LegacyConvertedEnhancedPETImageStorage,
00139     BreastProjectionXRayImageStorageForPresentation,
00140     BreastProjectionXRayImageStorageForProcessing,
00141     HardcopyColorImageStorage,
00142     EnhancedMRColorImageStorage,
00143     FujiPrivateMammoCRImageStorage,
00144     OphthalmicPhotographyl6BitImageStorage,
00145     VideoMicroscopicImageStorage,
00146     MS_END
00147 } MStype; // Media Storage Type
00148
00149 typedef enum {
00150     NoObject = 0, // DICOMDIR
00151     Video, // Most common, include image, video and volume
00152     Waveform, // Isn't it simply a 1D video ?
00153     Audio, // ???
00154     PDF,
00155     URI, // URL...
00156     Segmentation, // TODO
00157     ObjectEnd
00158 } ObjectType;
00159
00161 static const char* GetMSString(MStype ts);
00162
00164 const char* GetString() const;
00165 static MStype GetMStype(const char *str);
00166
00167 MediaStorage(MStype type = MS_END):MSField(type) {}
00168
00171 static bool IsImage(MStype ts);
00172
00173 operator MStype () const { return MSField; }
00174
00175 const char *GetModality() const;
00176 unsigned int GetModalityDimension() const;
00177
00178 static unsigned int GetNumberOfMStype();
00179 static unsigned int GetNumberOfMSString();
00180 static unsigned int GetNumberOfModality();
00181
00182
00187 bool SetFromFile(File const &file);
00188
00191 bool SetFromDataSet(DataSet const &ds); // Will get the SOP Class UID
00192 bool SetFromHeader(FileMetaInformation const &fmi); // Will get the Media Storage SOP Class UID
00193 bool SetFromModality(DataSet const &ds);
00194 void GuessFromModality(const char *modality, unsigned int dimension = 2);
00195
00196 friend std::ostream &operator<<(std::ostream &os, const MediaStorage &ms);
00197
00198 bool IsUndefined() const { return MSField == MS_END; }
00199
00200 protected:
00201 void SetFromSourceImageSequence(DataSet const &ds);
00202
00203 private:
00204 bool SetFromDataSetOrHeader(DataSet const &ds, const Tag &tag);
00205
00206 std::string GetFromDataSetOrHeader(DataSet const &ds, const Tag &tag);
00207 std::string GetFromHeader(FileMetaInformation const &fmi);
00208 std::string GetFromDataSet(DataSet const &ds);
00209
00210 private:
00211 MStype MSField;
00212 };
00213 //-----
00214 inline std::ostream &operator<<(std::ostream &_os, const MediaStorage &ms)
00215 {
00216     const char *msstring = MediaStorage::GetMSString(ms);
00217     _os << (msstring ? msstring : "INVALID MEDIA STORAGE");
00218     return _os;
00219 }
00220 }
00221

```

```
#include "gdcmTypes.h"
#include "gdcmDataSet.h"
Include dependency graph for gdcmMrProtocol.h:
```



This graph shows which files directly or indirectly include this file:



- class `gdcm::MrProtocol`
Class for `MrProtocol`.
- struct `gdcm::MrProtocol::Slice`
- struct `gdcm::MrProtocol::SliceArray`
- struct `gdcm::MrProtocol::Vector3`

Namespaces

- namespace `gdcm`

Functions

- `std::ostream & gdcm::operator<< (std::ostream &os, const MrProtocol &d)`

11.156 gdcmMrProtocol.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003     Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005     Copyright (c) 2006-2011 Mathieu Malaterre
00006     All rights reserved.
00007     See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009     This software is distributed WITHOUT ANY WARRANTY; without even
00010     the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011     PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMMRPROTOCOL_H
00015 #define GDCMMRPROTOCOL_H
00016
00017 #include "gdcmTypes.h"
00018 #include "gdcmDataSet.h"
00019
00020 namespace gdcm
00021 {
00022     class ByteValue;
00023     /*
00024      * Everything done in this code is for the sole purpose of writing interoperable
00025      * software under Sect. 1201 (f) Reverse Engineering exception of the DMCA.
00026      * If you believe anything in this code violates any law or any of your rights,
00027      * please contact us (gdcm-developers@lists.sourceforge.net) so that we can
00028      * find a solution.
00029      */
00030     //-----
00031
00032     class DataElement;
00036     class GDCM_EXPORT MrProtocol
00037     {
00038     friend std::ostream& operator<<(std::ostream &_os, const MrProtocol &d);
00039     public :
00040         MrProtocol();
00041         ~MrProtocol();
00042
00043         bool Load( const ByteValue * bv, const char * str, int version );
00044         void Print(std::ostream &os) const;
00045
00046         int GetVersion() const;
00047
00048         const char * GetMrProtocolByName(const char *name) const;
00049
00050         bool FindMrProtocolByName(const char *name) const;
00051
00052         struct Vector3
00053         {
00054             double dSag;
00055             double dCor;
00056             double dTra;
00057         };
00058         struct Slice
00059         {
00060             Vector3 Normal;
00061             Vector3 Position;
00062         };

```



```

00063  struct SliceArray
00064  {
00065      std::vector< Slice > Slices;
00066  };
00067  bool GetSliceArray( MrProtocol::SliceArray & sa ) const;
00068
00069 private:
00070  struct Element;
00071  struct Internals;
00072  Internals *Pimpl;
00073  };
00074  //-----
00075  inline std::ostream& operator<<(std::ostream &os, const MrProtocol &d)
00076  {
00077      d.Print( os );
00078      return os;
00079  }
00080
00081 } // end namespace gdcm
00082 //-----
00083 #endif //GDCMMRPROTOCOL_H


```

11.157 gdcmParseException.h File Reference


```
#include "gdcmException.h"
```

```
#include "gdcmDataElement.h"
```

Include dependency graph for gdcmParseException.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::ParseException](#)
ParseException Standard exception handling object.

Namespaces

- namespace [gdcm](#)

11.158 gdcmParseException.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003 Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005 Copyright (c) 2006-2011 Mathieu Malaterre
00006 All rights reserved.
00007 See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009 This software is distributed WITHOUT ANY WARRANTY; without even
00010 the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011 PURPOSE. See the above copyright notice for more information.
00012 =====*/
00013 #ifndef GDCMPARSEEXCEPTION_H
00014 #define GDCMPARSEEXCEPTION_H
00015
00016 #include "gdcmException.h"
00017 #include "gdcmDataElement.h"
00018
00019

```

```

00020 // Disable clang warning "dynamic exception specifications are deprecated".
00021 // We need to be C++03 and C++11 compatible, and if we remove the 'throw()'
00022 // specifier we'll get an error in C++03 by not matching the superclass.
00023 #if defined(__clang__) && defined(__has_warning)
00024 # if __has_warning("-Wdeprecated")
00025 # pragma clang diagnostic push
00026 # pragma clang diagnostic ignored "-Wdeprecated"
00027 # endif
00028 #endif
00029
00030 namespace gdcm_ns
00031 {
00032 class ParseException : public Exception
00033 {
00034 public:
00035     ParseException() = default;
00036     ~ParseException() throw() override {}
00037
00038     ParseException &operator= ( const ParseException &orig )
00039     {
00040         LastElement = orig.LastElement;
00041         return *this;
00042     }
00043     ParseException(const ParseException& orig):Exception(orig)
00044     {
00045         LastElement = orig.LastElement;
00046     }
00047     /* virtual bool operator==( const ParseException &orig )
00048     {
00049         return true;
00050     }*/
00051     /*
00052     // Multiple calls to what ??
00053     const char* what() const throw()
00054     {
00055         static std::string strwhat;
00056         std::ostringstream oswhat;
00057         oswhat << File << ":" << Line << ":\n";
00058         oswhat << Description;
00059         strwhat = oswhat.str();
00060         return strwhat.c_str();
00061     }
00062     */
00063     void SetLastElement(const DataElement& de)
00064     {
00065         LastElement = de;
00066     }
00067     const DataElement& GetLastElement() const { return LastElement; }
00068
00069 private:
00070     // Store last parsed element before error:
00071     DataElement LastElement;
00072 };
00073 } // end namespace gdcm_ns
00074
00075 // Undo warning suppression.
00076 #if defined(__clang__) && defined(__has_warning)
00077 # if __has_warning("-Wdeprecated")
00078 # pragma clang diagnostic pop
00079 # endif
00080 #endif
00081
00082 #endif

```

11.159 gdcmParser.h File Reference


```

#include "gdcmTag.h"
#include "gdcmByteBuffer.h"

```

```
#include <fstream>
```

Include dependency graph for `gdcParser.h`:



Classes

- class `gdc::Parser`
Parser ala *XML_Parser* from *expat* (SAX)

Namespaces

- namespace `gdc`

11.160 `gdcParser.h`

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdc.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012   =====*/
00013
00014
00015 #ifndef GDCMPARSER_H
00016 #define GDCMPARSER_H
00017
00018 #include "gdcTag.h"
00019 #error do not use
00020 #include "gdcByteBuffer.h"
00021
00022 #include <fstream> // std::ifstream
00023

```

```

00024 namespace gdc
00025 {
00032 class GDCM_EXPORT Parser /*: private IStream*/
00033 {
00034 public:
00035     typedef enum {
00036         NoError,
00037         NoMemoryError,
00038         SyntaxError,
00039         NoElementsError,
00040         TagMismatchError,
00041         DuplicateAttributeError,
00042         JunkAfterDocElementError,
00043         UndefinedEntityError,
00044         UnexpectedStateError
00045     } ErrorType;
00046
00047     Parser() : UserData(0), Buffer(), ErrorCode(NoError) {}
00048     ~Parser() {}
00049
00050     // Parse some more of the document. The string s is a buffer containing
00051     // part (or perhaps all) of the document. The number of bytes of s that
00052     // are part of the document is indicated by len. This means that s
00053     // doesn't have to be null terminated. It also means that if len is
00054     // larger than the number of bytes in the block of memory that s points
00055     // at, then a memory fault is likely. The isFinal parameter informs the
00056     // parser that this is the last piece of the document. Frequently, the
00057     // last piece is empty (i.e. len is zero.) If a parse error occurred,
00058     // it returns 0. Otherwise it returns a non-zero value.
00059     bool Parse(const char* s, int len, bool isFinal);
00060
00061     // Set handlers for start and end tags. Attributes are passed to the
00062     // start handler as a pointer to a vector of char pointers. Each
00063     // attribute seen in a start (or empty) tag occupies 2 consecutive places
00064     // in this vector: the attribute name followed by the attribute value.
00065     // These pairs are terminated by a null pointer.
00066     typedef void (*StartElementHandler) (void *userData,
00067                                         const Tag &tag,
00068                                         const char *atts[]);
00069     typedef void (*EndElementHandler) (void *userData, const Tag &name);
00070     void SetElementHandler(StartElementHandler start, EndElementHandler end);
00071
00072     // Return what type of error has occurred.
00073     ErrorType GetErrorCode() const;
00074
00075     // Return a string describing the error corresponding to code.
00076     // The code should be one of the enums that can be returned from
00077     // GetErrorCode.
00078     static const char *GetErrorString(ErrorType const &err);
00079
00080     // Return the byte offset of the position.
00081     unsigned long GetCurrentByteIndex() const;
00082
00083     // Miscellaneous functions
00084
00085     // The functions in this section either obtain state information from
00086     // the parser or can be used to dynamically set parser options.
00087
00088     // This sets the user data pointer that gets passed to handlers.
00089     void SetUserData(void *userData);
00090
00091     // This returns the user data pointer that gets passed to handlers.
00092     void * GetUserData() const;
00093
00094 protected:
00095
00096     // This is just like Parse, except in this case expat provides the buffer.
00097     // By obtaining the buffer from expat with the GetBuffer function,
00098     // the application can avoid double copying of the input.
00099     bool ParseBuffer(int len, bool isFinal);
00100
00101     // Obtain a buffer of size len to read a piece of the document into.
00102     // A NULL value is returned if expat can't allocate enough memory for
00103     // this buffer. This has to be called prior to every call to ParseBuffer.
00104     char *GetBuffer(int len);
00105
00106     ErrorType Process();
00107
00108 private:
00109     std::ifstream Stream;
00110     void* UserData;

```

```

00111   ByteBuffer Buffer;
00112   ErrorType ErrorCode;
00113
00114   StartElementHandler StartElement;
00115   EndElementHandler EndElement;
00116 };
00117
00118 } // end namespace gdcM
00119
00120 #endif //GDCMPARSER_H

```


11.161 gdcMPDBelement.h File Reference

```


#include "gdcMTag.h"
#include "gdcMVM.h"
#include "gdcMVR.h"
#include "gdcMByteValue.h"
#include "gdcMSmartPointer.h"

```

Include dependency graph for gdcMPDBelement.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::PDBelement](#)
Class to represent a PDB Element.

Namespaces

- namespace [gdcm](#)

Functions

- `std::ostream & gdcm::operator<< (std::ostream &os, const PDBelement &val)`

11.162 gdcmPDBelement.h

[Go to the documentation of this file.](#)

```

00001  /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013  =====*/
00014  #ifndef GDCMPDBeLEMENT_H
00015  #define GDCMPDBeLEMENT_H
00016
00017  #include "gdcmTag.h"
00018  #include "gdcmVM.h"
00019  #include "gdcmVR.h"
00020  #include "gdcmByteValue.h"
00021  #include "gdcmSmartPointer.h"
00022
00023  namespace gdcm
00024  {
00025  class GDCM_EXPORT PDBelement
00026  {
00027  public:
00028   PDBelement() = default;
00029
00030   friend std::ostream& operator<<(std::ostream &os, const PDBelement &val);
00031
00032   const char *GetName() const { return NameField.c_str(); }
00033   void SetName(const char *name) { NameField = name; }
00034
00035   const char *GetValue() const { return ValueField.c_str(); }
00036   void SetValue(const char *value) { ValueField = value; }
00037
00038   bool operator==(const PDBelement &de) const
00039   {
00040     return ValueField == de.ValueField
00041        && NameField == de.NameField;
00042   }
00043
00044 protected:
00045   std::string NameField;
00046   std::string ValueField;
00047 };
00048
00049  //-----
00050  inline std::ostream& operator<<(std::ostream &os, const PDBelement &val)

```


11.164 gdcmPDBHeader.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMPDBHEADER_H
00015 #define GDCMPDBHEADER_H
00016
00017 #include "gdcmTypes.h"
00018 #include "gdcmDataSet.h"
00019 #include "gdcmPDBelement.h"
00020
00021 namespace gdcm
00022 {
00023
00024   /*
00025    * Everything done in this code is for the sole purpose of writing interoperable
00026    * software under Sect. 1201 (f) Reverse Engineering exception of the DMCA.
00027    * If you believe anything in this code violates any law or any of your rights,
00028    * please contact us (gdcm-developers@lists.sourceforge.net) so that we can
00029    * find a solution.
00030    */
00031   //-----
00032
00033   class DataElement;
00034   class PrivateTag;
00035   class GDCM_EXPORT PDBHeader
00036   {
00037   public:
00038     PDBHeader() = default;
00039     ~PDBHeader() = default;
00040
00041     bool LoadFromDataElement(DataElement const &de);
00042
00043     void Print(std::ostream &os) const;
00044
00045     static const PrivateTag & GetPDBInfoTag();
00046
00047     const PDBelement &GetPDBelementByName(const char *name);
00048
00049     bool FindPDBelementByName(const char *name);
00050
00051 protected:
00052     const PDBelement & GetPDBeEnd() const;
00053
00054 private:
00055     int readprotocoldatablock(const char *input, size_t inputlen, bool verbose);
00056     std::vector<PDBelement> InternalPDBDataSet;
00057     static PDBelement PDBeEnd;
00058     bool IsXML;
00059     std::string xmltxt;
00060   };
00061   //-----
00062   inline std::ostream& operator<(std::ostream &os, const PDBHeader &d)
00063   {
00064     d.Print( os );
00065     return os;
00066   }
00067 } // end namespace gdcm
00068 //-----
00069 #endif //GDCMPDBHEADER_H

```


11.166 gdcmPreamble.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMPREAMBLE_H
00015 #define GDCMPREAMBLE_H
00016
00017 #include "gdcmTypes.h"
00018 #include "gdcmVL.h"
00019
00020 namespace gdcm
00021 {
00022
00023     class GDCM_EXPORT Preamble
00024     {
00025     public:
00026         Preamble();
00027         ~Preamble();
00028
00029         friend std::ostream &operator<(std::ostream &os, const Preamble &_val);
00030
00031         void Clear();
00032
00033         void Valid();
00034         void Create();
00035         void Remove();
00036
00037         std::istream &Read(std::istream &is);
00038
00039         std::ostream const &Write(std::ostream &os) const;
00040
00041         void Print(std::ostream &os) const;
00042
00043         const char *GetInternal() const { return Internal; }
00044
00045         bool IsEmpty() const { return !Internal; }
00046
00047         VL GetLength() const { return 128 + 4; }
00048
00049         Preamble(Preamble const &):Internal(nullptr)
00050         {
00051             Create();
00052         }
00053
00054         Preamble& operator=(Preamble const &)
00055         {
00056             Create();
00057             return *this;
00058         }
00059     protected:
00060         //
00061         bool IsValid() const {
00062             // is (IsValid == true) => Internal was read
00063             return true;
00064         }
00065     private:
00066         char *Internal;
00067     };
00068
00069 //-----
00070 inline std::ostream& operator<(std::ostream &os, const Preamble &val)
00071 {
00072     os << val.Internal;
00073     return os;
00074 }
00075
00076 } // end namespace gdcm


```

```
00087
00088 #endif //GDCMPREAMBLE_H
```


11.167 gdcmPrivateTag.h File Reference

```
#include "gdcmTag.h"
#include "gdcmVR.h"
#include "gdcmDataElement.h"
#include <iostream>
#include <iomanip>
#include <string>
#include <algorithm>
#include <string.h>
#include <ctype.h>
```

Include dependency graph for gdcmPrivateTag.h:



This graph shows which files directly or indirectly include this file:



Classes

- class `gdcm::PrivateTag`

Class to represent a Private DICOM Data [Element](#) ([Attribute](#)) [Tag](#) ([Group](#), [Element](#), [Owner](#))

Namespaces

- namespace `gdcm`

Functions

- `std::ostream & gdcm::operator<< (std::ostream &os, const PrivateTag &val)`

11.168 gdcmPrivateTag.h

[Go to the documentation of this file.](#)


```

00001 /*=====
00002
00003     Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005     Copyright (c) 2006-2011 Mathieu Malaterre
00006     All rights reserved.
00007     See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009     This software is distributed WITHOUT ANY WARRANTY; without even
00010     the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011     PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMPRIVATETAG_H
00015 #define GDCMPRIVATETAG_H
00016
00017 #include "gdcmTag.h"
00018 #include "gdcmVR.h"
00019 #include "gdcmDataElement.h"
00020
00021 #include <iostream>
00022 #include <iomanip>
00023 #include <string>
00024 #include <algorithm>
00025
00026 #include <string.h> // strlen
00027 #include <ctype.h> // tolower
00028
00029 namespace gdcm_ns
00030 {
00031
00032
00033 // TODO: We could save some space since we only store 8bits for element
00034 class GDCM_EXPORT PrivateTag : public Tag
00035 {
00036     friend std::ostream& operator<<(std::ostream &_os, const PrivateTag &_val);
00037 public:
00038     PrivateTag(uint16_t group = 0, uint16_t element = 0, const char *owner =
00039         ""):Tag(group,element),Owner(owner ? LOComp::Trim(owner) : "") {
00040         // truncate the high bits
00041         SetElement( (uint8_t)element );
00042     }
00043     PrivateTag( Tag const & t, const char *owner = ""):Tag(t),Owner(owner ? LOComp::Trim(owner) : "") {
00044         // truncate the high bits
00045         SetElement( (uint8_t)t.GetElement());
00046     }
00047
00048     const char *GetOwner() const { return Owner.c_str(); }
00049     void SetOwner(const char *owner) { if(owner) Owner = LOComp::Trim(owner); }
00050
00051     PrivateTag &operator=(const PrivateTag &_val)
00052     {
00053         SetElementTag( _val.GetElementTag() );
00054         Owner = _val.Owner;
00055         return *this;
00056     }
00057
00058     bool operator==(const Tag &_val) const
00059     {


```

11.169 gdcmReader.h File Reference

Include dependency graph for `gdcmReader.h`:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::Reader](#)
Reader ala DOM (Document *Object* Model)

Namespaces

- namespace [gdcm](#)

11.170 gdcmReader.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003     Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005     Copyright (c) 2006-2011 Mathieu Malaterre
00006     All rights reserved.
00007     See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009     This software is distributed WITHOUT ANY WARRANTY; without even
00010     the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011     PURPOSE. See the above copyright notice for more information.
00012
00013     =====*/
00014 #ifndef GDCMREADER_H
00015 #define GDCMREADER_H
00016
00017 #include "gdcmFile.h"
00018
00019 #include <fstream>
00020
00021 namespace gdcm_ns
00022 {
00023     class StreamImageReader;
00053 class GDCM_EXPORT Reader
00054 {
00055 public:

```

```

00056     Reader();
00057     virtual ~Reader();
00058
00060     virtual bool Read(); // Execute()
00061
00064     void SetFileName(const char *filename_native);
00065
00067     void SetStream(std::istream &input_stream) {
00068         Stream = &input_stream;
00069     }
00070
00072     const File &GetFile() const { return *F; }
00073
00075     File &GetFile() { return *F; }
00076
00078     void SetFile(File& file) { F = &file; }
00079
00082     bool ReadUpToTag(const Tag &tag, std::set<Tag> const &skiptags = std::set<Tag>() );
00083
00085     bool ReadSelectedTags(std::set<Tag> const &tags, bool readvalues = true);
00086
00088     bool ReadSelectedPrivateTags(std::set<PrivateTag> const &ptags, bool readvalues = true);
00089
00092     bool CanRead() const;
00093
00096     size_t GetStreamCurrentPosition() const;
00097
00098 protected:
00099     bool ReadPreamble();
00100     bool ReadMetaInformation();
00101     bool ReadDataSet();
00102
00103     SmartPointer<File> F;
00104
00105     friend class StreamImageReader; //need to be friended to be able to grab the GetStreamPtr
00106
00107     //this function is added for the StreamImageReader, which needs to read
00108     //up to the pixel data and then stops right before reading the pixel data.
00109     //it's used to get that position, so that reading can continue
00110     //apace once the read function is called.
00111     //so, this function gets the stream directly, and then allows for position information
00112     //from the tellg function, and allows for stream/pointer manip in order
00113     //to read the pixel data. Note, of course, that reading pixel elements
00114     //will still have to be subject to endianness swaps, if necessary.
00115     std::istream* GetStreamPtr() const { return Stream; }
00116
00117 private:
00118     template <typename T_Caller>
00119     bool InternalReadCommon(const T_Caller &caller);
00120     TransferSyntax GuessTransferSyntax();
00121     std::istream *Stream;
00122     std::ifstream *Ifstream;
00123
00124     // prevent copy/move to avoid 2 ifstream leak
00125     Reader(const Reader &) = delete;
00126     Reader &operator=(const Reader &) = delete;
00127     Reader(const Reader &&) = delete;
00128     Reader &operator=(const Reader &&) = delete;
00129 };
00130
00136
00137 } // end namespace gdcm_ns
00138
00139
00140 #endif //GDCMREADER_H

```

11.171 gdcmSequenceOfFragments.h File Reference

```


#include "gdcmValue.h"
#include "gdcmVL.h"
#include "gdcmFragment.h"

```



```
#include "gdcmBasicOffsetTable.h"
```

Include dependency graph for gdcmSequenceOfFragments.h:



Classes

- class [gdcm::SequenceOfFragments](#)
Class to represent a Sequence Of Fragments.

Namespaces

- namespace [gdcm](#)

11.172 gdcmSequenceOfFragments.h

[Go to the documentation of this file.](#)

```
00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013   =====*/
00014 #ifndef GDCMSEQUENCEOFFRAGMENTS_H
00015 #define GDCMSEQUENCEOFFRAGMENTS_H
00016
00017 #include "gdcmValue.h"
00018 #include "gdcmVL.h"
00019 #include "gdcmFragment.h"
00020 #include "gdcmBasicOffsetTable.h"
```

```

00021
00022 namespace gdcm_ns
00023 {
00024
00025     // FIXME gdcmSequenceOfItems and gdcmSequenceOfFragments
00026     // should be rethink (duplicate code)
00031 class GDCM_EXPORT SequenceOfFragments : public Value
00032 {
00033 public:
00034     // Typdefs:
00035     typedef std::vector<Fragment> FragmentVector;
00036     typedef FragmentVector::size_type SizeType;
00037     typedef FragmentVector::iterator Iterator;
00038     typedef FragmentVector::const_iterator ConstIterator;
00039     Iterator Begin() { return Fragments.begin(); }
00040     Iterator End() { return Fragments.end(); }
00041     ConstIterator Begin() const { return Fragments.begin(); }
00042     ConstIterator End() const { return Fragments.end(); }
00043
00044     SequenceOfFragments():Table(),SequenceLengthField(0xFFFFFFFF) { }
00045
00046
00048     VL GetLength() const override {
00049         return SequenceLengthField;
00050     }
00051
00053     void SetLength(VL length) override {
00054         SequenceLengthField = length;
00055     }
00056
00058     void Clear() override;
00059
00061     void AddFragment(Fragment const &item);
00062
00063     // Compute the length of all fragments (and fragments only!).
00064     // Basically the size of the PixelData as stored (in bytes).
00065     unsigned long ComputeByteLength() const;
00066
00067     // Compute the length of fragments (in bytes)+ length of tag...
00068     // to be used for computation of Group Length
00069     VL ComputeLength() const;
00070
00071     // Get the buffer
00072     bool GetBuffer(char *buffer, unsigned long length) const;
00073     bool GetFragBuffer(unsigned int fragNb, char *buffer, unsigned long &length) const;
00074
00075     SizeType GetNumberOfFragments() const;
00076     const Fragment& GetFragment(SizeType num) const;
00077
00078     // Write the buffer of each fragment (call WriteBuffer on all Fragments, which are
00079     // ByteValue). No Table information is written.
00080     bool WriteBuffer(std::ostream &os) const;
00081
00082     const BasicOffsetTable &GetTable() const { return Table; }
00083     BasicOffsetTable &GetTable() { return Table; }
00084
00085 template <typename TSwap>
00086 std::istream& Read(std::istream &is, bool readvalues = true)
00087 {
00088     gdcm_assert( SequenceLengthField.IsUndefined() );
00089     ReadPreValue<TSwap>(is);
00090     return ReadValue<TSwap>(is, readvalues);
00091 }
00092
00093 template <typename TSwap>
00094 std::istream& ReadPreValue(std::istream &is)
00095 {
00096     // First item is the basic offset table:
00097     #if 0
00098     try
00099     {
00100         Table.Read<TSwap>(is);
00101         gdcmDebugMacro( "Table: " << Table );
00102     }
00103     catch(...)
00104     {
00105         // throw "SIEMENS Icon thingy";
00106         // Bug_Siemens_PrivateIconNoItem.dcm
00107         // First thing first let's rewind
00108         is.seekg(-4, std::ios::cur);
00109         // FF D8 <=> Start of Image (SOI) marker
00110         // FF E0 <=> APP0 Reserved for Application Use

```

```

00111     if ( Table.GetTag() == Tag(0xd8ff,0xe0ff) )
00112     {
00113         Table = BasicOffsetTable(); // clear up stuff
00114         //Table.SetByteValue( "", 0 );
00115         Fragment frag;
00116         if( FillFragmentWithJPEG( frag, is ) )
00117         {
00118             Fragments.push_back( frag );
00119         }
00120         return is;
00121     }
00122     else
00123     {
00124         throw "Catch me if you can";
00125         //gdcassert(0);
00126     }
00127 }
00128 #endif
00129 Table.Read<TSwap>(is);
00130 gdcDebugMacro( "Table: " « Table );
00131 #endif
00132 return is;
00133 }
00134
00135 template <typename TSwap>
00136 std::istream& ReadValue(std::istream &is, bool /*readvalues*/)
00137 {
00138     const Tag seqDelItem(0xfffe,0xe0dd);
00139     // not used for now...
00140     Fragment frag;
00141     try
00142     {
00143         while( frag.Read<TSwap>(is) && frag.GetTag() != seqDelItem )
00144         {
00145             //gdcDebugMacro( "Frag: " « frag );
00146             Fragments.push_back( frag );
00147         }
00148         gdcassert( frag.GetTag() == seqDelItem && frag.GetVL() == 0 );
00149     }
00150     catch(Exception &ex)
00151     {
00152         (void)ex;
00153 #ifdef GDCM_SUPPORT_BROKEN_IMPLEMENTATION
00154         // that's ok ! In all cases the whole file was read, because
00155         // Fragment::Read only fail on eof() reached 1.
00156         // SIEMENS-JPEG-CorruptFrag.dcm is more difficult to deal with, we have a
00157         // partial fragment, read we decide to add it anyway to the stack of
00158         // fragments (eof was reached so we need to clear error bit)
00159         if( frag.GetTag() == Tag(0xfffe,0xe000) )
00160         {
00161             gdcWarningMacro( "Pixel Data Fragment could be corrupted. Use file at own risk" );
00162             Fragments.push_back( frag );
00163             is.clear(); // clear the error bit
00164         }
00165         // 2. GENESIS_SIGNA-JPEG-CorruptFrag.dcm
00166         else if ( frag.GetTag() == Tag(0xddff,0x00e0) )
00167         {
00168             gdcassert( Fragments.size() == 1 );
00169             const ByteValue *bv = Fragments[0].GetByteValue();
00170             gdcassert( (unsigned char)bv->GetPointer()[ bv->GetLength() - 1 ] == 0xfe );
00171             // Yes this is an extra copy, this is a bug anyway, go fix YOUR code
00172             Fragments[0].SetByteValue( bv->GetPointer(), bv->GetLength() - 1 );
00173             gdcWarningMacro( "JPEG Fragment length was declared with an extra byte"
00174                 " at the end: stripped !" );
00175             is.clear(); // clear the error bit
00176         }
00177         // 3. LEICA/WSI
00178         else if ( (frag.GetTag().GetGroup() == 0x00ff)
00179             && ((frag.GetTag().GetElement() & 0x00ff) == 0xe0) )
00180         {
00181             // Looks like there is a mess with offset and odd byte array
00182             // We are going first to backtrack one byte back, and then use a
00183             // ReadBacktrack function which in turn may backtrack up to 10 bytes
00184             // backward. This appears to be working on a set of DICOM/WSI files from
00185             // LEICA
00186             gdcWarningMacro( "Trying to fix the even-but-odd value length bug #1" );
00187             gdcassert( Fragments.size() );
00188             const size_t lastf = Fragments.size() - 1;
00189             const ByteValue *bv = Fragments[ lastf ].GetByteValue();
00190             const char *a = bv->GetPointer();
00191             gdcAssertAlwaysMacro( (unsigned char)a[ bv->GetLength() - 1 ] == 0xfe );

```

```

00192     Fragments[ lastf ].SetByteValue( bv->GetPointer(), bv->GetLength() - 1 );
00193     is.seekg( -9, std::ios::cur );
00194     gdcmm_assert( is.good() );
00195     while( frag.ReadBacktrack<TSwap>(is) && frag.GetTag() != seqDelItem )
00196     {
00197         gdcmmDebugMacro( "Frag: " << frag );
00198         Fragments.push_back( frag );
00199     }
00200     gdcmm_assert( frag.GetTag() == seqDelItem && frag.GetVL() == 0 );
00201 }
00202 // 4. LEICA/WSI (bis)
00203 else if ( frag.GetTag().GetGroup() == 0xe000 )
00204 {
00205     // Looks like there is a mess with offset and odd byte array
00206     // We are going first to backtrack one byte back, and then use a
00207     // ReadBacktrack function which in turn may backtrack up to 10 bytes
00208     // backward. This appears to be working on a set of DICOM/WSI files from
00209     // LEICA
00210     gdcmmWarningMacro( "Trying to fix the even-but-odd value length bug #2" );
00211     gdcmm_assert( Fragments.size() );
00212     const size_t lastf = Fragments.size() - 1;
00213     const ByteValue *bv = Fragments[ lastf ].GetByteValue();
00214     const char *a = bv->GetPointer();
00215     gdcmmAssertAlwaysMacro( (unsigned char)a[ bv->GetLength() - 2 ] == 0xfe );
00216     Fragments[ lastf ].SetByteValue( bv->GetPointer(), bv->GetLength() - 2 );
00217     is.seekg( -10, std::ios::cur );
00218     gdcmm_assert( is.good() );
00219     while( frag.ReadBacktrack<TSwap>(is) && frag.GetTag() != seqDelItem )
00220     {
00221         gdcmmDebugMacro( "Frag: " << frag );
00222         Fragments.push_back( frag );
00223     }
00224     gdcmm_assert( frag.GetTag() == seqDelItem && frag.GetVL() == 0 );
00225 }
00226 // 5. LEICA/WSI (ter)
00227 else if ( (frag.GetTag().GetGroup() & 0x00ff) == 0x00e0
00228 && (frag.GetTag().GetElement() & 0xff00) == 0x0000 )
00229 {
00230     // Looks like there is a mess with offset and odd byte array
00231     // We are going first to backtrack one byte back, and then use a
00232     // ReadBacktrack function which in turn may backtrack up to 10 bytes
00233     // backward. This appears to be working on a set of DICOM/WSI files from
00234     // LEICA
00235     gdcmmWarningMacro( "Trying to fix the even-but-odd value length bug #3" );
00236     gdcmm_assert( Fragments.size() );
00237     const size_t lastf = Fragments.size() - 1;
00238     const ByteValue *bv = Fragments[ lastf ].GetByteValue();
00239     const char *a = bv->GetPointer();
00240     gdcmmAssertAlwaysMacro( bv->GetLength() >= 3 && (unsigned char)a[ bv->GetLength() - 3 ] == 0xfe );
00241     Fragments[ lastf ].SetByteValue( bv->GetPointer(), bv->GetLength() - 3 );
00242     is.seekg( -11, std::ios::cur );
00243     gdcmm_assert( is.good() );
00244     while( frag.ReadBacktrack<TSwap>(is) && frag.GetTag() != seqDelItem )
00245     {
00246         gdcmmDebugMacro( "Frag: " << frag );
00247         Fragments.push_back( frag );
00248     }
00249     gdcmm_assert( frag.GetTag() == seqDelItem && frag.GetVL() == 0 );
00250 }
00251 else
00252 {
00253     // 3. gdcmm-JPEG-LossLess3a.dcm: easy case, an extra tag was found
00254     // instead of terminator (eof is the next char)
00255     gdcmmWarningMacro( "Reading failed at Tag:" << frag.GetTag() << " Index #"
00256 << Fragments.size() << " Offset " << is.tellg() << ". Use file at own risk."
00257 << ex.what() );
00258 }
00259 #endif /* GDCMM_SUPPORT_BROKEN_IMPLEMENTATION */
00260 }
00261
00262 return is;
00263 }
00264
00265 template <typename TSwap>
00266 std::ostream const &Write(std::ostream &os) const
00267 {
00268     if( !Table.Write<TSwap>(os) )
00269     {
00270         gdcmm_assert(0 && "Should not happen");
00271         return os;
00272     }

```

```

00273     for(ConstIterator it = Begin();it != End(); ++it)
00274     {
00275         it->Write<TSwap>(os);
00276     }
00277     // seq del item is not stored, write it !
00278     const Tag seqDelItem(0xfffe,0xe0dd);
00279     seqDelItem.Write<TSwap>(os);
00280     VL zero = 0;
00281     zero.Write<TSwap>(os);
00282
00283     return os;
00284 }
00285
00286 // #if defined(SWIGPYTHON) || defined(SWIGCSHARP) || defined(SWIGJAVA)
00287 // For now leave it there, this does not make sense in the C++ layer
00288 // Create a new object
00289 static SmartPointer<SequenceOfFragments> New()
00290 {
00291     return new SequenceOfFragments();
00292 }
00293 // #endif
00294
00295 protected:
00296 public:
00297     void Print(std::ostream &os) const override {
00298         os << "SQ L= " << SequenceLengthField << "\n";
00299         os << "Table:" << Table << "\n";
00300         for(ConstIterator it = Begin();it != End(); ++it)
00301         {
00302             os << " " << *it << "\n";
00303         }
00304         gdcm_assert( SequenceLengthField.IsUndefined() );
00305         {
00306             const Tag seqDelItem(0xfffe,0xe0dd);
00307             VL zero = 0;
00308             os << seqDelItem;
00309             os << "\t" << zero;
00310         }
00311     }
00312     bool operator==(const Value &val) const override
00313     {
00314         const SequenceOfFragments &sqf = dynamic_cast<const SequenceOfFragments>(val);
00315         return Table == sqf.Table &&
00316             SequenceLengthField == sqf.SequenceLengthField &&
00317             Fragments == sqf.Fragments;
00318     }
00319
00320 private:
00321     BasicOffsetTable Table;
00322     VL SequenceLengthField;
00324     FragmentVector Fragments;
00325
00326 private:
00327     bool FillFragmentWithJPEG( Fragment & frag, std::istream & is );
00328 };
00329
00334
00335 } // end namespace gdcm_ns
00336
00337 #endif //GDCMSEQUENCEOFFRAGMENTS_H

```

11.173 gdcmSequenceOfItems.h File Reference

```

#include "gdcmValue.h"
#include "gdcmItem.h"
#include <vector>
#include <cstring>
#include "gdcmSequenceOfItems.txx"

```



```

00041 public:
00042     // Typdefs:
00043     typedef std::vector< Item > ItemVector;
00044     typedef ItemVector::size_type SizeType;
00045     typedef ItemVector::iterator Iterator;
00046     typedef ItemVector::const_iterator ConstIterator;
00047     Iterator Begin() { return Items.begin(); }
00048     Iterator End() { return Items.end(); }
00049     ConstIterator Begin() const { return Items.begin(); }
00050     ConstIterator End() const { return Items.end(); }
00051
00053     SequenceOfItems():SequenceLengthField(0xFFFFFFFF) { }
00054     //SequenceOfItems(VL const &vl = 0xFFFFFFFF):SequenceLengthField(vl),NType(type) { }
00055
00057     VL GetLength() const override { return SequenceLengthField; }
00059     void SetLength(VL length) override {
00060         SequenceLengthField = length;
00061     }
00063     void SetLengthToUndefined();
00065     bool IsUndefinedLength() const {
00066         return SequenceLengthField.IsUndefined();
00067     }
00068
00069     template <typename TDE>
00070     VL ComputeLength() const;
00071
00073     void Clear() override;
00074
00076     void AddItem(Item const &item);
00077
00079     Item & AddNewUndefinedLengthItem();
00080
00083     bool RemoveItemByIndex( const SizeType index );
00084
00085     bool IsEmpty() const { return Items.empty(); }
00086     SizeType GetNumberOfItems() const { return Items.size(); }
00087     void SetNumberOfItems(SizeType n) { Items.resize(n); }
00088
00089     /* WARNING: first item is #1 (see DICOM standard)
00090     * Each Item shall be implicitly assigned an ordinal position starting with the value 1 for the
00091     * first Item in the Sequence, and incremented by 1 with each subsequent Item. The last Item in the
00092     * Sequence shall have an ordinal position equal to the number of Items in the Sequence.
00093     */
00094     const Item &GetItem(SizeType position) const;
00095     Item &GetItem(SizeType position);
00096
00097     SequenceOfItems &operator=(const SequenceOfItems &val) {
00098         SequenceLengthField = val.SequenceLengthField;
00099         Items = val.Items;
00100         return *this;
00101     }
00102
00103     template <typename TDE, typename TSwap>
00104     std::istream &Read(std::istream &is, bool readvalues = true)
00105     {
00106         (void)readvalues;
00107         const Tag seqDelItem(0xfffe,0xe0dd);
00108         if( SequenceLengthField.IsUndefined() )
00109         {
00110             Item item;
00111             while( item.Read<TDE,TSwap>(is) && item.GetTag() != seqDelItem )
00112             {
00113                 //gdcmDebugMacro( "Item: " << item );
00114                 gdcm_assert( item.GetTag() != seqDelItem );
00115                 Items.push_back( item );
00116                 item.Clear();
00117             }
00118             //gdcm_assert( item.GetTag() == seqDelItem && item.GetVL() == 0 );
00119         }
00120         else
00121         {
00122             Item item;
00123             VL l = 0;
00124             //is.seekg( SequenceLengthField, std::ios::cur ); return is;
00125             while( l != SequenceLengthField )
00126             {
00127                 try
00128                 {
00129                     item.Read<TDE,TSwap>(is);
00130                 }
00131                 catch( Exception &ex )

```

```

00132         {
00133         if( strcmp( ex.GetDescription(), "Changed Length" ) == 0 )
00134         {
00135             VL newlength = 1 + item.template GetLength<TDE>();
00136             if( newlength > SequenceLengthField )
00137             {
00138                 // BogugsItemAndSequenceLength.dcm
00139                 gdcWarningMacro( "SQ length is wrong" );
00140                 SequenceLengthField = newlength;
00141             }
00142         }
00143         else
00144         {
00145             throw ex;
00146         }
00147     }
00148 #ifndef GDCM_SUPPORT_BROKEN_IMPLEMENTATION
00149     if( item.GetTag() == seqDelItem )
00150     {
00151         gdcWarningMacro( "SeqDelItem found in defined length Sequence. Skipping" );
00152         gdcAssert( item.GetVL() == 0 );
00153         gdcAssert( item.GetNestedDataSet().Size() == 0 );
00154         // we need to pay attention that the length of the Sequence of Items will be wrong
00155         // this way. Indeed by not adding this item we are changing the size of this sqi
00156     }
00157     else // Not a seq del item marker
00158 #endif
00159     {
00160         // By design we never load them. If we were to load those attribute
00161         // as normal item it would become very complex to convert a sequence
00162         // from defined length to undefined length with the risk to write two
00163         // seq del marker
00164         Items.push_back( item );
00165     }
00166     l += item.template GetLength<TDE>();
00167     if( l > SequenceLengthField )
00168     {
00169         gdcDebugMacro( "Found: Length of Item larger than expected" );
00170         throw "Length of Item larger than expected";
00171     }
00172     gdcAssert( l <= SequenceLengthField );
00173     //std::cerr << "sqi debug len: " << is.tell() << " " << l << " " << SequenceLengthField << std::endl;
00174 #ifndef GDCM_SUPPORT_BROKEN_IMPLEMENTATION
00175     // MR_Philips_Intera_No_PrivateSequenceImplicitVR.dcm
00176     // (0x2005, 0x1080): for some reason computation of length fails...
00177     if( SequenceLengthField == 778 && l == 774 )
00178     {
00179         gdcWarningMacro( "PMS: Super bad hack" );
00180         SequenceLengthField = l;
00181         throw Exception( "Wrong Length" );
00182         //l = SequenceLengthField;
00183     }
00184     // Bug_Philips_ItemTag_3F3F
00185     // (0x2005, 0x1080): Because we do not handle fully the bug at the item
00186     // level we need to check here too
00187     else if ( SequenceLengthField == 444 && l == 3*71 )
00188     {
00189         // This one is a double bug. Item length is wrong and impact SQ length
00190         gdcWarningMacro( "PMS: Super bad hack" );
00191         l = SequenceLengthField;
00192     }
00193 #endif
00194     }
00195     gdcAssert( l == SequenceLengthField );
00196 }
00197 return is;
00198 }
00199
00200 template <typename TDE,typename TSwap>
00201 std::ostream const &Write(std::ostream &os) const
00202 {
00203     typename ItemVector::const_iterator it = Items.begin();
00204     for(;it != Items.end(); ++it)
00205     {
00206         it->Write<TDE,TSwap>(os);
00207     }
00208     if( SequenceLengthField.IsUndefined() )
00209     {
00210         // seq del item is not stored, write it !
00211         const Tag seqDelItem(0xffff,0xe0dd);
00212         seqDelItem.Write<TSwap>(os);

```



```

00213         VL zero = 0;
00214         zero.Write<TSwap>(os);
00215     }
00216
00217     return os;
00218 }
00219
00220 //protected:
00221 void Print(std::ostream &os) const override {
00222     os << "\t(" << SequenceLengthField << ")\n";
00223     ItemVector::const_iterator it =
00224         Items.begin();
00225     for(; it != Items.end(); ++it)
00226     {
00227         os << "    " << *it;
00228     }
00229     if( SequenceLengthField.IsUndefined() )
00230     {
00231         const Tag seqDelItem(0xfffe,0xe0dd);
00232         VL zero = 0;
00233         os << seqDelItem;
00234         os << "\t" << zero;
00235     }
00236 }
00237
00238 static SmartPointer<SequenceOfItems> New()
00239 {
00240     return new SequenceOfItems;
00241 }
00242 bool FindDataElement(const Tag &t) const;
00243
00244 bool operator==(const Value &val) const override
00245 {
00246     const SequenceOfItems &sqi = dynamic_cast<const SequenceOfItems>(val);
00247     return SequenceLengthField == sqi.SequenceLengthField &&
00248         Items == sqi.Items;
00249 }
00250
00251 private:
00252 public:
00253     VL SequenceLengthField;
00254     ItemVector Items;
00255 };
00256
00257 } // end namespace gdcm_ns
00258
00259 } // end namespace gdcm_ns
00260
00261 #include "gdcmSequenceOfItems.txx"
00262
00263 #endif //GDCMSEQUENCEOFITEMS_H

```


11.175 gdcmTag.h File Reference

```

#include "gdcmTypes.h"
#include <iostream>
#include <iomanip>

```

Include dependency graph for `gdcmTag.h`:



This graph shows which files directly or indirectly include this file:



Classes

- class `gdcm::Tag`
Class to represent a DICOM Data *Element (Attribute) Tag* (Group, *Element*).

Namespaces

- namespace `gdcm`

Functions

- `std::ostream & gdcm::operator<< (std::ostream &_os, const Tag &_val)`
- `std::istream & gdcm::operator>> (std::istream &_is, Tag &_val)`

11.176 gdcmTag.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMTAG_H
00015 #define GDCMTAG_H
00016
00017 #include "gdcmTypes.h"
00018
00019 #include <iostream>
00020 #include <iomanip>
00021
00022 namespace gdcm
00023 {
00024
00025     class GDCM_EXPORT Tag
00026     {
00027     public:
00028         Tag(uint16_t group, uint16_t element) {
00029             ElementTag.tags[0] = group; ElementTag.tags[1] = element;
00030         }
00031         Tag(uint32_t tag = 0) {
00032             SetElementTag(tag);
00033         }
00034
00035         friend std::ostream& operator<<(std::ostream &_os, const Tag &_val);
00036         friend std::istream& operator>>(std::istream &_is, Tag &_val);
00037
00038         uint16_t GetGroup() const { return ElementTag.tags[0]; }
00039         uint16_t GetElement() const { return ElementTag.tags[1]; }
00040         void SetGroup(uint16_t group) { ElementTag.tags[0] = group; }
00041         void SetElement(uint16_t element) { ElementTag.tags[1] = element; }
00042         void SetElementTag(uint16_t group, uint16_t element) {
00043             ElementTag.tags[0] = group; ElementTag.tags[1] = element;
00044         }
00045
00046         uint32_t GetElementTag() const {
00047             #ifndef GDCM_WORDS_BIGENDIAN
00048                 return (ElementTag.tag<16) | (ElementTag.tag>16);
00049             #else
00050                 return ElementTag.tag;
00051             #endif
00052         }
00053         void SetElementTag(uint32_t tag) {
00054             #ifndef GDCM_WORDS_BIGENDIAN
00055                 tag = ( (tag<16) | (tag>16) );
00056             #endif
00057             ElementTag.tag = tag;
00058         }
00059
00060         const uint16_t &operator[](const unsigned int &_id) const
00061         {
00062             gdcm_assert(_id<2);
00063             return ElementTag.tags[_id];
00064         }
00065         uint16_t &operator[](const unsigned int &_id)
00066         {
00067             gdcm_assert(_id<2);
00068             return ElementTag.tags[_id];
00069         }
00070
00071         Tag &operator=(const Tag &_val)
00072         {
00073             ElementTag.tag = _val.ElementTag.tag;
00074             return *this;
00075         }
00076     };
00077
00078     Tag &operator=(const Tag &_val)
00079     {
00080         ElementTag.tag = _val.ElementTag.tag;
00081         return *this;
00082     }
00083
00084     Tag &operator=(const Tag &_val)
00085     {
00086         ElementTag.tag = _val.ElementTag.tag;
00087         return *this;
00088     }
00089
00090     Tag &operator=(const Tag &_val)
00091     {
00092         ElementTag.tag = _val.ElementTag.tag;
00093         return *this;
00094     }
00095
00096     Tag &operator=(const Tag &_val)
00097     {
00098         ElementTag.tag = _val.ElementTag.tag;
00099         return *this;
00100     }

```

```

00101     }
00102
00103     bool operator==(const Tag &_val) const
00104     {
00105         return ElementTag.tag == _val.ElementTag.tag;
00106     }
00107     bool operator!=(const Tag &_val) const
00108     {
00109         return ElementTag.tag != _val.ElementTag.tag;
00110     }
00111
00112     // FIXME FIXME FIXME TODO
00113     // the following is pretty dumb. Since we have control over who is group
00114     // and who is element, we should reverse them in little endian and big endian case
00115     // since what we really want is fast comparison and not guarantee that group is in #0
00116     // ...
00117     bool operator<(const Tag &_val) const
00118     {
00119         #ifndef GDCM_WORDS_BIGENDIAN
00120             if( ElementTag.tags[0] < _val.ElementTag.tags[0] )
00121                 return true;
00122             if( ElementTag.tags[0] == _val.ElementTag.tags[0]
00123                 && ElementTag.tags[1] < _val.ElementTag.tags[1] )
00124                 return true;
00125             return false;
00126         #else
00127             // Plain comparison is enough!
00128             return ( ElementTag.tag < _val.ElementTag.tag );
00129         #endif
00130     }
00131     bool operator<=(const Tag &t2) const
00132     {
00133         const Tag &t1 = *this;
00134         return t1 == t2 || t1 < t2;
00135     }
00136
00137     Tag(const Tag &_val)
00138     {
00139         ElementTag.tag = _val.ElementTag.tag;
00140     }
00141
00142     uint32_t GetLength() const { return 4; }
00143
00144     bool IsPublic() const { return !(ElementTag.tags[0] % 2); }
00145
00146     bool IsPrivate() const { return !IsPublic(); }
00147
00148     //-----
00149     template <typename TSwap>
00150     std::istream &Read(std::istream &is)
00151     {
00152         if( is.read(ElementTag.bytes, 4) )
00153             TSwap::SwapArray(ElementTag.tags, 2);
00154         return is;
00155     }
00156
00157     template <typename TSwap>
00158     const std::ostream &Write(std::ostream &os) const
00159     {
00160         uint16_t copy[2];
00161         copy[0] = ElementTag.tags[0];
00162         copy[1] = ElementTag.tags[1];
00163         TSwap::SwapArray(copy, 2);
00164         return os.write((char*)(&copy), 4);
00165     }
00166
00167     Tag GetPrivateCreator() const
00168     {
00169         // See PS 3.5 - 7.8.1 PRIVATE DATA ELEMENT TAGS
00170         // eg: 0x0123,0x1425 -> 0x0123,0x0014
00171         if( IsPrivate() && !IsPrivateCreator() )
00172         {
00173             Tag r = *this;
00174             r.SetElement( (uint16_t)(GetElement() >> 8) );
00175             return r;
00176         }
00177         if( IsPrivateCreator() ) return *this;
00178         return Tag(0x0,0x0);
00179     }
00180
00181     void SetPrivateCreator(Tag const &t)
00182     {
00183         // See PS 3.5 - 7.8.1 PRIVATE DATA ELEMENT TAGS

```

```

00196     // eg: 0x0123,0x0045 -> 0x0123,0x4567
00197     gdcm_assert( t.IsPrivate() /*&& t.IsPrivateCreator()*/ );
00198     const uint16_t element = (uint16_t)(t.GetElement() << 8);
00199     const uint16_t base = (uint16_t)(GetElement() << 8);
00200     SetElement( (uint16_t)((base >> 8) + element) );
00201     SetGroup( t.GetGroup() );
00202 }
00203
00206 bool IsPrivateCreator() const
00207 {
00208     return IsPrivate() && (GetElement() <= 0xFF && GetElement() >= 0x10);
00209 }
00210
00212 bool IsIllegal() const
00213 {
00214     // DICOM reserved those groups:
00215     return GetGroup() == 0x0001 || GetGroup() == 0x0003 || GetGroup() == 0x0005 || GetGroup() == 0x0007
00216     // This is a very special case, in private group, one cannot use element [0x01,0x09] ...
00217     // || (IsPrivate() && !IsPrivateCreator() && !IsGroupLength());
00218     || (IsPrivate() && GetElement() > 0x0 && GetElement() < 0x10 );
00219 }
00220
00222 bool IsGroupLength() const
00223 {
00224     return GetElement() == 0x0;
00225 }
00226
00228 bool IsGroupXX(const Tag &t) const
00229 {
00230     if( t.GetElement() == GetElement() )
00231     {
00232         if( t.IsPrivate() ) return false;
00233         uint16_t group = (uint16_t)((GetGroup() >> 8) << 8);
00234         return group == t.GetGroup();
00235     }
00236     return false;
00237 }
00238
00244 bool ReadFromCommaSeparatedString(const char *str);
00245
00248 bool ReadFromContinuousString(const char *str);
00249
00252 std::string PrintAsContinuousString() const;
00253
00255 std::string PrintAsContinuousUpperCaseString() const;
00256
00259 bool ReadFromPipeSeparatedString(const char *str);
00260
00263 std::string PrintAsPipeSeparatedString() const;
00264
00265 private:
00266     union { uint32_t tag; uint16_t tags[2]; char bytes[4]; } ElementTag;
00267 };
00268 //-----
00269 inline std::istream& operator>(std::istream &_is, Tag &_val)
00270 {
00271     char c;
00272     _is >> c;
00273     uint16_t a, b;
00274     _is >> std::hex >> a;
00275     //_is >> std::hex >> _val[0];
00276     //_is >> std::hex >> _val.ElementTag.tags[0];
00277     _is >> c;
00278     //_is >> _val[1];
00279     //_is >> std::hex >> _val.ElementTag.tags[1];
00280     _is >> std::hex >> b;
00281     _is >> c;
00282     _val.SetGroup( a );
00283     _val.SetElement( b );
00284     return _is;
00285 }
00286
00287 inline std::ostream& operator<(std::ostream &_os, const Tag &_val)
00288 {
00289     _os.setf( std::ios::right);
00290     _os << std::hex << '(' << std::setw( 4 ) << std::setfill( '0' )
00291         << _val[0] << ',' << std::setw( 4 ) << std::setfill( '0' )
00292         << _val[1] << ')' << std::setfill( ' ' ) << std::dec;
00293     return _os;
00294 }
00295

```

```


00296 } // end namespace gdcM
00297
00298 #endif //GDCMTAG_H

```

11.177 gdcMTagToVR.h File Reference

```
#include "gdcMVR.h"
```

Include dependency graph for gdcMTagToVR.h:



Namespaces

- namespace [gdcM](#)

Functions

- [VR::VRType gdcM::GetVRFromTag](#) ([Tag](#) const &tag)

11.178 gdcMTagToVR.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003 Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005 Copyright (c) 2006-2011 Mathieu Malaterre
00006 All rights reserved.
00007 See Copyright.txt or http://gdcM.sourceforge.net/Copyright.html for details.
00008
00009 This software is distributed WITHOUT ANY WARRANTY; without even
00010 the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011 PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/

```

```


00014 #ifndef GDCMTAGTOVR_H
00015 #define GDCMTAGTOVR_H
00016
00017 #include "gdcmVR.h"
00018
00019 namespace gdcm
00020 {
00021     class Tag;
00022     VR::VRType GetVRFromTag( Tag const & tag );
00023 }
00024
00025 #endif // GDCMTAGTOVR_H

```

11.179 gdcmTransferSyntax.h File Reference

```
#include "gdcmSwapCode.h"
```

Include dependency graph for gdcmTransferSyntax.h:



This graph shows which files directly or indirectly include this file:



Classes

- class `gdcm::TransferSyntax`
Class to manipulate Transfer Syntax.

Namespaces

- namespace `gdcm`

Functions

- `std::ostream & gdcm::operator<< (std::ostream &_os, const TransferSyntax &ts)`

11.180 gdcmTransferSyntax.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMTRANSFERSYNTAX_H
00015 #define GDCMTRANSFERSYNTAX_H
00016
00017 #include "gdcmSwapCode.h"
00018
00019 namespace gdcm
00020 {
00021
00022     class GDCM_EXPORT TransferSyntax
00023     {
00024     public:
00025         typedef enum {
00026             Unknown = 0,
00027             Explicit,
00028             Implicit
00029         } NegotiatedType;
00030
00031         #if 0
00032         //NOT FLEXIBLE, since forces user to update lib every time new module
00033         //comes out...
00034         // TODO
00035         typedef enum {
00036             NoSpacing = 0,
00037             PixelSpacing,
00038             ImagerPixelSpacing,
00039             PixelAspectRatio
00040         } ImageSpacingType;
00041         ImageSpacingType GetImageSpacing();
00042         #endif
00043
00044         typedef enum {
00045             ImplicitVRLittleEndian = 0,
00046             ImplicitVRBigEndianPrivateGE,
00047             ExplicitVRLittleEndian,
00048             DeflatedExplicitVRLittleEndian,
00049             ExplicitVRBigEndian,
00050             JPEGBaselineProcess1,
00051             JPEGExtendedProcess2_4,
00052             JPEGExtendedProcess3_5,
00053             JPEGsSpectralSelectionProcess6_8,
00054             JPEGFullProgressionProcess10_12,
00055             JPEGLosslessProcess14,
00056             JPEGLosslessProcess14_1,
00057             JPEGLSLossless,
00058             JPEGLSNearLossless,
00059             JPEG2000Lossless,
00060             JPEG2000,
00061             JPEG2000Part2Lossless,
00062             JPEG2000Part2,
00063             RLELossless,
00064             MPEG2MainProfile,
00065             ImplicitVRBigEndianACRNEEMA,
00066             WeirdPapryus,

```



```

00084     CT_private_ELE,
00085     JPIPReferenced,
00086     MPEG2MainProfileHighLevel,
00087     MPEG4AVCH264HighProfileLevel4_1,
00088     MPEG4AVCH264BDcompatibleHighProfileLevel4_1,
00089     HTJ2KLossless,
00090     HTJ2KRPCLossless,
00091     HTJ2K,
00092     TS_END
00093 } TSType;
00094
00095 // Return the string as written in the official DICOM dict from
00096 // a custom enum type
00097 static const char* GetTSString(TSType ts);
00098 static TSType GetTSType(const char *str);
00099
00100 NegotiatedType GetNegotiatedType() const;
00101
00105 SwapCode GetSwapCode() const;
00106
00107 bool IsValid() const { return TSField != TS_END; }
00108
00109 operator TSType () const { return TSField; }
00110
00111 // FIXME: ImplicitVRLittleEndian used to be the default, but nowadays
00112 // this is rather the ExplicitVRLittleEndian instead...should be change the default ?
00113 TransferSyntax(TSType type = ImplicitVRLittleEndian):TSField(type) {}
00114
00115 // return if dataset is encoded or not (Deflate Explicit VR)
00116 bool IsEncoded() const;
00117
00118 bool IsImplicit() const;
00119 bool IsExplicit() const;
00120
00121 bool IsEncapsulated() const;
00122
00124 bool IsLossy() const;
00126 bool IsLossless() const;
00128 bool CanStoreLossy() const;
00129
00130 const char *GetString() const { return TransferSyntax::GetTSString(TSField); }
00131
00132 friend std::ostream &operator<<(std::ostream &os, const TransferSyntax &ts);
00133 private:
00134 // DO NOT EXPOSE the following. Internal details of TransferSyntax
00135 bool IsImplicit(TSType ts) const;
00136 bool IsExplicit(TSType ts) const;
00137 bool IsLittleEndian(TSType ts) const;
00138 bool IsBigEndian(TSType ts) const;
00139
00140     TSType TSField;
00141 };
00142 //-----
00143 inline std::ostream &operator<<(std::ostream &_os, const TransferSyntax &ts)
00144 {
00145     _os << TransferSyntax::GetTSString(ts);
00146     return _os;
00147 }
00148 }
00149
00150 } // end namespace gdcm
00151
00152 #endif //GDCMTRANSFERSYNTAX_H

```


11.181 gdcmUNExplicitDataElement.h File Reference

```

#include "gdcmDataElement.h"
#include "gdcmUNExplicitDataElement.txx"

```

Include dependency graph for `gdcmUNExplicitDataElement.h`:



Classes

- class `gdcm::UNExplicitDataElement`
Class to read/write a *DataElement* as *UNExplicit Data Element*.

Namespaces

- namespace `gdcm`

11.182 gdcmUNExplicitDataElement.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013   =====*/
00014 #ifndef GDCMUNEXPLICITDATAELEMENT_H
00015 #define GDCMUNEXPLICITDATAELEMENT_H
00016
00017 #include "gdcmDataElement.h"
00018
00019 namespace gdcm
00020 {
00021   // Data Element (UNExplicit)
00026   class GDCM_EXPORT UNExplicitDataElement : public DataElement
00027   {

```

```

00028 public:
00029     VL GetLength() const;
00030
00031     template <typename TSwap>
00032     std::istream &Read(std::istream &is);
00033
00034     template <typename TSwap>
00035     std::istream &ReadPreValue(std::istream &is);
00036
00037     template <typename TSwap>
00038     std::istream &ReadValue(std::istream &is, bool readvalues = true);
00039
00040     template <typename TSwap>
00041     std::istream &ReadWithLength(std::istream &is, VL &length);
00042
00043     // PURPOSELY do not provide an implementation for writing !
00044     //template <typename TSwap>
00045     //const std::ostream &Write(std::ostream &os) const;
00046 };
00047
00048 } // end namespace gdcm
00049
00050 #include "gdcmUNExplicitDataElement.txx"
00051
00052 #endif //GDCMUNEXPLICITDATAELEMENT_H


```

11.183 gdcmUNExplicitImplicitDataElement.h File Reference

```
#include "gdcmDataElement.h"
```

```
#include "gdcmUNExplicitImplicitDataElement.txx"
```

Include dependency graph for gdcmUNExplicitImplicitDataElement.h:



Classes

- class [gdcm::UNExplicitImplicitDataElement](#)

Class to read/write a [DataElement](#) as *ExplicitImplicit Data Element*.

Namespaces

- namespace [gdcm](#)

11.184 gdcmUNExplicitImplicitDataElement.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMUNEXPLICITIMPLICITDATAELEMENT_H
00015 #define GDCMUNEXPLICITIMPLICITDATAELEMENT_H
00016
00017 #include "gdcmDataElement.h"
00018
00019 namespace gdcm
00020 {
00021   // Data Element (ExplicitImplicit)
00022   class GDCM_EXPORT UNExplicitImplicitDataElement : public DataElement
00023   {
00024   public:
00025     VL GetLength() const;
00026
00027     template <typename TSwap>
00028     std::istream &Read(std::istream &is);
00029
00030     template <typename TSwap>
00031     std::istream &ReadPreValue(std::istream &is);
00032
00033     template <typename TSwap>
00034     std::istream &ReadValue(std::istream &is);
00035
00036     // PURPOSELY do not provide an implementation for writing !
00037     //template <typename TSwap>
00038     //const std::ostream &Write(std::ostream &os) const;
00039   };
00040
00041 } // end namespace gdcm
00042
00043 #include "gdcmUNExplicitImplicitDataElement.txx"
00044
00045 #endif //GDCMUNEXPLICITIMPLICITDATAELEMENT_H

```


11.185 gdcmValue.h File Reference

```

#include "gdcmObject.h"
#include "gdcmValue.txx"

```

Include dependency graph for gdcmValue.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::Value](#)
Class to represent the value of a Data [Element](#).

Namespaces

- namespace [gdcm](#)

11.186 gdcmValue.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003 Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005 Copyright (c) 2006-2011 Mathieu Malaterre
00006 All rights reserved.
00007 See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009 This software is distributed WITHOUT ANY WARRANTY; without even
00010 the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011 PURPOSE. See the above copyright notice for more information.
  
```

```

00012
00013 =====*/
00014 #ifndef GDCMVALUE_H
00015 #define GDCMVALUE_H
00016
00017 #include "gdcmObject.h"
00018
00019 namespace gdcm { class VL; }
00020 namespace gdcm_ns
00021 {
00022 #if !defined(SWIGPYTHON) && !defined(SWIGSHARP) && !defined(SWIGJAVA) && !defined(SWIGPHP)
00023 using namespace gdcm;
00024 #endif
00025 class GDCM_EXPORT Value : public Object
00026 {
00027 public:
00028     Value() = default;
00029     ~Value() override = default;
00030
00031     virtual VL GetLength() const = 0;
00032     virtual void SetLength(VL l) = 0;
00033
00034     virtual void Clear() = 0;
00035
00036     virtual bool operator==(const Value &val) const = 0;
00037
00038 protected:
00039     friend class DataElement;
00040     virtual void SetLengthOnly(VL l);
00041 };
00042 } // end namespace gdcm_ns
00043
00044 #include "gdcmValue.txx"
00045 #endif //GDCMVALUE_H


```

11.187 gdcmValueIO.h File Reference

```
#include "gdcmTypes.h"
```

```
#include "gdcmValueIO.txx"
```

Include dependency graph for gdcmValueIO.h:



Classes

- class [gdcm::ValueIO< TDE, TSwap, TType >](#)

Class to dispatch template calls.

Namespaces

- namespace [gdcm](#)

11.188 gdcmValueIO.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMVALUEIO_H
00015 #define GDCMVALUEIO_H
00016
00017 #include "gdcmTypes.h"
00018
00019 namespace gdcm_ns
00020 {
00021     template <typename TDE, typename TSwap, typename TType=uint8_t>
00022     class /*GDCM_EXPORT*/ ValueIO
00023     {
00024     public:
00025         static std::istream &Read(std::istream &is, Value& v, bool readvalues);
00026
00027         static const std::ostream &Write(std::ostream &os, const Value& v);
00028     };
00029 } // end namespace gdcm_ns
00030
00031 #include "gdcmValueIO.txx"
00032
00033 #endif //GDCMVALUEIO_H

```


11.189 gdcmVL.h File Reference

```

#include "gdcmTypes.h"
#include <iostream>

```

Include dependency graph for `gdcml.h`:



This graph shows which files directly or indirectly include this file:



Classes

- class `gdcml::VL`
Value Length.

Namespaces

- namespace `gdcml`

Functions

- `std::ostream & gdcml::operator<< (std::ostream &os, const VL &val)`

11.190 gdcml.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003 Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005 Copyright (c) 2006-2011 Mathieu Malaterre
00006 All rights reserved.

```



```

00007  See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009      This software is distributed WITHOUT ANY WARRANTY; without even
00010      the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011      PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMVL_H
00015 #define GDCMVL_H
00016
00017 #include "gdcmTypes.h"
00018
00019 #include <iostream>
00020
00021 namespace gdcm
00022 {
00023
00024     class GDCM_EXPORT VL
00025     {
00026     public:
00027         typedef uint32_t Type;
00028         VL(uint32_t vl = 0) : ValueLength(vl) { }
00029
00030         // FIXME: ugly
00031         static uint32_t GetVL32Max() { return 0xFFFFFFFF; }
00032         static uint16_t GetVL16Max() { return 0xFFFF; }
00033
00034         bool IsUndefined() const {
00035             return ValueLength == 0xFFFFFFFF;
00036         }
00037         void SetToUndefined() {
00038             ValueLength = 0xFFFFFFFF;
00039         }
00040
00041         bool IsOdd() const {
00042             return !IsUndefined() && ValueLength % 2;
00043         }
00044
00045         VL& operator+=(VL const &vl) {
00046             ValueLength += vl.ValueLength;
00047             return *this;
00048         }
00049         VL& operator++() {
00050             ++ValueLength;
00051             return *this;
00052         }
00053         VL operator++(int) {
00054             uint32_t tmp(ValueLength);
00055             ++ValueLength;
00056             return tmp;
00057         }
00058
00059         operator uint32_t () const { return ValueLength; }
00060
00061         VL GetLength() const {
00062             // VL cannot know it's length...well in implicit yes...
00063             // TODO: need to check we cannot call this function from an Explicit element
00064             return 4;
00065         }
00066
00067         friend std::ostream& operator<<(std::ostream& os, const VL& vl);
00068
00069         // PURPOSELY not implemented (could not differentiate 16bits vs 32bits VL)
00070         //friend std::istream& operator>>(std::istream& is, VL& n);
00071
00072         template <typename TSwap>
00073         std::istream &Read(std::istream &is)
00074         {
00075             is.read((char*)(&ValueLength), sizeof(uint32_t));
00076             TSwap::SwapArray(&ValueLength,1);
00077             return is;
00078         }
00079
00080         template <typename TSwap>
00081         std::istream &Read16(std::istream &is)
00082         {
00083             uint16_t copy;
00084             is.read((char*)(&copy), sizeof(uint16_t));
00085             TSwap::SwapArray(&copy,1);
00086             ValueLength = copy;
00087             gdcm_assert( ValueLength <= 65535 /*UINT16_MAX*/ ); // ?? doh !
00088         }
00089     };
00090
00091 }

```

```

00095     return is;
00096 }
00097
00098 template <typename TSwap>
00099 const std::ostream &Write(std::ostream &os) const
00100 {
00101     uint32_t copy = ValueLength;
00102     if( IsOdd() )
00103     {
00104         ++copy;
00105     }
00106     TSwap::SwapArray(&copy,1);
00107     return os.write((char*)(&copy), sizeof(uint32_t));
00108 }
00109
00110 template <typename TSwap>
00111 const std::ostream &Write16(std::ostream &os) const
00112 {
00113     gdcM_assert( ValueLength <= 65535 /*UINT16_MAX*/ );
00114     uint16_t copy = (uint16_t)ValueLength;
00115     if( IsOdd() )
00116     {
00117         ++copy;
00118     }
00119     TSwap::SwapArray(&copy,1);
00120     return os.write((char*)(&copy), sizeof(uint16_t));
00121 }
00122
00123 private:
00124     uint32_t ValueLength;
00125 };
00126 //-----
00127 inline std::ostream& operator<<(std::ostream& os, const VL& val)
00128 {
00129     os << /*std::hex <<*/ val.ValueLength;
00130     return os;
00131 }
00132
00133 } // end namespace gdcM
00134
00135 #endif //GDCMVL_H


```

11.191 gdcMVM.h File Reference

```
#include "gdcMTypes.h"
```

```
#include <iostream>
```

Include dependency graph for gdcMVM.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::VM](#)

Value Multiplicity Looking at the DICOMV3 dict only there is very few cases: 1 2 3 4 5 6 8 16 24 1-2 1-3 1-8 1-32 1-99 1-n 2-2n 2-n 3-3n 3-n.

Namespaces

- namespace [gdcm](#)

Macros

- #define [TYPETOLENGTH](#)(type, length)

Functions

- std::ostream & [gdcm::operator<<](#) (std::ostream &_os, const [VM](#) &_val)

11.191.1 Macro Definition Documentation

11.191.1.1 TYPETOLENGTH

```
#define TYPETOLENGTH(  
    type,  
    length)
```

Value:

```
template<> struct VMToLength<VM::type> \  
{ enum { Length = length }; };
```

11.192 gdcmmVM.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003     Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005     Copyright (c) 2006-2011 Mathieu Malaterre
00006     All rights reserved.
00007     See Copyright.txt or http://gdcmm.sourceforge.net/Copyright.html for details.
00008
00009     This software is distributed WITHOUT ANY WARRANTY; without even
00010     the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011     PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMMVM_H
00015 #define GDCMMVM_H
00016
00017 #include "gdcmTypes.h"
00018 #include <iostream>
00019
00020 namespace gdcm
00021 {
00022
00023     class GDCM_EXPORT VM
00024     {
00025     public:
00026         typedef enum {
00027             VM0 = 0, // aka the invalid VM
00028             VM1 = 1,
00029             VM2 = 2,
00030             VM3 = 4,
00031             VM4 = 8,
00032             VM5 = 16,
00033             VM6 = 32,
00034             VM8 = 64,
00035             VM9 = 128,
00036             VM10 = 256,
00037             VM12 = 512, //1024,
00038             VM16 = 1024, //2048,
00039             VM18 = 2048, //4096,
00040             VM24 = 4096, //8192,
00041             VM28 = 8192, //16384,
00042             VM32 = 16384, //32768,
00043             VM35 = 32768, //65536,
00044             VM99 = 65536, //131072,
00045             VM256 = 131072, //262144,
00046             VM1_2 = VM1 | VM2,
00047             VM1_3 = VM1 | VM2 | VM3,
00048             VM1_4 = VM1 | VM2 | VM3 | VM4,
00049             VM1_5 = VM1 | VM2 | VM3 | VM4 | VM5,
00050             VM1_8 = VM1 | VM2 | VM3 | VM4 | VM5 | VM6 | VM8,
00051 // The following need some work:
00052             VM1_32 = VM1 | VM2 | VM3 | VM4 | VM5 | VM6 | VM8 | VM9 | VM16 | VM24 | VM32,
00053             VM1_99 = VM1 | VM2 | VM3 | VM4 | VM5 | VM6 | VM8 | VM9 | VM16 | VM24 | VM32 | VM99,
00054             VM1_n = VM1 | VM2 | VM3 | VM4 | VM5 | VM6 | VM8 | VM9 | VM16 | VM24 | VM32 | VM99 | VM256,
00055             VM2_2n = VM2 | VM4 | VM6 | VM8 | VM16 | VM24 | VM32 | VM99 | VM256,
00056             VM2_n = VM2 | VM3 | VM4 | VM5 | VM6 | VM8 | VM9 | VM16 | VM24 | VM32 | VM99 | VM256,
00057             VM3_4 = VM3 | VM4,
00058             VM3_3n = VM3 | VM6 | VM9 | VM24 | VM99 | VM256,
00059             VM3_n = VM3 | VM4 | VM5 | VM6 | VM8 | VM9 | VM16 | VM24 | VM32 | VM99 | VM256,
00060             VM4_4n = VM4 | VM16 | VM24 | VM32 | VM256,
00061             VM6_6n = VM6 | VM12 | VM18 | VM24,
00062             VM6_n = VM6 | VM8 | VM9 | VM16 | VM24 | VM32 | VM99 | VM256,
00063             VM7_7n,
00064             VM30_30n,
00065             VM47_47n,
00066             VM_END = VM1_n + 1 // Custom tag to count number of entry
00067         } VMType;
00068
00069         static const char* GetVMString(VMType vm);
00070         static VMType GetVMType(const char *vm);
00071
00072         static bool IsValid(int vm1, VMType vm2);
00073         //bool IsValid() { return VMField != VM0 && VMField < VM_END; }
00074
00075         bool Compatible(VM const &vm) const;
00076
00077     };
00078
00079 }

```

```

00127
00129 static VMType GetVMTypeFromLength(size_t length, unsigned int size);
00130 static size_t GetNumberOfElementsFromArray(const char *array, size_t length);
00131
00132 VM(VMType type = VM0):VMField(type) {}
00133 operator VMType () const { return VMField; }
00134 unsigned int GetLength() const;
00135
00136 friend std::ostream &operator<<(std::ostream &os, const VM &vm);
00137 protected:
00138 static unsigned int GetIndex(VMType vm);
00139
00140 private:
00141 VMType VMField;
00142 };
00143 //-----
00144 inline std::ostream& operator<<(std::ostream& _os, const VM &_val)
00145 {
00146 gdcm_assert( VM::GetVMString(_val) );
00147 _os << VM::GetVMString(_val);
00148 return _os;
00149 }
00150
00151 //template <int TVM> struct LengthToVM;
00152 //template <> struct LengthToVM<1>
00153 //{ enum { TVM = VM::VM1 }; };
00154
00155 template<int T> struct VMToLength;
00156 #define TYPETOLENGTH(type,length) \
00157 template<> struct VMToLength<VM::type> \
00158 { enum { Length = length }; };
00159 // TODO: Could be generated from XML file
00160 //TYPETOLENGTH(VM0,1)
00161 TYPETOLENGTH(VM1,1)
00162 TYPETOLENGTH(VM2,2)
00163 TYPETOLENGTH(VM3,3)
00164 TYPETOLENGTH(VM4,4)
00165 TYPETOLENGTH(VM5,5)
00166 TYPETOLENGTH(VM6,6)
00167 TYPETOLENGTH(VM8,8)
00168 TYPETOLENGTH(VM9,9)
00169 TYPETOLENGTH(VM10,10)
00170 TYPETOLENGTH(VM12,12)
00171 TYPETOLENGTH(VM16,16)
00172 TYPETOLENGTH(VM18,18)
00173 TYPETOLENGTH(VM24,24)
00174 TYPETOLENGTH(VM28,28)
00175 TYPETOLENGTH(VM32,32)
00176 TYPETOLENGTH(VM35,35)
00177 TYPETOLENGTH(VM99,99)
00178 TYPETOLENGTH(VM256,256)
00179 //TYPETOLENGTH(VM1_2,2)
00180 //TYPETOLENGTH(VM1_3,3)
00181 //TYPETOLENGTH(VM1_8,8)
00182 //TYPETOLENGTH(VM1_32,32)
00183 //TYPETOLENGTH(VM1_99,99)
00184 //TYPETOLENGTH(VM1_n,
00185 //TYPETOLENGTH(VM2_2n,
00186 //TYPETOLENGTH(VM2_n,
00187 //TYPETOLENGTH(VM3_3n,
00188 //TYPETOLENGTH(VM3_n,
00189
00190 } // end namespace gdcm
00191
00192 #endif //GDCMVM_H

```

11.193 gdcmVR.h File Reference


```

#include "gdcmTag.h"
#include "gdcmTrace.h"
#include "gdcmString.h"
#include <iostream>
#include <fstream>

```

```
#include <assert.h>
```

Include dependency graph for `gdcmVR.h`:



This graph shows which files directly or indirectly include this file:



Classes

- struct `gdcm::UI`
- class `gdcm::VR`
VR class.

Namespaces

- namespace `gdcm`

Macros

- `#define` `TYPETOENCODING`(type, rep, rtype)
- `#define` `VRTypeTemplateCase`(type)

Typedefs

- typedef [String](#)<"\\", 16 > [gdcm::AECComp](#)
- typedef [String](#)<"\\", 64 > [gdcm::ASComp](#)
- typedef [String](#)<"\\", 16 > [gdcm::CSComp](#)
- typedef [String](#)<"\\", 64 > [gdcm::DAComp](#)
- typedef [String](#)<"\\", 64 > [gdcm::DTComp](#)
- typedef [String](#)<"\\", 64 > [gdcm::LOComp](#)
- typedef [String](#)<"\\", 64 > [gdcm::LTComp](#)
- typedef [String](#)<"\\", 64 > [gdcm::PNComp](#)
- typedef [String](#)<"\\", 64 > [gdcm::SHComp](#)
- typedef [String](#)<"\\", 64 > [gdcm::STComp](#)
- typedef [String](#)<"\\", 16 > [gdcm::TMComp](#)
- typedef [String](#)<"\\", 4294967294 > [gdcm::UCComp](#)
- typedef [String](#)<"\\", 64, 0 > [gdcm::UIComp](#)
- typedef [String](#)<"\\", 4294967294 > [gdcm::URComp](#)
- typedef [String](#)<"\\", 64 > [gdcm::UTComp](#)

Functions

- [std::ostream & gdcm::operator<<](#) ([std::ostream &_os](#), const [UI](#) &_val)
- [std::ostream & gdcm::operator<<](#) ([std::ostream &_os](#), const [VR](#) &val)

11.193.1 Macro Definition Documentation

11.193.1.1 TYPETOENCODING

```
#define TYPETOENCODING(
    type,
    rep,
    rtype)
```

Value:

```
template<> struct VRToEncoding<VR::type> \
{ enum:long long { Mode = VR::rep }; }; \
template<> struct VRToType<VR::type> \
{ typedef rtype Type; };
```

11.193.1.2 VRTypeTemplateCase

```
#define VRTypeTemplateCase(
    type)
```

Value:

```
case VR::type: \
    return sizeof ( VRToType<VR::type>::Type );
```

Referenced by [gdcm::VR::GetSize\(\)](#).

11.194 gdcmVR.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMVR_H
00015 #define GDCMVR_H
00016
00017 #include "gdcmTag.h"
00018 #include "gdcmTrace.h"
00019 #include "gdcmString.h"
00020
00021 #include <iostream>
00022 #include <fstream>
00023 #include <assert.h>
00024
00025 //these defines are here to ensure compilation on sunos gcc
00026 #if defined (CS)
00027 # undef CS
00028 #endif
00029 #if defined (DS)
00030 # undef DS
00031 #endif
00032 #if defined (SS)
00033 # undef SS
00034 #endif
00035
00036 namespace gdcm
00037 {
00038
00039   class GDCM_EXPORT VR
00040   {
00041   public:
00042     enum VRType : long long {
00043       // Warning: Do not write if ( vr & VR::INVALID ) but if ( vr == VR::INVALID )
00044       INVALID = 0, // For Item/(Seq) Item Delimitation Item
00045       AE = 1,
00046       AS = 2,
00047       AT = 4,
00048       CS = 8,
00049       DA = 16,
00050       DS = 32,
00051       DT = 64,
00052       FD = 128,
00053       FL = 256,
00054       IS = 512,
00055       LO = 1024,
00056       LT = 2048,
00057       OB = 4096,
00058       OD = 134217728, // 2^27
00059       OF = 8192,
00060       OL = 268435456, // 2^28
00061       OV = 2147483648, // 2^31
00062       OW = 16384,
00063       PN = 32768,
00064       SH = 65536,
00065       SL = 131072,
00066       SQ = 262144,
00067       SS = 524288,
00068       ST = 1048576,
00069       SV = 4294967296, // 2^32
00070       TM = 2097152,
00071       UC = 536870912, // 2^29
00072       UI = 4194304,
00073       UL = 8388608,
00074       UN = 16777216,

```



```

00090     UR = 1073741824, // 2^30
00091     US = 33554432,
00092     UT = 67108864,
00093     UV = 8589934592, // 2^33
00094     OB_OW = OB | OW,
00095     US_SS = US | SS,
00096     US_SS_OW = US | SS | OW,
00097     US_OW = US | OW,
00098     // The following do not have a VRString equivalent (ie cannot be found in PS 3.6)
00099     VL16 = AE | AS | AT | CS | DA | DS | DT | FD | FL | IS | LO | LT | PN | SH | SL | SS | ST | TM | UI |
UL | US, // if( VR & VL16 ) => VR has its VL coded over 16bits
00100     VL32 = OB | OW | OD | OF | OL | OV | SQ | SV | UC | UN | UR | UV, // if( VR & VL32 ) => VR has
its VL coded over 32bits
00101     VRASCII = AE | AS | CS | DA | DS | DT | IS | LO | LT | PN | SH | ST | TM | UC | UI | UR | UT,
00102     VRBINARY = AT | FL | FD | OB | OD | OF | OL | OV | OW | SL | SQ | SS | SV | UL | UN | US | UV, //
FIXME: UN ?
00103     // PS 3.5:
00104     // Data Elements with a VR of SQ, OD, OF, OL, OW, OB or UN shall always have a Value Multiplicity of
one.
00105     // GDCM is adding a couple more: AS, LT, ST, UT
00106     VR_VM1 = AS | LT | ST | UT | SQ | OF | OL | OV | OD | OW | OB | UN, // All those VR have a VM1
00107     VRALL = VRASCII | VRBINARY,
00108     VR_END = UV+1 // Invalid VR, need to be max(VRType)+1
00109 };
00110
00111 static const char *GetVRString(VRType vr);
00112
00113 // This function will only look at the very first two chars nothing else
00114 static VRType GetVRTypeFromFile(const char *vr);
00115
00116 // You need to make sure end of string is \0
00117 static VRType GetVRType(const char *vr);
00118 static const char *GetVRStringFromFile(VRType vr);
00119
00120 static bool IsValid(const char *vr);
00121 // Check if vr1 is valid against vr2,
00122 // Typically vr1 is read from the file and vr2 is taken from the dict
00123 static bool IsValid(const char *vr1, VRType vr2);
00124 //static bool IsValid(const VRType &vr1, const VRType &vr2);
00125 // Find out if the string read is byte swapped
00126 static bool IsSwap(const char *vr);
00127
00128 // Size read on disk
00129 // FIXME: int ?
00130 int GetLength() const {
00131     return VR::GetLength(VRField);
00132 }
00133 unsigned int GetSizeof() const;
00134 static uint32_t GetLength(VRType vr) {
00135     //if( vr == VR::INVALID ) return 4;
00136     if( vr & VL32 )
00137     {
00138         return 4;
00139     }
00140     else
00141         return 2;
00142 }
00143
00144 // Some use of template metaprograming with ugly macro
00145 static bool IsBinary(VRType vr);
00146 static bool IsASCII(VRType vr);
00147 // TODO: REMOVE ME
00148 static bool CanDisplay(VRType vr);
00149 // TODO: REMOVE ME
00150 static bool IsBinary2(VRType vr);
00151 // TODO: REMOVE ME
00152 static bool IsASCII2(VRType vr);
00153
00154 VR(VRType vr = INVALID):VRField(vr) { }
00155 //VR(VR const &vr):VRField(vr.VRField) { }
00156 std::istream &Read(std::istream &is)
00157 {
00158     char vr[2];
00159     is.read(vr, 2);
00160     VRField = GetVRTypeFromFile(vr);
00161     gdcmm_assert( VRField != VR::VR_END );
00162     if( VRField == VR::INVALID )
00163     {
00164         // \0\2 Data/TherapysGDCM120Bug.dcm
00165         // \0\0
Data/MR_Philips_Intera_PrivateSequenceExplicitVR_in_SQ_2001_e05f_item_wrong_lgt_use_NOSHADOWSEQ.dcm

```

```

00166         // \0\4 Data/BugGDCM2_UndefItemWrongVL.dcm
00167         // \44\0 Data/gdcm-MR-PHILIPS-16-Multi-Seq.dcm
00168         // \0\20 Data/ExplicitVRforPublicElementsImplicitVRforShadowElements.dcm
00169         // \0\3 Data/DMCPACS_ExplicitImplicit_BogusIOP.dcm
00170         // \0\4 Data/THERALYS-12-MONO2-Uncompressed-Even_Length_Tag.dcm
00171         // \0\4 Data/PrivateGEImplicitVRBigEndianTransferSyntax16Bits.dcm
00172         // \0\4 Data/GE_DLX-8-MONO2-PrivateSyntax.dcm
00173         throw Exception( "INVALID VR" );
00174     }
00175     if( VRField & VL32 )
00176     {
00177 #if 0
00178         // For some reason this seems slower on my linux box...
00179         is.seekg(2, std::ios::cur );
00180 #else
00181         char dumb[2];
00182         is.read(dumb, 2);
00183         if( !(dumb[0] == 0 && dumb[1] == 0 ) )
00184         {
00185             // JDDICOM_Sample4.dcm
00186             gdcmDebugMacro( "32bits VR contains non zero bytes. Skipped" );
00187         }
00188 #endif
00189     }
00190     return is;
00191 }
00192
00193 const std::ostream &Write(std::ostream &os) const
00194 {
00195     VRType vrfield = VRField;
00196     gdcmAssertAlwaysMacro( !IsDual() );
00197     if( vrfield == VR::INVALID )
00198     {
00199         //vrfield = VR::UN;
00200     }
00201     const char *vr = GetVRString(vrfield);
00202     //gdcm_assert( strlen( vr ) == 2 );
00203     gdcm_assert( vr[0] && vr[1] && vr[2] == 0 );
00204     os.write(vr, 2);
00205     // See PS 3.5, Data Element Structure With Explicit VR
00206     if( vrfield & VL32 )
00207     {
00208         const char dumb[2] = {0, 0};
00209         os.write(dumb, 2);
00210     }
00211     return os;
00212 }
00213 friend std::ostream &operator<<(std::ostream &os, const VR &vr);
00214
00215 operator VRType () const { return VRField; }
00216
00217 unsigned int GetSize() const;
00218
00219 bool Compatible(VR const &vr) const;
00220
00221 bool IsVRFile() const;
00222
00223 bool IsDual() const;
00224
00225 private:
00226     // Internal function that map a VRType to an index in the VRStrings table
00227     static unsigned int GetIndex(VRType vr);
00228     VRType VRField;
00229 };
00230 //-----
00231 inline std::ostream &operator<<(std::ostream &_os, const VR &val)
00232 {
00233     //_os << VR::GetVRStringFromFile(val.VRField);
00234     _os << VR::GetVRString(val.VRField);
00235     return _os;
00236 }
00237
00238 // Apparently SWIG is not happy with something, somewhere below...
00239 #ifndef SWIG
00240
00241 // Tells whether VR Type is ASCII or Binary
00242 template<long long T> struct VRToEncoding;
00243 // Convert from VR Type to real underlying type
00244 template<long long T> struct VRToType;
00245 #define TYPETOENCODING(type, rep, rtype) \
00246     template<> struct VRToEncoding<VR::type> \

```

```

00247 { enum:long long { Mode = VR::rep }; };
00248 template<> struct VRToType<VR::type> \
00249 { typedef rtype Type; };
00250
00251
00252 // Do not use me
00253 struct UI { char Internal[64+1];
00254 friend std::ostream& operator<<(std::ostream &_os, const UI &_val);
00255 };
00256 inline std::ostream& operator<<(std::ostream &_os, const UI &_val)
00257 {
00258 _os << _val.Internal;
00259 return _os;
00260 }
00261
00262 typedef String<'\\',16> AECComp;
00263 typedef String<'\\',64> ASCComp;
00264 typedef String<'\\',16> CSCComp;
00265 typedef String<'\\',64> DACComp;
00266 typedef String<'\\',64> DTCComp;
00267 typedef String<'\\',64> LOComp;
00268 typedef String<'\\',64> LTCComp;
00269 typedef String<'\\',64> PNComp;
00270 typedef String<'\\',64> SHComp;
00271 typedef String<'\\',64> STComp;
00272 typedef String<'\\',4294967294> UCComp;
00273 typedef String<'\\',4294967294> URComp;
00274 typedef String<'\\',16> TMComp;
00275 typedef String<'\\',64,0> UICComp;
00276 typedef String<'\\',64> UTCComp;
00277
00278
00279 // TODO: Could be generated from XML file
00280 TYPETOENCODING(AE,VRSCII ,AECComp)
00281 TYPETOENCODING(AS,VRSCII ,ASCComp)
00282 TYPETOENCODING(AT,VRBINARY,Tag)
00283 TYPETOENCODING(CS,VRSCII ,CSCComp)
00284 TYPETOENCODING(DA,VRSCII ,DACComp)
00285 TYPETOENCODING(DS,VRSCII ,double)
00286 TYPETOENCODING(DT,VRSCII ,DTCComp)
00287 TYPETOENCODING(FL,VRBINARY,float)
00288 TYPETOENCODING(FD,VRBINARY,double)
00289 TYPETOENCODING(IS,VRSCII ,int32_t)
00290 TYPETOENCODING(LO,VRSCII ,LOComp)
00291 TYPETOENCODING(LT,VRSCII ,LTCComp)
00292 TYPETOENCODING(OB,VRBINARY,uint8_t)
00293 TYPETOENCODING(OD,VRBINARY,double)
00294 TYPETOENCODING(OF,VRBINARY,float)
00295 TYPETOENCODING(OL,VRBINARY,uint32_t)
00296 TYPETOENCODING(OV,VRBINARY,uint64_t)
00297 TYPETOENCODING(OW,VRBINARY,uint16_t)
00298 TYPETOENCODING(PN,VRSCII ,PNComp)
00299 TYPETOENCODING(SH,VRSCII ,SHComp)
00300 TYPETOENCODING(SL,VRBINARY,int32_t)
00301 TYPETOENCODING(SQ,VRBINARY,unsigned char) // FIXME
00302 TYPETOENCODING(SS,VRBINARY,int16_t)
00303 TYPETOENCODING(ST,VRSCII ,STComp)
00304 TYPETOENCODING(SV,VRBINARY,int64_t)
00305 TYPETOENCODING(TM,VRSCII ,TMComp)
00306 TYPETOENCODING(UC,VRSCII ,UCComp)
00307 TYPETOENCODING(UI,VRSCII ,UICComp)
00308 TYPETOENCODING(UL,VRBINARY,uint32_t)
00309 TYPETOENCODING(UN,VRBINARY,uint8_t) // FIXME ?
00310 TYPETOENCODING(UR,VRSCII ,URComp)
00311 TYPETOENCODING(US,VRBINARY,uint16_t)
00312 TYPETOENCODING(UT,VRSCII ,UTCComp)
00313 TYPETOENCODING(UV,VRBINARY,uint64_t)
00314
00315 #define VRTypeTemplateCase(type) \
00316 case VR::type: \
00317 return sizeof ( VRToType<VR::type>::Type );
00318
00319 inline unsigned int VR::GetSize() const
00320 {
00321 switch(VRField)
00322 {
00323 VRTypeTemplateCase(AE)
00324 VRTypeTemplateCase(AS)
00325 VRTypeTemplateCase(AT)
00326 VRTypeTemplateCase(CS)
00327 VRTypeTemplateCase(DA)

```

```

00328     VRTypeTemplateCase (DS)
00329     VRTypeTemplateCase (DT)
00330     VRTypeTemplateCase (FL)
00331     VRTypeTemplateCase (FD)
00332     VRTypeTemplateCase (IS)
00333     VRTypeTemplateCase (LO)
00334     VRTypeTemplateCase (LT)
00335     VRTypeTemplateCase (OB)
00336     VRTypeTemplateCase (OD)
00337     VRTypeTemplateCase (OF)
00338     VRTypeTemplateCase (OL)
00339     VRTypeTemplateCase (OV)
00340     VRTypeTemplateCase (OW)
00341     VRTypeTemplateCase (PN)
00342     VRTypeTemplateCase (SH)
00343     VRTypeTemplateCase (SL)
00344     VRTypeTemplateCase (SQ)
00345     VRTypeTemplateCase (SS)
00346     VRTypeTemplateCase (ST)
00347     VRTypeTemplateCase (SV)
00348     VRTypeTemplateCase (TM)
00349     VRTypeTemplateCase (UC)
00350     VRTypeTemplateCase (UI)
00351     VRTypeTemplateCase (UL)
00352     VRTypeTemplateCase (UN)
00353     VRTypeTemplateCase (UR)
00354     VRTypeTemplateCase (US)
00355     VRTypeTemplateCase (UT)
00356     VRTypeTemplateCase (UV)
00357     case VR::US_SS:
00358         return 2;
00359
00360     case VR::INVALID:
00361     case VR::OB_OW:
00362     case VR::US_SS_OW:
00363     case VR::US_OW:
00364     case VR::VL16:
00365     case VR::VL32:
00366     case VR::VRASCII:
00367     case VR::VRBINARY:
00368     case VR::VR_VM1:
00369     case VR::VRALL:
00370     case VR::VR_END:
00371     default:
00372         gdcmm_assert( 0 && "should not" );
00373     }
00374     return 0;
00375 }
00376 #endif // SWIG
00377
00378
00379 } // end namespace gdcmm
00380
00381 #endif //GDCMMVR_H

```


11.195 gdcmmVR16ExplicitDataElement.h File Reference

```

#include "gdcmmDataElement.h"
#include "gdcmmVR16ExplicitDataElement.txx"

```

Include dependency graph for gdcmVR16ExplicitDataElement.h:



Classes

- class [gdcm::VR16ExplicitDataElement](#)
Class to read/write a *DataElement* as *Explicit Data Element*.

Namespaces

- namespace [gdcm](#)

11.196 gdcmVR16ExplicitDataElement.h


[Go to the documentation of this file.](#)

```


00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013   =====*/
00014 #ifndef GDCMVR16EXPLICITDATAELEMENT_H
00015 #define GDCMVR16EXPLICITDATAELEMENT_H
00016
00017 #include "gdcmDataElement.h"
00018
00019 namespace gdcm
00020 {
00021   // Data Element (Explicit)
00022   class GDCM_EXPORT VR16ExplicitDataElement : public DataElement
00023   {
00024   
```

11.197 gdcmWriter.h File Reference

Include dependency graph for gdcMWriter.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::Writer](#)
Writer *ala* DOM (Document *Object* Model)

Namespaces

- namespace [gdcm](#)

11.198 gdcmWriter.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003     Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005     Copyright (c) 2006-2011 Mathieu Malaterre
00006     All rights reserved.
00007     See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009     This software is distributed WITHOUT ANY WARRANTY; without even
00010     the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011     PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014
00015 #ifndef GDCMWRITER_H
00016 #define GDCMWRITER_H
00017
00018 #include "gdcmFile.h"
00019
00020 namespace gdcm
00021 {
00022
00023     class FileMetaInformation;
00048     class GDCM_EXPORT Writer
00049     {
00050     public:
00051         Writer();
00052         virtual ~Writer();
00053     };
  
```

```


00055     virtual bool Write(); // Execute()
00056
00058     void SetFileName(const char *filename_native);
00059
00061     void SetStream(std::ostream &output_stream) {
00062         Stream = &output_stream;
00063     }
00064
00066     void SetFile(const File& f) { F = f; }
00067     File &GetFile() { return *F; }
00068
00070     void SetCheckFileMetaInformation(bool b) { CheckFileMetaInformation = b; }
00071     void CheckFileMetaInformationOff() { CheckFileMetaInformation = false; }
00072     void CheckFileMetaInformationOn() { CheckFileMetaInformation = true; }
00073
00074 protected:
00075     void SetWriteDataSetOnly(bool b) { WriteDataSetOnly = b; }
00076
00077 protected:
00078     friend class StreamImageWriter;
00079     //this function is added for the StreamImageWriter, which needs to write
00080     //up to the pixel data and then stops right before writing the pixel data.
00081     //after that, for the raw codec at least, zeros are written for the length of the data
00082     std::ostream* GetStreamPtr() const { return Stream; }
00083
00084 protected:
00085     std::ostream *Stream;
00086     std::ofstream *Ofstream;
00087     bool GetCheckFileMetaInformation() const { return CheckFileMetaInformation; }
00088
00089 private:
00090     SmartPointer<File> F;
00091     bool CheckFileMetaInformation;
00092     bool WriteDataSetOnly;
00093 };
00094
00095 } // end namespace gdcm
00096
00097 #endif //GDCMWRITER_H

```

11.199 gdcmDefinedTerms.h File Reference

#include "gdcmTypes.h"

Include dependency graph for gdcmDefinedTerms.h:



Classes

- class [gdcm::DefinedTerms](#)

Defined Terms are used when the specified explicit Values may be extended by implementors to include additional new Values. These new Values shall be specified in the Conformance Statement (see PS 3.2) and shall not have the same meaning as currently defined Values in this standard. A Data [Element](#) with Defined Terms that does not contain a [Value](#) equivalent to one of the Values currently specified in this standard shall not be considered to have an invalid value. Note: Interpretation [Type](#) ID (4008,0210) is an example of a Data [Element](#) having Defined Terms. It is defined to have a [Value](#) that may be one of the set of standard Values; REPORT or AMENDMENT (see PS 3.3). Because this Data [Element](#) has Defined Terms other Interpretation [Type](#) IDs may be defined by the implementor.

Namespaces

- namespace [gdcm](#)

11.200 gdcmDefinedTerms.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003     Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005     Copyright (c) 2006-2011 Mathieu Malaterre
00006     All rights reserved.
00007     See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009     This software is distributed WITHOUT ANY WARRANTY; without even
00010     the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011     PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMDEFINEDTERMS_H
00015 #define GDCMDEFINEDTERMS_H
00016
00017 #include "gdcmTypes.h"
00018
00019 namespace gdcm
00020 {
00021     class GDCM_EXPORT DefinedTerms
00022     {
00023     public:
00024         DefinedTerms() = default;
00025     private:
00026     };
00027
00028 } // end namespace gdcm
00029
00030 #endif //GDCMDEFINEDTERMS_H

```

11.201 gdcmDefs.h File Reference


```

#include "gdcmModules.h"
#include "gdcmMacros.h"
#include "gdcmIODs.h"


```

```
#include <string>
```

Include dependency graph for gdcmDefs.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::Defs](#)

FIXME I do not like the name 'Defs'.

Namespaces

- namespace [gdcm](#)

11.202 gdcmDefs.h

[Go to the documentation of this file.](#)

```


00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMDEFS_H
00015 #define GDCMDEFS_H
00016
00017 #include "gdcmModules.h"
00018 #include "gdcmMacros.h"
00019 #include "gdcmIODs.h"
00020
00021 #include <string>
00022
00023 namespace gdcm
00024 {
00025   class DataSet;
00026   class File;
00027   class MediaStorage;
00032   class GDCM_EXPORT Defs
00033   {
00034   public:
00035     Defs();
00036     ~Defs();
00037     Defs &operator=(const Defs &val) = delete;
00038     Defs(const Defs &val) = delete;
00039
00040     const Modules &GetModules() const { return Part3Modules; }
00041     Modules &GetModules() { return Part3Modules; }
00042
00043     const Macros &GetMacros() const { return Part3Macros; }
00044     Macros &GetMacros() { return Part3Macros; }
00045
00046     const IODs & GetIODs() const { return Part3IODs; }
00047     IODs & GetIODs() { return Part3IODs; }
00050
00051     bool IsEmpty() const { return GetModules().IsEmpty(); }
00052
00053     bool Verify(const File& file) const;
00054
00055     // \deprecated DO NOT USE
00056     bool Verify(const DataSet& ds) const;
00057
00058     Type GetTypeFromTag(const File& file, const Tag& tag) const;
00059
00060     static const char *GetIODNameFromMediaStorage(MediaStorage const &ms);
00061
00062     const IOD& GetIODFromFile(const File& file) const;
00063
00064   protected:
00065     friend class Global;
00066     void LoadDefaults();
00067     void LoadFromFile(const char *filename);
00068
00069   private:
00070     // Part 3 stuff:
00071     Macros Part3Macros;
00072     Modules Part3Modules;
00073     IODs Part3IODs;
00074
00075   };
00076
00077 } // end namespace gdcm
00078
00079 #endif //GDCMDEFS_H

```

11.203 gdcmEnumeratedValues.h File Reference

```
#include "gdcmTypes.h"
```

Include dependency graph for gdcmEnumeratedValues.h:



Classes

- class [gdcm::EnumeratedValues](#)

Element. A Data [Element](#) with Enumerated Values that does not have a [Value](#) equivalent to one of the Values specified in this standard has an invalid value within the scope of a specific Information Object/SOP Class definition. Note:

Namespaces

- namespace [gdcm](#)

11.204 gdcmEnumeratedValues.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013   =====*/
00014 #ifndef GDCMENUMERATEDVALUES_H
00015 #define GDCMENUMERATEDVALUES_H
00016
00017 #include "gdcmTypes.h"
00018
00019 namespace gdcm
00020 {

```

```

00034 class GDCM_EXPORT EnumeratedValues
00035 {
00036 public:
00037     EnumeratedValues() = default;
00038 private:
00039 };
00040
00041 } // end namespace gdcm
00042
00043 #endif //GDCMENUMERATEDVALUES_H

```


11.205 gdcmIOD.h File Reference

```

#include "gdcmTypes.h"
#include "gdcmTag.h"
#include "gdcmIODEntry.h"
#include <vector>

```

Include dependency graph for gdcmIOD.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcml::IOD](#)
Class for representing a [IOD](#).

Namespaces

- namespace [gdcml](#)

Functions

- `std::ostream & gdcml::operator<< (std::ostream &_os, const IOD &_val)`

11.206 gdcmlOD.h

[Go to the documentation of this file.](#)

```

00001  /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library

```

```


00004
00005 Copyright (c) 2006-2011 Mathieu Malaterre
00006 All rights reserved.
00007 See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009 This software is distributed WITHOUT ANY WARRANTY; without even
00010 the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011 PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMIOD_H
00015 #define GDCMIOD_H
00016
00017 #include "gdcmTypes.h"
00018 #include "gdcmTag.h"
00019 #include "gdcmIODEntry.h"
00020
00021 #include <vector>
00022
00023 namespace gdcm
00024 {
00025 class DataSet;
00026 class Defs;
00027
00034 class GDCM_EXPORT IOD
00035 {
00036 public:
00037     typedef std::vector<IODEntry> MapIODEntry;
00038     typedef MapIODEntry::size_type SizeType;
00039
00040     IOD() = default;
00041     friend std::ostream& operator<<(std::ostream& _os, const IOD &_val);
00042
00043     void Clear() { IODInternal.clear(); }
00044
00045     void AddIODEntry(const IODEntry &iode)
00046     {
00047         IODInternal.push_back(iode);
00048     }
00049
00050     SizeType GetNumberOfIODs() const {
00051         return IODInternal.size();
00052     }
00053
00054     const IODEntry& GetIODEntry(SizeType idx) const
00055     {
00056         return IODInternal[idx];
00057     }
00058
00059     Type GetTypeFromTag(const Defs &defs, const Tag& tag) const;
00060
00061 private:
00062     //IOD &operator=(const IOD &_val); // purposely not implemented
00063     //IOD(const IOD &_val); // purposely not implemented
00064
00065     MapIODEntry IODInternal;
00066 };
00067 //-----
00068 inline std::ostream& operator<<(std::ostream& _os, const IOD &_val)
00069 {
00070     IOD::MapIODEntry::const_iterator it = _val.IODInternal.begin();
00071     for(; it != _val.IODInternal.end(); ++it)
00072     {
00073         _os << *it << '\n';
00074     }
00075
00076     return _os;
00077 }
00078
00079 } // end namespace gdcm
00080
00081 #endif //GDCMIOD_H

```


11.207 gdcmIODEntry.h File Reference

```
#include "gdcmUsage.h"
#include "gdcmType.h"
#include <string>
```

Include dependency graph for gdcmIODEntry.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::IODEntry](#)
Class for representing a [IODEntry](#).

Namespaces

- namespace [gdcm](#)

Functions

- `std::ostream & gdcm::operator<< (std::ostream &_os, const IODEntry &_val)`

11.208 gdcmIODEntry.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMIODENTRY_H
00015 #define GDCMIODENTRY_H
00016
00017 #include "gdcmUsage.h"
00018 #include "gdcmType.h"
00019
00020 #include <string>
00021
00022 namespace gdcm
00023 {
00024     class GDCM_EXPORT IODEntry
00025     {
00026     public:
00027         IODEntry(const char *name = "", const char *ref = "", const char *inUsage =
00028             "") : Name(name), Ref(ref), usage(inUsage) {
00029         }
00030         friend std::ostream& operator<<(std::ostream& _os, const IODEntry &_val);
00031
00032         void SetIE(const char *ie) { IE = ie; }
00033         const char *GetIE() const { return IE.c_str(); }
00034
00035         void SetName(const char *name) { Name = name; }
00036         const char *GetName() const { return Name.c_str(); }
00037
00038         void SetRef(const char *ref) { Ref = ref; }
00039         const char *GetRef() const { return Ref.c_str(); }
00040
00041         void SetUsage(const char *inUsage) { usage = inUsage; }
00042         const char *GetUsage() const { return usage.c_str(); }
00043         Usage::UsageType GetUsageType() const;
00044
00045     private:
00046         std::string IE;
00047         std::string Name;
00048         std::string Ref;
00049         std::string usage;
00050     };
00051 //-----
00052 inline std::ostream& operator<<(std::ostream& _os, const IODEntry &_val)
00053 {
00054     _os << _val.IE << "\t" << _val.Name << "\t" << _val.Ref << "\t" << _val.usage;
00055     return _os;
00056 }
00057
00058 } // end namespace gdcm
00059 #endif //GDCMIODENTRY_H

```

11.209 gdcmIODs.h File Reference


```

#include "gdcmTypes.h"
#include "gdcmIOD.h"


```

```
#include <map>
```

Include dependency graph for gdcmIODs.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::IODs](#)
Class for representing a [IODs](#).

Namespaces

- namespace `gdcm`

Functions

- `std::ostream & gdcm::operator<< (std::ostream &_os, const IODs &_val)`

11.210 gdcmIODs.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003     Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005     Copyright (c) 2006-2011 Mathieu Malaterre
00006     All rights reserved.
00007     See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009     This software is distributed WITHOUT ANY WARRANTY; without even
00010     the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011     PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMIODS_H
00015 #define GDCMIODS_H
00016
00017 #include "gdcmTypes.h"
00018 #include "gdcmIOD.h"
00019
00020 #include <map>
00021
00022 namespace gdcm
00023 {
00024     class GDCM_EXPORT IODs
00025     {
00026     public:
00027         typedef std::string IODName;
00028         typedef std::map<IODName, IOD> IODMapType;
00029
00030         IODs() = default;
00031         friend std::ostream& operator<<(std::ostream& _os, const IODs &_val);
00032
00033         void Clear() { IODsInternal.clear(); }
00034
00035         void AddIOD(const char *name, const IOD & module)
00036         {
00037             IODsInternal.insert(
00038                 IODMapType::value_type(name, module));
00039         }
00040         const IOD &GetIOD(const char *name) const
00041         {
00042             //return IODsInternal[name];
00043             IODMapType::const_iterator it = IODsInternal.find( name );
00044             gdcm_assert( it != IODsInternal.end() );
00045             gdcm_assert( it->first == name );
00046             return it->second;
00047         }
00048
00049         typedef IODMapType::const_iterator IODMapTypeConstIterator;
00050         IODMapTypeConstIterator Begin() const { return IODsInternal.begin(); }
00051         IODMapTypeConstIterator End() const { return IODsInternal.end(); }
00052
00053     private:
00054         IODMapType IODsInternal;
00055     };
00056
00057 //-----
00058 inline std::ostream& operator<<(std::ostream& _os, const IODs &_val)
00059 {
00060     IODs::IODMapType::const_iterator it = _val.IODsInternal.begin();

```

```

00065     for(; it != _val.IODsInternal.end(); ++it)
00066     {
00067         const std::string &name = it->first;
00068         const IOD &m = it->second;
00069         _os << name << " " << m << '\n';
00070     }
00071     return _os;
00072 }
00073 }
00074
00075
00076 } // end namespace gdcm
00077
00078 #endif //GDCMIODS_H

```


11.211 gdcmMacro.h File Reference

```


#include "gdcmTypes.h"
#include "gdcmTag.h"
#include "gdcmMacroEntry.h"
#include <map>
#include <vector>

```

Include dependency graph for gdcmMacro.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::Macro](#)
Class for representing a [Macro](#).

Namespaces

- namespace [gdc](#)

Functions

- `std::ostream & gdcm::operator<< (std::ostream &_os, const Macro &_val)`

11.212 gdcMacro.h

[Go to the documentation of this file.](#)

```

00001  /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library

```

```

00004
00005 Copyright (c) 2006-2011 Mathieu Malaterre
00006 All rights reserved.
00007 See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009 This software is distributed WITHOUT ANY WARRANTY; without even
00010 the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011 PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMMACRO_H
00015 #define GDCMMACRO_H
00016
00017 #include "gdcmTypes.h"
00018 #include "gdcmTag.h"
00019 #include "gdcMacroEntry.h"
00020
00021 #include <map>
00022 #include <vector>
00023
00024 namespace gdcm
00025 {
00026
00027 class DataSet;
00028 class Usage;
00036 class GDCM_EXPORT Macro
00037 {
00038 public:
00039     typedef std::map<Tag, MacroEntry> MapModuleEntry;
00040     typedef std::vector<std::string> ArrayIncludeMacrosType;
00041
00042     //typedef MapModuleEntry::const_iterator ConstIterator;
00043     //typedef MapModuleEntry::iterator Iterator;
00044     //ConstIterator Begin() const { return ModuleInternal.begin(); }
00045     //Iterator Begin() { return ModuleInternal.begin(); }
00046     //ConstIterator End() const { return ModuleInternal.end(); }
00047     //Iterator End() { return ModuleInternal.end(); }
00048
00049     Macro() = default;
00050     friend std::ostream& operator<<(std::ostream& _os, const Macro& _val);
00051
00052     void Clear() { ModuleInternal.clear(); }
00053
00055     void AddMacroEntry(const Tag& tag, const MacroEntry & module)
00056     {
00057         ModuleInternal.insert(
00058             MapModuleEntry::value_type(tag, module));
00059     }
00060
00063     bool FindMacroEntry(const Tag &tag) const;
00064     const MacroEntry& GetMacroEntry(const Tag &tag) const;
00065
00066     void SetName( const char *name) { Name = name; }
00067     const char *GetName() const { return Name.c_str(); }
00068
00069     // Verify will print on std::cerr for error
00070     // Upon success will return true, false otherwise
00071     bool Verify(const DataSet& ds, Usage const & usage) const;
00072
00073 private:
00074     //Module &operator=(const Module &_val); // purposely not implemented
00075     //Module(const Module &_val); // purposely not implemented
00076
00077     MapModuleEntry ModuleInternal;
00078     std::string Name;
00079 };
00080 //-----
00081 inline std::ostream& operator<<(std::ostream& _os, const Macro &_val)
00082 {
00083     _os << _val.Name << '\n';
00084     Macro::MapModuleEntry::const_iterator it = _val.ModuleInternal.begin();
00085     for(; it != _val.ModuleInternal.end(); ++it)
00086     {
00087         const Tag &t = it->first;
00088         const MacroEntry &de = it->second;
00089         _os << t << " " << de << '\n';
00090     }
00091
00092     return _os;
00093 }
00094

```

```


00095 } // end namespace gdcm
00096
00097 #endif //GDCMMACRO_H

```


11.213 gdcmMacroEntry.h File Reference

```
#include "gdcmModuleEntry.h"
```

Include dependency graph for gdcmMacroEntry.h:



This graph shows which files directly or indirectly include this file:



Macros

- #define [GDCMMACROENTRY_H](#)

11.213.1 Macro Definition Documentation

11.213.1.1 GDCMMACROENTRY_H

```
#define GDCMMACROENTRY_H
```

11.214 gdcmMacroEntry.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #if 0
00015 #ifndef GDCMMACROENTRY_H
00016 #define GDCMMACROENTRY_H
00017
00018 #include "gdcmTypes.h"
00019 #include "gdcmType.h"
00020
00021 #include <string>
00022
00023 namespace gdcm
00024 {
00030 class GDCM_EXPORT MacroEntry
00031 {
00032 public:
00033   MacroEntry(const char *name = "", const char *type = "3", const char *description =
00034   ""):Name(name)/*,Type(type)*/,DescriptionField(description) {
00035     DataElementType = Type::GetTypeType(type);
00036   }
00037   virtual ~MacroEntry() {} // important
00038   friend std::ostream& operator<<(std::ostream& _os, const MacroEntry &_val);
00039
00040   void SetName(const char *name) { Name = name; }
00041   const char *GetName() const { return Name.c_str(); }
00042
00043   void SetType(const Type &type) { DataElementType = type; }
00044   const Type &GetType() const { return DataElementType; }
00045
00046   /*
00047    * WARNING: 'Description' is currently a std::string, but it might change in the future
00048    * do not expect it to remain the same, and always use the ModuleEntry::Description typedef
00049    * instead.
00050    */
00051   typedef std::string Description;
00052   void SetDescription(const char *d) { DescriptionField = d; }
00053   const Description & GetDescription() const { return DescriptionField; }
00054 protected:
00055   // PS 3.3 repeats the name of an attribute, but often contains typos
00056   // for now we will not use this info, but instead access the DataDict instead
00057   std::string Name;
00058
00059   // An attribute, encoded as a Data Element, may or may not be required in a
00060   // Data Set, depending on that Attribute's Data Element Type.
00061   Type DataElementType;
00062
00063   // TODO: for now contains the raw description (with enumerated values, defined terms...)
00064   Description DescriptionField;
00065 };
00066 //-----
00067 inline std::ostream& operator<<(std::ostream& _os, const MacroEntry &_val)
00068 {
00069   _os << _val.Name << "\t" << _val.DataElementType << "\t" << _val.DescriptionField;
00070   return _os;
00071 }
00072
00073
00074 } // end namespace gdcm
00075
00076 #endif //GDCMMODULEENTRY_H
00077 #endif
00078
00079 #ifndef GDCMMACROENTRY_H

```

```

00080 #define GDCMMACROENTRY_H
00081 #include "gdcmModuleEntry.h"
00082 #endif

```


11.215 gdcmMacros.h File Reference

```


#include "gdcmTypes.h"
#include "gdcmMacro.h"
#include <map>

```

Include dependency graph for gdcmMacros.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::Macros](#)
Class for representing a [Modules](#).

Namespaces

- namespace [gdcm](#)

Functions

- `std::ostream & gdcm::operator<< (std::ostream &_os, const Macros &_val)`

11.216 gdcmMacros.h

[Go to the documentation of this file.](#)

```

00001  /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
  
```

```

00010     the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011     PURPOSE. See the above copyright notice for more information.
00012
00013     =====*/
00014 #ifndef GDCMMACROS_H
00015 #define GDCMMACROS_H
00016
00017 #include "gdcmTypes.h"
00018 #include "gdcmMacro.h"
00019
00020 #include <map>
00021
00022 namespace gdcm
00023 {
00024     class GDCM_EXPORT Macros
00025     {
00026     public:
00027         typedef std::map<std::string, Macro> ModuleMapType;
00028
00029         Macros() = default;
00030         friend std::ostream& operator<<(std::ostream& _os, const Macros& _val);
00031
00032         void Clear() { ModulesInternal.clear(); }
00033
00034         // A Module is inserted based on it's ref
00035         void AddMacro(const char *ref, const Macro & module )
00036         {
00037             gdcm_assert( ref && *ref );
00038             gdcm_assert( ModulesInternal.find( ref ) == ModulesInternal.end() );
00039             ModulesInternal.insert(
00040                 ModuleMapType::value_type(ref, module));
00041         }
00042         const Macro &GetMacro(const char *name) const
00043         {
00044             gdcm_assert( name && *name );
00045             ModuleMapType::const_iterator it = ModulesInternal.find( name );
00046             gdcm_assert( it != ModulesInternal.end() );
00047             gdcm_assert( it->first == name );
00048             return it->second;
00049         }
00050
00051         bool IsEmpty() const { return ModulesInternal.empty(); }
00052
00053     private:
00054         ModuleMapType ModulesInternal;
00055     };
00056
00057     //-----
00058     inline std::ostream& operator<<(std::ostream& _os, const Macros &_val)
00059     {
00060         Macros::ModuleMapType::const_iterator it = _val.ModulesInternal.begin();
00061         for(; it != _val.ModulesInternal.end(); ++it)
00062         {
00063             const std::string &name = it->first;
00064             const Macro &m = it->second;
00065             _os << name << " " << m << '\n';
00066         }
00067
00068         return _os;
00069     }
00070 } // end namespace gdcm
00071
00072 #endif //GDCMMODULES_H

```

11.217 gdcmModule.h File Reference

```

#include "gdcmTypes.h"
#include "gdcmTag.h"
#include "gdcmModuleEntry.h"
#include <map>

```


Classes

- class [gdcm::Module](#)
Class for representing a [Module](#).

Namespaces

- namespace [gdcm](#)

Functions

- `std::ostream & gdcm::operator<< (std::ostream &_os, const Module &_val)`

11.218 gdcmModule.h

[Go to the documentation of this file.](#)

```

00001  /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013  =====*/
00014  #ifndef GDCMMODULE_H
00015  #define GDCMMODULE_H
00016
00017  #include "gdcmTypes.h"
00018  #include "gdcmTag.h"
00019  #include "gdcmModuleEntry.h"
00020
00021  #include <map>
00022  #include <vector>
00023
00024  namespace gdcm
00025  {
00026
00027  class DataSet;
00028  class Usage;
00029  class Macros;
00037  class GDCM_EXPORT Module
00038  {
00039  public:
00040  typedef std::map<Tag, ModuleEntry> MapModuleEntry;
00041  typedef std::vector<std::string> ArrayIncludeMacroType;
00042
00043  //typedef MapModuleEntry::const_iterator ConstIterator;
00044  //typedef MapModuleEntry::iterator Iterator;
00045  //ConstIterator Begin() const { return ModuleInternal.begin(); }
00046  //Iterator Begin() { return ModuleInternal.begin(); }
00047  //ConstIterator End() const { return ModuleInternal.end(); }
00048  //Iterator End() { return ModuleInternal.end(); }
00049
00050  Module() = default;
00051  friend std::ostream& operator<<(std::ostream& _os, const Module &_val);
00052
00053  void Clear() { ModuleInternal.clear(); }
00054
00056  void AddModuleEntry(const Tag& tag, const ModuleEntry & module)
00057  {

```

```

00058     ModuleInternal.insert(
00059         MapModuleEntry::value_type(tag, module));
00060     }
00061
00062 void AddMacro(const char *include)
00063 {
00064     ArrayIncludeMacros.push_back( include );
00065 }
00066
00067 bool FindModuleEntryInMacros(Macros const &macros, const Tag &tag) const;
00070 const ModuleEntry& GetModuleEntryInMacros(Macros const &macros, const Tag &tag) const;
00071
00072 void SetName( const char *name) { Name = name; }
00073 const char *GetName() const { return Name.c_str(); }
00074
00075 // Verify will print on std::cerr for error
00076 // Upon success will return true, false otherwise
00077 bool Verify(const DataSet& ds, Usage const & usage) const;
00078
00079 private:
00080     //Module &operator=(const Module &_val); // purposely not implemented
00081     //Module(const Module &_val); // purposely not implemented
00082
00083     MapModuleEntry ModuleInternal;
00084     std::string Name;
00085     ArrayIncludeMacrosType ArrayIncludeMacros;
00086 };
00087 //-----
00088 inline std::ostream& operator<<(std::ostream& _os, const Module &_val)
00089 {
00090     _os << _val.Name << '\n';
00091     Module::MapModuleEntry::const_iterator it = _val.ModuleInternal.begin();
00092     for(; it != _val.ModuleInternal.end(); ++it)
00093     {
00094         const Tag &t = it->first;
00095         const ModuleEntry &de = it->second;
00096         _os << t << " " << de << '\n';
00097     }
00098
00099     return _os;
00100 }
00101
00102 } // end namespace gdcmm
00103
00104 #endif //GDCMMODULE_H

```


11.219 gdcmmModuleEntry.h File Reference

```


#include "gdcmmTypes.h"
#include "gdcmmType.h"
#include <string>

```


Include dependency graph for gdcmModuleEntry.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::ModuleEntry](#)

Class for representing a [ModuleEntry](#).

Namespaces

- namespace [gdcm](#)

Typedefs

- typedef [ModuleEntry](#) [gdcm::MacroEntry](#)

Functions

- [std::ostream & gdcm::operator<<](#) ([std::ostream &_os](#), const [ModuleEntry](#) &_val)

11.220 gdcmModuleEntry.h

[Go to the documentation of this file.](#)

```

00001  /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013  =====*/
00014  #ifndef GDCMMODULEENTRY_H
00015  #define GDCMMODULEENTRY_H
00016
00017  #include "gdcmTypes.h"
00018  #include "gdcmType.h"
00019
00020  #include <string>
00021
00022  namespace gdcm
00023  {
00024  class GDCM_EXPORT ModuleEntry
00025  {
00026  public:
00027    ModuleEntry(const char *name = "", const char *type = "3", const char *description =
00028    ""):Name(name),Type(type),DescriptionField(description) {
00029      DataElementType = Type::GetTypeType(type);
00030    }
00031    virtual ~ModuleEntry() = default; // important
00032    friend std::ostream& operator<<(std::ostream& _os, const ModuleEntry &_val);
00033
00034    void SetName(const char *name) { Name = name; }
00035    const char *GetName() const { return Name.c_str(); }
00036
00037    void SetType(const Type &type) { DataElementType = type; }
00038    const Type &GetType() const { return DataElementType; }
00039
00040    /*
00041     * WARNING: 'Description' is currently a std::string, but it might change in the future
00042     * do not expect it to remain the same, and always use the ModuleEntry::Description typedef
00043     * instead.
00044     */
00045    typedef std::string Description;
00046    void SetDescription(const char *d) { DescriptionField = d; }

```

```

00051     const Description & GetDescription() const { return DescriptionField; }
00052
00053 protected:
00054     // PS 3.3 repeats the name of an attribute, but often contains typos
00055     // for now we will not use this info, but instead access the DataDict instead
00056     std::string Name;
00057
00058     // An attribute, encoded as a Data Element, may or may not be required in a
00059     // Data Set, depending on that Attribute's Data Element Type.
00060     Type DataElementType;
00061
00062     // TODO: for now contains the raw description (with enumerated values, defined terms...)
00063     Description DescriptionField;
00064 };
00065 //-----
00066 inline std::ostream& operator<<(std::ostream& _os, const ModuleEntry &_val)
00067 {
00068     _os << _val.Name << "\t" << _val.DataElementType << "\t" << _val.DescriptionField;
00069     return _os;
00070 }
00071
00072 typedef ModuleEntry MacroEntry;
00073
00074
00075 } // end namespace gdcm
00076
00077 #endif //GDCMMODULEENTRY_H

```


11.221 gdcmModules.h File Reference

```


#include "gdcmTypes.h"
#include "gdcmModule.h"
#include <map>

```

Include dependency graph for gdcmModules.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::Modules](#)
Class for representing a [Modules](#).

Namespaces

- namespace [gdc](#)

Functions

- `std::ostream & gdcm::operator<< (std::ostream &_os, const Modules &_val)`

11.222 gdcModules.h

[Go to the documentation of this file.](#)

```

00001  /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdc.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
  
```

```

00010     the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011     PURPOSE. See the above copyright notice for more information.
00012
00013     =====*/
00014 #ifndef GDCMMODULES_H
00015 #define GDCMMODULES_H
00016
00017 #include "gdcmTypes.h"
00018 #include "gdcmModule.h"
00019
00020 #include <map>
00021
00022 namespace gdcm
00023 {
00024     class GDCM_EXPORT Modules
00025     {
00026     public:
00027         typedef std::map<std::string, Module> ModuleMapType;
00028
00029         Modules() = default;
00030         friend std::ostream& operator<<(std::ostream& _os, const Modules &_val);
00031
00032         void Clear() { ModulesInternal.clear(); }
00033
00034         // A Module is inserted based on it's ref
00035         void AddModule(const char *ref, const Module & module )
00036         {
00037             gdcm_assert( ref && *ref );
00038             gdcm_assert( ModulesInternal.find( ref ) == ModulesInternal.end() );
00039             ModulesInternal.insert(
00040                 ModuleMapType::value_type(ref, module));
00041         }
00042         const Module &GetModule(const char *name) const
00043         {
00044             gdcm_assert( name && *name );
00045             ModuleMapType::const_iterator it = ModulesInternal.find( name );
00046             gdcm_assert( it != ModulesInternal.end() );
00047             gdcm_assert( it->first == name );
00048             return it->second;
00049         }
00050
00051         bool IsEmpty() const { return ModulesInternal.empty(); }
00052
00053     private:
00054         ModuleMapType ModulesInternal;
00055     };
00056
00057 //-----
00058 inline std::ostream& operator<<(std::ostream& _os, const Modules &_val)
00059 {
00060     Modules::ModuleMapType::const_iterator it = _val.ModulesInternal.begin();
00061     for(; it != _val.ModulesInternal.end(); ++it)
00062     {
00063         const std::string &name = it->first;
00064         const Module &m = it->second;
00065         _os << name << " " << m << '\n';
00066     }
00067
00068     return _os;
00069 }
00070
00071 // end namespace gdcm
00072 #endif //GDCMMODULES_H

```


11.223 gdcmNestedModuleEntries.h File Reference

```

#include "gdcmModuleEntry.h"
#include <vector>

```

Include dependency graph for `gdcmNestedModuleEntries.h`:



Classes

- class [gdcm::NestedModuleEntries](#)
Class for representing a *NestedModuleEntries*.

Namespaces

- namespace [gdcm](#)

Typedefs

- typedef [NestedModuleEntries](#) [gdcm::NestedMacroEntries](#)

Functions

- `std::ostream & gdcm::operator<< (std::ostream &_os, const NestedModuleEntries &_val)`

11.224 gdcmNestedModuleEntries.h

[Go to the documentation of this file.](#)

```

00001  /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013  =====*/
00014  #ifndef GDCMNESTEDMODULEENTRIES_H
00015  #define GDCMNESTEDMODULEENTRIES_H
00016
00017  #include "gdcmModuleEntry.h"
00018  #include <vector>
00019
00020  namespace gdcm
00021  {
00022
00027  class GDCM_EXPORT NestedModuleEntries : public ModuleEntry
00028  {
00029  public:
00030      NestedModuleEntries(const char *name = "", const char *type = "3", const char *description =
00031                          ""):ModuleEntry(name,type,description) { }
00032      friend std::ostream& operator<(std::ostream& _os, const NestedModuleEntries &_val);
00033
00034      typedef std::vector<ModuleEntry>::size_type SizeType;
00035      SizeType GetNumberOfModuleEntries() { return ModuleEntriesList.size(); }
00036      const ModuleEntry &GetModuleEntry(SizeType idx) const { return ModuleEntriesList[idx]; }
00037      ModuleEntry &GetModuleEntry(SizeType idx) { return ModuleEntriesList[idx]; }
00038
00039      void AddModuleEntry(const ModuleEntry &me) { ModuleEntriesList.push_back( me ); }
00040
00041  private:
00042      std::vector<ModuleEntry> ModuleEntriesList;
00043  };
00044  //-----
00045  inline std::ostream& operator<(std::ostream& _os, const NestedModuleEntries &_val)
00046  {
00047      _os << "Nested:" << _val.Name << "\t" << _val.DataElementType << "\t" << _val.DescriptionField;
00048      return _os;
00049  }
00050
00051  typedef NestedModuleEntries NestedMacroEntries;
00052
00053  } // end namespace gdcm
00054
00055  #endif //GDCMNESTEDMODULEENTRIES_H

```


11.225 gdcmPatient.h File Reference

```

#include "gdcmTypes.h"
#include "gdcmStudy.h"

```

Include dependency graph for `gdcmPatient.h`:



Classes

- class [gdcm::Patient](#)

See PS 3.3 - 2007 DICOM MODEL OF THE REAL-WORLD, p 54.

Namespaces

- namespace [gdcm](#)

11.226 gdcmPatient.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012   =====*/
00013
00014 #ifndef GDCMPATIENT_H
00015 #define GDCMPATIENT_H
00016
00017 #include "gdcmTypes.h"
00018 #include "gdcmStudy.h"
00019

```



```


00020 namespace gdcm
00021 {
00027 class GDCM_EXPORT Patient
00028 {
00029 public:
00030     Patient() = default;
00031 private:
00032     std::vector<Study> StudyList;
00033 };
00034 } // end namespace gdcm
00035
00036 } // end namespace gdcm
00037
00038 #endif //GDCMPATIENT_H

```


11.227 gdcmSeries.h File Reference

```
#include "gdcmTypes.h"
```

Include dependency graph for gdcmSeries.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::Series](#)
Series.

Namespaces

- namespace [gdcm](#)

11.228 gdcmSeries.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013   =====*/
00014 #ifndef GDCMSERIES_H
00015 #define GDCMSERIES_H
00016
00017 #include "gdcmTypes.h"
00018
00019 namespace gdcm
00020 {
00021
00022   class GDCM_EXPORT Series
00023   {
00024   public:
00025     Series() = default;
00026   private:
00027     // Image, Waveform...
00028   };
00029
00030 } // end namespace gdcm
00031
00032 #endif //GDCMSERIES_H

```

11.229 gdcmStudy.h File Reference


```

#include "gdcmTypes.h"
#include "gdcmSeries.h"


```

```
#include <vector>
```

Include dependency graph for gdcmStudy.h:



This graph shows which files directly or indirectly include this file:



Classes

- class `gdcm::Study`
Study.

Namespaces

- namespace `gdcm`

11.230 gdcmStudy.h


[Go to the documentation of this file.](#)

```
00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMSTUDY_H
00015 #define GDCMSTUDY_H
00016
00017 #include "gdcmTypes.h"
00018 #include "gdcmSeries.h"
00019
00020 #include <vector>
00021
00022 namespace gdcm
00023 {
00024     class GDCM_EXPORT Study
00025     {
00026     public:
00027         Study() = default;
00028     private:
00029         std::vector<Series> SeriesList;
00030     };
00031 } // end namespace gdcm
00032
00033 #endif //GDCMSTUDY_H
```

11.231 gdcmTable.h File Reference

```
#include "gdcmTableEntry.h"
#include "gdcmTag.h"
#include <map>
```

Include dependency graph for gdcmTable.h:



Classes

- class [gdcm::Table](#)
Table.

Namespaces

- namespace [gdcm](#)

11.232 gdcmTable.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013   =====*/
00014 #ifndef GDCMTABLE_H
00015 #define GDCMTABLE_H
00016
00017 #include "gdcmTableEntry.h"
00018 #include "gdcmTag.h"
00019
00020 #include <map>

```

```

00021
00022 namespace gdcmm
00023 {
00024
00028 class Table
00029 {
00030 public:
00031     typedef std::map<Tag, TableEntry> MapTableEntry;
00032     Table() = default;
00033     ~Table() = default;
00034     Table &operator=(const Table &_val) = delete;
00035     Table(const Table&_val) = delete;
00036
00037     friend std::ostream& operator<<(std::ostream& _os, const Table &_val);
00038
00039     void InsertEntry(Tag const &tag, TableEntry const &te)
00040     {
00041 #ifndef NDEBUB
00042         MapTableEntry::size_type s = TableInternal.size();
00043 #endif
00044         TableInternal.insert(
00045             MapTableEntry::value_type(tag, te));
00046 #ifndef NDEBUB
00047         gdcmm_assert( s < TableInternal.size() );
00048 #endif
00049     }
00050
00051     const TableEntry &GetTableEntry(const Tag &tag) const
00052     {
00053         MapTableEntry::const_iterator it =
00054             TableInternal.find(tag);
00055         if (it == TableInternal.end())
00056         {
00057             gdcmm_assert( 0 && "Impossible" );
00058             return GetTableEntry(Tag(0,0));
00059         }
00060         return it->second;
00061     }
00062
00063     MapTableEntry TableInternal;
00064 };
00065
00066 } // end namespace gdcmm
00067
00068 #endif //GDCMTABLE_H

```


11.233 gdcmmTableEntry.h File Reference

```


#include "gdcmmType.h"
#include <string>

```

Include dependency graph for gdcmTableEntry.h:



This graph shows which files directly or indirectly include this file:



Classes

- class `gdcm::TableEntry`
TableEntry.

Namespaces

- namespace `gdcm`

11.234 gdcmTableEntry.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMTABLEENTRY_H
00015 #define GDCMTABLEENTRY_H
00016
00017 #include "gdcmType.h"
00018
00019 #include <string>
00020
00021 namespace gdcm
00022 {
00023
00024   class TableEntry
00025   {
00026   public:
00027     TableEntry(const char *attribute = nullptr,
00028               Type const &type = Type(), const char * des = nullptr ) :
00029       Attribute(attribute ? attribute : ""), TypeField(type), Description(des ? des : "") {}
00030     ~TableEntry() = default;
00031
00032   private:
00033     std::string Attribute;
00034     Type TypeField;
00035     std::string Description;
00036   };
00037
00038 } // end namespace gdcm
00039
00040 #endif //GDCMTABLEENTRY_H

```

11.235 gdcmTableReader.h File Reference

```

#include "gdcmTypes.h"
#include "gdcmDefs.h"
#include <string>
#include <vector>
#include <map>

```



```
graph BT; gdcmXMLDictReader.h --> gdcmTableReader.h; gdcmXMLPrivateDictReader.h --> gdcmTableReader.h
```

- class `gdcm::TableReader`
Class for representing a `TableReader`.

- namespace **gdcm**

11.236 gdcmTableReader.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMTABLEREADER_H
00015 #define GDCMTABLEREADER_H
00016
00017 #include "gdcmTypes.h"
00018 #include "gdcmDefs.h"
00019 // #include "gdcmModule.h"
00020 // #include "gdcmIOD.h"
00021 // #include "gdcmIODs.h"
00022 // #include "gdcmModules.h"
00023
00024 #include <string>
00025 #include <vector>
00026 #include <map>
00027
00028 namespace gdcm
00029 {
00030     class GDCM_EXPORT TableReader
00031     {
00032     public:
00033         TableReader(Defs &defs):CurrentDefs(defs),ParsingModule(false),ParsingModuleEntry(false),
00034             ParsingModuleEntryDescription(false),
00035             ParsingMacro(false),
00036             ParsingMacroEntry(false),
00037             ParsingMacroEntryDescription(false),
00038             ParsingIOD(false),
00039             ParsingIODEntry(false),
00040             Description() {}
00041         virtual ~TableReader() = default;
00042
00043         // Set/Get filename
00044         void SetFilename(const char *filename) { Filename = filename; }
00045         const char *GetFilename() { return Filename.c_str(); }
00046
00047         int Read();
00048
00049     protected:
00050         // You need to override those function in your subclasses:
00051         virtual void StartElement(const char *name, const char **atts);
00052         virtual void EndElement(const char *name);
00053         virtual void CharacterDataHandler(const char *data, int length);
00054
00055         void HandleModuleEntry(const char **atts);
00056         void HandleModule(const char **atts);
00057         void HandleModuleEntryDescription(const char **atts);
00058         void HandleMacroEntry(const char **atts);
00059         void HandleMacro(const char **atts);
00060         void HandleMacroEntryDescription(const char **atts);
00061         void HandleModuleInclude(const char **atts);
00062         void HandleIODEntry(const char **atts);
00063         void HandleIOD(const char **atts);
00064
00065         //const Modules & GetModules() const { return CurrentModules; }
00066         //const Macros & GetMacros() const { return CurrentMacros; }
00067         //const IODs & GetIODs() const { return CurrentIODs; }
00068         const Defs & GetDefs() const { return CurrentDefs; }
00069
00070     private:
00071         std::string Filename;
00072         Defs &CurrentDefs;
00073         //Macros CurrentMacros;
00074         //Modules CurrentModules;
00075         //IODs CurrentIODs;

```

```

00080 Macro CurrentMacro;
00081 Module CurrentModule;
00082 IOD CurrentIOD;
00083 MacroEntry CurrentMacroEntry;
00084 ModuleEntry CurrentModuleEntry;
00085 IOEntry CurrentIOEntry;
00086 std::string CurrentModuleName;
00087 std::string CurrentModuleRef;
00088 std::string CurrentMacroRef;
00089 bool ParsingModule;
00090 bool ParsingModuleEntry;
00091 bool ParsingModuleEntryDescription;
00092 bool ParsingMacro;
00093 bool ParsingMacroEntry;
00094 bool ParsingMacroEntryDescription;
00095 bool ParsingIOD;
00096 bool ParsingIOEntry;
00097 Tag CurrentTag;
00098 std::string Description;
00099 };
00100
00101 } // end namespace gdcm
00102
00103 #endif //GDCMTABLEREADER_H


```

11.237 gdcmType.h File Reference


```
#include "gdcmTypes.h"
```

```
#include <iostream>
```

Include dependency graph for gdcmType.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::Type](#)
Type.

Namespaces

- namespace [gdcm](#)

Functions

- `std::ostream & gdcm::operator<< (std::ostream &_os, const Type &val)`

11.238 gdcmType.h

[Go to the documentation of this file.](#)

```

00001  /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

```

```

00008
00009     This software is distributed WITHOUT ANY WARRANTY; without even
00010     the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011     PURPOSE. See the above copyright notice for more information.
00012
00013     =====*/
00014
00015 #ifndef GDCMTYPE_H
00016 #define GDCMTYPE_H
00017
00018 #include "gdcmTypes.h"
00019
00020 #include <iostream>
00021
00022 namespace gdcm
00023 {
00024
00041 class GDCM_EXPORT Type
00042 {
00043 public:
00044     typedef enum {
00045         T1 = 0,
00046         T1C,
00047         T2,
00048         T2C,
00049         T3,
00050         UNKNOWN
00051     } TypeType;
00052
00053     Type(TypeType type = UNKNOWN) : TypeField(type) { }
00054
00055     operator TypeType () const { return TypeField; }
00056     friend std::ostream &operator<<(std::ostream &os, const Type &vr);
00057
00058     static const char *GetTypeString(TypeType type);
00059     static TypeType GetTypeType(const char *type);
00060
00061 private:
00062     TypeType TypeField;
00063 };
00064 //-----
00065 inline std::ostream &operator<<(std::ostream &os, const Type &val)
00066 {
00067     _os << Type::GetTypeString(val.TypeField);
00068     return _os;
00069 }
00070
00071 } // end namespace gdcm
00072
00073 #endif //GDCMTYPE_H

```


11.239 gdcmUsage.h File Reference

```


#include "gdcmTypes.h"
#include <iostream>

```

Include dependency graph for `gdcmUsage.h`:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcml::Usage](#)
Usage.

Namespaces

- namespace [gdcml](#)

Functions

- `std::ostream & gdcml::operator<< (std::ostream &_os, const Usage &val)`

11.240 gdcmUsage.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMUSAGE_H
00015 #define GDCMUSAGE_H
00016
00017 #include "gdcmTypes.h"
00018
00019 #include <iostream>
00020
00021 namespace gdcm
00022 {
00023
00024   class GDCM_EXPORT Usage
00025   {
00026   public:
00027     typedef enum {
00028       Mandatory, // (see A.1.3.1) , abbreviated M
00029       Conditional, // (see A.1.3.2) , abbreviated C
00030       UserOption, // (see A.1.3.3) , abbreviated U
00031       Invalid
00032     } UsageType;
00033
00034     Usage(UsageType type = Invalid) : UsageField(type) { }
00035
00036     operator UsageType () const { return UsageField; }
00037     friend std::ostream &operator<<(std::ostream &os, const Usage &vr);
00038
00039     static const char *GetUsageString(UsageType type);
00040     static UsageType GetUsageType(const char *type);
00041
00042   private:
00043     UsageType UsageField;
00044   };
00045
00046   //-----
00047   inline std::ostream &operator<<(std::ostream &_os, const Usage &val)
00048   {
00049     _os << Usage::GetUsageString(val.UsageField);
00050     return _os;
00051   }
00052
00053 } // end namespace gdcm
00054
00055 #endif //GDCMUSAGE_H

```


11.241 gdcmXMLDictReader.h File Reference

```

#include "gdcmTableReader.h"
#include "gdcmDict.h"
#include "gdcmDictEntry.h"
#include "gdcmTag.h"

```


Include dependency graph for gdcmXMLDictReader.h:



Classes

- class [gdcm::XMLDictReader](#)
Class for representing a *XMLDictReader*.

Namespaces

- namespace [gdcm](#)

11.242 gdcmXMLDictReader.h

[Go to the documentation of this file.](#)

```

00001  /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012  =====*/
00013  #ifndef GDCMXMLDICTREADER_H
00014  #define GDCMXMLDICTREADER_H
00015
00016  #include "gdcmTableReader.h"
00017  #include "gdcmDict.h"
00018  #include "gdcmDictEntry.h"
00019  #include "gdcmTag.h"
00020
00021
00022  namespace gdcm
00023  {
00024
00029  class GDCM_EXPORT XMLDictReader : public TableReader
00030  {
00031  public:
00032    XMLDictReader();
00033    ~XMLDictReader() {}
00034
00035    void StartElement(const char *name, const char **atts);
00036    void EndElement(const char *name);
00037    void CharacterDataHandler(const char *data, int length);
00038
00039    const Dict & GetDict() { return DICOMDict; }

```

```

00040
00041 protected:
00042     void HandleEntry(const char **atts);
00043     void HandleDescription(const char **atts);
00044
00045 private:
00046     Dict DICOMDict;
00047     Tag CurrentTag;
00048     DictEntry CurrentDE;
00049     bool ParsingDescription;
00050     std::string Description;
00051 };
00052
00053 } // end namespace gdcM
00054
00055 #endif //GDCMXMLDICTREADER_H

```


11.243 gdcMXMLPrivateDictReader.h File Reference

```

#include "gdcMTableReader.h"
#include "gdcMDict.h"
#include "gdcMDictEntry.h"
#include "gdcMTag.h"

```

Include dependency graph for gdcMXMLPrivateDictReader.h:



Classes

- class [gdcM::XMLPrivateDictReader](#)
Class for representing a *XMLPrivateDictReader*.

Namespaces

- namespace [gdcM](#)

11.244 gdcMXMLPrivateDictReader.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003     Program: GDCM (Grassroots DICOM). A DICOM library


```

```
00004
00005 Copyright (c) 2006-2011 Mathieu Malaterre
00006 All rights reserved.
00007 See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009 This software is distributed WITHOUT ANY WARRANTY; without even
00010 the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011 PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMXMLPRIVATEDICTREADER_H
00015 #define GDCMXMLPRIVATEDICTREADER_H
00016
00017 #include "gdcmTableReader.h"
00018 #include "gdcmDict.h"
00019 #include "gdcmDictEntry.h"
00020 #include "gdcmTag.h"
00021
00022 namespace gdcm
00023 {
00024     class GDCM_EXPORT XMLPrivateDictReader : public TableReader
00025     {
00026     public:
00027         XMLPrivateDictReader();
00028         ~XMLPrivateDictReader() {}
00029
00030         void StartElement(const char *name, const char **atts);
00031         void EndElement(const char *name);
00032         void CharacterDataHandler(const char *data, int length);
00033
00034         const PrivateDict & GetPrivateDict() { return PDict; }
00035
00036     protected:
00037         void HandleEntry(const char **atts);
00038         void HandleDescription(const char **atts);
00039
00040     private:
00041         PrivateDict PDict;
00042         PrivateTag CurrentTag;
00043         DictEntry CurrentDE;
00044         bool ParsingDescription;
00045         std::string Description;
00046     };
00047 } // end namespace gdcm
00048
00049 #endif //GDCMXMLPRIVATEDICTREADER_H
```


11.245 gdcmAnonymizeEvent.h File Reference

```
#include "gdcmEvent.h"
#include "gdcmTag.h"
```

Include dependency graph for `gdcmAnonymizeEvent.h`:



This graph shows which files directly or indirectly include this file:



Classes

- class `gdcm::AnonymizeEvent`
AnonymizeEvent.

Namespaces

- namespace `gdcm`

11.246 gdcmAnonymizeEvent.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMANONYMIZEEVENT_H
00015 #define GDCMANONYMIZEEVENT_H
00016
00017 #include "gdcmEvent.h"
00018 #include "gdcmTag.h"
00019
00020 namespace gdcm
00021 {
00022
00023   class AnonymizeEvent : public AnyEvent
00024   {
00025   public:
00026     typedef AnonymizeEvent Self;
00027     typedef AnyEvent Superclass;
00028     AnonymizeEvent(Tag const &tag = 0):m_Tag(tag) {}
00029     ~AnonymizeEvent() override = default;
00030     AnonymizeEvent(const Self&s) : AnyEvent(s){}
00031     void operator=(const Self&) = delete;
00032
00033     const char * GetEventName() const override { return "AnonymizeEvent"; }
00034     bool CheckEvent(const ::gdcm::Event* e) const override
00035     { return (dynamic_cast<const Self*>(e) == nullptr ? false : true) ; }
00036     ::gdcm::Event* MakeObject() const override
00037     { return new Self; }
00038
00039     void SetTag(const Tag& t) { m_Tag = t; }
00040     Tag const & GetTag() const { return m_Tag; }
00041   private:
00042     Tag m_Tag;
00043   };
00044
00045 }
00046
00047 // end namespace gdcm
00048 #endif //GDCMANONYMIZEEVENT_H

```

11.247 gdcmAnonymizer.h File Reference

```

#include "gdcmFile.h"
#include "gdcmSubject.h"
#include "gdcmEvent.h"
#include "gdcmSmartPointer.h"
#include <map>

```



```


00027 class IOD;
00028 class CryptographicMessageSyntax;
00029
00077 class GDCM_EXPORT Anonymizer : public Subject
00078 {
00079 public:
00080     Anonymizer():F(new File),CMS(nullptr) {}
00081     ~Anonymizer() override;
00082
00084     bool Empty( Tag const &t );
00085
00090     bool Empty( PrivateTag const &pt );
00091
00093     bool Clear( Tag const &t );
00094     bool Clear( PrivateTag const &pt );
00095
00097     bool Remove( Tag const &t );
00098
00104     bool Remove( PrivateTag const &pt );
00105
00108     bool Replace( Tag const &t, const char *value );
00109     bool Replace( PrivateTag const &t, const char *value );
00110
00113     bool Replace( Tag const &t, const char *value, VL const &vl );
00114     bool Replace( PrivateTag const &t, const char *value, VL const &vl );
00115
00117     bool RemovePrivateTags();
00118
00120     bool RemoveGroupLength();
00121
00123     bool RemoveRetired();
00124
00126     void SetFile(const File& f) { F = f; }
00127     //const File &GetFile() const { return *F; }
00128     File &GetFile() { return *F; }
00129
00134     bool BasicApplicationLevelConfidentialityProfile(bool deidentify = true);
00135
00137     void SetCryptographicMessageSyntax( CryptographicMessageSyntax *cms );
00138     const CryptographicMessageSyntax *GetCryptographicMessageSyntax() const;
00139
00141     static SmartPointer<Anonymizer> New() { return new Anonymizer; }
00142
00144     static std::vector<Tag> GetBasicApplicationLevelConfidentialityProfileAttributes();
00145
00148     static void ClearInternalUIDs();
00149
00150 protected:
00151     // Internal function used to either empty a tag or set it's value to a dummy value (Type 1 vs Type 2)
00152     bool BALCPProtect(DataSet &ds, Tag const &tag, const IOD &ioid);
00153     bool CanEmptyTag(Tag const &tag, const IOD &ioid) const;
00154     void RecurseDataSet( DataSet &ds );
00155
00156 private:
00157     bool BasicApplicationLevelConfidentialityProfile1();
00158     bool BasicApplicationLevelConfidentialityProfile2();
00159     bool CheckIfSequenceContainsAttributeToAnonymize(File const &file, SequenceOfItems* sqi) const;
00160
00161 private:
00162     // I would prefer to have a smart pointer to DataSet but DataSet does not derive from Object...
00163     SmartPointer<File> F;
00164     CryptographicMessageSyntax *CMS;
00165
00166     typedef std::pair< Tag, std::string > TagValueKey;
00167     typedef std::map< TagValueKey, std::string > DummyMapNonUIDTags;
00168     typedef std::map< std::string, std::string > DummyMapUIDTags;
00169     static DummyMapNonUIDTags dummyMapNonUIDTags;
00170     static DummyMapUIDTags dummyMapUIDTags;
00171 };
00172
00178
00179 } // end namespace gdcm
00180
00181 #endif //GDCMANONYMIZER_H

```

11.249 gdcmApplicationEntity.h File Reference

```
#include "gdcmTypes.h"
#include <vector>
#include <stdlib.h>
```

Include dependency graph for gdcmApplicationEntity.h:



Classes

- class [gdcm::ApplicationEntity](#)
ApplicationEntity.

Namespaces

- namespace [gdcm](#)

11.250 gdcmApplicationEntity.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013  =====*/
00014 #ifndef GDCMAPPLICATIONENTITY_H
00015 #define GDCMAPPLICATIONENTITY_H
00016
00017 #include "gdcmTypes.h"
00018 #include <vector>
```



```


00019 #include <stdlib.h> // abort
00020
00021 namespace gdcm
00022 {
00023
00035 class GDCM_EXPORT ApplicationEntity
00036 {
00037 public:
00038     static const unsigned int MaxNumberOfComponents = 1;
00039     static const unsigned int MaxLength = 16;
00040     std::string Internal;
00041     static const char Separator = ' ';
00042     static const char Padding = ' ';
00043     //static const char Excluded[5] = { '\\', /* 5CH */, '\n', /* LF */, '\f', /* FF */, '\r', /* CR */, 0x1b
/* ESC */};
00044
00045     bool IsValid() const {
00046         return true;
00047     }
00048     void Squeeze() {
00049         // trim leading and trailing white spaces
00050     }
00051     void SetBlob(const std::vector<char>& v) {
00052         (void)v;
00053         gdcm_assert(0); //TODO
00054     }
00055     void Print(std::ostream &os) const {
00056         (void)os;
00057         gdcm_assert(0); //TODO
00058     }
00059 };
00060
00061 } // end namespace gdcm
00062
00063 #endif //GDCMAPPLICATIONENTITY_H

```

11.251 gdcmAudioCodec.h File Reference

#include "gdcmCodec.h"

Include dependency graph for gdcmAudioCodec.h:



Classes

- class [gdcm::AudioCodec](#)
AudioCodec.

Namespaces

- namespace `gdcm`

11.252 `gdcmAudioCodec.h`

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMAUDIOCODEC_H
00015 #define GDCMAUDIOCODEC_H
00016
00017 #include "gdcmCodec.h"
00018
00019 namespace gdcm
00020 {
00021
00022     class GDCM_EXPORT AudioCodec : public Codec
00023     {
00024     public:
00025         AudioCodec();
00026         ~AudioCodec() override;
00027         bool CanCode(TransferSyntax const &) const override { return false; }
00028         bool CanDecode(TransferSyntax const &) const override { return false; }
00029         bool Decode(DataElement const &is, DataElement &os) override;
00030     };
00031
00032 } // end namespace gdcm
00033
00034 #endif //GDCMAUDIOCODEC_H

```


11.253 `gdcmBitmap.h` File Reference

```


#include "gdcmObject.h"
#include "gdcmCurve.h"
#include "gdcmDataElement.h"
#include "gdcmLookupTable.h"
#include "gdcmOverlay.h"
#include "gdcmPhotometricInterpretation.h"
#include "gdcmPixelFormat.h"
#include "gdcmSmartPointer.h"
#include "gdcmTransferSyntax.h"

```

Include dependency graph for gdcmBitmap.h:



This graph shows which files directly or indirectly include this file:



Classes

- class `gdcm::Bitmap`
Bitmap class.

Namespaces

- namespace **gdcm**

11.254 gdcmBitmap.h

[Go to the documentation of this file.](#)

```
00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcml.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
```

```

00010     the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011     PURPOSE. See the above copyright notice for more information.
00012
00013     =====*/
00014 #ifndef GDCMBITMAP_H
00015 #define GDCMBITMAP_H
00016
00017 #include "gdcmObject.h"
00018 #include "gdcmCurve.h"
00019 #include "gdcmDataElement.h"
00020 // #include "gdcmIconImage.h"
00021 #include "gdcmLookupTable.h"
00022 #include "gdcmOverlay.h"
00023 #include "gdcmPhotometricInterpretation.h"
00024 #include "gdcmPixelFormat.h"
00025 #include "gdcmSmartPointer.h"
00026 #include "gdcmTransferSyntax.h"
00027
00028 #include <vector>
00029
00030 namespace gdcm
00031 {
00032
00033 class GDCM_EXPORT Bitmap : public Object
00034 {
00035 public:
00036     Bitmap();
00037     ~Bitmap() override;
00038     void Print(std::ostream &) const override;
00039
00040     virtual bool AreOverlaysInPixelData() const { return false; }
00041     virtual bool UnusedBitsPresentInPixelData() const { return false; }
00042
00043     unsigned int GetNumberOfDimensions() const;
00044     void SetNumberOfDimensions(unsigned int dim);
00045
00046     unsigned int GetPlanarConfiguration() const;
00047     void SetPlanarConfiguration(unsigned int pc);
00048
00049     bool GetNeedByteSwap() const
00050     {
00051         return NeedByteSwap;
00052     }
00053     void SetNeedByteSwap(bool b)
00054     {
00055         NeedByteSwap = b;
00056     }
00057
00058     void SetTransferSyntax(TransferSyntax const &ts) {
00059         TS = ts;
00060     }
00061     const TransferSyntax &GetTransferSyntax() const {
00062         return TS;
00063     }
00064     bool IsTransferSyntaxCompatible( TransferSyntax const & ts ) const;
00065     void SetDataElement(DataElement const &de) {
00066         PixelData = de;
00067     }
00068     const DataElement& GetDataElement() const { return PixelData; }
00069     DataElement& GetDataElement() { return PixelData; }
00070
00071     void SetLUT(LookupTable const &lut)
00072     {
00073         LUT = SmartPointer<LookupTable>( const_cast<LookupTable*>(&lut) );
00074     }
00075     const LookupTable &GetLUT() const
00076     {
00077         return *LUT;
00078     }
00079     LookupTable &GetLUT()
00080     {
00081         return *LUT;
00082     }
00083
00084     const unsigned int *GetDimensions() const;
00085     unsigned int GetDimension(unsigned int idx) const;
00086
00087     void SetColumns(unsigned int col) { SetDimension(0,col); }
00088     unsigned int GetColumns() const { return GetDimension(0); }
00089     void SetRows(unsigned int rows) { SetDimension(1,rows); }

```

```


00103 unsigned int GetRows() const { return GetDimension(1); }
00104 void SetDimensions(const unsigned int dims[3]);
00105 void SetDimension(unsigned int idx, unsigned int dim);
00107 const PixelFormat &GetPixelFormat() const
00108 {
00109     return PF;
00110 }
00111 PixelFormat &GetPixelFormat()
00112 {
00113     return PF;
00114 }
00115 void SetPixelFormat(PixelFormat const &pf)
00116 {
00117     PF = pf;
00118     PF.Validate();
00119 }
00120
00122 const PhotometricInterpretation &GetPhotometricInterpretation() const;
00123 void SetPhotometricInterpretation(PhotometricInterpretation const &pi);
00124
00125 bool IsEmpty() const { return Dimensions.empty(); }
00126 void Clear();
00127
00131 unsigned long GetBufferLength() const;
00132
00134 bool GetBuffer(char *buffer) const;
00135
00137 bool IsLossy() const;
00138
00140 void SetLossyFlag(bool f) { LossyFlag = f; }
00141
00142 protected:
00143     bool TryRAWCodec(char *buffer, bool &lossyflag) const;
00144     bool TryJPEGCodec(char *buffer, bool &lossyflag) const;
00145     bool TryPVRGCodec(char *buffer, bool &lossyflag) const;
00146     bool TryKAKADUCodec(char *buffer, bool &lossyflag) const;
00147     bool TryJPEGLSCCodec(char *buffer, bool &lossyflag) const;
00148     bool TryJPEG2000Codec(char *buffer, bool &lossyflag) const;
00149     bool TryRLECodec(char *buffer, bool &lossyflag) const;
00150
00151     bool TryJPEGCodec2(std::ostream &os) const;
00152     bool TryJPEG2000Codec2(std::ostream &os) const;
00153
00154     bool GetBuffer2(std::ostream &os) const;
00155
00156     friend class PixmapReader;
00157     friend class ImageChangeTransferSyntax;
00158     // Function to compute the lossy flag based only on the image buffer.
00159     // Watch out that image can be lossy but in implicit little endian format...
00160     bool ComputeLossyFlag();
00161
00162 //private:
00163 protected:
00164     unsigned int PlanarConfiguration;
00165     unsigned int NumberOfDimensions;
00166     TransferSyntax TS;
00167     PixelFormat PF; // SamplesPerPixel, BitsAllocated, BitsStored, HighBit, PixelRepresentation
00168     PhotometricInterpretation PI;
00169     // Mind dump: unsigned int is required here, since we are reading (0028,0008) Number Of Frames
00170     // which is VR::IS, so I cannot simply assumed that unsigned short is enough... :(
00171     std::vector<unsigned int> Dimensions; // Col/Row
00172     DataElement PixelData; // copied from 7fe0,0010
00173
00174     typedef SmartPointer<LookupTable> LUTPtr;
00175     LUTPtr LUT;
00176     // I believe the following 3 ivars can be derived from TS ...
00177     bool NeedByteSwap; // FIXME: remove me
00178     bool LossyFlag;
00179
00180 private:
00181     bool GetBufferInternal(char *buffer, bool &lossyflag) const;
00182 };
00183
00184 } // end namespace gdcm
00185
00186 #endif //GDCMBITMAP_H

```


11.255 gdcmBitmapToBitmapFilter.h File Reference

```
#include "gdcmBitmap.h"
```

Include dependency graph for gdcmBitmapToBitmapFilter.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::BitmapToBitmapFilter](#)
BitmapToBitmapFilter class.

Namespaces

- namespace [gdcm](#)

11.256 gdcmBitmapToBitmapFilter.h

[Go to the documentation of this file.](#)

```
00001 /*=====
00002
00003 Program: GDCM (Grassroots DICOM). A DICOM library
```

11.257 gdcmCleaner.h File Reference

[illegible]

Classes

- class `gdcm::Cleaner`
Cleaner.

Namespaces

- namespace `gdcm`

11.258 gdcmCleaner.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013   =====*/
00014 #ifndef GDCMCLEANER_H
00015 #define GDCMCLEANER_H
00016
00017 #include "gdcmDPath.h"
00018 #include "gdcmFile.h"
00019 #include "gdcmSmartPointer.h"
00020 #include "gdcmSubject.h"
00021
00022 namespace gdcm {
00030 class GDCM_EXPORT Cleaner : public Subject {
00031 public:
00032   Cleaner();
00033   ~Cleaner() override;
00034
00036   bool Empty(Tag const &t);
00037   bool Empty(PrivateTag const &pt);
00038   bool Empty(DPath const &dpath);
00039   bool Empty(VR const &vr);
00040
00041   bool Remove(Tag const &t);
00042   bool Remove(PrivateTag const &pt);
00043   bool Remove(DPath const &dpath);
00044   bool Remove(VR const &vr);
00045
00047   bool Scrub(Tag const &t);
00048   bool Scrub(PrivateTag const &pt);
00049   bool Scrub(DPath const &dpath);
00050   bool Scrub(VR const &vr);
00051
00052   // 8 Encoding of Coded Entry Data
00053   // https://dicom.nema.org/medical/dicom/current/output/chtml/part03/chapter_8.html
00054   typedef std::tuple<std::string, std::string, std::string> CodedEntryData;
00055
00057   bool ReplaceCodeMeaning(CodedEntryData const &ced);
00058
00060   bool Preserve(DPath const &dpath);
00061
00064   void RemoveAllMissingPrivateCreator(bool remove);
00065
00068   bool RemoveMissingPrivateCreator(Tag const &t);
00069
00071   void RemoveAllGroupLength(bool remove);
00072
00074   void RemoveAllIllegal(bool remove);

```


11.259 gdcmCodec.h File Reference

```

graph TD
    gdcmmCodec_h[gdcmmCodec.h] --> gdcmmAudioCodec_h[gdcmmAudioCodec.h]
    gdcmmCodec_h --> gdcmmImageCodec_h[gdcmmImageCodec.h]
    gdcmmCodec_h --> gdcmmPGFCodec_h[gdcmmPGFCodec.h]
    gdcmmImageCodec_h --> gdcmmKAKADICodec_h[gdcmmKAKADICodec.h]
    gdcmmImageCodec_h --> gdcmmPGCCodec_h[gdcmmPGCCodec.h]
    gdcmmImageCodec_h --> gdcmmPVMCodec_h[gdcmmPVMCodec.h]
    gdcmmImageCodec_h --> gdcmmPVPGCodec_h[gdcmmPVPGCodec.h]
    gdcmmImageCodec_h --> gdcmmRAWCodec_h[gdcmmRAWCodec.h]
    gdcmmImageCodec_h --> gdcmmFILECodec_h[gdcmmFILECodec.h]
    gdcmmKAKADICodec_h --> gdcmmJPEGCodec_h[gdcmmJPEGCodec.h]
    gdcmmKAKADICodec_h --> gdcmmJPEG2000Codec_h[gdcmmJPEG2000Codec.h]
    gdcmmKAKADICodec_h --> gdcmmJPEG18Codec_h[gdcmmJPEG18Codec.h]
    gdcmmKAKADICodec_h --> gdcmmJPEG12Codec_h[gdcmmJPEG12Codec.h]
    gdcmmJPEG18Codec_h --> gdcmmJPEG12Codec_h
    gdcmmJPEG12Codec_h --> gdcmmJ2KCodec_h[gdcmmJ2KCodec.h]
    gdcmmJ2KCodec_h --> gdcmmJ2KCodec_h
    gdcmmJ2KCodec_h --> gdcmmJ2KCodec_h
  
```

Classes

- class [gdcm::Codec](#)
Codec class.

Namespaces

- namespace [gdcm](#)

11.260 gdcmCodec.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013   =====*/
00014 #ifndef GDCMCODEC_H
00015 #define GDCMCODEC_H
00016
00017 #include "gdcmCoder.h"
00018 #include "gdcmDecoder.h"
00019
00020 namespace gdcm
00021 {
00022
00026   class GDCM_EXPORT Codec : public Coder, public Decoder
00027   {
00028   };
00029
00030 } // end namespace gdcm
00031
00032 #endif //GDCMCODEC_H

```

11.261 gdcmCoder.h File Reference

```

#include "gdcmTypes.h"
#include "gdcmDataElement.h"

```

[illegible]

- class `gdcm::Coder`
Coder.

- namespace **gdcm**

[Go to the documentation of this file.](#)

```
00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcml.sourceforge.net/Copyright.html for details.
```

```

00008
00009     This software is distributed WITHOUT ANY WARRANTY; without even
00010     the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011     PURPOSE. See the above copyright notice for more information.
00012
00013     =====*/
00014 #ifndef GDCMCODER_H
00015 #define GDCMCODER_H
00016
00017 #include "gdcmTypes.h"
00018 #include "gdcmDataElement.h" // FIXME
00019
00020 namespace gdcm
00021 {
00022
00023 class TransferSyntax;
00024 class DataElement;
00028 class GDCM_EXPORT Coder
00029 {
00030 public:
00031     virtual ~Coder() = default;
00032
00033     virtual bool CanCode(TransferSyntax const &) const = 0;
00035
00036     // Note: in / out are reserved keyword in C#. Change to in_ / out_
00037
00038     virtual bool Code(DataElement const &in_, DataElement &out_) { (void)in_; (void)out_; return false; }
00040 protected:
00041     virtual bool InternalCode(const char *bv, unsigned long len, std::ostream &os) {
00042         (void)bv; (void)os; (void)len; return false; }
00043 };
00044 } // end namespace gdcm
00045
00046 #endif //GDCMCODER_H

```

11.263 gdcmConstCharWrapper.h File Reference

Classes

- class [gdcm::ConstCharWrapper](#)

Do not use me.

Namespaces

- namespace [gdcm](#)

11.264 gdcmConstCharWrapper.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003     Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005     Copyright (c) 2006-2011 Mathieu Malaterre
00006     All rights reserved.
00007     See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009     This software is distributed WITHOUT ANY WARRANTY; without even
00010     the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011     PURPOSE. See the above copyright notice for more information.
00012
00013     =====*/

```

```

00014 #ifndef GDCMCONSTCHARWRAPPER_H
00015 #define GDCMCONSTCHARWRAPPER_H
00016
00017 namespace gdcm
00018 {
00019
00020 #error
00021
00022 /*
00023  * This class is a pure hack. Its only goal is to work around a bad bug in :
00024  * $ swig -version
00025  * SWIG Version 1.3.31
00026  *
00027  * See
00028  * -
00029  * http://sourceforge.net/mailarchive/forum.php?thread_name=bf0c3b3f0802290552y5163989t76572b80a044ce28%40mail.gmail.com&forum=
00030  * As a side note there is also a problem with const reference to enum type:
00031  * -
00032  * http://sourceforge.net/mailarchive/forum.php?thread_name=bf0c3b3f0802290552y5163989t76572b80a044ce28%40mail.gmail.com&forum=
00033  * And to keep track of an issue with swig here is the last one:
00034  *
00035  * -
00036  * http://sourceforge.net/mailarchive/forum.php?thread_name=bf0c3b3f0802290552y5163989t76572b80a044ce28%40mail.gmail.com&forum=
00037  */
00038
00042 class ConstCharWrapper
00043 {
00044 public:
00045     ConstCharWrapper(const char *i=0):Internal(i) {}
00046     operator const char * () const { return Internal; }
00047 private:
00048     const char *Internal;
00049 };
00050
00051 } // end namespace gdcm
00052
00053 #endif //GDCMCONSTCHARWRAPPER_H

```


11.265 gdcmCurve.h File Reference

```

#include "gdcmTypes.h"
#include "gdcmObject.h"
#include <vector>

```

Include dependency graph for gdcmCurve.h:




```

00047 void GetAsPoints(float *array) const;
00048
00049 static unsigned int GetNumberOfCurves(DataSet const & ds);
00050
00051 // Update curve data from dataelement de:
00052 void Update(const DataElement & de);
00053
00054 void SetGroup(unsigned short group);
00055 unsigned short GetGroup() const;
00056 void SetDimensions(unsigned short dimensions);
00057 unsigned short GetDimensions() const;
00058 void SetNumberOfPoints(unsigned short numberofpoints);
00059 unsigned short GetNumberOfPoints() const;
00060 void SetTypeOfData(const char *typeofdata);
00061 const char *GetTypeOfData() const;
00062 // See PS 3.3 - 2004 - C.10.2.1.1 Type of data
00063 const char *GetTypeOfDataDescription() const;
00064 void SetCurveDescription(const char *curvedescription);
00065 void SetDataValueRepresentation(unsigned short datavaluerepresentation);
00066 unsigned short GetDataValueRepresentation() const;
00067 void SetCurveDataDescriptor(const uint16_t * values, size_t num);
00068 std::vector<unsigned short> const &GetCurveDataDescriptor() const;
00069 void SetCoordinateStartValue( unsigned short v );
00070 void SetCoordinateStepValue( unsigned short v );
00071
00072 void SetCurve(const char *array, unsigned int length);
00073
00074 bool IsEmpty() const;
00075
00076 void Decode(std::istream &is, std::ostream &os);
00077
00078 Curve(Curve const &ov);
00079 private:
00080 double ComputeValueFromStartAndStep(unsigned int idx) const;
00081 CurveInternal *Internal;
00082 };
00083
00084 } // end namespace gdcm
00085
00086 #endif //GDCMCURVE_H


```

11.267 gdcmDataSetHelper.h File Reference

```
#include "gdcmTypes.h"
```

```
#include "gdcmVR.h"
```

Include dependency graph for gdcmDataSetHelper.h:



Classes

- class [gdcm::DataSetHelper](#)
[DataSetHelper](#) (internal class, not intended for user level)

Namespaces

- namespace [gdcm](#)

11.268 gdcmDataSetHelper.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013   =====*/
00014 #ifndef GDCMDATASETHELPER_H
00015 #define GDCMDATASETHELPER_H
00016
00017 #include "gdcmTypes.h"
00018 #include "gdcmVR.h"
00019
00020 namespace gdcm
00021 {
00022   class DataSet;
00023   class File;
00024   class Tag;
00025   class SequenceOfItems;
00026
00030   class GDCM_EXPORT DataSetHelper
00031   {
00032   public:
00035     static VR ComputeVR(File const & file, DataSet const &ds, const Tag& tag);
00036
00037     //static SequenceOfItems* ComputeSQFromByteValue(File const & file, DataSet const &ds, const Tag &tag);
00038
00039   protected:
00040   };
00041
00042 } // end namespace gdcm
00043
00044 #endif // GDCMDATASETHELPER_H

```

11.269 gdcmDecoder.h File Reference

```

#include "gdcmTypes.h"
#include "gdcmDataElement.h"

```


Namespaces

- namespace [gdcm](#)

11.272 gdcmDeltaEncodingCodec.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMDELTAENCODINGCODEC_H
00015 #define GDCMDELTAENCODINGCODEC_H
00016
00017 #include "gdcmImageCodec.h"
00018 #error do not use
00019
00020 namespace gdcm
00021 {
00022
00023   class DeltaEncodingCodec : public ImageCodec
00024   {
00025   public:
00026     DeltaEncodingCodec();
00027     ~DeltaEncodingCodec();
00028     bool CanDecode(TransferSyntax const &ts);
00029     bool Decode(DataElement const &is, DataElement &os);
00030   protected:
00031     bool Decode(std::istream &is, std::ostream &os);
00032   };
00033
00034 } // end namespace gdcm
00035
00036 #endif //GDCMDELTAENCODINGCODEC_H

```

11.273 gdcmDICOMDIR.h File Reference

```

#include <utility>
#include "gdcmFileSet.h"

```



```

00029 public:
00030     DICOMDIR() = default;
00031     DICOMDIR(FileSet fs) : _FS(std::move(std::move(fs))) {}
00032
00033 private:
00034     FileSet _FS;
00035     //13 sept 2010 mmr-- added the underscore to FS to compile under Sunos gcc
00036 };
00037
00038 } // end namespace gdcm
00039
00040 #endif //GDCMDICOMDIR_H

```


11.275 gdcmDICOMDIRGenerator.h File Reference

```

#include "gdcmDirectory.h"
#include "gdcmTag.h"
#include <utility>

```

Include dependency graph for gdcmDICOMDIRGenerator.h:



Classes

- class [gdcm::DICOMDIRGenerator](#)
DICOMDIRGenerator class.

Namespaces

- namespace [gdcm](#)

11.276 gdcmDICOMDIRGenerator.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003     Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005     Copyright (c) 2006-2011 Mathieu Malaterre
00006     All rights reserved.
00007     See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009     This software is distributed WITHOUT ANY WARRANTY; without even
00010     the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011     PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMDICOMDIRGENERATOR_H
00015 #define GDCMDICOMDIRGENERATOR_H
00016
00017 #include "gdcmDirectory.h"
00018 #include "gdcmTag.h"
00019 #include <utility> // std::pair
00020
00021 namespace gdcm
00022 {
00023     class File;
00024     class Scanner;
00025     class SequenceOfItems;
00026     class VL;
00027     class DICOMDIRGeneratorInternal;
00028
00029     class GDCM_EXPORT DICOMDIRGenerator
00030     {
00031     public:
00032         typedef Directory::FileNamesType FileNamesType;
00033         typedef Directory::FilenameType FilenameType;
00034         DICOMDIRGenerator();
00035         ~DICOMDIRGenerator();
00036
00037         void SetFileNames( FileNamesType const & fns );
00038
00039         void SetRootDirectory( FilenameType const & root );
00040
00041         void SetDescriptor( const char *d );
00042
00043         bool Generate();
00044
00045         void SetFile(const File& f);
00046         File &GetFile();
00047
00048     protected:
00049         Scanner &GetScanner();
00050         bool AddPatientDirectoryRecord();
00051         bool AddStudyDirectoryRecord();
00052         bool AddSeriesDirectoryRecord();
00053         bool AddImageDirectoryRecord();
00054
00055     private:
00056         const char *ComputeFileID(const char *);
00057         bool TraverseDirectoryRecords(VL start );
00058         bool ComputeDirectoryRecordsOffset(const SequenceOfItems *sqi, VL start);
00059         size_t FindNextDirectoryRecord( size_t item1, const char *directorytype );
00060         SequenceOfItems *GetDirectoryRecordSequence();
00061         size_t FindLowerLevelDirectoryRecord( size_t item1, const char *directorytype );
00062         typedef std::pair< std::string, Tag> MyPair;
00063         MyPair GetReferenceValueForDirectoryType(size_t item);
00064         bool SeriesBelongToStudy(const char *seriesuid, const char *studyuid);
00065         bool ImageBelongToSeries(const char *sopuid, const char *seriesuid, Tag const &t1, Tag const &t2);
00066         bool ImageBelongToSameSeries(const char *sopuid, const char *seriesuid, Tag const &t);
00067
00068         DICOMDIRGeneratorInternal * Internals;
00069     };
00070
00071 } // end namespace gdcm
00072
00073 #endif //GDCMDICOMDIRGENERATOR_H

```



```


00019 namespace gdc
00020 {
00021
00025 // It's a sink there is no output
00026 class GDCM_EXPORT DictPrinter : public Printer
00027 {
00028 public:
00029     DictPrinter();
00030     ~DictPrinter() = default;
00031
00032     void Print(std::ostream& os);
00033
00034 protected:
00035     void PrintDataElement2(std::ostream& os, const DataSet &ds, const DataElement &ide);
00036     void PrintDataSet2(std::ostream& os, const DataSet &ds);
00037 };
00038
00039 } // end namespace gdc
00040
00041 #endif //GDCMDICTPRINTER_H

```

11.279 gdcDirectionCosines.h File Reference

```
#include "gdcTypes.h"
```

Include dependency graph for gdcDirectionCosines.h:



Classes

- class `gdc::DirectionCosines`
class to handle *DirectionCosines*

Namespaces

- namespace `gdc`

11.280 gdcmDirectionCosines.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMDIRECTIONCOSINES_H
00015 #define GDCMDIRECTIONCOSINES_H
00016
00017 #include "gdcmTypes.h"
00018
00019 namespace gdcm
00020 {
00021
00022     class GDCM_EXPORT DirectionCosines
00023     {
00024     public:
00025         DirectionCosines();
00026         DirectionCosines(const double dircos[6]);
00027         // Cannot get the following signature to be wrapped with swig...
00028         //DirectionCosines(const double *dircos = 0 );
00029         ~DirectionCosines() = default;
00030
00031         void Print(std::ostream &) const;
00032
00033         void Cross(double z[3]) const;
00034
00035         double Dot() const;
00036
00037         static double Dot(const double x[3], const double y[3]);
00038
00039         void Normalize();
00040
00041         static void Normalize(double v[3]);
00042
00043         static double Norm(const double v[3]);
00044
00045         operator const double* () const { return Values; }
00046
00047         bool IsValid() const;
00048
00049         bool SetFromString(const char *str);
00050
00051         double CrossDot(DirectionCosines const &dc) const;
00052
00053         double ComputeDistAlongNormal(const double ipp[3]) const;
00054
00055     private:
00056         double Values[6];
00057     };
00058 } // end namespace gdcm
00059
00060 #endif //GDCMDIRECTIONCOSINES_H

```


11.281 gdcmDirectoryHelper.h File Reference

```

#include "gdcmDirectory.h"
#include "gdcmDataSet.h"

```

Include dependency graph for `gdcmDirectoryHelper.h`:



Classes

- class `gdcm::DirectoryHelper`
DirectoryHelper.

Namespaces

- namespace `gdcm`

11.282 gdcmDirectoryHelper.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013   =====*/
00014
00015 #include "gdcmDirectory.h"
00016 #include "gdcmDataSet.h"
00017
00018 namespace gdcm
00019 {
00020
00035 class GDCM_EXPORT DirectoryHelper
00036 {
00037 public:
00038   //returns all series UUIDs in a given directory that match a particular SOP Instance UID
00039   static Directory::FileNamesType GetSeriesUUIDsBySOPClassUID(const std::string& inDirectory,
00040     const std::string& inSOPClassUID);
00041

```

```

00042 //specific implementations of the SOPClassUID grabber, so you don't have to
00043 //remember the SOP Class UUIDs of CT or MR images.
00044 static Directory::FileNamesType GetCTImageSeriesUIDs(const std::string& inDirectory);
00045 static Directory::FileNamesType GetMRImageSeriesUIDs(const std::string& inDirectory);
00046 static Directory::FileNamesType GetRTStructSeriesUIDs(const std::string& inDirectory);
00047
00048 //given a directory and a series UID, provide all filenames with that series UID.
00049 static Directory::FileNamesType GetFilenamesFromSeriesUIDs(const std::string& inDirectory,
00050   const std::string& inSeriesUID);
00051
00052 //given a series UID, load all the images associated with that series UID
00053 //these images will be IPP sorted, so that they can be used for gathering all
00054 //the necessary information for generating an RTStruct
00055 //this function should be called by the writer once, if the writer's dataset
00056 //vector is empty. Make sure to have a new writer for new rtstructs.
00057 static std::vector<DataSet> LoadImageFromFiles(const std::string& inDirectory,
00058   const std::string& inSeriesUID);
00059
00060 //When writing RTStructs, each contour will have z position defined.
00061 //use that z position to determine the SOPInstanceUID for that plane.
00062 static std::string RetrieveSOPInstanceUIDFromZPosition(double inZPos,
00063   const std::vector<DataSet>& inDS);
00064
00065 //When writing RTStructs, the frame of reference is done by planes to start with
00066 static std::string RetrieveSOPInstanceUIDFromIndex(int inIndex,
00067   const std::vector<DataSet>& inDS);
00068
00069 //each plane needs to know the SOPClassUID, and that won't change from image to image
00070 //so, retrieve this once at the start of writing.
00071 static std::string GetSOPClassUID(const std::vector<DataSet>& inDS);
00072
00073 //retrieve the frame of reference from the set of datasets
00074 static std::string GetFrameOfReference(const std::vector<DataSet>& inDS);
00075
00076 //both the image and polydata readers use these functions to get std::strings
00077 static std::string GetStringValueFromTag(const Tag& t, const DataSet& ds);
00078 };
00079
00080 }


```

11.283 gdcmDPath.h File Reference


```
#include "gdcmTag.h"
```

```
#include <string>
```

Include dependency graph for gdcmDPath.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcml::DPath](#)

class to handle a DICOM path While supp 118 did introduced a notion of XPath for XML Native model this convention is too XML-centric. Instead prefer DCMTK style notation <https://groups.google.com/g/comp.protocols.dicom/c/IyIH0IOBMPA>

Namespaces

- namespace [gdcml](#)

Functions

- `std::ostream & gdcml::operator<< (std::ostream &os, const DPath &val)`

11.284 gdcmlDPath.h

[Go to the documentation of this file.](#)


```

00001  /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcml.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013  =====*/
00014  #ifndef GDCMLDPATH_H
00015  #define GDCMLDPATH_H
00016
00017  #include "gdcmlTag.h"
00018  #include <string>
00019

```

11.285 gdcuDumper.h File Reference

Include dependency graph for gdcuDumper.h:



- class `gdcm::Dumper`
Codec class.

Namespaces

- namespace `gdcm`

11.286 `gdcmDumper.h`


[Go to the documentation of this file.](#)

```
00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012 =====*/
00013 #ifndef GDCMDUMPER_H
00014 #define GDCMDUMPER_H
00015
00016 #include "gdcmPrinter.h"
00017
00018 namespace gdcm
00019 {
00020
00021 // It's a sink there is no output
00022 class GDCM_EXPORT Dumper : public Printer
00023 {
00024 public:
00025     Dumper() { PrintStyle = CONDENSED_STYLE; }
00026     ~Dumper() = default;
00027 };
00028
00029 } // end namespace gdcm
00030
00031 #endif //GDCMDUMPER_H
```

11.287 gdcmEmptyMaskGenerator.h File Reference

```
#include "gdcmSubject.h"
```

Include dependency graph for gdcmEmptyMaskGenerator.h:



Classes

- class [gdcm::EmptyMaskGenerator](#)

[EmptyMaskGenerator](#) Main class to generate a [Empty Mask Series](#) from an input [Series](#). This class takes an input folder and generates a series of DICOM files in the specified output directory. This class handles multiples DICOM [Series](#) within the same input directory.

Namespaces

- namespace [gdcm](#)

11.288 gdcmEmptyMaskGenerator.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003 Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005 Copyright (c) 2006-2011 Mathieu Malaterre
00006 All rights reserved.
00007 See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009 This software is distributed WITHOUT ANY WARRANTY; without even
00010 the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011 PURPOSE. See the above copyright notice for more information.

```


Namespaces

- namespace `gdcm`

11.290 gdcmEncapsulatedDocument.h

[Go to the documentation of this file.](#)

```


00001  /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013  =====*/
00014  #ifndef GDCMENCAPSULATEDDOCUMENT_H
00015  #define GDCMENCAPSULATEDDOCUMENT_H
00016
00017  #include "gdcmFile.h"
00018
00019  namespace gdcm
00020  {
00024  class GDCM_EXPORT EncapsulatedDocument
00025  {
00026  public:
00027      EncapsulatedDocument() = default;
00028
00029  private:
00030  };
00031
00032  } // end namespace gdcm
00033
00034  #endif //GDCMENCAPSULATEDDOCUMENT_H

```

11.291 gdcmEquipmentManufacturer.h File Reference

```
#include "gdcmTypes.h"
```

Include dependency graph for `gdcmEquipmentManufacturer.h`:



Classes

- class [gdcm::EquipmentManufacturer](#)

Namespaces

- namespace [gdcm](#)

11.292 gdcmEquipmentManufacturer.h

[Go to the documentation of this file.](#)

```

00001  /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013  =====*/
00014  #ifndef GDCMEQUIPMENTMANUFACTURER_H
00015  #define GDCMEQUIPMENTMANUFACTURER_H
00016
00017  #include "gdcmTypes.h"
00018
00019  namespace gdcm {
00020
00021  class DataSet;
00022  class GDCM_EXPORT EquipmentManufacturer {
00023  public:
00024      typedef enum {
00025          UNKNOWN = 0,
00026          AGFA,
00027          FUJI,
00028          GEMS,
00029          HITACHI,
00030          KODAK,
00031          MARCONI,
00032          PMS,
00033          SAMSUNG,
00034          SIEMENS,
00035          TOSHIBA,
00036          UIH
00037      } Type;
00038
00039      static Type Compute(DataSet const &ds);
00040
00041      static const char *TypeToString(Type type);
00042
00043  private:
00044      static EquipmentManufacturer::Type GuessFromPrivateAttributes(
00045          DataSet const &ds);
00046  };
00047  } // end namespace gdcm
00048
00049  #endif // GDCMEQUIPMENTMANUFACTURER_H

```



```

00025 {
00026 public:
00027     Fiducials() = default;
00028
00029 private:
00030 };
00031
00032 } // end namespace gdc
00033
00034 #endif //GDCMFIDUCIALS_H

```


11.295 gdcFileAnonymizer.h File Reference

```

#include "gdcSubject.h"
#include "gdcEvent.h"
#include "gdcTag.h"
#include "gdcVL.h"

```

Include dependency graph for gdcFileAnonymizer.h:



Classes

- class [gdc::FileAnonymizer](#)
FileAnonymizer.

Namespaces

- namespace [gdc](#)

11.296 gdcmFileAnonymizer.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMFILEANONYMIZER_H
00015 #define GDCMFILEANONYMIZER_H
00016
00017 #include "gdcmSubject.h"
00018 #include "gdcmEvent.h"
00019 #include "gdcmTag.h"
00020 #include "gdcmVL.h"
00021
00022 namespace gdcm
00023 {
00024   class FileAnonymizerInternals;
00025
00047   class GDCM_EXPORT FileAnonymizer : public Subject
00048   {
00049   public:
00050     FileAnonymizer();
00051     ~FileAnonymizer() override;
00052
00055     void Empty( Tag const &t );
00056
00058     void Remove( Tag const &t );
00059
00063     void Replace( Tag const &t, const char *value_str );
00064
00067     void Replace( Tag const &t, const char *value_data, VL const &vl );
00068
00070     void SetInputFileName(const char *filename_native);
00071
00073     void SetOutputFileName(const char *filename_native);
00074
00076     bool Write();
00077
00078   private:
00079     bool ComputeEmptyTagPosition();
00080     bool ComputeRemoveTagPosition();
00081     bool ComputeReplaceTagPosition();
00082     FileAnonymizerInternals *Internals;
00083   };
00084
00085 } // end namespace gdcm
00086
00087 #endif //GDCMFILEANONYMIZER_H

```


11.297 gdcmFileChangeTransferSyntax.h File Reference

```

#include "gdcmSubject.h"
#include "gdcmSmartPointer.h"

```

Include dependency graph for `gdcmFileChangeTransferSyntax.h`:



Classes

- class [gdcm::FileChangeTransferSyntax](#)
FileChangeTransferSyntax.

Namespaces

- namespace [gdcm](#)

11.298 gdcmFileChangeTransferSyntax.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012   =====*/
00013
00014 #ifndef GDCMFILECHANGETRANSFERSYNTAX_H
00015 #define GDCMFILECHANGETRANSFERSYNTAX_H
00016
00017 #include "gdcmSubject.h"
00018 #include "gdcmSmartPointer.h"
00019

```

11.299 gdcmFileDecompressLookupTable.h File Reference

- class `gdcm::FileDecompressLookupTable`
FileDecompressLookupTable class.

Namespaces

- namespace `gdcm`

11.300 `gdcmFileDecompressLookupTable.h`

[Go to the documentation of this file.](#)

```


00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMFILEDECOMPRESSLOOKUPTABLE_H
00015 #define GDCMFILEDECOMPRESSLOOKUPTABLE_H
00016
00017 #include "gdcmSubject.h"
00018 #include "gdcmFile.h"
00019 #include "gdcmPixmap.h"
00020
00021 namespace gdcm
00022 {
00023
00024   class DataElement;
00030   class GDCM_EXPORT FileDecompressLookupTable : public Subject
00031   {
00032   public:
00033     FileDecompressLookupTable() = default;
00034     ~FileDecompressLookupTable() override = default;
00035
00037     bool Change();
00038
00040     void SetFile(const File& f) { F = f; }
00041     File &GetFile() { return *F; }
00042
00043     const Pixmap& GetPixmap() const { return *PixelData; }
00044     Pixmap& GetPixmap() { return *PixelData; }
00045     void SetPixmap(Pixmap const &img) { PixelData = img; }
00046
00047   protected:
00048
00049   private:
00050     SmartPointer<File> F;
00051     SmartPointer<Pixmap> PixelData;
00052   };
00053
00054 } // end namespace gdcm
00055
00056 #endif //GDCMFILEDECOMPRESSLOOKUPTABLE_H

```


11.301 gdcmFileDerivation.h File Reference

```
#include "gdcmFile.h"
```

Include dependency graph for gdcmFileDerivation.h:



Classes

- class [gdcm::FileDerivation](#)
FileDerivation class.

Namespaces

- namespace [gdcm](#)

11.302 gdcmFileDerivation.h

[Go to the documentation of this file.](#)

```
00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013  =====*/
00014 #ifndef GDCMFILEDERIVATION_H
00015 #define GDCMFILEDERIVATION_H
00016
00017 #include "gdcmFile.h"
00018
00019 namespace gdcm
00020 {
00021
```


Classes

- class [gdcm::FileExplicitFilter](#)
FileExplicitFilter class.

Namespaces

- namespace [gdcm](#)

11.304 gdcmFileExplicitFilter.h

[Go to the documentation of this file.](#)

```

00001  /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013  =====*/
00014  #ifndef GDCMFILEEXPLICITFILTER_H
00015  #define GDCMFILEEXPLICITFILTER_H
00016
00017  #include "gdcmFile.h"
00018
00019  namespace gdcm
00020  {
00021  class Dicts;
00022
00038  class GDCM_EXPORT FileExplicitFilter
00039  {
00040  public:
00041      FileExplicitFilter():F(new
00042      File),ChangePrivateTags(false),UseVRUN(true),RecomputeItemLength(false),RecomputeSequenceLength(false) {}
00043      ~FileExplicitFilter() = default;
00044
00045      void SetChangePrivateTags(bool b) { ChangePrivateTags = b;}
00046
00048      void SetUseVRUN(bool b) { UseVRUN = b; }
00049
00051      void SetRecomputeItemLength(bool b);
00052      void SetRecomputeSequenceLength(bool b);
00053
00055
00057      bool Change();
00058
00060      void SetFile(const File& f) { F = f; }
00061      File &GetFile() { return *F; }
00062
00063  protected:
00064      bool ProcessDataSet(DataSet &ds, Dicts const &dicts);
00065      bool ChangeFMI();
00066
00067  private:
00068      SmartPointer<File> F;
00069      bool ChangePrivateTags;
00070      bool UseVRUN;
00071      bool RecomputeItemLength;
00072      bool RecomputeSequenceLength;
00073  };
00074
00075
00076  } // end namespace gdcm
00077
00078  #endif //GDCMFILEEXPLICITFILTER_H


```

11.305 gdcmFileStreamer.h File Reference

```
#include "gdcmSubject.h"
```

```
#include "gdcmSmartPointer.h"
```

Include dependency graph for gdcmFileStreamer.h:



Classes

- class [gdcm::FileStreamer](#)
FileStreamer.

Namespaces

- namespace [gdcm](#)

11.306 gdcmFileStreamer.h

[Go to the documentation of this file.](#)


```

00001  /*=====
00002
00003  Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005  Copyright (c) 2006-2011 Mathieu Malaterre
00006  All rights reserved.
00007  See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009  This software is distributed WITHOUT ANY WARRANTY; without even
00010  the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011  PURPOSE. See the above copyright notice for more information.
00012

```

11.307 gdcmlconImage.h File Reference

Include dependency graph for `gdcmlconImage.h`:




```

00036 ~IconImage();
00037 void Print(std::ostream &) const {}
00038
00040 void SetTransferSyntax(TransferSyntax const &ts) {
00041     TS = ts;
00042 }
00043 const TransferSyntax &GetTransferSyntax() const {
00044     return TS;
00045 }
00046 void SetDataElement(DataElement const &de) {
00047     PixelData = de;
00048 }
00049 const DataElement& GetDataElement() const { return PixelData; }
00050
00051 void SetColumns(unsigned int col) { SetDimension(0,col); }
00052 void SetRows(unsigned int rows) { SetDimension(1,rows); }
00053 void SetDimension(unsigned int idx, unsigned int dim);
00054 int GetColumns() const { return Dimensions[0]; }
00055 int GetRows() const { return Dimensions[1]; }
00056 // Get/Set PixelFormat
00057 const PixelFormat &GetPixelFormat() const
00058 {
00059     return PF;
00060 }
00061 void SetPixelFormat(PixelFormat const &pf)
00062 {
00063     PF = pf;
00064 }
00065
00066 const PhotometricInterpretation &GetPhotometricInterpretation() const;
00067 void SetPhotometricInterpretation(PhotometricInterpretation const &pi);
00068
00069 bool IsEmpty() const { return Dimensions.size() == 0; }
00070 void Clear();
00071
00072 bool GetBuffer(char *buffer) const;
00073
00074 private:
00075     TransferSyntax TS;
00076     PixelFormat PF; // SamplesPerPixel, BitsAllocated, BitsStored, HighBit, PixelRepresentation
00077     PhotometricInterpretation PI;
00078     std::vector<unsigned int> Dimensions; // Col/Row
00079     std::vector<double> Spacing; // PixelAspectRatio ?
00080     DataElement PixelData; // copied from 7fe0,0010
00081     static const unsigned int NumberOfDimensions = 2;
00082 };
00083
00084 } // end namespace gdcm
00085 #endif
00086 #include "gdcmBitmap.h"
00087
00088 namespace gdcm
00089 {
00090     //class GDCM_EXPORT IconImage : public Pixmap {};
00091     typedef Bitmap IconImage;
00092 }
00093
00094 #endif //GDCMICONIMAGE_H

```

11.309 gdcmIconImageFilter.h File Reference


```

#include "gdcmFile.h"
#include "gdcmIconImage.h"

```


11.311 gdcmlconImageGenerator.h File Reference

Include dependency graph for `qdcmlconImageGenerator.h`:



- class `gdcm::IconImageGenerator`
IconImageGenerator.

- namespace **gdcm**

11.312 gdcmlconImageGenerator.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMICONIMAGEGENERATOR_H
00015 #define GDCMICONIMAGEGENERATOR_H
00016
00017 #include "gdcmPixmap.h"
00018 #include "gdcmIconImage.h"
00019
00020 namespace gdcm
00021 {
00022   class IconImageGeneratorInternals;
00041   class GDCM_EXPORT IconImageGenerator
00042   {
00043   public:
00044     IconImageGenerator();
00045     ~IconImageGenerator();
00046
00048     void SetPixmap(const Pixmap& p) { P = p; }
00049     Pixmap &GetPixmap() { return *P; }
00050     const Pixmap &GetPixmap() const { return *P; }
00051
00053     void SetOutputDimensions(const unsigned int dims[2]);
00054
00058     void SetPixelMinMax(double min, double max);
00059
00063     void AutoPixelMinMax(bool b);
00064
00069     void ConvertRGBToPaletteColor(bool b);
00070
00074     void SetOutsideValuePixel(double v);
00075
00077     bool Generate();
00078
00080     const IconImage& GetIconImage() const { return *I; }
00081
00082   protected:
00083
00084   private:
00085     void BuildLUT( Bitmap & bitmap, unsigned int maxcolor );
00086
00087     SmartPointer<Pixmap> P;
00088     SmartPointer<IconImage> I;
00089     IconImageGeneratorInternals *Internals;
00090 };
00091
00092 } // end namespace gdcm
00093
00094 #endif //GDCMICONIMAGEGENERATOR_H

```

11.313 gdcmImage.h File Reference

```

#include "gdcmPixmap.h"
#include <vector>

```


11.314 gdcmImage.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMIMAGE_H
00015 #define GDCMIMAGE_H
00016
00017 #include "gdcmPixmap.h"
00018
00019 #include <vector>
00020
00021 namespace gdcm
00022 {
00023
00024   class GDCM_EXPORT Image : public Pixmap
00025   {
00026   public:
00027     Image () : Spacing(), SC(), Intercept(0), Slope(1) {
00028       //DirectionCosines.resize(6);
00029       Origin.resize( 3 /*NumberOfDimensions*/ ); // fill with 0
00030       DirectionCosines.resize( 6 ); // fill with 0
00031       DirectionCosines[0] = 1;
00032       DirectionCosines[4] = 1;
00033       Spacing.resize( 3 /*NumberOfDimensions*/, 1 ); // fill with 1
00034     }
00035     ~Image() override = default;
00036
00037     const double *GetSpacing() const;
00038     double GetSpacing(unsigned int idx) const;
00039     void SetSpacing(const double spacing[3]);
00040     void SetSpacing(unsigned int idx, double spacing);
00041
00042     const double *GetOrigin() const;
00043     double GetOrigin(unsigned int idx) const;
00044     void SetOrigin(const float origin[3]);
00045     void SetOrigin(const double origin[3]);
00046     void SetOrigin(unsigned int idx, double ori);
00047
00048     const double *GetDirectionCosines() const;
00049     double GetDirectionCosines(unsigned int idx) const;
00050     void SetDirectionCosines(const float dircos[6]);
00051     void SetDirectionCosines(const double dircos[6]);
00052     void SetDirectionCosines(unsigned int idx, double dircos);
00053
00054     void Print(std::ostream &os) const override;
00055
00056     void SetIntercept(double intercept) { Intercept = intercept; }
00057     double GetIntercept() const { return Intercept; }
00058
00059     void SetSlope(double slope) { Slope = slope; }
00060     double GetSlope() const { return Slope; }
00061
00062   private:
00063     std::vector<double> Spacing;
00064     std::vector<double> Origin;
00065     std::vector<double> DirectionCosines;
00066
00067     // I believe the following 3 ivars can be derived from TS ...
00068     SwapCode SC;
00069     double Intercept;
00070     double Slope;
00071   };
00072
00073 } // end namespace gdcm

```

```


00112
00113 #endif //GDCMIMAGE_H

```

11.315 gdcmImageApplyLookupTable.h File Reference

```
#include "gdcmImageToImageFilter.h"
```

Include dependency graph for gdcmImageApplyLookupTable.h:



Classes

- class [gdcm::ImageApplyLookupTable](#)
ImageApplyLookupTable class.

Namespaces

- namespace [gdcm](#)

11.316 gdcmImageApplyLookupTable.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.

```


Namespaces

- namespace [gdcm](#)

Functions

- [template<typename T>](#)
static T [gdcm::Clamp](#) (int v)
- [template<typename T>](#)
static int [gdcm::Round](#) (T x)

11.318 gdcmImageChangePhotometricInterpretation.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003     Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005     Copyright (c) 2006-2011 Mathieu Malaterre
00006     All rights reserved.
00007     See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009     This software is distributed WITHOUT ANY WARRANTY; without even
00010     the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011     PURPOSE. See the above copyright notice for more information.
00012
00013     =====*/
00014 #ifndef GDCMIMAGECHANGEPHOTOMETRICINTERPRETATION_H
00015 #define GDCMIMAGECHANGEPHOTOMETRICINTERPRETATION_H
00016
00017 #include "gdcmImageToImageFilter.h"
00018 #include "gdcmPhotometricInterpretation.h"
00019 #include <limits>
00020
00021 namespace gdcm
00022 {
00023
00024     class DataElement;
00029     class GDCM_EXPORT ImageChangePhotometricInterpretation : public ImageToImageFilter
00030     {
00031     public:
00032         ImageChangePhotometricInterpretation():PI() {}
00033         ~ImageChangePhotometricInterpretation() = default;
00034
00036         void SetPhotometricInterpretation(PhotometricInterpretation const &pi) { PI = pi; }
00037         const PhotometricInterpretation &GetPhotometricInterpretation() const { return PI; }
00038
00040         bool Change();
00041
00044         template <typename T>
00045         static void RGB2YBR(T ybr[3], const T rgb[3], unsigned short storedbits = 8);
00046         template <typename T>
00047         static void YBR2RGB(T rgb[3], const T ybr[3], unsigned short storedbits = 8);
00048
00049     protected:
00050         bool ChangeMonochrome();
00051         bool ChangeYBR2RGB();
00052         bool ChangeRGB2YBR();
00053
00054     private:
00055         PhotometricInterpretation PI;
00056     };
00057
00058     template <typename T>
00059     static inline int Round(T x)
00060     {
00061         return (int) (x+0.5);
00062     }

```

```


00063
00064 template <typename T>
00065 static inline T Clamp(int v)
00066 {
00067     gdcml_assert( std::numeric_limits<T>::min() == 0 );
00068     return v < 0 ? 0 : (v > std::numeric_limits<T>::max() ? std::numeric_limits<T>::max() : v);
00069 }
00070
00071
00072 template <typename T>
00073 void ImageChangePhotometricInterpretation::RGB2YBR(T ybr[3], const T rgb[3], unsigned short storedbits)
00074 {
00075     // Implementation details, since the equations from:
00076     // http://dicom.nema.org/medical/dicom/current/output/chtml/part03/sect_C.7.6.3.html#sect_C.7.6.3.1.2
00077     // are rounded to the 4th decimal precision, prefer the exact equation from the original document at:
00078     // CCIR Recommendation 601-2, also found in T.871 (Section §7, page 4)
00079     const double R = rgb[0];
00080     const double G = rgb[1];
00081     const double B = rgb[2];
00082     gdcml_assert( storedbits <= sizeof(T) * 8 );
00083     const int halffullscale = 1 « (storedbits - 1);
00084     const int Y = Round( 0.299 * R + 0.587 * G + 0.114 * B );
00085     const int CB = Round((-0.299 * R - 0.587 * G + 0.886 * B)/1.772 + halffullscale);
00086     const int CR = Round(( 0.701 * R - 0.587 * G - 0.114 * B)/1.402 + halffullscale);
00087     ybr[0] = Clamp<T>(Y);
00088     ybr[1] = Clamp<T>(CB);
00089     ybr[2] = Clamp<T>(CR);
00090 }
00091
00092 template <typename T>
00093 void ImageChangePhotometricInterpretation::YBR2RGB(T rgb[3], const T ybr[3], unsigned short storedbits)
00094 {
00095     const double Y = ybr[0];
00096     const double Cb = ybr[1];
00097     const double Cr = ybr[2];
00098     gdcml_assert( storedbits <= sizeof(T) * 8 );
00099     const int halffullscale = 1 « (storedbits - 1);
00100     const int R = Round(Y
                                + 1.402 * (Cr-halffullscale)
                                );
00101     const int G = Round(Y -( 0.114 * 1.772 * (Cb-halffullscale) + 0.299 * 1.402 *
                                (Cr-halffullscale))/0.587);
00102     const int B = Round(Y
                                + 1.772 * (Cb-halffullscale)
                                );
00103     rgb[0] = Clamp<T>(R);
00104     rgb[1] = Clamp<T>(G);
00105     rgb[2] = Clamp<T>(B);
00106 }
00107
00108 } // end namespace gdcml
00109
00110 #endif //GDCMIMAGECHANGEPHOTOMETRICINTERPRETATION_H

```


11.319 gdcmImageChangePlanarConfiguration.h File Reference

```
#include "gdcmImageToImageFilter.h"
```

Include dependency graph for gdcmImageChangePlanarConfiguration.h:



Classes

- class [gdcm::ImageChangePlanarConfiguration](#)
ImageChangePlanarConfiguration class.

Namespaces

- namespace [gdcm](#)

11.320 gdcmImageChangePlanarConfiguration.h

[Go to the documentation of this file.](#)

```
00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013   =====*/
00014 #ifndef GDCMIMAGECHANGEPLANARCONFIGURATION_H
00015 #define GDCMIMAGECHANGEPLANARCONFIGURATION_H
00016
00017 #include "gdcmImageToImageFilter.h"
```

```

00018
00019 namespace gdcm
00020 {
00021
00022 class DataElement;
00028 class GDCM_EXPORT ImageChangePlanarConfiguration : public ImageToImageFilter
00029 {
00030 public:
00031   ImageChangePlanarConfiguration():PlanarConfiguration(0) {}
00032   ~ImageChangePlanarConfiguration() = default;
00033
00035   void SetPlanarConfiguration(unsigned int pc) { PlanarConfiguration = pc; }
00036   unsigned int GetPlanarConfiguration() const { return PlanarConfiguration; }
00037
00040   template <typename T>
00041   static size_t RGBPlanesToRGBPixels(T *out, const T *r, const T *g, const T *b, size_t s);
00042
00046   template <typename T>
00047   static size_t RGBPixelsToRGBPlanes(T *r, T *g, T *b, const T *rgb, size_t s);
00048
00050   bool Change();
00051
00052 protected:
00053
00054 private:
00055   unsigned int PlanarConfiguration;
00056 };
00057
00058 template <typename T>
00059 size_t ImageChangePlanarConfiguration::RGBPlanesToRGBPixels(T *out, const T *r, const T *g, const T *b,
size_t s)
00060 {
00061   T *pout = out;
00062   for(size_t i = 0; i < s; ++i )
00063   {
00064     *pout++ = *r++;
00065     *pout++ = *g++;
00066     *pout++ = *b++;
00067   }
00068
00069   gdcm_assert( (size_t)(pout - out) == 3 * s );
00070   return pout - out;
00071 }
00072
00073 template <typename T>
00074 size_t ImageChangePlanarConfiguration::RGBPixelsToRGBPlanes(T *r, T *g, T *b, const T *rgb, size_t s)
00075 {
00076   const T *prgb = rgb;
00077   for(size_t i = 0; i < s; ++i )
00078   {
00079     *r++ = *prgb++;
00080     *g++ = *prgb++;
00081     *b++ = *prgb++;
00082   }
00083   gdcm_assert( (size_t)(prgb - rgb) == 3 * s );
00084   return prgb - rgb;
00085 }
00086
00087
00088 } // end namespace gdcm
00089
00090 #endif //GDCMIMAGECHANGEPLANARCONFIGURATION_H

```

11.321 gdcmImageChangeTransferSyntax.h File Reference

```

#include "gdcmImageToImageFilter.h"
#include "gdcmTransferSyntax.h"

```

[illegible]

- class `gdcm::ImageChangeTransferSyntax`
ImageChangeTransferSyntax class.

- namespace **gdcm**

[Go to the documentation of this file.](#)

```
00001  /*=====*/
00002
00003      Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005      Copyright (c) 2006-2011 Mathieu Malaterre
00006      All rights reserved.
00007      See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009      This software is distributed WITHOUT ANY WARRANTY; without even
00010      the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011      PURPOSE. See the above copyright notice for more information.
00012
00013  =====*/
00014  #ifndef GDCMIMAGECHANGETRANSFERSYNTAX_H
00015  #define GDCMIMAGECHANGETRANSFERSYNTAX_H
00016
00017  #include "gdcmImageToImageFilter.h"
00018  #include "gdcmTransferSyntax.h"
00019
00020  namespace gdcm
00021  {
00022
00023      class DataElement;
00024      class ImageCodec;
```

```

00039 class GDCM_EXPORT ImageChangeTransferSyntax : public ImageToImageFilter
00040 {
00041 public:
00042     ImageChangeTransferSyntax():TS(TransferSyntax::TS_END),Force(false),CompressIconImage(false),UserCodec(nullptr)
00043     {}
00044     ~ImageChangeTransferSyntax() = default;
00045     void SetTransferSyntax(const TransferSyntax &ts) { TS = ts; }
00046     const TransferSyntax &GetTransferSyntax() const { return TS; }
00047     bool Change();
00048     void SetCompressIconImage(bool b) { CompressIconImage = b; }
00049     void SetForce( bool f ) { Force = f; }
00050     void SetUserCodec(ImageCodec *ic) { UserCodec = ic; }
00051 protected:
00052     bool TryJPEGCodec(const DataElement &pixelde, Bitmap const &input, Bitmap &output);
00053     bool TryJPEG2000Codec(const DataElement &pixelde, Bitmap const &input, Bitmap &output);
00054     bool TryJPEGLSCCodec(const DataElement &pixelde, Bitmap const &input, Bitmap &output);
00055     bool TryRAWCodec(const DataElement &pixelde, Bitmap const &input, Bitmap &output);
00056     bool TryRLECodec(const DataElement &pixelde, Bitmap const &input, Bitmap &output);
00057 private:
00058     TransferSyntax TS;
00059     bool Force;
00060     bool CompressIconImage;
00061     ImageCodec *UserCodec;
00062 };
00063 // end namespace gdcmm
00064 #endif //GDCMIMAGECHANGETRANSFERSYNTAX_H

```


11.323 gdcmmImageCodec.h File Reference

```

#include "gdcmmCodec.h"
#include "gdcmmPhotometricInterpretation.h"
#include "gdcmmLookupTable.h"
#include "gdcmmSmartPointer.h"
#include "gdcmmPixelFormat.h"

```

Include dependency graph for gdcmmImageCodec.h:



This graph shows which files directly or indirectly include this file:



Classes

- class `gdcm::ImageCodec`
ImageCodec.

Namespaces

- namespace `gdcm`

11.324 gdcmImageCodec.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013   =====*/
00014 #ifndef GDCMIMAGECODEC_H
00015 #define GDCMIMAGECODEC_H
00016
00017 #include "gdcmCodec.h"
00018 #include "gdcmPhotometricInterpretation.h"
00019 #include "gdcmLookupTable.h"
00020 #include "gdcmSmartPointer.h"
00021 #include "gdcmPixelFormat.h"
00022
00023 namespace gdcm
00024 {
00025
00026     class GDCM_EXPORT ImageCodec : public Codec
00027     {
00028     public:
00029         ImageCodec();
00030         ~ImageCodec() override;
00031         bool CanCode(TransferSyntax const &) const override { return false; }
00032         bool CanDecode(TransferSyntax const &) const override { return false; }
00033         bool Decode(DataElement const &is_, DataElement &os) override;
00034         bool IsLossy() const;
00035         void SetLossyFlag(bool l);
00036         bool GetLossyFlag() const;
00037
00038         virtual bool GetHeaderInfo(std::istream &is_, TransferSyntax &ts);
00039
00040         virtual ImageCodec * Clone() const = 0;
00041     };
00042
00043 }
00044
00045
00046

```

```

00047 protected:
00048     bool DecodeByStreams(std::istream &is_, std::ostream &os) override;
00049     virtual bool IsValid(PhotometricInterpretation const &pi);
00050 public:
00051
00052     unsigned int GetPlanarConfiguration() const
00053     {
00054         return PlanarConfiguration;
00055     }
00056     void SetPlanarConfiguration(unsigned int pc)
00057     {
00058         gdcmm_assert( pc == 0 || pc == 1 );
00059         PlanarConfiguration = pc;
00060     }
00061
00062     PixelFormat &GetPixelFormat()
00063     {
00064         return PF;
00065     }
00066     const PixelFormat &GetPixelFormat() const
00067     {
00068         return PF;
00069     }
00070     virtual void SetPixelFormat(PixelFormat const &pf)
00071     {
00072         PF = pf;
00073     }
00074     const PhotometricInterpretation &GetPhotometricInterpretation() const;
00075     void SetPhotometricInterpretation(PhotometricInterpretation const &pi);
00076
00077     bool GetNeedByteSwap() const
00078     {
00079         return NeedByteSwap;
00080     }
00081     void SetNeedByteSwap(bool b)
00082     {
00083         NeedByteSwap = b;
00084     }
00085     void SetNeedOverlayCleanup(bool b)
00086     {
00087         NeedOverlayCleanup = b;
00088     }
00089     void SetLUT(LookupTable const &lut)
00090     {
00091         LUT = SmartPointer<LookupTable>( const_cast<LookupTable*>(&lut) );
00092     }
00093     const LookupTable &GetLUT() const
00094     {
00095         return *LUT;
00096     }
00097
00098     void SetDimensions(const unsigned int d[3]);
00099     void SetDimensions(const std::vector<unsigned int> &d);
00100     const unsigned int *GetDimensions() const { return Dimensions; }
00101     void SetNumberOfDimensions(unsigned int dim);
00102     unsigned int GetNumberOfDimensions() const;
00103
00104     bool CleanupUnusedBits(char * data, size_t datalen);
00105
00106 protected:
00107     // Streaming (write) API:
00108     friend class FileChangeTransferSyntax;
00109     virtual bool StartEncode( std::ostream & os );
00110     virtual bool IsRowEncoder();
00111     virtual bool IsFrameEncoder();
00112     virtual bool AppendRowEncode( std::ostream & out, const char * data, size_t datalen );
00113     virtual bool AppendFrameEncode( std::ostream & out, const char * data, size_t datalen );
00114     virtual bool StopEncode( std::ostream & os);
00115
00116 protected:
00117     bool RequestPlanarConfiguration;
00118     bool RequestPaddedCompositePixelCode;
00119 //private:
00120     unsigned int PlanarConfiguration;
00121     PhotometricInterpretation PI;
00122     PixelFormat PF;
00123     bool NeedByteSwap;
00124     bool NeedOverlayCleanup;
00125
00126     typedef SmartPointer<LookupTable> LUTPtr;
00127     LUTPtr LUT;

```

```


00134 unsigned int Dimensions[3]; // FIXME
00135 unsigned int NumberOfDimensions;
00136 bool LossyFlag;
00137
00138 bool DoOverlayCleanup(std::istream &is_, std::ostream &os);
00139 bool DoByteSwap(std::istream &is_, std::ostream &os);
00140 bool DoYBR(std::istream &is_, std::ostream &os);
00141 bool DoYBRFull422(std::istream &is_, std::ostream &os);
00142 bool DoPlanarConfiguration(std::istream &is_, std::ostream &os);
00143 bool DoSimpleCopy(std::istream &is_, std::ostream &os);
00144 bool DoPaddedCompositePixelCode(std::istream &is_, std::ostream &os);
00145 bool DoInvertMonochrome(std::istream &is_, std::ostream &os);
00146
00147 //template <typename T>
00148 //bool DoInvertPlanarConfiguration(T *output, const T *input, uint32_t length);
00149 };
00150
00151 } // end namespace gdcm
00152
00153 #endif //GDCMIMAGECODEC_H

```

11.325 gdcmImageConverter.h File Reference

```
#include "gdcmTypes.h"
```

Include dependency graph for gdcmImageConverter.h:



Classes

- class `gdcm::ImageConverter`
Image Converter.

Namespaces

- namespace `gdcm`

11.326 gdcmImageConverter.h


[Go to the documentation of this file.](#)

```
00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014
00015 #ifndef GDCMIMAGECONVERTER_H
00016 #define GDCMIMAGECONVERTER_H
00017
00018 #include "gdcmTypes.h"
00019
00020 namespace gdcm
00021 {
00022
00023   class Image;
00033   class GDCM_EXPORT ImageConverter
00034   {
00035   public:
00036     ImageConverter();
00037     ~ImageConverter();
00038
00039     void SetInput(Image const &input);
00040     const Image& GetOutput() const;
00041
00042     void Convert();
00043
00044   private:
00045     Image *Input;
00046     Image *Output;
00047   };
00048
00049 } // end namespace gdcm
00050
00051 #endif //GDCMIMAGECONVERTER_H
```


11.327 gdcmImageFragmentSplitter.h File Reference

```
#include "gdcmImageToImageFilter.h"
```

Include dependency graph for gdcmImageFragmentSplitter.h:



Classes

- class [gdcm::ImageFragmentSplitter](#)
ImageFragmentSplitter class.

Namespaces

- namespace [gdcm](#)

11.328 gdcmImageFragmentSplitter.h

[Go to the documentation of this file.](#)

```
00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013   =====*/
00014 #ifndef GDCMIMAGEFRAGMENTSPLITTER_H
00015 #define GDCMIMAGEFRAGMENTSPLITTER_H
00016
00017 #include "gdcmImageToImageFilter.h"
```

```

00018
00019 namespace gdcM
00020 {
00021
00022 class DataElement;
00027 class GDCM_EXPORT ImageFragmentSplitter : public ImageToImageFilter
00028 {
00029 public:
00030     ImageFragmentSplitter():FragmentSizeMax(0),Force(false) {}
00031     ~ImageFragmentSplitter() = default;
00032
00034     bool Split();
00035
00037     void SetFragmentSizeMax(unsigned int fragsize);
00038     unsigned int GetFragmentSizeMax() const { return FragmentSizeMax; }
00039
00042     void SetForce( bool f ) { Force = f; }
00043
00044 protected:
00045
00046 private:
00047     unsigned int FragmentSizeMax;
00048     bool Force;
00049 };
00050
00051 } // end namespace gdcM
00052
00053 #endif //GDCMIMAGEFRAGMENTSPLITTER_H

```


11.329 gdcMImageHelper.h File Reference

```

#include "gdcMTypes.h"
#include "gdcMTag.h"
#include <vector>
#include "gdcMPixelFormat.h"
#include "gdcMPhotometricInterpretation.h"
#include "gdcMSmartPointer.h"
#include "gdcMLookupTable.h"

```

Include dependency graph for gdcMImageHelper.h:



Classes

- class [gdcM::ImageHelper](#)

ImageHelper (internal class, not intended for user level)

- struct `gdcm::RealWorldValueMappingContent`

Namespaces

- namespace `gdcm`

11.330 gdcmImageHelper.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003     Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005     Copyright (c) 2006-2011 Mathieu Malaterre
00006     All rights reserved.
00007     See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009     This software is distributed WITHOUT ANY WARRANTY; without even
00010     the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011     PURPOSE. See the above copyright notice for more information.
00012
00013     =====*/
00014 #ifndef GDCMIMAGEHELPER_H
00015 #define GDCMIMAGEHELPER_H
00016
00017 #include "gdcmTypes.h"
00018 #include "gdcmTag.h"
00019 #include <vector>
00020 #include "gdcmPixelFormat.h"
00021 #include "gdcmPhotometricInterpretation.h"
00022 #include "gdcmSmartPointer.h"
00023 #include "gdcmLookupTable.h"
00024
00025 namespace gdcm
00026 {
00027
00028     class MediaStorage;
00029     class DataSet;
00030     class File;
00031     class Image;
00032     class Pixmap;
00033     class ByteValue;
00034
00035     // minimal struct:
00036     struct RealWorldValueMappingContent {
00037         double RealWorldValueIntercept;
00038         double RealWorldValueSlope;
00039         // http://dicom.nema.org/MEDICAL/DICOM/2014c/output/chtml/part16/sect_CID_7181.html
00040         std::string CodeValue;
00041         std::string CodeMeaning;
00042     };
00043
00044     class GDCM_EXPORT ImageHelper
00045     {
00046     public:
00047         static void SetForceRescaleInterceptSlope(bool);
00048         static bool GetForceRescaleInterceptSlope();
00049
00050         static void SetPMSRescaleInterceptSlope(bool);
00051         static bool GetPMSRescaleInterceptSlope();
00052
00053         static void SetForcePixelSpacing(bool);
00054         static bool GetForcePixelSpacing();
00055
00056         static void SetSecondaryCaptureImagePlaneModule(bool);
00057         static bool GetSecondaryCaptureImagePlaneModule();
00058
00059         static std::vector<unsigned int> GetDimensionsValue(const File& f);
00060         static void SetDimensionsValue(File& f, const Pixmap & img);
00061

```

```

00100
00103 static PixelFormat GetPixelFormatValue(const File& f);
00104
00109 static std::vector<double> GetRescaleInterceptSlopeValue(File const & f);
00110 static void SetRescaleInterceptSlopeValue(File & f, const Image & img);
00111
00112 // read only for now
00113 static bool GetRealWorldValueMappingContent(File const & f, RealWorldValueMappingContent & rwvmc);
00114
00116 static std::vector<double> GetOriginValue(File const & f);
00117 static void SetOriginValue(DataSet & ds, const Image & img);
00118
00121 static std::vector<double> GetDirectionCosinesValue(File const & f);
00127 // FIXME: There is a major issue for image with multiple IOP (eg. Enhanced * Image Storage).
00128 static void SetDirectionCosinesValue(DataSet & ds, const std::vector<double> & dircos);
00129
00131 static std::vector<double> GetSpacingValue(File const & f);
00133 static void SetSpacingValue(DataSet & ds, const std::vector<double> & spacing);
00134
00136 static bool ComputeSpacingFromImagePositionPatient(const std::vector<double> & imageposition,
std::vector<double> & spacing);
00137
00138 static bool GetDirectionCosinesFromDataSet(DataSet const & ds, std::vector<double> & dircos);
00139
00140 //functions to get more information from a file
00141 //useful for the stream image reader, which fills in necessary image information
00142 //distinctly from the reader-style data input
00143 static PhotometricInterpretation GetPhotometricInterpretationValue(File const& f);
00144 //returns the configuration of colors in a plane, either RGB RGB RGB or RRR GGG BBB
00145 static unsigned int GetPlanarConfigurationValue(const File& f);
00146
00148 static SmartPointer<LookupTable> GetLUT(File const& f);
00149
00150 // Moved from PixampReader to here. Generally used for photometric interpretation.
00151 static const ByteValue* GetPointerFromElement(Tag const &tag, File const& f);
00152
00154 static MediaStorage ComputeMediaStorageFromModality(const char *modality,
unsigned int dimension = 2, PixelFormat const & pf = PixelFormat(),
PhotometricInterpretation const & pi = PhotometricInterpretation(),
double rescaleintercept = 0, double rescaleslope = 1 );
00158
00159 protected:
00160 static Tag GetSpacingTagFromMediaStorage(MediaStorage const &ms);
00161 static Tag GetZSpacingTagFromMediaStorage(MediaStorage const &ms);
00162
00163 private:
00164 static bool ForceRescaleInterceptSlope;
00165 static bool PMSRescaleInterceptSlope;
00166 static bool ForcePixelSpacing;
00167 static bool SecondaryCaptureImagePlaneModule;
00168 };
00169
00170 } // end namespace gdcmm
00171
00172 #endif // GDCMIMAGEHELPER_H

```

11.331 gdcmmImageReader.h File Reference

```

#include "gdcmmPixmapReader.h"
#include "gdcmmImage.h"

```

```
graph BT; gdcmImageRegionReader.h --> gdcmImageReader.h
```

- class `gdcm::ImageReader`
ImageReader.

- namespace **gdcm**

[Go to the documentation of this file.](#)

Generated by Doxygen

```

00003 Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005 Copyright (c) 2006-2011 Mathieu Malaterre
00006 All rights reserved.
00007 See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009 This software is distributed WITHOUT ANY WARRANTY; without even
00010 the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011 PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMIMAGEREADER_H
00015 #define GDCMIMAGEREADER_H
00016
00017 #include "gdcmPixmapReader.h"
00018 #include "gdcmImage.h"
00019
00020 namespace gdcm
00021 {
00022
00023 class MediaStorage;
00024 class GDCM_EXPORT ImageReader : public PixmapReader
00025 {
00026 public:
00027     ImageReader();
00028     ~ImageReader() override; //needs to be virtual to ensure lack of memory leaks
00029
00030     bool Read() override;
00031
00032     // Following methods are valid only after a call to 'Read'
00033
00034     const Image& GetImage() const;
00035     Image& GetImage();
00036     //void SetImage(Image const &img);
00037
00038 protected:
00039     bool ReadImage(MediaStorage const &ms) override;
00040     bool ReadACRNEMAImage() override;
00041 };
00042
00043 } // end namespace gdcm
00044
00045 #endif //GDCMIMAGEREADER_H

```


11.333 gdcmImageRegionReader.h File Reference

```

#include "gdcmImageReader.h"
#include "gdcmImage.h"
#include "gdcmRegion.h"

```

Include dependency graph for gdcmImageRegionReader.h:



Classes

- class [gdcm::ImageRegionReader](#)
ImageRegionReader.

Namespaces

- namespace [gdcm](#)

11.334 gdcmImageRegionReader.h

[Go to the documentation of this file.](#)

```


00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013   =====*/
00014 #ifndef GDCMIMAGEEXTENTREADER_H
00015 #define GDCMIMAGEEXTENTREADER_H
00016
00017 #include "gdcmImageReader.h"
00018 #include "gdcmImage.h"
00019 #include "gdcmRegion.h"
00020
00021 namespace gdcm
00022 {
00023
00024   class ImageRegionReaderInternals;
00025   class GDCM_EXPORT ImageRegionReader : public ImageReader
00026   {
00027   public:
00028     ImageRegionReader();
00029     ~ImageRegionReader() override;
00030
00031     void SetRegion(const Region & region);
00032     const Region &GetRegion() const;
00033
00034     size_t ComputeBufferLength() const;
00035
00036     bool ReadInformation();
00037
00038     bool ReadIntoBuffer(char *inreadbuffer, size_t buflen);
00039
00040   protected:
00041     bool Read() override;
00042
00043   private:
00044     BoxRegion ComputeBoundingBox();
00045     bool ReadRAWIntoBuffer(char *buffer, size_t buflen);
00046     bool ReadRLEIntoBuffer(char *buffer, size_t buflen);
00047     bool ReadJPEG2000IntoBuffer(char *buffer, size_t buflen);
00048     bool ReadJPEGIntoBuffer(char *buffer, size_t buflen);
00049     bool ReadJPEGLSIntoBuffer(char *buffer, size_t buflen);
00050     ImageRegionReaderInternals *Internals;
00051   };
00052
00053 } // end namespace gdcm
00054
00055 #endif //GDCMIMAGEEXTENTREADER_H

```


11.335 gdcmImageToImageFilter.h File Reference

```
#include "gdcmPixmapToPixmapFilter.h"
```

Include dependency graph for gdcmImageToImageFilter.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::ImageToImageFilter](#)
ImageToImageFilter class.

Namespaces

- namespace [gdcm](#)

11.336 gdcmImageToImageFilter.h

[Go to the documentation of this file.](#)

```
00001  /*=====
00002
00003  Program: GDCM (Grassroots DICOM). A DICOM library
00004
```


11.337 gdcmlImageWriter.h File Reference

- class `gdcm::ImageWriter`
ImageWriter.

Namespaces

- namespace [gdcm](#)

11.338 gdcmImageWriter.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMIMAGEWRITER_H
00015 #define GDCMIMAGEWRITER_H
00016
00017 #include "gdcmPixmapWriter.h"
00018 #include "gdcmImage.h"
00019
00020 namespace gdcm
00021 {
00022
00023   class Image;
00032   class GDCM_EXPORT ImageWriter : public PixmapWriter
00033   {
00034   public:
00035     ImageWriter();
00036     ~ImageWriter() override;
00037
00041     const Image& GetImage() const override { return dynamic_cast<const Image&>(*PixelData); }
00042     Image& GetImage() override { return dynamic_cast<Image&>(*PixelData); } // FIXME
00043     //void SetImage(Image const &img);
00044
00046     bool Write() override; // Execute()
00047
00050     MediaStorage ComputeTargetMediaStorage();
00051   protected:
00052
00053   private:
00054   };
00055
00056 } // end namespace gdcm
00057
00058 #endif //GDCMIMAGEWRITER_H

```

11.339 gdcmIPPSorter.h File Reference


```

#include "gdcmSorter.h"
#include <vector>

```

```
#include <string>
```

Include dependency graph for gdcmlPPSorter.h:



Classes

- class `gdcml::IPPSorter`
IPPSorter.

Namespaces

- namespace `gdcml`

11.340 gdcmlPPSorter.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcml.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013   =====*/
00014 #ifndef GDCMIPPSORTER_H
00015 #define GDCMIPPSORTER_H
00016
00017 #include "gdcmlSorter.h"
00018
00019 #include <vector>
00020 #include <string>

```

```


00021
00022 namespace gdcmm
00023 {
00043 class GDCM_EXPORT IPPSorter : public Sorter
00044 {
00045 public:
00046     IPPSorter();
00047
00048     // FIXME: I do not like public virtual function...
00055     bool Sort(std::vector<std::string> const & filenames) override;
00056
00064     void SetComputeZSpacing(bool b) { ComputeZSpacing = b; }
00068     void SetZSpacingTolerance(double tol) { ZTolerance = tol; }
00069     double GetZSpacingTolerance() const { return ZTolerance; }
00070
00080     void SetDirectionCosinesTolerance(double tol) { DirCosTolerance = tol; }
00081     double GetDirectionCosinesTolerance() const { return DirCosTolerance; }
00082
00086     void SetDropDuplicatePositions(bool b) { DropDuplicatePositions = b; }
00087
00094     double GetZSpacing() const { return ZSpacing; }
00095
00096 protected:
00097     bool ComputeZSpacing;
00098     bool DropDuplicatePositions;
00099     double ZSpacing;
00100     double ZTolerance;
00101     double DirCosTolerance;
00102
00103 private:
00104     GDCM_LEGACY(bool ComputeSpacing(std::vector<std::string> const & filenames))
00105 };
00106
00107
00108 } // end namespace gdcmm
00109
00110 #endif //GDCMIPPSORTER_H

```

11.341 gdcmmJPEG12Codec.h File Reference

#include "gdcmmJPEGCodec.h"

Include dependency graph for gdcmmJPEG12Codec.h:



Classes

- class [gdcm::JPEG12Codec](#)
Class to do JPEG 12bits (lossy & lossless)

Namespaces

- namespace [gdcm](#)

11.342 gdcmJPEG12Codec.h

[Go to the documentation of this file.](#)

```


00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013   =====*/
00014 #ifndef GDCMJPEG12CODEC_H
00015 #define GDCMJPEG12CODEC_H
00016
00017 #include "gdcmJPEGCodec.h"
00018
00019 namespace gdcm
00020 {
00021
00022   class JPEGInternals_12BIT;
00023   class ByteValue;
00028   class JPEG12Codec : public JPEGCodec
00029   {
00030   public:
00031     JPEG12Codec();
00032     ~JPEG12Codec() override;
00033
00034     bool DecodeByStreams(std::istream &is, std::ostream &os) override;
00035     bool InternalCode(const char *input, unsigned long len, std::ostream &os) override;
00036
00037     bool GetHeaderInfo(std::istream &is, TransferSyntax &ts) override;
00038
00039   protected:
00040     bool IsStateSuspension() const override;
00041     bool EncodeBuffer(std::ostream &os, const char *data, size_t datalen) override;
00042
00043   private:
00044     JPEGInternals_12BIT *Internals;
00045   };
00046
00047 } // end namespace gdcm
00048
00049 #endif //GDCMJPEG12CODEC_H

```

11.343 gdcmJPEG16Codec.h File Reference

```
#include "gdcmJPEGCodec.h"
```

Include dependency graph for gdcmJPEG16Codec.h:



Classes

- class [gdcm::JPEG16Codec](#)
Class to do JPEG 16bits (lossless)

Namespaces

- namespace [gdcm](#)

11.344 gdcmJPEG16Codec.h

[Go to the documentation of this file.](#)

```
00001  /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013  =====*/
00014  #ifndef GDCMJPEG16CODEC_H
00015  #define GDCMJPEG16CODEC_H
00016
```

```


00017 #include "gdcmJPEGCodec.h"
00018
00019 namespace gdcm
00020 {
00021
00022 class JPEGInternals_16BIT;
00023 class ByteValue;
00028 class JPEG16Codec : public JPEGCodec
00029 {
00030 public:
00031     JPEG16Codec();
00032     ~JPEG16Codec() override;
00033
00034     bool DecodeByStreams(std::istream &is, std::ostream &os) override;
00035     bool InternalCode(const char *input, unsigned long len, std::ostream &os) override;
00036
00037     bool GetHeaderInfo(std::istream &is, TransferSyntax &ts) override;
00038
00039 protected:
00040     bool IsStateSuspension() const override;
00041     bool EncodeBuffer(std::ostream &os, const char *data, size_t datalen) override;
00042
00043 private:
00044     JPEGInternals_16BIT *Internals;
00045 };
00046
00047 } // end namespace gdcm
00048
00049 #endif //GDCMJPEG16CODEC_H

```

11.345 gdcmJPEG2000Codec.h File Reference

#include "gdcmImageCodec.h"

Include dependency graph for gdcmJPEG2000Codec.h:



Classes

- class [gdcm::JPEG2000Codec](#)
Class to do JPEG 2000.

Namespaces

- namespace [gdcm](#)

11.346 gdcmJPEG2000Codec.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMJPEG2000CODEC_H
00015 #define GDCMJPEG2000CODEC_H
00016
00017 #include "gdcmImageCodec.h"
00018
00019 namespace gdcm
00020 {
00021
00022   class JPEG2000Internals;
00023   class GDCM_EXPORT JPEG2000Codec : public ImageCodec
00024   {
00025   {
00026   friend class ImageRegionReader;
00027   friend class Bitmap;
00028   public:
00029     JPEG2000Codec();
00030     ~JPEG2000Codec() override;
00031
00032     bool CanDecode(TransferSyntax const &ts) const override;
00033     bool CanCode(TransferSyntax const &ts) const override;
00034
00035     bool Decode(DataElement const &is, DataElement &os) override;
00036     bool Code(DataElement const &in, DataElement &out) override;
00037
00038     bool GetHeaderInfo(std::istream &is, TransferSyntax &ts) override;
00039     ImageCodec * Clone() const override;
00040
00041     // JPEG-2000 / OpenJPEG specific way of encoding lossy-ness
00042     // ref: http://www.openjpeg.org/index.php?menu=doc#encoder
00043     void SetRate(unsigned int idx, double rate);
00044     double GetRate(unsigned int idx = 0) const;
00045
00046     void SetQuality(unsigned int idx, double q);
00047     double GetQuality(unsigned int idx = 0) const;
00048
00049     void SetTileSize(unsigned int tx, unsigned int ty);
00050
00051     void SetNumberOfResolutions(unsigned int nres);
00052
00053     void SetNumberOfThreadsForDecompression(int nThreads);
00054
00055     void SetReversible(bool res);
00056     void SetMCT(unsigned int mct);
00057
00058   protected:
00059     bool DecodeExtent(
00060       char *buffer,
00061       unsigned int xmin, unsigned int xmax,
00062       unsigned int ymin, unsigned int ymax,
00063       unsigned int zmin, unsigned int zmax,
00064       std::istream & is
00065     );
00066
00067     bool DecodeByStreams(std::istream &is, std::ostream &os) override;

```



```


00076
00077 bool StartEncode( std::ostream & ) override;
00078 bool IsRowEncoder() override;
00079 bool IsFrameEncoder() override;
00080 bool AppendRowEncode( std::ostream & out, const char * data, size_t datalen ) override;
00081 bool AppendFrameEncode( std::ostream & out, const char * data, size_t datalen ) override;
00082 bool StopEncode( std::ostream & ) override;
00083
00084 private:
00085     std::pair<char *, size_t> DecodeByStreamsCommon(char *dummy_buffer, size_t buf_size);
00086     bool CodeFrameIntoBuffer(char * outdata, size_t outlen, size_t & complen, const char * indata, size_t
inlen );
00087     bool GetHeaderInfo(const char * dummy_buffer, size_t len, TransferSyntax &ts);
00088     JPEG2000Internals *Internals;
00089 };
00090
00091 } // end namespace gdcm
00092
00093 #endif //GDCMJPEG2000CODEC_H

```

11.347 gdcmJPEG8Codec.h File Reference

```
#include "gdcmJPEGCodec.h"
```

Include dependency graph for gdcmJPEG8Codec.h:



Classes

- class [gdcm::JPEG8Codec](#)
Class to do JPEG 8bits (lossy & lossless)

Namespaces

- namespace [gdcm](#)

11.348 gdcmJPEG8Codec.h

[Go to the documentation of this file.](#)

```
00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMJPEG8CODEC_H
00015 #define GDCMJPEG8CODEC_H
00016
00017 #include "gdcmJPEGCodec.h"
00018
00019 namespace gdcm
00020 {
00021
00022   class JPEGInternals_8BIT;
00023   class ByteValue;
00024   class JPEG8Codec : public JPEGCodec
00025   {
00026   public:
00027     JPEG8Codec();
00028     ~JPEG8Codec() override;
00029
00030     bool DecodeByStreams(std::istream &is, std::ostream &os) override;
00031     bool InternalCode(const char *input, unsigned long len, std::ostream &os) override;
00032
00033     bool GetHeaderInfo(std::istream &is, TransferSyntax &ts) override;
00034
00035   protected:
00036     bool IsStateSuspension() const override;
00037     bool EncodeBuffer(std::ostream &os, const char *data, size_t datalen) override;
00038
00039   private:
00040     JPEGInternals_8BIT *Internals;
00041   };
00042
00043 } // end namespace gdcm
00044
00045 #endif //GDCMJPEG8CODEC_H
```


11.350 gdcmJPEGCodec.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013   =====*/
00014 #ifndef GDCMJPEGCODEC_H
00015 #define GDCMJPEGCODEC_H
00016
00017 #include "gdcmImageCodec.h"
00018
00019 namespace gdcm
00020 {
00021
00022   class PixelFormat;
00023   class TransferSyntax;
00024   class GDCM_EXPORT JPEGCodec : public ImageCodec
00025   {
00026   friend class ImageRegionReader;
00027   public:
00028     JPEGCodec();
00029     ~JPEGCodec() override;
00030     bool CanDecode(TransferSyntax const &ts) const override;
00031     bool CanCode(TransferSyntax const &ts) const override;
00032     bool Decode(DataElement const &is, DataElement &os) override;
00033     void SetPixelFormat(PixelFormat const &pf) override;
00034
00035     void ComputeOffsetTable(bool b);
00036
00037     bool Code(DataElement const &in, DataElement &out) override;
00038
00039     bool GetHeaderInfo(std::istream &is, TransferSyntax &ts) override;
00040     ImageCodec * Clone() const override;
00041
00042     //void SetReversible(bool res);
00043
00044     void SetQuality(double q);
00045     double GetQuality() const;
00046
00047     void SetLossless(bool l);
00048     bool GetLossless() const;
00049
00050     virtual bool EncodeBuffer( std::ostream & out,
00051                               const char *inbuffer, size_t inlen);
00052
00053   protected:
00054     bool DecodeExtent(
00055       char *buffer,
00056       unsigned int xmin, unsigned int xmax,
00057       unsigned int ymin, unsigned int ymax,
00058       unsigned int zmin, unsigned int zmax,
00059       std::istream & is
00060     );
00061
00062     bool DecodeByStreams(std::istream &is, std::ostream &os) override;
00063     bool IsValid(PhotometricInterpretation const &pi) override;
00064
00065     bool StartEncode( std::ostream & ) override;
00066     bool IsRowEncoder() override;
00067     bool IsFrameEncoder() override;
00068     bool AppendRowEncode( std::ostream & out, const char * data, size_t datalen ) override;
00069     bool AppendFrameEncode( std::ostream & out, const char * data, size_t datalen ) override;
00070     bool StopEncode( std::ostream & ) override;
00071
00072   protected:
00073     // Internal method called by SetPixelFormat
00074     // Instantiate the right jpeg codec (8, 12 or 16)
00075     void SetBitSample(int bit);

```

```


00094
00095     virtual bool IsStateSuspension() const;
00096
00097 protected:
00098     int BitSample;
00099     //bool Lossless;
00100     int Quality;
00101
00102 private:
00103     void SetupJPEGBitCodec(int bit);
00104     JPEGCodec *Internal;
00105 };
00106
00107 } // end namespace gdcm
00108
00109 #endif //GDCMJPEGCODEC_H

```

11.351 gdcmJPEGLSCodec.h File Reference

#include "gdcmImageCodec.h"

Include dependency graph for gdcmJPEGLSCodec.h:



Classes

- class [gdcm::JPEGLSCodec](#)
JPEG-LS.

Namespaces

- namespace [gdcm](#)

11.352 gdcmJPEGLSCodec.h

[Go to the documentation of this file.](#)

```


00001 /*=====
00002
00003     Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005     Copyright (c) 2006-2011 Mathieu Malaterre
00006     All rights reserved.
00007     See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009     This software is distributed WITHOUT ANY WARRANTY; without even
00010     the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011     PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMJPEGLSCODEC_H
00015 #define GDCMJPEGLSCODEC_H
00016
00017 #include "gdcmImageCodec.h"
00018
00019 namespace gdcm
00020 {
00021
00022     class JPEGLSInternals;
00023     class GDCM_EXPORT JPEGLSCodec : public ImageCodec
00024     {
00025     public:
00026         JPEGLSCodec();
00027         ~JPEGLSCodec() override;
00028         bool CanDecode(TransferSyntax const &ts) const override;
00029         bool CanCode(TransferSyntax const &ts) const override;
00030
00031         unsigned long GetBufferLength() const { return BufferLength; }
00032         void SetBufferLength(unsigned long l) { BufferLength = l; }
00033
00034         bool Decode(DataElement const &is, DataElement &os) override;
00035         bool Decode(DataElement const &in, char* outBuffer, size_t inBufferLength,
00036                     uint32_t inXMin, uint32_t inXMax, uint32_t inYMin,
00037                     uint32_t inYMax, uint32_t inZMin, uint32_t inZMax);
00038         bool Code(DataElement const &in, DataElement &out) override;
00039
00040         bool GetHeaderInfo(std::istream &is, TransferSyntax &ts) override;
00041         ImageCodec * Clone() const override;
00042
00043         void SetLossless(bool l);
00044         bool GetLossless() const;
00045
00046         /*
00047          * test.acr can look pretty bad, even with a lossy error of 2. Explanation follows:
00048          * I agree that the test image looks ugly. In this particular case I can
00049          * explain though.
00050          *
00051          * The image is 8 bit, but it does not use the full 8 bit dynamic range. The
00052          * black pixels have value 234 and the white 255. If you set allowed lossy
00053          * error to 2, you allow an error of about 10% of the actual dynamic range.
00054          * That is of course very visible.
00055          */
00056         void SetLossyError(int error);
00057
00058     protected:
00059         bool DecodeExtent(
00060             char *buffer,
00061             unsigned int xmin, unsigned int xmax,
00062             unsigned int ymin, unsigned int ymax,
00063             unsigned int zmin, unsigned int zmax,
00064             std::istream & is
00065         );
00066
00067         bool StartEncode( std::ostream & ) override;
00068         bool IsRowEncoder() override;
00069         bool IsFrameEncoder() override;
00070         bool AppendRowEncode( std::ostream & out, const char * data, size_t datalen ) override;
00071         bool AppendFrameEncode( std::ostream & out, const char * data, size_t datalen ) override;
00072         bool StopEncode( std::ostream & ) override;
00073
00074     private:

```

```
00084     bool DecodeByStreamsCommon(const char *buffer, size_t totalLen, std::vector<unsigned char> &rgbyteOut);
00085     bool CodeFrameIntoBuffer(char * outdata, size_t outlen, size_t & complen, const char * indata, size_t
inlen );
00086
00087     unsigned long BufferLength;
00088     int LossyError;
00089 };
00090
00091 } // end namespace gdcm
00092
00093 #endif //GDCMJPEGLSCODEC_H
```

11.353 gdcmJSON.h File Reference

```
#include "gdcmFile.h"
#include "gdcmDataElement.h"
Include dependency graph for gdcmJSON.h:
```



Classes

- class `gdcm::JSON`

Namespaces

- namespace **gdcm**

11.354 gdcJSON.h

[Go to the documentation of this file.](#)

```
00001  /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
```

```
00005 Copyright (c) 2006-2011 Mathieu Malaterre
00006 All rights reserved.
00007 See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009 This software is distributed WITHOUT ANY WARRANTY; without even
00010 the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011 PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMJSON_H
00015 #define GDCMJSON_H
00016
00017 /*
00018 See Sup 166 (QIDO-RS)
00019 http://www.dclunie.com/dicom-status/status.html#Supplement166
00020 */
00021
00022 #include "gdcmFile.h"
00023 #include "gdcmDataElement.h"
00024
00025 namespace gdcm
00026 {
00027
00028 class JSONInternal;
00029 class GDCM_EXPORT JSON
00030 {
00031 public:
00032     JSON();
00033     ~JSON();
00034
00035     bool GetPrettyPrint() const;
00036     void SetPrettyPrint(bool onoff);
00037     void PrettyPrintOn();
00038     void PrettyPrintOff();
00039
00040     bool Code(DataSet const & in, std::ostream & os);
00041     bool Decode(std::istream & is, DataSet & out);
00042
00043 private:
00044     JSONInternal *Internals;
00045 };
00046
00047 } // end namespace gdcm
00048
00049 #endif //GDCMXMLPRINTER_H
```



```

00019 namespace gdcm
00020 {
00021
00025 class KAKADUCodec : public ImageCodec
00026 {
00027 public:
00028     KAKADUCodec();
00029     ~KAKADUCodec() override;
00030     bool CanDecode(TransferSyntax const &ts) const override;
00031     bool CanCode(TransferSyntax const &ts) const override;
00032
00033     bool Decode(DataElement const &is, DataElement &os) override;
00034     bool Code(DataElement const &in, DataElement &out) override;
00035
00036     ImageCodec * Clone() const override;
00037 private:
00038 };
00039
00040 } // end namespace gdcm
00041
00042 #endif //GDCMKAKADUDEC_H

```


11.357 gdcmLookupTable.h File Reference

```


#include "gdcmTypes.h"
#include "gdcmObject.h"
#include <stdlib.h>

```

Include dependency graph for gdcmLookupTable.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::LookupTable](#)
LookupTable class.

Namespaces

- namespace [gdcm](#)

11.358 gdcmLookupTable.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013   =====*/
00014
00015 #ifndef GDCMLOOKUPTABLE_H
00016 #define GDCMLOOKUPTABLE_H
00017
00018 #include "gdcmTypes.h"
00019 #include "gdcmObject.h"
00020 #include <stdlib.h>
00021
00022 namespace gdcm
00023 {
00024
00025   class LookupTableInternal;
00029   class GDCM_EXPORT LookupTable : public Object
00030   {
00031   public:
00032     typedef enum {
00033       RED = 0, // Keep RED == 0
00034       GREEN,
00035       BLUE,
00036       GRAY,
00037       UNKNOWN
00038     } LookupTableType;
00039
00040     LookupTable();
00041     ~LookupTable() override;
00042     void Print(std::ostream &) const override;
00043
00044     void Allocate( unsigned short bitsample = 8 );
00047     //TODO: check to see if length should be unsigned short, unsigned int, or whatever
00048     void InitializeLUT(LookupTableType type, unsigned short length,
00049       unsigned short subscript, unsigned short bitsize);
00050     unsigned int GetLUTLength(LookupTableType type) const;
00051     virtual void SetLUT(LookupTableType type, const unsigned char *array,
00052       unsigned int length);
00053     void GetLUT(LookupTableType type, unsigned char *array, unsigned int &length) const;
00054     void GetLUTDescriptor(LookupTableType type, unsigned short &length,
00055       unsigned short &subscript, unsigned short &bitsize) const;
00056
00058     void InitializeRedLUT(unsigned short length, unsigned short subscript,
00059       unsigned short bitsize);
00060     void SetRedLUT(const unsigned char *red, unsigned int length);
00061     void InitializeGreenLUT(unsigned short length, unsigned short subscript,
00062       unsigned short bitsize);
00063     void SetGreenLUT(const unsigned char *green, unsigned int length);

```

```


00064 void InitializeBlueLUT(unsigned short length, unsigned short subscript,
00065     unsigned short bitsize);
00066 void SetBlueLUT(const unsigned char *blue, unsigned int length);
00067
00069 void Clear();
00070
00072 void Decode(std::istream &is, std::ostream &os) const;
00073
00077 bool Decode(char *outputbuffer, size_t outlen, const char *inputbuffer, size_t inlen) const;
00078
00080 bool IsRGB8() const;
00081
00083 bool Decode8(char *outputbuffer, size_t outlen, const char *inputbuffer, size_t inlen) const;
00084
00085 LookupTable(LookupTable const &lut):Object(lut), Internal(nullptr), BitSample(0), IncompleteLUT(false)
00086 {
00087     gdc_m_assert(0);
00088 }
00089
00091 bool GetBufferAsRGBA(unsigned char *rgba) const;
00092
00094 const unsigned char *GetPointer() const;
00095
00097 bool WriteBufferAsRGBA(const unsigned char *rgba);
00098
00100 unsigned short GetBitSample() const { return BitSample; }
00101
00103 bool Initialized() const;
00104
00105 private:
00107     void Encode(std::istream &is, std::ostream &os);
00108
00109 protected:
00110     LookupTableInternal *Internal;
00111     unsigned short BitSample; // refer to the pixel type (not the bit size of LUT)
00112     bool IncompleteLUT:1;
00113 };
00114
00115 } // end namespace gdc_m
00116
00117 #endif //GDCMLOOKUPTABLE_H

```

11.359 gdc_mMEC_MR3.h File Reference

#include "gdc_mPrivateTag.h"

Include dependency graph for gdc_mMEC_MR3.h:



Classes

- class [gdcm::MEC_MR3](#)
Class for [MEC_MR3](#).

Namespaces

- namespace [gdcm](#)

11.360 gdcmMEC_MR3.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013   =====*/
00014 #ifndef GDCMMEC_MR3_H
00015 #define GDCMMEC_MR3_H
00016
00017 #include "gdcmPrivateTag.h"
00018
00019 namespace gdcm {
00024 class GDCM_EXPORT MEC_MR3 {
00025 public:
00026   static bool Print(const char *src, size_t srclen);
00027
00030   static const PrivateTag &GetPMTFInformationDataTag();
00031
00034   static const PrivateTag &GetCanonMECMR3Tag();
00035
00038   static const PrivateTag &GetToshibaMECMR3Tag();
00039 };
00040
00041 } // end namespace gdcm
00042
00043 #endif // GDCMMEC_MR3_H

```


11.361 gdcmMeshPrimitive.h File Reference

```


#include <gdcmObject.h>
#include <gdcmDataElement.h>

```

Include dependency graph for `gdcmmeshPrimitive.h`:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcmmesh::MeshPrimitive](#)

This class defines surface mesh primitives.

Namespaces

- namespace [gdcm](#)

11.362 gdcmMeshPrimitive.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014
00015 #ifndef GDCMMESHPRIMITIVE_H
00016 #define GDCMMESHPRIMITIVE_H
00017
00018 #include <gdcmObject.h>
00019 #include <gdcmDataElement.h>
00020
00021 namespace gdcm
00022 {
00023
00024   class GDCM_EXPORT MeshPrimitive : public Object
00025   {
00026   public:
00027
00028     typedef std::vector< DataElement > PrimitivesData;
00029
00030     typedef enum {
00031       VERTEX = 0,
00032       EDGE,
00033       TRIANGLE,
00034       TRIANGLE_STRIP,
00035       TRIANGLE_FAN,
00036       LINE,
00037       FACET,
00038       MPType_END
00039     } MPType;
00040
00041     static const char * GetMPTypeString(const MPType type);
00042
00043     static MPType GetMPType(const char * type);
00044
00045     MeshPrimitive();
00046
00047     ~MeshPrimitive() override;
00048
00049     MPType GetPrimitiveType() const;
00050     void SetPrimitiveType(const MPType type);
00051
00052     const DataElement & GetPrimitiveData() const;
00053     DataElement & GetPrimitiveData();
00054     void SetPrimitiveData(DataElement const & de);
00055
00056     const PrimitivesData & GetPrimitivesData() const;
00057     PrimitivesData & GetPrimitivesData();
00058     void SetPrimitivesData(PrimitivesData const & DEs);
00059
00060     const DataElement & GetPrimitiveData(const unsigned int idx) const;
00061     DataElement & GetPrimitiveData(const unsigned int idx);
00062     void SetPrimitiveData(const unsigned int idx, DataElement const & de);
00063     void AddPrimitiveData(DataElement const & de);
00064
00065     unsigned int GetNumberOfPrimitivesData() const;
00066
00067   };
00068
00069   }
00070
00071   }

```

```


00078 protected:
00079
00080     // Use to define tag where PrimitiveData will be put.
00081     MPTyp    PrimitiveType;
00082
00083     // PrimitiveData contains point index list.
00084     // It shall have 1 or 1-n DataElement following PrimitiveType.
00085     PrimitivesData PrimitiveData;
00086 };
00087
00088 }
00089
00090 #endif // GDCMMESHPRIMITIVE_H

```

11.363 gdcmOrientation.h File Reference

```
#include "gdcmTypes.h"
```

Include dependency graph for gdcmOrientation.h:



Classes

- class `gdcm::Orientation`
class to handle `Orientation`

Namespaces

- namespace `gdcm`

Functions

- `std::ostream & gdcm::operator<< (std::ostream &os, const Orientation &o)`

11.364 gdcmOrientation.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMORIENTATION_H
00015 #define GDCMORIENTATION_H
00016
00017 #include "gdcmTypes.h"
00018
00019 namespace gdcm
00020 {
00021
00022     class GDCM_EXPORT Orientation
00023     {
00024     public:
00025         friend std::ostream& operator<<(std::ostream &_os, const Orientation &o);
00026     public:
00027         Orientation();
00028         ~Orientation() = default;
00029
00030         void Print(std::ostream &) const;
00031
00032         typedef enum {
00033             UNKNOWN,
00034             AXIAL,
00035             CORONAL,
00036             SAGITTAL,
00037             OBLIQUE
00038         } OrientationType;
00039
00040         static OrientationType GetType(const double dircos[6]);
00041
00042         static void SetObliquityThresholdCosineValue(double val);
00043         static double GetObliquityThresholdCosineValue();
00044
00045         static const char *GetLabel(OrientationType type);
00046
00047     protected:
00048         static char GetMajorAxisFromPatientRelativeDirectionCosine(double x, double y, double z);
00049
00050     private:
00051         static double ObliquityThresholdCosineValue;
00052     };
00053
00054 //-----
00055 inline std::ostream& operator<<(std::ostream &os, const Orientation &o)
00056 {
00057     o.Print( os );
00058     return os;
00059 }
00060
00061 } // end namespace gdcm
00062
00063 #endif //GDCMORIENTATION_H

```


11.365 gdcmOverlay.h File Reference

```


#include "gdcmTypes.h"
#include "gdcmObject.h"

```

Include dependency graph for `gdcOverlay.h`:



This graph shows which files directly or indirectly include this file:



Classes

- class `gdc::Overlay`
Overlay class.

Namespaces

- namespace `gdc`

11.366 gdcOverlay.h

[Go to the documentation of this file.](#)

```

00001 / * =====
00002

```

```

00003  Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005  Copyright (c) 2006-2011 Mathieu Malaterre
00006  All rights reserved.
00007  See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009      This software is distributed WITHOUT ANY WARRANTY; without even
00010      the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011      PURPOSE. See the above copyright notice for more information.
00012
00013  =====*/
00014  #ifndef GDCMOVERLAY_H
00015  #define GDCMOVERLAY_H
00016
00017  #include "gdcmTypes.h"
00018  #include "gdcmObject.h"
00019
00020  namespace gdcm
00021  {
00022
00023  class OverlayInternal;
00024  class ByteValue;
00025  class DataSet;
00026  class DataElement;
00038  class GDCM_EXPORT Overlay : public Object
00039  {
00040  public:
00041      Overlay();
00042      ~Overlay() override;
00044      void Print(std::ostream &) const override;
00045
00047      void Update(const DataElement & de);
00048
00050      void SetGroup(unsigned short group);
00052      unsigned short GetGroup() const;
00054      void SetRows(unsigned short rows);
00056      unsigned short GetRows() const;
00058      void SetColumns(unsigned short columns);
00060      unsigned short GetColumns() const;
00062      void SetNumberOfFrames(unsigned int numberofframes);
00064      void SetDescription(const char* description);
00066      const char *GetDescription() const;
00067      typedef enum {
00068          Invalid = 0,
00069          Graphics = 1,
00070          ROI = 2
00071      } OverlayType;
00073      void SetType(const char* type);
00075      const char *GetType() const;
00076      OverlayType GetTypeAsEnum() const;
00077      static const char *GetOverlayTypeAsString(OverlayType ot);
00078      static OverlayType GetOverlayTypeFromString(const char *);
00080      void SetOrigin(const signed short origin[2]);
00082      const signed short * GetOrigin() const;
00084      void SetFrameOrigin(unsigned short frameorigin);
00086      void SetBitsAllocated(unsigned short bitsallocated);
00088      unsigned short GetBitsAllocated() const;
00090      void SetBitPosition(unsigned short bitposition);
00092      unsigned short GetBitPosition() const;
00093
00095      void SetOverlay(const char *array, size_t length);
00097      bool GrabOverlayFromPixelData(DataSet const &ds);
00098
00101      const ByteValue &GetOverlayData() const;
00102
00104      bool IsEmpty() const;
00105
00107      bool IsZero() const;
00108
00110      bool IsInPixelData() const;
00111
00113      void IsInPixelData(bool b);
00114
00116      void Decompress(std::ostream &os) const;
00117
00120      size_t GetUnpackBufferLength() const;
00121
00124      bool GetUnpackBuffer(char *buffer, size_t len) const;
00125
00126      Overlay(Overlay const &ov);
00127      Overlay &operator=(Overlay const &ov);

```



```

00007  See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009      This software is distributed WITHOUT ANY WARRANTY; without even
00010      the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011      PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMPDFCODEC_H
00015 #define GDCMPDFCODEC_H
00016
00017 #include "gdcmCodec.h"
00018
00019 namespace gdcm
00020 {
00021
00025 class GDCM_EXPORT PDFCodec : public Codec
00026 {
00027 public:
00028     PDFCodec();
00029     ~PDFCodec() override;
00030     bool CanCode(TransferSyntax const &) const override { return false; }
00031     bool CanDecode(TransferSyntax const &) const override { return false; }
00032     bool Decode(DataElement const &is, DataElement &os) override;
00033 };
00034
00035 } // end namespace gdcm
00036
00037 #endif //GDCMPDFCODEC_H

```


11.369 gdcmPersonName.h File Reference

```

#include "gdcmTypes.h"
#include <vector>
#include <algorithm>
#include <string.h>

```

Include dependency graph for gdcmPersonName.h:



Classes

- class [gdcm::PersonName](#)
PersonName class.

Namespaces

- namespace [gdcm](#)

11.370 gdcmPersonName.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014
00015 #ifndef GDCMPERSONNAME_H
00016 #define GDCMPERSONNAME_H
00017
00018 #include "gdcmTypes.h"
00019 #include <vector>
00020 #include <algorithm> // std::min
00021 #include <string.h> // strlen
00022
00023 namespace gdcm
00024 {
00025
00026     class GDCM_EXPORT PersonName
00027     {
00028     public:
00029         static const unsigned int MaxNumberOfComponents = 5;
00030         static const unsigned int MaxLength = 64;
00031         char Component[MaxNumberOfComponents][MaxLength+1];
00032         static const char Separator = '^';
00033         static const char Padding = ' ';
00034
00035         unsigned int GetNumberOfComponents() const {
00036             unsigned int r = 0;
00037             for(unsigned int i = 0; i < 5; ++i) {
00038                 if( *Component[i] != '\0' ) r = i;
00039             }
00040             return r+1;
00041         }
00042         unsigned int GetMaxLength() const { return MaxLength; }
00043         void SetBlob(const std::vector<char>& v) {
00044             (void)v;
00045             //gdcm_assert(0); //TODO
00046         }
00047         void SetComponents(const char *comp1 = "",
00048             const char *comp2 = "",
00049             const char *comp3 = "",
00050             const char *comp4 = "",
00051             const char *comp5 = "") {
00052             const char *components[5] = { comp1, comp2, comp3, comp4, comp5 };
00053             SetComponents( components );
00054         }
00055         void SetComponents(const char *components[]) {
00056             if( components )
00057                 for(unsigned int i = 0; i < 5; ++i) {
00058                     if( components[i] && strlen(components[i]) < GetMaxLength() )
00059                         strcpy(Component[i], components[i]);
00060                     gdcm_assert( strlen(Component[i]) < GetMaxLength() );
00061                 }
00062         }
00063         void Print(std::ostream &os) const
00064         {
00065             //os << "Family Name Complex: " << Component[0] << std::endl;
00066             //os << "Given Name Complex: " << Component[1] << std::endl;
00067         }
00068     };
00069

```

```


00070      //os << "Middle Name           : " << Component[2] << std::endl;
00071      //os << "Name Suffix           : " << Component[3] << std::endl;
00072      //os << "Name Prefix           : " << Component[4] << std::endl;
00073      os << Component[0] << " ^';
00074      os << Component[1] << " ^';
00075      os << Component[2] << " ^';
00076      os << Component[3] << " ^';
00077      os << Component[4];
00078  }
00079 };
00080
00081 } // end namespace gdcms
00082
00083 #endif //GDCMPERSONNAME_H

```

11.371 gdcmPGXCodec.h File Reference

```
#include "gdcmImageCodec.h"
```

Include dependency graph for gdcnP GXCodec.h:



Classes

- class `gdc::PGXCodec`
Class to do PGX.

Namespaces

- namespace **gdcm**

11.372 gdcmPGXCodec.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013   =====*/
00014 #ifndef GDCMPGXCODEC_H
00015 #define GDCMPGXCODEC_H
00016
00017 #include "gdcmImageCodec.h"
00018
00019 namespace gdcm
00020 {
00021
00022   class GDCM_EXPORT PGXCodec : public ImageCodec
00023   {
00024   public:
00025     PGXCodec();
00026     ~PGXCodec() override;
00027     bool CanDecode(TransferSyntax const &ts) const override;
00028     bool CanCode(TransferSyntax const &ts) const override;
00029
00030     bool GetHeaderInfo(std::istream &is, TransferSyntax &ts) override;
00031     ImageCodec * Clone() const override;
00032
00033     bool Read(const char *filename, DataElement &out) const;
00034     bool Write(const char *filename, const DataElement &out) const;
00035   private:
00036   };
00037
00038 } // end namespace gdcm
00039 #endif //GDCMPGXCODEC_H


```

11.373 gdcmPhotometricInterpretation.h File Reference

```
#include "gdcmTypes.h"
```

```
#include <iostream>
```

Include dependency graph for gdcmPhotometricInterpretation.h:



- class `gdc::PhotometricInterpretation`
Class to represent an `PhotometricInterpretation`.

- namespace **gdcm**

- `std::ostream & gdcm::operator<< (std::ostream &os, const PhotometricInterpretation &val)`

[Go to the documentation of this file.](#)

```

00001  /*=====
00002
00003      Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005      Copyright (c) 2006-2011 Mathieu Malaterre
00006      All rights reserved.
00007      See Copyright.txt or http://gdcml.sourceforge.net/Copyright.html for details.
00008
00009      This software is distributed WITHOUT ANY WARRANTY; without even
00010      the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011      PURPOSE. See the above copyright notice for more information.
00012
00013  =====*/
00014
00015  #ifndef GDCMPHOTOMETRICINTERPRETATION_H
00016  #define GDCMPHOTOMETRICINTERPRETATION_H
00017
00018  #include "gdcmtypes.h"
00019  #include <iostream>
00020
00021  namespace gdcml
00022  {
00023
00024      class TransferSyntax;
00025
00026      class GDCM_EXPORT PhotometricInterpretation
00027      {
00028      public:
00029          typedef enum {
00030              UNKNOWN = 0,
00031              MONOCHROME1,
00032              MONOCHROME2,
00033              PALETTE_COLOR,
00034              RGB,
00035

```

```

00037     HSV,
00038     ARGB, // retired
00039     CMYK,
00040     YBR_FULL,
00041     YBR_FULL_422,
00042     YBR_PARTIAL_422,
00043     YBR_PARTIAL_420,
00044     YBR_ICT,
00045     YBR_RCT,
00046     // PALETTE_COLOR ?
00047     //MONOCHROME = MONOCHROME1 | MONOCHROME2,
00048     //COLOR      = RGB | HSV | ARGB | CMYK | YBR_FULL | YBR_FULL_422 | YBR_PARTIAL_422 | YBR_PARTIAL_420 |
YBR_ICT | YBR_RCT,
00049     PI_END // Helpful for internal implementation
00050 } PType; // PhotometricInterpretationType
00051
00052 PhotometricInterpretation(PType pi = UNKNOWN):PIField(pi) {}
00053
00054 static const char *GetPIString(PType pi);
00055
00056 const char *GetString() const;
00057
00058 // You need to make sure end of string is \0
00059 static PType GetPType(const char *pi);
00060
00061 static bool IsRetired(PType pi);
00062
00063 bool IsLossy() const;
00064 bool IsLossless() const;
00065
00066 unsigned short GetSamplesPerPixel() const;
00067
00068 // TODO
00069 // not all PhotometricInterpretation are allowed for compressed Transfer
00070 // syntax
00071 // static bool IsAllowedForCompressedTS(PType pi);
00072
00073 friend std::ostream& operator<(std::ostream& os, const PhotometricInterpretation& pi);
00074
00075 operator PType () const { return PIField; }
00076
00077 PType GetType () const { return PIField; }
00078
00079 // Will return whether current PhotometricInterpretation is the same Color Space as input:
00080 // eg. RGB and YBR_RCT are
00081 bool IsSameColorSpace( PhotometricInterpretation const &pi ) const;
00082
00083 //static PType GetEquivalent(TransferSyntax const &ts);
00084
00085 private:
00086 PType PIField;
00087 };
00088 //-----
00089 inline std::ostream& operator<(std::ostream& os, const PhotometricInterpretation &val)
00090 {
00091     const char *s = PhotometricInterpretation::GetPIString(val.PIField);
00092     os << (s ? s : "");
00093     return os;
00094 }
00095
00096
00097
00098 } // end namespace gdcm
00099
00100 #endif //GDCMPHOTOMETRICINTERPRETATION_H

```


11.375 gdcmPixelFormat.h File Reference

```

#include "gdcmTypes.h"
#include <iostream>
#include <assert.h>

```

Include dependency graph for gdcmPixelFormat.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::PixelFormat](#)
PixelFormat.

Namespaces

- namespace [gdcm](#)

Functions

- `std::ostream & gdcm::operator<< (std::ostream &os, const PixelFormat &pf)`

11.376 gdcmPixelFormat.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014
00015 #ifndef GDCMPIXELFORMAT_H
00016 #define GDCMPIXELFORMAT_H
00017
00018 #include "gdcmTypes.h"
00019 #include <iostream>
00020 #include <assert.h>
00021
00022 namespace gdcm
00023 {
00024
00025   class TransferSyntax;
00026
00045   class GDCM_EXPORT PixelFormat
00046   {
00047   friend class Bitmap;
00048   friend std::ostream& operator<<(std::ostream &_os, const PixelFormat &pf);
00049   public:
00050   // When adding a type please add its dual type (its unsigned counterpart)
00051   typedef enum {
00052     UINT8,
00053     INT8,
00054     UINT12,
00055     INT12,
00056     UINT16,
00057     INT16,
00058     UINT32, // For some DICOM files (RT or SC)
00059     INT32,  // " "
00060     UINT64, // Needed when input is 32bits + intercept/slope (incomplete support)
00061     INT64,  // " "
00062     FLOAT16, // sure why not...
00063     FLOAT32, // good ol' 'float'
00064     FLOAT64, // aka 'double'
00065     SINGLEBIT, // bool / monochrome
00066     UNKNOWN // aka BitsAllocated == 0 && PixelRepresentation == 0
00067   } ScalarType;
00068
00069   // default ctor:
00070   PixelFormat () : PixelFormat(1, 8, 8, 7, 0) {}
00071
00072   explicit PixelFormat (
00073     unsigned short samplesperpixel,
00074     unsigned short bitsallocated = 8,
00075     unsigned short bitsstored = 8,
00076     unsigned short highbit = 7,
00077     unsigned short pixelrepresentation = 0 ) :
00078     SamplesPerPixel(samplesperpixel),
00079     BitsAllocated(bitsallocated),
00080     BitsStored(bitsstored),
00081     HighBit(highbit),
00082     PixelRepresentation(pixelrepresentation) {}
00083   // helper, for the common case
00084   PixelFormat(ScalarType st);
00085
00086   // For transparency of use
00087   operator ScalarType() const { return GetScalarType(); }
00088
00091   unsigned short GetSamplesPerPixel() const;
00092   void SetSamplesPerPixel(unsigned short spp)
00093   {
00094     gdcmAssertMacro( spp <= 4 );
00095     SamplesPerPixel = spp;

```

```

00096     gdcm_assert( SamplesPerPixel == 1 || SamplesPerPixel == 3 || SamplesPerPixel == 4 );
00097 }
00098
00100 unsigned short GetBitsAllocated() const
00101 {
00102     return BitsAllocated;
00103 }
00104 void SetBitsAllocated(unsigned short ba)
00105 {
00106     if( ba )
00107     {
00108         switch( ba )
00109         {
00110             /* some devices (FUJIFILM CR + MONO1) incorrectly set BitsAllocated/BitsStored
00111              * as bitmask instead of value. Do what they mean instead of what they say.
00112              */
00113             case 0xffff: ba = 16; break;
00114             case 0x0fff: ba = 12; break;
00115             case 0x00ff: ba = 8; break;
00116         }
00117         BitsAllocated = ba;
00118         BitsStored = ba;
00119         HighBit = (unsigned short)(ba - 1);
00120     }
00121     else // Make the PixelFormat as UNKNOWN
00122     {
00123         BitsAllocated = 0;
00124         PixelRepresentation = 0;
00125     }
00126 }
00127
00129 unsigned short GetBitsStored() const
00130 {
00131     gdcm_assert( BitsStored <= BitsAllocated );
00132     return BitsStored;
00133 }
00134 void SetBitsStored(unsigned short bs)
00135 {
00136     switch( bs )
00137     {
00138         /* see SetBitsAllocated for explanation
00139         */
00140         case 0xffff: bs = 16; break;
00141         case 0x0fff: bs = 12; break;
00142         case 0x00ff: bs = 8; break;
00143     }
00144     if( bs <= BitsAllocated && bs )
00145     {
00146         BitsStored = bs;
00147         SetHighBit( (unsigned short) (bs - 1) );
00148     }
00149 }
00150
00152 unsigned short GetHighBit() const
00153 {
00154     gdcm_assert( HighBit < BitsStored );
00155     return HighBit;
00156 }
00157 void SetHighBit(unsigned short hb)
00158 {
00159     switch( hb )
00160     {
00161         /* broken implementations that use bitmask for BitsAllocated/Stored
00162          * nonetheless use (BitsStored-1) for HighBit. correct for this here.
00163          */
00164         case 0xffff: hb = 15; break;
00165         case 0x0ffe: hb = 11; break;
00166         case 0x00fe: hb = 7; break;
00167     }
00168     if( BitsStored > 1 && hb == 0 )
00169         HighBit = BitsStored - 1;
00170     else if( hb < BitsStored )
00171         HighBit = hb;
00172 }
00173
00175 unsigned short GetPixelRepresentation() const
00176 {
00177     return (unsigned short)(PixelRepresentation ? 1 : 0);
00178 }
00179 void SetPixelRepresentation(unsigned short pr)
00180 {

```

```

00181     PixelRepresentation = (unsigned short)(pr ? 1 : 0);
00182 }
00183
00185 ScalarType GetScalarType() const;
00186
00189 void SetScalarType(ScalarType st);
00190 const char *GetScalarTypeAsString() const;
00191
00197 uint8_t GetPixelSize() const;
00198
00200 void Print(std::ostream &os) const;
00201
00203 int64_t GetMin() const;
00204
00206 int64_t GetMax() const;
00207
00209 bool IsValid() const;
00210
00211 bool operator==(ScalarType st) const
00212 {
00213     return GetScalarType() == st;
00214 }
00215 bool operator!=(ScalarType st) const
00216 {
00217     return GetScalarType() != st;
00218 }
00219 bool operator==(const PixelFormat &pf) const
00220 {
00221     return
00222         SamplesPerPixel == pf.SamplesPerPixel &&
00223         BitsAllocated == pf.BitsAllocated &&
00224         BitsStored == pf.BitsStored &&
00225         HighBit == pf.HighBit &&
00226         PixelRepresentation == pf.PixelRepresentation;
00227 }
00228 bool operator!=(const PixelFormat &pf) const
00229 {
00230     return
00231         SamplesPerPixel != pf.SamplesPerPixel ||
00232         BitsAllocated != pf.BitsAllocated ||
00233         BitsStored != pf.BitsStored ||
00234         HighBit != pf.HighBit ||
00235         PixelRepresentation != pf.PixelRepresentation;
00236 }
00237
00238 bool IsCompatible(const TransferSyntax &ts) const;
00239 protected:
00241 bool Validate();
00242
00243 private:
00244     // D 0028|0002 [US] [Samples per Pixel] [1]
00245     unsigned short SamplesPerPixel;
00246     // D 0028|0100 [US] [Bits Allocated] [8]
00247     unsigned short BitsAllocated;
00248     // D 0028|0101 [US] [Bits Stored] [8]
00249     unsigned short BitsStored;
00250     // D 0028|0102 [US] [High Bit] [7]
00251     unsigned short HighBit;
00252     // D 0028|0103 [US] [Pixel Representation] [0]
00253     unsigned short PixelRepresentation;
00254 };
00255 //-----
00256 inline std::ostream& operator<(std::ostream &os, const PixelFormat &pf)
00257 {
00258     pf.Print(os);
00259     return os;
00260 }
00261
00262 } // end namespace gdcm
00263
00264 #endif //GDCMPIXELFORMAT_H

```


11.377 gdcmPixmap.h File Reference

```


#include "gdcmBitmap.h"
#include "gdcmCurve.h"

```

```
#include "gdcmIconImage.h"
#include "gdcmOverlay.h"
Include dependency graph for gdcmPixmap.h:
```



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::Pixmap](#)
Pixmap class.

Namespaces

- namespace [gdcm](#)

11.378 gdcmPixmap.h

[Go to the documentation of this file.](#)

```
00001 / * =====
00002
```

```

00003 Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005 Copyright (c) 2006-2011 Mathieu Malaterre
00006 All rights reserved.
00007 See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009 This software is distributed WITHOUT ANY WARRANTY; without even
00010 the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011 PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMPIXMAP_H
00015 #define GDCMPIXMAP_H
00016
00017 #include "gdcmBitmap.h"
00018 #include "gdcmCurve.h"
00019 #include "gdcmIconImage.h"
00020 #include "gdcmOverlay.h"
00021
00022 namespace gdcm
00023 {
00024
00025 class GDCM_EXPORT Pixmap : public Bitmap
00026 {
00027 public:
00028 Pixmap();
00029 ~Pixmap() override;
00030 void Print(std::ostream &) const override;
00031
00032 bool AreOverlaysInPixelData() const override;
00033 bool UnusedBitsPresentInPixelData() const override;
00034
00035 Curve& GetCurve(size_t i = 0) {
00036     gdcm_assert( i < Curves.size() );
00037     return Curves[i];
00038 }
00039 const Curve& GetCurve(size_t i = 0) const {
00040     gdcm_assert( i < Curves.size() );
00041     return Curves[i];
00042 }
00043 size_t GetNumberOfCurves() const { return Curves.size(); }
00044 void SetNumberOfCurves(size_t n) { Curves.resize(n); }
00045
00046 Overlay& GetOverlay(size_t i = 0) {
00047     gdcm_assert( i < Overlays.size() );
00048     return Overlays[i];
00049 }
00050 const Overlay& GetOverlay(size_t i = 0) const {
00051     gdcm_assert( i < Overlays.size() );
00052     return Overlays[i];
00053 }
00054 size_t GetNumberOfOverlays() const { return Overlays.size(); }
00055 void SetNumberOfOverlays(size_t n) { Overlays.resize(n); }
00056 void RemoveOverlay(size_t i) {
00057     gdcm_assert( i < Overlays.size() );
00058     Overlays.erase( Overlays.begin() + i );
00059 }
00060
00061 const IconImage &GetIconImage() const { return *Icon; }
00062 IconImage &GetIconImage() { return *Icon; }
00063 void SetIconImage(IconImage const &ii) { Icon = ii; }
00064
00065 //private:
00066 protected:
00067     std::vector<Overlay> Overlays;
00068     std::vector<Curve> Curves;
00069     SmartPointer<IconImage> Icon;
00070 };
00071
00072 } // end namespace gdcm
00073
00074 #endif //GDCMPIXMAP_H


```


11.380 gdcmPixmapReader.h

[Go to the documentation of this file.](#)

```
00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMPIXMAPREADER_H
00015 #define GDCMPIXMAPREADER_H
00016
00017 #include "gdcmReader.h"
00018 #include "gdcmPixmap.h"
00019
00020 namespace gdcm
00021 {
00022
00023   class ByteValue;
00024   class MediaStorage;
00039   class GDCM_EXPORT PixmapReader : public Reader
00040   {
00041   public:
00042     PixmapReader();
00043     ~PixmapReader() override; //needs to be virtual to ensure lack of memory leaks
00044
00048     bool Read() override;
00051     // Following methods are valid only after a call to 'Read'
00052
00054     const Pixmap& GetPixmap() const;
00055     Pixmap& GetPixmap();
00056     //void SetPixamp(Pixmap const &pix);
00057
00058   protected:
00059     bool ReadImageInternal(MediaStorage const &ms, bool handlepixeldata = true);
00060     virtual bool ReadImage(MediaStorage const &ms);
00061     virtual bool ReadACRNEMAImage();
00062
00063     SmartPointer<Pixmap> PixelData;
00064   };
00065
00070
00071 } // end namespace gdcm
00072
00073 #endif //GDCMPIXMAPREADER_H
```


This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::PixmapWriter](#)
PixmapWriter.

Namespaces

- namespace [gdcm](#)

11.384 gdcmPixmapWriter.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013   =====*/
00014 #ifndef GDCMPIXMAPWRITER_H
00015 #define GDCMPIXMAPWRITER_H
00016
00017 #include "gdcmWriter.h"
00018 #include "gdcmPixmap.h"
00019
00020 namespace gdcm
00021 {
00022
00023   class StreamImageWriter;
00024   class Pixmap;
00025
00026   class GDCM_EXPORT PixmapWriter : public Writer
00027   {
00028   public:
00029     PixmapWriter();
00030     ~PixmapWriter() override;
00031
00032   };
00033
00034 }
00035
00036 #endif

```


11.386 gdcmPNMCodec.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMPNMCODEC_H
00015 #define GDCMPNMCODEC_H
00016
00017 #include "gdcmImageCodec.h"
00018
00019 namespace gdcm
00020 {
00021
00022     class GDCM_EXPORT PNMCodec : public ImageCodec
00023     {
00024     public:
00025         PNMCodec();
00026         ~PNMCodec() override;
00027         bool CanDecode(TransferSyntax const &ts) const override;
00028         bool CanCode(TransferSyntax const &ts) const override;
00029
00030         unsigned long GetBufferLength() const { return BufferLength; }
00031         void SetBufferLength(unsigned long l) { BufferLength = l; }
00032
00033         bool GetHeaderInfo(std::istream &is, TransferSyntax &ts) override;
00034         ImageCodec * Clone() const override;
00035
00036         bool Read(const char *filename, DataElement &out) const;
00037         bool Write(const char *filename, const DataElement &out) const;
00038         //bool Write(const char *filename);
00039     private:
00040         unsigned long BufferLength;
00041     };
00042
00043 } // end namespace gdcm
00044
00045 #endif //GDCMPNMCODEC_H

```


11.387 gdcmPrinter.h File Reference

```


#include "gdcmFile.h"
#include "gdcmDataElement.h"

```

Include dependency graph for `gdcmPrinter.h`:



This graph shows which files directly or indirectly include this file:



Classes

- class `gdcm::Printer`
Printer class.

Namespaces

- namespace **gdcm**

11.388 gdcmPrinter.h

[Go to the documentation of this file.](#)


```

00001 /*=====
00002
00003     Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005     Copyright (c) 2006-2011 Mathieu Malaterre
00006     All rights reserved.
00007     See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009     This software is distributed WITHOUT ANY WARRANTY; without even
00010     the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011     PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMPRINTER_H
00015 #define GDCMPRINTER_H
00016
00017 // TODO Class to implement printing
00018 // Since DICOM does printing ?
00019 // Also I would like to encapsulate the IsCharacterPrintable thing
00020 // (to avoid printing \0 and other weird characters)
00021 // \todo I still need to implement skipping of group (shadow)
00022 // need to implement longer field to read
00023
00024 /*
00025  * Output:
00026  * For ASCII:
00027  * Typically will look like:
00028  * [ORIGINAL\PRIMARY\OTHER]
00029  * If a non printable character is found: RED and INVERSE is used:
00030  * [
00031  *
00032  * when the VR is not found (file or dict), we check if we can print the output:
00033  * on success ASCII mode is used, on failure the output is printed a series of bytes
00034  *
00035  * Special case when the data element is empty:
00036  * INVERSE < (no value)
00037  *
00038  * retired public element are printed in red and underline
00039  * unknown private element are printed in RED followed by 'UNKNOWN'
00040  *
00041  * Correct VR is printed in green just after the found VR
00042  *
00043  * length of data element is printed in bytes, followed by the VM, a green VM is appended
00044  * if this is not compatible
00045  */
00046 #include "gdcmFile.h"
00047 #include "gdcmDataElement.h"
00048
00049 namespace gdcm
00050 {
00051
00052     class DataSet;
00053     class DictEntry;
00054     class Dicts;
00055     // It's a sink there is no output
00056     class GDCM_EXPORT Printer
00057     {
00058     public:
00059         Printer();
00060         ~Printer() = default;
00061
00062         void SetFile(File const &f) { F = &f; }
00063
00064         void SetColor(bool c);
00065
00066         typedef enum {
00067             VERBOSE_STYLE = 0, // GDCM Legacy VERBOSE one
00068             CONDENSED_STYLE, //
00069             // Ok I am missing voc here ...better naming would be nice
00070             XML, //
00071             CXX
00072         } PrintStyles;
00073
00074         void SetStyle(PrintStyles ps) {
00075             PrintStyle = ps;
00076         }
00077     };
00078
00079     void SetStyle(PrintStyles ps) {
00080         PrintStyle = ps;
00081     }
00082

```

11.389 gdcnPVRGCodec.h File Reference

Include dependency graph for gdcnPVRGCodec.h:



- class `gdcm::PVRGCodec`
PVRGCodec.

- namespace **gdcm**

11.390 gdcmPVRGCodec.h


[Go to the documentation of this file.](#)

```
00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMPVRGCODEC_H
00015 #define GDCMPVRGCODEC_H
00016
00017 #include "gdcmImageCodec.h"
00018
00019 namespace gdcm
00020 {
00021
00022     class PVRGCodec : public ImageCodec
00023     {
00024     public:
00025         PVRGCodec();
00026         ~PVRGCodec() override;
00027         bool CanDecode(TransferSyntax const &ts) const override;
00028         bool CanCode(TransferSyntax const &ts) const override;
00029
00030         bool Decode(DataElement const &is, DataElement &os) override;
00031         bool Code(DataElement const &in, DataElement &out) override;
00032         void SetLossyFlag( bool l );
00033
00034         ImageCodec * Clone() const override;
00035     private:
00036     };
00037
00038 } // end namespace gdcm
00039
00040 #endif //GDCMPVRGCODEC_H
```

11.391 gdcmRAWCodec.h File Reference

```
#include "gdcmImageCodec.h"
```

Include dependency graph for gdcmRAWCodec.h:



Classes

- class [gdcm::RAWCodec](#)
RAWCodec class.

Namespaces

- namespace [gdcm](#)

11.392 gdcmRAWCodec.h

[Go to the documentation of this file.](#)

```
00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013   =====*/
00014 #ifndef GDCMRAWCODEC_H
00015 #define GDCMRAWCODEC_H
00016
00017 #include "gdcmImageCodec.h"
00018
```

```

00019 namespace gdcm
00020 {
00021
00022 class RAWInternals;
00026 class GDCM_EXPORT RAWCodec : public ImageCodec
00027 {
00028 public:
00029     RAWCodec();
00030     ~RAWCodec() override;
00031     bool CanCode(TransferSyntax const &ts) const override;
00032     bool CanDecode(TransferSyntax const &ts) const override;
00033     bool Decode(DataElement const &is, DataElement &os) override;
00034     bool Code(DataElement const &in, DataElement &out) override;
00035
00036     bool GetHeaderInfo(std::istream &is, TransferSyntax &ts) override;
00037     ImageCodec * Clone() const override;
00038
00041     bool DecodeBytes(const char* inBytes, size_t inBufferLength,
00042         char* outBytes, size_t inOutBufferLength);
00043
00044 protected:
00045     bool DecodeByStreams(std::istream &is, std::ostream &os) override;
00046
00047 private:
00048     RAWInternals *Internals;
00049 };
00050
00051 } // end namespace gdcm
00052
00053 #endif // GDCMRWCODEC_H


```

11.393 gdcmRescaler.h File Reference

```
#include "gdcmTypes.h"
```

```
#include "gdcmPixelFormat.h"
```

Include dependency graph for gdcmRescaler.h:



Classes

- class [gdcm::Rescaler](#)

Rescale class.

Namespaces

- namespace `gdcm`

11.394 gdcmRescaler.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMRESCALER_H
00015 #define GDCMRESCALER_H
00016
00017 #include "gdcmTypes.h"
00018 #include "gdcmPixelFormat.h"
00019
00020 namespace gdcm
00021 {
00022
00023     class GDCM_EXPORT Rescaler
00024     {
00025     public:
00026         Rescaler() : Intercept(0), Slope(1), PF(PixelFormat::UNKNOWN), TargetScalarType(PixelFormat::UNKNOWN),
00027             ScalarRangeMin(0), ScalarRangeMax(0), UseTargetPixelType(false) {}
00028         ~Rescaler() = default;
00029
00030         bool Rescale(char *out, const char *in, size_t n);
00031         bool InverseRescale(char *out, const char *in, size_t n);
00032
00033         void SetIntercept(double i) { Intercept = i; }
00034         double GetIntercept() const { return Intercept; }
00035
00036         void SetSlope(double s) { Slope = s; }
00037         double GetSlope() const { return Slope; }
00038
00039         void SetTargetPixelType(PixelFormat const & targetst);
00040         void SetUseTargetPixelType(bool b);
00041         void SetPixelFormat(PixelFormat const & pf) { PF = pf; }
00042
00043         PixelFormat::ScalarType ComputeInterceptSlopePixelType();
00044         void SetMinMaxForPixelType(double min, double max);
00045         PixelFormat ComputePixelTypeFromMinMax();
00046
00047     protected:
00048         template <typename TIn>
00049             void RescaleFunctionIntoBestFit(char *out, const TIn *in, size_t n);
00050         template <typename TIn>
00051             void InverseRescaleFunctionIntoBestFit(char *out, const TIn *in, size_t n);
00052
00053     private:
00054         double Intercept; // 0028,1052
00055         double Slope; // 0028,1053
00056         PixelFormat PF;
00057         PixelFormat::ScalarType TargetScalarType;
00058         double ScalarRangeMin;
00059         double ScalarRangeMax;
00060         bool UseTargetPixelType;
00061     };

```

```


00127
00128 } // end namespace gdcm
00129
00130 #endif //GDCMRESCALER_H

```

11.395 gdcmRLECodec.h File Reference

```
#include "gdcmImageCodec.h"
```

Include dependency graph for gdcmRLECodec.h:



Classes

- class [gdcm::RLECodec](#)
Class to do RLE.

Namespaces

- namespace [gdcm](#)

11.396 gdcmRLECodec.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003 Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005 Copyright (c) 2006-2011 Mathieu Malaterre
00006 All rights reserved.
00007 See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009 This software is distributed WITHOUT ANY WARRANTY; without even

```

```

00010     the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011     PURPOSE. See the above copyright notice for more information.
00012
00013     =====*/
00014 #ifndef GDCMRLECODEC_H
00015 #define GDCMRLECODEC_H
00016
00017 #include "gdcmImageCodec.h"
00018
00019 namespace gdcm
00020 {
00021
00022 class Fragment;
00023 class RLEInternals;
00024 class GDCM_EXPORT RLECodec : public ImageCodec
00025 {
00026 friend class ImageRegionReader;
00027 public:
00028     RLECodec();
00029     ~RLECodec() override;
00030     bool CanCode(TransferSyntax const &ts) const override;
00031     bool CanDecode(TransferSyntax const &ts) const override;
00032     bool Decode(DataElement const &is, DataElement &os) override;
00033     unsigned long GetBufferLength() const { return BufferLength; }
00034     void SetBufferLength(unsigned long l) { BufferLength = l; }
00035
00036     bool Code(DataElement const &in, DataElement &out) override;
00037     bool GetHeaderInfo(std::istream &is, TransferSyntax &ts) override;
00038     ImageCodec * Clone() const override;
00039
00040 protected:
00041     bool DecodeExtent(
00042         char *buffer,
00043         unsigned int XMin, unsigned int XMax,
00044         unsigned int YMin, unsigned int YMax,
00045         unsigned int ZMin, unsigned int ZMax,
00046         std::istream & is
00047     );
00048
00049     bool DecodeByStreams(std::istream &is, std::ostream &os) override;
00050 public:
00051     void SetLength(unsigned long l)
00052     {
00053         Length = l;
00054     }
00055
00056 protected:
00057     bool StartEncode( std::ostream & ) override;
00058     bool IsRowEncoder() override;
00059     bool IsFrameEncoder() override;
00060     bool AppendRowEncode( std::ostream & out, const char * data, size_t datalen ) override;
00061     bool AppendFrameEncode( std::ostream & out, const char * data, size_t datalen ) override;
00062     bool StopEncode( std::ostream & ) override;
00063
00064 private:
00065     bool DecodeByStreamsCommon(std::istream &is, std::ostream &os);
00066     RLEInternals *Internals;
00067     unsigned long Length;
00068     unsigned long BufferLength;
00069     size_t DecodeFragment(Fragment const & frag, char *buffer, size_t llen);
00070 };
00071
00072 } // end namespace gdcm
00073
00074 #endif //GDCMRLECODEC_H

```

11.397 gdcmScanner.h File Reference

```

#include "gdcmDirectory.h"
#include "gdcmSubject.h"
#include "gdcmTag.h"
#include "gdcmPrivateTag.h"

```


[illegible]

- struct `gdcm::Scanner::Itstr`
- class `gdcm::Scanner`
Scanner.

- namespace **gdcm**

- `std::ostream & gdcmm::operator<< (std::ostream &os, const Scanner &s)`

[Go to the documentation of this file.](#)

```
00001 /*=====
00002
00003     Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005     Copyright (c) 2006-2011 Mathieu Malaterre
00006     All rights reserved.
00007     See Copyright.txt or http://gdcms.sourceforge.net/Copyright.html for details.
00008
00009     This software is distributed WITHOUT ANY WARRANTY; without even
00010     the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011     PURPOSE. See the above copyright notice for more information.
00012
00013     =====*/
00014 #ifndef GDCMSCANNER_H
```

```

00015 #define GDCMSCANNER_H
00016
00017 #include "gdcmDirectory.h"
00018 #include "gdcmSubject.h"
00019 #include "gdcmTag.h"
00020 #include "gdcmPrivateTag.h"
00021 #include "gdcmSmartPointer.h"
00022
00023 #include <map>
00024 #include <set>
00025 #include <string>
00026
00027 #include <string.h> // strcmp
00028
00029 namespace gdcm
00030 {
00031 class StringFilter;
00032
00033 class GDCM_EXPORT Scanner : public Subject
00034 {
00035     friend std::ostream& operator<<(std::ostream &_os, const Scanner &s);
00036 public:
00037     Scanner():Values(), Filenames(), Mappings(), Progress(0.0) {}
00038     ~Scanner() override;
00039
00040     typedef std::map<Tag, const char*> TagToValue;
00041     //typedef std::map<Tag, ConstCharWrapper> TagToValue; //StringMap;
00042     //typedef TagToStringMap TagToValue;
00043     typedef TagToValue::value_type TagToValueValueType;
00044
00045     void AddTag( Tag const & t );
00046     void ClearTags();
00047
00048     // Work in progress do not use:
00049     void AddPrivateTag( PrivateTag const & t );
00050
00051     void AddSkipTag( Tag const & t );
00052     void ClearSkipTags();
00053
00054     bool Scan( Directory::FileNamesType const & filenames );
00055
00056     Directory::FileNamesType const &GetFileNames() const { return Filenames; }
00057
00058     void Print( std::ostream & os ) const override;
00059
00060     void PrintTable( std::ostream & os ) const;
00061
00062     bool IsKey( const char * filename ) const;
00063
00064     Directory::FileNamesType GetKeys() const;
00065
00066     // struct to store all the values found:
00067     typedef std::set< std::string > ValueType;
00068
00069     ValueType const & GetValues() const { return Values; }
00070
00071     ValueType GetValues(Tag const &t) const;
00072
00073     Directory::FileNamesType GetOrderedValues(Tag const &t) const;
00074
00075     /* ltstr is CRITICAL, otherwise pointers value are used to do the key comparison */
00076     struct ltstr
00077     {
00078         bool operator()(const char* s1, const char* s2) const
00079         {
00080             gdcm_assert( s1 && s2 );
00081             return strcmp(s1, s2) < 0;
00082         }
00083     };
00084
00085     typedef std::map<const char *, TagToValue, ltstr> MappingType;
00086     typedef MappingType::const_iterator ConstIterator;
00087     ConstIterator Begin() const { return Mappings.begin(); }
00088     ConstIterator End() const { return Mappings.end(); }
00089
00090     MappingType const & GetMappings() const { return Mappings; }
00091
00092     TagToValue const & GetMapping(const char *filename) const;
00093
00094     const char *GetFilenameFromTagToValue(Tag const &t, const char *valueref) const;
00095
00096     Directory::FileNamesType GetAllFileNamesFromTagToValue(Tag const &t, const char *valueref) const;

```

```

00144
00146 // by a call to GetMapping()
00147 TagToValue const & GetMappingFromTagToValue(Tag const &t, const char *value) const;
00148
00154 const char* GetValue(const char *filename, Tag const &t) const;
00155
00157 static SmartPointer<Scanner> New() { return new Scanner; }
00158
00159 protected:
00160 void ProcessPublicTag(StringFilter &sf, const char *filename);
00161 private:
00162 // struct to store all uniq tags in ascending order:
00163 typedef std::set< Tag > TagsType;
00164 typedef std::set< PrivateTag > PrivateTagsType;
00165 std::set< Tag > Tags;
00166 std::set< PrivateTag > PrivateTags;
00167 std::set< Tag > SkipTags;
00168 ValuesType Values;
00169 Directory::FileNamesType Filenames;
00170
00171 // Main struct that will hold all mapping:
00172 MappingType Mappings;
00173
00174 double Progress;
00175 };
00176 //-----
00177 inline std::ostream& operator<<(std::ostream &os, const Scanner &s)
00178 {
00179 s.Print( os );
00180 return os;
00181 }
00182
00183 #if defined(SWIGPYTHON) || defined(SWIGCSharp) || defined(SWIGJAVA) || defined(SWIGPHP)
00184 /*
00185 * HACK: I need this temp class to be able to manipulate a std::map from python,
00186 * swig does not support wrapping of simple class like std::map...
00187 */
00188 class SWIGTagToValue
00189 {
00190 public:
00191 SWIGTagToValue(Scanner::TagToValue const &t2v):Internal(t2v),it(t2v.begin()) {}
00192 const Scanner::TagToValueValueType& GetCurrent() const { return *it; }
00193 const Tag& GetCurrentTag() const { return it->first; }
00194 const char *GetCurrentValue() const { return it->second; }
00195 void Start() { it = Internal.begin(); }
00196 bool IsAtEnd() const { return it == Internal.end(); }
00197 void Next() { ++it; }
00198 private:
00199 const Scanner::TagToValue& Internal;
00200 Scanner::TagToValue::const_iterator it;
00201 };
00202 #endif /* SWIG */
00203
00208
00209 } // end namespace gdcmscanner
00210
00211 #endif //GDCMSCANNER_H

```

11.399 gdcmscanner2.h File Reference

```

#include "gdcmscanner2.h"
#include "gdcmscanner2.h"
#include "gdcmscanner2.h"
#include "gdcmscanner2.h"
#include "gdcmscanner2.h"
#include <map>
#include <set>
#include <string>

```



```

00021 #include "gdcmSmartPointer.h"
00022
00023 #include <map>
00024 #include <set>
00025 #include <string>
00026
00027 #include <string.h> // strcmp
00028
00029 namespace gdcm
00030 {
00031     class StringFilter;
00032
00033     class GDCM_EXPORT Scanner2 : public Subject
00034     {
00035     public:
00036         friend std::ostream& operator<<(std::ostream &_os, const Scanner2 &s);
00037     public:
00038         Scanner2():Values(),FileNames(),PublicMappings(),PrivateMappings(),Progress(0.0) {}
00039         ~Scanner2() override;
00040
00041         typedef std::map<Tag, const char*> PublicTagToValue;
00042         typedef PublicTagToValue::value_type PublicTagToValueValueType;
00043
00044         typedef std::map<PrivateTag, const char*> PrivateTagToValue;
00045         typedef PrivateTagToValue::value_type PrivateTagToValueValueType;
00046
00047         bool AddPublicTag( Tag const & t );
00048         void ClearPublicTags();
00049
00050         // Work in progress do not use:
00051         bool AddPrivateTag( PrivateTag const & pt );
00052         void ClearPrivateTags();
00053
00054         bool AddSkipTag( Tag const & t );
00055         void ClearSkipTags();
00056
00057         bool Scan( Directory::FileNamesType const & filenames );
00058
00059         Directory::FileNamesType const &GetFileNames() const { return FileNames; }
00060
00061         void Print( std::ostream & os ) const override;
00062
00063         void PrintTable( std::ostream & os, bool header = false ) const;
00064
00065         bool IsKey( const char * filename ) const;
00066
00067         Directory::FileNamesType GetKeys() const;
00068
00069         // struct to store all the values found:
00070         typedef std::set< std::string > ValueType;
00071
00072         ValueType const & GetValues() const { return Values; }
00073
00074         ValueType GetPublicValues(Tag const &t) const;
00075
00076         ValueType GetPrivateValues(PrivateTag const &pt) const;
00077
00078         Directory::FileNamesType GetPublicOrderedValues(Tag const &t) const;
00079
00080         Directory::FileNamesType GetPrivateOrderedValues(PrivateTag const &pt) const;
00081
00082         /* ltstr is CRITICAL, otherwise pointers value are used to do the key comparison */
00083         struct ltstr
00084         {
00085             bool operator()(const char* s1, const char* s2) const
00086             {
00087                 gdcm_assert( s1 && s2 );
00088                 return strcmp(s1, s2) < 0;
00089             }
00090         };
00091
00092         typedef std::map<const char *,PublicTagToValue, ltstr> PublicMappingType;
00093         typedef PublicMappingType::const_iterator PublicConstIterator;
00094         PublicConstIterator Begin() const { return PublicMappings.begin(); }
00095         PublicConstIterator End() const { return PublicMappings.end(); }
00096
00097         typedef std::map<const char *,PrivateTagToValue, ltstr> PrivateMappingType;
00098         typedef PrivateMappingType::const_iterator PrivateConstIterator;
00099         PrivateConstIterator PrivateBegin() const { return PrivateMappings.begin(); }
00100         PrivateConstIterator PrivateEnd() const { return PrivateMappings.end(); }
00101
00102         PublicMappingType const & GetPublicMappings() const { return PublicMappings; }
00103         PrivateMappingType const & GetPrivateMappings() const { return PrivateMappings; }

```

```

00148
00150 PublicTagToValue const & GetPublicMapping(const char *filename) const;
00151 PrivateTagToValue const & GetPrivateMapping(const char *filename) const;
00152
00155 const char *GetFilenameFromPublicTagToValue(Tag const &t, const char *valueref) const;
00156 const char *GetFilenameFromPrivateTagToValue(PrivateTag const &pt, const char *valueref) const;
00157
00160 Directory::FilenameType GetAllFileNamesFromPublicTagToValue(Tag const &t, const char *valueref) const;
00161 Directory::FilenameType GetAllFileNamesFromPrivateTagToValue(PrivateTag const &pt, const char
*valueref) const;
00162
00164 // by a call to GetMapping()
00165 PublicTagToValue const & GetMappingFromPublicTagToValue(Tag const &t, const char *value) const;
00166 PrivateTagToValue const & GetMappingFromPrivateTagToValue(PrivateTag const &pt, const char *value)
const;
00167
00173 const char* GetPublicValue(const char *filename, Tag const &t) const;
00174 const char* GetPrivateValue(const char *filename, PrivateTag const &t) const;
00175
00177 static SmartPointer<Scanner2> New() { return new Scanner2; }
00178
00179 protected:
00180 void ProcessPublicTag(StringFilter &sf, const char *filename);
00181 void ProcessPrivateTag(StringFilter &sf, const char *filename);
00182 private:
00183 // struct to store all uniq tags in ascending order:
00184 typedef std::set< Tag > PublicTagsType;
00185 typedef std::set< PrivateTag > PrivateTagsType;
00186 std::set< Tag > PublicTags; // Public and Private Creator
00187 std::set< PrivateTag > PrivateTags; // Only Private (no Private Creator)
00188 std::set< Tag > SkipTags;
00189 ValueType Values;
00190 Directory::FilenameType Filenames;
00191
00192 // Main struct that will hold all public mapping:
00193 PublicMappingType PublicMappings;
00194 // Main struct that will hold all private mapping:
00195 PrivateMappingType PrivateMappings;
00196
00197 double Progress;
00198 };
00199 //-----
00200 inline std::ostream& operator<<(std::ostream &os, const Scanner2 &s)
00201 {
00202     s.Print( os );
00203     return os;
00204 }
00205
00206 } // end namespace gdcm
00207
00208 #endif //GDCMSCANNER2_H

```

11.401 gdcmSegment.h File Reference

```

#include <vector>
#include <gdcmObject.h>
#include <gdcmSurface.h>
#include "gdcmSegmentHelper.h"

```


11.402 gdcmSegment.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMSEGMENT_H
00015 #define GDCMSEGMENT_H
00016
00017 #include <vector>
00018
00019 #include <gdcmObject.h>
00020 #include <gdcmSurface.h>
00021 #include "gdcmSegmentHelper.h"
00022
00023 namespace gdcm
00024 {
00025
00026     class GDCM_EXPORT Segment : public Object
00027     {
00028     public:
00029
00030         typedef std::vector<SmartPointer<Surface>> SurfaceVector;
00031         typedef std::vector<SegmentHelper::BasicCodedEntry> BasicCodedEntryVector;
00032
00033         typedef enum {
00034             AUTOMATIC = 0,
00035             SEMIAUTOMATIC,
00036             MANUAL,
00037             ALGOType_END
00038         } ALGOType;
00039
00040         static const char * GetALGOTypeString(ALGOType type);
00041         static ALGOType GetALGOType(const char * type);
00042
00043         Segment();
00044
00045         ~Segment() override;
00046
00047         /**      Segment getters/setters      **/
00048         unsigned short GetSegmentNumber() const;
00049         void SetSegmentNumber(const unsigned short num);
00050
00051         const char * GetSegmentLabel() const;
00052         void SetSegmentLabel(const char * label);
00053
00054         const char * GetSegmentDescription() const;
00055         void SetSegmentDescription(const char * description);
00056
00057         SegmentHelper::BasicCodedEntry const & GetAnatomicRegion() const;
00058         SegmentHelper::BasicCodedEntry & GetAnatomicRegion();
00059         void SetAnatomicRegion(SegmentHelper::BasicCodedEntry const & BSE);
00060
00061         BasicCodedEntryVector const & GetAnatomicRegionModifiers() const;
00062         BasicCodedEntryVector & GetAnatomicRegionModifiers();
00063         void SetAnatomicRegionModifiers(BasicCodedEntryVector const & BSEV);
00064
00065         SegmentHelper::BasicCodedEntry const & GetPropertyCategory() const;
00066         SegmentHelper::BasicCodedEntry & GetPropertyCategory();
00067         void SetPropertyCategory(SegmentHelper::BasicCodedEntry const & BSE);
00068
00069         SegmentHelper::BasicCodedEntry const & GetPropertyType() const;
00070         SegmentHelper::BasicCodedEntry & GetPropertyType();
00071         void SetPropertyType(SegmentHelper::BasicCodedEntry const & BSE);
00072
00073         BasicCodedEntryVector const & GetPropertyTypeModifiers() const;
00074         BasicCodedEntryVector & GetPropertyTypeModifiers();

```



```


00083 void SetPropertyTypeModifiers(BasicCodedEntryVector const & BSEV);
00084
00085 ALGOType GetSegmentAlgorithmType() const;
00086 void SetSegmentAlgorithmType(ALGOType type);
00087 void SetSegmentAlgorithmType(const char * typeStr);
00088
00089 const char * GetSegmentAlgorithmName() const;
00090 void SetSegmentAlgorithmName(const char * name);
00091
00092 /**      Surface getters/setters      **/
00093 unsigned long GetSurfaceCount();
00094 void SetSurfaceCount(const unsigned long nb);
00095
00096 SurfaceVector const & GetSurfaces() const;
00097 SurfaceVector & GetSurfaces();
00098
00099 SmartPointer< Surface > GetSurface(const unsigned int idx = 0) const;
00100
00101 void AddSurface(SmartPointer< Surface > surface);
00102
00103 protected :
00104 /**      Segment members      **/
00105 //0062 0004 US 1 Segment Number
00106 unsigned short SegmentNumber;
00107 //0062 0005 LO 1 Segment Label
00108 std::string SegmentLabel;
00109 //0062 0006 ST 1 Segment Description
00110 std::string SegmentDescription;
00111
00112 // General Anatomic Region
00113 SegmentHelper::BasicCodedEntry AnatomicRegion;
00114 // General Anatomic Region Modifier
00115 BasicCodedEntryVector AnatomicRegionModifiers;
00116 // Property Category Code
00117 SegmentHelper::BasicCodedEntry PropertyCategory;
00118 // Property Type Code
00119 SegmentHelper::BasicCodedEntry PropertyType;
00120 // Property Type Modifier Code
00121 BasicCodedEntryVector PropertyTypeModifiers;
00122
00123 //0062 0008 CS 1 Segment Algorithm Type
00124 ALGOType SegmentAlgorithmType;
00125 //0062 0009 LO 1 Segment Algorithm Name
00126 std::string SegmentAlgorithmName;
00127
00128 /**      Surface members      **/
00129 //0066 002a UL 1 Surface Count
00130 unsigned long SurfaceCount;
00131
00132 SurfaceVector Surfaces;
00133
00134 private :
00135 void ComputeSurfaceCount();
00136 };
00137
00138 }
00139
00140 #endif // GDCMSEGMENT_H

```

11.403 gdcmSegmentedPaletteColorLookupTable.h File Reference

```
#include "gdcmLookupTable.h"
```

Include dependency graph for gdcmSegmentedPaletteColorLookupTable.h:



Classes

- class [gdcm::SegmentedPaletteColorLookupTable](#)
SegmentedPaletteColorLookupTable class.

Namespaces

- namespace [gdcm](#)

11.404 gdcmSegmentedPaletteColorLookupTable.h

[Go to the documentation of this file.](#)

```

00001  /*=====
00002
00003  Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005  Copyright (c) 2006-2011 Mathieu Malaterre
00006  All rights reserved.
00007  See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009  This software is distributed WITHOUT ANY WARRANTY; without even
00010  the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011  PURPOSE. See the above copyright notice for more information.
00012
00013  =====*/

```

```

00014
00015 #ifndef GDCMSEGMENTEDPALETTECOLORLOOKUPTABLE_H
00016 #define GDCMSEGMENTEDPALETTECOLORLOOKUPTABLE_H
00017
00018 #include "gdcmLookupTable.h"
00019
00020 namespace gdcm
00021 {
00022
00026 class GDCM_EXPORT SegmentedPaletteColorLookupTable : public LookupTable
00027 {
00028 public:
00029     SegmentedPaletteColorLookupTable();
00030     ~SegmentedPaletteColorLookupTable() override;
00031     void Print(std::ostream &) const override {}
00032
00034     void SetLUT(LookupTableType type, const unsigned char *array,
00035               unsigned int length) override;
00036
00037 };
00038
00039 } // end namespace gdcm
00040
00041 #endif //GDCMSEGMENTEDPALETTECOLORLOOKUPTABLE_H

```


11.405 gdcmSegmentHelper.h File Reference

```


#include "gdcmTypes.h"
#include <string>

```

Include dependency graph for gdcmSegmentHelper.h:



This graph shows which files directly or indirectly include this file:



Classes

- struct [gdcm::SegmentHelper::BasicCodedEntry](#)
This structure defines a basic coded entry with all of its attributes.

Namespaces

- namespace [gdcm](#)
- namespace [gdcm::SegmentHelper](#)

11.406 gdcmSegmentHelper.h

[Go to the documentation of this file.](#)

```

00001  /*=====
00002
00003  Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005  Copyright (c) 2006-2011 Mathieu Malaterre
00006  All rights reserved.
00007  See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009  This software is distributed WITHOUT ANY WARRANTY; without even
00010  the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011  PURPOSE. See the above copyright notice for more information.
00012

```

```

00013 =====*/
00014 #ifndef GDCMSEGMENTHELPER_H
00015 #define GDCMSEGMENTHELPER_H
00016
00017 #include "gdcmTypes.h"
00018
00019 #include <string>
00020
00021 namespace gdcm
00022 {
00023
00024     namespace SegmentHelper
00025     {
00026
00032         struct GDCM_EXPORT BasicCodedEntry
00033         {
00037             BasicCodedEntry() :
00038                 CV(""),
00039                 CSD(""),
00040                 CSV(""),
00041                 CM("")
00042             {}
00043
00047             BasicCodedEntry(const char * a_CV,
00048                             const char * a_CSD,
00049                             const char * a_CM) :
00050                 CV(a_CV),
00051                 CSD(a_CSD),
00052                 CSV(""),
00053                 CM(a_CM)
00054             {}
00055
00059             BasicCodedEntry(const char * a_CV,
00060                             const char * a_CSD,
00061                             const char * a_CSV,
00062                             const char * a_CM) :
00063                 CV(a_CV),
00064                 CSD(a_CSD),
00065                 CSV(a_CSV),
00066                 CM(a_CM)
00067             {}
00068
00074             bool IsEmpty(const bool checkOptionalAttributes = false) const;
00075
00076
00077             /**      Members      **/
00078             // 0008 0100 1   Code Value
00079             std::string CV;
00080             // 0008 0102 1   Coding Scheme Designator
00081             std::string CSD;
00082             // 0008 0103 1C   Coding Scheme Version
00083             std::string CSV;
00084             // 0008 0104 1   Code Meaning
00085             std::string CM;
00086         };
00087
00088     } // end of SegmentHelper namespace
00089
00090 } // end of gdcm namespace
00091
00092 #endif // GDCMSEGMENTHELPER_H

```


11.407 gdcmSegmentReader.h File Reference

```


#include <map>
#include <gdcmReader.h>
#include <gdcmSegment.h>

```

Include dependency graph for `gdcmSegmentReader.h`:



This graph shows which files directly or indirectly include this file:



Classes

- class `gdcm::SegmentReader`
This class defines a segment reader.

Namespaces

- namespace **gdcm**

11.408 gdcmSegmentReader.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMSEGMENTREADER_H
00015 #define GDCMSEGMENTREADER_H
00016
00017 #include <map>
00018
00019 #include <gdcmReader.h>
00020 #include <gdcmSegment.h>
00021
00022 namespace gdcm
00023 {
00024
00025     class GDCM_EXPORT SegmentReader : public Reader
00026     {
00027     public:
00028         typedef std::vector<SmartPointer<Segment>> SegmentVector;
00029
00030         SegmentReader();
00031
00032         ~SegmentReader() override;
00033
00034         bool Read() override; // Set to protected ?
00035
00036         /** Segment getters/setters */
00037         SegmentVector GetSegments() const;
00038         SegmentVector GetSegments();
00039
00040         // unsigned int GetNumberOfSegments();
00041
00042     protected:
00043
00044         typedef std::map<unsigned long, SmartPointer<Segment>> SegmentMap;
00045
00046         bool ReadSegments();
00047
00048         bool ReadSegment(const Item & segmentItem, const unsigned int idx);
00049
00050         SegmentMap Segments; // The key value is item number (in segment sequence)
00051                             // or the surface number (for a surface segmentation).
00052     };
00053
00054 #endif // GDCMSEGMENTREADER_H

```


11.409 gdcmSegmentWriter.h File Reference

```


#include <gdcmWriter.h>
#include <gdcmSegment.h>

```

Include dependency graph for `gdcmSegmentWriter.h`:



This graph shows which files directly or indirectly include this file:



Classes

- class `gdcm::SegmentWriter`
This class defines a segment writer.

Namespaces

- namespace **gdcm**

11.410 gdcmSegmentWriter.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMSEGMENTWRITER_H
00015 #define GDCMSEGMENTWRITER_H
00016
00017 #include <gdcmWriter.h>
00018 #include <gdcmSegment.h>
00019
00020 namespace gdcm
00021 {
00022
00023   class GDCM_EXPORT SegmentWriter : public Writer
00024   {
00025   public:
00026     typedef std::vector<SmartPointer<Segment>> SegmentVector;
00027
00028     SegmentWriter();
00029     ~SegmentWriter() override;
00030
00031     bool Write() override; // Set to protected ?
00032
00033     /**      Segment getters/setters      **/
00034     unsigned int GetNumberOfSegments() const;
00035     void SetNumberOfSegments(const unsigned int size);
00036
00037     const SegmentVector & GetSegments() const;
00038     SegmentVector & GetSegments();
00039     SmartPointer<Segment> GetSegment(const unsigned int idx = 0) const;
00040
00041     void AddSegment(SmartPointer<Segment> segment);
00042
00043     void SetSegments(SegmentVector & segments);
00044
00045   protected:
00046     bool PrepareWrite();
00047
00048     SegmentVector Segments;
00049   };
00050
00051 #endif // GDCMSEGMENTWRITER_H

```

11.411 gdcmSerieHelper.h File Reference

```

#include "gdcmTag.h"
#include "gdcmSmartPointer.h"
#include "gdcmFile.h"
#include <vector>
#include <string>

```


11.412 gdcmSerieHelper.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMSERIEHELPER_H
00015 #define GDCMSERIEHELPER_H
00016
00017 #include "gdcmTag.h"
00018 #include "gdcmSmartPointer.h"
00019 #include "gdcmFile.h"
00020 #include <vector>
00021 #include <string>
00022 #include <map>
00023
00024 namespace gdcm
00025 {
00026
00027   enum CompOperators {
00028     GDCM_EQUAL = 0,
00029     GDCM_DIFFERENT,
00030     GDCM_GREATER,
00031     GDCM_GREATEROREQUAL,
00032     GDCM_LESS,
00033     GDCM_LESSOREQUAL
00034   };
00035   enum LodModeType
00036   {
00037     LD_ALL          = 0x00000000,
00038     LD_NOSEQ        = 0x00000001,
00039     LD_NOSHADOW     = 0x00000002,
00040     LD_NOSHADOWSEQ = 0x00000004
00041   };
00042
00043
00044
00045
00046
00047
00048
00049
00050   class GDCM_EXPORT FileWithName : public File
00051   {
00052   public:
00053     FileWithName(File &f):File(f),filename({})
00054     std::string filename;
00055   };
00056
00057   typedef std::vector< SmartPointer<FileWithName> > FileList;
00058   typedef bool (*BOOL_FUNCTION_PFILE_PFILE_POINTER)(File *, File *);
00059   class Scanner;
00060
00061   class GDCM_EXPORT SerieHelper
00062   {
00063   public:
00064     SerieHelper();
00065     ~SerieHelper();
00066
00067     void Clear();
00068     void SetLoadMode (int ) {}
00069     void SetDirectory(std::string const &dir, bool recursive=false);
00070
00071     void AddRestriction(const std::string & tag);
00072     void SetUseSeriesDetails( bool useSeriesDetails );
00073     void CreateDefaultUniqueSeriesIdentifier();
00074     FileList *GetFirstSingleSerieUIDFileSet();
00075     FileList *GetNextSingleSerieUIDFileSet();
00076     std::string CreateUniqueSeriesIdentifier( File * inFile );
00077     void OrderFileList(FileList *fileSet);
00078     void AddRestriction(uint16_t group, uint16_t elem, std::string const &value, int op);
00079
00080   protected:
00081     bool UserOrdering(FileList *fileSet);

```

```

00089 void AddFileName(std::string const &filename);
00090 bool AddFile(FileWithName &header);
00091 void AddRestriction(const Tag& tag);
00092 bool ImagePositionPatientOrdering(FileList *fileSet);
00093 bool ImageNumberOrdering( FileList *fileList );
00094 bool FileNameOrdering( FileList *fileList );
00095
00096 using Rule = struct RuleStructure{
00097     uint16_t group;
00098     uint16_t elem;
00099     std::string value;
00100     int op;
00101 };
00102 typedef std::vector<Rule> SerieRestrictions;
00103
00104 typedef std::map<std::string, FileList *> SingleSerieUIDFileSetmap;
00105 SingleSerieUIDFileSetmap SingleSerieUIDFileSetHT;
00106 SingleSerieUIDFileSetmap::iterator ItFileSetHt;
00107
00108 private:
00109     SerieRestrictions Restrictions;
00110     SerieRestrictions Refine;
00111
00112     bool UseSeriesDetails;
00113     bool DirectOrder;
00114
00115     BOOL_FUNCTION_PFILE_PFILE_POINTER UserLessThanFunction;
00116 };
00117
00118 // backward compat
00119 } // end namespace gdcmm
00120
00121
00122 #endif //GDCMSERIEHELPER_H

```


11.413 gdcmmSimpleSubjectWatcher.h File Reference

```

#include "gdcmmSubject.h"
#include "gdcmmCommand.h"
#include "gdcmmSmartPointer.h"
#include "gdcmmAnonymizeEvent.h"
#include "gdcmmDataEvent.h"

```

Include dependency graph for gdcmSimpleSubjectWatcher.h:



Classes

- class [gdcm::SimpleSubjectWatcher](#)
SimpleSubjectWatcher.

Namespaces

- namespace [gdcm](#)

11.414 gdcmSimpleSubjectWatcher.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003 Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005 Copyright (c) 2006-2011 Mathieu Malaterre
00006 All rights reserved.
00007 See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009 This software is distributed WITHOUT ANY WARRANTY; without even
00010 the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011 PURPOSE. See the above copyright notice for more information.
00012 =====*/
00013
00014 #ifndef GDCMSIMPLESUBJECTWATCHER_H
00015 #define GDCMSIMPLESUBJECTWATCHER_H
00016

```

```

00017 #include "gdcmSubject.h"
00018 #include "gdcmCommand.h"
00019 #include "gdcmSmartPointer.h"
00020 #include "gdcmAnonymizeEvent.h"
00021 #include "gdcmDataEvent.h"
00022
00023 namespace gdcm
00024 {
00025 //-----
00026 class Event;
00031 class GDCM_EXPORT SimpleSubjectWatcher
00032 {
00033 public:
00034     SimpleSubjectWatcher(Subject * s, const char *comment = "");
00035     virtual ~SimpleSubjectWatcher();
00036     SimpleSubjectWatcher(const SimpleSubjectWatcher&) = delete;
00037     void operator=(const SimpleSubjectWatcher&) = delete;
00038
00039 protected:
00040     virtual void StartFilter();
00041     virtual void EndFilter();
00042     virtual void ShowProgress(Subject *caller, const Event &evt);
00043     virtual void ShowFileName(Subject *caller, const Event &evt);
00044     virtual void ShowIteration();
00045     virtual void ShowAnonymization(Subject *caller, const Event &evt);
00046     virtual void ShowDataSet(Subject *caller, const Event &evt);
00047     virtual void ShowData(Subject *caller, const Event &evt);
00048     virtual void ShowAbort();
00049
00050 protected:
00051     // Custom API used for internal Testing do not use !
00052     void TestAbortOn();
00053     void TestAbortOff();
00054
00055 private:
00056     SmartPointer<Subject> m_Subject;
00057     std::string m_Comment;
00058
00059     typedef SimpleMemberCommand<SimpleSubjectWatcher> SimpleCommandType;
00060     typedef MemberCommand<SimpleSubjectWatcher> CommandType;
00061
00062     SmartPointer<SimpleCommandType> m_StartFilterCommand;
00063     SmartPointer<SimpleCommandType> m_EndFilterCommand;
00064     SmartPointer<CommandType> m_ProgressFilterCommand;
00065     SmartPointer<CommandType> m_FileNameFilterCommand;
00066     SmartPointer<SimpleCommandType> m_IterationFilterCommand;
00067     SmartPointer<SimpleCommandType> m_AbortFilterCommand;
00068     SmartPointer<CommandType> m_AnonymizeFilterCommand;
00069     SmartPointer<CommandType> m_DataFilterCommand;
00070     SmartPointer<CommandType> m_DataSetFilterCommand;
00071
00072     unsigned long m_StartTag;
00073     unsigned long m_EndTag;
00074     unsigned long m_ProgressTag;
00075     unsigned long m_FileNameTag;
00076     unsigned long m_IterationTag;
00077     unsigned long m_AbortTag;
00078     unsigned long m_AnonymizeTag;
00079     unsigned long m_DataTag;
00080     unsigned long m_DataSetTag;
00081
00082     bool m_TestAbort;
00083
00084 };
00085 } // end namespace gdcm
00086 //-----
00087 #endif //GDCMSIMPLESUBJECTWATCHER_H

```

11.415 gdcmSorter.h File Reference

```


#include "gdcmDirectory.h"
#include "gdcmTag.h"
#include <vector>
#include <string>

```


```
#include <map>
```

```
#include <set>
```

Include dependency graph for gdcmSorter.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::Sorter](#)
[Sorter](#).

Namespaces

- namespace [gdcm](#)

Functions

- `std::ostream & gdcm::operator<< (std::ostream &os, const Sorter &s)`

11.416 gdcmSorter.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMSORTER_H
00015 #define GDCMSORTER_H
00016
00017 #include "gdcmDirectory.h"
00018 #include "gdcmTag.h"
00019
00020 #include <vector>
00021 #include <string>
00022 #include <map>
00023 #include <set>
00024
00025 namespace gdcm
00026 {
00027   class DataSet;
00028
00039   class GDCM_EXPORT Sorter
00040   {
00041   friend std::ostream& operator<<(std::ostream &_os, const Sorter &s);
00042   public:
00043     Sorter();
00044     virtual ~Sorter();
00045
00047     virtual bool Sort(std::vector<std::string> const & filenames);
00048
00051     const std::vector<std::string> &GetFilenames() const { return Filenames; }
00052
00054     void Print(std::ostream &os) const;
00055
00057     bool AddSelect( Tag const &tag, const char *value );
00058
00062     void SetTagsToRead( std::set<Tag> const & tags );
00063
00065     typedef bool (*SortFunction)(DataSet const &, DataSet const &);
00066     void SetSortFunction( SortFunction f );
00067
00068     virtual bool StableSort(std::vector<std::string> const & filenames);
00069
00070   protected:
00071     std::vector<std::string> Filenames;
00072     typedef std::map<Tag, std::string> SelectionMap;
00073     std::map<Tag, std::string> Selection;
00074     SortFunction SortFunc;
00075     std::set<Tag> TagsToRead;
00076   };
00077   //-----
00078   inline std::ostream& operator<<(std::ostream &os, const Sorter &s)
00079   {
00080     s.Print( os );
00081     return os;
00082   }
00083
00084
00085 } // end namespace gdcm
00086
00087 #endif //GDCMSORTER_H

```


Classes

- class [gdcm::Spectroscopy](#)
Spectroscopy class.

Namespaces

- namespace [gdcm](#)

11.420 gdcmSpectroscopy.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013   =====*/
00014 #ifndef GDCMSPECTROSCOPY_H
00015 #define GDCMSPECTROSCOPY_H
00016
00017 #include "gdcmFile.h"
00018
00019 namespace gdcm
00020 {
00021
00024   class GDCM_EXPORT Spectroscopy
00025   {
00026   public:
00027     Spectroscopy() = default;
00028
00029   private:
00030   };
00031
00032 } // end namespace gdcm
00033
00034 #endif //GDCMSPECTROSCOPY_H

```

11.421 gdcmSplitMosaicFilter.h File Reference

```

#include "gdcmFile.h"
#include "gdcmImage.h"

```



```
00045 public:
00046     SplitMosaicFilter();
00047     ~SplitMosaicFilter();
00048
00050     bool Split();
00051
00054     bool ComputeMOSAICDimensions(unsigned int dims[3]);
00055
00057     bool ComputeMOSAICSliceNormal( double dims[3], bool & inverted );
00058
00061     bool ComputeMOSAICSlicePosition( double pos[3], bool inverted );
00062
00064     bool ComputeMOSAICImagePositionPatient( double pos[3],
00065         const double ipp[6],
00066         const double dircos[6],
00067         const double pixelspacing[3],
00068         const unsigned int image_dims[3] ,
00069         const unsigned int mosaic_dims[3], bool inverted );
00070
00071     void SetImage(const Image& image);
00072     const Image &GetImage() const { return *I; }
00073     Image &GetImage() { return *I; }
00074
00075     void SetFile(const File& f) { F = f; }
00076     File &GetFile() { return *F; }
00077     const File &GetFile() const { return *F; }
00078
00080     static bool GetAcquisitionSize(unsigned int size[2], DataSet const & ds);
00081
00083     static unsigned int GetNumberOfImagesInMosaic( File const & file );
00084
00086     static const DataElement& ComputeCSAImageHeaderInfo(const DataSet& ds, bool handleMissingPrivateCreator
= true);
00087
00089     static const DataElement& ComputeCSASeriesHeaderInfo(const DataSet& ds, bool handleMissingPrivateCreator
= true);
00090
00091 protected:
00092
00093 private:
00094     SmartPointer<File> F;
00095     SmartPointer<Image> I;
00096 };
00097
00098 } // end namespace gdcm
00099
00100 #endif //GDCMSPLITMOSAICFILTER_H
```



```

00020
00021 #include "gdcmReader.h"
00022
00023 namespace gdcm
00024 {
00025
00026 class MediaStorage;
00038 class GDCM_EXPORT StreamImageReader
00039 {
00040
00041 public:
00042     StreamImageReader();
00043     virtual ~StreamImageReader();
00044
00048     void SetFileName(const char* inFileName);
00049     void SetStream(std::istream& inStream);
00050
00051     std::vector<unsigned int> GetDimensionsValueForResolution( unsigned int  );
00052
00060     void DefinePixelExtent(uint16_t inXMin, uint16_t inXMax,
00061         uint16_t inYMin, uint16_t inYMax, uint16_t inZMin = 0, uint16_t inZMax = 1);
00062
00067     uint32_t DefineProperBufferLength() const;
00068
00076     bool Read(char* inReadBuffer, const std::size_t& inBufferLength);
00077
00083     bool CanReadImage() const;
00084
00088     virtual bool ReadImageInformation();
00089
00093     File const & GetFile() const;
00094
00095 protected:
00096 private:
00097     //contains a reader for being able to ReadUpToTag
00098     //however, we don't want the user to be able to call Read
00099     //either directly or via a parent class call, so we hide the reader in here.
00100     Reader mReader;
00101
00102     std::streamoff mFileOffset; //the file offset for getting header information
00103     #if 0
00104     std::streamoff mFileOffset1;
00105     #endif
00106     DataSet mHeaderInformation; //all the non-pixel information
00107
00108     //for thread safety, these should not be stored here, but should be used
00109     //for every read subregion operation.
00110     uint16_t mXMin, mYMin, mXMax, mYMax, mZMin, mZMax;
00111
00116     bool ReadImageSubregionRAW(char* inReadBuffer, const std::size_t& inBufferLength);
00117
00120     bool ReadImageSubregionJpegLS(char* inReadBuffer, const std::size_t& inBufferLength);
00121 };
00122
00123 } // end namespace gdcm
00124
00125 #endif //GDCMSTREAMIMAGEREADER_H
00126

```


11.425 gdcmStreamImageWriter.h File Reference

```

#include "gdcmWriter.h"
#include <iostream>
#include "gdcmDataSet.h"

```

Include dependency graph for `gdcmStreamImageWriter.h`:



Classes

- class `gdcm::StreamImageWriter`
StreamImageReader.

Namespaces

- namespace `gdcm`

11.426 gdcmStreamImageWriter.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002  *
00003  *   Copyright NumFOCUS
00004  *
00005  *   Licensed under the Apache License, Version 2.0 (the "License");
00006  *   you may not use this file except in compliance with the License.
00007  *   You may obtain a copy of the License at
00008  *
00009  *       http://www.apache.org/licenses/LICENSE-2.0.txt
00010  *
00011  *   Unless required by applicable law or agreed to in writing, software
00012  *   distributed under the License is distributed on an "AS IS" BASIS,
00013  *   WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied.
00014  *   See the License for the specific language governing permissions and
00015  *   limitations under the License.
00016  *
00017  *===== */
00018
00019 #ifndef GDCMSTREAMIMAGEWRITER_H
00020 #define GDCMSTREAMIMAGEWRITER_H
00021
00022 #include "gdcmWriter.h"
00023 #include <iostream>

```



```

00024 #include "gdcmDataSet.h"
00025
00026 namespace gdcm
00027 {
00028
00029 class MediaStorage;
00030 class RAWCodec;
00042 class GDCM_EXPORT StreamImageWriter
00043 {
00044
00045 public:
00046     StreamImageWriter();
00047     virtual ~StreamImageWriter();
00048
00049
00053     void SetFileName(const char* inFileName);
00054     void SetStream(std::ostream& inStream);
00055
00064     void DefinePixelExtent(uint16_t inXMin, uint16_t inXMax,
00065         uint16_t inYMin, uint16_t inYMax, uint16_t inZMin = 0, uint16_t inZMax = 1);
00066
00067
00073     uint32_t DefineProperBufferLength();
00074
00082     bool Write(void* inWriteBuffer, const std::size_t& inBufferLength);
00083
00087     virtual bool WriteImageInformation();
00088
00092     bool CanWriteFile() const;
00093
00094
00097     void SetFile(const File& inFile);
00098
00099 protected:
00100
00101     //contains the PrepareWrite function, which will get the given dataset ready
00102     //for writing to disk by manufacturing the header information.
00103     //note that if there is a pixel element in the given dataset, that will be removed
00104     //during the copy, so that the imagewriter can write everything else out
00105     Writer mWriter;
00106
00107     //is the offset necessary if we always append?
00108     //std::streamoff mFileOffset; //the fileoffset for getting header information
00109     SmartPointer<File> mspFile; //all the non-pixel information
00110
00111     //for thread safety, these should not be stored here, but should be used
00112     //for every read subregion operation.
00113     uint16_t mXMin, mYMin, mXMax, mYMax, mZMin, mZMax;
00114
00119     //virtual bool ReadImageSubregionRAW(std::ostream& os);
00120     virtual bool WriteImageSubregionRAW(char* inWriteBuffer, const std::size_t& inBufferLength);
00121
00131     int WriteRawHeader(RAWCodec* inCodec, std::ostream* inStream);
00132
00137     int mElementOffsets;
00138     int mElementOffsets1;
00139
00140 };
00141
00142
00143 } // end namespace gdcm
00144
00145 #endif //GDCMSTREAMIMAGEWRITER_H

```

11.427 gdcmStrictScanner.h File Reference

```

#include "gdcmDirectory.h"
#include "gdcmSubject.h"
#include "gdcmTag.h"
#include "gdcmPrivateTag.h"
#include "gdcmSmartPointer.h"
#include <map>

```



```

00018 #include "gdcmSubject.h"
00019 #include "gdcmTag.h"
00020 #include "gdcmPrivateTag.h"
00021 #include "gdcmSmartPointer.h"
00022
00023 #include <map>
00024 #include <set>
00025 #include <string>
00026
00027 #include <string.h> // strcmp
00028
00029 namespace gdcm
00030 {
00031   class StringFilter;
00032
00033   class GDCM_EXPORT StrictScanner : public Subject
00034   {
00035   {
00036     friend std::ostream& operator<<(std::ostream &_os, const StrictScanner &s);
00037   public:
00038     StrictScanner():Values(),FileNames(),Mappings(),Progress(0.0) {}
00039     ~StrictScanner() override;
00040
00041     typedef std::map<Tag, const char*> TagToValue;
00042     //typedef std::map<Tag, ConstCharWrapper> TagToValue; //StringMap;
00043     //typedef TagToStringMap TagToValue;
00044     typedef TagToValue::value_type TagToValueValueType;
00045
00046     void AddTag( Tag const & t );
00047     void ClearTags();
00048
00049     // Work in progress do not use:
00050     void AddPrivateTag( PrivateTag const & t );
00051
00052     void AddSkipTag( Tag const & t );
00053     void ClearSkipTags();
00054
00055     bool Scan( Directory::FileNamesType const & filenames );
00056
00057     Directory::FileNamesType const &GetFileNames() const { return FileNames; }
00058
00059     void Print( std::ostream & os ) const override;
00060
00061     void PrintTable( std::ostream & os ) const;
00062
00063     bool IsKey( const char * filename ) const;
00064
00065     Directory::FileNamesType GetKeys() const;
00066
00067     // struct to store all the values found:
00068     typedef std::set< std::string > ValueType;
00069
00070     ValueType const & GetValues() const { return Values; }
00071
00072     ValueType GetValues(Tag const &t) const;
00073
00074     Directory::FileNamesType GetOrderedValues(Tag const &t) const;
00075
00076     /* ltstr is CRITICAL, otherwise pointers value are used to do the key comparison */
00077     struct ltstr
00078     {
00079     {
00080       bool operator()(const char* s1, const char* s2) const
00081       {
00082         gdcm_assert( s1 && s2 );
00083         return strcmp(s1, s2) < 0;
00084       }
00085     };
00086
00087     typedef std::map<const char *,TagToValue, ltstr> MappingType;
00088     typedef MappingType::const_iterator ConstIterator;
00089     ConstIterator Begin() const { return Mappings.begin(); }
00090     ConstIterator End() const { return Mappings.end(); }
00091
00092     MappingType const & GetMappings() const { return Mappings; }
00093
00094     TagToValue const & GetMapping(const char *filename) const;
00095
00096     const char *GetFilenameFromTagToValue(Tag const &t, const char *valueref) const;
00097
00098     Directory::FileNamesType GetAllFileNamesFromTagToValue(Tag const &t, const char *valueref) const;
00099
00100     // by a call to GetMapping()
00101     TagToValue const & GetMappingFromTagToValue(Tag const &t, const char *value) const;

```

```

00148
00154     const char* GetValue(const char *filename, Tag const &t) const;
00155
00157     static SmartPointer<StrictScanner> New() { return new StrictScanner; }
00158
00159 protected:
00160     void ProcessPublicTag(StringFilter &sf, const char *filename);
00161 private:
00162     // struct to store all uniq tags in ascending order:
00163     typedef std::set< Tag > TagsType;
00164     typedef std::set< PrivateTag > PrivateTagsType;
00165     std::set< Tag > Tags;
00166     std::set< PrivateTag > PrivateTags;
00167     std::set< Tag > SkipTags;
00168     ValueType Values;
00169     Directory::FileNamesType Filenames;
00170
00171     // Main struct that will hold all mapping:
00172     MappingType Mappings;
00173
00174     double Progress;
00175 };
00176 //-----
00177 inline std::ostream& operator<<(std::ostream &os, const StrictScanner &s)
00178 {
00179     s.Print( os );
00180     return os;
00181 }
00182
00183 } // end namespace gdcms
00184
00185 #endif //GDCMSTRICTSCANNER_H

```


11.429 gdcmsStrictScanner2.h File Reference

```

#include "gdcmsDirectory.h"
#include "gdcmsPrivateTag.h"
#include "gdcmsSmartPointer.h"
#include "gdcmsSubject.h"
#include "gdcmsTag.h"
#include <map>
#include <set>
#include <string>
#include <string.h>

```

Include dependency graph for gdcmsStrictScanner2.h:



Classes

- struct `gdcm::StrictScanner2::Itstr`
- class `gdcm::StrictScanner2`
StrictScanner2.

Namespaces

- namespace `gdcm`

Functions

- `std::ostream & gdcm::operator<< (std::ostream &os, const StrictScanner2 &s)`

11.430 gdcmStrictScanner2.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003     Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005     Copyright (c) 2006-2011 Mathieu Malaterre
00006     All rights reserved.
00007     See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009     This software is distributed WITHOUT ANY WARRANTY; without even
00010     the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011     PURPOSE. See the above copyright notice for more information.
00012
00013     =====*/
00014 #ifndef GDCMSTRICTSCANNER2_H
00015 #define GDCMSTRICTSCANNER2_H
00016
00017 #include "gdcmDirectory.h"
00018 #include "gdcmPrivateTag.h"
00019 #include "gdcmSmartPointer.h"
00020 #include "gdcmSubject.h"
00021 #include "gdcmTag.h"
00022
00023 #include <map>
00024 #include <set>
00025 #include <string>
00026
00027 #include <string.h> // strcmp
00028
00029 namespace gdcm {
00030 class StringFilter;
00031
00032 class GDCM_EXPORT StrictScanner2 : public Subject {
00033     friend std::ostream &operator<<(std::ostream &_os, const StrictScanner2 &s);
00034
00035 public:
00036     StrictScanner2() : Values(), Filenames(), PublicMappings(), PrivateMappings(), Progress(0.0) {}
00037     ~StrictScanner2() override;
00038
00039     typedef std::map<Tag, const char *> PublicTagToValue;
00040     typedef PublicTagToValue::value_type PublicTagToValueValueType;
00041
00042     typedef std::map<PrivateTag, const char *> PrivateTagToValue;
00043     typedef PrivateTagToValue::value_type PrivateTagToValueValueType;
00044
00045     bool AddPublicTag(Tag const &t);
00046     void ClearPublicTags();
00047
00048

```

```

00075 // Work in progress do not use:
00076 bool AddPrivateTag(PrivateTag const &pt);
00077 void ClearPrivateTags();
00078
00080 bool AddSkipTag(Tag const &t);
00081 void ClearSkipTags();
00082
00084 bool Scan(Directory::FileNamesType const &filenames);
00085
00087 Directory::FileNamesType const &GetFileNames() const { return Filenames; }
00088
00090 void Print(std::ostream &os) const override;
00091
00093 void PrintTable(std::ostream &os, bool header = false) const;
00094
00098 bool IsKey(const char *filename) const;
00099
00102 Directory::FileNamesType GetKeys() const;
00103
00104 // struct to store all the values found:
00105 typedef std::set<std::string> ValueType;
00106
00108 ValueType const &GetValues() const { return Values; }
00109
00111 ValueType GetPublicValues(Tag const &t) const;
00112
00115 ValueType GetPrivateValues(PrivateTag const &pt) const;
00116
00120 Directory::FileNamesType GetPublicOrderedValues(Tag const &t) const;
00121
00122 Directory::FileNamesType GetPrivateOrderedValues(PrivateTag const &pt) const;
00123
00124 /* ltstr is CRITICAL, otherwise pointers value are used to do the key
00125  * comparison */
00126 struct ltstr {
00127     bool operator()(const char *s1, const char *s2) const {
00128         gdcmm_assert(s1 && s2);
00129         return strcmp(s1, s2) < 0;
00130     }
00131 };
00132 typedef std::map<const char *, PublicTagToValue, ltstr> PublicMappingType;
00133 typedef PublicMappingType::const_iterator PublicConstIterator;
00134 PublicConstIterator Begin() const { return PublicMappings.begin(); }
00135 PublicConstIterator End() const { return PublicMappings.end(); }
00136
00137 typedef std::map<const char *, PrivateTagToValue, ltstr> PrivateMappingType;
00138 typedef PrivateMappingType::const_iterator PrivateConstIterator;
00139 PrivateConstIterator PrivateBegin() const { return PrivateMappings.begin(); }
00140 PrivateConstIterator PrivateEnd() const { return PrivateMappings.end(); }
00141
00144 PublicMappingType const &GetPublicMappings() const { return PublicMappings; }
00145 PrivateMappingType const &GetPrivateMappings() const {
00146     return PrivateMappings;
00147 }
00148
00150 PublicTagToValue const &GetPublicMapping(const char *filename) const;
00151 PrivateTagToValue const &GetPrivateMapping(const char *filename) const;
00152
00155 const char *GetFilenameFromPublicTagToValue(Tag const &t,
00156                                             const char *valueref) const;
00157 const char *GetFilenameFromPrivateTagToValue(PrivateTag const &pt,
00158                                              const char *valueref) const;
00159
00162 Directory::FileNamesType GetAllFileNamesFromPublicTagToValue(
00163     Tag const &t, const char *valueref) const;
00164 Directory::FileNamesType GetAllFileNamesFromPrivateTagToValue(
00165     PrivateTag const &pt, const char *valueref) const;
00166
00169 // by a call to GetMapping()
00170 PublicTagToValue const &GetMappingFromPublicTagToValue(
00171     Tag const &t, const char *value) const;
00172 PrivateTagToValue const &GetMappingFromPrivateTagToValue(
00173     PrivateTag const &pt, const char *value) const;
00174
00180 const char *GetPublicValue(const char *filename, Tag const &t) const;
00181 const char *GetPrivateValue(const char *filename, PrivateTag const &t) const;
00182
00184 static SmartPointer<StrictScanner2> New() { return new StrictScanner2; }
00185
00186 protected:
00187 void ProcessPublicTag(StringFilter &sf, const char *filename);

```

```

00188 void ProcessPrivateTag(StringFilter &sf, const char *filename);
00189
00190 private:
00191 // struct to store all uniq tags in ascending order:
00192 typedef std::set<Tag> PublicTagsType;
00193 typedef std::set<PrivateTag> PrivateTagsType;
00194 std::set<Tag> PublicTags; // Public and Private Creator
00195 std::set<PrivateTag> PrivateTags; // Only Private (no Private Creator)
00196 std::set<Tag> SkipTags;
00197 ValueType Values;
00198 Directory::FileNamesType Filenames;
00199
00200 // Main struct that will hold all public mapping:
00201 PublicMappingType PublicMappings;
00202 // Main struct that will hold all private mapping:
00203 PrivateMappingType PrivateMappings;
00204
00205 double Progress;
00206 };
00207 //-----
00208 inline std::ostream &operator<<(std::ostream &os, const StrictScanner2 &s) {
00209     s.Print(os);
00210     return os;
00211 }
00212
00213 } // end namespace gdcm
00214
00215 #endif // GDCMSTRICTSCANNER2_H

```


11.431 gdcmStringFilter.h File Reference

```
#include "gdcmDataElement.h"
```

```
#include "gdcmDicts.h"
```

```
#include "gdcmFile.h"
```

Include dependency graph for gdcmStringFilter.h:



Classes

- class `gdcm::StringFilter`
StringFilter.

Namespaces

- namespace `gdcm`

11.432 gdcmStringFilter.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMSTRINGFILTER_H
00015 #define GDCMSTRINGFILTER_H
00016
00017 #include "gdcmDataElement.h"
00018 #include "gdcmDicts.h"
00019 #include "gdcmFile.h"
00020
00021 namespace gdcm
00022 {
00023
00029   class GDCM_EXPORT StringFilter
00030   {
00031   public:
00032     StringFilter();
00033     ~StringFilter();
00034
00036     void UseDictAlways(bool) {}
00037
00039     void SetDicts(const Dicts &dicts);
00040
00044     std::string ToString(const DataElement& de) const;
00045
00047     std::string ToString(const Tag& t) const;
00048
00049     std::string ToString(const PrivateTag& t) const;
00050
00055     std::pair<std::string, std::string> ToStringPair(const DataElement& de) const;
00057     std::pair<std::string, std::string> ToStringPair(const Tag& t) const;
00058
00060     std::string FromString(const Tag&t, const char * value, size_t len);
00061
00063     void SetFile(const File& f) { F = f; }
00064     File &GetFile() { return *F; }
00065     const File &GetFile() const { return *F; }
00066
00070     bool ExecuteQuery(std::string const &query, std::string & value) const;
00071
00072   protected:
00073     std::pair<std::string, std::string> ToStringPair(const Tag& t, DataSet const &ds) const;
00074     bool ExecuteQuery(std::string const &query, DataSet const &ds, std::string & value) const;
00075
00076   private:
00077     std::pair<std::string, std::string> ToStringPairInternal(const DataElement& de, DataSet const &ds)
00078     const;
00078     SmartPointer<File> F;
00079   };
00080
00081 } // end namespace gdcm
00082
00083 #endif //GDCMSTRINGFILTER_H

```

11.433 gdcmSurface.h File Reference


```

#include <gdcmObject.h>
#include <gdcmDataElement.h>


```



```
#include <gdcMESHPrimitive.h>
#include "gdcSegmentHelper.h"
Include dependency graph for gdcSurface.h:
```



This graph shows which files directly or indirectly include this file:



Classes

- class `gdcm::Surface`
This class defines a SURFACE IE.

Namespaces

- namespace **gdcm**

11.434 gdcmSurface.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMSURFACE_H
00015 #define GDCMSURFACE_H
00016
00017 #include <gdcmObject.h>
00018 #include <gdcmDataElement.h>
00019 #include <gdcmMeshPrimitive.h>
00020 #include "gdcmSegmentHelper.h" // for BasicCodedEntry
00021
00022 namespace gdcm
00023 {
00024
00025 class GDCM_EXPORT Surface : public Object
00026 {
00027 public:
00028
00029     typedef enum {
00030         NO = 0,
00031         YES,
00032         UNKNOWN,
00033         STATES_END
00034     } STATES;
00035
00036     static const char * GetSTATESString(STATES state);
00037     static STATES GetSTATES(const char * state);
00038
00039     typedef enum {
00040         SURFACE = 0,
00041         WIREFRAME,
00042         POINTS,
00043         VIEWType_END
00044     } VIEWType;
00045
00046     static const char * GetVIEWTypeString(VIEWType type);
00047     static VIEWType GetVIEWType(const char * type);
00048
00049     Surface();
00050
00051     ~Surface() override;
00052
00053     /** Common getters/setters */
00054     unsigned long GetSurfaceNumber() const;
00055     void SetSurfaceNumber(const unsigned long nb);
00056
00057     const char * GetSurfaceComments() const;
00058     void SetSurfaceComments(const char * comment);
00059
00060     bool GetSurfaceProcessing() const;
00061     void SetSurfaceProcessing(bool b);
00062
00063     float GetSurfaceProcessingRatio() const;
00064     void SetSurfaceProcessingRatio(const float ratio);
00065
00066     const char * GetSurfaceProcessingDescription() const;
00067     void SetSurfaceProcessingDescription(const char * description);
00068
00069     SegmentHelper::BasicCodedEntry const & GetProcessingAlgorithm() const;
00070     SegmentHelper::BasicCodedEntry & GetProcessingAlgorithm();
00071     void SetProcessingAlgorithm(SegmentHelper::BasicCodedEntry const & BSE);
00072
00073     unsigned short GetRecommendedDisplayGrayscaleValue() const;
00074     void SetRecommendedDisplayGrayscaleValue(const unsigned short vl);
00075
00076

```

```

00087     const unsigned short * GetRecommendedDisplayCIELabValue() const;
00088     unsigned short GetRecommendedDisplayCIELabValue(const unsigned int idx) const;
00089     void SetRecommendedDisplayCIELabValue(const unsigned short vl[3]);
00090     void SetRecommendedDisplayCIELabValue(const unsigned short vl, const unsigned int idx = 0);
00091     void SetRecommendedDisplayCIELabValue(const std::vector< unsigned short > & vl);
00092
00093     float GetRecommendedPresentationOpacity() const;
00094     void SetRecommendedPresentationOpacity(const float opacity);
00095
00096     VIEWType GetRecommendedPresentationType() const;
00097     void SetRecommendedPresentationType(VIEWType type);
00098
00099     STATES GetFiniteVolume() const;
00100     void SetFiniteVolume(STATES state);
00101
00102     STATES GetManifold() const;
00103     void SetManifold(STATES state);
00104
00105     SegmentHelper::BasicCodedEntry const & GetAlgorithmFamily() const;
00106     SegmentHelper::BasicCodedEntry & GetAlgorithmFamily();
00107     void SetAlgorithmFamily(SegmentHelper::BasicCodedEntry const & BSE);
00108
00109     const char * GetAlgorithmVersion() const;
00110     void SetAlgorithmVersion(const char * str);
00111
00112     const char * GetAlgorithmName() const;
00113     void SetAlgorithmName(const char * str);
00114
00115     /** Points getters/setters */
00116     unsigned long GetNumberOfSurfacePoints() const;
00117     void SetNumberOfSurfacePoints(const unsigned long nb);
00118
00119     const DataElement & GetPointCoordinatesData() const;
00120     DataElement & GetPointCoordinatesData();
00121
00122     void SetPointCoordinatesData(DataElement const & de);
00123
00127     const float * GetPointPositionAccuracy() const;
00128     void SetPointPositionAccuracy(const float * accuracies);
00129
00130     float GetMeanPointDistance() const;
00131     void SetMeanPointDistance(float average);
00132
00133     float GetMaximumPointDistance() const;
00134     void SetMaximumPointDistance(float maximum);
00135
00139     const float * GetPointsBoundingBoxCoordinates() const;
00140     void SetPointsBoundingBoxCoordinates(const float * coordinates);
00141
00145     const float * GetAxisOfRotation() const;
00146     void SetAxisOfRotation(const float * axis);
00147
00151     const float * GetCenterOfRotation() const;
00152     void SetCenterOfRotation(const float * center);
00153
00154     /** Vectors getters/setters */
00155     unsigned long GetNumberOfVectors() const;
00156     void SetNumberOfVectors(const unsigned long nb);
00157
00158     unsigned short GetVectorDimensionality() const;
00159     void SetVectorDimensionality(const unsigned short dim);
00160
00161     const float * GetVectorAccuracy() const;
00162     void SetVectorAccuracy(const float * accuracy);
00163
00164     const DataElement & GetVectorCoordinateData() const;
00165     DataElement & GetVectorCoordinateData();
00166
00167     void SetVectorCoordinateData(DataElement const & de);
00168
00169     /** Primitive getters/setters */
00170     MeshPrimitive const & GetMeshPrimitive() const;
00171     MeshPrimitive & GetMeshPrimitive();
00172
00173     void SetMeshPrimitive(MeshPrimitive const & mp);
00174
00175 private:
00176
00177     /** Common members */
00178
00179     /**0066 0003 UL 1 Surface Number

```

```

00180 unsigned long SurfaceNumber;
00181 //0066 0004 LT 1 Surface Comments
00182 std::string SurfaceComments;
00183
00184 //0066 0009 CS 1 Surface Processing
00185 bool SurfaceProcessing;
00186 //0066 000a FL 1 Surface Processing Ratio
00187 float SurfaceProcessingRatio;
00188 //0066 000b LO 1 Surface Processing Description
00189 std::string SurfaceProcessingDescription;
00190 // Processing Algorithm Code
00191 SegmentHelper::BasicCodedEntry ProcessingAlgorithm;
00192
00193 //0062 000c US 1 Recommended Display Grayscale Value
00194 unsigned short RecommendedDisplayGrayscaleValue;
00195 //0062 000d US 3 Recommended Display CIELab Value
00196 unsigned short RecommendedDisplayCIELabValue[3];
00197
00198 // 0066 000c FL 1 Recommended Presentation Opacity
00199 float RecommendedPresentationOpacity;
00200 // 0066 000d CS 1 Recommended Presentation Type
00201 VIEWType RecommendedPresentationType;
00202
00203 //0066 000e CS 1 Finite Volume
00204 STATES FiniteVolume;
00205 //0066 0010 CS 1 Manifold
00206 STATES Manifold;
00207
00208 // Algorithm Family Code
00209 SegmentHelper::BasicCodedEntry AlgorithmFamily;
00210
00211 //0066 0031 LO 1 Algorithm Version
00212 std::string AlgorithmVersion;
00213 //0066 0032 LT 1 Algorithm Parameters
00214 //0066 0036 LO 1 Algorithm Name
00215 std::string AlgorithmName;
00216
00217
00218 /** Point members */
00219
00220 //0066 0015 UL 1 Number of Surface Points
00221 unsigned long NumberOfSurfacePoints;
00222 //0066 0016 OF 1 Point Coordinates Data
00223 DataElement PointCoordinatesData;
00224 //0066 0017 FL 3 Point Position Accuracy
00225 float * PointPositionAccuracy;
00226 //0066 0018 FL 1 Mean Point Distance
00227 float MeanPointDistance;
00228 //0066 0019 FL 1 Maximum Point Distance
00229 float MaximumPointDistance;
00230 //0066 001a FL 6 Points Bounding Box Coordinates
00231 float * PointsBoundingBoxCoordinates;
00232 //0066 001b FL 3 Axis of Rotation
00233 float * AxisOfRotation;
00234 //0066 001c FL 3 Center of Rotation
00235 float * CenterOfRotation;
00236
00237
00238 /** Normal members */
00239
00240 //0066 001e UL 1 Number of Vectors
00241 unsigned long NumberOfVectors;
00242 //0066 001f US 1 Vector Dimensionality
00243 unsigned short VectorDimensionality;
00244 //0066 0020 FL 1-n Vector Accuracy
00245 float * VectorAccuracy;
00246 //0066 0021 OF 1 Vector Coordinate Data
00247 DataElement VectorCoordinateData;
00248
00249
00250 /** Primitive members */
00251 SmartPointer< MeshPrimitive > Primitive;
00252 };
00253
00254 }
00255
00256 #endif // GDCMSURFACE_H

```


11.435 gdcmSurfaceHelper.h File Reference

```
#include "gdcmTypes.h"
```

```
#include <vector>
```

```
#include <iostream>
```

Include dependency graph for gdcmSurfaceHelper.h:



Classes

- class [gdcm::SurfaceHelper](#)
SurfaceHelper.

Namespaces

- namespace [gdcm](#)

11.436 gdcmSurfaceHelper.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2017 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013  =====*/
00014 #ifndef GDCMSURFACEHELPER_H
00015 #define GDCMSURFACEHELPER_H
00016
00017 #include "gdcmTypes.h" // for GDCM_EXPORT
00018

```

```

00019 #include <vector>
00020 #include <iostream>
00021
00022 namespace gdcm
00023 {
00024
00029 class GDCM_EXPORT SurfaceHelper
00030 {
00031 public:
00032
00033     typedef std::vector< unsigned short > ColorArray;
00034
00046     template <typename T, typename U>
00047     static unsigned short RGBToRecommendedDisplayGrayscale(const std::vector<T> & RGB,
00048                                                            const U rangeMax = 255);
00060     template <typename T, typename U>
00061     static ColorArray RGBToRecommendedDisplayCIELab(const std::vector<T> & RGB,
00062                                                     const U rangeMax = 255);
00074     template <typename T, typename U>
00075     static std::vector<T> RecommendedDisplayCIELabToRGB(const ColorArray & CIELab,
00076                                                         const U rangeMax = 255);
00087     template <typename U>
00088     static std::vector<float> RecommendedDisplayCIELabToRGB(const ColorArray & CIELab,
00089                                                            const U rangeMax = 255);
00090
00091 private:
00092
00093     static std::vector< float > RGBToXYZ(const std::vector<float> & RGB);
00094
00095     static std::vector< float > XYZToRGB(const std::vector<float> & XYZ);
00096
00097     static std::vector< float > XYZToCIELab(const std::vector<float> & XYZ);
00098
00099     static std::vector< float > CIELabToXYZ(const std::vector<float> & CIELab);
00100 };
00101
00102 template <typename T, typename U>
00103 unsigned short SurfaceHelper::RGBToRecommendedDisplayGrayscale(const std::vector<T> & RGB,
00104                                                                const U rangeMax/* = 255*/)
00105 {
00106     gdcm_assert(RGB.size() > 2);
00107
00108     unsigned short Grayscale = 0;
00109
00110     const float inverseRangeMax = 1.0f / (float) rangeMax;
00111
00112     // 0xFFFF "=" 255 "=" white
00113     Grayscale = (unsigned short) ((0.2989 * RGB[0] + 0.5870 * RGB[1] + 0.1140 * RGB[2])
00114                                  * inverseRangeMax // Convert to range 0-1
00115                                  * 0xFFFF);        // Convert to range 0x0000-0xFFFF
00116
00117     return Grayscale;
00118 }
00119
00120 template <typename T, typename U>
00121 SurfaceHelper::ColorArray SurfaceHelper::RGBToRecommendedDisplayCIELab(const std::vector<T> & RGB,
00122                                                                           const U rangeMax/* = 255*/)
00123 {
00124     gdcm_assert(RGB.size() > 2);
00125
00126     ColorArray CIELab(3);
00127     std::vector<float> tmp(3);
00128
00129     // Convert to range 0-1
00130     const float inverseRangeMax = 1.0f / (float) rangeMax;
00131     tmp[0] = (float) (RGB[0] * inverseRangeMax);
00132     tmp[1] = (float) (RGB[1] * inverseRangeMax);
00133     tmp[2] = (float) (RGB[2] * inverseRangeMax);
00134
00135     tmp = SurfaceHelper::XYZToCIELab( SurfaceHelper::RGBToXYZ( tmp ) );
00136
00137     // Convert to range 0x0000-0xFFFF
00138     // 0xFFFF "=" 127, 0x8080 "=" 0, 0x0000 "=" -128
00139     CIELab[0] = (unsigned short) ( 0xFFFF * (tmp[0]*0.01f));
00140     if(tmp[1] >= -128 && tmp[1] <= 0)
00141     {
00142         CIELab[1] = (unsigned short) (((float) (0x8080)/128.0f)*tmp[1] + ((float) 0x8080));
00143     }
00144     else if(tmp[1] <= 127 && tmp[1] > 0)
00145     {
00146         CIELab[1] = (unsigned short) (((float) (0xFFFF - 0x8080)/127.0f)*tmp[1] + (float) (0x8080));
00147     }
00148 }

```

```

00147     }
00148     if(tmp[2] >= -128 && tmp[2] <= 0)
00149     {
00150         CIELab[2] = (unsigned short)(((float)0x8080/128.0f)*tmp[2] + ((float)0x8080));
00151     }
00152     else if(tmp[2] <= 127 && tmp[2] > 0)
00153     {
00154         CIELab[2] = (unsigned short)(((float)(0xFFFF - 0x8080)/127.0f)*tmp[2] + (float)(0x8080));
00155     }
00156     return CIELab;
00157 }
00158
00159 template <typename T, typename U>
00160 std::vector<T> SurfaceHelper::RecommendedDisplayCIELabToRGB(const ColorArray & CIELab,
00161                                                            const U rangeMax/* = 255*/)
00162 {
00163     gdcm_assert(CIELab.size() > 2);
00164     std::vector<T> RGB(3);
00165     std::vector<float> tmp(3);
00166     // Convert to range 0-1
00167     tmp[0] = 100.0f*CIELab[0] / (float)(0xFFFF);
00168     if(CIELab[1] <= 0x8080)
00169     {
00170         tmp[1] = (float)((CIELab[1] - 0x8080) * 128.0f) / (float)0x8080;
00171     }
00172     else
00173     {
00174         tmp[1] = (float)((CIELab[1]-0x8080)*127.0f / (float)(0xFFFF - 0x8080));
00175     }
00176     if(CIELab[2] <= 0x8080)
00177     {
00178         tmp[2] = (float)((CIELab[2] - 0x8080) * 128.0f) / (float)0x8080;
00179     }
00180     else
00181     {
00182         tmp[2] = (float)((CIELab[2]-0x8080)*127.0f / (float)(0xFFFF - 0x8080));
00183     }
00184     tmp = SurfaceHelper::XYZToRGB( SurfaceHelper::CIELabToXYZ( tmp ) );
00185     // Convert to range 0-rangeMax
00186     RGB[0] = (T) (tmp[0] * rangeMax);
00187     RGB[1] = (T) (tmp[1] * rangeMax);
00188     RGB[2] = (T) (tmp[2] * rangeMax);
00189     return RGB;
00190 }
00191
00192 template <typename U>
00193 std::vector<float> SurfaceHelper::RecommendedDisplayCIELabToRGB(const ColorArray & CIELab,
00194                                                                const U rangeMax/* = 255*/)
00195 {
00196     return RecommendedDisplayCIELabToRGB<float>(CIELab, rangeMax);
00197 }
00198
00199 // end namespace gdcm
00200 #endif // GDCMSURFACEHELPER_H

```

11.437 gdcmSurfaceReader.h File Reference

```

#include <gdcmSegmentReader.h>
#include <gdcmSurface.h>

```

- class `gdcm::SurfaceReader`
This class defines a SURFACE IE reader.

- namespace **gdcm**

[Go to the documentation of this file.](#)

Generated by Doxygen

11.439 gdcmsurfacewriter.h File Reference

[illegible]

- class `gdcm::SurfaceWriter`
This class defines a SURFACE IE writer.

- namespace **gdcm**

11.440 gdcmSurfaceWriter.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMSURFACEWRITER_H
00015 #define GDCMSURFACEWRITER_H
00016
00017 #include <gdcmSegmentWriter.h>
00018 #include <gdcmSurface.h>
00019
00020 namespace gdcm
00021 {
00022
00023   class GDCM_EXPORT SurfaceWriter : public SegmentWriter
00024   {
00025   public:
00026     SurfaceWriter();
00027     ~SurfaceWriter() override;
00028
00029     // const Surface & GetSurface() const { return *SurfaceData; }
00030     // Surface & GetSurface() { return *SurfaceData; }
00031     void SetSurface(Surface const & segment);
00032
00033     bool Write() override; // Execute()
00034
00035     unsigned long GetNumberOfSurfaces();
00036     void SetNumberOfSurfaces(const unsigned long nb);
00037
00038   protected:
00039
00040     bool PrepareWrite();
00041
00042     void ComputeNumberOfSurfaces();
00043
00044     bool PrepareWritePointMacro(SmartPointer< Surface > surface,
00045                                DataSet & surfaceDS,
00046                                const TransferSyntax & ts);
00047
00048     //00066 0001 UL 1 Number of Surfaces
00049     unsigned long NumberOfSurfaces;
00050   };
00051
00052 #endif // GDCMSURFACEWRITER_H

```


11.441 gdcmTagPath.h File Reference

```

#include "gdcmTag.h"
#include <vector>

```

Include dependency graph for gdcmTagPath.h:



Classes

- class `gdcm::TagPath`
class to handle a path of tag.

Namespaces

- namespace `gdcm`

11.442 gdcmTagPath.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013   =====*/
00014 #ifndef GDCMTAGPATH_H
00015 #define GDCMTAGPATH_H
00016
00017 #include "gdcmTag.h"
00018
00019 #include <vector>
00020
00021 namespace gdcm
00022 {
00023

```

```


00030 class GDCM_EXPORT TagPath
00031 {
00032 public:
00033     TagPath();
00034     ~TagPath();
00035     void Print(std::ostream &) const;
00036
00041     bool ConstructFromString(const char *path);
00042
00044     static bool IsValid(const char *path);
00045
00047     bool ConstructFromTagList(Tag const *l, unsigned int n);
00048
00049     bool Push(Tag const & t);
00050     bool Push(unsigned int itemnum);
00051
00052 private:
00053     std::vector<Tag> Path;
00054 };
00055
00056 } // end namespace gdcmm
00057
00058 #endif //GDCMTAGPATH_H

```

11.443 gdcmmUIDGenerator.h File Reference

```
#include "gdcmmTypes.h"
```

Include dependency graph for gdcmmUIDGenerator.h:



Classes

- class `gdcmm::UIDGenerator`
Class for generating unique UID.

Namespaces

- namespace `gdcmm`

11.444 gdcmUIDGenerator.h

[Go to the documentation of this file.](#)

```


00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMUIDGENERATOR_H
00015 #define GDCMUIDGENERATOR_H
00016
00017 #include "gdcmTypes.h"
00018
00019 namespace gdcm
00020 {
00021
00022   class GDCM_EXPORT UIDGenerator
00023   {
00024   public:
00025     UIDGenerator():Unique() {}
00026
00027     // Function to override the GDCM root with a user one:
00028     // WARNING: This need to be a valid root, otherwise call will fail
00029     // Implementation note. According to DICOM standard PS 3.5, Section 9 :
00030     // Unique Identifiers (UIDs), we have:
00031     /*
00032     ...
00033     The <org root> portion of the UID uniquely identifies an organization, (i.e., manufacturer, research
00034     organization, NEMA, etc.), and is composed of a number of numeric components as defined by ISO 8824.
00035     The <suffix> portion of the UID is also composed of a number of numeric components, and shall be
00036     unique within the scope of the <org root>. This implies that the organization identified in the <org
00037     root> is
00038     responsible for guaranteeing <suffix> uniqueness by providing registration policies. These policies
00039     shall
00040     guarantee <suffix> uniqueness for all UID's created by that organization. Unlike the <org root>, which
00041     may
00042     be common for UID's in an organization, the <suffix> shall take different unique values between
00043     different
00044     UID's that identify different objects.
00045     ...
00046     */
00047     static void SetRoot(const char * root);
00048     static const char *GetRoot();
00049
00050     const char* Generate();
00051
00052     static bool IsValid(const char *uid);
00053
00054     static const char *GetGDCMUID(); // who would want that in the public API ??
00055
00056   protected:
00057     static bool GenerateUUID(unsigned char *uuid_data);
00058
00059   private:
00060     static const char GDCM_UID[];
00061     static std::string Root;
00062     static std::string EncodedHardwareAddress;
00063     static std::string Unique; // Buffer
00064 };
00065
00066 } // end namespace gdcm
00067
00068 #endif //GDCMUIDGENERATOR_H

```

11.445 gdcmUUIDGenerator.h File Reference

```
#include "gdcmTypes.h"
```

Include dependency graph for gdcmUUIDGenerator.h:



Classes

- class [gdcm::UUIDGenerator](#)
Class for generating unique UUID.

Namespaces

- namespace [gdcm](#)

11.446 gdcmUUIDGenerator.h

[Go to the documentation of this file.](#)


```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013  =====*/
00014 #ifndef GDCMUUUIDGENERATOR_H
00015 #define GDCMUUUIDGENERATOR_H
00016
00017 #include "gdcmTypes.h"
00018
00019 namespace gdcm
00020 {
00021

```

11.447 gdcmValidate.h File Reference

Include dependency graph for gdcmlValidate.h:



- class `gdcm::Validate`
Validate class.

- namespace **gdcm**

11.448 gdcMValidate.h

[Go to the documentation of this file.](#)

```


00001  /*=====
00002
00003      Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005      Copyright (c) 2006-2011 Mathieu Malaterre
00006      All rights reserved.
00007      See Copyright.txt or http://gdcml.sourceforge.net/Copyright.html for details.
00008
00009      This software is distributed WITHOUT ANY WARRANTY; without even
00010      the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011      PURPOSE. See the above copyright notice for more information.
00012
00013      =====*/
00014  #ifndef GDCMVALIDATE_H
00015  #define GDCMVALIDATE_H
00016
00017  #include "gdcmlFile.h"
00018
00019  namespace gdcml
00020  {
00021
00022      class GDCM_EXPORT Validate
00023      {
00024      public:
00025          Validate();
00026          ~Validate();
00027
00028          void SetFile(File const &f) { F = &f; }
00029          const File& GetValidatedFile() { return V; }
00030
00031          void Validation();
00032
00033      protected:
00034          const File *F;
00035          File V; // Validated file
00036      };
00037
00038  } // end namespace gdcml
00039
00040  #endif //GDCMVALIDATE_H

```

11.449 gdcWaveform.h File Reference

```
#include "gdcmFile.h"
```

Include dependency graph for `gdcmWaveform.h`:



Classes

- class [gdcm::Waveform](#)
Waveform class.

Namespaces

- namespace [gdcm](#)

11.450 gdcmWaveform.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013   =====*/
00014 #ifndef GDCMWAVEFORM_H
00015 #define GDCMWAVEFORM_H
00016
00017 #include "gdcmFile.h"
00018
00019 namespace gdcm
00020 {
00024   class GDCM_EXPORT Waveform
00025   {
00026   public:
00027     Waveform() = default;
00028
00029   private:
00030   };
00031
00032 } // end namespace gdcm
00033
00034 #endif //GDCMWAVEFORM_H

```

11.451 gdcmXMLPrinter.h File Reference

```

#include "gdcmFile.h"
#include "gdcmDataElement.h"

```



```

00028
00029 DicomDataSet = DicomAttribute*
00030 DicomAttribute = element DicomAttribute {
00031   Tag, VR, Keyword?, PrivateCreator?,
00032   ( BulkData | Value+ | Item+ | PersonName+ )?
00033 }
00034
00035 BulkData = element BulkData{ UUID }
00036 Value = element Value { Number, xsd:string }
00037 Item = element Item { Number, DicomDataSet }
00038 PersonName = element PersonName {
00039   Number,
00040   element SingleByte { NameComponents }?,
00041   element Ideographic { NameComponents }?,
00042   element Phonetic
00043   { NameComponents }?
00044 }
00045
00046 NameComponents =
00047   element FamilyName {xsd:string}?,
00048   element GivenName {xsd:string}?,
00049   element MiddleName {xsd:string}?,
00050   element NamePrefix {xsd:string}?,
00051   element NameSuffix {xsd:string}?
00052
00053 # keyword is the attribute tag from PS3.6
00054 # (derived from the DICOM Attribute's name)
00055 Keyword = attribute keyword { xsd:token }
00056 # canonical XML definition of Hex, with lowercase letters disallowed
00057 Tag = attribute tag { xsd:string{ minLength="8" maxLength="8" pattern="[0-9A-F]{8}" } }
00058 VR = attribute vr { "AE" | "AS" | "AT" | "CS" | "DA" | "DS" | "DT" | "FL" | "FD"
00059 | "IS" | "LO" | "LT" | "OB" | "OF" | "OW" | "PN" | "SH" | "SL"
00060 | "SQ" | "SS" | "ST" | "TM" | "UI" | "UL" | "UN" | "US" | "UT" }
00061 PrivateCreator = attribute privateCreator{ xsd:string }
00062 UUID = attribute uuid { xsd:string }
00063 Number = attribute number { xsd:positiveInteger }
00064
00065
00066 */
00067
00068 #include "gdcmFile.h"
00069 #include "gdcmDataElement.h"
00070
00071 namespace gdcm
00072 {
00073
00074   class DataSet;
00075   class DictEntry;
00076   class Dicts;
00077
00078   class GDCM_EXPORT XMLPrinter
00079   {
00080   public:
00081     XMLPrinter();
00082     virtual ~XMLPrinter();
00083
00084     // Set file
00085     void SetFile(File const &f) { F = &f; }
00086
00087
00088
00089     typedef enum {
00090
00091       OnlyUUID = 0 ,
00092       LOADBULKDATA = 1
00093
00094     } PrintStyles;
00095
00096     // Set PrintStyle value
00097     void SetStyle(PrintStyles ps)
00098     {
00099       PrintStyle = ps;
00100     }
00101
00102     // Get PrintStyle value
00103     PrintStyles GetPrintStyle() const
00104     {
00105       return PrintStyle;
00106     }
00107
00108     // Print

```

```

00109 void Print(std::ostream& os);
00110
00111 // Print an individual dataset
00112 void PrintDataSet(const DataSet &ds, const TransferSyntax & ts, std::ostream& os);
00113
00114 //void PrintUID(std::ostream &os);
00115
00119 virtual void HandleBulkData(const char *uuid, const TransferSyntax &ts,
00120     const char *bulkdata, size_t bulklen);
00121
00122 protected:
00123
00124 VR PrintDataElement(std::ostream &os, const Dicts &dicts, const DataSet & ds, const DataElement &de,
00125     const TransferSyntax & ts);
00126
00127 void PrintSQ(const SequenceOfItems *sqi, const TransferSyntax & ts, std::ostream &os);
00128
00129 PrintStyles PrintStyle;
00130
00131 const File *F;
00132 };
00133
00134 } // end namespace gdcm
00135
00136 #endif //GDCMXMLPRINTER_H


```

11.453 gdcmAAbortPDU.h File Reference

```
#include "gdcmTypes.h"
```

```
#include "gdcmBasePDU.h"
```

Include dependency graph for gdcmAAbortPDU.h:



Classes

- class `gdcm::network::AAbortPDU`
AAbortPDU.

Namespaces

- namespace [gdcm](#)
- namespace [gdcm::network](#)

11.454 gdcmAAbortPDU.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003     Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005     Copyright (c) 2006-2011 Mathieu Malaterre
00006     All rights reserved.
00007     See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009     This software is distributed WITHOUT ANY WARRANTY; without even
00010     the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011     PURPOSE. See the above copyright notice for more information.
00012
00013     =====*/
00014 #ifndef GDCMAABORTPDU_H
00015 #define GDCMAABORTPDU_H
00016
00017 #include "gdcmTypes.h"
00018 #include "gdcmBasePDU.h"
00019
00020 namespace gdcm
00021 {
00022
00023     namespace network
00024     {
00025
00026         class GDCM_EXPORT AAbortPDU : public BasePDU
00027         {
00028         public:
00029             AAbortPDU();
00030             std::istream &Read(std::istream &is) override;
00031             const std::ostream &Write(std::ostream &os) const override;
00032
00033             size_t Size() const override;
00034             void Print(std::ostream &os) const override;
00035
00036             bool IsLastFragment() const override { return true; }
00037
00038             void SetSource(const uint8_t s);
00039             void SetReason(const uint8_t r);
00040
00041         private:
00042             static const uint8_t ItemType; // PDUType ?
00043             static const uint8_t Reserved2;
00044             uint32_t ItemLength; // PDU Length
00045             static const uint8_t Reserved7;
00046             static const uint8_t Reserved8;
00047             uint8_t Source;
00048             uint8_t Reason; // diag
00049         };
00050
00051     } // end namespace network
00052
00053 } // end namespace gdcm
00054
00055 #endif //GDCMAABORTPDU_H

```

11.455 gdcmAAssociateACPDU.h File Reference


```

#include "gdcmTypes.h"
#include "gdcmApplicationContext.h"

```

```
#include "gdcmPresentationContextAC.h"
#include "gdcmUserInformation.h"
#include "gdcmBasePDU.h"
#include <vector>
```

Include dependency graph for gdcmAAssociateACPDU.h:



Classes

- class `gdcm::network::AAssociateACPDU`
AAssociateACPDU.

Namespaces

- namespace `gdcm`
- namespace `gdcm::network`

11.456 gdcmAAssociateACPDU.h

[Go to the documentation of this file.](#)

```
00001 /*=====
00002
00003 Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005 Copyright (c) 2006-2011 Mathieu Malaterre
00006 All rights reserved.
00007 See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009 This software is distributed WITHOUT ANY WARRANTY; without even
00010 the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011 PURPOSE. See the above copyright notice for more information.
00012 =====*/
00013
00014 #ifndef GDCMASSOCIATEACPDU_H
00015 #define GDCMASSOCIATEACPDU_H
00016
00017 #include "gdcmTypes.h"
00018 #include "gdcmApplicationContext.h"
00019 #include "gdcmPresentationContextAC.h"
```

```

00020 #include "gdcmUserInformation.h"
00021 #include "gdcmBasePDU.h"
00022
00023 #include <vector>
00024
00025 namespace gdcm
00026 {
00027
00028 namespace network
00029 {
00030 class AAssociateRQPDU;
00031
00037 class AAssociateACPDU : public BasePDU
00038 {
00039 public:
00040     AAssociateACPDU();
00041     std::istream &Read(std::istream &is) override;
00042     const std::ostream &Write(std::ostream &os) const override;
00043
00044     void AddPresentationContextAC( PresentationContextAC const &pcac );
00045
00046     typedef std::vector<PresentationContextAC>::size_type SizeType;
00047     const PresentationContextAC &GetPresentationContextAC( SizeType i ) {
00048         gdcm_assert( !PresContextAC.empty() && i < PresContextAC.size() );
00049         return PresContextAC[i];
00050     }
00051     SizeType GetNumberOfPresentationContextAC() const {
00052         return PresContextAC.size();
00053     }
00054     const UserInformation &GetUserInformation() const { return UserInfo; }
00055
00056     SizeType Size() const override;
00057
00058     void Print(std::ostream &os) const override;
00059     bool IsLastFragment() const override { return true; }
00060
00061     void InitFromRQ( AAssociateRQPDU const &rqpdu );
00062 protected:
00063     friend class AAssociateRQPDU;
00064     void SetCalledAETitle(const char calledaetitle[16]);
00065     void SetCallingAETitle(const char callingaetitle[16]);
00066
00067 private:
00068     void InitSimple( AAssociateRQPDU const &rqpdu );
00069
00070 private:
00071     static const uint8_t ItemType; // PDUType ?
00072     static const uint8_t Reserved2;
00073     uint32_t PDULength; // len of
00074     static const uint16_t ProtocolVersion;
00075     static const uint16_t Reserved9_10;
00076
00077     // This reserved field shall be sent with a value identical to the value
00078     // received in the same field of the A-ASSOCIATE-RQ PDU, but its value
00079     // shall not be tested when received.
00080     char Reserved11_26[16];
00081     // This reserved field shall be sent with a value identical to the value
00082     // received in the same field of the A-ASSOCIATE-RQ PDU, but its value
00083     // shall not be tested when received.
00084     char Reserved27_42[16];
00085     // This reserved field shall be sent with a value identical to the value
00086     // received in the same field of the A-ASSOCIATE-RQ PDU, but its value
00087     // shall not be tested when received.
00088     char Reserved43_74[32];
00089     /*
00090     75-xxx Variable items This variable field shall contain the following items: one Application
00091     Context Item, one or more Presentation Context Item(s) and one User
00092     Information Item. For a complete description of these items see Sections
00093     7.1.1.2, 7.1.1.14, and 7.1.1.6.
00094     */
00095     ApplicationContext AppContext;
00096     std::vector<PresentationContextAC> PresContextAC;
00097     UserInformation UserInfo;
00098 };
00099
00100 } // end namespace network
00101
00102 } // end namespace gdcm
00103
00104 #endif //GDCMASSOCIATEACPDU_H


```

11.457 gdcmAAssociateRJPDU.h File Reference

```
#include "gdcmTypes.h"
```

```
#include "gdcmBasePDU.h"
```

Include dependency graph for gdcmAAssociateRJPDU.h:



Classes

- class [gdcm::network::AAssociateRJPDU](#)
AAssociateRJPDU.

Namespaces

- namespace [gdcm](#)
- namespace [gdcm::network](#)

11.458 gdcmAAssociateRJPDU.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013   =====*/
00014 #ifndef GDCMAASSOCIATERJPDU_H

```



```

00015 #define GDCMAASSOCIATERJPDU_H
00016
00017 #include "gdcmTypes.h"
00018 #include "gdcmBasePDU.h"
00019
00020 namespace gdcm
00021 {
00022
00023 namespace network
00024 {
00025
00031 class AAssociateRJPDU : public BasePDU
00032 {
00033 public:
00034   AAssociateRJPDU();
00035   std::istream &Read(std::istream &is) override;
00036   const std::ostream &Write(std::ostream &os) const override;
00037   void Print(std::ostream &os) const override;
00038   size_t Size() const override;
00039   bool IsLastFragment() const override { return true; }
00040 private:
00041   static const uint8_t ItemType; // PDUType ?
00042   static const uint8_t Reserved2;
00043   uint32_t ItemLength; // PDU Length ?
00044   static const uint8_t Reserved8;
00045   uint8_t Result;
00046   uint8_t Source;
00047   uint8_t Reason; // diag ?
00048 };
00049
00050 } // end namespace network
00051
00052 } // end namespace gdcm
00053
00054 #endif //GDCMAASSOCIATERJPDU_H

```


11.459 gdcmAAssociateRQPDU.h File Reference

```

#include "gdcmTypes.h"
#include "gdcmVR.h"
#include "gdcmApplicationContext.h"
#include "gdcmPresentationContextRQ.h"
#include "gdcmUserInformation.h"
#include "gdcmBasePDU.h"

```

Include dependency graph for gdcmAAssociateRQPDU.h:



Classes

- class `gdcm::network::AAssociateRQPDU`
AAssociateRQPDU.

Namespaces

- namespace [gdcm](#)
- namespace [gdcm::network](#)

11.460 gdcmAAssociateRQPDU.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003     Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005     Copyright (c) 2006-2011 Mathieu Malaterre
00006     All rights reserved.
00007     See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009     This software is distributed WITHOUT ANY WARRANTY; without even
00010     the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011     PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMAASSOCIATERQPDU_H
00015 #define GDCMAASSOCIATERQPDU_H
00016
00017 #include "gdcmTypes.h"
00018 #include "gdcmVR.h" // AEComp
00019 #include "gdcmApplicationContext.h"
00020 #include "gdcmPresentationContextRQ.h"
00021 #include "gdcmUserInformation.h"
00022 #include "gdcmBasePDU.h"
00023
00024 namespace gdcm
00025 {
00026
00027     namespace network
00028     {
00029
00030         class AAssociateACPDU;
00031         class AAssociateRQPDU : public BasePDU
00032         {
00033         public:
00034             AAssociateRQPDU();
00035             std::istream &Read(std::istream &is) override;
00036             const std::ostream &Write(std::ostream &os) const override;
00037             size_t Size() const override;
00038             void AddPresentationContext( PresentationContextRQ const &pc );
00039
00040             void SetCalledAETitle(const char calledaetitle[16]);
00041             std::string GetCalledAETitle() const { return std::string(CalledAETitle,16); }
00042
00043             void SetCallingAETitle(const char callingaetitle[16]);
00044             std::string GetCallingAETitle() const { return std::string(CallingAETitle,16); }
00045
00046             static bool IsAETitleValid(const char title[16]);
00047
00048             //void InitFromRQ( AAssociateACPDU & acpdu );
00049
00050             void Print(std::ostream &os) const override;
00051
00052             AAssociateRQPDU(const AAssociateRQPDU &pdu):BasePDU(pdu)
00053             {
00054                 gdcm_assert( 0 );
00055             }
00056             //this function fails to compile on windows.
00057             // AAssociateRQPDU &operator=(const AAssociateRQPDU &_val)
00058             // {
00059             //     gdcm_assert( 0 );
00060             // }
00061
00062             typedef std::vector<PresentationContextRQ>::size_type SizeType;
00063             SizeType GetNumberOfPresentationContext() const {
00064                 return PresContext.size();
00065             }
00066         }
00067     }
00068 }

```

```

00075 PresentationContextRQ const &GetPresentationContext(SizeType i) const {
00076     gdcma_assert( !PresContext.empty() && i < PresContext.size() );
00077     return PresContext[i];
00078 }
00079 typedef std::vector<PresentationContextRQ> PresentationContextArrayType;
00080 PresentationContextArrayType const &GetPresentationContexts() { return PresContext; }
00081
00082 const PresentationContextRQ *GetPresentationContextByID(uint8_t i) const;
00083 const PresentationContextRQ *GetPresentationContextByAbstractSyntax(AbstractSyntax const & absyn )
00084 const;
00084 bool IsLastFragment() const override { return true; }
00085
00086 const UserInformation & GetUserInformation() const { return UserInfo; }
00087 void SetUserInformation( UserInformation const & ui );
00088
00089 protected:
00090     friend class AAssociateACPDU;
00091     std::string GetReserved43_74() const;
00092
00093 private:
00094     // 1 PDU-type 01H
00095     static const uint8_t ItemType; // PDUType ?
00096     // 2 Reserved This reserved field shall be sent with a value 00H but not tested to this value when
00097     received.
00098     static const uint8_t Reserved2;
00098     /* 3-6 PDU-length This PDU-length shall be the number of bytes from the first byte of the
00099     following field to the last byte of the variable field. It shall be encoded as
00100     an unsigned binary number
00101     */
00102     uint32_t ItemLength; // PDU Length
00103     /*
00104     7-8 Protocol-version This two byte field shall use one bit to identify each version of the
00105     DICOM UL protocol supported by the calling end-system. This is
00106     Version 1 and shall be identified with bit 0 set. A receiver of this PDU
00107     implementing only this version of the DICOM UL protocol shall only test
00108     that bit 0 is set.
00109     */
00110     static const uint16_t ProtocolVersion;
00111     /*
00112     9-10 Reserved This reserved field shall be sent with a value 0000H but not tested to
00113     this value when received.
00114     */
00115     static const uint16_t Reserved9_10;
00116     /*
00117     11-26 Called-AE-title Destination DICOM Application Name. It shall be encoded as 16
00118     characters as defined by the ISO 646:1990-Basic G0 Set with leading
00119     and trailing spaces (20H) being non-significant. The value made of 16
00120     spaces (20H) meaning "no Application Name specified" shall not be
00121     used. For a complete description of the use of this field, see Section
00122     7.1.1.4.
00123     */
00124     char CalledAETitle[16];
00125     /*
00126     27-42 Calling-AE-title Source DICOM Application Name. It shall be encoded as 16
00127     characters as defined by the ISO 646:1990-Basic G0 Set with leading
00128     and trailing spaces (20H) being non-significant. The value made of 16
00129     spaces (20H) meaning "no Application Name specified" shall not be
00130     used. For a complete description of the use of this field, see Section
00131     7.1.1.3.
00132     */
00133     char CallingAETitle[16];
00134     /*
00135     43-74 Reserved This reserved field shall be sent with a value 00H for all bytes but not
00136     tested to this value when received
00137     */
00138     char Reserved43_74[32]; // { 0 }
00139     /*
00140     75-xxx Variable items This variable field shall contain the following items: one Application
00141     Context Item, one or more Presentation Context Items and one User
00142     Information Item. For a complete description of the use of these items
00143     see Sections 7.1.1.2, 7.1.1.13, and 7.1.1.6.
00144     */
00145     ApplicationContext AppContext;
00146     std::vector<PresentationContextRQ> PresContext;
00147     UserInformation UserInfo;
00148 };
00149
00150 } // end namespace network
00151 } // end namespace gdcma
00152
00153 #endif //GDCMAASSOCIATERQPDU_H

```


11.462 gdcmAbstractSyntax.h

[Go to the documentation of this file.](#)

```


00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMABSTRACTSYNTAX_H
00015 #define GDCMABSTRACTSYNTAX_H
00016
00017 #include "gdcmTypes.h"
00018 #include "gdcmUIDs.h"
00019 #include "gdcmDataElement.h"
00020
00021 namespace gdcm
00022 {
00023
00024   namespace network
00025   {
00026
00032     class AbstractSyntax
00033     {
00034     public:
00035       AbstractSyntax();
00036       std::istream &Read(std::istream &is);
00037       const std::ostream &Write(std::ostream &os) const;
00038
00039       void SetName( const char *name ) { UpdateName( name ); }
00040       const char *GetName() const { return Name.c_str(); }
00041
00042       // accept a UID::TSType also...
00043       void SetNameFromUID( UID::TSType tname );
00044       //now that the PresentationContext messes around with UIDs and returns a string
00045       //use that string as well.
00046       //void SetNameFromUIDString( const std::string& inUIDName );
00047
00048       size_t Size() const;
00049
00050       void Print(std::ostream &os) const;
00051
00052       bool operator==(const AbstractSyntax & as) const
00053       {
00054         return Name == as.Name;
00055       }
00056
00057       DataElement GetAsDataElement() const;
00058
00059     private:
00060       void UpdateName( const char *name );
00061       static const uint8_t ItemType;
00062       static const uint8_t Reserved2;
00063       uint16_t ItemLength; // len of
00064       std::string /*AbstractSyntax*/ Name; // UID
00065     };
00066
00067   } // end namespace network
00068 } // end namespace gdcm
00069
00070 #endif //GDCMABSTRACTSYNTAX_H

```


11.463 gdcmApplicationContext.h File Reference

```
#include "gdcmTypes.h"
```

Include dependency graph for gdcmApplicationContext.h:



This graph shows which files directly or indirectly include this file:



Classes

- class `gdcm::network::ApplicationContext`
ApplicationContext.

Namespaces

- namespace `gdcm`
- namespace `gdcm::network`

11.464 gdcmApplicationContext.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMAPPLICATIONCONTEXT_H
00015 #define GDCMAPPLICATIONCONTEXT_H
00016
00017 #include "gdcmTypes.h"
00018
00019 namespace gdcm
00020 {
00021
00022 namespace network
00023 {
00024
00032 class ApplicationContext
00033 {
00034 public:
00035   ApplicationContext();
00036   std::istream &Read(std::istream &is);
00037   const std::ostream &Write(std::ostream &os) const;
00038
00039   void SetName( const char *name ) { UpdateName( name ); }
00040   const char *GetName() const { return Name.c_str(); }
00041   size_t Size() const;
00042
00043   //static const uint8_t GetItemType() { return ItemType; }
00044   void Print(std::ostream &os) const;
00045
00046 private:
00047   void UpdateName( const char *name );
00048   static const uint8_t ItemType;
00049   static const uint8_t Reserved2;
00050   uint16_t ItemLength; // len of application context name
00051   std::string /*ApplicationContext*/ Name; // UID
00052 };
00053
00054 } // end namespace network
00055
00056 } // end namespace gdcm
00057
00058 #endif //GDCMAPPLICATIONCONTEXT_H

```


11.465 gdcmAReleaseRPPDU.h File Reference

```

#include "gdcmTypes.h"
#include "gdcmBasePDU.h"

```

Include dependency graph for `gdcmAReleaseRPPDU.h`:



Classes

- class `gdcm::network::AReleaseRPPDU`
AReleaseRPPDU.

Namespaces

- namespace `gdcm`
- namespace `gdcm::network`

11.466 gdcmAReleaseRPPDU.h

[Go to the documentation of this file.](#)

```

00001  /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012  =====*/
00013  #ifndef GDCMARELEASERPPDU_H
00014  #define GDCMARELEASERPPDU_H
00015
00016  #include "gdcmTypes.h"
00017  #include "gdcmBasePDU.h"
00018
00019  namespace gdcm
00020  {
00021  {
00022

```



```

00023 namespace network
00024 {
00025
00031 class AReleaseRPPDU : public BasePDU
00032 {
00033 public:
00034     AReleaseRPPDU();
00035     std::istream &Read(std::istream &is) override;
00036     const std::ostream &Write(std::ostream &os) const override;
00037     size_t Size() const override;
00038     void Print(std::ostream &os) const override;
00039     bool IsLastFragment() const override { return true; }
00040 private:
00041     static const uint8_t ItemType; // PDUType ?
00042     static const uint8_t Reserved2;
00043     uint32_t ItemLength; // PDU Length
00044     static const uint32_t Reserved7_10;
00045 };
00046
00047 } // end namespace network
00048
00049 } // end namespace gdcm
00050
00051 #endif //GDCMARELEASERPPDU_H


```

11.467 gdcmAReleaseRQPDU.h File Reference

```
#include "gdcmTypes.h"
```

```
#include "gdcmBasePDU.h"
```

Include dependency graph for gdcmAReleaseRQPDU.h:



Classes

- class `gdcm::network::AReleaseRQPDU`
AReleaseRQPDU.

Namespaces

- namespace `gdcm`
- namespace `gdcm::network`

11.468 gdcmAReleaseRQPDU.h

[Go to the documentation of this file.](#)


```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMARELEASERQPDU_H
00015 #define GDCMARELEASERQPDU_H
00016
00017 #include "gdcmTypes.h"
00018 #include "gdcmBasePDU.h"
00019
00020 namespace gdcm
00021 {
00022
00023   namespace network
00024   {
00025
00031     class AReleaseRQPDU : public BasePDU
00032     {
00033     public:
00034       AReleaseRQPDU();
00035       std::istream &Read(std::istream &is) override;
00036       const std::ostream &Write(std::ostream &os) const override;
00037       size_t Size() const override;
00038       void Print(std::ostream &os) const override;
00039       bool IsLastFragment() const override { return true; }
00040     private:
00041       static const uint8_t ItemType; // PDUType ?
00042       static const uint8_t Reserved2;
00043       uint32_t ItemLength; // PDU Length
00044       static const uint32_t Reserved7_10;
00045     };
00046
00047   } // end namespace network
00048
00049 } // end namespace gdcm
00050
00051 #endif //GDCMARELEASERQPDU_H

```

11.469 gdcmARTIMTimer.h File Reference

This graph shows which files directly or indirectly include this file:



Classes

- class `gdcm::network::ARTIMTimer`
ARTIMTimer.

Namespaces

- namespace `gdcm`
- namespace `gdcm::network`

11.470 gdcmARTIMTimer.h

[Go to the documentation of this file.](#)

```


00001 /*=====
00002  *
00003  * Copyright NumFOCUS
00004  *
00005  * Licensed under the Apache License, Version 2.0 (the "License");
00006  * you may not use this file except in compliance with the License.
00007  * You may obtain a copy of the License at
00008  *
00009  * http://www.apache.org/licenses/LICENSE-2.0.txt
00010  *
00011  * Unless required by applicable law or agreed to in writing, software
00012  * distributed under the License is distributed on an "AS IS" BASIS,
00013  * WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied.
00014  * See the License for the specific language governing permissions and
00015  * limitations under the License.
00016  *
00017  *=====*/
00018 #ifndef GDCMARTIMTIMER_H
00019 #define GDCMARTIMTIMER_H
00020
00021 namespace gdcm {
00022     namespace network{
00023     class ARTIMTimer
00024     {
00025     private:
00026         double mStartTime; //ms timing should be good enough, but there are also
00027         //high-resolution timing options. Those return doubles. For now,
00028         //go with integer timing solutions based on milliseconds (DWORD on windows),
00029         //but leave as doubles to ease transitions to other timing methods.
00030
00031         double mTimeout;
00032         //once GetCurrentTime() -mStartTime > mTimeout, GetHasExpired returns true.
00033
00034         double GetCurrentTime() const;//a platform-specific implementation of getting the
00035         //current time.
00036
00037     public:
00038         ARTIMTimer(); //initiates the start and timeout at -1;
00039         void Start(); //start the timer by getting the current wall time
00040         void Stop();//stop the timer by resetting the 'start' to -1;
00041         void SetTimeout(double inTimeout);
00042         double GetTimeout() const;
00043
00044         double GetElapsedTime() const;
00045
00046         bool GetHasExpired() const;
00047
00048     };
00049 }
00050
00051 #endif //GDCMARTIMTIMER_H

```

11.471 gdcmAsynchronousOperationsWindowSub.h File Reference

```
#include "gdcmTypes.h"
```

Include dependency graph for gdcmAsynchronousOperationsWindowSub.h:



Classes

- class [gdcm::network::AsynchronousOperationsWindowSub](#)
AsynchronousOperationsWindowSub.

Namespaces

- namespace [gdcm](#)
- namespace [gdcm::network](#)

11.472 gdcmAsynchronousOperationsWindowSub.h

[Go to the documentation of this file.](#)

```


00001  /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012  =====*/
00013
00014  #ifndef GDCMASYNCHRONOUSOPERATIONSWINDOWSUB_H
00015  #define GDCMASYNCHRONOUSOPERATIONSWINDOWSUB_H
00016
00017  #include "gdcmTypes.h"
00018
00019  namespace gdcm

```

11.473 gdcmbaseCompositeMessage.h File Reference

[illegible]

This graph shows which files directly or indirectly include this file:



Classes

- class `gdc::network::BaseCompositeMessage`
BaseCompositeMessage.

Namespaces

- namespace `gdc`
- namespace `gdc::network`

11.474 gdcBaseCompositeMessage.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002  *
00003  *   Copyright NumFOCUS
00004  *
00005  *   Licensed under the Apache License, Version 2.0 (the "License");
00006  *   you may not use this file except in compliance with the License.
00007  *   You may obtain a copy of the License at
00008  *
00009  *       http://www.apache.org/licenses/LICENSE-2.0.txt
00010  *
00011  *   Unless required by applicable law or agreed to in writing, software
00012  *   distributed under the License is distributed on an "AS IS" BASIS,
00013  *   WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied.
00014  *   See the License for the specific language governing permissions and
00015  *   limitations under the License.
00016  *
00017  *=====*/
00018 #ifndef GDCMBASECOMPOSITEMESSAGE_H
00019 #define GDCMBASECOMPOSITEMESSAGE_H
00020
00021 #include "gdcPresentationDataValue.h"
00022 #include "gdcBaseRootQuery.h"
00023
00024 #include <vector>
00025
00026 namespace gdc
00027 {
00028     namespace network
00029     {
00030         class ULConnection;
00052         class BaseCompositeMessage
00053         {
00054             public:
00055                 virtual ~BaseCompositeMessage() = default;
00056                 //construct the appropriate pdv and dataset for this message
00057                 //for instance, setting tag 0x0,0x100 to the appropriate value
00058                 //the pdv, as described in Annex E of 3.8-2009, is the first byte

```

11.475 gdcmbaseNormalizedMessage.h File Reference

```

graph TD
    Base[gdcmBaseNormalizedMessage.h]
    Action[gdcmActionMessages.h]
    Create[gdcmCreateMessages.h]
    Delete[gdcmDeleteMessages.h]
    Event[gdcmEventReportMessages.h]
    Get[gdcmGetMessages.h]
    Set[gdcmSetMessages.h]

    Action --> Base
    Create --> Base
    Delete --> Base
    Event --> Base
    Get --> Base
    Set --> Base
  
```

- class `gdcmm::network::BaseNormalizedMessage`
BaseNormalizedMessage.

- namespace `gdcm`
- namespace `gdcm::network`

11.476 gdcmBaseNormalizedMessage.h

[Go to the documentation of this file.](#)

```


00001  /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2014 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013  =====*/
00014  #ifndef GDCMBASENORMALIZEDMESSAGE_H
00015  #define GDCMBASENORMALIZEDMESSAGE_H
00016
00017  #include "gdcmPresentationDataValue.h"
00018  #include "gdcmBaseQuery.h"
00019
00020  #include <vector>
00021
00022  namespace gdcm
00023  {
00024      namespace network
00025      {
00026          class ULConnection;
00049          class BaseNormalizedMessage
00050          {
00051          public:
00052              virtual ~BaseNormalizedMessage() = default;
00053              //construct the appropriate pdv and dataset for this message
00054              //for instance, setting tag 0x0,0x100 to the appropriate value
00055              //the pdv, as described in Annex E of 3.8-2009, is the first byte
00056              //of the message (the MessageHeader), and then the subsequent dataset
00057              //that describes the operation.
00058              virtual std::vector<PresentationDataValue> ConstructPDV( const ULConnection &inConnection,
00059                                                                      const BaseQuery * inQuery) = 0;
00060          };
00061      }
00062  }
00063  #endif //GDCMBASENORMALIZEDMESSAGE_H

```


11.477 gdcmBasePDU.h File Reference

```
#include "gdcmTypes.h"
```

Include dependency graph for gdcmBasePDU.h:



This graph shows which files directly or indirectly include this file:



Classes

- class `gdcm::network::BasePDU`
BasePDU.

Namespaces

- namespace `gdcm`
- namespace `gdcm::network`

11.478 gdcmBasePDU.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002  *
00003  *   Copyright NumFOCUS
00004  *
00005  *   Licensed under the Apache License, Version 2.0 (the "License");
00006  *   you may not use this file except in compliance with the License.
00007  *   You may obtain a copy of the License at
00008  *
00009  *       http://www.apache.org/licenses/LICENSE-2.0.txt
00010  *
00011  *   Unless required by applicable law or agreed to in writing, software
00012  *   distributed under the License is distributed on an "AS IS" BASIS,
00013  *   WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied.
00014  *   See the License for the specific language governing permissions and
00015  *   limitations under the License.
00016  *
00017  *=====*/
00018 #ifndef GDCMBASEPDU_H
00019 #define GDCMBASEPDU_H
00020
00021 #include "gdcmTypes.h"
00022
00023 namespace gdcm
00024 {
00025     namespace network
00026     {
00027
00050         class BasePDU
00051         {
00052         public:
00053             virtual ~BasePDU() = default;
00054
00055             virtual std::istream &Read(std::istream &is) = 0;
00056             virtual const std::ostream &Write(std::ostream &os) const = 0;
00057
00058             virtual size_t Size() const = 0;
00059             virtual void Print(std::ostream &os) const = 0;
00060

```

```

00061     virtual bool IsLastFragment() const = 0;
00062 };
00063
00064 } // end namespace network
00065 } // end namespace gdcm
00066
00067 #endif // GDCMBASEPDU_H

```


11.479 gdcmBaseQuery.h File Reference

```

#include "gdcmDataSet.h"
#include "gdcmUIDs.h"
#include "gdcmObject.h"

```

Include dependency graph for gdcmBaseQuery.h:



This graph shows which files directly or indirectly include this file:



Classes

- class `gdcm::BaseQuery`
BaseQuery.

Namespaces

- namespace `gdcm`

Enumerations

- enum gdcm::ENQueryType {
 gdcm::eCreateMMPS = 0 ,
 gdcm::eSetMMPS }

11.480 gdcmBaseQuery.h

[Go to the documentation of this file.](#)


```

00001 /*=====
00002  *
00003  *   Copyright NumFOCUS
00004  *
00005  *   Licensed under the Apache License, Version 2.0 (the "License");
00006  *   you may not use this file except in compliance with the License.
00007  *   You may obtain a copy of the License at
00008  *
00009  *       http://www.apache.org/licenses/LICENSE-2.0.txt
00010  *
00011  *   Unless required by applicable law or agreed to in writing, software
00012  *   distributed under the License is distributed on an "AS IS" BASIS,
00013  *   WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied.
00014  *   See the License for the specific language governing permissions and
00015  *   limitations under the License.
00016  *
00017  *=====*/
00018 #ifndef GDCMBASEQUERY_H
00019 #define GDCMBASEQUERY_H
00020
00021 #include "gdcmDataSet.h"
00022 #include "gdcmUIDs.h"
00023 #include "gdcmObject.h"
00024
00025 namespace gdcm
00026 {
00027     class QueryFactory;
00028     class DictEntry;
00029
00030     enum ENQueryType
00031     {
00032         eCreateMMPS = 0,
00033         eSetMMPS
00034     };
00041 class GDCM_EXPORT BaseQuery : public Object
00042 {
00043     //these four classes contain the required, unique, and optional tags from the standard.
00044     //used both to list the tags as well as to validate a dataset, if ever we were to do so.
00045 protected:
00046
00047     DataSet mDataSet;
00048     friend class QueryFactory;
00049     BaseQuery();
00050
00051     std::string mSopInstanceUID;
00052
00053     void SetSearchParameter(const Tag& inTag, const DictEntry& inDictEntry, const std::string& inValue);
00054
00055     bool ValidDataSet( const DataSet & dataSetToValid, const DataSet & dataSetReference ) const ;
00056 public:
00057     ~BaseQuery() override;
00058
00059     void SetSearchParameter(const Tag& inTag, const std::string& inValue);
00060     void SetSearchParameter(const std::string& inKeyword, const std::string& inValue);
00061
00062     const std::ostream &WriteHelpFile(std::ostream &os);
00063
00064     //this function allows writing of the query to disk for storing for future use
00065     //virtual in case it needs to be overridden
00066     //returns false if the operation failed
00067     bool WriteQuery(const std::string& inFileName);
00068
00070     DataSet const & GetQueryDataSet() const;

```

11.481 gdcmbaseRootQuery.h File Reference

Include dependency graph for `gdcmBaseRootQuery.h`:



- class `gdcm::BaseRootQuery`
BaseRootQuery.

Namespaces

- namespace [gdcm](#)

Enumerations

- enum [gdcm::EQueryLevel](#) {
[gdcm::ePatient](#) = 0 ,
[gdcm::eStudy](#) = 1 ,
[gdcm::eSeries](#) = 2 ,
[gdcm::eImage](#) = 3 }
- enum [gdcm::EQueryType](#) {
[gdcm::eFind](#) = 0 ,
[gdcm::eMove](#) ,
[gdcm::eWLMFind](#) }

11.482 gdcmBaseRootQuery.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002  *
00003  *   Copyright NumFOCUS
00004  *
00005  *   Licensed under the Apache License, Version 2.0 (the "License");
00006  *   you may not use this file except in compliance with the License.
00007  *   You may obtain a copy of the License at
00008  *
00009  *       http://www.apache.org/licenses/LICENSE-2.0.txt
00010  *
00011  *   Unless required by applicable law or agreed to in writing, software
00012  *   distributed under the License is distributed on an "AS IS" BASIS,
00013  *   WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied.
00014  *   See the License for the specific language governing permissions and
00015  *   limitations under the License.
00016  *
00017  *=====*/
00018 #ifndef GDCMBASEROOTQUERY_H
00019 #define GDCMBASEROOTQUERY_H
00020
00021 #include "gdcmDataSet.h"
00022 #include "gdcmUIDs.h"
00023 #include "gdcmBaseQuery.h"
00024 #include "gdcmQueryPatient.h"
00025 #include "gdcmQueryStudy.h"
00026 #include "gdcmQuerySeries.h"
00027 #include "gdcmQueryImage.h"
00028
00029 namespace gdcm
00030 {
00031     class QueryFactory;
00032     class DictEntry;
00033
00034     enum EQueryLevel
00035     {
00036         // -1 is reserved do not use
00037         ePatient = 0,
00038         eStudy = 1,
00039         eSeries = 2,
00040         eImage = 3
00041     };
00042     enum EQueryType
00043     {
00044         eFind = 0,
00045         eMove,
00046         eWLMFind
00047     };

```


CEchoRQ.

- class `gdcm::network::CEchoRSP`

CEchoRSP this file defines the messages for the cecho action.

Namespaces

- namespace `gdcm`
- namespace `gdcm::network`

11.484 gdcmCEchoMessages.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002  *
00003  * Copyright NumFOCUS
00004  *
00005  * Licensed under the Apache License, Version 2.0 (the "License");
00006  * you may not use this file except in compliance with the License.
00007  * You may obtain a copy of the License at
00008  *
00009  * http://www.apache.org/licenses/LICENSE-2.0.txt
00010  *
00011  * Unless required by applicable law or agreed to in writing, software
00012  * distributed under the License is distributed on an "AS IS" BASIS,
00013  * WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied.
00014  * See the License for the specific language governing permissions and
00015  * limitations under the License.
00016  *
00017  *=====*/
00018 #ifndef GDCMCECHOMESSAGES_H
00019 #define GDCMCECHOMESSAGES_H
00020
00021 #include "gdcmBaseCompositeMessage.h"
00022
00023 namespace gdcm{
00024     namespace network{
00025
00026         class ULConnection;
00027
00032         class CEchoRQ : public BaseCompositeMessage {
00033         public:
00034             std::vector<PresentationDataValue> ConstructPDV(const ULConnection &inConnection,
00035                 const BaseRootQuery* inRootQuery) override;
00036         };
00037
00042         class CEchoRSP : public BaseCompositeMessage {
00043         public:
00044             std::vector<PresentationDataValue> ConstructPDVByDataSet(const DataSet* inDataSet);
00045         };
00046     }
00047 }
00048 #endif // GDCMCECHOMESSAGES_H

```


11.485 gdcmCFindMessages.h File Reference

```

#include "gdcmBaseCompositeMessage.h"
#include "gdcmBaseRootQuery.h"

```

Include dependency graph for `gdcmCFindMessages.h`:



Classes

- class `gdcm::network::CFindCancelRQ`
CFindCancelRQ this file defines the messages for the *cfind* action.
- class `gdcm::network::CFindRQ`
CFindRQ.
- class `gdcm::network::CFindRSP`
CFindRSP this file defines the messages for the *cfind* action.

Namespaces

- namespace `gdcm`
- namespace `gdcm::network`

11.486 gdcmCFindMessages.h

[Go to the documentation of this file.](#)


```

00001 /*=====
00002  *
00003  *   Copyright NumFOCUS
00004  *
00005  *   Licensed under the Apache License, Version 2.0 (the "License");
00006  *   you may not use this file except in compliance with the License.
00007  *   You may obtain a copy of the License at
00008  *
00009  *       http://www.apache.org/licenses/LICENSE-2.0.txt
00010  *
00011  *   Unless required by applicable law or agreed to in writing, software
00012  *   distributed under the License is distributed on an "AS IS" BASIS,
00013  *   WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied.
00014  *   See the License for the specific language governing permissions and
00015  *   limitations under the License.
00016  *
00017  *===== */

```


11.487 gdcnCMoveMessages.h File Reference

Include dependency graph for `gdcmCMoveMessages.h`:



- class `gdcmm::network::CMoveCancelRq`
- class `gdcmm::network::CMoveRQ`
CMoveRQ.
- class `gdcmm::network::CMoveRSP`
CMoveRSP this file defines the messages for the cmove action.

Namespaces

- namespace [gdcm](#)
- namespace [gdcm::network](#)

11.488 gdcmCMoveMessages.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002  *
00003  *   Copyright NumFOCUS
00004  *
00005  *   Licensed under the Apache License, Version 2.0 (the "License");
00006  *   you may not use this file except in compliance with the License.
00007  *   You may obtain a copy of the License at
00008  *
00009  *       http://www.apache.org/licenses/LICENSE-2.0.txt
00010  *
00011  *   Unless required by applicable law or agreed to in writing, software
00012  *   distributed under the License is distributed on an "AS IS" BASIS,
00013  *   WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied.
00014  *   See the License for the specific language governing permissions and
00015  *   limitations under the License.
00016  *
00017  *=====*/
00018 #ifndef GDCMCMOVEMESSAGES_H
00019 #define GDCMCMOVEMESSAGES_H
00020
00021 #include "gdcmBaseCompositeMessage.h"
00022 #include "gdcmBaseRootQuery.h"
00023
00024 namespace gdcm{
00025     namespace network{
00026         class ULConnection;
00031     class CMoveRQ : public BaseCompositeMessage {
00032         //this class will fulfill the inheritance,
00033         //but additional information is needed by cmovd
00034         //namely, the root type or the calling AE-TITLE
00035         std::vector<PresentationDataValue> ConstructPDVByDataSet(const DataSet* inDataSet);
00036     public:
00037         std::vector<PresentationDataValue> ConstructPDV(
00038             const ULConnection &inConnection,
00039             const BaseRootQuery* inRootQuery) override;
00040     };
00041
00046     class CMoveRSP : public BaseCompositeMessage {
00047     public:
00048         std::vector<PresentationDataValue> ConstructPDVByDataSet(const DataSet* inDataSet);
00049     };
00050
00051     class CMoveCancelRq : public BaseCompositeMessage {
00052     public:
00053         std::vector<PresentationDataValue> ConstructPDVByDataSet(const DataSet* inDataSet);
00054     };
00055     }
00056 }
00057 #endif

```

11.489 gdcmCommandDataSet.h File Reference

```

#include "gdcmDataSet.h"
#include "gdcmDataElement.h"

```



```

00018 #include "gdcmDataElement.h"
00019
00020 namespace gdcm
00021 {
00027 class GDCM_EXPORT CommandDataSet : public DataSet
00028 {
00029 public:
00030     CommandDataSet() = default;
00031     ~CommandDataSet() = default;
00032
00033     friend std::ostream &operator<<(std::ostream &_os, const CommandDataSet &_val);
00034
00035     // FIXME: no virtual function means: duplicate code...
00036     void Insert(const DataElement& de) {
00037         if( de.GetTag().GetGroup() == 0x0000 )
00038         {
00039             InsertDataElement( de );
00040         }
00041         else
00042         {
00043             gdcmErrorMacro( "Cannot add element with group != 0x0000 in the command dataset : " << de );
00044         }
00045     }
00046     void Replace(const DataElement& de) {
00047         Remove(de.GetTag());
00048         Insert(de);
00049     }
00050
00052     std::istream &Read(std::istream &is);
00053
00055     std::ostream &Write(std::ostream &os) const;
00056
00057 protected:
00058 };
00059 //-----
00060 inline std::ostream& operator<<(std::ostream &os, const CommandDataSet &val)
00061 {
00062     val.Print( os );
00063     return os;
00064 }
00065
00066 } // end namespace gdcm
00067
00068 #endif //GDCMFILEMETAINFORMATION_H


```

11.491 gdcmCompositeMessageFactory.h File Reference

```
#include "gdcmPresentationDataValue.h"
```

```
#include "gdcmULConnection.h"
```

Include dependency graph for gdcmCompositeMessageFactory.h:



Classes

- class `gdcm::network::CompositeMessageFactory`
CompositeMessageFactory.

Namespaces

- namespace [gdcm](#)
- namespace [gdcm::network](#)

11.492 gdcmCompositeMessageFactory.h

[Go to the documentation of this file.](#)

```

00001  /*=====
00002  *
00003  *   Copyright NumFOCUS
00004  *
00005  *   Licensed under the Apache License, Version 2.0 (the "License");
00006  *   you may not use this file except in compliance with the License.
00007  *   You may obtain a copy of the License at
00008  *
00009  *       http://www.apache.org/licenses/LICENSE-2.0.txt
00010  *
00011  *   Unless required by applicable law or agreed to in writing, software
00012  *   distributed under the License is distributed on an "AS IS" BASIS,
00013  *   WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied.
00014  *   See the License for the specific language governing permissions and
00015  *   limitations under the License.
00016  *
00017  *=====*/
00018  #ifndef GDCMCOMPOSITEMESSAGEFACTORY_H
00019  #define GDCMCOMPOSITEMESSAGEFACTORY_H
00020
00021  #include "gdcmPresentationDataValue.h"
00022  #include "gdcmULConnection.h"
00023
00024  namespace gdcm {
00025      class BaseRootQuery;
00026      class File;
00027      namespace network {
00028          class BasePDU;
00037      class CompositeMessageFactory
00038      {
00039      public:
00040          //the echo request only needs a properly constructed PDV.
00041          //find, move, etc, may need something more robust, but since those are
00042          //easily placed into the appropriate pdatapdu in the pdufactory,
00043          //this approach without a base class (but done internally) is useful.
00044          static std::vector<PresentationDataValue> ConstructCEchoRQ(const ULConnection& inConnection);
00045
00046          static std::vector<PresentationDataValue> ConstructCStoreRQ(const ULConnection& inConnection, const
File &file, bool writeDataSet = true );
00047          static std::vector<PresentationDataValue> ConstructCStoreRSP(const DataSet *inDataSet, const
BasePDU* inPC);
00048
00049          static std::vector<PresentationDataValue> ConstructCFindRQ(const ULConnection& inConnection, const
BaseRootQuery* inRootQuery);
00050
00051          static std::vector<PresentationDataValue> ConstructCMoveRQ(const ULConnection& inConnection, const
BaseRootQuery* inRootQuery);
00052
00053      };
00054  };
00055  }
00056  }
00057
00058  #endif // GDCMCOMPOSITEMESSAGEFACTORY_H

```

11.493 gdcmCompositeNetworkFunctions.h File Reference

```

#include "gdcmDirectory.h"
#include "gdcmBaseRootQuery.h"

```


11.495 qdcmCStoreMessages.h File Reference

Classes

- class [gdcm::network::CStoreRQ](#)
[CStoreRQ](#).
- class [gdcm::network::CStoreRSP](#)
[CStoreRSP](#) *this file defines the messages for the cecho action.*

Namespaces

- namespace [gdcm](#)
- namespace [gdcm::network](#)

11.496 gdcmCStoreMessages.h

[Go to the documentation of this file.](#)

```


00001 /*=====
00002  *
00003  *   Copyright NumFOCUS
00004  *
00005  *   Licensed under the Apache License, Version 2.0 (the "License");
00006  *   you may not use this file except in compliance with the License.
00007  *   You may obtain a copy of the License at
00008  *
00009  *       http://www.apache.org/licenses/LICENSE-2.0.txt
00010  *
00011  *   Unless required by applicable law or agreed to in writing, software
00012  *   distributed under the License is distributed on an "AS IS" BASIS,
00013  *   WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied.
00014  *   See the License for the specific language governing permissions and
00015  *   limitations under the License.
00016  *
00017  *=====*/
00018 #ifndef GDCMCSTOREMESSAGES_H
00019 #define GDCMCSTOREMESSAGES_H
00020
00021 #include "gdcmBaseCompositeMessage.h"
00022
00023 namespace gdcm{
00024 class File;
00025     namespace network{
00026         class BasePDU;
00031 class CStoreRQ : public BaseCompositeMessage {
00032     std::vector<PresentationDataValue> ConstructPDV(const ULConnection &inConnection, const
BaseRootQuery* inRootQuery) override;//to fulfill the virtual contract
00033     public:
00034         std::vector<PresentationDataValue> ConstructPDV(const ULConnection &inConnection,
00035             const File& file, bool writeDataSet = true );
00036     };
00037
00042     class CStoreRSP : public BaseCompositeMessage {
00043     std::vector<PresentationDataValue> ConstructPDV(const ULConnection &inConnection, const
BaseRootQuery* inRootQuery) override;//to fulfill the virtual contract
00044     public:
00045         std::vector<PresentationDataValue> ConstructPDV(const DataSet* inDataSet, const BasePDU* inPC);
00046     };
00047 }
00048 }
00049 #endif // GDCMCSTOREMESSAGES_H

```


11.497 gdcmDIMSE.h File Reference

```
#include "gdcmTypes.h"
```

Include dependency graph for gdcmDIMSE.h:



Classes

- class [gdcm::network::CEchoRQ](#)
CEchoRQ.
- class [gdcm::network::CEchoRSP](#)
CEchoRSP this file defines the messages for the cecho action.
- class [gdcm::network::CFind](#)
- class [gdcm::network::DIMSE](#)
DIMSE.

Namespaces

- namespace [gdcm](#)
- namespace [gdcm::network](#)

11.498 gdcmDIMSE.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.

```

```

00012
00013 =====*/
00014 #ifndef GDCMDIMSE_H
00015 #define GDCMDIMSE_H
00016
00017 #include "gdcTypes.h"
00018
00019 namespace gdc
00020 {
00021
00022 namespace network
00023 {
00024
00025 class DIMSE {
00026 public:
00027     typedef enum {
00028         C_STORE_RQ      = 0x0001,
00029         C_STORE_RSP     = 0x8001,
00030         C_GET_RQ        = 0x0010,
00031         C_GET_RSP       = 0x8010,
00032         C_FIND_RQ       = 0x0020,
00033         C_FIND_RSP      = 0x8020,
00034         C_MOVE_RQ       = 0x0021,
00035         C_MOVE_RSP      = 0x8021,
00036         C_ECHO_RQ       = 0x0030,
00037         C_ECHO_RSP      = 0x8030,
00038         N_EVENT_REPORT_RQ = 0x0100,
00039         N_EVENT_REPORT_RSP = 0x8100,
00040         N_GET_RQ        = 0x0110,
00041         N_GET_RSP       = 0x8110,
00042         N_SET_RQ        = 0x0120,
00043         N_SET_RSP       = 0x8120,
00044         N_ACTION_RQ     = 0x0130,
00045         N_ACTION_RSP    = 0x8130,
00046         N_CREATE_RQ     = 0x0140,
00047         N_CREATE_RSP    = 0x8140,
00048         N_DELETE_RQ     = 0x0150,
00049         N_DELETE_RSP    = 0x8150,
00050         C_CANCEL_RQ     = 0x0FFF
00051     } CommandTypes;
00052 };
00053
00054 /*
00055 9.1.5.1 C-ECHO parameters
00056 Table 9.1-5
00057 C-ECHO PARAMETERS
00058 */
00059 class CEchoRQ
00060 {
00061 public:
00062     uint16_t      MessageID;          /* M */
00063     UIComp        AffectedSOPClassUID; /* M */
00064 };
00065
00066 class CEchoRSP
00067 {
00068 public:
00069     /*
00070     Message ID M U
00071     Message ID Being Responded To M
00072     Affected SOP Class UID M U(=)
00073     Status M
00074     */
00075 };
00076
00077 class CFind
00078 {
00079     /*
00080     Failure Refused: Out of Resources A700 (0000,0902)
00081     Identifier does not match SOP Class A900 (0000,0901)
00082     (0000,0902)
00083     Unable to process Cxxx (0000,0901)
00084     (0000,0902)
00085     Cancel Matching terminated due to Cancel
00086     request
00087     FE00 None
00088     Success Matching is complete - No final Identifier
00089     is supplied.
00090     0000 None
00091     Pending Matches are continuing - Current Match
00092     is supplied and any Optional Keys were


```

```
00105 supported in the same manner as
00106 Required Keys.
00107 FF00 Identifier
00108 Matches are continuing - Warning that
00109 one or more Optional Keys were not
00110 supported for existence and/or matching
00111 for this Identifier.
00112 FF01 Identifier
00113 */
00114 };
00115
00116
00117 } // end namespace network
00118
00119 } // end namespace gdcmm
00120
00121 #endif //GDCMDIMSE_H
```


11.499 gdcMFindPatientRootQuery.h File Reference

```
#include "gdcmBaseRootQuery.h"
```

Include dependency graph for gdcMFindPatientRootQuery.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::FindPatientRootQuery](#)
PatientRootQuery.

Namespaces

- namespace [gdcm](#)

11.500 gdcmFindPatientRootQuery.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013   =====*/
00014 #ifndef GDCMFINDPATIENTROOTQUERY_H
00015 #define GDCMFINDPATIENTROOTQUERY_H
00016
00017 #include "gdcmBaseRootQuery.h"
00018
00019 namespace gdcm
00020 {
00021     class GDCM_EXPORT FindPatientRootQuery : public BaseRootQuery
00022     {
00023     public:
00024         FindPatientRootQuery();
00025
00026         void InitializeDataSet(const EQueryLevel& inQueryLevel) override;
00027
00028         std::vector<Tag> GetTagListByLevel(const EQueryLevel& inQueryLevel) override;
00029         bool ValidateQuery(bool inStrict = true) const override;
00030         UIDs::TSName GetAbstractSyntaxUID() const override;
00031     };
00032 } // end namespace gdcm
00033
00034 #endif // GDCMFINDPATIENTROOTQUERY_H

```



```


00025 class GDCM_EXPORT FindStudyRootQuery : public BaseRootQuery
00026 {
00027     friend class QueryFactory;
00028 public:
00029     FindStudyRootQuery();
00030
00031     void InitializeDataSet(const EQueryLevel& inQueryLevel) override;
00032
00033     std::vector<Tag> GetTagListByLevel(const EQueryLevel& inQueryLevel) override;
00034
00035     bool ValidateQuery(bool inStrict = true) const override;
00036
00037     UIDs::TSName GetAbstractSyntaxUID() const override;
00038 };
00039
00040 // end namespace gdcm
00041 #endif // GDCMFINDSTUDYROOTQUERY_H

```


11.503 gdcmImplementationClassUIDSub.h File Reference

```
#include "gdcmTypes.h"
```

Include dependency graph for gdcmImplementationClassUIDSub.h:



This graph shows which files directly or indirectly include this file:



Classes

- class `gdcm::network::ImplementationClassUIDSub`
ImplementationClassUIDSub.

Namespaces

- namespace `gdcm`
- namespace `gdcm::network`

11.504 gdcmImplementationClassUIDSub.h

[Go to the documentation of this file.](#)

```


00001  /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013  =====*/
00014  #ifndef GDCMIMPLEMENTATIONCLASSUIDSUB_H
00015  #define GDCMIMPLEMENTATIONCLASSUIDSUB_H
00016
00017  #include "gdcmTypes.h"
00018
00019  namespace gdcm
00020  {
00021
00022  namespace network
00023  {
00024
00031  class ImplementationClassUIDSub
00032  {
00033  public:
00034      ImplementationClassUIDSub();
00035      std::istream &Read(std::istream &is);
00036      const std::ostream &Write(std::ostream &os) const;
00037
00038      size_t Size() const;
00039
00040      void Print(std::ostream &os) const;
00041
00042  private:
00043      static const uint8_t ItemType;
00044      static const uint8_t Reserved2;
00045      uint16_t ItemLength;
00046      std::string ImplementationClassUID;
00047  };
00048
00049  } // end namespace network
00050
00051  } // end namespace gdcm
00052
00053  #endif //GDCMMAXIMUMLENGTHSUB_H

```

11.505 gdcmImplementationUIDSub.h File Reference

```
#include "gdcmTypes.h"
```

Include dependency graph for gdcmImplementationUIDSub.h:



Classes

- class [gdcm::network::ImplementationUIDSub](#)
ImplementationUIDSub.

Namespaces

- namespace [gdcm](#)
- namespace [gdcm::network](#)

11.506 gdcmImplementationUIDSub.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013   =====*/
00014 #ifndef GDCMIMPLEMENTATIONUIDSUB_H
00015 #define GDCMIMPLEMENTATIONUIDSUB_H
00016
00017 #include "gdcmTypes.h"
00018
00019 namespace gdcm
00020 {

```



```


00021
00022 namespace network
00023 {
00024
00030 class GDCM_EXPORT ImplementationUIDSub
00031 {
00032 public:
00033     ImplementationUIDSub();
00034     const std::ostream &Write(std::ostream &os) const;
00035 private:
00036     static const uint8_t ItemType;
00037     static const uint8_t Reserved2;
00038     uint16_t ItemLength;
00039     std::string ImplementationClassUID;
00040 };
00041
00042 } // end namespace network
00043
00044 } // end namespace gdcm
00045
00046 #endif //GDCMMAXIMULENGTHSUB_H

```


11.507 gdcmImplementationVersionNameSub.h File Reference

```
#include "gdcmTypes.h"
```

Include dependency graph for gdcmImplementationVersionNameSub.h:



This graph shows which files directly or indirectly include this file:



Classes

- class `gdcml::network::ImplementationVersionNameSub`
ImplementationVersionNameSub.

Namespaces

- namespace `gdcml`
- namespace `gdcml::network`

11.508 gdcmlImplementationVersionNameSub.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003     Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005     Copyright (c) 2006-2011 Mathieu Malaterre
00006     All rights reserved.
00007     See Copyright.txt or http://gdcml.sourceforge.net/Copyright.html for details.
00008
00009     This software is distributed WITHOUT ANY WARRANTY; without even
00010     the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011     PURPOSE. See the above copyright notice for more information.
00012
00013     =====*/
00014 #ifndef GDCMIMPLEMENTATIONVERSIONNAMESUB_H
00015 #define GDCMIMPLEMENTATIONVERSIONNAMESUB_H
00016
00017 #include "gdcmlTypes.h"
00018
00019 namespace gdcml
00020 {
00021
00022     namespace network
00023     {
00024
00025         class ImplementationVersionNameSub
00026         {
00027
00028         
```

```


00032 public:
00033     ImplementationVersionNameSub();
00034     std::istream &Read(std::istream &is);
00035     const std::ostream &Write(std::ostream &os) const;
00036
00037     size_t Size() const;
00038     void Print(std::ostream &os) const;
00039
00040 private:
00041     static const uint8_t ItemType;
00042     static const uint8_t Reserved2;
00043     uint16_t ItemLength;
00044     std::string ImplementationVersionName;
00045 };
00046
00047 } // end namespace network
00048
00049 } // end namespace gdcm
00050
00051 #endif //GDCMMAXIMUMLENGTHSUB_H

```


11.509 gdcmMaximumLengthSub.h File Reference

```
#include "gdcmTypes.h"
```

Include dependency graph for gdcmMaximumLengthSub.h:



This graph shows which files directly or indirectly include this file:



Classes

- class `gdcm::network::MaximumLengthSub`
MaximumLengthSub.

Namespaces

- namespace `gdcm`
- namespace `gdcm::network`

11.510 gdcmMaximumLengthSub.h

[Go to the documentation of this file.](#)


```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013   =====*/
00014 #ifndef GDCMMAXIMUMLENGTHSUB_H
00015 #define GDCMMAXIMUMLENGTHSUB_H
00016
00017 #include "gdcmTypes.h"
00018
00019 namespace gdcm
00020 {
00021
00022   namespace network
00023   {
00024
00025     class MaximumLengthSub
00026     {
00027     public:
00028       MaximumLengthSub();
00029       std::istream &Read(std::istream &is);
00030       const std::ostream &Write(std::ostream &os) const;
00031
00032       size_t Size() const;
00033
00034       uint32_t GetMaximumLength() const { return MaximumLength; }
00035       void SetMaximumLength(uint32_t maximumlength);
00036
00037       void Print(std::ostream &os) const;
00038
00039     private:
00040       static const uint8_t ItemType;
00041       static const uint8_t Reserved2;
00042       uint16_t ItemLength;
00043       uint32_t MaximumLength;
00044     };
00045
00046   } // end namespace network
00047
00048 } // end namespace gdcm
00049
00050 #endif //GDCMMAXIMUMLENGTHSUB_H

```


11.513 gdcModalityPerformedProcedureStepSetQuery.h File Reference

Include dependency graph for `gdcModalityPerformedProcedureStepSetQuery.h`:



- class `gdcmm::ModalityPerformedProcedureStepSetQuery`
`ModalityPerformedProcedureStepSetQuery.`

- namespace **gdcm**

Classes

- class [gdcm::MovePatientRootQuery](#)
MovePatientRootQuery.

Namespaces

- namespace [gdcm](#)

11.516 gdcmMovePatientRootQuery.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013   =====*/
00014 #ifndef GDCMMOVEPATIENTROOTQUERY_H
00015 #define GDCMMOVEPATIENTROOTQUERY_H
00016
00017 #include "gdcmFindPatientRootQuery.h"
00018
00019 namespace gdcm
00020 {
00021     class GDCM_EXPORT MovePatientRootQuery : public BaseRootQuery
00022     {
00023     public:
00024         friend class QueryFactory;
00025         MovePatientRootQuery();
00026
00027         void InitializeDataSet(const EQueryLevel& inQueryLevel) override;
00028
00029         std::vector<Tag> GetTagListByLevel(const EQueryLevel& inQueryLevel) override;
00030
00031         bool ValidateQuery(bool inStrict = true) const override;
00032
00033         UIDs::TSName GetAbstractSyntaxUID() const override;
00034     };
00035 }
00036
00037 // end namespace gdcm
00038
00039 #endif // GDCMMOVEPATIENTROOTQUERY_H

```


Classes

- class [gdcm::network::NCreateRQ](#)
NCreateRQ.
- class [gdcm::network::NCreateRSP](#)
NCreateRSP this file defines the messages for the ncreate action.

Namespaces

- namespace [gdcm](#)
- namespace [gdcm::network](#)

11.522 gdcmNCreateMessages.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003     Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005     Copyright (c) 2006-2014 Mathieu Malaterre
00006     All rights reserved.
00007     See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009     This software is distributed WITHOUT ANY WARRANTY; without even
00010     the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011     PURPOSE. See the above copyright notice for more information.
00012
00013     =====*/
00014 #ifndef GDCMCNCREATEMESSAGES_H
00015 #define GDCMCNCREATEMESSAGES_H
00016
00017 #include "gdcmBaseNormalizedMessage.h"
00018
00019 namespace gdcm{
00020     namespace network{
00021
00022     class ULConnection;
00023
00028     class NCreateRQ : public BaseNormalizedMessage {
00029     public:
00030         std::vector<PresentationDataValue> ConstructPDV(const ULConnection &inConnection,
00031             const BaseQuery* inQuery) override;
00032     };
00033
00038     class NCreateRSP : public BaseNormalizedMessage {
00039     public:
00040         std::vector<PresentationDataValue> ConstructPDVByDataSet(const DataSet* inDataSet);
00041     };
00042     }
00043 }
00044 #endif // GDCMCNCREATEMESSAGES_H

```




```

00016
00017 #include "gdcmBaseNormalizedMessage.h"
00018
00019 namespace gdcm{
00020     namespace network{
00021
00022     class ULConnection;
00023
00028     class NDeleteRQ : public BaseNormalizedMessage {
00029     public:
00030         std::vector<PresentationDataValue> ConstructPDV(const ULConnection &inConnection,
00031             const BaseQuery* inQuery) override;
00032     };
00033
00038     class NDeleteRSP : public BaseNormalizedMessage {
00039     public:
00040         std::vector<PresentationDataValue> ConstructPDVByDataSet(const DataSet* inDataSet);
00041     };
00042     }
00043 }
00044 #endif // GDCMCNDELETEMESSAGES_H

```

11.525 gdcmNetworkEvents.h File Reference

This graph shows which files directly or indirectly include this file:



Namespaces

- namespace `gdcm`
- namespace `gdcm::network`

Enumerations

- enum `gdcm::network::EEventID` {
`gdcm::network::eAASSOCIATERequestLocalUser = 0` ,
`gdcm::network::eTransportConnConfirmLocal` ,
`gdcm::network::eASSOCIATE_ACPDUreceived` ,
`gdcm::network::eASSOCIATE_RJPDUreceived` ,
`gdcm::network::eTransportConnIndicLocal` ,
`gdcm::network::eAASSOCIATE_RQPDUreceived` ,

```

gdcm::network::eAASSOCIATEresponseAccept ,
gdcm::network::eAASSOCIATEresponseReject ,
gdcm::network::ePDATArequest ,
gdcm::network::ePDATATFPDU ,
gdcm::network::eARELEASERequest ,
gdcm::network::eARELEASE_RQPDUReceivedOpen ,
gdcm::network::eARELEASE_RPPDUReceived ,
gdcm::network::eARELEASEResponse ,
gdcm::network::eAABORTRequest ,
gdcm::network::eAABORTPDUReceivedOpen ,
gdcm::network::eTransportConnectionClosed ,
gdcm::network::eARTIMTimerExpired ,
gdcm::network::eUnrecognizedPDUReceived ,
gdcm::network::eEventDoesNotExist }

```

Variables

- const int gdcm::network::cMaxEventID = eEventDoesNotExist

11.526 gdcmNetworkEvents.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002  *
00003  * Copyright NumFOCUS
00004  *
00005  * Licensed under the Apache License, Version 2.0 (the "License");
00006  * you may not use this file except in compliance with the License.
00007  * You may obtain a copy of the License at
00008  *
00009  * http://www.apache.org/licenses/LICENSE-2.0.txt
00010  *
00011  * Unless required by applicable law or agreed to in writing, software
00012  * distributed under the License is distributed on an "AS IS" BASIS,
00013  * WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied.
00014  * See the License for the specific language governing permissions and
00015  * limitations under the License.
00016  *
00017  *=====*/
00018 /*
00019 The NetworkEvents enumeration defines the inputs into the state of the network connection.
00020
00021 These inputs can come either from user input or input from other things on the socket,
00022 ie, responses from the peer or ARTIM timeouts.
00023
00024 Note that this enumeration is not 'power of two', like the states, because you can't have
00025 multiple simultaneous events. Multiple state outputs in transition tables, however, is possible.
00026
00027 */
00028 #ifndef GDCMNETWORKEVENTS_H
00029 #define GDCMNETWORKEVENTS_H
00030
00031 namespace gdcm {
00032 namespace network {
00033 typedef enum {
00034 eAASSOCIATERequestLocalUser = 0,
00035 eTransportConnConfirmLocal,
00036 eASSOCIATE_ACPDUreceived,
00037 eASSOCIATE_RJPDUreceived,
00038 eTransportConnIndicLocal,
00039 eAASSOCIATE_RQPDUreceived,
00040 eAASSOCIATEresponseAccept,
00041 eAASSOCIATEresponseReject,
00042 ePDATArequest,

```


```

00043     ePDATATFPDU,
00044     eARELEASERequest,
00045     eARELEASE_RQPDUReceivedOpen,
00046     eARELEASE_RPPDUReceived,
00047     eARELEASEResponse,
00048     eAABORTRequest,
00049     eAABORTPDUReceivedOpen,
00050     eTransportConnectionClosed,
00051     eARTIMTimerExpired,
00052     eUnrecognizedPDUReceived,
00053     eEventDoesNotExist
00054 } EEventID;
00055
00056 const int cMaxEventID = eEventDoesNotExist;
00057 }
00058 }
00059
00060 #endif //NETWORKEVENTS_H

```

11.527 gdcmlNetworkStateID.h File Reference

This graph shows which files directly or indirectly include this file:



Namespaces

- namespace [gdcml](#)
- namespace [gdcml::network](#)

Enumerations

- enum [gdcml::network::EStateID](#) {
[gdcml::network::eStaDoesNotExist](#) = 0 ,
[gdcml::network::eSta1Idle](#) = 1 ,
[gdcml::network::eSta2Open](#) = 2 ,
[gdcml::network::eSta3WaitLocalAssoc](#) = 4 ,
[gdcml::network::eSta4LocalAssocDone](#) = 8 ,
[gdcml::network::eSta5WaitRemoteAssoc](#) = 16 ,
[gdcml::network::eSta6TransferReady](#) = 32 ,
[gdcml::network::eSta7WaitRelease](#) = 64 ,
[gdcml::network::eSta8WaitLocalRelease](#) = 128 ,
[gdcml::network::eSta9ReleaseCollisionRqLocal](#) = 256 ,
[gdcml::network::eSta10ReleaseCollisionAc](#) = 512 ,
[gdcml::network::eSta11ReleaseCollisionRq](#) = 1024 ,
[gdcml::network::eSta12ReleaseCollisionAcLocal](#) = 2048 ,
[gdcml::network::eSta13AwaitingClose](#) = 4096 }

Functions

- `int gdcm::network::GetStateIndex (EStateID inState)`

Variables

- `const int gdcm::network::cMaxStateID = 13`

11.528 gdcmNetworkStateID.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002  *
00003  *   Copyright NumFOCUS
00004  *
00005  *   Licensed under the Apache License, Version 2.0 (the "License");
00006  *   you may not use this file except in compliance with the License.
00007  *   You may obtain a copy of the License at
00008  *
00009  *       http://www.apache.org/licenses/LICENSE-2.0.txt
00010  *
00011  *   Unless required by applicable law or agreed to in writing, software
00012  *   distributed under the License is distributed on an "AS IS" BASIS,
00013  *   WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied.
00014  *   See the License for the specific language governing permissions and
00015  *   limitations under the License.
00016  *
00017  *=====*/
00018 #ifndef GDCMNETWORKSTATEID_H
00019 #define GDCMNETWORKSTATEID_H
00020
00021 namespace gdcm {
00022     namespace network {
00023
00024         enum EStateID {
00025             eStaDoesNotExist = 0,
00026             eStaIdle = 1,
00027             eSta2Open = 2,
00028             eSta3WaitLocalAssoc = 4,
00029             eSta4LocalAssocDone = 8,
00030             eSta5WaitRemoteAssoc = 16,
00031             eSta6TransferReady = 32,
00032             eSta7WaitRelease = 64,
00033             eSta8WaitLocalRelease = 128,
00034             eSta9ReleaseCollisionRqLocal = 256,
00035             eSta10ReleaseCollisionAc = 512,
00036             eSta11ReleaseCollisionRq = 1024,
00037             eSta12ReleaseCollisionAcLocal = 2048,
00038             eSta13AwaitingClose = 4096
00039         };
00040
00041         const int cMaxStateID = 13;
00042
00043         //the transition table is built on state indices
00044         //this function will produce the index from the power-of-two EStateID
00045         inline int GetStateIndex(EStateID inState){
00046             switch (inState){
00047                 case eStaDoesNotExist:
00048                     default:
00049                         return -1;
00050                 case eStaIdle:
00051                     return 0;
00052                 case eSta2Open:
00053                     return 1;
00054                 case eSta3WaitLocalAssoc:
00055                     return 2;
00056                 case eSta4LocalAssocDone:
00057                     return 3;
00058                 case eSta5WaitRemoteAssoc:
00059                     return 4;
00060             }
00061         }
00062     }
00063 }

```


11.530 gdcmlNEventReportMessages.h

[Go to the documentation of this file.](#)

```


00001  /*=====*/
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2014 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013  =====*/
00014  #ifndef GDCMCNEVENTREPORTMESSAGES_H
00015  #define GDCMCNEVENTREPORTMESSAGES_H
00016
00017  #include "gdcmBaseNormalizedMessage.h"
00018
00019  namespace gdcm{
00020    namespace network{
00021
00022      class ULConnection;
00023
00024      class NEventReportRQ : public BaseNormalizedMessage {
00025      public:
00026        std::vector<PresentationDataValue> ConstructPDV(const ULConnection &inConnection,
00027              const BaseQuery* inQuery) override;
00028      };
00029
00030      class NEventReportRSP : public BaseNormalizedMessage {
00031      public:
00032        std::vector<PresentationDataValue> ConstructPDVByDataSet(const DataSet* inDataSet);
00033      };
00034    }
00035  }
00036  #endif // GDCMCNEVENTREPORTMESSAGES_H

```

11.531 gdcnNGetMessages.h File Reference

```
#include "gdcmBaseNormalizedMessage.h"
```

Include dependency graph for gdcmnGetMessages.h:



Classes

- class `gdcm::network::NGetRQ`
NGetRQ.
- class `gdcm::network::NGetRSP`
NGetRSP this file defines the messages for the nget action.

Namespaces

- namespace `gdcm`
- namespace `gdcm::network`

11.532 gdcmNGetMessages.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2014 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMCNGETMESSAGES_H
00015 #define GDCMCNGETMESSAGES_H
00016
00017 #include "gdcmBaseNormalizedMessage.h"
00018
00019 namespace gdcm{
00020     namespace network{
00021
00022     class ULConnection;
00023
00024     class NGetRQ : public BaseNormalizedMessage {
00025     public:
00026         std::vector<PresentationDataValue> ConstructPDV(const ULConnection &inConnection,
00027             const BaseQuery* inQuery) override;
00028     };
00029
00030     class NGetRSP : public BaseNormalizedMessage {
00031     public:
00032         std::vector<PresentationDataValue> ConstructPDVByDataSet(const DataSet* inDataSet);
00033     };
00034     }
00035 }
00036 #endif // GDCMCNGETMESSAGES_H

```


11.533 gdcmNormalizedMessageFactory.h File Reference

```

#include "gdcmPresentationDataValue.h"
#include "gdcmULConnection.h"

```

Include dependency graph for gdcmNormalizedMessageFactory.h:



Classes

- class [gdcm::network::NormalizedMessageFactory](#)

Namespaces

- namespace [gdcm](#)
- namespace [gdcm::network](#)

11.534 gdcmNormalizedMessageFactory.h

[Go to the documentation of this file.](#)

```

00001  /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2014 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013  =====*/
00014  #ifndef GDCMNORMALIZEDMESSAGEFACTORY_H
00015  #define GDCMNORMALIZEDMESSAGEFACTORY_H
00016
00017  #include "gdcmPresentationDataValue.h"
00018  #include "gdcmULConnection.h"
00019
00020  namespace gdcm {
00021      class BaseQuery;
00022      class File;
00023      namespace network {
00024          class BasePDU;
00025
00026          class NormalizedMessageFactory
00027          {
00028          public:
00029              static std::vector<PresentationDataValue> ConstructNEventReport (const ULConnection& inConnection,
00030              const BaseQuery* inQuery);
00031              static std::vector<PresentationDataValue> ConstructNGet (const ULConnection& inConnection,
00032              const BaseQuery* inQuery);
00033              static std::vector<PresentationDataValue> ConstructNSet (const ULConnection& inConnection,
00034              const BaseQuery* inQuery);
00035          };
00036      }
00037  }

```


11.536 gdcmNormalizedNetworkFunctions.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2014 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMNORMALIZEDNETWORKFUNCTIONS_H
00015 #define GDCMNORMALIZEDNETWORKFUNCTIONS_H
00016
00017 #include "gdcmDirectory.h"
00018 #include "gdcmBaseQuery.h" // EQueryLevel / EQueryType
00019
00020 #include <vector>
00021 #include <string>
00022
00023 namespace gdcm
00024 {
00046 class GDCM_EXPORT NormalizedNetworkFunctions
00047 {
00048 public:
00049   static BaseQuery* ConstructQuery( const std::string & sopInstanceUID,
00050                                     const DataSet& queryds, ENQueryType queryType = eCreateMMPS );
00051   static bool NEventReport( const char *remote, uint16_t portno,
00052                             const BaseQuery* query, std::vector<DataSet> &retDataSets,
00053                             const char *aetitle, const char *call );
00054   static bool NGet( const char *remote, uint16_t portno,
00055                     const BaseQuery* query, std::vector<DataSet> &retDataSets,
00056                     const char *aetitle, const char *call );
00057   static bool NSet( const char *remote, uint16_t portno,
00058                     const BaseQuery* query, std::vector<DataSet> &retDataSets,
00059                     const char *aetitle, const char *call );
00060   static bool NAction( const char *remote, uint16_t portno,
00061                        const BaseQuery* query, std::vector<DataSet> &retDataSets,
00062                        const char *aetitle, const char *call );
00063   static bool NCreate( const char *remote, uint16_t portno,
00064                        BaseQuery* query, std::vector<DataSet> &retDataSets,
00065                        const char *aetitle, const char *call );
00066   static bool NDelete( const char *remote, uint16_t portno,
00067                        const BaseQuery* query, std::vector<DataSet> &retDataSets,
00068                        const char *aetitle, const char *call );
00069 };
00070
00071 } // end namespace gdcm
00072
00073 #endif // GDCMCOMPOSITENETWORKFUNCTIONS_H

```



```

00016
00017 #include "gdcmBaseNormalizedMessage.h"
00018
00019 namespace gdcm{
00020     namespace network{
00021
00022     class ULConnection;
00023
00024     class NSetRQ : public BaseNormalizedMessage {
00025     public:
00026         std::vector<PresentationDataValue> ConstructPDV(const ULConnection &inConnection,
00027             const BaseQuery* inQuery) override;
00028     };
00029
00030     class NSetRSP : public BaseNormalizedMessage {
00031     public:
00032         std::vector<PresentationDataValue> ConstructPDVByDataSet(const DataSet* inDataSet);
00033     };
00034 }
00035 #endif // GDCMCNSETMESSAGES_H

```


11.539 gdcmPDataTFPDU.h File Reference

```

#include "gdcmTypes.h"
#include "gdcmPresentationDataValue.h"
#include "gdcmBasePDU.h"
#include <limits>

```

Include dependency graph for gdcmPDataTFPDU.h:



Classes

- class `gdcm::network::PDataTFPDU`
PDataTFPDU.

Namespaces

- namespace `gdcm`
- namespace `gdcm::network`

11.540 gdcmPDataTFPDU.h

[Go to the documentation of this file.](#)

```


00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMPDATATFPDU_H
00015 #define GDCMPDATATFPDU_H
00016
00017 #include "gdcmTypes.h"
00018 #include "gdcmPresentationDataValue.h"
00019 #include "gdcmBasePDU.h"
00020 #include <limits>
00021
00022 namespace gdcm
00023 {
00024
00025 namespace network
00026 {
00027
00033 class GDCM_EXPORT PDataTFPDU : public BasePDU
00034 {
00035 public:
00036   PDataTFPDU();
00037   std::istream &Read(std::istream &is) override;
00038   const std::ostream &Write(std::ostream &os) const override;
00039
00041   size_t Size() const override;
00042
00043   void AddPresentationDataValue( PresentationDataValue const &pdv ) {
00044     V.push_back( pdv );
00045     gdcm_assert( Size() < std::numeric_limits<uint32_t>::max() );
00046     ItemLength = (uint32_t)Size() - 6;
00047   }
00048
00049   typedef std::vector<PresentationDataValue>::size_type SizeType;
00050   PresentationDataValue const &GetPresentationDataValue( SizeType i ) const {
00051     gdcm_assert( !V.empty() && i < V.size() );
00052     return V[i];
00053   }
00054   SizeType GetNumberOfPresentationDataValues() const {
00055     return V.size();
00056   }
00057
00058   void Print(std::ostream &os) const override;
00059   bool IsLastFragment() const override;
00060
00061 protected:
00062   std::istream &ReadInto(std::istream &is, std::ostream &os);
00063 private:
00064   static const uint8_t ItemType; // PDUType ?
00065   static const uint8_t Reserved2;
00066   uint32_t ItemLength; // PDU Length ?
00067   std::vector<PresentationDataValue> V;
00068 };
00069
00070 } // end namespace network
00071
00072 } // end namespace gdcm
00073
00074 #endif //GDCMPDATATFPDU_H

```

11.541 gdcmPDUFactory.h File Reference

```
#include "gdcmTypes.h"
#include "gdcmNetworkEvents.h"
#include "gdcmULConnection.h"
#include "gdcmPresentationDataValue.h"
```

Include dependency graph for gdcmPDUFactory.h:



Classes

- class [gdcm::network::PDUFactory](#)
PDUFactory basically, given an initial byte, construct the.

Namespaces

- namespace [gdcm](#)
- namespace [gdcm::network](#)

11.542 gdcmPDUFactory.h

[Go to the documentation of this file.](#)

```
00001 /*=====
00002  *
00003  *   Copyright NumFOCUS
00004  *
00005  *   Licensed under the Apache License, Version 2.0 (the "License");
00006  *   you may not use this file except in compliance with the License.
00007  *   You may obtain a copy of the License at
00008  *
00009  *       http://www.apache.org/licenses/LICENSE-2.0.txt
00010  *
00011  *   Unless required by applicable law or agreed to in writing, software
00012  *   distributed under the License is distributed on an "AS IS" BASIS,
00013  *   WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied.
00014  *   See the License for the specific language governing permissions and
00015  *   limitations under the License.
00016  *
00017  *=====*/
00018 #ifndef GDCMPDUFACTORY_H
00019 #define GDCMPDUFACTORY_H
00020
00021 #include "gdcmTypes.h"
00022 #include "gdcmNetworkEvents.h"
```

```

00023 #include "gdcmULConnection.h"
00024 #include "gdcmPresentationDataValue.h"
00025
00026 namespace gdcm{
00027     class BaseRootQuery;
00028     class BaseQuery;
00029     class File;
00030     namespace network{
00031         class BasePDU;
00032
00033         class PDUFactory {
00034         public:
00035             static BasePDU* ConstructPDU(uint8_t itemtype); //eventually needs to be smartpointer'd
00036             static EEventID DetermineEventByPDU(const BasePDU* inPDU);
00037             static BasePDU* ConstructReleasePDU();
00038             static BasePDU* ConstructAbortPDU();
00039
00040             //these are the composite PDU construction methods for the PDataPDUs.
00041             //basically, builds a pdatapdu, and then puts the appropriate information in
00042             //for the appropriate composite service (c-echo, c-find, c-store, c-get, c-move)
00043             //the connection is necessary to construct the stream of PDVs that will
00044             //be then placed into the vector of PDUs
00045             static std::vector<BasePDU*> CreateCEchoPDU(const ULConnection& inConnection);
00046             static std::vector<BasePDU*> CreateCStoreRQPDU(const ULConnection& inConnection, const File &file,
00047             bool writeDataSet = true );
00048             static std::vector<BasePDU*> CreateCStoreRSPDU(const DataSet *inDataSet, const BasePDU* inPC);
00049             static std::vector<BasePDU*> CreateCFindPDU(const ULConnection& inConnection, const BaseRootQuery*
00050             inRootQuery);
00051             static std::vector<BasePDU*> CreateCMovePDU(const ULConnection& inConnection, const BaseRootQuery*
00052             inRootQuery);
00053
00054             static std::vector<BasePDU*> CreateNEventReportPDU (const ULConnection& inConnection, const BaseQuery
00055             *inQuery);
00056             static std::vector<BasePDU*> CreateNGetPDU (const ULConnection& inConnection, const BaseQuery
00057             *inQuery);
00058             static std::vector<BasePDU*> CreateNSetPDU (const ULConnection& inConnection, const BaseQuery
00059             *inQuery);
00060             static std::vector<BasePDU*> CreateNActionPDU (const ULConnection& inConnection, const BaseQuery
00061             *inQuery);
00062             static std::vector<BasePDU*> CreateNCreatePDU (const ULConnection& inConnection, const BaseQuery
00063             *inQuery);
00064             static std::vector<BasePDU*> CreateNDeletePDU (const ULConnection& inConnection, const BaseQuery
00065             *inQuery);
00066
00067             //given data pdus, produce the presentation data values stored within.
00068             //all operations have these as the payload of the data sending operation
00069             //however, echo does not have a dataset in the pdv.
00070             static std::vector<PresentationDataValue> GetPDVs(const std::vector<BasePDU*> & inDataPDUs);
00071         };
00072     }
00073 }
00074 #endif //GDCMPDUFACTORY_H

```


11.543 gdcmPresentationContext.h File Reference

```


#include "gdcmTypes.h"
#include "gdcmUIDs.h"
#include <vector>

```

Include dependency graph for gdcmPresentationContext.h:



This graph shows which files directly or indirectly include this file:



Classes

- class `gdcm::PresentationContext`
PresentationContext.

Namespaces

- namespace `gdcm`

11.544 gdcmPresentationContext.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMPRESENTATIONCONTEXT_H
00015 #define GDCMPRESENTATIONCONTEXT_H
00016
00017 #include "gdcmTypes.h"
00018 #include "gdcmUIDs.h"
00019
00020 #include <vector>
00021
00022 namespace gdcm
00023 {
00024
00025     class GDCM_EXPORT PresentationContext
00026     {
00027     public:
00028         PresentationContext();
00029
00030         PresentationContext( UID::TSName asname,
00031             UID::TSName tsname = UID::ImplicitVRLittleEndianDefaultTransferSyntaxforDICOM );
00032
00033         void SetAbstractSyntax( const char *absyn ) { AbstractSyntax = absyn; }
00034         const char *GetAbstractSyntax() const { return AbstractSyntax.c_str(); }
00035
00036         void AddTransferSyntax( const char *tsstr );
00037         typedef std::vector<std::string> TransferSyntaxArrayType;
00038         typedef TransferSyntaxArrayType::size_type SizeType;
00039         const char *GetTransferSyntax(SizeType i) const { return TransferSyntaxes[i].c_str(); }
00040         SizeType GetNumberOfTransferSyntaxes() const { return TransferSyntaxes.size(); }
00041
00042         void SetPresentationContextID( uint8_t id );
00043         uint8_t GetPresentationContextID() const;
00044
00045         void Print(std::ostream &os) const;
00046
00047         bool operator==(const PresentationContext & pc) const
00048         {
00049             gdcm_assert( TransferSyntaxes.size() == 1 ); // TODO
00050             gdcm_assert( pc.TransferSyntaxes.size() == 1 );
00051             return AbstractSyntax == pc.AbstractSyntax && TransferSyntaxes == pc.TransferSyntaxes;
00052         }
00053     protected :
00054         std::string AbstractSyntax;
00055         std::vector<std::string> TransferSyntaxes;
00056         uint8_t /*PresentationContext*/ID;
00057     };
00058
00059 } // end namespace gdcm
00060
00061 #endif //GDCMPRESENTATIONCONTEXT_H

```


11.545 gdcmPresentationContextAC.h File Reference

```


#include "gdcmTypes.h"
#include "gdcmTransferSyntaxSub.h"

```

Include dependency graph for gdcmPresentationContextAC.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::network::PresentationContextAC](#)
PresentationContextAC.

Namespaces

- namespace [gdcm](#)
- namespace [gdcm::network](#)

11.546 gdcmPresentationContextAC.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003     Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005     Copyright (c) 2006-2011 Mathieu Malaterre
00006     All rights reserved.
00007     See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009     This software is distributed WITHOUT ANY WARRANTY; without even
00010     the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011     PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMPRESENTATIONCONTEXTAC_H
00015 #define GDCMPRESENTATIONCONTEXTAC_H
00016
00017 #include "gdcmTypes.h"
00018 #include "gdcmTransferSyntaxSub.h"
00019
00020 namespace gdcm
00021 {
00022
00023     namespace network
00024     {
00025
00032         class PresentationContextAC
00033         {
00034         public:
00035             PresentationContextAC();
00036             std::istream &Read(std::istream &is);
00037             const std::ostream &Write(std::ostream &os) const;
00038
00039             size_t Size() const;
00040
00041             void SetTransferSyntax( TransferSyntaxSub const &ts );
00042             void SetPresentationContextID( uint8_t id );
00043
00044             void Print(std::ostream &os) const;
00045
00046             uint8_t GetPresentationContextID() const
00047             {
00048                 return ID;
00049             }
00050             TransferSyntaxSub const & GetTransferSyntax() const { return SubItems; }
00051
00052             void SetReason( uint8_t r ) { Result = r; }
00053             uint8_t GetReason() const { return Result; }
00054
00055         private:
00056             static const uint8_t ItemType;
00057             static const uint8_t Reserved2;
00058             uint16_t ItemLength; // len of last transfer syntax
00059             uint8_t /*PresentationContext*/ID;
00060             static const uint8_t Reserved6;
00061             uint8_t /*Reason*/Result;
00062             static const uint8_t Reserved8;
00063             TransferSyntaxSub SubItems;
00064         };
00065
00066     } // end namespace network
00067
00068 } // end namespace gdcm
00069
00070 #endif //GDCMPRESENTATIONCONTEXTAC_H

```


11.547 gdcmPresentationContextGenerator.h File Reference

```

#include "gdcmDirectory.h"
#include "gdcmPresentationContext.h"

```


Include dependency graph for gdcmPresentationContextGenerator.h:



Classes

- class [gdcm::PresentationContextGenerator](#)
PresentationContextGenerator.

Namespaces

- namespace [gdcm](#)

11.548 gdcmPresentationContextGenerator.h

[Go to the documentation of this file.](#)


```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013   =====*/
00014 #ifndef GDCMPRESENTATIONCONTEXTGENERATOR_H
00015 #define GDCMPRESENTATIONCONTEXTGENERATOR_H
00016
00017 #include "gdcmDirectory.h"
00018 #include "gdcmPresentationContext.h"
00019
00020 namespace gdcm
00021 {

```

11.549 gdcmpresentationcontextrq.h File Reference

This graph shows which files directly or indirectly include this file:



Classes

- class `gdcm::network::PresentationContextRQ`
PresentationContextRQ.

Namespaces

- namespace `gdcm`
- namespace `gdcm::network`

11.550 gdcmPresentationContextRQ.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003     Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005     Copyright (c) 2006-2011 Mathieu Malaterre
00006     All rights reserved.
00007     See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009     This software is distributed WITHOUT ANY WARRANTY; without even
00010     the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011     PURPOSE. See the above copyright notice for more information.
00012
00013     =====*/
00014 #ifndef GDCMPRESENTATIONCONTEXTTRQ_H
00015 #define GDCMPRESENTATIONCONTEXTTRQ_H
00016
00017 #include "gdcmTypes.h"
00018 #include "gdcmAbstractSyntax.h"
00019 #include "gdcmTransferSyntaxSub.h"
00020 #include "gdcmDataSet.h"
00021
00022 namespace gdcm
00023 {
00024     class PresentationContext;
00025     namespace network
00026     {
00027
00034     class GDCM_EXPORT PresentationContextRQ
00035     {
00036     public:
00037         PresentationContextRQ();
00038     }
  
```

```

00042 PresentationContextRQ( UIDs::TSName asname, UIDs::TSName tname =
00043     UIDs::ImplicitVRLittleEndianDefaultTransferSyntaxforDICOM );
00044
00045 std::istream &Read(std::istream &is);
00046 const std::ostream &Write(std::ostream &os) const;
00047 size_t Size() const;
00048
00049 void SetAbstractSyntax( AbstractSyntax const & absyn );
00050 AbstractSyntax const &GetAbstractSyntax() const { return SubItems; }
00051 AbstractSyntax &GetAbstractSyntax() { return SubItems; }
00052
00053 void AddTransferSyntax( TransferSyntaxSub const &ts );
00054 typedef std::vector<TransferSyntaxSub>::size_type SizeType;
00055 TransferSyntaxSub const &GetTransferSyntax(SizeType i) const { return TransferSyntaxes[i]; }
00056 TransferSyntaxSub &GetTransferSyntax(SizeType i) { return TransferSyntaxes[i]; }
00057 std::vector<TransferSyntaxSub> const &GetTransferSyntaxes() const {return TransferSyntaxes; }
00058 SizeType GetNumberOfTransferSyntaxes() const { return TransferSyntaxes.size(); }
00059
00060 void SetPresentationContextID( uint8_t id );
00061 uint8_t GetPresentationContextID() const;
00062
00063 void Print(std::ostream &os) const;
00064
00065 bool operator==(const PresentationContextRQ & pc) const
00066 {
00067     gdcml_assert( TransferSyntaxes.size() == 1 ); // TODO
00068     gdcml_assert( pc.TransferSyntaxes.size() == 1 );
00069     return SubItems == pc.SubItems && TransferSyntaxes == pc.TransferSyntaxes;
00070 }
00071
00072 PresentationContextRQ(const PresentationContext & pc);
00073
00074 private:
00075     static const uint8_t ItemType;
00076     static const uint8_t Reserved2;
00077     uint16_t ItemLength; // len of last transfer syntax
00078     uint8_t /*PresentationContext*/ID;
00079     static const uint8_t Reserved6;
00080     static const uint8_t Reserved7;
00081     static const uint8_t Reserved8;
00082     /*
00083     This variable field shall contain the following sub-items: one Abstract
00084     Syntax and one or more Transfer Syntax(es). For a complete
00085     description of the use and encoding of these sub-items see Sections
00086     9.3.2.2.1 and 9.3.2.2.2.
00087     */
00088     AbstractSyntax SubItems;
00089     std::vector<TransferSyntaxSub> TransferSyntaxes;
00090 };
00091
00092 } // end namespace network
00093
00094 } // end namespace gdcml
00095
00096 #endif //GDCMPRESENTATIONCONTEXTRO_H

```

11.551 gdcmlPresentationDataValue.h File Reference

```

#include "gdcmlTypes.h"
#include <vector>

```

```

graph TD
    gdcmPresentationDataValue.h[gdcmPresentationDataValue.h] --> gdcmTypes.h[gdcmTypes.h]
    gdcmPresentationDataValue.h --> vector[vectord]
    gdcmTypes.h --> gdcmConfigure.h[gdcmConfigure.h]
    gdcmTypes.h --> gdcmWin32.h[gdcmWin32.h]
    gdcmTypes.h --> gdcmLegacyMacro.h[gdcmLegacyMacro.h]
    gdcmTypes.h --> cstdint[cstdint]
    gdcmTypes.h --> gdcmTrace.h[gdcmTrace.h]
    gdcmLegacyMacro.h --> gdcmException.h[gdcmException.h]
    gdcmLegacyMacro.h --> gdcmTrace.h
    gdcmTrace.h --> gdcmException.h
    gdcmTrace.h --> cassert[cassert]
    gdcmTrace.h --> iosfwd[iosfwd]
    gdcmTrace.h --> gdcmSystem.h[gdcmSystem.h]
    gdcmException.h --> cstdlib[cstdlib]
    gdcmException.h --> exception[exception]
    gdcmException.h --> sstream[sstream]
    gdcmException.h --> stdexcept[stdexcept]
    gdcmException.h --> string[string]
    gdcmException.h --> cassert
  
```

- class `gdcm::network::PresentationDataValue`
PresentationDataValue.

- namespace `gdcm`
- namespace `gdcm::network`

[Go to the documentation of this file.](#)

```
00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcml.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013  =====*/
```

```

00014 #ifndef GDCMPRESENTATIONDATAVALUE_H
00015 #define GDCMPRESENTATIONDATAVALUE_H
00016
00017 #include "gdcmTypes.h"
00018
00019 #include <vector>
00020
00021 namespace gdcm
00022 {
00023 class DataSet;
00024 namespace network
00025 {
00026
00032 class GDCM_EXPORT PresentationDataValue
00033 {
00034 public:
00035     PresentationDataValue();
00036     std::istream &Read(std::istream &is);
00037     std::istream &ReadInto(std::istream &is, std::ostream &os);
00038
00039     const std::ostream &Write(std::ostream &os) const;
00040
00042     size_t Size() const;
00043
00046     void SetDataSet(const DataSet & ds);
00047     void SetBlob(const std::string & partialblob);
00048     const std::string &GetBlob() const;
00049
00050     uint8_t GetPresentationContextID() const { return PresentationContextID; }
00051     void SetPresentationContextID(uint8_t id) {
00052         gdcm_assert( id );
00053         PresentationContextID = id;
00054     }
00055     uint8_t GetMessageHeader() const {
00056         gdcm_assert( MessageHeader <= 0x3 );
00057         return MessageHeader;
00058     }
00059     // E.2 MESSAGE CONTROL HEADER ENCODING
00060     // Only the first two bits are considered
00061     void SetMessageHeader(uint8_t messageheader) {
00062         MessageHeader = messageheader;
00063         gdcm_assert( MessageHeader <= 0x3 );
00064     }
00065     //flip the least significant bit of the message header to 1
00066     //if this is a command, else set it to 0.
00067     void SetCommand(bool inCommand);
00068     void SetLastFragment(bool inLast); //set to true if this is the last PDV of a set
00069
00070     bool GetIsCommand() const;
00071     bool GetIsLastFragment() const;
00072
00073     void Print(std::ostream &os) const;
00074
00075     //NOTE that the PDVs have to be given in the order in which they were received!
00076     //also note that a dataset may be across multiple PDVs
00077     static DataSet ConcatenatePDVBlobs(const std::vector<PresentationDataValue>& inPDVs);
00078
00079     static DataSet ConcatenatePDVBlobsAsExplicit(const std::vector<PresentationDataValue>& inPDVs);
00081 private:
00083     uint32_t ItemLength;
00084     uint8_t PresentationContextID;
00085     uint8_t MessageHeader;
00086     std::string Blob;
00087 };
00088 } // end namespace network
00089
00090 } // end namespace gdcm
00091
00092 #endif //GDCMPRESENTATIONDATAVALUE_H

```


11.553 gdcmQueryBase.h File Reference

```


#include "gdcmTag.h"
#include "gdcmDataElement.h"

```

Include dependency graph for gdcmQueryBase.h:



This graph shows which files directly or indirectly include this file:



Classes

- class `gdcm::QueryBase`
QueryBase.

Namespaces

- namespace **gdcm**

Enumerations

- enum `gdcm::ERootType` {
`gdcm::ePatientRootType` ,
`gdcm::eStudyRootType` }

11.554 gdcmQueryBase.h

[Go to the documentation of this file.](#)


```

00001 /*=====
00002  *
00003  *   Copyright NumFOCUS
00004  *
00005  *   Licensed under the Apache License, Version 2.0 (the "License");
00006  *   you may not use this file except in compliance with the License.
00007  *   You may obtain a copy of the License at
00008  *
00009  *       http://www.apache.org/licenses/LICENSE-2.0.txt
00010  *
00011  *   Unless required by applicable law or agreed to in writing, software
00012  *   distributed under the License is distributed on an "AS IS" BASIS,
00013  *   WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied.
00014  *   See the License for the specific language governing permissions and
00015  *   limitations under the License.
00016  *
00017  *=====*/
00018 #ifndef GDCMQUERYBASE_H
00019 #define GDCMQUERYBASE_H
00020
00021 #include "gdcmTag.h"
00022 #include "gdcmDataElement.h"
00023
00024 #include <vector>
00025
00026 namespace gdcm
00027 {
00028     enum ERootType
00029     {
00030         ePatientRootType,
00031         eStudyRootType
00032     };
00033
00060 class GDCM_EXPORT QueryBase
00061 {
00062 public:
00063     virtual ~QueryBase() = default;
00064
00065     virtual std::vector<Tag> GetRequiredTags(const ERootType& inRootType) const = 0;
00066     virtual std::vector<Tag> GetUniqueTags(const ERootType& inRootType) const = 0;
00067     virtual std::vector<Tag> GetOptionalTags(const ERootType& inRootType) const = 0;
00068     // C.4.1.2.1 Baseline Behavior of SCU
00069     // All C-FIND SCUs shall be capable of generating query requests which
00070     // meet the requirements of the Hierarchical Search.
00071     // The Identifier contained in a C-FIND request shall contain a single
00072     // value in the Unique Key Attribute for each level above the
00073     // Query/Retrieve level. No Required or Optional Keys shall be
00074     // specified which are associated with levels above the Query/Retrieve
00075     // level.
00077     virtual std::vector<Tag> GetHierachicalSearchTags(const ERootType& inRootType) const = 0;
00078
00081     std::vector<Tag> GetAllTags(const ERootType& inRootType) const;
00082
00085     std::vector<Tag> GetAllRequiredTags(const ERootType& inRootType) const;
00086
00087     virtual const char * GetName() const = 0;
00088     virtual DataElement GetQueryLevel() const = 0;
00089 };
00090 }
00091
00092 #endif //GDCMQUERYBASE_H

```



```
#include "gdcmBaseRootQuery.h"
Include dependency graph for gdcmQueryFactory.h:
```



- class `gdcm::QueryFactory`
QueryFactory.h.

- namespace **gdcm**

- `enum gdcmm::ECharSet {
gdcmm::eLatin1 = 0 ,
gdcmm::eLatin2 ,
gdcmm::eLatin3 ,
gdcmm::eLatin4 ,
gdcmm::eCyrillic ,
gdcmm::eArabic ,
gdcmm::eGreek ,
gdcmm::eHebrew ,
gdcmm::eLatin5 ,
gdcmm::eJapanese ,
gdcmm::eThai ,
gdcmm::eJapaneseKanjiMultibyte ,
gdcmm::eJapaneseSupplementaryKanjiMultibyte ,
gdcmm::eKoreanHangulHanjaMultibyte ,
gdcmm::eUTF8 ,
gdcmm::eGB18030 }`

11.556 gdcmQueryFactory.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002  *
00003  *   Copyright NumFOCUS
00004  *
00005  *   Licensed under the Apache License, Version 2.0 (the "License");
00006  *   you may not use this file except in compliance with the License.
00007  *   You may obtain a copy of the License at
00008  *
00009  *       http://www.apache.org/licenses/LICENSE-2.0.txt
00010  *
00011  *   Unless required by applicable law or agreed to in writing, software
00012  *   distributed under the License is distributed on an "AS IS" BASIS,
00013  *   WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied.
00014  *   See the License for the specific language governing permissions and
00015  *   limitations under the License.
00016  *
00017  *=====*/
00018 #ifndef GDCMQUERYFACTORY_H
00019 #define GDCMQUERYFACTORY_H
00020
00021 #include "gdcmBaseRootQuery.h"
00022
00023 namespace gdcm{
00024     enum ECharSet {
00025         eLatin1 = 0,
00026         eLatin2,
00027         eLatin3,
00028         eLatin4,
00029         eCyrillic,
00030         eArabic,
00031         eGreek,
00032         eHebrew,
00033         eLatin5, // Latin Alphabet No. 5 (Turkish) Extended
00034         eJapanese, // JIS X 0201 (Shift JIS) Extended
00035         eThai, // TIS 620-2533 (Thai) Extended
00036         eJapaneseKanjiMultibyte, // JIS X 0208 (Kanji) Extended
00037         eJapaneseSupplementaryKanjiMultibyte, // JIS X 0212 (Kanji) Extended
00038         eKoreanHangulHanjaMultibyte, // KS X 1001 (Hangul and Hanja) Extended
00039         eUTF8,
00040         eGB18030 // Chinese (Simplified) Extended
00041     };
00042
00043     class GDCM_EXPORT QueryFactory
00044     {
00045     public:
00046         static BaseQuery* ProduceQuery( const std::string & sopInstanceUID, ENQueryType inQueryType );
00047         static BaseRootQuery* ProduceQuery(ERootType inRootType, EQueryType inQueryType,
00048             EQueryLevel inQueryLevel);
00049         static DataElement ProduceCharacterSetDataElement(
00050             const std::vector<ECharSet>& inCharSetType);
00051         static ECharSet GetCharacterFromCurrentLocale();
00052         static void ListCharSets(std::ostream& os);
00053     };
00054 } // end namespace gdcm
00055 #endif // GDCMQUERYFACTORY_H

```

11.557 gdcmQueryImage.h File Reference

```

#include "gdcmQueryBase.h"
#include "gdcmDataSet.h"

```

[illegible]


- class `gdcm::QueryImage`
QueryImage.

- namespace **gdcm**

[Go to the documentation of this file.](#)

Generated by Doxygen

This graph shows which files directly or indirectly include this file:



Classes

- class `gdcm::QueryPatient`
QueryPatient.

Namespaces

- namespace `gdcm`

11.560 gdcmQueryPatient.h

[Go to the documentation of this file.](#)

```


00001 /*=====
00002  *
00003  *   Copyright NumFOCUS
00004  *
00005  *   Licensed under the Apache License, Version 2.0 (the "License");
00006  *   you may not use this file except in compliance with the License.
00007  *   You may obtain a copy of the License at
00008  *
00009  *       http://www.apache.org/licenses/LICENSE-2.0.txt
00010  *
00011  *   Unless required by applicable law or agreed to in writing, software
00012  *   distributed under the License is distributed on an "AS IS" BASIS,
00013  *   WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied.
00014  *   See the License for the specific language governing permissions and
00015  *   limitations under the License.
00016  *
00017  *=====*/
00018 #ifndef GDCMQUERYPATIENT_H
00019 #define GDCMQUERYPATIENT_H
00020
00021 #include "gdcmQueryBase.h"
00022
00023 namespace gdcm
00024 {
00025     class GDCM_EXPORT QueryPatient : public QueryBase
00026     {
00027     public:
00028         std::vector<Tag> GetRequiredTags(const ERootType& inRootType) const override;
00029         std::vector<Tag> GetUniqueTags(const ERootType& inRootType) const override;
00030         std::vector<Tag> GetOptionalTags(const ERootType& inRootType) const override;
00031         std::vector<Tag> GetHierachicalSearchTags(const ERootType& inRootType) const override;
00032
00033         const char * GetName() const override;
00034         DataElement GetQueryLevel() const override;
00035     };
00036 } // end namespace gdcm
00037
00038 #endif //GDCMQUERYPATIENT_H

```

11.561 gdcmQuerySeries.h File Reference

```
#include "gdcmQueryBase.h"
```

Include dependency graph for gdcmQuerySeries.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::QuerySeries](#)
QuerySeries.

Namespaces

- namespace [gdcm](#)

11.562 gdcmQuerySeries.h


[Go to the documentation of this file.](#)

```
00001 /*=====
00002  *
00003  *   Copyright NumFOCUS
00004  *
00005  *   Licensed under the Apache License, Version 2.0 (the "License");
00006  *   you may not use this file except in compliance with the License.
00007  *   You may obtain a copy of the License at
00008  *
00009  *       http://www.apache.org/licenses/LICENSE-2.0.txt
00010  *
00011  *   Unless required by applicable law or agreed to in writing, software
00012  *   distributed under the License is distributed on an "AS IS" BASIS,
00013  *   WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied.
00014  *   See the License for the specific language governing permissions and
00015  *   limitations under the License.
00016  *
00017  *=====*/
00018 #ifndef GDCMQUERYSERIES_H
00019 #define GDCMQUERYSERIES_H
00020
00021 #include "gdcmQueryBase.h"
00022
00023 namespace gdcm
00024 {
00029 class GDCM_EXPORT QuerySeries : public QueryBase
00030 {
00031 public:
00032     std::vector<Tag> GetRequiredTags(const ERootType& inRootType) const override;
00033     std::vector<Tag> GetUniqueTags(const ERootType& inRootType) const override;
00034     std::vector<Tag> GetOptionalTags(const ERootType& inRootType) const override;
00035     std::vector<Tag> GetHierachicalSearchTags(const ERootType& inRootType) const override;
00036
00037     const char * GetName() const override;
00038     DataElement GetQueryLevel() const override;
00039 };
00040
00041 } // end namespace gdcm
00042
00043 #endif //GDCMQUERYSERIES_H
```

11.563 gdcmQueryStudy.h File Reference

```
#include "gdcmQueryBase.h"
```

Include dependency graph for gdcmQueryStudy.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::QueryStudy](#)
QueryStudy.h.

Namespaces

- namespace [gdcm](#)

11.564 gdcmQueryStudy.h

[Go to the documentation of this file.](#)

```


00001 /*=====
00002  *
00003  *   Copyright NumFOCUS
00004  *
00005  *   Licensed under the Apache License, Version 2.0 (the "License");
00006  *   you may not use this file except in compliance with the License.
00007  *   You may obtain a copy of the License at
00008  *
00009  *       http://www.apache.org/licenses/LICENSE-2.0.txt
00010  *
00011  *   Unless required by applicable law or agreed to in writing, software
00012  *   distributed under the License is distributed on an "AS IS" BASIS,
00013  *   WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied.
00014  *   See the License for the specific language governing permissions and
00015  *   limitations under the License.
00016  *
00017  *=====*/
00018 #ifndef GDCMQUERYSTUDY_H
00019 #define GDCMQUERYSTUDY_H
00020
00021 #include "gdcmQueryBase.h"
00022
00023 namespace gdcm
00024 {
00025     class GDCM_EXPORT QueryStudy : public QueryBase
00026     {
00027     public:
00028         std::vector<Tag> GetRequiredTags(const ERootType& inRootType) const override;
00029         std::vector<Tag> GetUniqueTags(const ERootType& inRootType) const override;
00030         std::vector<Tag> GetOptionalTags(const ERootType& inRootType) const override;
00031         std::vector<Tag> GetHierarchicalSearchTags(const ERootType& inRootType) const override;
00032
00033         const char *GetName() const override;
00034         DataElement GetQueryLevel() const override;
00035     };
00036 }
00037
00038 // end namespace gdcm
00039
00040 #endif //GDCMQUERYSTUDY_H

```

11.565 gdcmRoleSelectionSub.h File Reference

```
#include "gdcmTypes.h"
```

Include dependency graph for gdcmRoleSelectionSub.h:



Classes

- class `gdcm::network::RoleSelectionSub`
RoleSelectionSub.

Namespaces

- namespace `gdcm`
- namespace `gdcm::network`

11.566 gdcmRoleSelectionSub.h

[Go to the documentation of this file.](#)

```


00001  /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013  =====*/
00014  #ifndef GDCMROLESELECTIONSUB_H
00015  #define GDCMROLESELECTIONSUB_H
00016
00017  #include "gdcmTypes.h"
00018
00019  namespace gdcm
00020  {
00021
00022  namespace network
00023  {
00024
00025  class RoleSelectionSub
00026  {
00027  public:
00028    RoleSelectionSub();
00029    std::istream &Read(std::istream &is);
00030    const std::ostream &Write(std::ostream &os) const;
00031
00032    size_t Size() const;
00033    void Print(std::ostream &os) const;
00034
00035    void SetTuple(const char *uid, uint8_t scurole, uint8_t scprole);
00036
00037  private:
00038    static const uint8_t ItemType;
00039    static const uint8_t Reserved2;
00040    uint16_t ItemLength;
00041    uint16_t UIDLength;
00042    std::string /*SOP-class-uid*/ Name; // UID
00043    uint8_t SCURole;
00044    uint8_t SCPRole;
00045  };
00046
00047  } // end namespace network
00048
00049  } // end namespace gdcm
00050
00051  #endif // GDCMROLESELECTIONSUB_H

```


11.567 gdcmServiceClassApplicationInformation.h File Reference

```
#include "gdcmTypes.h"
```

Include dependency graph for gdcmServiceClassApplicationInformation.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::network::ServiceClassApplicationInformation](#)

Namespaces

- namespace [gdcm](#)
- namespace [gdcm::network](#)

11.568 gdcmServiceClassApplicationInformation.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMSERVICECLASSAPPLICATIONINFORMATION_H
00015 #define GDCMSERVICECLASSAPPLICATIONINFORMATION_H
00016
00017 #include "gdcmTypes.h"
00018
00019 namespace gdcm
00020 {
00021
00022 namespace network
00023 {
00024
00030 class ServiceClassApplicationInformation
00031 {
00032 public:
00033   ServiceClassApplicationInformation();
00034   std::istream &Read(std::istream &is);
00035   const std::ostream &Write(std::ostream &os) const;
00036
00037   size_t Size() const;
00038   void SetTuple(uint8_t levelofsupport, uint8_t levelofdigitalsig,
00039     uint8_t elementcoercion);
00040
00041   void Print(std::ostream &os) const;
00042 private:
00043   uint8_t InternalArray[6];
00044 };
00045
00046 } // end namespace network
00047
00048 } // end namespace gdcm
00049
00050 #endif //GDCMSERVICECLASSAPPLICATIONINFORMATION_H

```

11.569 gdcmServiceClassUser.h File Reference

```

#include "gdcmSubject.h"
#include "gdcmPresentationContext.h"
#include "gdcmFile.h"
#include "gdcmNetworkStateID.h"

```

- class `gdcm::ServiceClassUser`
ServiceClassUser.

- namespace `gdcm`
- namespace `gdcm::network`

[Go to the documentation of this file.](#)

Generated by Doxygen

```


00027 class BaseRootQuery;
00028 namespace network{
00029 class ULEvent;
00030 class ULConnection;
00031 class ULConnectionCallback;
00032 }
00036 class GDCM_EXPORT ServiceClassUser : public Subject
00037 {
00038 public:
00042 ServiceClassUser();
00043 ~ServiceClassUser() override;
00044 ServiceClassUser(const ServiceClassUser&) = delete;
00045 void operator=(const ServiceClassUser &) = delete;
00046
00048 void SetHostname( const char *hostname );
00049
00051 void SetPort( uint16_t port );
00052
00054 void SetPortSCP( uint16_t portscp );
00055
00057 void SetAETitle(const char *aetitle);
00058 const char *GetAETitle() const;
00059
00061 void SetCalledAETitle(const char *aetitle);
00062 const char *GetCalledAETitle() const;
00063
00065 void SetTimeout(double t);
00066 double GetTimeout() const;
00067
00071 bool InitializeConnection();
00072
00074 void SetPresentationContexts(std::vector<PresentationContext> const & pcs);
00075
00077 bool IsPresentationContextAccepted(const PresentationContext& pc) const;
00078
00080 bool StartAssociation();
00081
00083 bool StopAssociation();
00084
00086 bool SendEcho();
00087
00089 bool SendStore(const char *filename);
00092 bool SendStore(File const &file);
00094 bool SendStore(DataSet const &ds);
00095
00097 bool SendFind(const BaseRootQuery* query, std::vector<DataSet> &retDatasets);
00098
00100 bool SendMove(const BaseRootQuery* query, const char *outputdir);
00102 bool SendMove(const BaseRootQuery* query, std::vector<DataSet> &retDatasets);
00104 bool SendMove(const BaseRootQuery* query, std::vector<File> &retFile);
00105
00107 static SmartPointer<ServiceClassUser> New() { return new ServiceClassUser; }
00108
00109 private:
00110     network::EStateID RunEventLoop(network::ULEvent& inEvent,
00111         network::ULConnection* inWhichConnection,
00112         network::ULConnectionCallback* inCallback, const bool& startWaiting);
00113     network::EStateID RunMoveEventLoop(network::ULEvent& inEvent,
00114         network::ULConnectionCallback* inCallback);
00115
00116 private:
00117     ServiceClassUserInternals *Internals;
00118 };
00119
00120 } // end namespace gdcms
00121
00122 #endif // GDCMSERVICECLASSUSER_H

```

11.571 gdcmSOPClassExtendedNegociationSub.h File Reference

```
#include "gdcmServiceClassApplicationInformation.h"
```

Include dependency graph for gdcmSOPClassExtendedNegociationSub.h:



Classes

- class [gdcm::network::SOPClassExtendedNegociationSub](#)
SOPClassExtendedNegociationSub.

Namespaces

- namespace [gdcm](#)
- namespace [gdcm::network](#)

11.572 gdcmSOPClassExtendedNegociationSub.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013   =====*/
00014 #ifndef GDCMSOPCLASSEXTENDEDNEGOCIATIONSUB_H

```

```

00015 #define GDCMSOPCLASSEXTENDEDNEGOCIATIONSUB_H
00016
00017 #include "gdcmServiceClassApplicationInformation.h"
00018
00019 namespace gdcm
00020 {
00021     namespace network
00022     {
00023
00031         class SOPClassExtendedNegociationSub
00032         {
00033         public:
00034             SOPClassExtendedNegociationSub();
00035             std::istream &Read(std::istream &is);
00036             const std::ostream &Write(std::ostream &os) const;
00037
00038             size_t Size() const;
00039             void Print(std::ostream &os) const;
00040
00041             void SetTuple(const char *uid, uint8_t levelofsupport = 3,
00042                 uint8_t levelofdigitalsig = 0,
00043                 uint8_t elementcoercion = 2);
00044
00045         private:
00046             static const uint8_t ItemType;
00047             static const uint8_t Reserved2;
00048             uint16_t ItemLength;
00049             uint16_t UIDLength;
00050             std::string /*SOP-class-uid*/ Name; // UID
00051             ServiceClassApplicationInformation SCAI;
00052         };
00053
00054     } // end namespace network
00055
00056 } // end namespace gdcm
00057
00058 #endif // GDCMSOPCLASSEXTENDEDNEGOCIATIONSUB_H

```


11.573 gdcmTransferSyntaxSub.h File Reference

```


#include "gdcmTypes.h"
#include "gdcmTransferSyntax.h"
#include "gdcmUIDs.h"

```


Include dependency graph for gdcmTransferSyntaxSub.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::network::TransferSyntaxSub](#)
TransferSyntaxSub.

Namespaces

- namespace [gdcm](#)
- namespace [gdcm::network](#)

11.574 gdcmTransferSyntaxSub.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMTRANSFERSYNTAXSUB_H
00015 #define GDCMTRANSFERSYNTAXSUB_H
00016
00017 #include "gdcmTypes.h"
00018 #include "gdcmTransferSyntax.h"
00019 #include "gdcmUIDs.h"
00020
00021 namespace gdcm
00022 {
00023
00024   namespace network
00025   {
00026
00027     class TransferSyntaxSub
00028     {
00029     public:
00030       TransferSyntaxSub();
00031       void SetName( const char *name );
00032       const char *GetName() const { return Name.C_str(); }
00033
00034       // accept a UIDs::TSType also...
00035       void SetNameFromUID( UIDs::TSType tsname );
00036
00037       std::istream &Read(std::istream &is);
00038       const std::ostream &Write(std::ostream &os) const;
00039       size_t Size() const;
00040       void Print(std::ostream &os) const;
00041
00042       bool operator==(const TransferSyntaxSub & ts) const
00043       {
00044         return Name == ts.Name;
00045       }
00046
00047     private:
00048       void UpdateName( const char *name );
00049       static const uint8_t ItemType;
00050       static const uint8_t Reserved2;
00051       uint16_t ItemLength; // len of
00052       std::string /*TransferSyntaxSub*/ Name; // UID
00053     };
00054
00055   } // end namespace network
00056
00057 } // end namespace gdcm
00058
00059 #endif //GDCMTRANSFERSYNTAXSUB_H

```


11.575 gdcmULAction.h File Reference

```


#include "gdcmNetworkStateID.h"
#include "gdcmULEvent.h"

```

```
#include "gdcmULConnection.h"
Include dependency graph for gdcmULAction.h:
```



This graph shows which files directly or indirectly include this file:



Classes

- class `gdcm::network::ULAction`
ULAction.

Namespaces

- namespace `gdcm`
- namespace `gdcm::network`

11.576 gdcmULAction.h

[Go to the documentation of this file.](#)

```
00001 /*=====
00002  *
00003  * Copyright NumFOCUS
00004  *
00005  * Licensed under the Apache License, Version 2.0 (the "License");
00006  * you may not use this file except in compliance with the License.
00007  * You may obtain a copy of the License at
00008  *
00009  * http://www.apache.org/licenses/LICENSE-2.0.txt
00010  *
```


- class [gdcm::network::ULActionAA4](#)
- class [gdcm::network::ULActionAA5](#)
- class [gdcm::network::ULActionAA6](#)
- class [gdcm::network::ULActionAA7](#)
- class [gdcm::network::ULActionAA8](#)

Namespaces

- namespace [gdcm](#)
- namespace [gdcm::network](#)

11.578 gdcmULActionAA.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002  *
00003  * Copyright NumFOCUS
00004  *
00005  * Licensed under the Apache License, Version 2.0 (the "License");
00006  * you may not use this file except in compliance with the License.
00007  * You may obtain a copy of the License at
00008  *
00009  *      http://www.apache.org/licenses/LICENSE-2.0.txt
00010  *
00011  * Unless required by applicable law or agreed to in writing, software
00012  * distributed under the License is distributed on an "AS IS" BASIS,
00013  * WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied.
00014  * See the License for the specific language governing permissions and
00015  * limitations under the License.
00016  *
00017  *=====*/
00018 #ifndef GDCMULACTIONAA_H
00019 #define GDCMULACTIONAA_H
00020
00021 #include "gdcmULAction.h"
00022
00023 namespace gdcm {
00024     namespace network {
00025
00026         //Send A-ABORT PDU (service-user source) and start (or restart if already started) ARTIM timer
00027         //Next State: eStal3AwaitingClose
00028         class ULActionAA1 : public ULAction {
00029         public:
00030             EStateID PerformAction(Subject *s, ULEvent& inEvent, ULConnection& inConnection,
00031                 bool& outWaitingForEvent, EEventID& outRaisedEvent) override;
00032         };
00033
00034         //Stop ARTIM timer if running. Close transport connection.
00035         //Next State: eStalIdle
00036         class ULActionAA2 : public ULAction {
00037         public:
00038             EStateID PerformAction(Subject *s, ULEvent& inEvent, ULConnection& inConnection,
00039                 bool& outWaitingForEvent, EEventID& outRaisedEvent) override;
00040         };
00041
00042         //If (service-user initiated abort)
00043         //- issue A-ABORT indication and close transport connection
00044         //otherwise (service-provider initiated abort):
00045         //- issue A-P-ABORT indication and close transport connection
00046         //Next State: eStalIdle
00047         class ULActionAA3 : public ULAction {
00048         public:
00049             EStateID PerformAction(Subject *s, ULEvent& inEvent, ULConnection& inConnection,
00050                 bool& outWaitingForEvent, EEventID& outRaisedEvent) override;
00051         };
00052
00053         //Issue A-P-ABORT indication primitive

```

```


00062 //Next State: eStalIdle
00063 class UActionAA4 : public UAction {
00064 public:
00065     EStateID PerformAction(Subject *s, ULEvent& inEvent, ULConnection& inConnection,
00066         bool& outWaitingForEvent, EEventID& outRaisedEvent) override;
00067 };
00068
00069 //Stop ARTIM timer
00070 //Next State: eStalIdle
00071 class UActionAA5 : public UAction {
00072 public:
00073     EStateID PerformAction(Subject *s, ULEvent& inEvent, ULConnection& inConnection,
00074         bool& outWaitingForEvent, EEventID& outRaisedEvent) override;
00075 };
00076
00077 //Ignore PDU
00078 //Next State: eStal3AwaitingClose
00079 class UActionAA6 : public UAction {
00080 public:
00081     EStateID PerformAction(Subject *s, ULEvent& inEvent, ULConnection& inConnection,
00082         bool& outWaitingForEvent, EEventID& outRaisedEvent) override;
00083 };
00084
00085 //Send A-ABORT PDU
00086 //Next State: eStal3AwaitingClose
00087 class UActionAA7 : public UAction {
00088 public:
00089     EStateID PerformAction(Subject *s, ULEvent& inEvent, ULConnection& inConnection,
00090         bool& outWaitingForEvent, EEventID& outRaisedEvent) override;
00091 };
00092
00093 //Send A-ABORT PDU (service-provider source), issue an A-P-ABORT indication, and start ARTIM timer
00094 //Next State: eStal3AwaitingClose
00095 class UActionAA8 : public UAction {
00096 public:
00097     EStateID PerformAction(Subject *s, ULEvent& inEvent, ULConnection& inConnection,
00098         bool& outWaitingForEvent, EEventID& outRaisedEvent) override;
00099 };
00100 }
00101 }
00102
00103 #endif // GDCMULACTIONAA_H

```

11.579 gdcmlUActionAE.h File Reference

```
#include "gdcmlUAction.h"
```

Include dependency graph for gdcmlUActionAE.h:



Classes

- class [gdcml::network::UActionAE1](#)

- class [gdcm::network::ULActionAE2](#)
- class [gdcm::network::ULActionAE3](#)
- class [gdcm::network::ULActionAE4](#)
- class [gdcm::network::ULActionAE5](#)
- class [gdcm::network::ULActionAE6](#)
- class [gdcm::network::ULActionAE7](#)
- class [gdcm::network::ULActionAE8](#)

Namespaces

- namespace [gdcm](#)
- namespace [gdcm::network](#)

11.580 gdcmULActionAE.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002  *
00003  *   Copyright NumFOCUS
00004  *
00005  *   Licensed under the Apache License, Version 2.0 (the "License");
00006  *   you may not use this file except in compliance with the License.
00007  *   You may obtain a copy of the License at
00008  *
00009  *       http://www.apache.org/licenses/LICENSE-2.0.txt
00010  *
00011  *   Unless required by applicable law or agreed to in writing, software
00012  *   distributed under the License is distributed on an "AS IS" BASIS,
00013  *   WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied.
00014  *   See the License for the specific language governing permissions and
00015  *   limitations under the License.
00016  *
00017  *=====*/
00018 #ifndef GDCMULACTIONAE_H
00019 #define GDCMULACTIONAE_H
00020
00021 #include "gdcmULAction.h"
00022
00031
00032 namespace gdcm {
00033     namespace network {
00034
00035         //Issue TRANSPORT CONNECT request primitive to local transport service.
00036         class ULActionAE1 : public ULAction {
00037         public:
00038             EStateID PerformAction(Subject *s, ULEvent& inEvent, ULConnection& inConnection,
00039                 bool& outWaitingForEvent, EEventID& outRaisedEvent) override;
00040         };
00041
00042         //Send A-ASSOCIATE-RQ-PDU
00043         //Next State: eSta5WaitRemoteAssoc
00044         class ULActionAE2 : public ULAction {
00045         public:
00046             EStateID PerformAction(Subject *s, ULEvent& inEvent, ULConnection& inConnection,
00047                 bool& outWaitingForEvent, EEventID& outRaisedEvent) override;
00048         };
00049
00050         //Issue A-ASSOCIATE confirmation (accept) primitive
00051         //Next State: eSta6TransferReady
00052         class ULActionAE3 : public ULAction {
00053         public:
00054             EStateID PerformAction(Subject *s, ULEvent& inEvent, ULConnection& inConnection,
00055                 bool& outWaitingForEvent, EEventID& outRaisedEvent) override;
00056         };
00057
00058         //Issue A-ASSOCIATE confirmation (reject) primitive and close transport connection

```

```


00059 //Next State: eStaIdle
00060 class ULAActionAE4 : public ULAAction {
00061 public:
00062     EStateID PerformAction(Subject *s, ULEvent& inEvent, ULConnection& inConnection,
00063         bool& outWaitingForEvent, EEventID& outRaisedEvent) override;
00064 };
00065
00066 //Issue Transport connection response primitive, start ARTIM timer
00067 //Next State: eSta2Open
00068 class ULAActionAE5 : public ULAAction {
00069 public:
00070     EStateID PerformAction(Subject *s, ULEvent& inEvent, ULConnection& inConnection,
00071         bool& outWaitingForEvent, EEventID& outRaisedEvent) override;
00072 };
00073
00074 //Stop ARTIM timer and if A-ASSOCIATE-RQ acceptable by service-provider:
00075 // issue A-ASSOCIATE indication primitive
00076 //Next state: eSta3WaitLocalAssoc
00077 //otherwise:
00078 // issue A-ASSOCIATE-RJ-PDU and start ARTIM timer
00079 //Next state: eSta3AwaitingClose
00080 class ULAActionAE6 : public ULAAction {
00081 public:
00082     EStateID PerformAction(Subject *s, ULEvent& inEvent, ULConnection& inConnection,
00083         bool& outWaitingForEvent, EEventID& outRaisedEvent) override;
00084 };
00085
00086 //Send A-ASSOCIATE-AC PDU
00087 //Next State: eSta6TransferReady
00088 class ULAActionAE7 : public ULAAction {
00089 public:
00090     EStateID PerformAction(Subject *s, ULEvent& inEvent, ULConnection& inConnection,
00091         bool& outWaitingForEvent, EEventID& outRaisedEvent) override;
00092 };
00093
00094 //Send A-ASSOCIATE-RJ PDU and start ARTIM timer
00095 //Next State: eSta13AwaitingClose
00096 class ULAActionAE8 : public ULAAction {
00097 public:
00098     EStateID PerformAction(Subject *s, ULEvent& inEvent, ULConnection& inConnection,
00099         bool& outWaitingForEvent, EEventID& outRaisedEvent) override;
00100 };
00101 }
00102 }
00103 #endif // GDCMULACTIONAE_H

```

11.581 gdcmlActionAR.h File Reference

#include "gdcmlAction.h"

Include dependency graph for gdcmlActionAR.h:



Classes

- class [gdcml::network::ULActionAR1](#)

- class [gdcm::network::ULActionAR10](#)
- class [gdcm::network::ULActionAR2](#)
- class [gdcm::network::ULActionAR3](#)
- class [gdcm::network::ULActionAR4](#)
- class [gdcm::network::ULActionAR5](#)
- class [gdcm::network::ULActionAR6](#)
- class [gdcm::network::ULActionAR7](#)
- class [gdcm::network::ULActionAR8](#)
- class [gdcm::network::ULActionAR9](#)

Namespaces

- namespace [gdcm](#)
- namespace [gdcm::network](#)

11.582 gdcmULActionAR.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002  *
00003  *   Copyright NumFOCUS
00004  *
00005  *   Licensed under the Apache License, Version 2.0 (the "License");
00006  *   you may not use this file except in compliance with the License.
00007  *   You may obtain a copy of the License at
00008  *
00009  *       http://www.apache.org/licenses/LICENSE-2.0.txt
00010  *
00011  *   Unless required by applicable law or agreed to in writing, software
00012  *   distributed under the License is distributed on an "AS IS" BASIS,
00013  *   WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied.
00014  *   See the License for the specific language governing permissions and
00015  *   limitations under the License.
00016  *
00017  *=====*/
00018 #ifndef GDCMULACTIONAR_H
00019 #define GDCMULACTIONAR_H
00020
00021 #include "gdcmULAction.h"
00022
00030
00031 namespace gdcm {
00032     namespace network {
00033
00034         //Send A-RELEASE-RQ-PDU
00035         //Next State: eSta7WaitRelease
00036         class ULActionAR1 : public ULAction {
00037         public:
00038             EStateID PerformAction(Subject *s, ULEvent& inEvent, ULConnection& inConnection,
00039                                     bool& outWaitingForEvent, EEventID& outRaisedEvent) override;
00040         };
00041
00042         //Issue A-RELEASE indication primitive
00043         //Next State: eSta8WaitLocalRelease
00044         class ULActionAR2 : public ULAction {
00045         public:
00046             EStateID PerformAction(Subject *s, ULEvent& inEvent, ULConnection& inConnection,
00047                                     bool& outWaitingForEvent, EEventID& outRaisedEvent) override;
00048         };
00049
00050         //Issue A-RELEASE confirmation primitive, and close transport connection
00051         //Next State: eStaIdle
00052         class ULActionAR3 : public ULAction {
00053         public:
00054             EStateID PerformAction(Subject *s, ULEvent& inEvent, ULConnection& inConnection,

```

```


00055         bool& outWaitingForEvent, EEventID& outRaisedEvent) override;
00056     };
00057
00058     //Issue A-RELEASE-RP PDU and start ARTIM timer
00059     //Next State: eSta13AwaitingClose
00060     class UActionAR4 : public UAction {
00061     public:
00062         EStateID PerformAction(Subject *s, ULEvent& inEvent, ULConnection& inConnection,
00063             bool& outWaitingForEvent, EEventID& outRaisedEvent) override;
00064     };
00065
00066     //Stop ARTIM timer
00067     //Next State: eStaIdle
00068     class UActionAR5 : public UAction {
00069     public:
00070         EStateID PerformAction(Subject *s, ULEvent& inEvent, ULConnection& inConnection,
00071             bool& outWaitingForEvent, EEventID& outRaisedEvent) override;
00072     };
00073
00074     //Issue P-Data indication
00075     //Next State: eSta7WaitRelease
00076     class UActionAR6 : public UAction {
00077     public:
00078         EStateID PerformAction(Subject *s, ULEvent& inEvent, ULConnection& inConnection,
00079             bool& outWaitingForEvent, EEventID& outRaisedEvent) override;
00080     };
00081
00082     //Issue P-DATA-TF PDU
00083     //Next State: eSta8WaitLocalRelease
00084     class UActionAR7 : public UAction {
00085     public:
00086         EStateID PerformAction(Subject *s, ULEvent& inEvent, ULConnection& inConnection,
00087             bool& outWaitingForEvent, EEventID& outRaisedEvent) override;
00088     };
00089
00090     //Issue A-RELEASE indication (release collision):
00091     //- If association-requestor, next state is eSta9ReleaseCollisionRqLocal
00092     //- if not, next state is eSta10ReleaseCollisionAc
00093     class UActionAR8 : public UAction {
00094     public:
00095         EStateID PerformAction(Subject *s, ULEvent& inEvent, ULConnection& inConnection,
00096             bool& outWaitingForEvent, EEventID& outRaisedEvent) override;
00097     };
00098
00099     //Send A-RELEASE-RP PDU
00100     //Next State: eSta11ReleaseCollisionRq
00101     class UActionAR9 : public UAction {
00102     public:
00103         EStateID PerformAction(Subject *s, ULEvent& inEvent, ULConnection& inConnection,
00104             bool& outWaitingForEvent, EEventID& outRaisedEvent) override;
00105     };
00106
00107     //Issue A-RELEASE confirmation primitive
00108     //Next State: eSta12ReleaseCollisionAcLocal
00109     class UActionAR10 : public UAction {
00110     public:
00111         EStateID PerformAction(Subject *s, ULEvent& inEvent, ULConnection& inConnection,
00112             bool& outWaitingForEvent, EEventID& outRaisedEvent) override;
00113     };
00114 }
00115 }
00116 #endif // GDCMULACTIONAR_H

```

11.583 gdcmULActionDT.h File Reference

```
#include "gdcmULAction.h"
```

Include dependency graph for gdcmULActionDT.h:



Classes

- class `gdcm::network::ULActionDT1`
- class `gdcm::network::ULActionDT2`

Namespaces

- namespace `gdcm`
- namespace `gdcm::network`

11.584 gdcmULActionDT.h

[Go to the documentation of this file.](#)

```
00001 /*=====
00002  *
00003  *   Copyright NumFOCUS
00004  *
00005  *   Licensed under the Apache License, Version 2.0 (the "License");
00006  *   you may not use this file except in compliance with the License.
00007  *   You may obtain a copy of the License at
00008  *
00009  *       http://www.apache.org/licenses/LICENSE-2.0.txt
00010  *
00011  *   Unless required by applicable law or agreed to in writing, software
00012  *   distributed under the License is distributed on an "AS IS" BASIS,
00013  *   WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied.
00014  *   See the License for the specific language governing permissions and
00015  *   limitations under the License.
00016  *
00017  *=====*/
00018 #ifndef GDCMULACTIONDT_H
00019 #define GDCMULACTIONDT_H
00020
00021 #include "gdcmULAction.h"
00022
00030
00031 namespace gdcm {
00032     namespace network {
```


11.586 gdcmULBasicCallback.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002  *
00003  *   Copyright NumFOCUS
00004  *
00005  *   Licensed under the Apache License, Version 2.0 (the "License");
00006  *   you may not use this file except in compliance with the License.
00007  *   You may obtain a copy of the License at
00008  *
00009  *       http://www.apache.org/licenses/LICENSE-2.0.txt
00010  *
00011  *   Unless required by applicable law or agreed to in writing, software
00012  *   distributed under the License is distributed on an "AS IS" BASIS,
00013  *   WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied.
00014  *   See the License for the specific language governing permissions and
00015  *   limitations under the License.
00016  *
00017  *=====*/
00018 #ifndef GDCMULCONNECTIONBASICCALLBACK_H
00019 #define GDCMULCONNECTIONBASICCALLBACK_H
00020
00021 #include "gdcmULConnectionCallback.h"
00022 #include "gdcmDataSet.h"
00023 #include <vector>
00024
00025 namespace gdcm
00026 {
00027     namespace network
00028     {
00029         class GDCM_EXPORT ULBasicCallback : public ULConnectionCallback
00030         {
00031         {
00032             std::vector<DataSet> mDataSets;
00033             std::vector<DataSet> mResponses;
00034         public:
00035             ULBasicCallback() = default;
00036             ~ULBasicCallback() override = default; //empty, for later inheritance
00037
00038             void HandleDataSet(const DataSet& inDataSet) override;
00039             void HandleResponse(const DataSet& inDataSet) override;
00040
00041             std::vector<DataSet> const & GetDataSets() const;
00042             std::vector<DataSet> const & GetResponses() const;
00043         };
00044     } // end namespace network
00045 } // end namespace gdcm
00046
00047 #endif // GDCMULCONNECTIONBASICCALLBACK_H

```


11.587 gdcmULConnection.h File Reference

```


#include "gdcmNetworkStateID.h"
#include "gdcmARTIMTimer.h"
#include "gdcmULConnectionInfo.h"
#include "gdcmPresentationContextRQ.h"
#include "gdcmDataElement.h"
#include "gdcmPresentationContextAC.h"
#include "gdcmPresentationContext.h"

```

Include dependency graph for `gdcmlULConnection.h`:



This graph shows which files directly or indirectly include this file:



Classes

- class `gdcml::network::ULConnection`
ULConnection.

Namespaces

- namespace `gdcml`
- namespace `gdcml::network`

11.588 gdcmlULConnection.h

[Go to the documentation of this file.](#)

```

00001  /*=====
00002  *
00003  *   Copyright NumFOCUS
00004  *
00005  *   Licensed under the Apache License, Version 2.0 (the "License");
00006  *   you may not use this file except in compliance with the License.
00007  *   You may obtain a copy of the License at
00008  *
00009  *       http://www.apache.org/licenses/LICENSE-2.0.txt
00010  *
00011  *   Unless required by applicable law or agreed to in writing, software
00012  *   distributed under the License is distributed on an "AS IS" BASIS,
00013  *   WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied.
00014  *   See the License for the specific language governing permissions and

```

```

00015  * limitations under the License.
00016  *
00017  *=====*/
00018 #ifndef GDCMULCONNECTION_H
00019 #define GDCMULCONNECTION_H
00020
00021 #include "gdcmNetworkStateID.h"
00022 #include "gdcmARTIMTimer.h"
00023 #include "gdcmULConnectionInfo.h"
00024 #include "gdcmPresentationContextRQ.h"
00025 #include "gdcmDataElement.h"
00026 #include "gdcmPresentationContextAC.h"
00027 #include "gdcmPresentationContext.h"
00028
00029 class iosocket;
00030 class echo;
00031 namespace gdcm{
00032     namespace network{
00033
00057 class GDCM_EXPORT ULConnection
00058 {
00059     ULConnectionInfo mInfo;
00060     //this is a dirty dirty hack
00061     //but to establish an outgoing connection (scu), we need the echo service
00062     //to establish incoming, we just need a port and localhost, so an iosocket works while an
00063     //echo would fail (probably because one already exists)
00064     echo* mEcho;
00065     iosocket* mSocket; //of the three protocols offered by socket+--- echo, smtp, and ftp--
00066     //echo most closely matches what the DICOM standard describes as a network connection
00067     ARTIMTimer mTimer;
00068
00069     EStateID mCurrentState;
00070
00071     std::vector<PresentationContextRQ> mPresentationContexts;
00072     //this is our list of presentation contexts of what we can send
00073     uint32_t mMaxPDUSize;
00074
00075     std::vector<PresentationContextAC> mAcceptedPresentationContexts; //these come back from the server
00076     //and tell us what can be sent over this connection
00077
00078     TransferSyntaxSub cstorets;
00079
00080     friend class ULActionAE6;
00081     void SetCStoreTransferSyntax( TransferSyntaxSub const & ts );
00082     friend class ULConnectionManager;
00083     TransferSyntaxSub const & GetCStoreTransferSyntax( ) const;
00084 public:
00085
00086     ULConnection(const ULConnectionInfo& inUserInformation);
00087     //destructors are virtual to prevent memory leaks by inherited classes
00088     virtual ~ULConnection();
00089
00090     EStateID GetState() const;
00091     void SetState(const EStateID& inState); //must be able to update state...
00092
00093     //echo* GetProtocol();
00094     std::ostream* GetProtocol();
00095     void StopProtocol();
00096
00097     ARTIMTimer& GetTimer();
00098
00099     const ULConnectionInfo &GetConnectionInfo() const;
00100
00101     //when the connection is first associated, the connection is told
00102     //the max packet/PDU size and the way in which to present data
00103     //(presentation contexts, etc). Store that here.
00104     void SetMaxPDUSize(uint32_t inSize);
00105     uint32_t GetMaxPDUSize() const;
00106
00107     const PresentationContextAC *GetPresentationContextACByID(uint8_t id) const;
00108     const PresentationContextRQ *GetPresentationContextRQByID(uint8_t id) const;
00109
00110     uint8_t GetPresentationContextIDFromPresentationContext(PresentationContextRQ const & pc) const;
00111
00112     std::vector<PresentationContextRQ> const & GetPresentationContexts() const;
00113     void SetPresentationContexts(const std::vector<PresentationContextRQ>& inContexts);
00114
00115     void SetPresentationContexts(const std::vector<PresentationContext>& inContexts);
00116
00117     //given a particular data element, presumably the SOP class,
00118     //find the presentation context for that SOP

```

```


00120      //NOT YET IMPLEMENTED
00121      PresentationContextRQ FindContext(const DataElement& de) const;
00122
00123      std::vector<PresentationContextAC> const & GetAcceptedPresentationContexts() const;
00124      std::vector<PresentationContextAC> & GetAcceptedPresentationContexts();
00125      void AddAcceptedPresentationContext(const PresentationContextAC& inPC);
00126
00127      bool InitializeConnection();
00128
00129      bool InitializeIncomingConnection();
00130
00131      ULConnection(const ULConnection&) = delete;
00132      void operator=(const ULConnection&) = delete;
00133  };
00134  };
00135  };
00136  };
00137  };
00138  };
00139  #endif // ULCONNECTION_H

```


11.589 gdcmULConnectionCallback.h File Reference

#include "gdcmTypes.h"

Include dependency graph for gdcmULConnectionCallback.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::network::ULConnectionCallback](#)

Namespaces

- namespace [gdcm](#)
- namespace [gdcm::network](#)

11.590 gdcmULConnectionCallback.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002  *
00003  *   Copyright NumFOCUS
00004  *
00005  *   Licensed under the Apache License, Version 2.0 (the "License");
00006  *   you may not use this file except in compliance with the License.
00007  *   You may obtain a copy of the License at
00008  *
00009  *       http://www.apache.org/licenses/LICENSE-2.0.txt
00010  *
00011  *   Unless required by applicable law or agreed to in writing, software
00012  *   distributed under the License is distributed on an "AS IS" BASIS,
00013  *   WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied.
00014  *   See the License for the specific language governing permissions and
00015  *   limitations under the License.
00016  *
00017  *=====*/
00018 #ifndef GDCMULCONNECTIONCALLBACK_H
00019 #define GDCMULCONNECTIONCALLBACK_H
00020
00021 #include "gdcmTypes.h" //to be able to export the class
00022
00023 namespace gdcm
00024 {
00025     class DataSet;
00026     namespace network
00027     {
00028     {
00039         class GDCM_EXPORT ULConnectionCallback {
00040             bool mHandledDataSet;
00041         protected:
00042             bool mImplicit;
00043             //inherited callbacks MUST call this function for the cmove loop to work properly
00044             void DataSetHandled() { mHandledDataSet = true; }
00045         public:
00046             ULConnectionCallback():mHandledDataSet(false),mImplicit(true){}
00047             virtual ~ULConnectionCallback() = default; //placeholder for inherited objects
00048             virtual void HandleDataSet(const DataSet& inDataSet) = 0;
00049             virtual void HandleResponse(const DataSet& inDataSet) = 0;
00050
00051             bool DataSetHandles() const { return mHandledDataSet; }
00052             void ResetHandledDataSet() { mHandledDataSet = false; }
00053
00054             void SetImplicitFlag( const bool imp ) { mImplicit = imp; }
00055         };
00056     }
00057 }
00058 #endif //GDCMULCONNECTIONCALLBACK_H

```


11.591 gdcmULConnectionInfo.h File Reference

```


#include "gdcmUserInformation.h"
#include <string>

```

Include dependency graph for `gdcmULConnectionInfo.h`:



This graph shows which files directly or indirectly include this file:



Classes

- class `gdcm::network::ULConnectionInfo`
ULConnectionInfo.

Namespaces

- namespace `gdcm`
- namespace `gdcm::network`

11.592 gdcmULConnectionInfo.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002  *
00003  *   Copyright NumFOCUS
00004  *
00005  *   Licensed under the Apache License, Version 2.0 (the "License");
00006  *   you may not use this file except in compliance with the License.
00007  *   You may obtain a copy of the License at
00008  *
00009  *       http://www.apache.org/licenses/LICENSE-2.0.txt
00010  *
00011  *   Unless required by applicable law or agreed to in writing, software
00012  *   distributed under the License is distributed on an "AS IS" BASIS,
00013  *   WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied.
00014  *   See the License for the specific language governing permissions and
00015  *   limitations under the License.
00016  *
00017  *=====*/
00018 #ifndef GDCMULCONNECTIONINFO_H
00019 #define GDCMULCONNECTIONINFO_H
00020
00021 #include "gdcmUserInformation.h"
00022 #include <string>
00023
00024 namespace gdcm{
00025     namespace network {
00038     class ULConnectionInfo {
00039     public:
00040         UserInformation mUserInformation;
00041
00042         std::string mCalledAETitle;
00043         std::string mCallingAETitle;
00044
00045         unsigned long mCalledIPAddress;
00046         int mCalledIPPort;
00047         std::string mCalledComputerName; //either the IP or the name has to be filled in
00048
00049         unsigned long mMaxPDULength;
00050     public:
00051         ULConnectionInfo();
00052
00053         //it is possible to misinitialize this object, so
00054         //have it return false if something breaks (ie, given AEs are bigger than 16 characters,
00055         //no name or IP address).
00056         bool Initialize(UserInformation const &inUserInformation,
00057             const char *inCalledAETitle, const char *inCallingAETitle,
00058             unsigned long inCalledIPAddress, int inCalledIPPort,
00059             std::string inCalledComputerName);
00060
00061         //UserInformation GetUserInformation() const;
00062         const char* GetCalledAETitle() const;
00063         const char* GetCallingAETitle() const;
00064
00065         unsigned long GetCalledIPAddress() const;
00066         int GetCalledIPPort() const;
00067         std::string GetCalledComputerName() const;
00068
00069         //CStore needs to know the max pdu length, so the value gets initialized
00070         //when a cstore connection is established (but not for the others).
00071         void SetMaxPDULength(unsigned long inMaxPDULength);
00072         unsigned long GetMaxPDULength() const;
00073     };
00074 }
00075
00076 #endif //GDCMULCONNECTIONINFO_H

```


11.593 gdcmULConnectionManager.h File Reference

```

#include "gdcmULTransitionTable.h"
#include "gdcmULConnection.h"

```

```
#include "gdcmULConnectionInfo.h"
#include "gdcmPresentationDataValue.h"
#include "gdcmULConnectionCallback.h"
#include "gdcmSubject.h"
#include "gdcmPresentationContext.h"
Include dependency graph for gdcmULConnectionManager.h:
```



Classes

- class [gdcm::network::ULConnectionManager](#)
ULConnectionManager.

Namespaces

- namespace [gdcm](#)
- namespace [gdcm::network](#)

11.594 gdcmULConnectionManager.h

[Go to the documentation of this file.](#)

```
00001 /*=====
00002  *
00003  *   Copyright NumFOCUS
00004  *
00005  *   Licensed under the Apache License, Version 2.0 (the "License");
00006  *   you may not use this file except in compliance with the License.
00007  *   You may obtain a copy of the License at
00008  *
00009  *       http://www.apache.org/licenses/LICENSE-2.0.txt
00010  *
00011  *   Unless required by applicable law or agreed to in writing, software
00012  *   distributed under the License is distributed on an "AS IS" BASIS,
00013  *   WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied.
00014  *   See the License for the specific language governing permissions and
00015  *   limitations under the License.
00016  *
00017  *=====*/
00018 #ifndef GDCMULCONNECTIONMANAGER_H
00019 #define GDCMULCONNECTIONMANAGER_H
00020
00021 #include "gdcmULTransitionTable.h"
00022 #include "gdcmULConnection.h"
```

```

00023 #include "gdcmlULConnectionInfo.h"
00024 #include "gdcmlPresentationDataValue.h"
00025 #include "gdcmlULConnectionCallback.h"
00026 #include "gdcmlSubject.h"
00027 #include "gdcmlPresentationContext.h"
00028
00029 namespace gdcml {
00030     class File;
00031     class BaseRootQuery;
00032     class BaseQuery;
00033
00034     namespace network {
00035
00036     class GDCM_EXPORT ULConnectionManager : public Subject
00037     {
00038     protected:
00039         ULConnection* mConnection;
00040         ULConnection* mSecondaryConnection;
00041         ULTransitionTable mTransitions;
00042
00043         //no copying
00044         ULConnectionManager(const ULConnectionManager& inCM);
00045
00046         //event handler loop.
00047         //will just keep running until the current event is nonexistent.
00048         //at which point, it will return the current state of the connection
00049         //this starts by initiating an action, but can be put into a passive mode
00050         //for a cmove/cstore combination by setting startWaiting to true
00051         EStateID RunEventLoop(ULEvent& inEvent, ULConnection* inWhichConnection,
00052             ULConnectionCallback* inCallback, const bool& startWaiting);
00053
00054         //like the above, but will manage the event loop for a move event (which
00055         //is basically two simultaneous connections interwoven, one inbound and
00056         //the other outbound. Note, for instance, that cmoversp's can be sent back
00057         //during the other connection's operation.
00058         EStateID RunMoveEventLoop(ULEvent& inEvent, ULConnectionCallback* inCallback);
00059
00060     public:
00061         ULConnectionManager();
00062         ~ULConnectionManager() override;
00063
00064         // NOTE: (MM) The following two functions are difficult to use, therefore marking
00065         // them as internal for now.
00066
00067         // \internal
00068         bool EstablishConnection(const std::string& inAETitle,
00069             const std::string& inConnectAETitle,
00070             const std::string& inComputerName, long inIPAddress,
00071             uint16_t inConnectPort, double inTimeout,
00072             std::vector<PresentationContext> const & pcVector );
00073
00074         bool EstablishConnectionMove(const std::string& inAETitle,
00075             const std::string& inConnectAETitle,
00076             const std::string& inComputerName, long inIPAddress,
00077             uint16_t inConnectPort, double inTimeout,
00078             uint16_t inReturnPort,
00079             std::vector<PresentationContext> const & pcVector);
00080         // \endinternal
00081
00082         //bool ReestablishConnection(const EConnectionType& inConnectionType,
00083         // const DataSet& inDS);
00084
00085         //allows for a connection to be broken, but waits for an acknowledgement
00086         //of the breaking for a certain amount of time. Returns true if the
00087         //other side acknowledges the break
00088         bool BreakConnection(const double& inTimeout);
00089
00090         //severs the connection, if it's open, without waiting for any kind of response.
00091         //typically done if the program is going down.
00092         void BreakConnectionNow();
00093
00094         //This function will send a given piece of data
00095         //across the network connection. It will return true if the
00096         //sending worked, false otherwise.
00097         //note that sending is asynchronous; as such, there's
00098         //also a 'receive' option, but that requires a callback function.
00099         //bool SendData();
00100
00101         //send the Data PDU associated with Echo (ie, a default DataPDU)
00102         //this lets the user confirm that the connection is alive.

```

```

00122     //the user should look to cout to see the response of the echo command
00123     //returns the PresentationDataValue that was returned by the remote
00124     //host. Note that the PDV can be uninitialized, which would indicate failure.
00125     //Echo does not use a callback for results.
00126     std::vector<PresentationDataValue> SendEcho();
00127
00128     // \internal
00129     // API will change...
00130     std::vector<DataSet> SendStore(const File &file, std::istream * pStream = nullptr, std::streampos
dataSetOffset = 0 );
00131     std::vector<DataSet> SendFind(const BaseRootQuery* inRootQuery);
00132     std::vector<DataSet> SendMove(const BaseRootQuery* inRootQuery);
00133
00134     std::vector<DataSet> SendNEventReport (const BaseQuery* inQuery);
00135     std::vector<DataSet> SendNGet      (const BaseQuery* inQuery);
00136     std::vector<DataSet> SendNSet      (const BaseQuery* inQuery);
00137     std::vector<DataSet> SendNAction   (const BaseQuery* inQuery);
00138     std::vector<DataSet> SendNCreate   (const BaseQuery* inQuery);
00139     std::vector<DataSet> SendNDelete   (const BaseQuery* inQuery);
00140     // \endinternal
00141
00142     void SendStore(const File &file, ULConnectionCallback* inCallback, std::istream * pStream = nullptr
, std::streampos dataSetOffset = 0 );
00143     void SendFind(const BaseRootQuery* inRootQuery, ULConnectionCallback* inCallback);
00144     bool SendMove(const BaseRootQuery* inRootQuery, ULConnectionCallback* inCallback);
00145
00146     void SendNEventReport (const BaseQuery* inQuery, ULConnectionCallback* inCallback);
00147     void SendNGet      (const BaseQuery* inQuery, ULConnectionCallback* inCallback);
00148     void SendNSet      (const BaseQuery* inQuery, ULConnectionCallback* inCallback);
00149     void SendNAction   (const BaseQuery* inQuery, ULConnectionCallback* inCallback);
00150     void SendNCreate   (const BaseQuery* inQuery, ULConnectionCallback* inCallback);
00151     void SendNDelete   (const BaseQuery* inQuery, ULConnectionCallback* inCallback);
00152
00153 };
00154 }
00155 #endif // GDCMULCONNECTIONMANAGER_H

```


11.595 gdcmULEvent.h File Reference

```


#include "gdcmNetworkStateID.h"
#include "gdcmNetworkEvents.h"
#include "gdcmBasePDU.h"
#include <vector>

```

Include dependency graph for gdcmULEvent.h:



This graph shows which files directly or indirectly include this file:



Classes

- class `gdcml::network::UEvent`
UEvent.

Namespaces

- namespace `gdcml`
- namespace `gdcml::network`

11.596 gdcmlEvent.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002  *
00003  *   Copyright NumFOCUS
00004  *
00005  *   Licensed under the Apache License, Version 2.0 (the "License");
00006  *   you may not use this file except in compliance with the License.
00007  *   You may obtain a copy of the License at
00008  *
00009  *       http://www.apache.org/licenses/LICENSE-2.0.txt
00010  *
00011  *   Unless required by applicable law or agreed to in writing, software
00012  *   distributed under the License is distributed on an "AS IS" BASIS,
00013  *   WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied.
00014  *   See the License for the specific language governing permissions and
00015  *   limitations under the License.
00016  *
00017  *=====*/
00018 #ifndef GDCMLEVENT_H
00019 #define GDCMLEVENT_H
00020
00021 #include "gdcmlNetworkStateID.h"
00022 #include "gdcmlNetworkEvents.h"
00023 #include "gdcmlBasePDU.h"
00024 #include <vector>
00025
00026 namespace gdcml {
00027     namespace network {
00028
00037     class UEvent {
00038     public:
00039         EEventID mEvent;
00040         std::vector<BasePDU*> mBasePDU;
00041     };
00042     }
00043 }
  
```

```

00040     std::istream * m_pStream ;
00041     std::streampos m_posDataSet ;
00042     void DeletePDUVector(){
00043         std::vector<BasePDU*>::iterator baseItr;
00044         for (baseItr = mBasePDU.begin(); baseItr < mBasePDU.end(); baseItr++){
00045             if (*baseItr != nullptr){
00046                 delete *baseItr;
00047                 *baseItr = nullptr;
00048             }
00049         }
00050     }
00051
00052     public:
00053     ULEvent(const EEventID& inEventID, std::vector<BasePDU*> inBasePDU, std::istream * iStream =
nullptr, std::streampos posDataSet = 0 ){
00054         mEvent = inEventID;
00055         mBasePDU = inBasePDU;
00056         m_pStream = iStream ;
00057         m_posDataSet = posDataSet ;
00058     }
00059     ULEvent(const EEventID& inEventID, BasePDU* inBasePDU, std::istream * iStream = nullptr,
std::streampos posDataSet = 0 ){
00060         mEvent = inEventID;
00061         mBasePDU.push_back(inBasePDU);
00062         m_pStream = iStream ;
00063         m_posDataSet = posDataSet ;
00064     }
00065     ~ULEvent() {
00066         DeletePDUVector();
00067     }
00068
00069     EEventID GetEvent() const { return mEvent; }
00070     std::vector<BasePDU*> const & GetPDUs() const { return mBasePDU; }
00071     std::istream * GetIStream() const { return m_pStream; }
00072     std::streampos GetDataSetPos() const { return m_posDataSet; }
00073
00074     void SetEvent(const EEventID& inEvent) { mEvent = inEvent; }
00075     void SetPDU(std::vector<BasePDU*> const & inPDU) {
00076         DeletePDUVector();
00077         mBasePDU = inPDU;
00078     }
00079 };
00080 }
00081 }
00082
00083 #endif //GDCMULEVENT_H

```

11.597 gdcmULTransitionTable.h File Reference


```
#include "gdcmNetworkStateID.h"
```

```
#include "gdcmNetworkEvents.h"
```


```
#include "gdcmULAction.h"
```

```
#include <cstdlib>
```

Include dependency graph for gdcmULTransitionTable.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::network::TableRow](#)
- struct [gdcm::network::Transition](#)
- class [gdcm::network::ULTransitionTable](#)

[ULTransitionTable](#) The transition table of all the ULEvents, new ULActions, and ULStates.

Namespaces

- namespace [gdcm](#)
- namespace [gdcm::network](#)

11.598 gdcmULTransitionTable.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002  *
00003  *   Copyright NumFOCUS
00004  *
00005  *   Licensed under the Apache License, Version 2.0 (the "License");
00006  *   you may not use this file except in compliance with the License.
00007  *   You may obtain a copy of the License at
00008  *
00009  *       http://www.apache.org/licenses/LICENSE-2.0.txt
00010  *
00011  *   Unless required by applicable law or agreed to in writing, software
00012  *   distributed under the License is distributed on an "AS IS" BASIS,
00013  *   WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied.
00014  *   See the License for the specific language governing permissions and
00015  *   limitations under the License.
00016  *
00017  *=====*/
00018 #ifndef GDCMULTRANSITIONTABLE_H
00019 #define GDCMULTRANSITIONTABLE_H
00020
00021 #include "gdcmNetworkStateID.h"
00022 #include "gdcmNetworkEvents.h"
00023 #include "gdcmULAction.h"
00024
00025 #include <stdlib.h> // NULL
  
```

```


00026
00027 namespace gdc {
00028     class Subject;
00029     namespace network {
00030     class ULConnection;
00031     class ULAction;
00032     class ULEvent;
00033
00034         //The transition dictates the action that should be taken from the start state to the end state
00035     struct Transition {
00036         int mEnd;
00037         ULAction* mAction;
00038         Transition() {
00039             mEnd = eStaDoesNotExist;
00040             mAction = nullptr;
00041         }
00042         ~Transition() {
00043             if (mAction != nullptr) {
00044                 delete mAction;
00045                 mAction = nullptr;
00046             }
00047         }
00048         Transition(int inEndState, ULAction* inAction) {
00049             mEnd = inEndState;
00050             mAction = inAction;
00051         }
00052         static Transition* MakeNew(int inEndState, ULAction* inAction) {
00053             return new Transition(inEndState, inAction);
00054         }
00055     };
00056
00057     //used to define a row in table 9-10 of 3.8 2009
00058     //the transition table is events, then state,
00059     //then the transition itself (which has the event
00060     //and start state implied by their starting locations)
00061     //don't need to store the event; that's implicitly defined in the Table itself by location
00062     class TableRow {
00063     public:
00064         TableRow() {
00065             for(int stateIndex = 0; stateIndex < cMaxStateID; ++stateIndex)
00066             {
00067                 transitions[stateIndex] = nullptr;
00068             }
00069         }
00070         ~TableRow() {
00071             for(int stateIndex = 0; stateIndex < cMaxStateID; ++stateIndex)
00072             {
00073                 Transition *t = transitions[stateIndex];
00074                 delete t;
00075             }
00076         }
00077         Transition *transitions[cMaxStateID];
00078
00079         //copy constructor for stl additions into the transition table below.
00080     };
00081
00082     class ULTransitionTable
00083     {
00084     private:
00085         TableRow mTable[cMaxEventID];
00086     public:
00087         ULTransitionTable();
00088
00089         void HandleEvent(Subject*s, ULEvent& inEvent, ULConnection& inConnection,
00090             bool& outWaitingForEvent, EEventID& outRaisedEvent) const;
00091
00092         void PrintTable() const; //so that the table can be printed and verified against the DICOM standard
00093     };
00094 }
00095 #endif // GDCMULTRANSITIONTABLE_H

```

11.599 gdcmULWritingCallback.h File Reference

```
#include "gdcmULConnectionCallback.h"
```

Include dependency graph for gdcmULWritingCallback.h:



Classes

- class [gdcm::network::ULWritingCallback](#)

Namespaces

- namespace [gdcm](#)
- namespace [gdcm::network](#)

11.600 gdcmULWritingCallback.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002  *
00003  *   Copyright NumFOCUS
00004  *
00005  *   Licensed under the Apache License, Version 2.0 (the "License");
00006  *   you may not use this file except in compliance with the License.
00007  *   You may obtain a copy of the License at
00008  *
00009  *       http://www.apache.org/licenses/LICENSE-2.0.txt
00010  *
00011  *   Unless required by applicable law or agreed to in writing, software
00012  *   distributed under the License is distributed on an "AS IS" BASIS,
00013  *   WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied.
00014  *   See the License for the specific language governing permissions and
00015  *   limitations under the License.
00016  *
00017  *=====*/
00018 #ifndef GDCMULCONNECTIONWRITINGCALLBACK_H

```

```

00019 #define GDCMULCONNECTIONWRITINGCALLBACK_H
00020
00021 #include "gdcmULConnectionCallback.h"
00022
00023 namespace gdcm
00024 {
00025 class DataSet;
00026 namespace network
00027 {
00028 /* \brief ULWritingCallback
00029 * \details This is the most basic of callbacks for how the ULConnectionManager handles
00030 * incoming datasets. DataSets are immediately written to disk as soon as they
00031 * are received. NOTE that if the incoming connection is faster than the disk
00032 * writing speed, this callback could cause some pileups!
00033 */
00034 class GDCM_EXPORT ULWritingCallback : public ULConnectionCallback
00035 {
00036     std::string mDirectoryName;
00037 public:
00038     ULWritingCallback() = default;
00039     ~ULWritingCallback() override = default; //empty, for later inheritance
00040
00042     void SetDirectory(const std::string& inDirectoryName) { mDirectoryName = inDirectoryName; }
00043
00044     void HandleDataSet(const DataSet& inDataSet) override;
00045     void HandleResponse(const DataSet& inDataSet) override;
00046 };
00047 } // end namespace network
00048 } // end namespace gdcm
00049
00050 #endif //GDCMULCONNECTIONWRITINGCALLBACK_H

```


11.601 gdcmUserInformation.h File Reference

```


#include "gdcmTypes.h"
#include "gdcmMaximumLengthSub.h"
#include "gdcmImplementationVersionNameSub.h"
#include "gdcmImplementationClassUIDSub.h"

```

Include dependency graph for gdcmUserInformation.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [gdcm::network::UserInformation](#)
UserInformation.

Namespaces

- namespace [gdcm](#)
- namespace [gdcm::network](#)

11.602 gdcmUserInformation.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 #ifndef GDCMUSERINFORMATION_H
00015 #define GDCMUSERINFORMATION_H
00016
00017 #include "gdcmTypes.h"
00018 #include "gdcmMaximumLengthSub.h"
00019 #include "gdcmImplementationVersionNameSub.h"
00020 #include "gdcmImplementationClassUIDSub.h"
00021
00022 namespace gdcm
00023 {
00024
00025   namespace network
00026   {
00027
00028     class AsynchronousOperationsWindowSub;
00029     class RoleSelectionSub;
00030     struct RoleSelectionSubItems;
  
```


Classes

- class [gdcm::WLMFindQuery](#)
PatientRootQuery.

Namespaces

- namespace [gdcm](#)

11.604 gdcmWLMFindQuery.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013   =====*/
00014 #ifndef GDCMWLMFindQuery_H
00015 #define GDCMWLMFindQuery_H
00016
00017 #include "gdcmBaseRootQuery.h"
00018
00019 namespace gdcm
00020 {
00021     class GDCM_EXPORT WLMFindQuery : public BaseRootQuery
00022     {
00023     public:
00024         friend class QueryFactory;
00025         WLMFindQuery();
00026
00027         // no sense here
00028         void InitializeDataSet(const EQueryLevel& inQueryLevel) override;
00029         std::vector<Tag> GetTagListByLevel(const EQueryLevel& inQueryLevel) override;
00030         // validate query has required tag
00031         bool ValidateQuery(bool inStrict = true) const override;
00032
00033         UIDs::TSName GetAbstractSyntaxUID() const override;
00034     protected:
00035         DataSet GetValidDataSet() const;
00036     };
00037 } // end namespace gdcm
00038 #endif // GDCMWLMFindQuery_H

```

11.605 vtkGDCMImageReader.h File Reference


```

#include "vtkgdcmModule.h"
#include "vtkMedicalImageReader2.h"
#include "vtkImageData.h"


```

```
#include "vtkVersion.h"
```

Include dependency graph for vtkGDCMImageReader.h:



This graph shows which files directly or indirectly include this file:



Classes

- class [vtkGDCMImageReader](#)

Namespaces

- namespace [gdcM](#)

Macros

- #define [VTK_CMYK](#) 8
- #define [VTK_INVERSE_LUMINANCE](#) 5
- #define [VTK_LOOKUP_TABLE](#) 6
- #define [VTK_YBR](#) 7

11.605.1 Macro Definition Documentation

11.605.1.1 VTK_CMYK

```
#define VTK_CMYK 8
```

11.605.1.2 VTK_INVERSE_LUMINANCE

```
#define VTK_INVERSE_LUMINANCE 5
```

11.605.1.3 VTK_LOOKUP_TABLE

```
#define VTK_LOOKUP_TABLE 6
```

11.605.1.4 VTK_YBR

```
#define VTK_YBR 7
```

11.606 vtkGDCMImageReader.h

[Go to the documentation of this file.](#)

```
00001 /*=====
00002
00003 Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005 Copyright (c) 2006-2011 Mathieu Malaterre
00006 All rights reserved.
00007 See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009 This software is distributed WITHOUT ANY WARRANTY; without even
00010 the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011 PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 // .NAME vtkGDCMImageReader - read DICOM Image files (Pixel Data)
00015 // .SECTION Description
00016 // vtkGDCMImageReader is a source object that reads some DICOM files
00017 // this reader is single threaded.
00018 // .SECTION Implementation note: when FileLowerLeft is set to on the image is not flipped
00019 // upside down as VTK would expect, use this option only if you know what you are doing.
00020 // .SECTION Implementation note: when reading a series of 2D slices, user is
00021 // expected to provide an ordered list of filenames. No sorting will be applied afterward.
00022 // .SECTION Implementation note: Although 99% of the time the Zspacing as read
00023 // from a tag in a 2D DICOM file should be correct, there has been reports that this
00024 // value can be missing, or incorrect, in which case users are advised to override this
00025 // value using the return value from gdcm::IPPSorter::GetZSpacing() and set it via
00026 // vtkImageChangeInformation on the reader itself.
00027 // .SECTION TODO
00028 // This reader does not handle a series of 3D images, only a single 3D (multi frame) or a
00029 // list of 2D files are supported for now.
00030 // .SECTION TODO
00031 // Did not implement SetFilePattern / SetFilePrefix API, move it to protected section for now.
00032 // .SECTION BUG
00033 // Overlay are assumed to have the same extent as image. Right now if overlay origin is not
00034 // 0,0 the overlay will have an offset...
00035 // Only the very first overlay is loaded at the VTK level, for now (even if there are more than one in the
file)
```

```

00036 // .SECTION DataOrigin
00037 // When the reader is instantiated with FileLowerLeftOn the DataOrigin and Image Position (Patient) are
00038 // identical. But when FileLowerLeft is Off, we have to reorder the Y-line of the image, and thus the
    DataOrigin
00039 // is then translated to the other side of the image.
00040 // .SECTION Spacing
00041 // When reading a 3D volume, the spacing along the Z dimension might be negative (so as to respect
    up-side-down)
00042 // as specified in the Image Orientation (Patient) tag. When Z-spacing is 0, this means the multi-frame
    object
00043 // contains image which do not represent uniform volume.
00044 // .SECTION Warning
00045 // When using vtkGDCMPolyDataReader in conjunction with vtkGDCMImageReader
00046 // it is *required* that FileLowerLeft is set to ON as coordinate system
00047 // would be inconsistent in between the two data structures.
00048 // .SECTION Color Space mapping:
00049 // * VTK_LUMINANCE <=> MONOCHROME2
00050 // * VTK_LUMINANCE_ALPHA <=> Not supported
00051 // * VTK_RGB <=> RGB
00052 // * VTK_RGBA <=> ARGB (deprecated, DICOM 2008)
00053 // * VTK_INVERSE_LUMINANCE <=> MONOCHROME1
00054 // * VTK_LOOKUP_TABLE <=> PALETTE COLOR
00055 // * VTK_YBR <=> YBR_FULL
00056 //
00057 // For detailed information on color space transformation and true lossless transformation see:
00058 // http://gdcm.sourceforge.net/wiki/index.php/Color\_Space\_Transformations
00059
00060 // .SECTION See Also
00061 // vtkMedicalImageReader2 vtkMedicalImageProperties vtkGDCMPolyDataReader vtkGDCMImageWriter
00062 // vtkDICOMImageReader
00063
00064 #ifndef VTKGDCMIMAGEREADER_H
00065 #define VTKGDCMIMAGEREADER_H
00066
00067 #include "vtkgdcmModule.h"
00068 #include "vtkMedicalImageReader2.h"
00069 #include "vtkImageData.h"
00070 #include "vtkVersion.h"
00071
00072 #if (VTK_MAJOR_VERSION >= 5) || ( VTK_MAJOR_VERSION == 4 && VTK_MINOR_VERSION > 5 )
00073 #else
00074 class vtkMedicalImageProperties;
00075 #endif
00076 #if (VTK_MAJOR_VERSION > 5) || ( VTK_MAJOR_VERSION == 5 && VTK_MINOR_VERSION > 0 )
00077 #else
00078 class vtkStringArray;
00079 #endif
00080 class vtkPolyData;
00081
00082 // vtkSystemIncludes.h defines:
00083 // #define VTK_LUMINANCE 1
00084 // #define VTK_LUMINANCE_ALPHA 2
00085 // #define VTK_RGB 3
00086 // #define VTK_RGBA 4
00087 #ifndef VTK_INVERSE_LUMINANCE
00088 #define VTK_INVERSE_LUMINANCE 5
00089 #endif
00090 #ifndef VTK_LOOKUP_TABLE
00091 #define VTK_LOOKUP_TABLE 6
00092 #endif
00093 #ifndef VTK_YBR
00094 #define VTK_YBR 7
00095 #endif
00096 #ifndef VTK_CMYK
00097 #define VTK_CMYK 8
00098 #endif
00099
00100 //BTX
00101 namespace gdcm { class ImageReader; }
00102 //ETX
00103 class vtkMatrix4x4;
00104 class VTKGDCM_EXPORT vtkGDCMImageReader : public vtkMedicalImageReader2
00105 {
00106 public:
00107     static vtkGDCMImageReader *New();
00108     vtkTypeMacro(vtkGDCMImageReader,vtkMedicalImageReader2);
00109     virtual void PrintSelf(ostream& os, vtkIndent indent);
00110
00111     // Description: is the given file name a DICOM file containing an image ?
00112     virtual int CanReadFile(const char* fname);
00113

```

```

00114 // Description:
00115 // Valid extensions
00116 virtual const char* GetFileExtensions()
00117 {
00118     // I would like to get rid of ACR/NEMA/IMA so only allow dcm extension for now
00119     return ".dcm .DCM";
00120 }
00121
00122 // Description:
00123 // A descriptive name for this format
00124 virtual const char* GetDescriptiveName()
00125 {
00126     return "DICOM";
00127 }
00128
00129 // Description:
00130 // Get the Image Position (Patient) as stored in the DICOM file
00131 // This is a read-only data member
00132 vtkGetObjectMacro(DirectionCosines, vtkMatrix4x4);
00133
00134 #if (VTK_MAJOR_VERSION >= 5) || ( VTK_MAJOR_VERSION == 4 && VTK_MINOR_VERSION > 5 )
00135 #else
00136     // Description:
00137     // Get the medical image properties object
00138     vtkGetObjectMacro(MedicalImageProperties, vtkMedicalImageProperties);
00139 #endif
00140 virtual void SetMedicalImageProperties(vtkMedicalImageProperties *pd);
00141
00142 #if (VTK_MAJOR_VERSION > 5) || ( VTK_MAJOR_VERSION == 5 && VTK_MINOR_VERSION > 0 )
00143 #else
00144     virtual void SetFileNames(vtkStringArray*);
00145     vtkGetObjectMacro(FileNames, vtkStringArray);
00146 #endif
00147
00148 // Description:
00149 // Specifically request to load the overlay into the gdcm-VTK layer (gdcm always loads them when found).
00150 // If no overlay is found in the image, then the vtkImageData for the overlay will be empty.
00151 vtkGetMacro(LoadOverlays,int);
00152 vtkSetMacro(LoadOverlays,int);
00153 vtkBooleanMacro(LoadOverlays,int);
00154
00155 // Description:
00156 // Set/Get whether or not to load the Icon as vtkImageData (if found in the DICOM file)
00157 vtkGetMacro(LoadIconImage,int);
00158 vtkSetMacro(LoadIconImage,int);
00159 vtkBooleanMacro(LoadIconImage,int);
00160
00161 // Description:
00162 // Set/Get whether or not the image was compressed using a lossy compression algorithm
00163 vtkGetMacro(LossyFlag,int);
00164 vtkSetMacro(LossyFlag,int);
00165 vtkBooleanMacro(LossyFlag,int);
00166
00167 // Description:
00168 // Read only: number of overlays as found in this image (multiple overlays per slice is allowed)
00169 // Only valid when LoadOverlays is true
00170 vtkGetMacro(NumberOfOverlays,int);
00171
00172 // Description:
00173 // Read only: number of icon image (there can only be zero or one icon per file)
00174 // Only valid when LoadIconImage is true
00175 vtkGetMacro(NumberOfIconImages,int);
00176
00177 // Description:
00178 // Get Overlay/IconImage
00179 // Remember to ALWAYS use those methods in your code, as the internal number for the output port
00180 // is not guaranteed to remain the same, as features are added to the reader
00181 #if (VTK_MAJOR_VERSION >= 5) || ( VTK_MAJOR_VERSION == 4 && VTK_MINOR_VERSION > 5 )
00182 //FIXME: Need to get rid of BTX/ETX if only the Python Wrapper of VTK 4.2 would let me
00183 //BTX
00184     vtkAlgorithmOutput* GetOverlayPort(int index);
00185     vtkAlgorithmOutput* GetIconImagePort();
00186 //ETX
00187 #endif
00188 vtkImageData* GetOverlay(int i);
00189 vtkImageData* GetIconImage();
00190
00191 // Description:
00192 // Load image with its associated Lookup Table
00193 vtkGetMacro(ApplyLookupTable,int);
00194 vtkSetMacro(ApplyLookupTable,int);

```

```

00195     vtkBooleanMacro(ApplyLookupTable,int);
00196
00197     // Description:
00198     // Load image as YBR
00199     vtkGetMacro(ApplyYBRToRGB,int)
00200     vtkSetMacro(ApplyYBRToRGB,int)
00201     vtkBooleanMacro(ApplyYBRToRGB,int);
00202
00203     // Description:
00204     // Return VTK_LUMINANCE, VTK_INVERSE_LUMINANCE, VTK_RGB, VTK_RGBA, VTK_LOOKUP_TABLE, VTK_YBR or VTK_CMYK
00205     // or 0 when ImageFormat is not handled.
00206     // Warning: For color image, PlanarConfiguration need to be taken into account.
00207     vtkGetMacro(ImageFormat,int);
00208
00209     // Description:
00210     // Return the Planar Configuration. This simply means that the internal DICOM image was stored
00211     // using a particular planar configuration (most of the time: 0)
00212     // For monochrome image, PlanarConfiguration is always 0
00213     vtkGetMacro(PlanarConfiguration,int);
00214
00215     // Description:
00216     // Return the 'raw' information stored in the DICOM file:
00217     // In case of a series of multiple files, only the first file is considered. The Image Orientation
(Patient)
00218     // is guaranteed to remain the same, and image Image Position (Patient) in other slice can be computed
00219     // using the ZSpacing (3rd dimension)
00220     // (0020,0032) DS [87.774866\~182.908510\168.629671] # 32, 3 ImagePositionPatient
00221     // (0020,0037) DS [0.001479\0.999989\~0.004376\~0.002039\~0.004372\~0.999988] # 58, 6
ImageOrientationPatient
00222     vtkGetVector3Macro(ImagePositionPatient,double);
00223     vtkGetVector6Macro(ImageOrientationPatient,double);
00224
00225     // Description:
00226     // Set/Get the first Curve Data:
00227     vtkGetObjectMacro(Curve,vtkPolyData);
00228     virtual void SetCurve(vtkPolyData *pd);
00229
00230     // Description:
00231     // \DEPRECATED:
00232     // Modality LUT
00233     // Value returned by GetShift/GetScale might be inaccurate since Shift/Scale could be
00234     // varying along the Series read. Therefore user are advices not to use those functions
00235     // anymore
00236     vtkGetMacro(Shift,double);
00237     vtkGetMacro(Scale,double);
00238
00239 protected:
00240     vtkGDCMImageReader();
00241     ~vtkGDCMImageReader();
00242
00243     vtkSetVector6Macro(ImageOrientationPatient,double);
00244
00245 //BTX
00246 void FillMedicalImageInformation(const gdcm::ImageReader &reader);
00247 //ETX
00248 int RequestInformationCompat();
00249 int RequestDataCompat();
00250
00251 #if (VTK_MAJOR_VERSION >= 5) || ( VTK_MAJOR_VERSION == 4 && VTK_MINOR_VERSION > 5 )
00252 int ProcessRequest(vtkInformation* request,
00253                   vtkInformationVector** inputVector,
00254                   vtkInformationVector* outputVector);
00255 int RequestInformation(vtkInformation *request,
00256                       vtkInformationVector **inputVector,
00257                       vtkInformationVector *outputVector);
00258 int RequestData(vtkInformation *request,
00259                vtkInformationVector **inputVector,
00260                vtkInformationVector *outputVector);
00261 #else /*(VTK_MAJOR_VERSION >= 5) || ( VTK_MAJOR_VERSION == 4 && VTK_MINOR_VERSION > 5 )*/
00262 void ExecuteInformation();
00263 void ExecuteData(vtkDataObject *out);
00264 #endif /*(VTK_MAJOR_VERSION >= 5) || ( VTK_MAJOR_VERSION == 4 && VTK_MINOR_VERSION > 5 )*/
00265
00266 protected:
00267 #if (VTK_MAJOR_VERSION >= 5) || ( VTK_MAJOR_VERSION == 4 && VTK_MINOR_VERSION > 5 )
00268 #else
00269     // Description:
00270     // Medical Image properties
00271     vtkMedicalImageProperties *MedicalImageProperties;
00272 #endif
00273 #if (VTK_MAJOR_VERSION > 5) || ( VTK_MAJOR_VERSION == 5 && VTK_MINOR_VERSION > 0 )

```

```

00274 #else
00275     vtkStringArray *FileNames;
00276 #endif
00277
00278     vtkMatrix4x4 *DirectionCosines;
00279     int LoadOverlays;
00280     int NumberOfOverlays;
00281     int LoadIconImage;
00282     int NumberOfIconImages;
00283     int IconImageDataExtent[6];
00284     double ImagePositionPatient[3];
00285     double ImageOrientationPatient[6];
00286     vtkPolyData *Curve;
00287
00288     int ImageFormat;
00289     // the following 3, should remain optional
00290     int ApplyInverseVideo;
00291     int ApplyLookupTable;
00292     int ApplyYBRToRGB;
00293     // I think that planar configuration need to always be applied as far as VTK is concerned
00294     int ApplyPlanarConfiguration;
00295     int ApplyShiftScale;
00296
00297     int LoadSingleFile(const char *filename, char *pointer, unsigned long &outlen);
00298
00299     double Shift;
00300     double Scale;
00301     int IconDataScalarType;
00302     int IconNumberOfScalarComponents;
00303     int PlanarConfiguration;
00304     int LossyFlag;
00305     int ForceRescale;
00306
00307 protected:
00308     // TODO / FIXME
00309     void SetFilePrefix(const char *) {}
00310     vtkGetStringMacro(FilePrefix);
00311     void SetFilePattern(const char *) {}
00312     vtkGetStringMacro(FilePattern);
00313
00314 private:
00315     vtkGDCMImageReader(const vtkGDCMImageReader&); // Not implemented.
00316     void operator=(const vtkGDCMImageReader&); // Not implemented.
00317 };
00318 #endif

```


11.607 vtkGDCMImageReader2.h File Reference

```

#include "vtkgdcmModule.h"
#include "vtkMedicalImageReader2.h"
#include "vtkImageData.h"

```

Include dependency graph for vtkGDCMImageReader2.h:



Classes

- class [vtkGDCMImageReader2](#)

Namespaces

- namespace [gdcml](#)

Macros

- `#define VTK_CMYK 8`
- `#define VTK_INVERSE_LUMINANCE 5`
- `#define VTK_LOOKUP_TABLE 6`
- `#define VTK_YBR 7`

11.607.1 Macro Definition Documentation

11.607.1.1 VTK_CMYK

```
#define VTK_CMYK 8
```

11.607.1.2 VTK_INVERSE_LUMINANCE

```
#define VTK_INVERSE_LUMINANCE 5
```

11.607.1.3 VTK_LOOKUP_TABLE

```
#define VTK_LOOKUP_TABLE 6
```

11.607.1.4 VTK_YBR

```
#define VTK_YBR 7
```

11.608 vtkGDCMImageReader2.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003     Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005     Copyright (c) 2006-2011 Mathieu Malaterre
00006     All rights reserved.
00007     See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009     This software is distributed WITHOUT ANY WARRANTY; without even
00010     the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011     PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 // .NAME vtkGDCMImageReader2 - read DICOM Image files (Pixel Data)
00015 // .SECTION Description
00016 // vtkGDCMImageReader2 is a source object that reads some DICOM files
00017 // this reader is single threaded.
00018 // .SECTION Implementation note: when FileLowerLeft is set to on the image is not flipped
00019 // upside down as VTK would expect, use this option only if you know what you are doing.
00020 // .SECTION Implementation note: when reading a series of 2D slices, user is
00021 // expected to provide an ordered list of filenames. No sorting will be applied afterward.
00022 // .SECTION Implementation note: Although 99% of the time the Zspacing as read
00023 // from a tag in a 2D DICOM file should be correct, there has been reports that this
00024 // value can be missing, or incorrect, in which case users are advised to override this
00025 // value using the return value from gdcm::IPPSorter::GetZSpacing() and set it via
00026 // vtkImageChangeInformation on the reader itself.
00027 // .SECTION TODO
00028 // This reader does not handle a series of 3D images, only a single 3D (multi frame) or a
00029 // list of 2D files are supported for now.
00030 // .SECTION TODO
00031 // Did not implement SetFilePattern / SetFilePrefix API, move it to protected section for now.
00032 // .SECTION BUG
00033 // Overlay are assumed to have the same extent as image. Right now if overlay origin is not
00034 // 0,0 the overlay will have an offset...
00035 // Only the very first overlay is loaded at the VTK level, for now (even if there are more than one in the
    file)
00036 // .SECTION DataOrigin
00037 // When the reader is instantiated with FileLowerLeftOn the DataOrigin and Image Position (Patient) are
00038 // identical. But when FileLowerLeft is Off, we have to reorder the Y-line of the image, and thus the
    DataOrigin
00039 // is then translated to the other side of the image.
00040 // .SECTION Spacing
00041 // When reading a 3D volume, the spacing along the Z dimension might be negative (so as to respect
    up-side-down)
00042 // as specified in the Image Orientation (Patient) tag. When Z-spacing is 0, this means the multi-frame
    object
00043 // contains image which do not represent uniform volume.
00044 // .SECTION Warning
00045 // When using vtkGDCMPolyDataReader in conjunction with vtkGDCMImageReader2
00046 // it is *required* that FileLowerLeft is set to ON as coordinate system
00047 // would be inconsistent in between the two data structures.
00048 // .SECTION Color Space mapping:
00049 // * VTK_LUMINANCE      <=> MONOCHROME2
00050 // * VTK_LUMINANCE_ALPHA <=> Not supported
00051 // * VTK_RGB            <=> RGB
00052 // * VTK_RGBA          <=> ARGB (deprecated, DICOM 2008)
00053 // * VTK_INVERSE_LUMINANCE <=> MONOCHROME1
00054 // * VTK_LOOKUP_TABLE   <=> PALETTE COLOR
00055 // * VTK_YBR            <=> YBR_FULL
00056 //
00057 // For detailed information on color space transformation and true lossless transformation see:
00058 // http://gdcm.sourceforge.net/wiki/index.php/Color_Space_Transformations
00059
00060 // .SECTION See Also
00061 // vtkMedicalImageReader2 vtkMedicalImageProperties vtkGDCMPolyDataReader vtkGDCMImageWriter
00062 // vtkDICOMImageReader
00063
00064 #ifndef VTKGDCMIMAGEREADER2_H
00065 #define VTKGDCMIMAGEREADER2_H
00066
00067 #include "vtkgdcmModule.h"
00068 #include "vtkMedicalImageReader2.h"
00069 #include "vtkImageData.h"
00070
00071 class vtkPolyData;
```

```

00072
00073 // vtkSystemIncludes.h defines:
00074 // #define VTK_LUMINANCE 1
00075 // #define VTK_LUMINANCE_ALPHA 2
00076 // #define VTK_RGB 3
00077 // #define VTK_RGBA 4
00078 #ifndef VTK_INVERSE_LUMINANCE
00079 #define VTK_INVERSE_LUMINANCE 5
00080 #endif
00081 #ifndef VTK_LOOKUP_TABLE
00082 #define VTK_LOOKUP_TABLE 6
00083 #endif
00084 #ifndef VTK_YBR
00085 #define VTK_YBR 7
00086 #endif
00087 #ifndef VTK_CMYK
00088 #define VTK_CMYK 8
00089 #endif
00090
00091 //BTX
00092 namespace gdcm { class ImageReader; }
00093 //ETX
00094 class vtkMatrix4x4;
00095 class VTKGDCM_EXPORT vtkGDCMImageReader2 : public vtkMedicalImageReader2
00096 {
00097 public:
00098     static vtkGDCMImageReader2 *New();
00099     vtkTypeMacro(vtkGDCMImageReader2,vtkMedicalImageReader2);
00100     virtual void PrintSelf(ostream& os, vtkIndent indent);
00101
00102     // Description: is the given file name a DICOM file containing an image ?
00103     virtual int CanReadFile(const char* fname);
00104
00105     // Description:
00106     // Valid extensions
00107     virtual const char* GetFileExtensions()
00108     {
00109         // I would like to get rid of ACR/NEMA/IMA so only allow dcm extension for now
00110         return ".dcm .DCM";
00111     }
00112
00113     // Description:
00114     // A descriptive name for this format
00115     virtual const char* GetDescriptiveName()
00116     {
00117         return "DICOM";
00118     }
00119
00120     // Description:
00121     // Get the Image Position (Patient) as stored in the DICOM file
00122     // This is a read-only data member
00123     vtkGetObjectMacro(DirectionCosines, vtkMatrix4x4);
00124
00125     virtual void SetMedicalImageProperties(vtkMedicalImageProperties *pd);
00126
00127     // Description:
00128     // Specifically request to load the overlay into the gdcm-VTK layer (gdcm always loads them when found).
00129     // If no overlay is found in the image, then the vtkImageData for the overlay will be empty.
00130     vtkGetMacro(LoadOverlays,int);
00131     vtkSetMacro(LoadOverlays,int);
00132     vtkBooleanMacro(LoadOverlays,int);
00133
00134     // Description:
00135     // Set/Get whether or not to load the Icon as vtkImageData (if found in the DICOM file)
00136     vtkGetMacro(LoadIconImage,int);
00137     vtkSetMacro(LoadIconImage,int);
00138     vtkBooleanMacro(LoadIconImage,int);
00139
00140     // Description:
00141     // Set/Get whether or not the image was compressed using a lossy compression algorithm
00142     vtkGetMacro(LossyFlag,int);
00143     vtkSetMacro(LossyFlag,int);
00144     vtkBooleanMacro(LossyFlag,int);
00145
00146     // Description:
00147     // Read only: number of overlays as found in this image (multiple overlays per slice is allowed)
00148     // Only valid when LoadOverlays is true
00149     vtkGetMacro(NumberOfOverlays,int);
00150
00151     // Description:
00152     // Read only: number of icon image (there can only be zero or one icon per file)

```



```

00153 // Only valid when LoadIconImage is true
00154 vtkGetMacro(NumberOfIconImages,int);
00155
00156 // Description:
00157 // Get Overlay/IconImage
00158 // Remember to ALWAYS use those methods in your code, as the internal number for the output port
00159 // is not guaranteed to remain the same, as features are added to the reader
00160 vtkAlgorithmOutput* GetOverlayPort(int index);
00161 vtkAlgorithmOutput* GetIconImagePort();
00162 vtkImageData* GetOverlay(int i);
00163 vtkImageData* GetIconImage();
00164
00165 // Description:
00166 // Load image with its associated Lookup Table
00167 vtkGetMacro(ApplyLookupTable,int);
00168 vtkSetMacro(ApplyLookupTable,int);
00169 vtkBooleanMacro(ApplyLookupTable,int);
00170
00171 // Description:
00172 // Load image as YBR
00173 vtkGetMacro(ApplyYBRToRGB,int)
00174 vtkSetMacro(ApplyYBRToRGB,int)
00175 vtkBooleanMacro(ApplyYBRToRGB,int);
00176
00177 // Description:
00178 // Return VTK_LUMINANCE, VTK_INVERSE_LUMINANCE, VTK_RGB, VTK_RGBA, VTK_LOOKUP_TABLE, VTK_YBR or VTK_CMYK
00179 // or 0 when ImageFormat is not handled.
00180 // Warning: For color image, PlanarConfiguration need to be taken into account.
00181 vtkGetMacro(ImageFormat,int);
00182
00183 // Description:
00184 // Return the Planar Configuration. This simply means that the internal DICOM image was stored
00185 // using a particular planar configuration (most of the time: 0)
00186 // For monochrome image, PlanarConfiguration is always 0
00187 vtkGetMacro(PlanarConfiguration,int);
00188
00189 // Description:
00190 // Return the 'raw' information stored in the DICOM file:
00191 // In case of a series of multiple files, only the first file is considered. The Image Orientation
(Patient)
00192 // is guaranteed to remain the same, and image Image Position (Patient) in other slice can be computed
00193 // using the ZSpacing (3rd dimension)
00194 // (0020,0032) DS [87.774866~-182.908510~168.629671] # 32, 3 ImagePositionPatient
00195 // (0020,0037) DS [0.001479~0.999989~-0.004376~-0.002039~-0.004372~-0.999988] # 58, 6
ImageOrientationPatient
00196 vtkGetVector3Macro(ImagePositionPatient,double);
00197 vtkGetVector6Macro(ImageOrientationPatient,double);
00198
00199 // Description:
00200 // Set/Get the first Curve Data:
00201 vtkGetObjectMacro(Curve,vtkPolyData);
00202 virtual void SetCurve(vtkPolyData *pd);
00203
00204 // Description:
00205 // \DEPRECATED:
00206 // Modality LUT
00207 // Value returned by GetShift/GetScale might be inaccurate since Shift/Scale could be
00208 // varying along the Series read. Therefore user are advices not to use those functions
00209 // anymore
00210 vtkGetMacro(Shift,double);
00211 vtkGetMacro(Scale,double);
00212
00213 protected:
00214 vtkGDCMImageReader2();
00215 ~vtkGDCMImageReader2();
00216
00217 vtkSetVector6Macro(ImageOrientationPatient,double);
00218
00219 //BTX
00220 void FillMedicalImageInformation(const gdcm::ImageReader &reader);
00221 //ETX
00222 int RequestInformationCompat();
00223 int RequestDataCompat();
00224
00225 int ProcessRequest(vtkInformation* request,
00226                   vtkInformationVector** inputVector,
00227                   vtkInformationVector* outputVector);
00228 int RequestInformation(vtkInformation *request,
00229                       vtkInformationVector **inputVector,
00230                       vtkInformationVector *outputVector);
00231 int RequestData(vtkInformation *request,

```

```

00232         vtkInformationVector **inputVector,
00233         vtkInformationVector *outputVector);
00234
00235 protected:
00236     vtkMatrix4x4 *DirectionCosines;
00237     int LoadOverlays;
00238     int NumberOfOverlays;
00239     int LoadIconImage;
00240     int NumberOfIconImages;
00241     int IconImageDataExtent[6];
00242     double ImagePositionPatient[3];
00243     double ImageOrientationPatient[6];
00244     vtkPolyData *Curve;
00245
00246     int ImageFormat;
00247     // the following 3, should remain optional
00248     int ApplyInverseVideo;
00249     int ApplyLookupTable;
00250     int ApplyYBRToRGB;
00251     // I think that planar configuration need to always be applied as far as VTK is concerned
00252     int ApplyPlanarConfiguration;
00253     int ApplyShiftScale;
00254
00255     int LoadSingleFile(const char *filename, char *pointer, unsigned long &outlen);
00256
00257     double Shift;
00258     double Scale;
00259     int IconDataScalarType;
00260     int IconNumberOfScalarComponents;
00261     int PlanarConfiguration;
00262     int LossyFlag;
00263     int ForceRescale;
00264
00265 protected:
00266     // TODO / FIXME
00267     void SetFilePrefix(const char *) {}
00268     vtkGetStringMacro(FilePrefix);
00269     void SetFilePattern(const char *) {}
00270     vtkGetStringMacro(FilePattern);
00271
00272 private:
00273     vtkGDCMImageReader2(const vtkGDCMImageReader2&); // Not implemented.
00274     void operator=(const vtkGDCMImageReader2&); // Not implemented.
00275 };
00276 #endif

```


11.609 vtkGDCMImageWriter.h File Reference

```

#include "vtkgdcmModule.h"
#include "vtkImageWriter.h"
#include "vtkVersion.h"

```

Include dependency graph for vtkGDCMImageWriter.h:



Classes

- class [vtkGDCMImageWriter](#)

11.610 vtkGDCMImageWriter.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcms.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 // .NAME vtkGDCMImageWriter - write DICOM files
00015 // .SECTION Description
00016 // vtkGDCMImageWriter is a sink object that write DICOM files
00017 // this writer is single threaded (see vtkGDCMThreadedImageReader2 for multi-thread)
00018 //
00019 // .SECTION Warning: vtkLookupTable from the vtkImageData object taken into account
00020 // only if ImageFormat is set to VTK_LOOKUP_TABLE
00021 //
00022 // .SECTION NOTE We are not using the usual API SetFilePrefix / SetFilePattern,
00023 // but instead a list of filenames: see SetFileNames and class gdcms::FilenameGenerator
00024 //
00025 // .SECTION Warning
00026 // You need to specify the correct ImageFormat (taken from the reader)
00027 // You need to explicitly specify the DirectionCosines (taken from the reader)
00028 // Since VTK 5.4 vtkMedicalImageProperties has its own DirectionCosine (no 's')
00029 // user need to make sure the vtkMatrix4x4 is compatible with the 6-vector DirectionCosine.
00030 //
00031 // .SECTION NOTE Shift/Scale are global to all DICOM frames (=files) written
00032 // as 2D slice, therefore the shift/scale operation might not be optimized for
00033 // all slices. This is not recommended for image with a large dynamic range.
00034 //
00035 // .SECTION See Also
00036 // vtkImageWriter vtkMedicalImageProperties vtkGDCMImageReader
00037
00038 #ifndef VTKGDCMIMAGEWRITER_H
00039 #define VTKGDCMIMAGEWRITER_H
00040
00041 #include "vtkgdcmsModule.h"
00042 #include "vtkImageWriter.h"
00043 #include "vtkVersion.h"
00044
00045 class vtkLookupTable;
00046 class vtkMedicalImageProperties;
00047 class vtkMatrix4x4;
00048 class vtkStringArray;
00049 class VTKGDCM_EXPORT vtkGDCMImageWriter : public vtkImageWriter
00050 {
00051 public:
00052   static vtkGDCMImageWriter *New();
00053   vtkTypeMacro(vtkGDCMImageWriter,vtkImageWriter);
00054   virtual void PrintSelf(ostream& os, vtkIndent indent);
00055
00056   // Description:
00057   // Pass in the vtkmedicalimageproperties object for medical information
00058   // to be mapped to DICOM attributes.
00059   vtkGetObjectMacro(MedicalImageProperties, vtkMedicalImageProperties);
00060   virtual void SetMedicalImageProperties(vtkMedicalImageProperties*);
00061
00062   // Description:
00063   // Pass in the list of filename to be used to write out the DICOM file(s)
00064   virtual void SetFileNames(vtkStringArray*);
00065   vtkGetObjectMacro(FileNames, vtkStringArray);
00066

```

```

00067 // Description:
00068 // Set/Get whether or not the image was compressed using a lossy compression algorithm
00069 vtkGetMacro(LossyFlag,int);
00070 vtkSetMacro(LossyFlag,int);
00071 vtkBooleanMacro(LossyFlag,int);
00072
00073 // I need that...
00074 virtual void Write();
00075
00076 // Description:
00077 // Get the extension for this file format.
00078 virtual const char* GetFileExtensions() {
00079     return ".dcm .DCM"; }
00080
00081 // Description:
00082 // Get the name of this file format.
00083 virtual const char* GetDescriptiveName() {
00084     return "DICOM"; }
00085
00086 // Description:
00087 // You need to manually specify the direction the image is in to write a valid DICOM file
00088 // since vtkImageData do not contains one (eg. MR Image Storage, CT Image Storage...)
00089 virtual void SetDirectionCosines(vtkMatrix4x4 *matrix);
00090 vtkGetObjectMacro(DirectionCosines, vtkMatrix4x4);
00091 virtual void SetDirectionCosinesFromImageOrientationPatient(const double dircos[6]);
00092
00093 // Description:
00094 // Modality LUT
00095 vtkSetMacro(Shift, double);
00096 vtkGetMacro(Shift, double);
00097 vtkSetMacro(Scale, double);
00098 vtkGetMacro(Scale, double);
00099
00100 // Description:
00101 // See vtkGDCMImageReader for list of ImageFormat
00102 vtkGetMacro(ImageFormat,int);
00103 vtkSetMacro(ImageFormat,int);
00104
00105 // Description:
00106 // Set/Get whether the data comes from the file starting in the lower left
00107 // corner or upper left corner.
00108 vtkBooleanMacro(FileLowerLeft, int);
00109 vtkGetMacro(FileLowerLeft, int);
00110 vtkSetMacro(FileLowerLeft, int);
00111
00112 // Description:
00113 // For color image (more than a single comp) you can specify the planar configuration you prefer
00114 vtkSetMacro(PlanarConfiguration,int);
00115 vtkGetMacro(PlanarConfiguration,int);
00116
00117 // Description:
00118 // Set/Get specific StudyUID / SeriesUID
00119 vtkSetStringMacro(StudyUID);
00120 vtkGetStringMacro(StudyUID);
00121 vtkSetStringMacro(SeriesUID);
00122 vtkGetStringMacro(SeriesUID);
00123
00124 //BTX
00125 enum CompressionTypes {
00126     NO_COMPRESSION = 0, // raw (default)
00127     JPEG_COMPRESSION, // JPEG
00128     JPEG2000_COMPRESSION, // J2K
00129     JPEGLS_COMPRESSION, // JPEG-LS
00130     RLE_COMPRESSION // RLE
00131 };
00132 //ETX
00133 // Set/Get the compression type
00134 vtkSetMacro(CompressionType, int);
00135 vtkGetMacro(CompressionType, int);
00136
00137 //void SetCompressionTypeFromString(const char *);
00138 //const char *GetCompressionTypeAsString();
00139
00140 protected:
00141     vtkGDCMImageWriter();
00142     ~vtkGDCMImageWriter();
00143
00144 #if (VTK_MAJOR_VERSION >= 5) || ( VTK_MAJOR_VERSION == 4 && VTK_MINOR_VERSION > 5 )
00145     int FillInputPortInformation(int port, vtkInformation *info);
00146     int RequestInformation(
00147         vtkInformation *request,

```

```

00148     vtkInformationVector **inputVector,
00149     vtkInformationVector *outputVector);
00150 int RequestUpdateExtent(
00151     vtkInformation *request,
00152     vtkInformationVector **inputVector,
00153     vtkInformationVector *outputVector);
00154 int RequestData(
00155     vtkInformation *request,
00156     vtkInformationVector **inputVector,
00157     vtkInformationVector *outputVector);
00158 #else
00159     void WriteSlice(vtkImageData *data);
00160 #endif /*(VTK_MAJOR_VERSION >= 5) || ( VTK_MAJOR_VERSION == 4 && VTK_MINOR_VERSION > 5 )*/
00161 int WriteGDCMData(vtkImageData *data, int timeStep);
00162
00163 protected:
00164     virtual /*const*/ char *GetFileName();
00165
00166 private:
00167     vtkGDCMImageWriter(const vtkGDCMImageWriter&); // Not implemented.
00168     void operator=(const vtkGDCMImageWriter&); // Not implemented.
00169
00170     // VTK structs:
00171     //vtkLookupTable *LookupTable;
00172     vtkMedicalImageProperties *MedicalImageProperties;
00173     char *StudyUID;
00174     char *SeriesUID;
00175
00176     int DataUpdateExtent[6];
00177     int ImageFormat;
00178
00179     vtkStringArray *FileNames;
00180     vtkMatrix4x4 *DirectionCosines;
00181
00182     double Shift;
00183     double Scale;
00184     int FileLowerLeft;
00185     int PlanarConfiguration;
00186     int LossyFlag;
00187     int CompressionType;
00188 };
00189
00190 #endif


```

11.611 vtkGDCMMedicalImageProperties.h File Reference

```
#include "vtkgdcmModule.h"
```

```
#include "vtkMedicalImageProperties.h"
```

Include dependency graph for vtkGDCMMedicalImageProperties.h:



Classes

- class [vtkGDCMMedicalImageProperties](#)

Namespaces

- namespace [gdcm](#)

11.612 vtkGDCMMedicalImageProperties.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003     Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005     Copyright (c) 2006-2011 Mathieu Malaterre
00006     All rights reserved.
00007     See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009     This software is distributed WITHOUT ANY WARRANTY; without even
00010     the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011     PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 // .NAME vtkGDCMMedicalImageProperties - some medical image properties.
00015 // .SECTION Description
00016 // vtkGDCMMedicalImageProperties is a helper class that can be used by medical
00017 // image readers and applications to encapsulate medical image/acquisition
00018 // properties. Later on, this should probably be extended to add
00019 // any user-defined property.
00020 // .SECTION See Also
00021 // vtkMedicalImageReader2
00022
00023 #ifndef VTKGDCMMEDICALIMAGEPROPERTIES_H
00024 #define VTKGDCMMEDICALIMAGEPROPERTIES_H
00025
00026 #include "vtkgdcmModule.h"
00027 #include "vtkMedicalImageProperties.h"
00028
00029 class vtkGDCMMedicalImagePropertiesInternals;
00030 //BTX
00031 namespace gdcm { class File; }
00032 //ETX
00033
00034 class VTKGDCM_EXPORT vtkGDCMMedicalImageProperties : public vtkMedicalImageProperties
00035 {
00036 public:
00037     static vtkGDCMMedicalImageProperties *New();
00038     vtkTypeMacro(vtkGDCMMedicalImageProperties,vtkMedicalImageProperties);
00039     void PrintSelf(ostream& os, vtkIndent indent);
00040
00041     // Description:
00042     // Convenience method to reset all fields to an empty string/value
00043     virtual void Clear();
00044
00045 /*
00046     // Description:
00047     // Patient name
00048     // For ex: DICOM (0010,0010) = DOE,JOHN
00049     vtkSetStringMacro(PatientName);
00050     vtkGetStringMacro(PatientName);
00051
00052     // Description:
00053     // Patient ID
00054     // For ex: DICOM (0010,0020) = 1933197
00055     vtkSetStringMacro(PatientID);
00056     vtkGetStringMacro(PatientID);
00057
00058     // Description:
00059     // Patient age

```

```
00060 // Format: nnnD, nnW, nnnM or nnnY (eventually nnD, nnW, nnY)
00061 //       with D (day), M (month), W (week), Y (year)
00062 // For ex: DICOM (0010,1010) = 031Y
00063 vtkSetStringMacro(PatientAge);
00064 vtkGetStringMacro(PatientAge);
00065
00066 // Description:
00067 // Take as input a string in VR=AS (DICOM PS3.5) and extract either
00068 // different fields namely: year month week day
00069 // Return 0 on error, 1 on success
00070 // One can test fields if they are different from -1 upon success
00071 static int GetAgeAsFields(const char *age, int &year, int &month, int &week, int &day);
00072
00073 // For Tcl:
00074 // From C++ use GetPatientAge + GetAgeAsField
00075 // Those function parse a DICOM string, and return the value of the number expressed
00076 // this is either expressed in year, month or days. Thus if a string is expressed in years
00077 // GetPatientAgeDay/GetPatientAgeWeek/GetPatientAgeMonth will return 0
00078 int GetPatientAgeYear();
00079 int GetPatientAgeMonth();
00080 int GetPatientAgeWeek();
00081 int GetPatientAgeDay();
00082
00083 // Description:
00084 // Patient sex
00085 // For ex: DICOM (0010,0040) = M
00086 vtkSetStringMacro(PatientSex);
00087 vtkGetStringMacro(PatientSex);
00088
00089 // Description:
00090 // Patient birth date
00091 // Format: yyyyymmdd
00092 // For ex: DICOM (0010,0030) = 19680427
00093 vtkSetStringMacro(PatientBirthDate);
00094 vtkGetStringMacro(PatientBirthDate);
00095
00096 // For Tcl:
00097 // From C++ use GetPatientBirthDate + GetDateAsFields
00098 int GetPatientBirthDateYear();
00099 int GetPatientBirthDateMonth();
00100 int GetPatientBirthDateDay();
00101
00102 // Description:
00103 // Study Date
00104 // Format: yyyyymmdd
00105 // For ex: DICOM (0008,0020) = 20030617
00106 vtkSetStringMacro(StudyDate);
00107 vtkGetStringMacro(StudyDate);
00108
00109 // Description:
00110 // Acquisition Date
00111 // Format: yyyyymmdd
00112 // For ex: DICOM (0008,0022) = 20030617
00113 vtkSetStringMacro(AcquisitionDate);
00114 vtkGetStringMacro(AcquisitionDate);
00115
00116 // For Tcl:
00117 // From C++ use GetAcquisitionDate + GetDateAsFields
00118 int GetAcquisitionDateYear();
00119 int GetAcquisitionDateMonth();
00120 int GetAcquisitionDateDay();
00121
00122 // Description:
00123 // Study Time
00124 // Format: hhmmss.frac (any trailing component(s) can be omitted)
00125 // For ex: DICOM (0008,0030) = 162552.0705 or 230012, or 0012
00126 vtkSetStringMacro(StudyTime);
00127 vtkGetStringMacro(StudyTime);
00128
00129 // Description:
00130 // Acquisition time
00131 // Format: hhmmss.frac (any trailing component(s) can be omitted)
00132 // For ex: DICOM (0008,0032) = 162552.0705 or 230012, or 0012
00133 vtkSetStringMacro(AcquisitionTime);
00134 vtkGetStringMacro(AcquisitionTime);
00135
00136 // Description:
00137 // Image Date aka Content Date
00138 // Format: yyyyymmdd
00139 // For ex: DICOM (0008,0023) = 20030617
00140 vtkSetStringMacro(ImageDate);
```

```
00141 vtkGetStringMacro(ImageDate);
00142
00143 // For Tcl:
00144 // From C++ use GetImageDate + GetDateAsFields
00145 int GetImageDateYear();
00146 int GetImageDateMonth();
00147 int GetImageDateDay();
00148
00149 // Description:
00150 // Take as input a string in ISO 8601 date (YYYY/MM/DD) and extract the
00151 // different fields namely: year month day
00152 // Return 0 on error, 1 on success
00153 static int GetDateAsFields(const char *date, int &year, int &month, int &day);
00154
00155 // Description:
00156 // Take as input a string in ISO 8601 date (YYYY/MM/DD) and construct a
00157 // locale date based on the different fields (see GetDateAsFields to extract
00158 // different fields)
00159 // Return 0 on error, 1 on success
00160 static int GetDateAsLocale(const char *date, char *locale);
00161
00162 // Description:
00163 // Image Time
00164 // Format: hhmmss.frac (any trailing component(s) can be omitted)
00165 // For ex: DICOM (0008,0033) = 162552.0705 or 230012, or 0012
00166 vtkSetStringMacro(ImageTime);
00167 vtkGetStringMacro(ImageTime);
00168
00169 // Description:
00170 // Image number
00171 // For ex: DICOM (0020,0013) = 1
00172 vtkSetStringMacro(ImageNumber);
00173 vtkGetStringMacro(ImageNumber);
00174
00175 // Description:
00176 // Series number
00177 // For ex: DICOM (0020,0011) = 902
00178 vtkSetStringMacro(SeriesNumber);
00179 vtkGetStringMacro(SeriesNumber);
00180
00181 // Description:
00182 // Series Description
00183 // User provided description of the Series
00184 // For ex: DICOM (0008,103e) = SCOUT
00185 vtkSetStringMacro(SeriesDescription);
00186 vtkGetStringMacro(SeriesDescription);
00187
00188 // Description:
00189 // Study ID
00190 // For ex: DICOM (0020,0010) = 37481
00191 vtkSetStringMacro(StudyID);
00192 vtkGetStringMacro(StudyID);
00193
00194 // Description:
00195 // Study description
00196 // For ex: DICOM (0008,1030) = BRAIN/C-SP/FACIAL
00197 vtkSetStringMacro(StudyDescription);
00198 vtkGetStringMacro(StudyDescription);
00199
00200 // Description:
00201 // Modality
00202 // For ex: DICOM (0008,0060)= CT
00203 vtkSetStringMacro(Modality);
00204 vtkGetStringMacro(Modality);
00205
00206 // Description:
00207 // Manufacturer
00208 // For ex: DICOM (0008,0070) = Siemens
00209 vtkSetStringMacro(Manufacturer);
00210 vtkGetStringMacro(Manufacturer);
00211
00212 // Description:
00213 // Manufacturer's Model Name
00214 // For ex: DICOM (0008,1090) = LightSpeed QX/i
00215 vtkSetStringMacro(ManufacturerModelName);
00216 vtkGetStringMacro(ManufacturerModelName);
00217
00218 // Description:
00219 // Station Name
00220 // For ex: DICOM (0008,1010) = LSPD_OC8
00221 vtkSetStringMacro(StationName);
```



```
00222   vtkGetStringMacro(StationName);
00223
00224   // Description:
00225   // Institution Name
00226   // For ex: DICOM (0008,0080) = FooCity Medical Center
00227   vtkSetStringMacro(InstitutionName);
00228   vtkGetStringMacro(InstitutionName);
00229
00230   // Description:
00231   // Convolution Kernel (or algorithm used to reconstruct the data)
00232   // For ex: DICOM (0018,1210) = Bone
00233   vtkSetStringMacro(ConvolutionKernel);
00234   vtkGetStringMacro(ConvolutionKernel);
00235
00236   // Description:
00237   // Slice Thickness (Nominal reconstructed slice thickness, in mm)
00238   // For ex: DICOM (0018,0050) = 0.273438
00239   vtkSetStringMacro(SliceThickness);
00240   vtkGetStringMacro(SliceThickness);
00241   virtual double GetSliceThicknessAsDouble();
00242
00243   // Description:
00244   // Peak kilo voltage output of the (x-ray) generator used
00245   // For ex: DICOM (0018,0060) = 120
00246   vtkSetStringMacro(KVP);
00247   vtkGetStringMacro(KVP);
00248
00249   // Description:
00250   // Gantry/Detector tilt (Nominal angle of tilt in degrees of the scanning
00251   // gantry.)
00252   // For ex: DICOM (0018,1120) = 15
00253   vtkSetStringMacro(GantryTilt);
00254   vtkGetStringMacro(GantryTilt);
00255   virtual double GetGantryTiltAsDouble();
00256
00257   // Description:
00258   // Echo Time
00259   // (Time in ms between the middle of the excitation pulse and the peak of
00260   // the echo produced)
00261   // For ex: DICOM (0018,0081) = 105
00262   vtkSetStringMacro(EchoTime);
00263   vtkGetStringMacro(EchoTime);
00264
00265   // Description:
00266   // Echo Train Length
00267   // (Number of lines in k-space acquired per excitation per image)
00268   // For ex: DICOM (0018,0091) = 35
00269   vtkSetStringMacro(EchoTrainLength);
00270   vtkGetStringMacro(EchoTrainLength);
00271
00272   // Description:
00273   // Repetition Time
00274   // The period of time in msec between the beginning of a pulse sequence and
00275   // the beginning of the succeeding (essentially identical) pulse sequence.
00276   // For ex: DICOM (0018,0080) = 2040
00277   vtkSetStringMacro(RepetitionTime);
00278   vtkGetStringMacro(RepetitionTime);
00279
00280   // Description:
00281   // Exposure time (time of x-ray exposure in msec)
00282   // For ex: DICOM (0018,1150) = 5
00283   vtkSetStringMacro(ExposureTime);
00284   vtkGetStringMacro(ExposureTime);
00285
00286   // Description:
00287   // X-ray tube current (in mA)
00288   // For ex: DICOM (0018,1151) = 400
00289   vtkSetStringMacro(XRayTubeCurrent);
00290   vtkGetStringMacro(XRayTubeCurrent);
00291
00292   // Description:
00293   // Exposure (The exposure expressed in mAs, for example calculated
00294   // from Exposure Time and X-ray Tube Current)
00295   // For ex: DICOM (0018,1152) = 114
00296   vtkSetStringMacro(Exposure);
00297   vtkGetStringMacro(Exposure);
00298
00299   // Interface to allow insertion of user define values, for instance in DICOM one would want to
00300   // store the Protocol Name (0018,1030), in this case one would do:
00301   // AddUserDefinedValue( "Protocol Name", "T1W/SE/1024" );
00302   void AddUserDefinedValue(const char *name, const char *value);
```

```

00303 // Get a particular user value
00304 const char *GetUserDefinedValue(const char *name);
00305 // Get the number of user defined values
00306 unsigned int GetNumberOfUserDefinedValues();
00307 // Get a name/value by index
00308 const char *GetUserDefinedNameByIndex(unsigned int idx);
00309 const char *GetUserDefinedValueByIndex(unsigned int idx);
00310
00311 // Description:
00312 // Copy the contents of p to this instance.
00313 virtual void DeepCopy(vtkGDCMMedicalImageProperties *p);
00314
00315 // Description:
00316 // Add/Remove/Query the window/level presets that may have been associated
00317 // to a medical image. Window is also known as 'width', level is also known
00318 // as 'center'. The same window/level pair can not be added twice.
00319 // As a convenience, a comment (aka Explanation) can be associated to a preset.
00320 // For ex: DICOM Window Center (0028,1050) = 00045\000470
00321 //           DICOM Window Width (0028,1051) = 0106\03412
00322 //           DICOM Window Center Width Explanation (0028,1055) = WINDOW1\WINDOW2
00323 virtual void AddWindowLevelPreset(double w, double l);
00324 virtual void RemoveWindowLevelPreset(double w, double l);
00325 virtual void RemoveAllWindowLevelPresets();
00326 virtual int GetNumberOfWindowLevelPresets();
00327 virtual int HasWindowLevelPreset(double w, double l);
00328 virtual int GetNthWindowLevelPreset(int idx, double *w, double *l);
00329 virtual double* GetNthWindowLevelPreset(int idx);
00330 virtual void SetNthWindowLevelPresetComment(int idx, const char *comment);
00331 virtual const char* GetNthWindowLevelPresetComment(int idx);
00332
00333 // Description:
00334 // Mapping from a sliceidx within a volumeidx into a DICOM Instance UID
00335 // Some DICOM reader can populate this structure so that later on from a slice index
00336 // in a vtkImageData volume we can backtrack and find out which 2d slice it was coming from
00337 const char *GetInstanceUIDFromSliceID(int volumeidx, int sliceid);
00338 void SetInstanceUIDFromSliceID(int volumeidx, int sliceid, const char *uid);
00339
00340 // Description:
00341 // Provides the inverse mapping. Returns -1 if a slice for this uid is
00342 // not found.
00343 int GetSliceIDFromInstanceUID(int &volumeidx, const char *uid);
00344
00345 //BTX
00346 typedef enum {
00347     AXIAL = 0,
00348     CORONAL,
00349     SAGITTAL
00350 } OrientationType;
00351 //ETX
00352 int GetOrientationType(int volumeidx);
00353 void SetOrientationType(int volumeidx, int orientation);
00354 static const char *GetStringFromOrientationType(unsigned int type);
00355 */
00356 protected:
00357     vtkGDCMMedicalImageProperties();
00358     ~vtkGDCMMedicalImageProperties();
00359
00360 //BTX
00361 friend class vtkGDCMImageReader;
00362 friend class vtkGDCMImageReader2;
00363 friend class vtkGDCMImageWriter;
00364 void PushBackFile(gdcm::File const &f);
00365 gdcm::File const & GetFile(unsigned int t);
00366 //ETX
00367
00368 private:
00369     vtkGDCMMedicalImagePropertiesInternals *Internals;
00370
00371     vtkGDCMMedicalImageProperties(const vtkGDCMMedicalImageProperties&); // Not implemented.
00372     void operator=(const vtkGDCMMedicalImageProperties&); // Not implemented.
00373 };
00374
00375 #endif


```

11.613 vtkGDCMPolyDataReader.h File Reference

```
#include "vtkgdcmModule.h"
```

```
#include "vtkPolyDataAlgorithm.h"
```

Include dependency graph for vtkGDCMPolyDataReader.h:



Classes

- class [vtkGDCMPolyDataReader](#)

Namespaces

- namespace [gdcm](#)

11.614 vtkGDCMPolyDataReader.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013   =====*/
00014 // .NAME vtkGDCMPolyDataReader - read DICOM PolyData files (Contour Data...)
00015 // .SECTION Description
00016 // For now only support RTSTRUCT (RT Structure Set Storage)
00017 // .SECTION TODO
00018 // Need to do the same job for DVH Sequence/DVH Data...
00019 // .SECTION Warning
00020 // When using vtkGDCMPolyDataReader in conjunction with vtkGDCMImageReader
00021 // it is *required* that FileLowerLeft is set to ON as coordinate system
00022 // would be inconsistent in between the two data structures.
00023 //
00024 // .SECTION See Also

```

```

00025 // vtkGDCMImageReader vtkGDCMPolyDataWriter vtkRTStructSetProperties
00026
00027
00028 #ifndef VTKGDCMPOLYDATAREADER_H
00029 #define VTKGDCMPOLYDATAREADER_H
00030
00031 #include "vtkgdcmModule.h"
00032 #include "vtkPolyDataAlgorithm.h"
00033
00034 class vtkMedicalImageProperties;
00035 class vtkRTStructSetProperties;
00036 //BTX
00037 namespace gdcm { class Reader; }
00038 //ETX
00039 class VTKGDCM_EXPORT vtkGDCMPolyDataReader : public vtkPolyDataAlgorithm
00040 {
00041 public:
00042     static vtkGDCMPolyDataReader *New();
00043     vtkTypeMacro(vtkGDCMPolyDataReader,vtkPolyDataAlgorithm);
00044     virtual void PrintSelf(ostream& os, vtkIndent indent);
00045
00046     // Description:
00047     // Set/Get the filename of the file to be read
00048     vtkSetStringMacro(FileName);
00049     vtkGetStringMacro(FileName);
00050
00051     // Description:
00052     // Get the medical image properties object
00053     vtkGetObjectMacro(MedicalImageProperties, vtkMedicalImageProperties);
00054
00055     vtkGetObjectMacro(RTStructSetProperties, vtkRTStructSetProperties);
00056
00057 protected:
00058     vtkGDCMPolyDataReader();
00059     ~vtkGDCMPolyDataReader();
00060
00061     char *FileName;
00062     vtkMedicalImageProperties *MedicalImageProperties;
00063     vtkRTStructSetProperties *RTStructSetProperties;
00064 //BTX
00065     void FillMedicalImageInformation(const gdcm::Reader &reader);
00066 //ETX
00067
00068     int RequestData(vtkInformation *, vtkInformationVector **, vtkInformationVector *);
00069     int RequestInformation(
00070         vtkInformation *vtkNotUsed(request),
00071         vtkInformationVector **vtkNotUsed(inputVector),
00072         vtkInformationVector *outputVector);
00073 //BTX
00074     int RequestInformation_RTStructureSetStorage(gdcm::Reader const &reader);
00075     int RequestData_RTStructureSetStorage(gdcm::Reader const &reader, vtkInformationVector *outputVector);
00076     int RequestInformation_HemodynamicWaveformStorage(gdcm::Reader const &reader);
00077     int RequestData_HemodynamicWaveformStorage(gdcm::Reader const &reader, vtkInformationVector
00078         *outputVector);
00079 //ETX
00080 private:
00081     vtkGDCMPolyDataReader(const vtkGDCMPolyDataReader&); // Not implemented.
00082     void operator=(const vtkGDCMPolyDataReader&); // Not implemented.
00083 };
00084
00085 #endif

```


11.615 vtkGDCMPolyDataWriter.h File Reference

```

#include "vtkgdcmModule.h"
#include "vtkPolyDataWriter.h"
#include "vtkStringArray.h"
#include "vtkStdString.h"

```

Include dependency graph for vtkGDCMPolyDataWriter.h:



Classes

- class [vtkGDCMPolyDataWriter](#)

Namespaces

- namespace [gdcM](#)

11.616 vtkGDCMPolyDataWriter.h

[Go to the documentation of this file.](#)

```

00001  /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcM.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013  =====*/
00014  // .NAME vtkGDCMPolyDataWriter - writer DICOM PolyData files (Contour Data...)
00015  // .SECTION Description
00016  // For now only support RTSTRUCT (RT Structure Set Storage)
00017  // .SECTION TODO
00018  // Need to do the same job for DVH Sequence/DVH Data...
00019  // .SECTION Warning
00020  //
00021  // .SECTION See Also
00022  // vtkGDCMImageReader vtkGDCMPolyDataReader vtkRTStructSetProperties
00023
00024
00025  #ifndef VTKGDCMPOLYDATAWRITER_H
00026  #define VTKGDCMPOLYDATAWRITER_H
00027
00028  #include "vtkgdcModule.h"
00029  #include "vtkPolyDataWriter.h"
00030  #include "vtkStringArray.h"
00031  #include "vtkStdString.h"
00032
00033
00034  class vtkMedicalImageProperties;
00035  class vtkRTStructSetProperties;
00036  //BTX
00037  namespace gdcM { class File; }

```

```

00038 //ETX
00039 class VTKGDCM_EXPORT vtkGDCMPolyDataWriter : public vtkPolyDataWriter
00040 {
00041 public:
00042     static vtkGDCMPolyDataWriter *New();
00043     vtkTypeMacro(vtkGDCMPolyDataWriter,vtkPolyDataWriter);
00044     virtual void PrintSelf(ostream& os, vtkIndent indent);
00045
00046     // Description:
00047     // Set/Get the filename of the file to be read
00048     //   vtkSetStringMacro(FileName);
00049     //   vtkGetStringMacro(FileName);
00050
00051     // Description:
00052     // Get the medical image properties object
00053     //   vtkGetObjectMacro(MedicalImageProperties, vtkMedicalImageProperties);
00054     virtual void SetMedicalImageProperties(vtkMedicalImageProperties *pd);
00055
00056     virtual void SetRTStructSetProperties(vtkRTStructSetProperties *pd);
00057
00058
00059     //this function will initialize the contained rtstructset with
00060     //the inputs of the writer and the various extra information
00061     //necessary for writing a complete rtstructset.
00062     //NOTE: inputs must be set BEFORE calling this function!
00063     //NOTE: the number of outputs for the appendpolydata MUST MATCH the ROI vectors!
00064     void InitializeRTStructSet(vtkStdString inDirectory,
00065         vtkStdString inStructLabel, vtkStdString inStructName,
00066         vtkStringArray* inROINames,
00067         vtkStringArray* inROIAlgorithmName,
00068         vtkStringArray* inROIType);
00069
00070     // make parent class public...
00071     void SetNumberOfInputPorts(int n);
00072
00073 protected:
00074     vtkGDCMPolyDataWriter();
00075     ~vtkGDCMPolyDataWriter();
00076
00077     vtkMedicalImageProperties *MedicalImageProperties;
00078     vtkRTStructSetProperties *RTStructSetProperties;
00079
00080     void WriteData();
00081 //BTX
00082     void WriteRTSTRUCTInfo(gdcm::File &file);
00083     void WriteRTSTRUCTData(gdcm::File &file, int num);
00084 //ETX
00085
00086 private:
00087     vtkGDCMPolyDataWriter(const vtkGDCMPolyDataWriter&); // Not implemented.
00088     void operator=(const vtkGDCMPolyDataWriter&); // Not implemented.
00089 };
00090
00091 #endif

```


11.617 vtkGDCMTesting.h File Reference

```

#include "vtkgdcmModule.h"
#include "vtkObject.h"

```

Include dependency graph for vtkGDCMTesting.h:



Classes

- class [vtkGDCMTesting](#)

11.618 vtkGDCMTesting.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013  =====*/
00014 // .NAME vtkGDCMTesting - GDCM Testing
00015 // .SECTION Description
00016 // GDCM Testing
00017
00018 // .SECTION See Also
00019 // vtkTesting
00020
00021 #ifndef VTKGDCMTESTING_H
00022 #define VTKGDCMTESTING_H
00023
00024 #include "vtkgdcModule.h"
00025 #include "vtkObject.h"
00026
00027 class VTKGDCM_EXPORT vtkGDCMTesting : public vtkObject
00028 {
00029 public:
00030   static vtkGDCMTesting *New();
00031   vtkTypeMacro(vtkGDCMTesting,vtkObject);
00032   void PrintSelf(ostream& os, vtkIndent indent);
00033
00034   static const char *GetVTKDataRoot();
00035   static const char *GetGDCMDataRoot();
00036
00037 //BTX
00038   typedef const char* const (*MD5MetaImagesType)[3];
00039   static const char * const * GetMD5MetaImage(unsigned int file);

```

```

00040 //ETX
00041 static unsigned int GetNumberOfMD5MetaImages();
00042
00043 static const char * GetMHDMD5FromFile(const char *filepath);
00044 static const char * GetRAWMD5FromFile(const char *filepath);
00045
00046 protected:
00047   vtkGDCMTesting();
00048   ~vtkGDCMTesting();
00049
00050 private:
00051   vtkGDCMTesting(const vtkGDCMTesting&); // Not implemented.
00052   void operator=(const vtkGDCMTesting&); // Not implemented.
00053 };
00054
00055 #endif

```


11.619 vtkGDCMThreadedImageReader.h File Reference

```

#include "vtkgdcmModule.h"
#include "vtkGDCMImageReader.h"
#include "vtkVersion.h"

```

Include dependency graph for vtkGDCMThreadedImageReader.h:



Classes

- class [vtkGDCMThreadedImageReader](#)

11.620 vtkGDCMThreadedImageReader.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.

```



```

00012
00013 =====*/
00014 // .NAME vtkGDCMThreadedImageReader - read DICOM files with multiple threads
00015 // .SECTION Description
00016 // vtkGDCMThreadedImageReader is a source object that reads some DICOM files
00017 // This reader is threaded. Meaning that on a multiple core CPU with N cpu, it will
00018 // read approx N times faster than when reading in a single thread.
00019 //
00020 // .SECTION Warning: Advanced users only. Do not use this class in the general case,
00021 // you have to understand how physically medium works first (sequential reading for
00022 // instance) before playing with this class
00023 //
00024 // .SECTION Implementation note: when FileLowerLeft is set to on the image is not flipped
00025 // upside down as VTK would expect, use this option only if you know what you are doing
00026 //
00027 // .SECTION FIXME: need to implement the other mode where FileLowerLeft is set to OFF
00028 //
00029 // .SECTION FIXME: you need to call SetFileName when reading a volume file (multiple slices DICOM)
00030 // since SetFileNames expect each single file to be single slice (see parent class)
00031 //
00032 // .SECTION BUG: you should really consider using vtkGDCMThreadedImageReader2 instead !
00033 //
00034 // .SECTION See Also
00035 // vtkMedicalImageReader2 vtkMedicalImageProperties vtkGDCMThreadedImageReader2
00036
00037 #ifndef VTKGDCMTHREADEDIMAGEREADER_H
00038 #define VTKGDCMTHREADEDIMAGEREADER_H
00039
00040 #include "vtkgdcmModule.h"
00041 #include "vtkGDCMImageReader.h"
00042 #include "vtkVersion.h"
00043
00044 class VTKGDCM_EXPORT vtkGDCMThreadedImageReader : public vtkGDCMImageReader
00045 {
00046 public:
00047     static vtkGDCMThreadedImageReader *New();
00048     vtkTypeMacro(vtkGDCMThreadedImageReader,vtkGDCMImageReader);
00049     virtual void PrintSelf(ostream& os, vtkIndent indent);
00050
00051     // Description:
00052     // Explicitly set the Rescale Intercept (0028,1052)
00053     vtkSetMacro(Shift,double);
00054
00055     // Description:
00056     // Explicitly get/set the Rescale Slope (0028,1053)
00057     vtkSetMacro(Scale,double);
00058
00059     // Description:
00060     // Determine whether or not reader should use value from Shift/Scale
00061     // Default is 1
00062     vtkSetMacro(UseShiftScale,int);
00063     vtkGetMacro(UseShiftScale,int);
00064     vtkBooleanMacro(UseShiftScale,int);
00065
00066     // Within this class this is allowed to set the Number of Overlays from outside
00067     //vtkSetMacro(NumberOfOverlays,int);
00068
00069 protected:
00070     vtkGDCMThreadedImageReader();
00071     ~vtkGDCMThreadedImageReader();
00072
00073     #if (VTK_MAJOR_VERSION >= 5) || ( VTK_MAJOR_VERSION == 4 && VTK_MINOR_VERSION > 5 )
00074     int RequestInformation(vtkInformation *request,
00075                           vtkInformationVector **inputVector,
00076                           vtkInformationVector *outputVector);
00077     int RequestData(vtkInformation *request,
00078                    vtkInformationVector **inputVector,
00079                    vtkInformationVector *outputVector);
00080     #else /*(VTK_MAJOR_VERSION >= 5) || ( VTK_MAJOR_VERSION == 4 && VTK_MINOR_VERSION > 5 )*/
00081     void ExecuteInformation();
00082     void ExecuteData(vtkDataObject *out);
00083     #endif /*(VTK_MAJOR_VERSION >= 5) || ( VTK_MAJOR_VERSION == 4 && VTK_MINOR_VERSION > 5 )*/
00084
00085     void ReadFiles(unsigned int nfiles, const char *filenames[]);
00086     void RequestDataCompat();
00087
00088 private:
00089     vtkGDCMThreadedImageReader(const vtkGDCMThreadedImageReader&); // Not implemented.
00090     void operator=(const vtkGDCMThreadedImageReader&); // Not implemented.
00091
00092     int UseShiftScale;

```

```

00093 };
00094
00095 #endif

```


11.621 vtkGDCMThreadedImageReader2.h File Reference

```

#include "vtkgdcModule.h"
#include "vtkThreadedImageAlgorithm.h"

```

Include dependency graph for vtkGDCMThreadedImageReader2.h:



Classes

- class [vtkGDCMThreadedImageReader2](#)

11.622 vtkGDCMThreadedImageReader2.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdc.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013   =====*/
00014 // .NAME vtkGDCMThreadedImageReader2 - read DICOM files with multiple threads
00015 // .SECTION Description
00016 // vtkGDCMThreadedImageReader2 is a source object that reads some DICOM files
00017 // This reader is threaded. Meaning that on a multiple core CPU with N cpu, it will
00018 // read approx N times faster than when reading in a single thread assuming the IO is
00019 // not a bottleneck operation.
00020 // If looking for a single threaded class see: vtkGDCMImageReader
00021 //
00022 // .SECTION Warning: Advanced users only. Do not use this class in the general case,
00023 // you have to understand how physically medium works first (sequential reading for
00024 // instance) before playing with this class

```

```

00025 //
00026 // .SECTION Implementation note: when FileLowerLeft is set to on the image is not flipped
00027 // upside down as VTK would expect, use this option only if you know what you are doing
00028 //
00029 // .SECTION FIXME: need to implement the other mode where FileLowerLeft is set to OFF
00030 //
00031 // .SECTION FIXME: need to implement reading of series of 3D files
00032 //
00033 // .SECTION Implementation note: this class is meant to supersede vtkGDCMThreadedImageReader
00034 // because it had support for ProgressEvent support even from python layer. There is a
00035 // subtle trick down in the threading mechanism in VTK were the main thread (talking to the
00036 // python interpreter) is also part of the execution process (and the N-1 other thread
00037 // are just there to execute the remaining of ThreadedRequestData), this separation into
00038 // two types of thread is necessary to achieve a working implementation of UpdateProgress
00039 //
00040 // .SECTION See Also
00041 // vtkMedicalImageReader2 vtkMedicalImageProperties vtkGDCMImageReader
00042 //
00043 #ifndef VTKGDCMTHREADEDIMAGEREADER2_H
00044 #define VTKGDCMTHREADEDIMAGEREADER2_H
00045 //
00046 #include "vtkgdcModule.h"
00047 #include "vtkThreadedImageAlgorithm.h"
00048 //
00049 class vtkStringArray;
00050 class VTKGDCM_EXPORT vtkGDCMThreadedImageReader2 : public vtkThreadedImageAlgorithm
00051 {
00052 public:
00053     static vtkGDCMThreadedImageReader2 *New();
00054     vtkTypeMacro(vtkGDCMThreadedImageReader2,vtkThreadedImageAlgorithm);
00055     virtual void PrintSelf(ostream& os, vtkIndent indent);
00056 //
00057     vtkGetMacro(FileLowerLeft,int);
00058     vtkSetMacro(FileLowerLeft,int);
00059     vtkBooleanMacro(FileLowerLeft,int);
00060 //
00061     vtkGetMacro(NumberOfOverlays,int);
00062 //
00063     vtkSetMacro(DataScalarType,int);
00064     vtkGetMacro(DataScalarType,int);
00065 //
00066     vtkSetMacro(NumberOfScalarComponents,int);
00067     vtkGetMacro(NumberOfScalarComponents,int);
00068 //
00069     vtkGetMacro(LoadOverlays,int);
00070     vtkSetMacro(LoadOverlays,int);
00071     vtkBooleanMacro(LoadOverlays,int);
00072 //
00073     vtkSetVector6Macro(DataExtent,int);
00074     vtkGetVector6Macro(DataExtent,int);
00075 //
00076     vtkSetVector3Macro(DataOrigin,double);
00077     vtkGetVector3Macro(DataOrigin,double);
00078 //
00079     vtkSetVector3Macro(DataSpacing,double);
00080     vtkGetVector3Macro(DataSpacing,double);
00081 //
00082     //vtkGetStringMacro(FileName);
00083     //vtkSetStringMacro(FileName);
00084     virtual const char *GetFileName(int i = 0);
00085     virtual void SetFileName(const char *filename);
00086 //
00087     virtual void SetFileNames(vtkStringArray*);
00088     vtkGetObjectMacro(FileNames, vtkStringArray);
00089 //
00090     int SplitExtent(int splitExt[6], int startExt[6],
00091                     int num, int total);
00092 //
00093     // Description:
00094     // Explicitly set the Rescale Intercept (0028,1052)
00095     vtkSetMacro(Shift,double);
00096     vtkGetMacro(Shift,double);
00097 //
00098     // Description:
00099     // Explicitly get/set the Rescale Slope (0028,1053)
00100     vtkSetMacro(Scale,double);
00101     vtkGetMacro(Scale,double);
00102 //
00103     // Description:
00104     // Determine whether or not reader should use value from Shift/Scale
00105     // Default is 1

```

```

00106     vtkSetMacro(UseShiftScale,int);
00107     vtkGetMacro(UseShiftScale,int);
00108     vtkBooleanMacro(UseShiftScale,int);
00109
00110 protected:
00111     vtkGDCMThreadedImageReader2();
00112     ~vtkGDCMThreadedImageReader2();
00113
00114     int RequestInformation(vtkInformation *request,
00115                           vtkInformationVector **inputVector,
00116                           vtkInformationVector *outputVector);
00117
00118 protected:
00119     void ThreadedRequestData (
00120         vtkInformation * request,
00121         vtkInformationVector** inputVector,
00122         vtkInformationVector * outputVector,
00123         vtkImageData ***inData,
00124         vtkImageData **outData,
00125         int outExt[6], int id);
00126
00127 private:
00128     int FileLowerLeft;
00129     char *FileName;
00130     vtkStringArray *FileNames;
00131     int LoadIconImage;
00132     int DataExtent[6];
00133     int LoadOverlays;
00134     int NumberOfOverlays;
00135     int DataScalarType;
00136
00137     int NumberOfScalarComponents;
00138     double DataSpacing[3];
00139     double DataOrigin[3];
00140     int IconImageDataExtent[6];
00141
00142     double Shift;
00143     double Scale;
00144     int UseShiftScale;
00145
00146 private:
00147     vtkGDCMThreadedImageReader2(const vtkGDCMThreadedImageReader2&); // Not implemented.
00148     void operator=(const vtkGDCMThreadedImageReader2&); // Not implemented.
00149 };
00150
00151 #endif

```


11.623 vtkImageColorViewer.h File Reference

```

#include "vtkgdcmModule.h"
#include "vtkObject.h"
#include "vtkVersion.h"

```

Include dependency graph for vtkImageColorViewer.h:



Classes

- class [vtkImageColorViewer](#)

11.624 vtkImageColorViewer.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcms.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 // .NAME vtkImageColorViewer - Display a 2D image.
00015 // .SECTION Description
00016 // vtkImageColorViewer is a convenience class for displaying a 2D image. It
00017 // packages up the functionality found in vtkRenderWindow, vtkRenderer,
00018 // vtkImageActor and vtkImageMapToWindowLevelColors into a single easy to use
00019 // class. This class also creates an image interactor style
00020 // (vtkInteractorStyleImage) that allows zooming and panning of images, and
00021 // supports interactive window/level operations on the image. Note that
00022 // vtkImageColorViewer is simply a wrapper around these classes.
00023 //
00024 // vtkImageColorViewer uses the 3D rendering and texture mapping engine
00025 // to draw an image on a plane. This allows for rapid rendering,
00026 // zooming, and panning. The image is placed in the 3D scene at a
00027 // depth based on the z-coordinate of the particular image slice. Each
00028 // call to SetSlice() changes the image data (slice) displayed AND
00029 // changes the depth of the displayed slice in the 3D scene. This can
00030 // be controlled by the AutoAdjustCameraClippingRange ivar of the
00031 // InteractorStyle member.
00032 //
00033 // It is possible to mix images and geometry, using the methods:
00034 //
00035 // viewer->SetInput( myImage );
00036 // viewer->GetRenderer()->AddActor( myActor );
00037 //
00038 // This can be used to annotate an image with a PolyData of "edges" or
00039 // or highlight sections of an image or display a 3D isosurface
00040 // with a slice from the volume, etc. Any portions of your geometry
00041 // that are in front of the displayed slice will be visible; any
00042 // portions of your geometry that are behind the displayed slice will
00043 // be obscured. A more general framework (with respect to viewing
00044 // direction) for achieving this effect is provided by the
00045 // vtkImagePlaneWidget .
00046 //
00047 // Note that pressing 'r' will reset the window/level and pressing
00048 // shift+'r' or control+'r' will reset the camera.
00049 //
00050 // .SECTION See Also
00051 // vtkRenderWindow vtkRenderer vtkImageActor vtkImageMapToWindowLevelColors
00052
00053 #ifndef VTKIMAGECOLORVIEWER_H
00054 #define VTKIMAGECOLORVIEWER_H
00055
00056 #include "vtkgdcModule.h"
00057 #include "vtkObject.h"
00058 #include "vtkVersion.h"
00059
00060 class vtkAlgorithm;
00061 class vtkAlgorithmOutput;
00062 class vtkImageActor;
00063 class vtkImageData;
00064 class vtkImageMapToWindowLevelColors2;
00065 class vtkInformation;
00066 class vtkInteractorStyleImage;

```

```

00067 class vtkRenderWindow;
00068 class vtkRenderer;
00069 class vtkRenderWindowInteractor;
00070 class vtkPolyData;
00071
00072 class VTKGDCM_EXPORT vtkImageColorViewer : public vtkObject
00073 {
00074 public:
00075     static vtkImageColorViewer *New();
00076     vtkTypeMacro(vtkImageColorViewer,vtkObject);
00077     void PrintSelf(ostream& os, vtkIndent indent);
00078
00079     // Description:
00080     // Get the name of rendering window.
00081     virtual const char *GetWindowName();
00082
00083     // Description:
00084     // Render the resulting image.
00085     virtual void Render(void);
00086
00087     // Description:
00088     // Set/Get the input image to the viewer.
00089     #if (VTK_MAJOR_VERSION >= 6)
00090     virtual void SetInputData(vtkImageData *in);
00091     #else
00092     virtual void SetInput(vtkImageData *in);
00093     #endif
00094     virtual vtkImageData *GetInput();
00095     virtual void SetInputConnection(vtkAlgorithmOutput* input);
00096     virtual void AddInputConnection(vtkAlgorithmOutput* input);
00097     virtual void AddInput(vtkImageData * input);
00098     //virtual void AddInput(vtkPolyData * input);
00099
00100     double GetOverlayVisibility();
00101     void SetOverlayVisibility(double vis);
00102
00103     // Description:
00104     // Set/get the slice orientation
00105     //BTX
00106     enum
00107     {
00108         SLICE_ORIENTATION_YZ = 0,
00109         SLICE_ORIENTATION_XZ = 1,
00110         SLICE_ORIENTATION_XY = 2
00111     };
00112     //ETX
00113     vtkGetMacro(SliceOrientation, int);
00114     virtual void SetSliceOrientation(int orientation);
00115     virtual void SetSliceOrientationToXY()
00116     { this->SetSliceOrientation(vtkImageColorViewer::SLICE_ORIENTATION_XY); };
00117     virtual void SetSliceOrientationToYZ()
00118     { this->SetSliceOrientation(vtkImageColorViewer::SLICE_ORIENTATION_YZ); };
00119     virtual void SetSliceOrientationToXZ()
00120     { this->SetSliceOrientation(vtkImageColorViewer::SLICE_ORIENTATION_XZ); };
00121
00122     // Description:
00123     // Set/Get the current slice to display (depending on the orientation
00124     // this can be in X, Y or Z).
00125     vtkGetMacro(Slice, int);
00126     virtual void SetSlice(int s);
00127
00128     // Description:
00129     // Update the display extent manually so that the proper slice for the
00130     // given orientation is displayed. It will also try to set a
00131     // reasonable camera clipping range.
00132     // This method is called automatically when the Input is changed, but
00133     // most of the time the input of this class is likely to remain the same,
00134     // i.e. connected to the output of a filter, or an image reader. When the
00135     // input of this filter or reader itself is changed, an error message might
00136     // be displayed since the current display extent is probably outside
00137     // the new whole extent. Calling this method will ensure that the display
00138     // extent is reset properly.
00139     virtual void UpdateDisplayExtent();
00140
00141     // Description:
00142     // Return the minimum and maximum slice values (depending on the orientation
00143     // this can be in X, Y or Z).
00144     virtual int GetSliceMin();
00145     virtual int GetSliceMax();
00146     virtual void GetSliceRange(int range[2])
00147     { this->GetSliceRange(range[0], range[1]); }

```

```

00148     virtual void GetSliceRange(int &min, int &max);
00149     virtual int* GetSliceRange();
00150
00151     // Description:
00152     // Set window and level for mapping pixels to colors.
00153     virtual double GetColorWindow();
00154     virtual double GetColorLevel();
00155     virtual void SetColorWindow(double s);
00156     virtual void SetColorLevel(double s);
00157
00158     // Description:
00159     // These are here when using a Tk window.
00160     virtual void SetDisplayId(void *a);
00161     virtual void SetWindowId(void *a);
00162     virtual void SetParentId(void *a);
00163
00164     // Description:
00165     // Set/Get the position in screen coordinates of the rendering window.
00166     virtual int* GetPosition();
00167     virtual void SetPosition(int a,int b);
00168     virtual void SetPosition(int a[2]) { this->SetPosition(a[0],a[1]); }
00169
00170     // Description:
00171     // Set/Get the size of the window in screen coordinates in pixels.
00172     virtual int* GetSize();
00173     virtual void SetSize(int a, int b);
00174     virtual void SetSize(int a[2]) { this->SetSize(a[0],a[1]); }
00175
00176     // Description:
00177     // Get the internal render window, renderer, image actor, and
00178     // image map instances.
00179     vtkGetObjectMacro(RenderWindow,vtkRenderWindow);
00180     vtkGetObjectMacro(Renderer, vtkRenderer);
00181     vtkGetObjectMacro(ImageActor,vtkImageActor);
00182     vtkGetObjectMacro(WindowLevel,vtkImageMapToWindowLevelColors2);
00183     vtkGetObjectMacro(InteractorStyle,vtkInteractorStyleImage);
00184
00185     // Description:
00186     // Set your own renderwindow and renderer
00187     virtual void SetRenderWindow(vtkRenderWindow *arg);
00188     virtual void SetRenderer(vtkRenderer *arg);
00189
00190     // Description:
00191     // Attach an interactor for the internal render window.
00192     virtual void SetupInteractor(vtkRenderWindowInteractor*);
00193
00194     // Description:
00195     // Create a window in memory instead of on the screen. This may not
00196     // be supported for every type of window and on some windows you may
00197     // need to invoke this prior to the first render.
00198     virtual void SetOffScreenRendering(int);
00199     virtual int GetOffScreenRendering();
00200     vtkBooleanMacro(OffScreenRendering,int);
00201
00202 protected:
00203     vtkImageColorViewer();
00204     ~vtkImageColorViewer();
00205
00206     virtual void InstallPipeline();
00207     virtual void UnInstallPipeline();
00208
00209     vtkImageMapToWindowLevelColors2 *WindowLevel;
00210     vtkRenderWindow *RenderWindow;
00211     vtkRenderer *Renderer;
00212     vtkImageActor *ImageActor;
00213     vtkImageActor *OverlayImageActor;
00214     vtkRenderWindowInteractor *Interactor;
00215     vtkInteractorStyleImage *InteractorStyle;
00216
00217     int SliceOrientation;
00218     int FirstRender;
00219     int Slice;
00220
00221     virtual void UpdateOrientation();
00222
00223 #if (VTK_MAJOR_VERSION >= 6)
00224     vtkAlgorithm* GetInputAlgorithm();
00225     vtkInformation* GetInputInformation();
00226 #endif
00227
00228     friend class vtkImageColorViewerCallback;

```

```

00229
00230 private:
00231     vtkImageColorViewer(const vtkImageColorViewer&); // Not implemented.
00232     void operator=(const vtkImageColorViewer&); // Not implemented.
00233 };
00234
00235 #endif

```


11.625 vtkImageMapToColors16.h File Reference

```

#include "vtkgdcmModule.h"
#include "vtkThreadedImageAlgorithm.h"

```

Include dependency graph for vtkImageMapToColors16.h:



Classes

- class [vtkImageMapToColors16](#)

11.626 vtkImageMapToColors16.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003     Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005     Copyright (c) 2006-2011 Mathieu Malaterre
00006     All rights reserved.
00007     See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009     This software is distributed WITHOUT ANY WARRANTY; without even
00010     the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011     PURPOSE. See the above copyright notice for more information.
00012
00013     =====*/
00014 /*=====
00015
00016     Portions of this file are subject to the VTK Toolkit Version 3 copyright.
00017
00018     Program:   Visualization Toolkit
00019     Module:    $RCSfile: vtkImageMapToColors16.h,v $
00020

```



```

00021 Copyright (c) Ken Martin, Will Schroeder, Bill Lorensen
00022 All rights reserved.
00023 See Copyright.txt or http://www.kitware.com/Copyright.htm for details.
00024
00025 This software is distributed WITHOUT ANY WARRANTY; without even
00026 the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00027 PURPOSE. See the above copyright notice for more information.
00028
00029 =====*/
00030 // .NAME vtkImageMapToColors16 - map the input image through a lookup table
00031 // .SECTION Description
00032 // The vtkImageMapToColors16 filter will take an input image of any valid
00033 // scalar type, and map the first component of the image through a
00034 // lookup table. The result is an image of type VTK_UNSIGNED_CHAR.
00035 // If the lookup table is not set, or is set to NULL, then the input
00036 // data will be passed through if it is already of type VTK_UNSIGNED_CHAR.
00037
00038 // .SECTION See Also
00039 // vtkLookupTable vtkScalarsToColors
00040
00041 #ifndef VTKIMAGEMAPTOCOLORS16_H
00042 #define VTKIMAGEMAPTOCOLORS16_H
00043
00044
00045 #include "vtkgdcmModule.h"
00046 #include "vtkThreadedImageAlgorithm.h"
00047
00048 class vtkScalarsToColors;
00049
00050 class VTKGDCM_EXPORT vtkImageMapToColors16 : public vtkThreadedImageAlgorithm
00051 {
00052 public:
00053     static vtkImageMapToColors16 *New();
00054     vtkTypeMacro(vtkImageMapToColors16,vtkThreadedImageAlgorithm);
00055     void PrintSelf(ostream& os, vtkIndent indent);
00056
00057     // Description:
00058     // Set the lookup table.
00059     virtual void SetLookupTable(vtkScalarsToColors*);
00060     vtkGetObjectMacro(LookupTable,vtkScalarsToColors);
00061
00062     // Description:
00063     // Set the output format, the default is RGBA.
00064     vtkSetMacro(OutputFormat,int);
00065     vtkGetMacro(OutputFormat,int);
00066     void SetOutputFormatToRGBA() { this->OutputFormat = VTK_RGBA; };
00067     void SetOutputFormatToRGB() { this->OutputFormat = VTK_RGB; };
00068     void SetOutputFormatToLuminanceAlpha() { this->OutputFormat = VTK_LUMINANCE_ALPHA; };
00069     void SetOutputFormatToLuminance() { this->OutputFormat = VTK_LUMINANCE; };
00070
00071     // Description:
00072     // Set the component to map for multi-component images (default: 0)
00073     vtkSetMacro(ActiveComponent,int);
00074     vtkGetMacro(ActiveComponent,int);
00075
00076     // Description:
00077     // Use the alpha component of the input when computing the alpha component
00078     // of the output (useful when converting monochrome+alpha data to RGBA)
00079     vtkSetMacro(PassAlphaToOutput,int);
00080     vtkBooleanMacro(PassAlphaToOutput,int);
00081     vtkGetMacro(PassAlphaToOutput,int);
00082
00083     // Description:
00084     // We need to check the modified time of the lookup table too.
00085     #ifndef VTK_HAS_MTIME_TYPE
00086     virtual vtkMTimeType GetMTime();
00087     #else
00088     virtual unsigned long GetMTime();
00089     #endif
00090
00091 protected:
00092     vtkImageMapToColors16();
00093     ~vtkImageMapToColors16();
00094
00095     virtual int RequestInformation (vtkInformation *, vtkInformationVector **, vtkInformationVector *);
00096
00097     void ThreadedRequestData(vtkInformation *request,
00098                             vtkInformationVector **inputVector,
00099                             vtkInformationVector *outputVector,
00100                             vtkImageData ***inData, vtkImageData **outData,
00101                             int extent[6], int id);

```

```

00102
00103     virtual int RequestData(vtkInformation *request,
00104                             vtkInformationVector **inputVector,
00105                             vtkInformationVector *outputVector);
00106
00107     vtkScalarsToColors *LookupTable;
00108     int OutputFormat;
00109
00110     int ActiveComponent;
00111     int PassAlphaToOutput;
00112
00113     int DataWasPassed;
00114 private:
00115     vtkImageMapToColors16(const vtkImageMapToColors16&); // Not implemented.
00116     void operator=(const vtkImageMapToColors16&); // Not implemented.
00117 };
00118
00119 #endif

```


11.627 vtkImageMapToWindowLevelColors2.h File Reference

```

#include "vtkgdcmModule.h"
#include "vtkImageMapToColors.h"

```

Include dependency graph for vtkImageMapToWindowLevelColors2.h:



Classes

- class [vtkImageMapToWindowLevelColors2](#)

11.628 vtkImageMapToWindowLevelColors2.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003     Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005     Copyright (c) 2006-2011 Mathieu Malaterre
00006     All rights reserved.
00007     See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008

```

```

00009      This software is distributed WITHOUT ANY WARRANTY; without even
00010      the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011      PURPOSE. See the above copyright notice for more information.
00012
00013      =====*/
00014  /*=====
00015
00016      Portions of this file are subject to the VTK Toolkit Version 3 copyright.
00017
00018      Program:   Visualization Toolkit
00019      Module:    $RCSfile: vtkImageMapToWindowLevelColors2.h,v $
00020
00021      Copyright (c) Ken Martin, Will Schroeder, Bill Lorensen
00022      All rights reserved.
00023      See Copyright.txt or http://www.kitware.com/Copyright.htm for details.
00024
00025      This software is distributed WITHOUT ANY WARRANTY; without even
00026      the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00027      PURPOSE. See the above copyright notice for more information.
00028
00029      =====*/
00030  // .NAME vtkImageMapToWindowLevelColors2 - map the input image through a lookup table and window / level
    it
00031  // .SECTION Description
00032  // The vtkImageMapToWindowLevelColors2 filter will take an input image of any
00033  // valid scalar type, and map the first component of the image through a
00034  // lookup table. This resulting color will be modulated with value obtained
00035  // by a window / level operation. The result is an image of type
00036  // VTK_UNSIGNED_CHAR. If the lookup table is not set, or is set to NULL, then
00037  // the input data will be passed through if it is already of type
00038  // UNSIGNED_CHAR.
00039  //
00040  // .SECTION See Also
00041  // vtkLookupTable vtkScalarsToColors
00042
00043  #ifndef VTKIMAGEMAPTOWINDOWLEVELCOLORS2_H
00044  #define VTKIMAGEMAPTOWINDOWLEVELCOLORS2_H
00045
00046  #include "vtkgdcmModule.h"
00047  #include "vtkImageMapToColors.h"
00048
00049  class VTKGDCM_EXPORT vtkImageMapToWindowLevelColors2 : public vtkImageMapToColors
00050  {
00051  public:
00052      static vtkImageMapToWindowLevelColors2 *New();
00053      vtkTypeMacro(vtkImageMapToWindowLevelColors2,vtkImageMapToColors);
00054      void PrintSelf(ostream& os, vtkIndent indent);
00055
00056      // Description:
00057      // Set / Get the Window to use -> modulation will be performed on the
00058      // color based on (S - (L - W/2))/W where S is the scalar value, L is
00059      // the level and W is the window.
00060      vtkSetMacro( Window, double );
00061      vtkGetMacro( Window, double );
00062
00063      // Description:
00064      // Set / Get the Level to use -> modulation will be performed on the
00065      // color based on (S - (L - W/2))/W where S is the scalar value, L is
00066      // the level and W is the window.
00067      vtkSetMacro( Level, double );
00068      vtkGetMacro( Level, double );
00069
00070  protected:
00071      vtkImageMapToWindowLevelColors2();
00072      ~vtkImageMapToWindowLevelColors2();
00073
00074      virtual int RequestInformation (vtkInformation *, vtkInformationVector **, vtkInformationVector *);
00075      void ThreadedRequestData(vtkInformation *request,
00076                              vtkInformationVector **inputVector,
00077                              vtkInformationVector *outputVector,
00078                              vtkImageData **inData, vtkImageData **outData,
00079                              int extent[6], int id);
00080      virtual int RequestData(vtkInformation *request,
00081                              vtkInformationVector **inputVector,
00082                              vtkInformationVector *outputVector);
00083
00084      double Window;
00085      double Level;
00086
00087  private:
00088      vtkImageMapToWindowLevelColors2(const vtkImageMapToWindowLevelColors2&); // Not implemented.

```

```

00089 void operator=(const vtkImageMapToWindowLevelColors2&); // Not implemented.
00090 };
00091
00092 #endif


```

11.629 vtkImagePlanarComponentsToComponents.h File Reference

```
#include "vtkgdcmModule.h"
```

```
#include "vtkImageAlgorithm.h"
```

Include dependency graph for vtkImagePlanarComponentsToComponents.h:



Classes

- class [vtkImagePlanarComponentsToComponents](#)

11.630 vtkImagePlanarComponentsToComponents.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003 Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005 Copyright (c) 2006-2011 Mathieu Malaterre
00006 All rights reserved.
00007 See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009 This software is distributed WITHOUT ANY WARRANTY; without even
00010 the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011 PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 /*=====
00015
00016 Portions of this file are subject to the VTK Toolkit Version 3 copyright.
00017
00018 Program: Visualization Toolkit
00019 Module: $RCSfile: vtkImagePlanarComponentsToComponents.h,v $
00020
00021 Copyright (c) Ken Martin, Will Schroeder, Bill Lorensen
00022 All rights reserved.

```

```

00023 See Copyright.txt or http://www.kitware.com/Copyright.htm for details.
00024
00025 This software is distributed WITHOUT ANY WARRANTY; without even
00026 the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00027 PURPOSE. See the above copyright notice for more information.
00028
00029 =====*/
00030 // .NAME vtkImagePlanarComponentsToComponents - Converts planar comp to pixel comp
00031 // .SECTION Description
00032
00033 // .SECTION See Also
00034 // TODO: Can I make this filter threaded ?
00035 // TODO: How do I handle the VTK-flipping (FileLowerLeft)?
00036
00037 #ifndef VTKIMAGEPLANARCOMPONENTSTOCOMPONENTS_H
00038 #define VTKIMAGEPLANARCOMPONENTSTOCOMPONENTS_H
00039
00040 #include "vtkgdcmModule.h"
00041 #include "vtkImageAlgorithm.h"
00042
00043 // everything is now handled within the vtkGDCMImageReader as Planar Configuration can not
00044 // be externalized (conflict with file lower left)
00045
00046 #error do not use this class
00047
00048 //class VTKGDCM_EXPORT vtkImagePlanarComponentsToComponents : public vtkThreadedImageAlgorithm
00049 class VTKGDCM_EXPORT vtkImagePlanarComponentsToComponents : public vtkImageAlgorithm
00050 {
00051 public:
00052     static vtkImagePlanarComponentsToComponents *New();
00053     //vtkTypeMacro(vtkImagePlanarComponentsToComponents,vtkThreadedImageAlgorithm);
00054     vtkTypeMacro(vtkImagePlanarComponentsToComponents,vtkImageAlgorithm);
00055
00056     void PrintSelf(ostream& os, vtkIndent indent);
00057
00058 protected:
00059     vtkImagePlanarComponentsToComponents();
00060     ~vtkImagePlanarComponentsToComponents() {};
00061
00062 // void ThreadedExecute (vtkImageData *inData, vtkImageData *outData,
00063 // int ext[6], int id);
00064 // virtual int RequestInformation (vtkInformation *, vtkInformationVector**, vtkInformationVector *);
00065 virtual int RequestData(vtkInformation *, vtkInformationVector **, vtkInformationVector *);
00066
00067 private:
00068     vtkImagePlanarComponentsToComponents(const vtkImagePlanarComponentsToComponents&); // Not implemented.
00069     void operator=(const vtkImagePlanarComponentsToComponents&); // Not implemented.
00070 };
00071
00072 #endif

```


11.631 vtkImageRGBToYBR.h File Reference

```

#include "vtkgdcmModule.h"
#include "vtkThreadedImageAlgorithm.h"

```

Include dependency graph for vtkImageRGBToYBR.h:



Classes

- class [vtkImageRGBToYBR](#)

11.632 vtkImageRGBToYBR.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program:  GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009       This software is distributed WITHOUT ANY WARRANTY; without even
00010       the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011       PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 /*=====
00015
00016   Portions of this file are subject to the VTK Toolkit Version 3 copyright.
00017
00018   Program:   Visualization Toolkit
00019   Module:    $RCSfile: vtkImageRGBToYBR.h,v $
00020
00021   Copyright (c) Ken Martin, Will Schroeder, Bill Lorensen
00022   All rights reserved.
00023   See Copyright.txt or http://www.kitware.com/Copyright.htm for details.
00024
00025       This software is distributed WITHOUT ANY WARRANTY; without even
00026       the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00027       PURPOSE. See the above copyright notice for more information.
00028
00029 =====*/
00030 // .NAME vtkImageRGBToYBR - Converts YBR components to RGB.
00031 // .SECTION Description
00032 // For each pixel with hue, saturation and value components this filter
00033 // outputs the color coded as red, green, blue. Output type must be the same
00034 // as input type.
00035
00036 // .SECTION See Also
00037 // vtkImageRGBToHSV
00038
00039 #ifndef VTKIMAGERGBTOYBR_H

```

```

00040 #define VTKIMAGERGBTOYBR_H
00041
00042 #include "vtkgdcmModule.h"
00043 #include "vtkThreadedImageAlgorithm.h"
00044
00045 class VTKGDCM_EXPORT vtkImageRGBToYBR : public vtkThreadedImageAlgorithm
00046 {
00047 public:
00048     static vtkImageRGBToYBR *New();
00049     vtkTypeMacro(vtkImageRGBToYBR,vtkThreadedImageAlgorithm);
00050
00051     void PrintSelf(ostream& os, vtkIndent indent);
00052
00053 protected:
00054     vtkImageRGBToYBR();
00055     ~vtkImageRGBToYBR() {};
00056
00057     void ThreadedExecute (vtkImageData *inData, vtkImageData *outData,
00058                          int ext[6], int id);
00059 private:
00060     vtkImageRGBToYBR(const vtkImageRGBToYBR&); // Not implemented.
00061     void operator=(const vtkImageRGBToYBR&); // Not implemented.
00062 };
00063
00064 #endif

```


11.633 vtkImageYBRToRGB.h File Reference

```

#include "vtkgdcmModule.h"
#include "vtkThreadedImageAlgorithm.h"

```

Include dependency graph for vtkImageYBRToRGB.h:



Classes

- class [vtkImageYBRToRGB](#)

11.634 vtkImageYBRToRGB.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002

```

```

00003 Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005 Copyright (c) 2006-2011 Mathieu Malaterre
00006 All rights reserved.
00007 See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009 This software is distributed WITHOUT ANY WARRANTY; without even
00010 the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011 PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 /*=====
00015
00016 Portions of this file are subject to the VTK Toolkit Version 3 copyright.
00017
00018 Program: Visualization Toolkit
00019 Module: $RCSfile: vtkImageYBRToRGB.h,v $
00020
00021 Copyright (c) Ken Martin, Will Schroeder, Bill Lorensen
00022 All rights reserved.
00023 See Copyright.txt or http://www.kitware.com/Copyright.htm for details.
00024
00025 This software is distributed WITHOUT ANY WARRANTY; without even
00026 the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00027 PURPOSE. See the above copyright notice for more information.
00028
00029 =====*/
00030 // .NAME vtkImageYBRToRGB - Converts YBR components to RGB.
00031 // .SECTION Description
00032 // For each pixel with hue, saturation and value components this filter
00033 // outputs the color coded as red, green, blue. Output type must be the same
00034 // as input type.
00035
00036 // .SECTION See Also
00037 // vtkImageRGBToHSV
00038
00039 #ifndef VTKIMAGEYBRTORGB_H
00040 #define VTKIMAGEYBRTORGB_H
00041
00042 #include "vtkgdcmModule.h"
00043 #include "vtkThreadedImageAlgorithm.h"
00044
00045 class VTKGDCM_EXPORT vtkImageYBRToRGB : public vtkThreadedImageAlgorithm
00046 {
00047 public:
00048     static vtkImageYBRToRGB *New();
00049     vtkTypeMacro(vtkImageYBRToRGB,vtkThreadedImageAlgorithm);
00050
00051     void PrintSelf(ostream& os, vtkIndent indent);
00052
00053 protected:
00054     vtkImageYBRToRGB();
00055     ~vtkImageYBRToRGB() {};
00056
00057     void ThreadedExecute (vtkImageData *inData, vtkImageData *outData,
00058                          int ext[6], int id);
00059 private:
00060     vtkImageYBRToRGB(const vtkImageYBRToRGB&); // Not implemented.
00061     void operator=(const vtkImageYBRToRGB&); // Not implemented.
00062 };
00063
00064 #endif

```


11.635 vtkLookupTable16.h File Reference

```

#include "vtkgdcmModule.h"
#include "vtkLookupTable.h"
#include "vtkUnsignedShortArray.h"

```


Include dependency graph for vtkLookupTable16.h:



Classes

- class [vtkLookupTable16](#)

11.636 vtkLookupTable16.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013   =====*/
00014 /*=====
00015
00016   Portions of this file are subject to the VTK Toolkit Version 3 copyright.
00017
00018   Program: Visualization Toolkit
00019   Module:   $RCSfile: vtkLookupTable16.h,v $
00020
00021   Copyright (c) Ken Martin, Will Schroeder, Bill Lorensen
00022   All rights reserved.
00023   See Copyright.txt or http://www.kitware.com/Copyright.htm for details.
00024
00025   This software is distributed WITHOUT ANY WARRANTY; without even
00026   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00027   PURPOSE. See the above copyright notice for more information.
00028
00029   =====*/
00030 // .NAME vtkLookupTable16 -
00031 // .SECTION Description
00032 //
00033 // .SECTION Caveats
00034 //
00035 // .SECTION See Also
00036 // vtkLookupTable
00037
00038 #ifndef VTKLOOKUPTABLE16_H
00039 #define VTKLOOKUPTABLE16_H
00040
00041 #include "vtkgdcmModule.h"
00042 #include "vtkLookupTable.h"
00043 #include "vtkUnsignedShortArray.h"

```

```

00044
00045 class VTKGDCM_EXPORT vtkLookupTable16 : public vtkLookupTable
00046 {
00047 public:
00048     static vtkLookupTable16 *New();
00049
00050     vtkTypeMacro(vtkLookupTable16,vtkLookupTable);
00051     void PrintSelf(ostream& os, vtkIndent indent);
00052
00053     void Build();
00054
00055     void SetNumberOfTableValues(vtkIdType number);
00056
00057     unsigned char *WritePointer(const vtkIdType id, const int number);
00058
00059     unsigned short *GetPointer(const vtkIdType id) {
00060         return this->Table16->GetPointer(4*id); };
00061
00062 protected:
00063     vtkLookupTable16(int size=256, int ext=256);
00064     ~vtkLookupTable16();
00065
00066     vtkUnsignedShortArray *Table16;
00067
00068     void MapScalarsThroughTable2(void *input,
00069                                 unsigned char *output,
00070                                 int inputDataType,
00071                                 int numberOfValues,
00072                                 int inputIncrement,
00073                                 int outputFormat);
00074
00075 private:
00076     vtkLookupTable16(const vtkLookupTable16&); // Not implemented.
00077     void operator=(const vtkLookupTable16&); // Not implemented.
00078 };
00079
00080 //-----
00081 inline unsigned char *vtkLookupTable16::WritePointer(const vtkIdType id,
00082                                                       const int number)
00083 {
00084     //this->InsertTime.Modified();
00085     return (unsigned char*)this->Table16->WritePointer(4*id,4*number);
00086 }
00087
00088 #endif

```


11.637 vtkRTStructSetProperties.h File Reference

```

#include "vtkgdcModule.h"
#include "vtkObject.h"

```

Include dependency graph for vtkRTStructSetProperties.h:



Classes

- class [vtkRTStructSetProperties](#)

11.638 vtkRTStructSetProperties.h

[Go to the documentation of this file.](#)

```

00001 /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013 =====*/
00014 // .NAME vtkRTStructSetProperties - some rtstruct properties.
00015 // .SECTION Description
00016 //
00017 // .SECTION See Also
00018 // vtkGDCMPolyDataReader vtkGDCMPolyDataWriter
00019
00020 #ifndef VTKRTSTRUCTSETPROPERTIES_H
00021 #define VTKRTSTRUCTSETPROPERTIES_H
00022
00023 #include "vtkgdcmModule.h"
00024 #include "vtkObject.h"
00025
00026 class vtkRTStructSetPropertiesInternals;
00027
00028 class VTKGDCM_EXPORT vtkRTStructSetProperties : public vtkObject
00029 {
00030 public:
00031   static vtkRTStructSetProperties *New();
00032   vtkTypeMacro(vtkRTStructSetProperties,vtkObject);
00033   void PrintSelf(ostream& os, vtkIndent indent);
00034
00035   // Description:
00036   // Convenience method to reset all fields to an empty string/value
00037   virtual void Clear();
00038
00039   // Description:
00040   //
00041   vtkSetStringMacro(StructureSetLabel);
00042   vtkGetStringMacro(StructureSetLabel);
00043
00044   vtkSetStringMacro(StructureSetName);
00045   vtkGetStringMacro(StructureSetName);
00046
00047   vtkSetStringMacro(StructureSetDate);
00048   vtkGetStringMacro(StructureSetDate);
00049
00050   vtkSetStringMacro(StructureSetTime);
00051   vtkGetStringMacro(StructureSetTime);
00052
00053   vtkSetStringMacro(SOPInstanceUID);
00054   vtkGetStringMacro(SOPInstanceUID);
00055
00056   vtkSetStringMacro(StudyInstanceUID);
00057   vtkGetStringMacro(StudyInstanceUID);
00058
00059   vtkSetStringMacro(SeriesInstanceUID);
00060   vtkGetStringMacro(SeriesInstanceUID);
00061
00062   vtkSetStringMacro(ReferenceSeriesInstanceUID);
00063   vtkGetStringMacro(ReferenceSeriesInstanceUID);
00064
00065   vtkSetStringMacro(ReferenceFrameOfReferenceUID);
00066   vtkGetStringMacro(ReferenceFrameOfReferenceUID);

```

```

00067
00068 // Description:
00069 // Copy the contents of p to this instance.
00070 virtual void DeepCopy(vtkRTStructSetProperties *p);
00071
00072 void AddContourReferencedFrameOfReference( vtkIdType pdnum, const char *classuid , const char *
instanceuid );
00073 const char *GetContourReferencedFrameOfReferenceClassUID( vtkIdType pdnum, vtkIdType id );
00074 const char *GetContourReferencedFrameOfReferenceInstanceUID( vtkIdType pdnum, vtkIdType id );
00075 vtkIdType GetNumberOfContourReferencedFrameOfReferences();
00076 vtkIdType GetNumberOfContourReferencedFrameOfReferences(vtkIdType pdnum);
00077
00078 void AddReferencedFrameOfReference( const char *classuid , const char * instanceuid );
00079 const char *GetReferencedFrameOfReferenceClassUID( vtkIdType id );
00080 const char *GetReferencedFrameOfReferenceInstanceUID( vtkIdType id );
00081 vtkIdType GetNumberOfReferencedFrameOfReferences();
00082
00083 void AddStructureSetROI( int roinumber,
00084     const char* refframerefid,
00085     const char* roiname,
00086     const char* ROIGenerationAlgorithm,
00087     const char* ROIDescription = 0
00088 );
00089 void AddStructureSetROIObservation( int refnumber,
00090     int observationnumber,
00091     const char *rtroiinterpretedtype,
00092     const char *roiinterpreter,
00093     const char *roiobservationlabel = 0
00094 );
00095
00096 vtkIdType GetNumberOfStructureSetROIs();
00097 int GetStructureSetObservationNumber(vtkIdType id);
00098 int GetStructureSetROIInumber(vtkIdType id);
00099 const char *GetStructureSetROIRefFrameRefUID(vtkIdType);
00100 const char *GetStructureSetROIName(vtkIdType);
00101 const char *GetStructureSetROIGenerationAlgorithm(vtkIdType);
00102 const char *GetStructureSetROIDescription(vtkIdType id);
00103 const char *GetStructureSetRTROIInterpretedType(vtkIdType id);
00104 const char *GetStructureSetROIObservationLabel(vtkIdType id);
00105
00106 protected:
00107     vtkRTStructSetProperties();
00108     ~vtkRTStructSetProperties();
00109
00110     char *StructureSetLabel;
00111     char *StructureSetName;
00112     char *StructureSetDate;
00113     char *StructureSetTime;
00114
00115     char *SOPInstanceUID;
00116     char *StudyInstanceUID;
00117     char *SeriesInstanceUID;
00118
00119     char *ReferenceSeriesInstanceUID;
00120     char *ReferenceFrameOfReferenceUID;
00121
00122 // Description:
00123 // PIMPL Encapsulation for STL containers
00124 //BTX
00125 vtkRTStructSetPropertiesInternals *Internals;
00126 //ETX
00127
00128 private:
00129     vtkRTStructSetProperties(const vtkRTStructSetProperties&); // Not implemented.
00130     void operator=(const vtkRTStructSetProperties&); // Not implemented.
00131 };
00132
00133 #endif

```

11.639 gdcmPythonFilter.h File Reference


```

#include <Python.h>
#include "gdcmDataElement.h"
#include "gdcmDicts.h"

```

```
#include "gdcmFile.h"
```

Include dependency graph for gdcmPythonFilter.h:



Classes

- class [gdcm::PythonFilter](#)

PythonFilter PythonFilter is the class that make *gdcm2.x* looks more like *gdcm1* and transform the binary blob contained in a *DataElement* into a string, typically this is a nice feature to have for wrapped language.

Namespaces

- namespace [gdcm](#)

11.640 gdcmPythonFilter.h

[Go to the documentation of this file.](#)

```
00001  /*=====
00002
00003   Program: GDCM (Grassroots DICOM). A DICOM library
00004
00005   Copyright (c) 2006-2011 Mathieu Malaterre
00006   All rights reserved.
00007   See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.
00008
00009   This software is distributed WITHOUT ANY WARRANTY; without even
00010   the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00011   PURPOSE. See the above copyright notice for more information.
00012
00013  =====*/
00014  #ifndef GDCMPYTHONFILTER_H
00015  #define GDCMPYTHONFILTER_H
00016
00017  #include <Python.h>
00018
00019  #include "gdcmDataElement.h"
00020  #include "gdcmDicts.h"
00021  #include "gdcmFile.h"
00022
00023  namespace gdcm
00024  {
00025
00031  class GDCM_EXPORT PythonFilter
00032  {
00033  public:
00034      PythonFilter();
00035      ~PythonFilter();
00036  }
```

```
00037 void UseDictAlways(bool ) {}
00038
00039 // Allow user to pass in there own dicts
00040 void SetDicts(const Dicts &dicts);
00041
00042 // Convert to string the ByteValue contained in a DataElement
00043 PyObject *ToPyObject(const Tag& t) const;
00044
00045 void SetFile(const File& f);
00046 File &GetFile();
00047 const File &GetFile() const;
00048
00049 private:
00050     SmartPointer<File> F;
00051 };
00052
00053 } // end namespace gdcmm
00054
00055 #endif //GDCMPYTHONFILTER_H
```

Chapter 12

Examples

12.1 TestByteSwap.cxx

This is a C++ example on how to use [gdcm::ByteSwap](#)

```
/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
#include "gdcmTypes.h"
#include "gdcmSwapCode.h"
#include "gdcmByteSwap.h"

#include <cstring> // memcpy

int myfunc()
{
    char vl_str[4];
    const char raw[] = "\000\000\000\004";
    memcpy(vl_str, raw, 4);
    uint32_t vl;
    memcpy(&vl, vl_str, 4);
    gdcm::ByteSwap<uint32_t>::SwapRangeFromSwapCodeIntoSystem(&vl, gdcm::SwapCode::BigEndian, 1);
    if( vl != 0x00000004 )
    {
        std::cerr << std::hex << "vl: " << vl << std::endl;
        return 1;
    }

    gdcm::ByteSwap<uint32_t>::SwapFromSwapCodeIntoSystem(vl, gdcm::SwapCode::LittleEndian);
    if( vl != 0x00000004 )
    {
        std::cerr << std::hex << "vl: " << vl << std::endl;
        return 1;
    }

    gdcm::ByteSwap<uint32_t>::SwapFromSwapCodeIntoSystem(vl, gdcm::SwapCode::BigEndian);
    if( vl != 0x40000000 )
    {
        std::cerr << std::hex << "vl: " << vl << std::endl;
        return 1;
    }

    return 0;
}
```

```

}

int TestByteSwap(int , char *[])
{
    gdcm::SwapCode sc = gdcm::SwapCode::Unknown;
    if ( gdcm::ByteSwap<uint16_t>::SystemIsBigEndian() )
    {
        sc = gdcm::SwapCode::BigEndian;
    }
    else if ( gdcm::ByteSwap<uint16_t>::SystemIsLittleEndian() )
    {
        sc = gdcm::SwapCode::LittleEndian;
    }
    if( sc == gdcm::SwapCode::Unknown )
    {
        std::cerr << "unk" << std::endl;
        return 1;
    }

    //std::cout << "sc: " << sc << std::endl;

    uint16_t t = 0x1234;
    gdcm::ByteSwap<uint16_t>::SwapFromSwapCodeIntoSystem(t, sc);
    if( sc == gdcm::SwapCode::BigEndian )
    {
        if( t != 0x3412 )
        {
            std::cerr << std::hex << "t: " << t << std::endl;
            return 1;
        }
        // ok test pass rest value to old one
        t = 0x1234;
    }
    else if ( sc == gdcm::SwapCode::LittleEndian )
    {
        if( t != 0x1234 )
        {
            std::cerr << std::hex << "t: " << t << std::endl;
            return 1;
        }
    }
}

union { char n[2]; uint16_t tn; } ul6;
memcpy(ul6.n, &t, 2 );
gdcm::ByteSwap<uint16_t>::SwapRangeFromSwapCodeIntoSystem(&ul6.tn, sc, 1);
uint16_t tn = ul6.tn;
if( sc == gdcm::SwapCode::BigEndian )
{
    if( tn != 0x3412 )
    {
        std::cerr << std::hex << "tn: " << tn << std::endl;
        return 1;
    }
    // ok test pass rest value to old one
    t = 0x1234;
}
else if ( sc == gdcm::SwapCode::LittleEndian )
{
    if( tn != 0x1234 )
    {
        std::cerr << std::hex << "tn: " << tn << std::endl;
        return 1;
    }
}
gdcm::ByteSwap<uint16_t>::SwapRangeFromSwapCodeIntoSystem(&ul6.tn, gdcm::SwapCode::BigEndian, 1);
tn = ul6.tn;
if( sc == gdcm::SwapCode::LittleEndian )
{
    if( tn != 0x3412 )
    {
        std::cerr << std::hex << "tn: " << tn << std::endl;
        return 1;
    }
}
else if ( sc == gdcm::SwapCode::BigEndian )
{
    if( tn != 0x1234 )
    {
        std::cerr << std::hex << "tn: " << tn << std::endl;
        return 1;
    }
}

```



```

    }

    if( myfunc() )
    {
        return 1;
    }

    uint16_t array[] = { 0x1234 };
    gdcm::ByteSwap<uint16_t>::SwapRangeFromSwapCodeIntoSystem(array,
        gdcm::SwapCode::BigEndian,1);
    if ( array[0] != 0x3412 )
    {
        std::cerr << std::hex << "array: " << array[0] << std::endl;
        return 1;
    }

    return 0;
}

```

12.2 PatchFile.cxx

This is a C++ example on how to use `gdcm::Attribute`

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
/*
 * The image was a broken file where the Pixel Data element was 8 times too big
 * Apparently multiplying the BitsAllocated to 4 and multiplying the number of
 * frames by 2 would solve the problem
 *
 * This C++ code can be used to patch the header.
 */

#include "gdcmReader.h"
#include "gdcmImageReader.h"
#include "gdcmWriter.h"
#include "gdcmDataSet.h"
#include "gdcmAttribute.h"

int main(int argc, char *argv[])
{
    if( argc < 3 )
    {
        return 1;
    }
    const char *f = argv[1];
    const char *out = argv[2];
    gdcm::Reader r;
    r.SetFileName( f );
    if( !r.Read() )
    {
        return 1;
    }

    gdcm::File &file = r.GetFile();
    gdcm::DataSet& ds = file.GetDataSet();
    // (0028,0100) US 16 # 2, 1 BitsAllocated
    // (0028,0101) US 16 # 2, 1 BitsStored
    // (0028,0102) US 15 # 2, 1 HighBit
    //
    {
        gdcm::Attribute<0x28,0x100> at;
        at.SetFromDataElement( ds.GetDataElement( at.GetTag() ) );
        if( at.GetValue() != 8 )

```

```

        {
            return 1;
        }
        at.SetValue( 32 );
        ds.Replace( at.GetAsDataElement() );
    }
    {
        gdcmm::Attribute<0x28,0x101> at;
        at.SetFromDataElement( ds.GetDataElement( at.GetTag() ) );
        if( at.GetValue() != 8 )
        {
            return 1;
        }
        at.SetValue( 32 );
        ds.Replace( at.GetAsDataElement() );
    }
    {
        gdcmm::Attribute<0x28,0x102> at;
        at.SetFromDataElement( ds.GetDataElement( at.GetTag() ) );
        if( at.GetValue() != 7 )
        {
            return 1;
        }
        at.SetValue( 31 );
        ds.Replace( at.GetAsDataElement() );
    }
    // (0028,0008) IS [56] # 2, 1 NumberOfFrames

    {
        gdcmm::Attribute<0x28,0x8> at;
        at.SetFromDataElement( ds.GetDataElement( at.GetTag() ) );
        at.SetValue( at.GetValue() * 2 );
        ds.Replace( at.GetAsDataElement() );
    }

    gdcmm::Writer w;
    w.SetFile( file );
    w.SetCheckFileMetaInformation( false );
    w.SetFileName( out );
    if( !w.Write() )
    {
        return 1;
    }

    // Now let's see if we can read it as an image:
    gdcmm::ImageReader ir;
    ir.SetFileName( out );
    if(!ir.Read())
    {
        return 1;
    }
    gdcmm::Image &image = ir.GetImage();
    unsigned long len = image.GetBufferLength();
    const gdcmm::ByteValue *bv = ir.GetFile().GetDataSet().GetDataElement( gdcmm::Tag(0x7fe0,0x0010) )
        .GetByteValue();
    if( !bv || len != bv->GetLength() )
    {
        return 1;
    }
    std::cout << bv->GetLength() << " " << len << std::endl;

    std::cout << "Success to rewrite image !" << std::endl;
    image.Print( std::cout );
    return 0;
}

```

12.3 SimplePrint.cs

This is a C# example on how to use gdcmm::SWIGDataSet

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre

```

All rights reserved.
See Copyright.txt or <http://gdcm.sourceforge.net/Copyright.html> for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

```

=====*/
/*
    Convertor convertor = new Convertor();
    int a = convertor.Convert<int>( some_int_blob );
    double b = convertor.Convert<double>( some_double_blob );
*/

/*
 * Usage:
 * $ export LD_LIBRARY_PATH=$HOME/Projects/gdcm/debug-gcc/bin
 * $ mono bin/SimplePrint.exe gdcmData/012345.002.050.dcm
 */
using System;
using gdcm;

public class SimplePrint
{
    public static void RecurseDataSet(File f, DataSet ds, string indent)
    {
        CSharpDataSet cds = new CSharpDataSet(ds);
        while(!cds.IsAtEnd())
        {
            DataElement de = cds.GetCurrent();
            // Compute VR from the toplevel file, and the currently processed dataset:
            VR vr = DataSetHelper.ComputeVR(f, ds, de.GetTag() );

            if( vr.Compatible( new VR(VR.VRType.SQ) ) )
            {
                uint uvl = (uint)de.GetVL(); // Test cast is ok
                System.Console.WriteLine( indent + de.GetTag().toString() + ":" + uvl ); // why not ?
                //SequenceOfItems sq = de.GetSequenceOfItems();
                // GetValueAsSQ handle more cases than GetSequenceOfItems
                SmartPtrSQ sq = de.GetValueAsSQ();
                uint n = sq.GetNumberOfItems();
                for( uint i = 1; i <= n; i++) // item starts at 1, not 0
                {
                    Item item = sq.GetItem( i );
                    DataSet nested = item.GetNestedDataSet();
                    RecurseDataSet( f, nested, indent + "  " );
                }
            }
            else
            {
                System.Console.WriteLine( indent + de.toString() );
            }
            cds.Next();
        }
    }

    public static int Main(string[] args)
    {
        string filename = args[0];
        Reader reader = new Reader();
        reader.SetFileName( filename );
        bool ret = reader.Read();
        if( !ret )
        {
            return 1;
        }
        File f = reader.GetFile();
        DataSet ds = f.GetDataSet();

        RecurseDataSet( f, ds, "" );

        return 0;
    }
}

```

12.4 TestReader.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.
=====*/
#include "gdcmReader.h"
#include "gdcmFileMetaInformation.h"
#include "gdcmFile.h"
#include "gdcmTesting.h"
#include "gdcmMediaStorage.h"

int TestRead(const char* filename, bool verbose = false)
{
    if( verbose )
        std::cout << "TestRead: " << filename << std::endl;

    gdcm::Reader reader;
    reader.SetFileName( filename );
    if ( !reader.Read() )
    {
        std::cerr << "TestReadError: Failed to read: " << filename << std::endl;
        return 1;
    }

    //commenting out the fmi and ds to avoid warnings
    //const gdcm::FileMetaInformation &h = reader.GetFile().GetHeader();
    //std::cout << h << std::endl;

    //const gdcm::DataSet &ds = reader.GetFile().GetDataSet();
    //std::cout << ds << std::endl;

    const char *ref = gdcm::Testing::GetMediaStorageFromFile(filename);
    gdcm::MediaStorage ms;
    ms.SetFromFile( reader.GetFile() );
    if( !ref )
    {
        std::cerr << "TestReadError: Missing MediaStorage: " << filename << std::endl;
        std::cerr << "It should be: " << ms << std::endl;
        return 1;
    }

    if( ms.IsUndefined() && ref && *ref != 0 )
    {
        std::cerr << "TestReadError: MediaStorage: " << filename << std::endl;
        std::cerr << "It should be instead: " << ref << std::endl;
        return 1;
    }

    // Make sure it is the right one:

    if( ref && *ref != 0 && ms != gdcm::MediaStorage::GetMSType(ref) )
    {
        std::cerr << "Error: Found MediaStorage: " << ms << " for " << filename << std::endl;
        std::cerr << "It should be instead: " << ref << std::endl;
        return 1;
    }

    return 0;
}

int TestReader(int argc, char *argv[])
{
    if( argc == 2 )
    {
        const char *filename = argv[1];
        return TestRead(filename, true);
    }

    // else
    gdcm::Trace::DebugOff();
}

```

```

gdcmm::Trace::WarningOff();
int r = 0, i = 0;
const char *filename;
const char * const *filenames = gdcmm::Testing::GetFileNames();
while( (filename = filenames[i]) )
{
    r += TestRead( filename );
    ++i;
}

return r;
}

```

12.5 TestReader.py

This is a C++ example on how to use [gdcmm::Reader](#)

```

00001
00014
00015 import os,sys
00016 import gdcmm
00017
00018 def TestRead(filename, verbose = False):
00019     r = gdcmm.Reader()
00020     r.SetFileName( filename )
00021     success = r.Read()
00022     #if verbose: print r.GetFile()
00023     if verbose: print (r.GetFile().GetDataSet())
00024     return success
00025
00026 if __name__ == "__main__":
00027     success = 0
00028     try:
00029         filename = os.sys.argv[1]
00030         success += TestRead( filename, True )
00031     except:
00032         # loop over all files:
00033         gdcmm.Trace.DebugOff()
00034         gdcmm.Trace.WarningOff()
00035         t = gdcmm.Testing()
00036         nfiles = t.GetNumberOfFileNames()
00037         for i in range(0,nfiles):
00038             filename = t.GetFileName(i)
00039             success += TestRead( filename )
00040
00041
00042     # Test succeed ?
00043     sys.exit(success == 0)

```

12.6 DecompressJPEGFile.cs

This is a C# example on how to use [gdcmm::SequenceOfFragments](#)

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcmm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/

/*
 * Usage:
 * $ export LD_LIBRARY_PATH=$HOME/Projects/gdcm/debug-gcc/bin

```

```

* $ mono bin/DecompressJPEGFile.exe somejpegfile.jpg
*/
using System;
using gdcmm;

public class DecompressJPEGFile
{
    public static int Main(string[] args)
    {
        string file1 = args[0];
        System.IO.FileStream infile =
            new System.IO.FileStream(file1, System.IO.FileMode.Open, System.IO.FileAccess.Read);
        uint fsize = gdcmm.PosixEmulation.FileSize(file1);

        byte[] jstream = new byte[fsize];
        infile.Read(jstream, 0, jstream.Length);

        Trace.DebugOn();
        Image image = new Image();
        image.SetNumberOfDimensions( 2 ); // important for now
        DataElement pixeldata = new DataElement( new gdcmm.Tag(0x7fe0,0x0010) );

        // DO NOT set a ByteValue here, JPEG is a particular kind of encapsulated syntax
        // in which can one cannot use a simple byte array for storage. Instead, see
        // gdcmm.SequenceOfFragments
        //pixeldata.SetByteValue( jstream, new gdcmm.VL( (uint)jstream.Length ) );

        // Create a new SequenceOfFragments C++ object, store it as a SmartPointer :
        SmartPtrFrag sq = SequenceOfFragments.New();
        Fragment frag = new Fragment();
        frag.SetByteValue( jstream, new gdcmm.VL( (uint)jstream.Length ) );
        // Single file => single fragment
        sq.AddFragment( frag );
        // Pass by reference:
        pixeldata.SetValue( sq.__ref__() );

        // insert:
        image.SetDataElement( pixeldata );

        // JPEG use YBR to achieve better compression ratio by default (not RGB)
        // FIXME hardcoded:
        PhotometricInterpretation pi = new PhotometricInterpretation( PhotometricInterpretation.PIType.YBR_FULLL );
        image.SetPhotometricInterpretation( pi );
        // FIXME hardcoded:
        PixelFormat pixeltype = new PixelFormat(3,8,8,7);
        image.SetPixelFormat( pixeltype );

        // FIXME hardcoded:
        image.SetTransferSyntax( new TransferSyntax( TransferSyntax.TSType.JPEGLosslessProcess14_1 ) );
        image.SetDimension(0, 692);
        image.SetDimension(1, 721);

        // Decompress !
        byte[] decompressedData = new byte[(int)image.GetBufferLength()];
        image.GetBuffer(decompressedData);

        // Write out the decompressed bytes
        System.Console.WriteLine(image.toString());
        using (System.IO.Stream stream =
            System.IO.File.Open(@"tmp/dd.raw",
                System.IO.FileMode.Create))
        {
            System.IO.BinaryWriter writer = new System.IO.BinaryWriter(stream);
            writer.Write(decompressedData);
        }

        return 0;
    }
}

```

12.7 ManipulateFile.cs

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

```

```

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/

/*
 * Usage:
 * $ export LD_LIBRARY_PATH=$HOME/Projects/gdcm/debug-gcc/bin
 * $ mono bin/ManipulateFile.exe gdcmData/012345.002.050.dcm out.dcm
 */
using System;
using gdcm;

public class ManipulateFile
{
    public static int Main(string[] args)
    {
        string file1 = args[0];
        string file2 = args[1];
        Reader reader = new Reader();
        reader.SetFileName( file1 );
        bool ret = reader.Read();
        if( !ret )
        {
            return 1;
        }

        Anonymizer ano = new Anonymizer();
        ano.SetFile( reader.GetFile() );
        ano.RemovePrivateTags();
        ano.RemoveGroupLength();
        Tag t = new Tag(0x10,0x10);
        ano.Replace( t, "GDCM^Csharp^Test^Hello^World" );

        UIDGenerator g = new UIDGenerator();
        ano.Replace( new Tag(0x0008,0x0018), g.Generate() );
        ano.Replace( new Tag(0x0020,0x000d), g.Generate() );
        ano.Replace( new Tag(0x0020,0x000e), g.Generate() );
        ano.Replace( new Tag(0x0020,0x0052), g.Generate() );

        Writer writer = new Writer();
        writer.SetFileName( file2 );
        writer.SetFile( ano.GetFile() );
        ret = writer.Write();
        if( !ret )
        {
            return 1;
        }

        return 0;
    }
}

```

12.8 ClinicalTrialIdentificationWorkflow.cs

This is a C# example on how to use Anonymizer

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

```

```

=====*/

/*
 * Typical usage on UNIX:
 * $ export LD_LIBRARY_PATH=$HOME/Projects/gdcm/debug-gcc/bin
 * $ mono bin/ClinicalTrialIdentificationWorkflow.exe input_dir output_dir
 */
using System;
using gdcm;

public class MyWatcher : SimpleSubjectWatcher
{
    public MyWatcher(Subject s):base(s,"Override String"){
        protected override void StartFilter() {
            System.Console.WriteLine( "This is my start" );
        }
        protected override void EndFilter(){
            System.Console.WriteLine( "This is my end" );
        }
        protected override void ShowProgress(Subject caller, Event evt){
            ProgressEvent pe = ProgressEvent.Cast(evt);
            System.Console.WriteLine( "This is my progress: " + pe.GetProgress() );
        }
        protected override void ShowIteration(){
            System.Console.WriteLine( "This is my iteration" );
        }
        protected override void ShowAnonymization(Subject caller, Event evt){
/*
 * A couple of explanation are necessary here to understand how SWIG work
 * http://www.swig.org/Doc1.3/Java.html#adding_downcasts
 *
 * System.Console.WriteLine( "This is my Anonymization. Type: " + evt.GetEventName() );
 * System.Type type = evt.GetType();
 * System.Console.WriteLine( "This is my Anonymization. System.Type: " + type.ToString() );
 * System.Console.WriteLine( "This is my Anonymization. CheckEvent: " + ae.CheckEvent( evt ) );
 * System.Console.WriteLine( "This is my Anonymization. Processing Tag #" + ae.GetTag().toString() );
 */
            AnonymizeEvent ae = AnonymizeEvent.Cast(evt);
            if( ae != null )
            {
                Tag t = ae.GetTag();
                System.Console.WriteLine( "This is my Anonymization. Processing Tag #" + t.toString() );
            }
            else
            {
                System.Console.WriteLine( "This is my Anonymization. Unhandled Event type: " + evt.GetEventName() );
            }
        }
        protected override void ShowAbort(){
            System.Console.WriteLine( "This is my abort" );
        }
    }
}

public class ClinicalTrialIdentificationWorkflow
{
    public static bool ProcessOneFile( gdcm.Anonymizer ano , string filename, string outfilename )
    {
        Reader reader = new Reader();
        reader.SetFileName( filename );
        bool ret = reader.Read();
        if( !ret )
        {
            return false;
        }
        // Pass in the file:
        ano.SetFile( reader.GetFile() );

        // First step, let's protect all Patient information as per
        // PS 3.15 / E.1 / Basic Application Level Confidentiality Profile
        if( !ano.BasicApplicationLevelConfidentialityProfile() )
        {
            return false;
        }

        // Now let's pass in all Clinical Trial fields
        // PS 3.3 - 2008 / C.7.1.3 Clinical Trial Subject Module
        /*
        Clinical Trial Sponsor Name (0012,0010) 1 The name of the clinical trial sponsor. See C.7.1.3.1.1.
        Clinical Trial Protocol ID (0012,0020) 1 Identifier for the noted protocol. See C.7.1.3.1.2.
        Clinical Trial Protocol Name (0012,0021) 2 The name of the clinical trial protocol. See C.7.1.3.1.3.
        Clinical Trial Site ID (0012,0030) 2 The identifier of the site responsible for submitting clinical trial

```



```

    data. See C.7.1.3.1.4.
Clinical Trial Site Name (0012,0031) 2 Name of the site responsible for submitting clinical trial data. See
C.7.1.3.1.5
Clinical Trial Subject ID (0012,0040) 1C The assigned identifier for the clinical trial subject. See
C.7.1.3.1.6. Shall be present if Clinical Trial Subject Reading ID (0012,0042) is absent. May be present
otherwise.
Clinical Trial Subject Reading ID (0012,0042) 1C Identifies the subject for blinded evaluations. Shall be
present if Clinical Trial Subject ID (0012,0040) is absent. May be present otherwise. See C.7.1.3.1.7.
*/
ano.Replace( new gdcm.Tag(0x0012,0x0010), "MySponsorName");
ano.Replace( new gdcm.Tag(0x0012,0x0020), "MyProtocolID");
ano.Replace( new gdcm.Tag(0x0012,0x0021), "MyProtocolName");
ano.Replace( new gdcm.Tag(0x0012,0x0030), "MySiteId");
ano.Replace( new gdcm.Tag(0x0012,0x0031), "MySiteName");
ano.Replace( new gdcm.Tag(0x0012,0x0040), "MySponsorId");
ano.Replace( new gdcm.Tag(0x0012,0x0050), "MyTPId");
ano.Replace( new gdcm.Tag(0x0012,0x0051), "MyTPDescription");

// The following two are not required as they are guaranteed to be filled in by the
// Basic Application Level Confidentiality Profile. Only override if you understand what
// you are doing
//ano.Replace( new gdcm.Tag(0x0012,0x0062), "YES");
//ano.Replace( new gdcm.Tag(0x0012,0x0063), "My Super Duper Anonymization Overload");

// We might be generating a subdirectory. Let's make sure the subdir exist:
gdcm.FileMetaInformation fmi = ano.GetFile().GetHeader();
string subdir = fn.GetPath();
if( !gdcm.PosixEmulation.MakeDirectory( subdir ) )
{
    return false;
}

gdcm.FileMetaInformation fmi = ano.GetFile().GetHeader();
// The following three lines make sure to regenerate any value:
fmi.Remove( new gdcm.Tag(0x0002,0x0012) );
fmi.Remove( new gdcm.Tag(0x0002,0x0013) );
fmi.Remove( new gdcm.Tag(0x0002,0x0016) );

Writer writer = new Writer();
writer.SetFileName( outfilename );
writer.SetFile( ano.GetFile() );
ret = writer.Write();
if( !ret )
{
    return false;
}

return true;
}

public static int Main(string[] args)
{
    gdcm.FileMetaInformation.SetSourceApplicationEntityTitle( "My ClinicalTrial App" );

    // http://www.oid-info.com/get/1.3.6.1.4.17434
    string THERALYS_ORG_ROOT = "1.3.6.1.4.17434";
    gdcm.UIDGenerator.SetRoot( THERALYS_ORG_ROOT );
    System.Console.WriteLine( "Root dir is now: " + gdcm.UIDGenerator.GetRoot() );

    gdcm.Global global = gdcm.Global.GetInstance();
    if( !global.LoadResourcesFiles() )
    {
        System.Console.WriteLine( "Could not LoadResourcesFiles" );
        return 1;
    }

    if( args.Length != 2 )
    {
        System.Console.WriteLine( "Usage:" );
        System.Console.WriteLine( "ClinicalTrialIdentificationWorkflow input_dir output_dir" );
        return 1;
    }
    string dir1 = args[0];
    string dir2 = args[1];

    // Check input is valid:
    if( !gdcm.PosixEmulation.FileIsDirectory(dir1) )
    {
        System.Console.WriteLine( "Input directory: " + dir1 + " does not exist. Sorry" );
        return 1;
    }
}

```

```

if( !gdcm.PosixEmulation.FileIsDirectory(dir2) )
{
    System.Console.WriteLine( "Output directory: " + dir2 + " does not exist. Sorry" );
    return 1;
}

// Recursively search all file within this toplevel directory:
Directory d = new Directory();
uint nfiles = d.Load( dir1, true );
if(nfiles == 0) return 1;

// Let's use the pre-shipped certificate of GDCM.
string certpath = gdcm.Filename.Join(gdcm.Testing.GetSourceDirectory(),
    "/Testing/Source/Data/certificate.pem" );
gdcm.CryptoFactory fact = gdcm.CryptoFactory.GetFactoryInstance();
gdcm.CryptographicMessageSyntax cms = fact.CreateCMSProvider();
if( !cms.ParseCertificateFile( certpath ) )
{
    System.Console.WriteLine( "PEM Certificate : " + certpath + " could not be read. Sorry" );
    return 1;
}

//Anonymizer ano = new Anonymizer();
// A reference to an actual C++ instance is required here:
SmartPtrAno sano = Anonymizer.New();
Anonymizer ano = sano.__ref__();

//SimpleSubjectWatcher watcher = new SimpleSubjectWatcher(ano, "Anonymizer");
MyWatcher watcher = new MyWatcher(ano);

// Explicitly specify the Cryptographic Message Syntax to use:
ano.SetCryptographicMessageSyntax( cms );

// Process all filenames:
FilenameType filenames = d.GetFilenames();
for( uint i = 0; i < nfiles; ++i )
{
    string filename = filenames[ (int)i ];
    string outfilename = filename.Replace( dir1, dir2 );
    System.Console.WriteLine( "Filename: " + filename );
    System.Console.WriteLine( "Out Filename: " + outfilename );
    if( !ProcessOneFile( ano , filename, outfilename ) )
    {
        System.Console.WriteLine( "Could not process filename: " + filename );
        return 1;
    }
}

return 0;
}
}

```

12.9 GenerateDICOMDIR.cs

This is a C# example on how to use DICOMDIRGenerator

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/

/*
 * Simple C# example to show how to use DICOMDIRGenerator
 *
 * Usage:
 * $ export LD_LIBRARY_PATH=$HOME/Projects/gdcm/debug-gcc/bin

```

```

* $ mono bin/GenerateDICOMDIR.exe path output_filename
*/
using System;
using gdcmm;

public class GenerateDICOMDIR
{
    public static int Main(string[] args)
    {
        string directory = args[0];
        string outfilename = args[1];

        Directory d = new Directory();
        uint nfiles = d.Load( directory, true );
        if(nfiles == 0) return 1;
        //System.Console.WriteLine( "Files:\n" + d.toString() );

        // Implement fast path ?
        // Scanner s = new Scanner();

        string descriptor = "My_Descriptor";
        FilenamesType filenames = d.GetFilesNames();

        gdcmm.DICOMDIRGenerator gen = new DICOMDIRGenerator();
        gen.SetFilenames( filenames );
        gen.SetDescriptor( descriptor );
        if( !gen.Generate() )
        {
            return 1;
        }

        gdcmm.FileMetaInformation.SetSourceApplicationEntityTitle( "GenerateDICOMDIR" );
        gdcmm.Writer writer = new Writer();
        writer.SetFile( gen.GetFile() );
        writer.SetFileName( outfilename );
        if( !writer.Write() )
        {
            return 1;
        }

        return 0;
    }
}

```

12.10 GenFakelImage.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcmm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.
=====*/
#include "gdcmmImage.h"
#include "gdcmmImageWriter.h"
#include "gdcmmFileDerivation.h"
#include "gdcmmUIDGenerator.h"
#include "gdcmmImageChangePhotometricInterpretation.h"

/*
* This example shows two things:
* 1. How to create an image ex-nihilo
* 2. How to use the gdcmm.FileDerivation filter. This filter is meant to create "DERIVED" image
* object. FileDerivation has a simple API where you can reference *all* the input image that have been
* used to generate the image. The API also allows user to specify the purpose of reference (see CID 7202,
* PS 3.16 - 2008), and the image derivation type (CID 7203, PS 3.16 - 2008).
*/
int main(int, char *[])
{
    // Step 1: Fake Image

```

```

gdcM::SmartPointer<gdcM::Image> im = new gdcM::Image;

char * buffer = new char[ 256 * 256 * 3];
char * p = buffer;
int b = 128;
//int ybr[3];
int ybr2[3];
//int rgb[3];

for(int r = 0; r < 256; ++r)
    for(int g = 0; g < 256; ++g)
        //for(int b = 0; b < 256; ++b)
        {
            //rgb[0] = r;
            //rgb[1] = g;
            //rgb[1] = 128;
            //rgb[2] = b;
            //ybr[0] = r;
            //ybr[1] = g;
            //ybr[1] = 128;
            //ybr[2] = b;

            ybr2[0] = r;
            ybr2[1] = g;
            ybr2[1] = 128;
            ybr2[2] = b;
            //gdcM::ImageChangePhotometricInterpretation::YBR2RGB(rgb, ybr);
            //gdcM::ImageChangePhotometricInterpretation::RGB2YBR(ybr2, rgb);
            *p++ = (char)ybr2[0];
            *p++ = (char)ybr2[1];
            *p++ = (char)ybr2[2];
        }

im->SetNumberOfDimensions( 2 );
im->SetDimension(0, 256 );
im->SetDimension(1, 256 );

im->GetPixelFormat().SetSamplesPerPixel(3);
//im->SetPhotometricInterpretation( gdcM::PhotometricInterpretation::RGB );
im->SetPhotometricInterpretation( gdcM::PhotometricInterpretation::YBR_FULL );

unsigned long l = im->GetBufferLength();
if( l != 256 * 256 * 3 )
{
    return 1;
}
gdcM::DataElement pixeldata( gdcM::Tag(0x7fe0,0x0010) );
pixeldata.SetByteValue( buffer, (uint32_t)l );
delete[] buffer;
im->SetDataElement( pixeldata );

gdcM::UIDGenerator uid; // helper for uid generation

gdcM::SmartPointer<gdcM::File> file = new gdcM::File; // empty file

// Step 2: DERIVED object
gdcM::FileDerivation fd;
// For the purpose of this exercise we will pretend that this image is referencing
// two source image (we need to generate fake UID for that).
const char ReferencedSOPClassUID[] = "1.2.840.10008.5.1.4.1.1.7"; // Secondary Capture
fd.AddReference( ReferencedSOPClassUID, uid.Generate() );
fd.AddReference( ReferencedSOPClassUID, uid.Generate() );

// Again for the purpose of the exercise we will pretend that the image is a
// multiplanar reformat (MPR):
// CID 7202 Source Image Purposes of Reference
// {"DCM",121322,"Source image for image processing operation"},
fd.SetPurposeOfReferenceCodeSequenceCodeValue( 121322 );
// CID 7203 Image Derivation
// { "DCM",113072,"Multiplanar reformatting" },
fd.SetDerivationCodeSequenceCodeValue( 113072 );
fd.SetFile( *file );
// If all Code Value are ok the filter will execute properly
if( !fd.Derive() )
{
    std::cerr << "Sorry could not derive using input info" << std::endl;
    return 1;
}

// We pass both :
// 1. the fake generated image

```

```

// 2. the 'DERIVED' dataset object
// to the writer.
gdcm::ImageWriter w;
w.SetImage( *im );
w.SetFile( fd.GetFile() );

// Set the filename:
w.SetFileName( "ybr2.dcm" );
if( !w.Write() )
{
    return 1;
}

return 0;
}

```

12.11 ReformatFile.cs

This is a C++ example on how to use FileDerivation

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/

/*
 * Simple C# example
 *
 * Usage:
 * $ export LD_LIBRARY_PATH=$HOME/Projects/gdcm/debug-gcc/bin
 * $ mono bin/ReformatFile.exe input.dcm output.dcm
 */
using System;
using gdcm;

public class ReformatFile
{
    public static int Main(string[] args)
    {
        gdcm.FileMetaInformation.SetSourceApplicationEntityTitle( "My Reformat App" );

        // http://www.oid-info.com/get/1.3.6.1.4.17434
        string THERALYS_ORG_ROOT = "1.3.6.1.4.17434";
        gdcm.UIDGenerator.SetRoot( THERALYS_ORG_ROOT );
        System.Console.WriteLine( "Root dir is now: " + gdcm.UIDGenerator.GetRoot() );

        string filename = args[0];
        string outfilename = args[1];

        Reader reader = new Reader();
        reader.SetFileName( filename );
        if( !reader.Read() )
        {
            System.Console.WriteLine( "Could not read: " + filename );
            return 1;
        }

        UIDGenerator uid = new UIDGenerator(); // helper for uid generation
        FileDerivation fd = new FileDerivation();
        // For the purpose of this exercise we will pretend that this image is referencing
        // two source image (we need to generate fake UID for that).
        string ReferencedSOPClassUID = "1.2.840.10008.5.1.4.1.1.7"; // Secondary Capture
        fd.AddReference( ReferencedSOPClassUID, uid.Generate() );
        fd.AddReference( ReferencedSOPClassUID, uid.Generate() );

        // Again for the purpose of the exercise we will pretend that the image is a

```

```

// multiplanar reformat (MPR):
// CID 7202 Source Image Purposes of Reference
// {"DCM",121322,"Source image for image processing operation"},
fd.SetPurposeOfReferenceCodeSequenceCodeValue( 121322 );
// CID 7203 Image Derivation
// {"DCM",113072,"Multiplanar reformatting" },
fd.SetDerivationCodeSequenceCodeValue( 113072 );
fd.SetFile( reader.GetFile() );
// If all Code Value are ok the filter will execute properly
if( !fd.Derive() )
{
    return 1;
}

gdcm.FileMetaInformation fmi = reader.GetFile().GetHeader();
// The following three lines make sure to regenerate any value:
fmi.Remove( new gdcm.Tag(0x0002,0x0012) );
fmi.Remove( new gdcm.Tag(0x0002,0x0013) );
fmi.Remove( new gdcm.Tag(0x0002,0x0016) );

Writer writer = new Writer();
writer.SetFileName( outfilename );
writer.SetFile( fd.GetFile() );
if( !writer.Write() )
{
    System.Console.WriteLine( "Could not write: " + outfilename );
    return 1;
}

return 0;
}
}

```

12.12 DecompressImage.cs

This is a C# example on how to use Image

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/

/*
 * Usage:
 * $ export LD_LIBRARY_PATH=$HOME/Projects/gdcm/debug-gcc/bin
 * $ mono bin/DecompressImage.exe gdcmData/012345.002.050.dcm decompress.dcm
 */
using System;
using gdcm;

public class DecompressImage
{
    public static int Main(string[] args)
    {
        {
            string file1 = args[0];
            string file2 = args[1];
            ImageReader reader = new ImageReader();
            reader.SetFileName( file1 );
            bool ret = reader.Read();
            if( !ret )
            {
                return 1;
            }
        }

        // check that one can access a Fragment from C#:
    }
}

```

```

var de = reader.GetFile().GetDataSet().GetDataElement(new Tag(0x7fe0, 0x0010));
var sq = de.GetSequenceOfFragments();
sq.GetFragment(0);

Image image = new Image();
Image ir = reader.GetImage();

image.SetNumberOfDimensions( ir.GetNumberOfDimensions() );

//Just for fun:
//int dircos = ir.GetDirectionCosines();
//t = gdcm.Orientation.GetType(dircos);
//int l = gdcm.Orientation.GetLabel(t);
//System.Console.WriteLine( "Orientation label:" + l );

// Set the dimensions,
// 1. either one at a time
//image.SetDimension(0, ir.GetDimension(0) );
//image.SetDimension(1, ir.GetDimension(1) );

// 2. the array at once
uint[] dims = {0, 0};
// Just for fun let's invert the dimensions:
dims[0] = ir.GetDimension(1);
dims[1] = ir.GetDimension(0);
ir.SetDimensions( dims );

PixelFormat pixeltype = ir.GetPixelFormat();
image.SetPixelFormat( pixeltype );

PhotometricInterpretation pi = ir.GetPhotometricInterpretation();
image.SetPhotometricInterpretation( pi );

DataElement pixeldata = new DataElement( new Tag(0x7fe0,0x0010) );
byte[] str1 = new byte[ ir.GetBufferLength()];
ir.GetBuffer( str1 );
//System.Console.WriteLine( ir.GetBufferLength() );
pixeldata.SetByteValue( str1, new VL( (uint)str1.Length ) );
//image.SetDataElement( pixeldata );
ir.SetDataElement( pixeldata );

ImageWriter writer = new ImageWriter();
writer.SetFileName( file2 );
writer.SetFile( reader.GetFile() );
writer.SetImage( ir );
ret = writer.Write();
if( !ret )
{
    return 1;
}

return 0;
}
}

```

12.13 StandardizeFiles.cs

This is a C++ example on how to use ImageChangeTransferSyntax

```

/*=====

Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
/*

```

```

* Simple C# example to show how one would 'Standardize' a DICOM File-Set
*
* Usage:
* $ export LD_LIBRARY_PATH=$HOME/Projects/gdcm/debug-gcc/bin
* $ mono bin/StandardizeFiles.exe input_path output_path
*/
using System;
using gdcm;

public class StandardizeFiles
{
    public static bool ProcessOneFile( string filename, string outfilename )
    {
        PixmapReader reader = new PixmapReader();
        reader.SetFileName( filename );
        if( !reader.Read() )
        {
            System.Console.WriteLine( "Could not read: " + filename );
            return false;
        }

        ImageChangeTransferSyntax change = new ImageChangeTransferSyntax();
        change.SetForce( false ); // do we really want to recompress when input is already compressed in same alg ?
        change.SetCompressIconImage( false ); // Keep it simple
        change.SetTransferSyntax( new TransferSyntax( TransferSyntax.TSType.JPEG2000Lossless ) );
        change.SetInput( reader.GetPixmap() );
        if( !change.Change() )
        {
            System.Console.WriteLine( "Could not change: " + filename );
            return false;
        }

        gdcm.FileMetaInformation fmi = reader.GetFile().GetHeader();
        // The following three lines make sure to regenerate any value:
        fmi.Remove( new gdcm.Tag(0x0002,0x0012) );
        fmi.Remove( new gdcm.Tag(0x0002,0x0013) );
        fmi.Remove( new gdcm.Tag(0x0002,0x0016) );

        PixmapWriter writer = new PixmapWriter();
        writer.SetFileName( outfilename );
        writer.SetFile( reader.GetFile() );
        gdcm.Pixmap pixout = ((PixmapToPixmapFilter)change).GetOutput();

        writer.SetPixmap( pixout );
        if( !writer.Write() )
        {
            System.Console.WriteLine( "Could not write: " + outfilename );
            return false;
        }

        return true;
    }

    public static int Main(string[] args)
    {
        gdcm.FileMetaInformation.SetSourceApplicationEntityTitle( "My Standardize App" );

        // http://www.oid-info.com/get/1.3.6.1.4.17434
        string THERALYS_ORG_ROOT = "1.3.6.1.4.17434";
        gdcm.UIDGenerator.SetRoot( THERALYS_ORG_ROOT );
        System.Console.WriteLine( "Root dir is now: " + gdcm.UIDGenerator.GetRoot() );

        string dir1 = args[0];
        string dir2 = args[1];

        // Check input is valid:
        if( !gdcm.PosixEmulation.FileIsDirectory(dir1) )
        {
            System.Console.WriteLine( "Input directory: " + dir1 + " does not exist. Sorry" );
            return 1;
        }
        if( !gdcm.PosixEmulation.FileIsDirectory(dir2) )
        {
            System.Console.WriteLine( "Output directory: " + dir2 + " does not exist. Sorry" );
            return 1;
        }

        Directory d = new Directory();
        uint nfiles = d.Load( dir1, true );
    }
}

```



```

        if(nfiles == 0) return 1;

        // Process all filenames:
        FilenamesType filenames = d.GetFilesNames();
        for( uint i = 0; i < nfiles; ++i )
        {
            string filename = filenames[ (int)i ];
            string outfilename = filename.Replace( dir1, dir2 );
            System.Console.WriteLine( "Filename: " + filename );
            System.Console.WriteLine( "Out Filename: " + outfilename );
            if( !ProcessOneFile( filename, outfilename ) )
            {
                System.Console.WriteLine( "Could not process filename: " + filename );
                //return 1;
            }
        }

        return 0;
    }
}

```

12.14 ScanDirectory.cs

This is a C# example on how to use Scanner

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/

/*
 * Usage:
 * $ bin/ScanDirectory.exe /path/to/gdcmData/
 */
using System;
using gdcm;

// We will print each filename being processed
public class MyWatcher : SimpleSubjectWatcher
{
    public MyWatcher(Subject s):base(s,"Override String"){
    protected override void ShowFileName(Subject caller, Event evt){
        FileNameEvent fne = FileNameEvent.Cast(evt);
        if( fne != null )
        {
            string fn = fne.GetFileName();
            System.Console.WriteLine( "This is my Scanner. Processing FileName: " + fn );
        }
        else
        {
            System.Console.WriteLine( "This is my Anonymization. Unhandled Event type: " + evt.GetEventName() );
        }
    }
}

public class ScanDirectory
{
    public static int Main(string[] args)
    {
        string directory = args[0];
        Tag t = new Tag(0x8,0x80);

        Directory d = new Directory();
        uint nfiles = d.Load( directory );
        if(nfiles == 0) return 1;
    }
}

```

```

//System.Console.WriteLine( "Files:\n" + d.toString() );

// Use a StrictScanner, need to use a reference to pass the C++ pointer to
// MyWatcher implementation
SmartPtrStrictScan sscan = StrictScanner.New();
StrictScanner s = sscan.__ref__();
MyWatcher watcher = new MyWatcher(s);

s.AddTag( t );
bool b = s.Scan( d.GetFilesNames() );
if(!b) return 1;

for(int i = 0; i < (int)nfiles; ++i)
{
    if( !s.IsKey( d.GetFilesNames()[i] ) )
    {
        System.Console.WriteLine( "File is not DICOM or could not be read: " + d.GetFilesNames()[i] );
    }
}

System.Console.WriteLine( "Scan:\n" + s.toString() );

System.Console.WriteLine( "success" );
return 0;
}
}

```

12.15 BasicAnonymizer.cs

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/

/*
 * Usage:
 * $ export LD_LIBRARY_PATH=$HOME/Projects/gdcm/debug-gcc/bin
 * $ mono bin/BasicAnonymizer.exe gdcmData/012345.002.050.dcm out.dcm
 */
using System;
using gdcm;

public class MyWatcher : SimpleSubjectWatcher
{
    public MyWatcher(Subject s):base(s,"Override String"){
    protected override void StartFilter() {
        System.Console.WriteLine( "This is my start" );
    }
    protected override void EndFilter(){
        System.Console.WriteLine( "This is my end" );
    }
    protected override void ShowProgress(Subject caller, Event evt){
        ProgressEvent pe = ProgressEvent.Cast(evt);
        System.Console.WriteLine( "This is my progress: " + pe.GetProgress() );
    }
    protected override void ShowIteration(){
        System.Console.WriteLine( "This is my iteration" );
    }
    protected override void ShowAnonymization(Subject caller, Event evt){
/*
 * A couple of explanation are necessary here to understand how SWIG work
 * http://www.swig.org/Doc1.3/Java.html#adding_downcasts
 *
 * System.Console.WriteLine( "This is my Anonymization. Type: " + evt.GetEventName() );
 * System.Type type = evt.GetType();
 * System.Console.WriteLine( "This is my Anonymization. System.Type: " + type.ToString() );
 * System.Console.WriteLine( "This is my Anonymization. CheckEvent: " + ae.CheckEvent( evt ) );
 */
    }
}

```

```

* System.Console.WriteLine( "This is my Anonymization. Processing Tag #" + ae.GetTag().ToString() );
*/
AnonymizeEvent ae = AnonymizeEvent.Cast(evt);
if( ae != null )
{
    Tag t = ae.GetTag();
    System.Console.WriteLine( "This is my Anonymization. Processing Tag #" + t.ToString() );
}
else
{
    System.Console.WriteLine( "This is my Anonymization. Unhandled Event type: " + evt.GetEventName() );
}
}
protected override void ShowAbort(){
    System.Console.WriteLine( "This is my abort" );
}
}

public class BasicAnonymizer
{
    public static int Main(string[] args)
    {
        gdcn.Global global = gdcn.Global.GetInstance();
        if( !global.LoadResourcesFiles() )
        {
            System.Console.WriteLine( "Could not LoadResourcesFiles" );
            return 1;
        }

        string file1 = args[0];
        string file2 = args[1];
        Reader reader = new Reader();
        reader.SetFileName( file1 );
        bool ret = reader.Read();
        if( !ret )
        {
            return 1;
        }

        string certpath = gdcn.Filename.Join(gdcn.Testing.GetSourceDirectory(),
            "/Testing/Source/Data/certificate.pem" );
        gdcn.CryptoFactory fact = gdcn.CryptoFactory.GetFactoryInstance();
        gdcn.CryptographicMessageSyntax cms = fact.CreateCMSProvider();
        if( !cms.ParseCertificateFile( certpath ) )
        {
            return 1;
        }

        //Anonymizer ano = new Anonymizer();
        SmartPtrAno sano = Anonymizer.New();
        Anonymizer ano = sano.__ref__();

        //SimpleSubjectWatcher watcher = new SimpleSubjectWatcher(ano, "Anonymizer");
        MyWatcher watcher = new MyWatcher(ano);

        ano.SetFile( reader.GetFile() );
        ano.SetCryptographicMessageSyntax( cms );
        if( !ano.BasicApplicationLevelConfidentialityProfile() )
        {
            return 1;
        }

        Writer writer = new Writer();
        writer.SetFileName( file2 );
        writer.SetFile( ano.GetFile() );
        ret = writer.Write();
        if( !ret )
        {
            return 1;
        }

        return 0;
    }
}

```

12.16 BasicImageAnonymizer.cs

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/

/*
 */
using System;
using gdcm;

public class BasicImageAnonymizer
{
    public static int Main(string[] args)
    {
        string filename = args[0];

        // instantiate the reader:
        gdcm.ImageReader reader = new gdcm.ImageReader();
        reader.SetFileName( filename );

        if (!reader.Read()) return 1;

        Image ir = reader.GetImage();

        uint[] dims = {0, 0, 0};
        dims[0] = ir.GetDimension(0);
        dims[1] = ir.GetDimension(1);
        dims[2] = ir.GetDimension(2);
        System.Console.WriteLine( "Dim:" + dims[0] );
        System.Console.WriteLine( "Dim:" + dims[1] );
        System.Console.WriteLine( "Dim:" + dims[2] );

        // buffer to get the pixels
        byte[] buffer = new byte[ ir.GetBufferLength()];
        System.Console.WriteLine( "Dim:" + ir.GetBufferLength() );
        ir.GetBuffer( buffer );

        for (uint z = 0; z < dims[2]; z++)
        {
            for (uint y = 0; y < dims[1] / 2; y++) // only half Y
            {
                for (uint x = 0; x < dims[0] / 2; x++) // only half X
                {
                    buffer[ (z * dims[1] + y) * dims[0] + x ] = 0; // works when pixel type == UINT8
                }
            }
        }

        DataElement pixeldata = new DataElement( new Tag(0x7fe0,0x0010) );
        pixeldata.SetByteValue( buffer, new VL( (uint)buffer.Length ) );
        ir.SetDataElement( pixeldata );
        ir.SetTransferSyntax( new TransferSyntax( TransferSyntax.TSType.ExplicitVRLittleEndian ) );

        ImageChangeTransferSyntax change = new ImageChangeTransferSyntax();
        change.SetTransferSyntax( new TransferSyntax( TransferSyntax.TSType.JPEGLSLossless ) );
        change.SetInput( ir );
        if( !change.Change() )
        {
            System.Console.WriteLine( "Could not change: " + filename );
            return 1;
        }

        ImageWriter writer = new ImageWriter();
        writer.SetFileName( "out.dcm" );
        writer.SetFile( reader.GetFile() );
        writer.SetImage( change.GetOutput() );
        bool ret = writer.Write();
        if( !ret )
        {

```

```

        return 1;
    }

    return 0;
}

```

12.17 Cleaner.cs

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/

/*
 * Usage:
 * $ export LD_LIBRARY_PATH=$HOME/Projects/gdcm/debug-gcc/bin
 * $ mono bin/Cleaner.exe gdcmData/012345.002.050.dcm out.dcm
 */
using System;
using gdcm;

public class MyWatcher : SimpleSubjectWatcher
{
    public MyWatcher(Subject s):base(s,"Override String"){
    protected override void StartFilter() {
        System.Console.WriteLine( "This is my start" );
    }
    protected override void EndFilter(){
        System.Console.WriteLine( "This is my end" );
    }
    protected override void ShowProgress(Subject caller, Event evt){
        ProgressEvent pe = ProgressEvent.Cast(evt);
        System.Console.WriteLine( "This is my progress: " + pe.GetProgress() );
    }
    protected override void ShowIteration(){
        System.Console.WriteLine( "This is my iteration" );
    }
    protected override void ShowAnonymization(Subject caller, Event evt){
/*
 * A couple of explanation are necessary here to understand how SWIG work
 * http://www.swig.org/Doc1.3/Java.html#adding_downcasts
 *
 * System.Console.WriteLine( "This is my Anonymization. Type: " + evt.GetEventName() );
 * System.Type type = evt.GetType();
 * System.Console.WriteLine( "This is my Anonymization. System.Type: " + type.ToString() );
 * System.Console.WriteLine( "This is my Anonymization. CheckEvent: " + ae.CheckEvent( evt ) );
 * System.Console.WriteLine( "This is my Anonymization. Processing Tag #" + ae.GetTag().toString() );
 */
        AnonymizeEvent ae = AnonymizeEvent.Cast(evt);
        if( ae != null )
        {
            Tag t = ae.GetTag();
            System.Console.WriteLine( "This is my Anonymization. Processing Tag #" + t.toString() );
        }
        else
        {
            System.Console.WriteLine( "This is my Anonymization. Unhandled Event type: " + evt.GetEventName() );
        }
    }
    protected override void ShowAbort(){
        System.Console.WriteLine( "This is my abort" );
    }
}

public class Cleaner

```

```

{
    public static int Main(string[] args)
    {
        gdc.Global global = gdc.Global.GetInstance();
        if( !global.LoadResourcesFiles() )
        {
            System.Console.WriteLine( "Could not LoadResourcesFiles" );
            return 1;
        }

        string file1 = args[0];
        string file2 = args[1];
        Reader reader = new Reader();
        reader.SetFileName( file1 );
        bool ret = reader.Read();
        if( !ret )
        {
            return 1;
        }

        SmartPtrCleaner scleaner = gdc.Cleaner.New();
        gdc.Cleaner cleaner = scleaner.__ref__();

        //SimpleSubjectWatcher watcher = new SimpleSubjectWatcher(cleaner, "Anonymizer");
        MyWatcher watcher = new MyWatcher(cleaner);

        cleaner.SetFile( reader.GetFile() );
        cleaner.Empty( new gdc.VR(gdc.VR.VRType.PN) );
        gdc.DPath dpath = new gdc.DPath();
        dpath.ConstructFromString( "/0010,0010" );
        cleaner.Preserve( dpath );
        gdc.Tag t1 = new gdc.Tag(0x10, 0x30);
        cleaner.Empty( t1 );
        gdc.PrivateTag pt0 = new gdc.PrivateTag( new gdc.Tag(0x29,0x60), "SIEMENS MEDCOM HEADER2" );
        cleaner.Remove( pt0 );
        gdc.PrivateTag pt1 = new gdc.PrivateTag( new gdc.Tag(0x29,0x10), "SIEMENS CSA HEADER" );
        gdc.PrivateTag pt2 = new gdc.PrivateTag( new gdc.Tag(0x29,0x20), "SIEMENS CSA HEADER" );
        cleaner.Scrub( pt1 );
        cleaner.Scrub( pt2 );
        if( !cleaner.Clean() )
        {
            return 1;
        }

        Writer writer = new Writer();
        writer.SetFileName( file2 );
        writer.SetFile( cleaner.GetFile() );
        ret = writer.Write();
        if( !ret )
        {
            return 1;
        }

        return 0;
    }
}

```

12.18 CompressLossyJPEG.cs

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdc.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
/*
* Usage:
* $ export LD_LIBRARY_PATH=$HOME/Perso/gdc/debug-gcc/bin
* $ mono bin/CompressLossyJPEG.exe input.dcm output.dcm

```

```

*/

using System;
using gdcm;

public class CompressLossyJPEG
{
    public static int Main(string[] args)
    {
        if( args.Length < 2 )
        {
            System.Console.WriteLine( " input.dcm output.dcm" );
            return 1;
        }
        string filename = args[0];
        string outfilename = args[1];

        ImageReader reader = new ImageReader();
        reader.SetFileName( filename );
        if( !reader.Read() )
        {
            System.Console.WriteLine( "Could not read: " + filename );
            return 1;
        }

        // The output of gdcm::Reader is a gdcm::File
        File file = reader.GetFile();

        // the dataset is the the set of element we are interested in:
        DataSet ds = file.GetDataSet();

        Image image = reader.GetImage();
        //image.Print( cout );

        ImageChangeTransferSyntax change = new ImageChangeTransferSyntax();
        TransferSyntax targetts = new TransferSyntax( TransferSyntax.TSType.JPEGBaselineProcess1 );
        change.SetTransferSyntax( targetts );

        // Setup our JPEGCodec, warning it should be compatible with JPEGBaselineProcess1
        JPEGCodec jpegcodec = new JPEGCodec();
        if( !jpegcodec.CanCode( targetts ) )
        {
            System.Console.WriteLine( "Something went really wrong, JPEGCodec cannot handle JPEGBaselineProcess1" );
            return 1;
        }
        jpegcodec.SetLossless( false );
        jpegcodec.SetQuality( 50 ); // poor quality !
        change.SetUserCodec( jpegcodec ); // specify the codec to use to the ImageChangeTransferSyntax

        change.SetInput( image );
        bool b = change.Change();
        if( !b )
        {
            System.Console.WriteLine( "Could not change the Transfer Syntax" );
            return 1;
        }

        ImageWriter writer = new ImageWriter();
        writer.SetImage( (gdcm.Image)change.GetOutput() );
        writer.SetFile( reader.GetFile() );
        writer.SetFileName( outfilename );
        if( !writer.Write() )
        {
            System.Console.WriteLine( "Could not write: " + outfilename );
            return 1;
        }

        return 0;
    }
}

```

12.19 DecompressImageMultiframe.cs

```

/*=====

```

```

Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/

/*
$ gdcminfo ~/Desktop/angiogram-06.dcm
MediaStorage is 1.2.840.10008.5.1.4.1.1.12.1 [X-Ray Angiographic Image Storage]
TransferSyntax is 1.2.840.10008.1.2.4.50 [JPEG Baseline (Process 1): Default Transfer Syntax for Lossy JPEG 8
  Bit Image Compression]
NumberOfDimensions: 3
Dimensions: (512,512,355)
Origin: (0,0,0)
Spacing: (1,1,40)
DirectionCosines: (1,0,0,0,1,0)
Rescale Intercept/Slope: (0,1)
SamplesPerPixel :1
BitsAllocated :8
BitsStored :8
HighBit :7
PixelRepresentation:0
ScalarType found :UINT8
PhotometricInterpretation: MONOCHROME2
PlanarConfiguration: 0
TransferSyntax: 1.2.840.10008.1.2.4.50
Orientation Label: AXIAL
*/

/*
* Description:
*
* Assume we have a file angiogram-06.dcm as described above.
* the following program will decompress directly from the extracted jpeg stream.
*
* First step extract the jpeg stream (but not the Basic Offset Table):
*
* $ gdcmrw -i angiogram-06.dcm -o /tmp/output/chris --split-frags --pattern %d.jpg
*
* Check that indeed there are 355 files, while there are 356 fragments in the original DICOM file, since
* gdcmrw always skip the first fragment (Basic Offset Table).
*
* Now from those individual jpeg stream, recreate a fake gdcm.DataElement...
*
* Usage:
*
* $ export LD_LIBRARY_PATH=$HOME/Projects/gdcm/debug-gcc/bin
* $ mono ./bin/DecompressImageMultiframe.exe /tmp/output
*/
using System;
using gdcm;

public class DecompressImageMultiframe
{
    public static int Main(string[] args)
    {
        string directory = args[0];
        gdcm.Directory dir = new gdcm.Directory();
        uint nfiles = dir.Load(directory);
        //System.Console.WriteLine(dir.toString());
        gdcm.FilenamesType filenames = dir.GetFilesNames();

        Image image = new Image();
        image.SetNumberOfDimensions( 3 ); // important for now
        DataElement pixeldata = new DataElement( new gdcm.Tag(0x7fe0,0x0010) );

        // Create a new SequenceOfFragments C++ object, store it as a SmartPointer :
        SmartPtrFrag sq = SequenceOfFragments.New();

        // Yeah, the files are not guaranteed to be in order, please adapt...
        for(uint i = 0; i < nfiles; ++i)
        {
            System.Console.WriteLine( filenames[(int)i] );
            string file = filenames[(int)i];
            System.IO.FileStream infile =

```



```

        new System.IO.FileStream(file, System.IO.FileMode.Open, System.IO.FileAccess.Read);
        uint fsize = gdcm.PosixEmulation.FileSize(file);

        byte[] jstream = new byte[fsize];
        infile.Read(jstream, 0, jstream.Length);

        Fragment frag = new Fragment();
        frag.SetByteValue( jstream, new gdcm.VL( (uint)jstream.Length) );
        sq.AddFragment( frag );
    }

    // Pass by reference:
    pixeldata.SetValue( sq.__ref__() );

    // insert:
    image.SetDataElement( pixeldata );

    // JPEG use YBR to achieve better compression ratio by default (not RGB)
    // FIXME hardcoded:
    PhotometricInterpretation pi = new PhotometricInterpretation( PhotometricInterpretation.PIType.MONOCHROME2
    );
    image.SetPhotometricInterpretation( pi );
    // FIXME hardcoded:
    PixelFormat pixeltype = new PixelFormat(1,8,8,7);
    image.SetPixelFormat( pixeltype );

    // FIXME hardcoded:
    image.SetTransferSyntax( new TransferSyntax( TransferSyntax.TSType.JPEGLosslessProcess14_1 ) );
    image.SetDimension(0, 512);
    image.SetDimension(1, 512);
    image.SetDimension(2, 355);

    // Decompress !
    byte[] decompressedData = new byte[(int)image.GetBufferLength()];
    image.GetBuffer(decompressedData);

    // Write out the decompressed bytes
    System.Console.WriteLine(image.toString());
    using (System.IO.Stream stream =
        System.IO.File.Open(@"tmp/dd.raw",
            System.IO.FileMode.Create))
    {
        System.IO.BinaryWriter writer = new System.IO.BinaryWriter(stream);
        writer.Write(decompressedData);
    }

    return 0;
}

```

12.20 DumpCSA.cs

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/

/*
 * Usage:
 * $ bin/DumpCSA.exe input.dcm
 */
using System;
using gdcm;

public class DumpCSA
{

```

```

public static int Main(string[] args)
{
    string filename = args[0];

    gdcm.Reader reader = new gdcm.Reader();
    reader.SetFileName( filename );
    if (!reader.Read()) return 1;

    gdcm.File f = reader.GetFile();
    gdcm.DataSet ds = f.GetDataSet();

    string[] expectedSiemensTags = new string[] { "B_value" , "AcquisitionMatrixText" };
    using (PrivateTag gtag = CSAHeader.GetCSAImageHeaderInfoTag())
    {
        if (ds.FindDataElement(gtag))
        {
            using (DataElement de = ds.GetDataElement(gtag))
            {
                if (de != null && !de.IsEmpty())
                {
                    using (CSAHeader csa = new CSAHeader())
                    {
                        if (csa.LoadFromDataElement(de))
                        {
                            foreach (string str in expectedSiemensTags)
                            {
                                if (csa.FindCSAElementByName(str))
                                {
                                    using (CSAElement elem = csa.GetCSAElementByName(str))
                                    {
                                        if (elem != null)
                                        {
                                            System.Console.WriteLine( elem.toString() );
                                        }
                                    }
                                }
                            }
                        }
                    }
                }
            }
        }
    }

    return 0;
}

```

12.21 ExplicitLittleEndian.cs

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/

/*
 * Simple C# example to show how one would 'Standardize' a DICOM File-Set
 *
 * Usage:
 * $ export LD_LIBRARY_PATH=$HOME/Projects/gdcm/debug-gcc/bin
 * $ mono bin/StandardizeFiles.exe input_path output_path
 */
using System;
using gdcm;

public class ExplicitLittleEndian

```

```

{
    public static bool ToExplicitLittleEndian(string aSrc, string aDst)
    {
        using (ImageReader reader = new ImageReader())
        {
            bool b = System.IO.File.Exists(aSrc);
            reader.SetFileName(aSrc);
            if (!reader.Read())
            {
                throw new System.Exception(string.Format("Cannot read '{0}'", aSrc));
            }
            using (FileExplicitFilter fef = new FileExplicitFilter())
            {
                fef.SetChangePrivateTags(false);
                fef.SetFile(reader.GetFile());
                if (!fef.Change())
                {
                    throw new System.Exception(string.Format("Cannot make explicit '{0}'", aSrc));
                }
            }
            using (var syntax = new TransferSyntax(TransferSyntax.TSType.ExplicitVRLittleEndian))
            {
                using (ImageChangeTransferSyntax tsc = new ImageChangeTransferSyntax())
                {
                    tsc.SetTransferSyntax(syntax);
                    tsc.SetInput(reader.GetImage());
                    tsc.SetForce(true);
                    if (!tsc.Change())
                    {
                        throw new System.Exception(string.Format("Cannot change '{0}'", aSrc));
                    }
                }
                using (var writer = new ImageWriter())
                {
                    writer.SetFile(fef.GetFile());
                    writer.SetImage(tsc.GetOutput());
                    writer.SetFileName(aDst);
                    if (!writer.Write())
                    {
                        throw new System.Exception(string.Format("Cannot write to '{0}'", aDst));
                    }
                }
            }
        }
    }
}

public static int Main(string[] args)
{
    gdcmm.FileMetaInformation.SetSourceApplicationEntityTitle( "My Standardize App" );

    // http://www.oid-info.com/get/1.3.6.1.4.1.7434
    string THERALYS_ORG_ROOT = "1.3.6.1.4.1.7434";
    gdcmm.UIDGenerator.SetRoot( THERALYS_ORG_ROOT );
    System.Console.WriteLine( "Root dir is now: " + gdcmm.UIDGenerator.GetRoot() );

    string dir1 = args[0];
    string dir2 = args[1];

    // Check input is valid:
    if( !gdcmm.PosixEmulation.FileIsDirectory(dir1) )
    {
        System.Console.WriteLine( "Input directory: " + dir1 + " does not exist. Sorry" );
        return 1;
    }
    if( !gdcmm.PosixEmulation.FileIsDirectory(dir2) )
    {
        System.Console.WriteLine( "Output directory: " + dir2 + " does not exist. Sorry" );
        return 1;
    }

    Directory d = new Directory();
    uint nfiles = d.Load( dir1, true );
    if(nfiles == 0) return 1;

    // Process all filenames:
    FilenamesType filenames = d.GetFilesNames();
    for( uint i = 0; i < nfiles; ++i )
    {
        string filename = filenames[ (int)i ];
        string outfilename = filename.Replace( dir1, dir2 );
    }
}

```

```

        System.Console.WriteLine( "Filename: " + filename );
        System.Console.WriteLine( "Out Filename: " + outfilename );
        if( !ToExplicitLittleEndian( filename, outfilename ) )
        {
            System.Console.WriteLine( "Could not process filename: " + filename );
            //return 1;
        }
    }

    return 0;
}
}

```

12.22 ExtractEncapsulatedFile.cs

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

    This software is distributed WITHOUT ANY WARRANTY; without even
    the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
    PURPOSE. See the above copyright notice for more information.
=====*/

/*
 * This example shows how one from C# context can extract a binary blob
 * and write out as a file.
 * This example is meant for pdf encapsulated file, but can be adapted for other type
 * of binary blob.
 *
 * DICOM file is:
 * ...
 * (0042,0010) ST (no value available) # 0, 0 DocumentTitle
 * (0042,0011) OB 25\50\44\46\2d\31\2e\32\20\0d\25\e2\e3\cf\d3\20\0d\31\30\20\30\20... # 40718, 1
 *     EncapsulatedDocument
 * (0042,0012) LO [application/pdf] # 16, 1 MIMETimeTypeOfEncapsulatedDocument
 * ...
 *
 * Usage:
 * $ export LD_LIBRARY_PATH=$HOME/Projects/gdcm/debug-gcc/bin
 * $ mono bin/ExtractEncapsulatedFile.exe some_pdf_encapsulated.dcm
 */
using System;
using gdcm;

public class ExtractEncapsulatedFile
{
    public static int Main(string[] args)
    {
        string file = args[0];
        Reader reader = new Reader();
        reader.SetFileName( file );
        bool ret = reader.Read();
        if( !ret )
        {
            return 1;
        }

        File f = reader.GetFile();
        DataSet ds = f.GetDataSet();
        Tag tencapsulated_stream = new Tag(0x0042,0x0011); // Encapsulated Document
        if( !ds.FindDataElement( tencapsulated_stream ) )
        {
            return 1;
        }
        // else
        DataElement de = ds.GetDataElement( tencapsulated_stream );
        ByteValue bv = de.GetByteValue();
        uint len = bv.GetLength();
        byte[] encapsulated_stream = new byte[len];
    }
}

```

```

        bv.GetBuffer( encapsulated_stream, len );

        // Write out the decompressed bytes
        //System.Console.WriteLine(image.toString());
        using (System.IO.Stream stream =
            System.IO.File.Open(@"tmp/dd.pdf",
                System.IO.FileMode.Create))
        {
            System.IO.BinaryWriter writer = new System.IO.BinaryWriter(stream);
            writer.Write( encapsulated_stream );
        }

        return 0;
    }
}

```

12.23 ExtractImageRegion.cs

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/

/*
 * This small code shows how to use the gdcm.ImageRegionReader API
 * In this example we are taking each frame by frame and dump them to
 * /tmp/frame.raw.
 *
 * Usage:
 * $ bin/ExtractImageRegion.exe input.dcm
 *
 * Example:
 * $ bin/ExtractImageRegion.exe gdcmData/012345.002.050.dcm
 * $ md5sum /tmp/frame.raw
 * d594a5e2fde12f32b6633ca859b4d4a6 /tmp/frame.raw
 * $ gdcminfo --md5sum gdcmData/012345.002.050.dcm
 * [...]
 * md5sum: d594a5e2fde12f32b6633ca859b4d4a6
 */
using System;
using gdcm;

public class ExtractImageRegion
{
    public static int Main(string[] args)
    {
        string filename = args[0];

        uint file_size = gdcm.PosixEmulation.FileSize(filename);

        // instantiate the reader:
        gdcm.ImageRegionReader reader = new gdcm.ImageRegionReader();
        reader.SetFileName( filename );

        // pull DICOM info:
        if (!reader.ReadInformation()) return 1;

        // store current offset:
        uint cur_pos = reader.GetStreamCurrentPosition();

        uint remaining = file_size - cur_pos;

        Console.WriteLine("Remaining bytes to read (Pixel Data): " + remaining.ToString() );

        // Get file infos
    }
}

```

```

gdcM.File f = reader.GetFiles();

// get some info about image
UIntArrayType dims = ImageHelper.GetDimensionsValue(f);
PixelFormat pf = ImageHelper.GetPixelFormatValue(f);
int pixelSize = pf.GetPixelSize();
PhotometricInterpretation pi = ImageHelper.GetPhotometricInterpretationValue(f);
Console.WriteLine(pi.ToString());

// buffer to get the pixels
byte[] buffer = new byte[ dims[0] * dims[1] * pixelSize ];

// define a simple box region.
BoxRegion box = new BoxRegion();
for (uint z = 0; z < dims[2]; z++)
{
    // Define that I want the image 0, full size (dimx x dimy pixels)
    // and do that for each z:
    box.SetDomain(0, dims[0] - 1, 0, dims[1] - 1, z, z);
    //System.Console.WriteLine(box.ToString());
    reader.SetRegion(box);

    // reader will try to load the uncompressed image region into buffer.
    // the call returns an error when buffer.Length is too small. For instance
    // one can call:
    // uint buf_len = reader.ComputeBufferLength(); // take into account pixel size
    // to get the exact size of minimum buffer
    if (reader.ReadIntoBuffer(buffer, (uint)buffer.Length))
    {
        using (System.IO.Stream stream =
            System.IO.File.Open(@"tmp/frame.raw",
                System.IO.FileMode.Create))
        {
            System.IO.BinaryWriter writer = new System.IO.BinaryWriter(stream);
            writer.Write(buffer);
        }
    }
    else
    {
        throw new Exception("can't read pixels error");
    }
}

return 0;
}

```

12.24 ExtractImageRegionWithLUT.cs

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/

/*
 * This small code shows how to use the gdcm.ImageRegionReader API
 * In this example we are taking each frame by frame and dump them to
 * /tmp/frame.raw.
 * Furthermore we are applying the LUT on this image.
 * Special care should be taken in case the image is not PALETTE COLOR
 *
 * Usage:
 * $ bin/ExtractImageRegionWithLUT.exe input.dcm
 *
 * Example:
 * $ bin/ExtractImageRegionWithLUT.exe gdcmData/rle16l00.dcm
 * $ md5sum /tmp/frame_rgb.raw

```

```

* 73bf61325fdb6e2830244a2b7b0c4ae2 /tmp/frame_rgb.raw
* $ gdcming --depth 16 --spp 3 --size 600,430 /tmp/frame_rgb.raw rgb.dcm
* $ gdcviewer rgb.dcm
*/
using System;
using gdcm;

public class ExtractImageRegion
{
    public static int Main(string[] args)
    {
        string filename = args[0];

        // instantiate the reader:
        gdcm.ImageRegionReader reader = new gdcm.ImageRegionReader();
        reader.SetFileName( filename );

        // pull DICOM info:
        if (!reader.ReadInformation()) return 1;
        // Get file infos
        gdcm.File f = reader.GetFile();

        gdcm.LookupTable lut = reader.GetImage().GetLUT();

        // get some info about image
        UIntArrayType dims = ImageHelper.GetDimensionsValue(f);
        PixelFormat pf = ImageHelper.GetPixelFormatValue(f);
        int pixelsize = pf.GetPixelSize();

        // buffer to get the pixels
        byte[] buffer = new byte[ dims[0] * dims[1] * pixelsize ];

        // output buffer for the RGB decoded image:
        byte[] buffer2 = new byte[ dims[0] * dims[1] * pixelsize * 3 ];

        // define a simple box region.
        BoxRegion box = new BoxRegion();
        for (uint z = 0; z < dims[2]; z++)
        {
            // Define that I want the image 0, full size (dimx x dimy pixels)
            // and do that for each z:
            box.SetDomain(0, dims[0] - 1, 0, dims[1] - 1, z, z);
            //System.Console.WriteLine( box.ToString() );
            reader.SetRegion( box );

            // reader will try to load the uncompressed image region into buffer.
            // the call returns an error when buffer.Length is too small. For instance
            // one can call:
            // uint buf_len = reader.ComputeBufferLength(); // take into account pixel size
            // to get the exact size of minimum buffer
            if (reader.ReadIntoBuffer(buffer, (uint)buffer.Length))
            {
                if( !lut.Decode( buffer2, (uint)buffer2.Length, buffer, (uint)buffer.Length ) )
                {
                    throw new Exception("can't decode");
                }

                using (System.IO.Stream stream =
                    System.IO.File.Open(@"tmp/frame_rgb.raw",
                        System.IO.FileMode.Create))
                {
                    System.IO.BinaryWriter writer = new System.IO.BinaryWriter(stream);
                    writer.Write(buffer2);
                }
            }
            else
            {
                throw new Exception("can't read pixels error");
            }
        }

        return 0;
    }
}

```

12.25 ExtractOneFrame.cs

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.
=====*/

/*
 * This small code shows how to use the gdcm.StreamImageReader API
 * to read a single (whole) frame at a time
 * The API allow extracting a smaller extent of the frame of course.
 * It will write out the extracted frame in /tmp/frame.raw
 *
 * Usage:
 * $ bin/ExtractOneFrame.exe input.dcm
 */
using System;
using gdcm;

public class ExtractOneFrame
{
    public static int Main(string[] args)
    {
        string filename = args[0];

        gdcm.StreamImageReader reader = new gdcm.StreamImageReader();

        reader.SetFileName( filename );

        if (!reader.ReadImageInformation()) return 1;
        // Get file infos
        gdcm.File f = reader.GetFile();

        // get some info about image
        UIntArrayType extent = ImageHelper.GetDimensionsValue(f);
        //System.Console.WriteLine( extent[0] );
        uint dimx = extent[0];
        //System.Console.WriteLine( extent[1] );
        uint dimy = extent[1];
        //System.Console.WriteLine( extent[2] );
        uint dimz = extent[2];
        PixelFormat pf = ImageHelper.GetPixelFormatValue (f);
        int pixelsize = pf.GetPixelSize();
        //System.Console.WriteLine( pixelsize );

        // buffer to get the pixels
        byte[] buffer = new byte[ dimx * dimy * pixelsize ];

        for (int i = 0; i < dimz; i++)
        {
            // Define that I want the image 0, full size (dimx x dimy pixels)
            reader.DefinePixelExtent(0, (ushort)dimx, 0, (ushort)dimy, (ushort)i, (ushort)(i+1));
            uint buf_len = reader.DefineProperBufferLength(); // take into account pixel size
            //System.Console.WriteLine( buf_len );
            if( buf_len > buffer.Length )
            {
                throw new Exception("buffer is too small for target");
            }

            if (reader.Read(buffer, (uint)buffer.Length))
            {
                using (System.IO.Stream stream =
                    System.IO.File.Open(@"tmp/frame.raw",
                        System.IO.FileMode.Create))
                {
                    System.IO.BinaryWriter writer = new System.IO.BinaryWriter(stream);
                    writer.Write(buffer);
                }
            }
            else
            {

```



```

        throw new Exception("can't read pixels error");
    }
}

return 0;
}
}

```

12.26 FileAnonymize.cs

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/

/*
 * Simple C# example
 *
 * Usage:
 * $ mono bin/FileAnonymize.exe input.dcm output.dcm
 */
using System;
using gdcm;

public class FileAnonymize
{
    public static int Main(string[] args)
    {
        string filename = args[0];
        string outfilename = args[1];

        gdcm.FileAnonymizer fa = new gdcm.FileAnonymizer();
        fa.SetInputFileName( filename );
        fa.SetOutputFileName( outfilename );

        // Empty Operations
        // It will create elements, since those tags are non-registered public elements (2011):
        fa.Empty( new Tag(0x0008,0x1313) );
        fa.Empty( new Tag(0x0008,0x1317) );
        // Remove Operations
        // The following Tag are actually carefully chosen, since they refer to SQ:
        fa.Remove( new Tag(0x0008,0x2112) );
        fa.Remove( new Tag(0x0008,0x9215) );
        // Replace Operations
        // do not call replace operation on SQ attribute !
        fa.Replace( new Tag(0x0018,0x5100), "MYVALUE " );
        fa.Replace( new Tag(0x0008,0x1160), "MYOTHERVAL" );

        if( !fa.Write() )
        {
            System.Console.WriteLine( "Could not write" );
            return 1;
        }

        return 0;
    }
}

```

12.27 FileChangeTS.cs

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

```

Copyright (c) 2006-2011 Mathieu Malaterre
 All rights reserved.
 See Copyright.txt or <http://gdcm.sourceforge.net/Copyright.html> for details.

This software is distributed WITHOUT ANY WARRANTY; without even
 the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
 PURPOSE. See the above copyright notice for more information.

```

=====*/

/*
 * Simple C# example
 *
 * Shows multiple steps:
 * Steps 1.
 * Create a fake (dummy) DICOM file, with size 512 x 512 x 2 We use a small
 * image to be able to create the volume in memory Of course you can use any
 * existing DICOM instead
 *
 * Step 2.
 * Hack the DICOM file to pretend the number of frames is 1000 (instead of 2)
 * At this point in time this makes the DICOM file invalid (truncated). But the
 * next step will fix this.
 *
 * Step 3.
 * Use C# to create a binary data which will represent our source object for
 * image.
 *
 * Step 4.
 * We use gdcm.FileStreamer to merge the template DICOM file from Step 2, with
 * the binary data from Step 3. We decide to read a scanline at a time, but
 * this can be read with any number of bytes. AppendToDataElement() will always
 * do the proper computation.
 *
 * Step 5.
 * We compress this gigantic file, into [JPEG Lossless, Non-Hierarchical,
 * First-Order Prediction (Process 14 [Selection Value 1])]
 *
 * Usage:
 * $ mono bin/FileChangeTS.exe small.dcm big.dcm raw.data merge.dcm jpeg.dcm
 */
using System;
using System.IO;
using gdcm;

public class FileChangeTS
{
    public static byte[] StrToByteArray(string str)
    {
        System.Text.ASCIIEncoding encoding=new System.Text.ASCIIEncoding();
        return encoding.GetBytes(str);
    }
    // Create a 256 x 256 Secondary Capture Image Storage
    static private void CreateSmallDICOM(string fileName)
    {
        using( var writer = new gdcm.PixmapWriter() )
        {
            gdcm.Pixmap img = writer.GetImage();
            img.SetNumberOfDimensions( 3 );
            img.SetDimension(0, 512 );
            img.SetDimension(1, 512 );
            img.SetDimension(2, 2 ); // fake a 3d volume
            PhotometricInterpretation pi = new PhotometricInterpretation( PhotometricInterpretation.PITYPE.MONOCHROME2 );
            img.SetPhotometricInterpretation( pi );
            gdcm.DataElement pixeldata = new gdcm.DataElement( new gdcm.Tag(0x7fe0,0x0010) );
            byte[] buffer = new byte[ 512 * 512 * 2 ];
            pixeldata.SetByteValue( buffer, new gdcm.VL((uint)buffer.Length) );
            img.SetDataElement( pixeldata );

            gdcm.File file = writer.GetFile();
            gdcm.DataSet ds = file.GetDataSet();
            gdcm.DataElement ms = new gdcm.DataElement(new gdcm.Tag(0x0008,0x0016));
            string mediastorage = "1.2.840.10008.5.1.4.1.1.7.2"; // Multi-frame Grayscale Byte Secondary Capture Image Storage
            byte[] val = StrToByteArray(mediastorage);
            ms.SetByteValue( val, new gdcm.VL( (uint)val.Length) );
            ds.Insert( ms );

            writer.SetFileName( fileName );
        }
    }
}

```

```

        writer.Write();
    }
}

static private void CreateBigDICOM(string fileName, string outfilename)
{
    using( var ano = new gdcm.FileAnonymizer() )
    {
        // The following is somewhat dangerous, do not try at home:
        string nframes = "1000";
        ano.Replace( new gdcm.Tag(0x0028,0x0008), nframes );
        ano.SetInputFileName(fileName);
        ano.SetOutputFileName(outfilename);
        ano.Write(); // at this point the DICOM is invalid !
    }
}

static private void CreateDummyFile(string fileName, long length)
{
    using (var fileStream = new FileStream(fileName, FileMode.Create, FileAccess.Write, FileShare.None))
    {
        // Looks like C# always init to 0 (fallocate ?)
        // For the purpose of the test we could add some random noise
        fileStream.SetLength(length);
    }
}

static private void ReadBytesIntoArray( byte[] array, FileStream source )
{
    int numBytesToRead = array.Length;
    int numBytesRead = 0;
    while (numBytesToRead > 0)
    {
        // According to spec: Read() may return anything from 0 to numBytesToRead.
        int n = source.Read(array, numBytesRead, numBytesToRead);

        // Break when the end of the file is reached.
        if (n == 0)
            break;

        numBytesRead += n;
        numBytesToRead -= n;
    }
}

static private void AssembleDICOMAndRaw(string dicomfn, string rawdata, string outfn)
{
    using ( var fs = new gdcm.FileStreamer() )
    {
        fs.SetTemplateFileName(dicomfn);
        fs.SetOutputFileName(outfn);
        gdcm.Tag pixeldata = new gdcm.Tag(0x7fe0, 0x0010);
        // FileStreamer support automatic checking of pixel data length
        // based on DICOM attributes, only if we say so:
        fs.CheckDataElement( pixeldata );
        // Declare we are working on Pixel Data attribute:
        fs.StartDataElement( pixeldata );
        using (FileStream rawSource = new FileStream(rawdata,
            FileMode.Open, FileAccess.Read))
        {
            byte[] bytes = new byte[512];
            // Only read one scanline at a time
            // We could have been reading more at once, if this is more efficient,
            // AppendToDataElement will do the logic in all cases.
            for( int i = 0; i < 512 * 1000; ++i )
            {
                // Read the source file into a byte array.
                ReadBytesIntoArray( bytes, rawSource );
                fs.AppendToDataElement( pixeldata, bytes, (uint)bytes.Length );
            }
        }
        if( !fs.StopDataElement( pixeldata ) )
        {
            // Most likely an issue with Pixel Data Length computation:
            throw new Exception("StopDataElement failed");
        }
    }
}

static private void CompressIntoJPEG(string rawdicom, string jpegdicom)
{
    using( var sfcts = FileChangeTransferSyntax.New() )
    {
        // Need to retrieve the actual C++ reference, to pass to
        // SimpleSubjectWatcher:
        FileChangeTransferSyntax fcts = sfcts.__ref__();
    }
}

```

```

        SimpleSubjectWatcher watcher = new SimpleSubjectWatcher(fcts, "FileChangeTransferSyntax");
        gdcm.TransferSyntax ts = new TransferSyntax( TransferSyntax.TType.JPEGLosslessProcess14_1 );
        fcts.SetTransferSyntax( ts );
        fcts.SetInputFileName( rawdicom );
        fcts.SetOutputFileName( jpegdicom );
        fcts.Change();
    }
}

public static int Main(string[] args)
{
    string filename = args[0];
    string outfilename = args[1];
    string rawfilename = args[2];
    string mergefn = args[3];
    string jpegfn = args[4];

    CreateSmallDICOM(filename);
    CreateBigDICOM(filename, outfilename);
    CreateDummyFile(rawfilename, 512 * 512 * 1000 );
    AssembleDICOMAndRaw(outfilename, rawfilename, mergefn);
    CompressIntoJPEG(mergefn, jpegfn);

    return 0;
}
}

```

12.28 FileChangeTSLossy.cs

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/

/*
 * Simple C# example
 *
 * Shows multiple steps:
 * Steps 1.
 * Create a fake (dummy) DICOM file, with size 512 x 512 x 2 We use a small
 * image to be able to create the volume in memory Of course you can use any
 * existing DICOM instead
 *
 * Step 2.
 * Hack the DICOM file to pretend the number of frames is 1000 (instead of 2)
 * At this point in time this makes the DICOM file invalid (truncated). But the
 * next step will fix this.
 *
 * Step 3.
 * Use C# to create a binary data which will represent our source object for
 * image.
 *
 * Step 4.
 * We use gdcm.FileStreamer to merge the template DICOM file from Step 2, with
 * the binary data from Step 3. We decide to read a scanline at a time, but
 * this can be read with any number of bytes. AppendToDataElement() will always
 * do the proper computation.
 *
 * Step 5.
 * We compress this gigantic file, into [JPEG Baseline (Process 1): Default Transfer Syntax for Lossy JPEG 8 Bit
 * Image Compression]
 *
 * Usage:
 * $ bin/FileChangeTSLossy.exe small.dcm big.dcm raw.data merge.dcm jpeg.dcm
 */
using System;
using System.IO;

```

```

using gdcm;

public class FileChangeTS
{
    public static byte[] StrToByteArray(string str)
    {
        System.Text.ASCIIEncoding encoding=new System.Text.ASCIIEncoding();
        return encoding.GetBytes(str);
    }
    // Create a 256 x 256 Secondary Capture Image Storage
    static private void CreateSmallDICOM(string fileName)
    {
        using( var writer = new gdcm.PixmapWriter() )
        {
            gdcm.Pixmap img = writer.GetImage();
            img.SetNumberOfDimensions( 3 );
            img.SetDimension(0, 512 );
            img.SetDimension(1, 512 );
            img.SetDimension(2, 2 ); // fake a 3d volume
            PhotometricInterpretation pi = new PhotometricInterpretation( PhotometricInterpretation.PIType.MONOCHROME2 );
            img.SetPhotometricInterpretation( pi );
            gdcm.DataElement pixeldata = new gdcm.DataElement( new gdcm.Tag(0x7fe0,0x0010) );
            byte[] buffer = new byte[ 512 * 512 * 2 ];
            pixeldata.SetByteValue( buffer, new gdcm.VL((uint)buffer.Length) );
            img.SetDataElement( pixeldata );

            gdcm.File file = writer.GetFile();
            gdcm.DataSet ds = file.GetDataSet();
            gdcm.DataElement ms = new gdcm.DataElement(new gdcm.Tag(0x0008,0x0016));
            string mediastorage = "1.2.840.10008.5.1.4.1.1.7.2"; // Multi-frame Grayscale Byte Secondary Capture Image Storage
            byte[] val = StrToByteArray(mediastorage);
            ms.SetByteValue( val, new gdcm.VL( (uint)val.Length) );
            ds.Insert( ms );

            writer.SetFileName( fileName );
            writer.Write();
        }
    }
    static private void CreateBigDICOM(string fileName, string outfilename)
    {
        using( var ano = new gdcm.FileAnonymizer() )
        {
            // The following is somewhat dangerous, do not try at home:
            string nframes = "1000";
            ano.Replace( new gdcm.Tag(0x0028,0x0008), nframes );
            ano.SetInputFileName(fileName);
            ano.SetOutputFileName(outfilename);
            ano.Write(); // at this point the DICOM is invalid !
        }
    }
    static private void CreateDummyFile(string fileName, long length)
    {
        using (var fileStream = new FileStream(fileName, FileMode.Create, FileAccess.Write, FileShare.None))
        {
            // Looks like C# always init to 0 (fallocate ?)
            // For the purpose of the test we could add some random noise
            fileStream.SetLength(length);
        }
    }
    static private void ReadBytesIntoArray( byte[] array, FileStream source )
    {
        int numBytesToRead = array.Length;
        int numBytesRead = 0;
        while (numBytesToRead > 0)
        {
            // According to spec: Read() may return anything from 0 to numBytesToRead.
            int n = source.Read(array, numBytesRead, numBytesToRead);

            // Break when the end of the file is reached.
            if (n == 0)
                break;

            numBytesRead += n;
            numBytesToRead -= n;
        }
    }
    static private void AssembleDICOMAndRaw(string dicomfn, string rawdata, string outfn)
    {
        using ( var fs = new gdcm.FileStreamer() )
    
```

```

    {
        fs.SetTemplateFileName(dicomfn);
        fs.SetOutputFileName(outfn);
        gdcm.Tag pixeldata = new gdcm.Tag(0x7fe0, 0x0010);
        // FileStreamer support automatic checking of pixel data length
        // based on DICOM attributes, only if we say so:
        fs.CheckDataElement( pixeldata );
        // Declare we are working on Pixel Data attribute:
        fs.StartDataElement( pixeldata );
        using (FileStream rawSource = new FileStream(rawdata,
            FileMode.Open, FileAccess.Read))
        {
            byte[] bytes = new byte[512];
            // Only read one scanline at a time
            // We could have been reading more at once, if this is more efficient,
            // AppendToDataElement will do the logic in all cases.
            for( int i = 0; i < 512 * 1000; ++i )
            {
                // Read the source file into a byte array.
                ReadBytesIntoArray( bytes, rawSource );
                fs.AppendToDataElement( pixeldata, bytes, (uint)bytes.Length );
            }
        }
        if( !fs.StopDataElement( pixeldata ) )
        {
            // Most likely an issue with Pixel Data Length computation:
            throw new Exception("StopDataElement failed");
        }
    }
}

static private void CompressIntoJPEG(string rawdicom, string jpegdicom)
{
    using( var sfcts = FileChangeTransferSyntax.New() )
    {
        // Need to retrieve the actual C++ reference, to pass to
        // SimpleSubjectWatcher:
        FileChangeTransferSyntax fcts = sfcts.__ref__();
        SimpleSubjectWatcher watcher = new SimpleSubjectWatcher(fcts, "FileChangeTransferSyntax");
        gdcm.TransferSyntax ts = new TransferSyntax( TransferSyntax.TSType.JPEGBaselineProcess1 );
        fcts.SetTransferSyntax( ts );
        ImageCodec ic = fcts.GetCodec();
        JPEGCodec jpeg = JPEGCodec.Cast( ic );
        jpeg.SetLossless( false );
        jpeg.SetQuality( 50 ); // poor quality !

        fcts.SetInputFileName( rawdicom );
        fcts.SetOutputFileName( jpegdicom );
        fcts.Change();
    }
}

public static int Main(string[] args)
{
    string filename = args[0];
    string outfilename = args[1];
    string rawfilename = args[2];
    string mergefn = args[3];
    string jpegfn = args[4];

    CreateSmallDICOM(filename);
    CreateBigDICOM(filename, outfilename);
    CreateDummyFile(rawfilename, 512 * 512 * 1000 );
    AssembleDICOMAndRaw(outfilename, rawfilename, mergefn);
    CompressIntoJPEG(mergefn, jpegfn);

    return 0;
}
}

```

12.29 FileStreaming.cs

```

/*=====

Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.

```

See Copyright.txt or <http://gdcm.sourceforge.net/Copyright.html> for details.

This software is distributed WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the above copyright notice for more information.

```

=====*/

/*
 * Simple C# example
 *
 * Usage:
 * $ mono bin/FileStreaming.exe gdcmData/CT_16b_signed-UsedBits13.dcm output.dcm
 *
 * The class will take care of group handling and will use the first available group:
 * (0009,0012) ?? (LO) [MYTEST] # 6,1 Private Creator
 */
using System;
using gdcm;

public class FileStreaming
{
    public static int Main(string[] args)
    {
        string filename = args[0];
        string outfilename = args[1];

        gdcm.PrivateTag pt = new gdcm.PrivateTag( new gdcm.Tag(0x9,0x10), "MYTEST" );

        gdcm.FileStreamer fs = new gdcm.FileStreamer();
        fs.SetTemplateFileName( filename );
        fs.SetOutputFileName( outfilename );

        byte[] buffer = new byte[ 8192 ];
        uint len = (uint)buffer.Length;

        // In this example, we want that each newly created Private Attribute
        // contains at most 1000 bytes of incoming dataset.
        // We are also calling the function twice to check that appending mode is
        // working from one call to the other. The last element will have a length
        // of (2 * 8192) % 1000 = 384
        if( !fs.StartGroupDataElement( pt, 1000, 1 ) )
        {
            || !fs.AppendToGroupDataElement( pt, buffer, len )
            || !fs.AppendToGroupDataElement( pt, buffer, len )
            || !fs.StopGroupDataElement( pt ) )
        {
            System.Console.WriteLine( "Could not change private group" );
            return 1;
        }

        return 0;
    }
}

```

12.30 GetArray.cs

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/

/*
 * Usage:
 * $ export LD_LIBRARY_PATH=$HOME/Projects/gdcm/debug-gcc/bin
 * $ mono bin/GetArray.exe gdcmData/012345.002.050.dcm
 */
using System;

```

```

using gdcmm;

public class GetArray
{
    public static int Main(string[] args)
    {
        string file1 = args[0];
        ImageReader reader = new ImageReader();
        reader.SetFileName( file1 );
        bool ret = reader.Read();
        if( !ret )
        {
            return 1;
        }

        Image image = reader.GetImage();

        PixelFormat pixeltype = image.GetPixelFormat();

        if( image.GetNumberOfDimensions() != 2 )
        {
            // For the purpose of the test, exit early on
            return 1;
        }
        uint dimx = image.GetDimension(0);
        uint dimy = image.GetDimension(1);
        uint npixels = dimx * dimy;
        //LookupTable lut = image.GetLUT();
        //uint r1 = lut.GetLUTLength( LookupTable.LookupTableType.RED );
        //byte[] rbuf = new byte[ r1 ];
        //uint r12 = lut.GetLUT( LookupTable.LookupTableType.RED, rbuf );
        //assert r1 == r12;

        //byte[] str1 = new byte[ image.GetBufferLength()];
        //image.GetBuffer( str1 );
        if( pixeltype.GetScalarType() == PixelFormat.ScalarType.UINT8 )
        {
            System.Console.WriteLine( "Processing UINT8 image type" );
            byte[] str1 = new byte[ npixels ];
            image.GetArray( str1 );
        }
        else if( pixeltype.GetScalarType() == PixelFormat.ScalarType.INT16 )
        {
            System.Console.WriteLine( "Processing INT16 image type" );
            short[] str1 = new short[ npixels ];
            image.GetArray( str1 );
        }
        else if( pixeltype.GetScalarType() == PixelFormat.ScalarType.UINT16 )
        {
            System.Console.WriteLine( "Processing UINT16 image type" );
            ushort[] str1 = new ushort[ npixels ];
            image.GetArray( str1 );
        }
        else
        {
            //System.Console.WriteLine( "Default (unhandled pixel format): " + pixeltype.ToString() );
            System.Console.WriteLine( "Default (unhandled pixel format): " + pixeltype.GetScalarTypeAsString() );
            // Get bytes
            byte[] str1 = new byte[ image.GetBufferLength()];
            image.GetBuffer( str1 );
        }

        return 0;
    }
}

```

12.31 MpegVideoInfo.cs

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcmm.sourceforge.net/Copyright.html for details.

```


This software is distributed WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the above copyright notice for more information.

```

=====*/
/*
 * This examples takes in a MPEG2 and write out a Video Endoscopic Imagae Storage
 * encoded using MPEG2 @ Main Profile
 * ref: http://chrisa.wordpress.com/2007/11/21/decoding-mpeg2-information/
 * See also:
 * http://dvd.sourceforge.net/dvdinfo/mpeghdrs.html#gop
 * http://cvs.linux.hr/cgi-bin/viewcvs.cgi/mpeg_mod/README.infompeg?view=markup
 * http://www.guru-group.fi/~too/sw/m2vmp2cut/mpeg2info.c
 */

/*
 * Provides information about an MPEG2 file, including the duration, frame rate, aspect
 * ratio, and resolution. Good information about the MPEG2 file structure that helps
 * explain parts of the code can be found here:
 * http://dvd.sourceforge.net/dvdinfo/mpeghdrs.html#gop
 *
 * Copyright (c) 2007 Chris Anderson (chrisa@wordpress.com)
 *
 * This library is free software; you can redistribute it and/or
 * modify it under the terms of the GNU Lesser General Public
 * License as published by the Free Software Foundation; either
 * version 2 of the License, or (at your option) any later version.
 *
 * This library is distributed in the hope that it will be useful,
 * but WITHOUT ANY WARRANTY; without even the implied warranty of
 * MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU
 * Lesser General Public License for more details.
 */
using System;
using System.IO;
using gdc;

public class Mpeg2VideoInfo
{
    #region Member Variables
    private TimeSpan m_startTime = TimeSpan.Zero;
    private TimeSpan m_endTime = TimeSpan.Zero;
    private TimeSpan m_duration = TimeSpan.Zero;
    private eAspectRatios m_aspectRatio = eAspectRatios.Invalid;
    private eFrameRates m_frameRate = 0;
    private int m_pictureWidth = 0;
    private int m_pictureHeight = 0;
    #endregion

    #region Constants
    private const byte PADDING_PACKET = 0xBE;
    private const byte VIDEO_PACKET = 0xE0;
    private const byte AUDIO_PACKET = 0xC0;
    private const byte SYSTEM_PACKET = 0xBB;
    private const byte TIMESTAMP_PACKET = 0xB8;
    private const byte HEADER_PACKET = 0xB3;

    private const int BUFFER_SIZE = 8162; // 8K buffer

    private readonly static TimeSpan EMPTY_TIMESPAN = new TimeSpan(0, 0, -1);
    #endregion

    #region Enumerations
    public enum eFrameRates
    {
        Invalid,
        PulldownNTSC, // 24000d/1001d = 23.976 Hz
        Film, // 24 Hz
        PAL, // 25 Hz
        NTSC, // 30000d/1001d = 29.97 Hz
        DropFrameNTSC, // 30 Hz
        DoubleRatePAL, // 50 Hz
        DoubleRateNTSC, // 59.97 Hz
        DoubleRateDropFrameNTSC // 60 Hz
    }

    public enum eAspectRatios
    {
        Invalid,
        VGA, // 1/1
        StandardTV, // 4/3
    }
    }

```

```

        LargeTV,    // 16/9
        Cinema     // 2.21/1
    }
#endregion

#region Constructor
public Mpeg2VideoInfo(string file)
{
    ParseMpeg(file);
}
#endregion

#region Public Properties
public TimeSpan StartTime
{
    get { return m_startTime; }
}

public TimeSpan EndTime
{
    get { return m_endTime; }
}

public TimeSpan Duration
{
    get { return m_duration; }
}

public eAspectRatios AspectRatio
{
    get { return m_aspectRatio; }
}

public eFrameRates FrameRate
{
    get { return m_frameRate; }
}

public int PictureWidth
{
    get { return m_pictureWidth; }
}

public int PictureHeight
{
    get { return m_pictureHeight; }
}
#endregion

#region Private Functions
private void ParseMpeg(string file)
{
    FileStream fs = new FileStream(file, FileMode.Open, FileAccess.Read, FileShare.ReadWrite);
    BinaryReader br = new BinaryReader(fs);

    m_startTime = GetStartTimeStampInfo(br);
    m_endTime = GetEndTimeStampInfo(br);

    m_duration = m_endTime.Subtract(m_startTime);

    GetHeaderInfo(br);

    br.Close();
    fs.Close();
}

private TimeSpan GetStartTimeStampInfo(BinaryReader br)
{
    TimeSpan startTime = EMPTY_TIMESPAN;
    byte[] buffer = new byte[BUFFER_SIZE];

    br.BaseStream.Seek(0, SeekOrigin.Begin);

    while (startTime == EMPTY_TIMESPAN && br.BaseStream.Position < br.BaseStream.Length)
    {
        int readBytes = br.Read(buffer, 0, BUFFER_SIZE);

        for (int offset = 0; offset < readBytes - 8; offset++)
        {
            if (IsStreamMarker(ref buffer, offset, TIMESTAMP_PACKET))
            {

```

```

        offset += 4; // Move to the data position which follows the stream header
        uint timeStampEncoded = GetData(ref buffer, offset);
        startTime = DecodeTimeStamp(timeStampEncoded);

        if (startTime != EMPTY_TIMESPAN)
            break;
    }
}

return startTime;
}

private TimeSpan GetEndTimeStampInfo(BinaryReader br)
{
    TimeSpan endTime = EMPTY_TIMESPAN;
    byte[] buffer = new byte[BUFFER_SIZE];

    br.BaseStream.Seek(-BUFFER_SIZE, SeekOrigin.End);

    while (endTime == EMPTY_TIMESPAN && br.BaseStream.Position > BUFFER_SIZE)
    {
        int readBytes = br.Read(buffer, 0, BUFFER_SIZE);

        for (int offset = readBytes - 8; offset >= 0; offset--)
        {
            if (IsStreamMarker(ref buffer, offset, TIMESTAMP_PACKET))
            {
                offset += 4; // Move to the data position which follows the stream header
                uint timeStampEncoded = GetData(ref buffer, offset);
                endTime = DecodeTimeStamp(timeStampEncoded);

                if (endTime != EMPTY_TIMESPAN)
                    break;
            }
        }

        br.BaseStream.Seek(-BUFFER_SIZE * 2, SeekOrigin.Current);
    }

    return endTime;
}

private TimeSpan DecodeTimeStamp(uint timeStampEncoded)
{
    TimeSpan timeStamp = EMPTY_TIMESPAN;

    // Mask out the bits containing the property we are after, then
    // shift the data to the right to get its value
    int hour = (int)(timeStampEncoded & 0x7C000000) » 26; // Bits 31 -> 27
    int minute = (int)(timeStampEncoded & 0x03F00000) » 20; // Bits 26 -> 21
    int second = (int)(timeStampEncoded & 0x0007E000) » 13; // Bits 19 -> 14
    int frame = (int)(timeStampEncoded & 0x00001F80) » 7; // Bits 13 -> 8 - not used, but included for
    completeness

    timeStamp = new TimeSpan(hour, minute, second);
    return timeStamp;
}

private void GetHeaderInfo(BinaryReader br)
{
    byte[] buffer = new byte[BUFFER_SIZE];

    br.BaseStream.Seek(0, SeekOrigin.Begin);
    br.Read(buffer, 0, BUFFER_SIZE);

    for (int offset = 0; offset < buffer.Length - 4; offset++)
    {
        if (IsStreamMarker(ref buffer, offset, HEADER_PACKET))
        {
            offset += 4; // Move to the data position which follows the stream header
            uint headerData = GetData(ref buffer, offset);

            // Mask out the bits containing the property we are after, then
            // shift the data to the right to get its value
            m_pictureWidth = (int)(headerData & 0xFFFF0000) » 20;
            m_pictureHeight = (int)(headerData & 0x000FFF00) » 8;

            uint aspectRatioIndex = (headerData & 0x000000F0) » 4;

```

```

        uint fpsIndex = headerData & 0x0000000F;

        m_aspectRatio = (eAspectRatios)fpsIndex;
        m_frameRate = (eFrameRates)fpsIndex;

        break;
    }
}

private uint GetData(ref byte[] buffer, int offset)
{
    return (uint) ((buffer[offset] << 24) |
        (buffer[offset + 1] << 16) |
        (buffer[offset + 2] << 8) |
        (buffer[offset + 3]));
}

private bool IsStreamMarker(ref byte[] buffer, int offset, byte markerType)
{
    return (buffer[offset] == 0x00 &&
        buffer[offset + 1] == 0x00 &&
        buffer[offset + 2] == 0x01 &&
        buffer[offset + 3] == markerType);
}
#endregion
public static int Main(string[] args)
{
    string file1 = args[0];
    Mpeg2VideoInfo info = new Mpeg2VideoInfo(file1);
    System.Console.WriteLine( info.StartTime );
    System.Console.WriteLine( info.EndTime );
    System.Console.WriteLine( info.Duration );
    System.Console.WriteLine( info.AspectRatio );
    System.Console.WriteLine( info.FrameRate );
    System.Console.WriteLine( info.PictureWidth );
    System.Console.WriteLine( info.PictureHeight );

    ImageReader r = new ImageReader();
    //Image image = new Image();
    Image image = r.GetImage();
    image.SetNumberOfDimensions( 3 );
    DataElement pixeldata = new DataElement( new gdcm.Tag(0x7fe0,0x0010) );

    System.IO.FileStream infile =
        new System.IO.FileStream(file1, System.IO.FileMode.Open, System.IO.FileAccess.Read);
    uint fsize = gdcm.PosixEmulation.FileSize(file1);

    byte[] jstream = new byte[fsize];
    infile.Read(jstream, 0, jstream.Length);

    SmartPtrFrag sq = SequenceOfFragments.New();
    Fragment frag = new Fragment();
    frag.SetByteValue( jstream, new gdcm.VL( (uint)jstream.Length) );
    sq.AddFragment( frag );
    pixeldata.SetValue( sq.__ref__() );

    // insert:
    image.SetDataElement( pixeldata );

    PhotometricInterpretation pi = new PhotometricInterpretation(
        PhotometricInterpretation.PIType.YBR_PARTIAL_420 );
    image.SetPhotometricInterpretation( pi );
    // FIXME hardcoded:
    PixelFormat pixeltype = new PixelFormat(3,8,8,7);
    image.SetPixelFormat( pixeltype );

    // FIXME hardcoded:
    TransferSyntax ts = new TransferSyntax( TransferSyntax.TSType.MPEG2MainProfile);
    image.SetTransferSyntax( ts );

    image.SetDimension(0, (uint)info.PictureWidth);
    image.SetDimension(1, (uint)info.PictureHeight);
    image.SetDimension(2, 721);

    ImageWriter writer = new ImageWriter();
    gdcm.File file = writer.GetFile();
    file.GetHeader().SetDataSetTransferSyntax( ts );
    Anonymizer anon = new Anonymizer();

```

```

anon.SetFile( file );

MediaStorage ms = new MediaStorage( MediaStorage.MSType.VideoEndoscopicImageStorage);

UIDGenerator gen = new UIDGenerator();
anon.Replace( new Tag(0x0008,0x16), ms.GetString() );
anon.Replace( new Tag(0x0018,0x40), "25" );
anon.Replace( new Tag(0x0018,0x1063), "40.000000" );
anon.Replace( new Tag(0x0028,0x34), "4\\3" );
anon.Replace( new Tag(0x0028,0x2110), "01" );

writer.SetImage( image );
writer.SetFileName( "dummy.dcm" );
if( !writer.Write() )
{
    System.Console.WriteLine( "Could not write" );
    return 1;
}

return 0;
}

```

12.32 NewSequence.cs

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/

/*
 * Usage:
 * $ export LD_LIBRARY_PATH=$HOME/Projects/gdcm/debug-gcc/bin
 * $ mono bin/NewSequence.exe gdcmData/012345.002.050.dcm out.dcm
 */
using System;
//using gdcm;

public class NewSequence
{
    public static byte[] StrToByteArray(string str)
    {
        System.Text.ASCIIEncoding encoding=new System.Text.ASCIIEncoding();
        return encoding.GetBytes(str);
    }

    public static int Main(string[] argv)
    {
        string file1 = argv[0];
        string file2 = argv[1];

        gdcm.Reader r = new gdcm.Reader();
        r.SetFileName( file1 );
        if ( ! r.Read() )
        {
            return 1;
        }

        gdcm.File f = r.GetFile();
        gdcm.DataSet ds = f.GetDataSet();
        // tsis = gdcm.Tag(0x0008,0x2112) # SourceImageSequence

        // Create a dataelement
        gdcm.DataElement de = new gdcm.DataElement(new gdcm.Tag(0x0010, 0x2180));
        string occ = "Occupation";
        de.SetByteValue( StrToByteArray(occ), new gdcm.VL((uint)occ.Length));
    }
}

```

```

de.SetVR(new gdcm.VR(gdcm.VR.VRType.SH));

// Create an item
gdcm.Item it = new gdcm.Item();
it.SetVLToUndefined(); // Needed to not popup error message
//it.InsertDataElement(de)
gdcm.DataSet nds = it.GetNestedDataSet();
nds.Insert(de);

// Create a Sequence
gdcm.SmartPtrSQ sq = gdcm.SequenceOfItems.New();
sq.SetLengthToUndefined();
sq.AddItem(it);

// Insert sequence into data set
gdcm.DataElement des = new gdcm.DataElement(new gdcm.Tag(0x0400, 0x0550));
des.SetVR(new gdcm.VR(gdcm.VR.VRType.SQ));
des.SetValue(sq.__ref__());
des.SetVLToUndefined();

ds.Insert(des);

gdcm.Writer w = new gdcm.Writer();
w.SetFile( f );
w.SetFileName( file2 );
if ( !w.Write() )
    return 1;

return 0;
}
}

```

12.33 RescaleImage.cs

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/

/*
 * Usage:
 * $ export LD_LIBRARY_PATH=$HOME/Projects/gdcm/debug-gcc/bin
 * $ mono bin/DecompressImage.exe gdcmData/012345.002.050.dcm rescaled.dcm
 */
using System;
using gdcm;

public class DecompressImage
{
    public static int Main(string[] args)
    {
        string file1 = args[0];
        ImageReader reader = new ImageReader();
        reader.SetFileName( file1 );
        bool ret = reader.Read();
        if( !ret )
        {
            return 1;
        }

        Image image = reader.GetImage();
        PixelFormat pixeltype = image.GetPixelFormat();

        Rescaler r = new Rescaler();
        r.SetIntercept( 0 );
        r.SetSlope( 1.2 );
        r.SetPixelFormat( pixeltype );
    }
}

```

```

PixelFormat outputpt = new PixelFormat( r.ComputeInterceptSlopePixelFormat() );

System.Console.WriteLine( "pixeltype" );
System.Console.WriteLine( pixeltype.ToString() );
System.Console.WriteLine( "outputpt" );
System.Console.WriteLine( outputpt.ToString() );

uint len = image.GetBufferLength();
short[] input = new short[ len / 2 ]; // sizeof(short) == 2
image.GetArray( input );

double[] output = new double[ len / 2 ];
r.Rescale( output, input, len );

// First Pixel is:
System.Console.WriteLine( "Input:" );
System.Console.WriteLine( input[0] );

System.Console.WriteLine( "Output:" );
System.Console.WriteLine( output[0] );

return 0;
}
}

```

12.34 SendFileSCU.cs

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/

/*
 * Usage:
 * $ export LD_LIBRARY_PATH=$HOME/Perso/gdcm-gcc/bin
 * $ mono bin/SendFileSCU.exe server port input.dcm
 */
using System;
using gdcm;

public class SendFileSCU
{
    public static int Main(string[] args)
    {
        {
            string server = args[0];
            ushort port = ushort.Parse(args[1]);
            string filename = args[2];

            bool b = CompositeNetworkFunctions.CEcho( server, port );
            if( !b ) return 1;

            FilenamesType files = new FilenamesType();
            files.Add( filename );
            b = CompositeNetworkFunctions.CStore( server, port, files );
            if( !b ) return 1;

            return 0;
        }
    }
}

```

12.35 SimplePrintPatientName.cs

```

/*=====

```

```

Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
/*
 * Usage:
 * $ export LD_LIBRARY_PATH=$HOME/Perso/gdcm/debug-gcc/bin
 * $ mono bin/SimplePrintPatientName.exe gdcmData/012345.002.050.dcm
 */
/*
This example was provided by Jonathan Morra /jonmorra gmail com/
on the gdcm mailing list (Fri, 28 May 2010)
*/
using System;
using gdcm;

namespace GDCMTest
{
    class SimplePrintPatientName
    {
        static int Main(string[] args)
        {
            if (args.Length != 1)
            {
                Console.WriteLine("This program prints the patient name of a dicom file with gdcm");
                Console.WriteLine("Usage: [input.dcm]");
                return 1;
            }

            gdcm.Reader reader = new gdcm.Reader();
            reader.SetFileName(args[0]);
            bool ret = reader.Read();
            //TagSetType tst = new TagSetType();
            //tst.Add( new Tag(0x7fe0,0x10) );
            //bool ret = reader.ReadUpToTag( new Tag(0x88,0x200), tst );
            if( !ret )
            {
                return 1;
            }

            gdcm.File file = reader.GetFile();

            gdcm.StringFilter filter = new gdcm.StringFilter();
            filter.SetFile(file);
            string value = filter.ToString(new gdcm.Tag(0x0010, 0x0010));

            Console.WriteLine("Patient Name: " + value);
            return 0;
        }
    }
}

```

12.36 SortImage2.cs

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
/*

```



```

* Usage:
* $ export LD_LIBRARY_PATH=$HOME/Projects/gdcm/debug-gcc/bin
* $ mono bin/SortImage.exe gdcmData/012345.002.050.dcm out.dcm
*/
using System;
using gdcm;

public class SortImage2
{
    bool mysort(DataSet ds1, DataSet ds2)
    {
        return false;
    }

    public static int Main(string[] args)
    {
        Sorter sorter = new Sorter();
        sorter.SetSortFunction( mysort );

        return 0;
    }
}

```

12.37 CStoreQtProgress.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.
=====*/

/*
* This small example show how one can use the virtual function
* mechanism of the SimpleSubjectWatcher class to redirect progress
* report to a custom Qt classes
*
* http://doc.qt.nokia.com/latest/qprogressdialog.html
*
* Usage:
* CStoreQtProgress dicom.example.com 11112 gdcmData/MR_Spectroscopy_SIEMENS_OF.dcm
*
*/

#include "gdcmServiceClassUser.h"
#include "gdcmSimpleSubjectWatcher.h"
#include "gdcmProgressEvent.h"
#include "gdcmDirectory.h"
#include "gdcmPresentationContextGenerator.h"

#include <QApplication>
#include <QProgressDialog>
#include <QVBoxLayout>

namespace gdcm {
/*
* This class is a little more complicated than what this example demonstrate
* This watcher is capable of handling nested progress. Since the Progress
* grows from [0 to 1] on a per file basis and we only have one instance of a
* watcher per association, we need some calculation to compute the global
* (total) progress
* In fact we simply divide the per-file progress by the number of files.
*
* This QtWatcher class will then update the progress bar according to the
* progress.
*/
class MyQtWatcher : public SimpleSubjectWatcher
{
    size_t nfiles;
    double progress;

```

```

size_t index;
double refprogress;
QWidget* win;
QProgressDialog* qtprogress;
public:
    MyQtWatcher(Subject * s, const char *comment = "", QWidget *w = NULL, QProgressDialog* p = NULL, size_t n =
        1):
        SimpleSubjectWatcher(s,comment),nfiles(n),progress(0),index(0),refprogress(0),win(w),qtprogress(p){}
    void ShowIteration()
    {
        index++;
        gdcmm_assert( index <= nfiles );
        // update refprogress (we are moving to the next file)
        refprogress = progress;
    }
    void ShowProgress(Subject *, const Event &evt)
    {
        // Retrieve the ProgressEvent:
        const ProgressEvent &pe = dynamic_cast<const ProgressEvent*>(evt);
        // compute global progress:
        progress = refprogress + (1. / (double)nfiles ) * pe.GetProgress();
        // Print Global and local progress to stdout:
        std::cout << "Global Progress: " << progress << " per file progress " << pe.GetProgress() << std::endl;
        //set progress value in the QtProgress bar
        int i = (int)(progress * 100 + 0.5); // round to next int
        qtprogress->setValue(i);
        win->show();
    }
    virtual void ShowDataSet(Subject *caller, const Event &evt)
    {
        (void)caller;
        (void)evt;
    }
};
} // end namespace gdcmm

int main(int argc, char *argv[])
{
    if( argc < 4 )
    {
        std::cerr << argv[0] << " remote_server port filename" << std::endl;
        return 1;
    }
    QApplication a(argc, argv);

    std::ostringstream error_log;
    gdcmm::Trace::SetErrorStream( error_log );

    const char *remote = argv[1];
    int portno = atoi(argv[2]);
    const char *filename = argv[3];

    QVBoxLayout* layout = new QVBoxLayout;
    QWidget* win = new QWidget;

    QProgressDialog* progress = new QProgressDialog("Sending data...", "Cancel", 0, 100);
    progress->setWindowModality(Qt::WindowModal);

    layout->addWidget(progress,Qt::AlignCenter);
    win->setLayout(layout);

    gdcmm::SmartPointer<gdcmm::ServiceClassUser> scup = new gdcmm::ServiceClassUser;
    gdcmm::ServiceClassUser &scu = *scup;
    //gdcmm::SimpleSubjectWatcher w( &scu, "TestServiceClassUser" );
    // let's use a more complicated progress reported in this example
    gdcmm::MyQtWatcher w( &scu, "QtWatcher", win, progress );

    scu.SetHostname( remote );
    scu.SetPort( (uint16_t)portno );
    scu.SetTimeout( 1000 );
    scu.SetCalledAETitle( "GDCM_STORE" );

    if( !scu.InitializeConnection() )
    {
        std::cerr << "Could not InitializeConnection" << std::endl;
        return 1;
    }

    gdcmm::Directory::FilenameType filenames;

```

```

filenames.push_back( filename );

// setup the PC(s) based on the filenames:
gdcm::PresentationContextGenerator generator;
if( !generator.GenerateFromFilenames(filenames) )
{
    std::cerr << "Could not GenerateFromFilenames" << std::endl;
    return 1;
}

// Setup PresentationContext(s)
scu.SetPresentationContexts( generator.GetPresentationContexts() );

// Start ASSOCIATION
if( !scu.StartAssociation() )
{
    std::cerr << "Could not Start" << std::endl;
    return 1;
}

// Send C-STORE
if( !scu.SendStore( filename ) )
{
    std::cerr << "Could not Store" << std::endl;
    std::cerr << "Error log is:" << std::endl;
    std::cerr << error_log.str() << std::endl;
    return 1;
}

// Stop ASSOCIATION
if( !scu.StopAssociation() )
{
    std::cerr << "Could not Stop" << std::endl;
    return 1;
}

win->show();

return a.exec();
}

```

12.38 ChangePrivateTags.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
#include "gdcmReader.h"
#include "gdcmWriter.h"
#include "gdcmPrivateTag.h"

int main(int argc, char* argv[] )
{
    if( argc < 3 )
    {
        std::cerr << argv[0] << " path/to/05148044-mr-siemens-avanto-syngo.dcm output.dcm" << std::endl;
        return 1;
    }
    const char *filename = argv[1];
    const char *outfilename = argv[2];

    gdcm::Reader reader;
    reader.SetFileName( filename );
    if ( ! reader.Read() )
    {
        return 1;
    }
}

```

```

    }

    // (0029,0010) LO [SIEMENS CSA HEADER]          # 18,1 Private Creator
    // (0029,0011) LO [SIEMENS MEDCOM HEADER ]      # 22,1 Private Creator
    // (0029,0012) LO [SIEMENS MEDCOM HEADER2]      # 22,1 Private Creator
    // [...]
    // (0029,1018) CS [MR]                          # 2,1 CSA Series Header Type
    // (0029,1134) CS [DB TO DICOM ]                # 12,1 PMTF Information 4
    // (0029,1260) LO [com ]                        # 4,1 Series Workflow Status

    gdcM::File &file = reader.GetFile();
    gdcM::DataSet &ds = file.GetDataSet();

    // Declare private tag we need to find:
    gdcM::PrivateTag pt1( 0x29,0x18, "SIEMENS CSA HEADER" );
    gdcM::PrivateTag pt2( 0x29,0x34, "SIEMENS MEDCOM HEADER" );
    gdcM::PrivateTag pt3( 0x29,0x60, "SIEMENS MEDCOM HEADER2" );

    const char str1[] = "GDCM was here 3!";
    if( !ds.FindDataElement( pt1 ) ) return 1;
    gdcM::DataElement de1 = ds.GetDataElement( pt1 ); // Convert Private tag, into actual DataElement
    std::cout << de1 << std::endl;
    de1.SetByteValue( str1, (uint32_t)strlen(str1) );
    ds.Replace( de1 );

    const char str2[] = "GDCM was here 2!";
    if( !ds.FindDataElement( pt2 ) ) return 1;
    gdcM::DataElement de2 = ds.GetDataElement( pt2 );
    std::cout << de2 << std::endl;
    de2.SetByteValue( str2, (uint32_t)strlen(str2) );
    ds.Replace( de2 );

    const char str3[] = "GDCM was here 3!";
    if( !ds.FindDataElement( pt3 ) ) return 1;
    gdcM::DataElement de3 = ds.GetDataElement( pt3 );
    std::cout << de3 << std::endl;
    de3.SetByteValue( str3, (uint32_t)strlen(str3) );
    ds.Replace( de3 );

    gdcM::Writer writer;
    writer.SetFile( file );
    writer.SetFileName( outfilename );
    if ( !writer.Write() )
    {
        return 1;
    }

    return 0;
}

```

12.39 ChangeSequenceUltrasound.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcM.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
#include "gdcMReader.h"
#include "gdcMWriter.h"
#include "gdcMSmartPointer.h"
#include "gdcMDataSetHelper.h"

/*
./ChangeSequenceUltrasound gdcMData/D_CLUNIE_CT1_J2KI.dcm myoutput.dcm

This is the exact C++ translation of the original python example: ManipulateSequence.py
*/

int main(int argc, char* argv[] )

```

```

{
    if( argc < 3 )
    {
        std::cerr << argv[0] << " input.dcm output.dcm" << std::endl;
        return 1;
    }
    const char *filename = argv[1];
    const char *outfilename = argv[2];

    gdcm::Reader reader;
    reader.SetFileName( filename );
    if ( ! reader.Read() )
    {
        return 1;
    }

    gdcm::File &file = reader.GetFile();
    gdcm::DataSet &ds = file.GetDataSet();
    gdcm::Tag tsis(0x0008,0x2112); // SourceImageSequence
    if ( ds.FindDataElement( tsis ) )
    {
        const gdcm::DataElement &sis = ds.GetDataElement( tsis );
        gdcm::SmartPointer<gdcm::SequenceOfItems> sqsis = sis.GetValueAsSQ();
        if ( sqsis && sqsis->GetNumberOfItems() )
        {
            gdcm::Item &item1 = sqsis->GetItem(1);
            gdcm::DataSet &nestedds = item1.GetNestedDataSet();
            gdcm::Tag tprcs(0x0040,0xa170); // PurposeOfReferenceCodeSequence
            if( nestedds.FindDataElement( tprcs ) )
            {
                const gdcm::DataElement &prcs = nestedds.GetDataElement( tprcs );
                gdcm::SmartPointer<gdcm::SequenceOfItems> sqprcs = prcs.GetValueAsSQ();
                if ( sqprcs && sqprcs->GetNumberOfItems() )
                {
                    gdcm::Item &item2 = sqprcs->GetItem(1);
                    gdcm::DataSet &nestedds2 = item2.GetNestedDataSet();
                    // (0008,0104) LO [Uncompressed predecessor] # 24, 1 CodeMeaning
                    gdcm::Tag tcm(0x0008,0x0104);
                    if( nestedds2.FindDataElement( tcm ) )
                    {
                        gdcm::DataElement cm = nestedds2.GetDataElement( tcm );
                        std::string mystr = "GDCM was here";
                        cm.SetByteValue( mystr.c_str(), (uint32_t)mystr.size() );
                        nestedds2.Replace( cm );
                    }
                }
            }
        }
    }

    gdcm::Writer writer;
    writer.SetFile( file );
    writer.SetFileName( outfile );
    if ( !writer.Write() )
    {
        return 1;
    }

    return 0;
}

```

12.40 CheckBigEndianBug.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/

```

```

/*
 * WARNING: This is a dev tool, do not use !
 *
 * Usage: after a gdcmconv, you would like to know if the conversion process is acceptable
 * sometime a vbindiff is acceptable, sometime it is not. In the case of the famous Philips
 * Little/Big Endian Explicit Transfer Syntax it is not easy to compare two files. However
 * this only impact byte ordering, thus we can compute byte-independant information to still
 * compare the files.
 */

#include "gdcmImageReader.h"
#include "gdcmImage.h"
#include "gdcmWriter.h"
#include "gdcmAttribute.h"
#include "gdcmSystem.h"

#include <iostream>
#include <fstream>

int main(int argc, char *argv[])
{
    if( argc < 3 )
    {
        std::cerr << argv[0] << " input1.dcm input2.dcm" << std::endl;
        return 1;
    }
    const char *filename1 = argv[1];
    const char *filename2 = argv[2];

    gdcm::ImageReader reader1;
    reader1.SetFileName( filename1 );
    if( !reader1.Read() )
    {
        std::cerr << "Could not read: " << filename1 << std::endl;
        return 1;
    }

    gdcm::ImageReader reader2;
    reader2.SetFileName( filename2 );
    if( !reader2.Read() )
    {
        std::cerr << "Could not read: " << filename2 << std::endl;
        return 1;
    }

    // TODO: need a DataSet== operator implementation

    std::cout << "Both files can be read and looks like DICOM" << std::endl;

    size_t s1 = gdcm::System::FileSize(filename1);
    size_t s2 = gdcm::System::FileSize(filename2);

    if( s1 != s2 )
    {
        std::cout << "Size mismatch: " << s1 << " != " << s2 << std::endl;
        return 1;
    }
    else
    {
        std::cout << "Size match: " << s1 << " = " << s2 << std::endl;
    }

    std::ifstream is1( filename1, std::ios::binary );
    char *buffer1 = new char[s1];
    is1.read(buffer1, s1);

    std::ifstream is2( filename2, std::ios::binary );
    char *buffer2 = new char[s2];
    is2.read(buffer2, s2);

    gdcm_assert( s1 == s2 );
    if( memcmp(buffer1, buffer2, s1 ) == 0 )
    {
        std::cout << "memcmp succeed ! File are bit identical" << std::endl;
    }
    else
    {
        std::cout << "memcmp failed!" << std::endl;
    }

    // Hum...memcmp failed, for big endian/ little endian inversion the histogram of bytes

```

```

// should still be the same. So let's compute it
// buffer2[0] = 1; // let's make the test fail
std::multiset<char> set1( buffer1, buffer1 + s1 );
std::multiset<char> set2( buffer2, buffer2 + s2 );

if( set1 == set2 )
{
    std::cout << "set1 == set2. Byte histogram seems valid" << std::endl;
}
else
{
    std::cout << "set1 != set2" << std::endl;
}
delete[] buffer1;
delete[] buffer2;

return 0;
}

```

12.41 ClinicalTrialAnnotate.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
/*
 * Dummy implementation of C.7.1.3 Clinical Trial Subject Module
 *
 * Usage:
 * ClinicalTrialAnnotate gdcmData/012345.002.050.dcm out.dcm
 */

#include "gdcmReader.h"
#include "gdcmWriter.h"
#include "gdcmAnonymizer.h"

int main(int argc, char *argv[])
{
    if( argc < 3 )
    {
        std::cerr << argv[0] << " input.dcm output.dcm" << std::endl;
        return 1;
    }
    const char *filename = argv[1];
    const char *outfilename = argv[2];

    gdcm::Reader reader;
    reader.SetFileName( filename );
    if( !reader.Read() )
    {
        std::cerr << "Could not read: " << filename << std::endl;
        return 1;
    }

    // The output of gdcm::Reader is a gdcm::File
    //gdcm::File &file = reader.GetFile();

    // the dataset is the the set of element we are interested in:
    //gdcm::DataSet &ds = file.GetDataSet();

    gdcm::Anonymizer ano;
    ano.SetFile( reader.GetFile() );
    ano.RemoveGroupLength();
    ano.RemovePrivateTags();

    // PS 3.3 - 2008

```

```

// C.7.1.3 Clinical Trial Subject Module
// <entry group="0012" element="0010" vr="LO" vm="1" name="Clinical Trial Sponsor Name"/>
ano.Replace( gdcm::Tag(0x12,0x10), "BigCompany name" );
// <entry group="0012" element="0020" vr="LO" vm="1" name="Clinical Trial Protocol ID"/>
ano.Replace( gdcm::Tag(0x12,0x20), "My Clinical Trial Protocol ID" );
// <entry group="0012" element="0021" vr="LO" vm="1" name="Clinical Trial Protocol Name"/>
ano.Replace( gdcm::Tag(0x12,0x21), "My Clinical Trial Protocol Name" );
// <entry group="0012" element="0030" vr="LO" vm="1" name="Clinical Trial Site ID"/>
ano.Replace( gdcm::Tag(0x12,0x30), "My Clinical Trial Site ID" );
// <entry group="0012" element="0031" vr="LO" vm="1" name="Clinical Trial Site Name"/>
ano.Replace( gdcm::Tag(0x12,0x31), "My Clinical Trial Site Name" );
// <entry group="0012" element="0040" vr="LO" vm="1" name="Clinical Trial Subject ID"/>
ano.Replace( gdcm::Tag(0x12,0x40), "My Clinical Trial Subject ID" );
// <entry group="0012" element="0042" vr="LO" vm="1" name="Clinical Trial Subject Reading ID"/>
ano.Replace( gdcm::Tag(0x12,0x42), "My Clinical Trial Subject Reading ID" );

gdcm::Writer writer;
writer.SetFile( reader.GetFile() );
writer.SetFileName( outfilename );
if( !writer.Write() )
{
    return 1;
}

return 0;
}

```

12.42 CompressImage.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
/*
 *
 */

#include "gdcmImageReader.h"
#include "gdcmImage.h"
#include "gdcmWriter.h"
#include "gdcmAttribute.h"
#include "gdcmImageWriter.h"
#include "gdcmImageChangeTransferSyntax.h"

#include <iostream>
#include <fstream>

int main(int argc, char *argv[])
{
    if( argc < 3 )
    {
        std::cerr << argv[0] << " input.dcm output.dcm" << std::endl;
        return 1;
    }
    const char *filename = argv[1];
    const char *outfilename = argv[2];

    gdcm::ImageReader reader;
    reader.SetFileName( filename );
    if( !reader.Read() )
    {
        std::cerr << "Could not read: " << filename << std::endl;
        return 1;
    }

    // The output of gdcm::Reader is a gdcm::File

```



```

//gdcm::File &file = reader.GetFile();

// the dataset is the the set of element we are interested in:
//gdcm::DataSet &ds = file.GetDataSet();

gdcm::Image &image = reader.GetImage();
// image.SetSpacing(0, 0.1);
// image.SetSpacing(1, 0.2);
image.Print( std::cout );

gdcm::ImageChangeTransferSyntax change;
change.SetTransferSyntax( gdcm::TransferSyntax::JPEG2000Lossless );
change.SetTransferSyntax( gdcm::TransferSyntax::JPEGLosslessProcess14_1 );
//change.SetTransferSyntax( gdcm::TransferSyntax::JPEGBaselineProcess1 );
//change.SetTransferSyntax( image.GetTransferSyntax() );
change.SetInput( image );
bool b = change.Change();
if( !b )
{
    std::cerr << "Could not change the Transfer Syntax" << std::endl;
    return 1;
}

//std::ofstream out( outfilename, std::ios::binary );
//image.GetBuffer2(out);
//out.close();
gdcm::ImageWriter writer;
writer.SetImage( change.GetOutput() );
writer.SetFile( reader.GetFile() );
writer.SetFileName( outfilename );
if( !writer.Write() )
{
    return 1;
}

return 0;
}

```

12.43 ConvertToQImage.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.
=====*/

/*
 * This example shows how to setup the pipeline from a gdcm::ImageReader into a
 * Qt QImage data structure.
 * It only handles 2D image.
 *
 * Ref:
 * http://doc.trolltech.com/4.5/qimage.html
 *
 * Usage:
 * ConvertToQImage gdcmData/012345.002.050.dcm output.png
 *
 * Thanks:
 * Sylvain ADAM (sylvain51 hotmail com) for contributing this example
 */

#include "gdcmImageReader.h"
#include <QImage>
#include <QImageWriter>

bool ConvertToFormat_RGB888(gdcm::Image const & gimage, char *buffer, QImage* &imageQt)
{
    const unsigned int* dimension = gimage.GetDimensions();

    unsigned int dimX = dimension[0];

```

```

unsigned int dimY = dimension[1];

gimage.GetBuffer(buffer);

// Let's start with the easy case:
if( gimage.GetPhotometricInterpretation() == gdcm::PhotometricInterpretation::RGB )
{
    if( gimage.GetPixelFormat() != gdcm::PixelFormat::UINT8 )
    {
        return false;
    }
    unsigned char *ubuffer = (unsigned char*)buffer;
    // QImage::Format_RGB888 13 The image is stored using a 24-bit RGB format (8-8-8).
    imageQt = new QImage((unsigned char *)ubuffer, dimX, dimY, 3*dimX, QImage::Format_RGB888);
}
else if( gimage.GetPhotometricInterpretation() == gdcm::PhotometricInterpretation::MONOCHROME2 )
{
    if( gimage.GetPixelFormat() == gdcm::PixelFormat::UINT8 )
    {
        // We need to copy each individual 8bits into R / G and B:
        unsigned char *ubuffer = new unsigned char[dimX*dimY*3];
        unsigned char *pubuffer = ubuffer;
        for(unsigned int i = 0; i < dimX*dimY; i++)
        {
            *pubuffer++ = *buffer;
            *pubuffer++ = *buffer;
            *pubuffer++ = *buffer;
        }

        imageQt = new QImage(ubuffer, dimX, dimY, QImage::Format_RGB888);
    }
    else if( gimage.GetPixelFormat() == gdcm::PixelFormat::INT16 )
    {
        // We need to copy each individual 16bits into R / G and B (truncate value)
        short *buffer16 = (short*)buffer;
        unsigned char *ubuffer = new unsigned char[dimX*dimY*3];
        unsigned char *pubuffer = ubuffer;
        for(unsigned int i = 0; i < dimX*dimY; i++)
        {
            // Scalar Range of gdcmData/012345.002.050.dcm is [0,192], we could simply do:
            // *pubuffer++ = *buffer16;
            // *pubuffer++ = *buffer16;
            // *pubuffer++ = *buffer16;
            // instead do it right:
            *pubuffer++ = (unsigned char)std::min(255, (32768 + *buffer16) / 255);
            *pubuffer++ = (unsigned char)std::min(255, (32768 + *buffer16) / 255);
            *pubuffer++ = (unsigned char)std::min(255, (32768 + *buffer16) / 255);
            buffer16++;
        }

        imageQt = new QImage(ubuffer, dimX, dimY, QImage::Format_RGB888);
    }
    else
    {
        std::cerr << "Pixel Format is: " << gimage.GetPixelFormat() << std::endl;
        return false;
    }
}
else
{
    std::cerr << "Unhandled PhotometricInterpretation: " << gimage.GetPhotometricInterpretation() << std::endl;
    return false;
}

return true;
}

int main(int argc, char *argv[])
{
    if( argc < 2 )
    {
        return 1;
    }
    const char *filename = argv[1];
    const char *outfilename = argv[2];

    gdcm::ImageReader ir;
    ir.SetFileName( filename );
    if(!ir.Read())
    {
        //Read failed

```

```

        return 1;
    }

    std::cout<<"Getting image from ImageReader..."<<std::endl;

    const gdcm::Image &gimage = ir.GetImage();
    std::vector<char> vbuffer;
    vbuffer.resize( gimage.GetBufferLength() );
    char *buffer = &vbuffer[0];

    QImage *imageQt = NULL;
    if( !ConvertToFormat_RGB888( gimage, buffer, imageQt ) )
    {
        return 1;
    }

    QImageWriter writer;
    writer.setFormat("png");
    writer.setFileName( outfilename );
    if( !writer.write( *imageQt ) )
    {
        return 1;
    }

    return 0;
}

```

12.44 CreateARGBImage.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
/*
 * http://www.w3.org/Graphics/PNG/inline-alpha.html
 * alphatest.png: PNG image data, 380 x 287, 8-bit/color RGBA, non-interlaced
 *
 * $ convert alphatest.png alphatest.rgba
 */

#include "gdcmImageReader.h"
#include "gdcmSequenceOfFragments.h"
#include "gdcmSystem.h"
#include "gdcmImageWriter.h"

#include <iostream>
#include <fstream>

int main(int argc, char *argv[])
{
    if( argc < 3 )
    {
        std::cerr << argv[0] << " input.rgb output.dcm" << std::endl;
        return 1;
    }
    const char *filename = argv[1];
    const char *outfilename = argv[2];

    size_t len = gdcm::System::FileSize(filename);
    std::ifstream is(filename, std::ios::binary);

    char * buf = new char[len];
    is.read(buf, len);

    gdcm::ImageWriter writer;
    gdcm::Image &image = writer.GetImage();
    image.SetNumberOfDimensions( 2 );

```

```

unsigned int dims[3] = {};
dims[0] = 380;
dims[1] = 287;
image.SetDimensions( dims );
gdcm::PixelFormat pf = gdcm::PixelFormat::UINT8;
pf.SetSamplesPerPixel( 4 );
image.SetPixelFormat( pf );
gdcm::PhotometricInterpretation pi = gdcm::PhotometricInterpretation::ARGB;
image.SetPhotometricInterpretation( pi );
image.SetTransferSyntax( gdcm::TransferSyntax::ExplicitVRLittleEndian );

gdcm::DataElement pixeldata( gdcm::Tag(0x7fe0,0x0010) );
pixeldata.SetByteValue( buf, (uint32_t)len );
image.SetDataElement( pixeldata );

writer.SetFileName( outfilename );
if( !writer.Write() )
{
    return 1;
}
delete[] buf;

return 0;
}

```

12.45 CreateCMYKImage.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.
=====*/

/*
 * http://www.w3.org/Graphics/PNG/inline-alpha.html
 * alphatest.png: PNG image data, 380 x 287, 8-bit/color RGBA, non-interlaced
 *
 * $ convert alphatest.png alphatest.cmyk
 */

#include "gdcmImageReader.h"
#include "gdcmSequenceOfFragments.h"
#include "gdcmSystem.h"
#include "gdcmImageWriter.h"

#include <iostream>
#include <fstream>

int main(int argc, char *argv[])
{
    if( argc < 3 )
    {
        std::cerr << argv[0] << " input.cmyk output.dcm" << std::endl;
        return 1;
    }
    const char *filename = argv[1];
    const char *outfilename = argv[2];

    size_t len = gdcm::System::FileSize(filename);
    std::ifstream is(filename, std::ios::binary);

    char * buf = new char[len];
    is.read(buf, len);

    gdcm::ImageWriter writer;
    gdcm::Image &image = writer.GetImage();
    image.SetNumberOfDimensions( 2 );
    unsigned int dims[3] = {};

```

```

dims[0] = 380;
dims[1] = 287;
image.SetDimensions( dims );
gdcm::PixelFormat pf = gdcm::PixelFormat::UINT8;
pf.SetSamplesPerPixel( 4 );
image.SetPixelFormat( pf );
gdcm::PhotometricInterpretation pi = gdcm::PhotometricInterpretation::CMYK;
image.SetPhotometricInterpretation( pi );
image.SetTransferSyntax( gdcm::TransferSyntax::ExplicitVRLittleEndian );

gdcm::DataElement pixeldata( gdcm::Tag(0x7fe0,0x0010) );
pixeldata.SetByteValue( buf, (uint32_t)len );
image.SetDataElement( pixeldata );

writer.SetFileName( outfilename );
if( !writer.Write() )
{
    return 1;
}
delete[] buf;

return 0;
}

```

12.46 CreateJPIPDataSet.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
/*
 * This example was created during the GSOC 2011 project for
 * JPIP
 */
#include "gdcmAnonymizer.h"
#include "gdcmWriter.h"
#include "gdcmUIDGenerator.h"
#include "gdcmFile.h"
#include "gdcmTag.h"
#include "gdcmSystem.h"
#include "gdcmAttribute.h"

int main(int argc, char *argv[])
{
    if( argc < 2 )
    {
        std::cerr << argv[0] << " output.dcm" << std::endl;
        return 1;
    }
    const char *outfilename = argv[1];

    gdcm::Writer w;
    gdcm::File &file = w.GetFile();
    gdcm::DataSet &ds = file.GetDataSet();
    //w.SetCheckFileMetaInformation( true );
    w.SetFileName( outfilename );

    file.GetHeader().SetDataSetTransferSyntax( gdcm::TransferSyntax::JPIPReferenced );

    gdcm::Anonymizer anon;
    anon.SetFile( file );

    gdcm::MediaStorage ms = gdcm::MediaStorage::SecondaryCaptureImageStorage;

    gdcm::UIDGenerator gen;
    anon.Replace( gdcm::Tag(0x0008,0x16), ms.GetString() );
    std::cout << ms.GetString() << std::endl;
}

```

```

anon.Replace( gdcm::Tag(0x0008,0x18), gen.Generate() );
//
anon.Replace( gdcm::Tag(0x0010,0x10), "JPIP^EXAMPLE" );
anon.Replace( gdcm::Tag(0x0010,0x20), "012345" );
anon.Empty( gdcm::Tag(0x0010,0x30) );
anon.Empty( gdcm::Tag(0x0010,0x40) );
anon.Empty( gdcm::Tag(0x0008,0x20) );
anon.Empty( gdcm::Tag(0x0008,0x30) );
anon.Empty( gdcm::Tag(0x0008,0x90) );
anon.Empty( gdcm::Tag(0x0020,0x10) );
anon.Empty( gdcm::Tag(0x0020,0x11) );
anon.Empty( gdcm::Tag(0x0008,0x50) );
anon.Empty( gdcm::Tag(0x0020,0x0013) );
anon.Replace( gdcm::Tag(0x0020,0xd), gen.Generate() );
anon.Replace( gdcm::Tag(0x0020,0xe), gen.Generate() );
anon.Replace( gdcm::Tag(0x0008,0x64), "WSD " );
anon.Replace( gdcm::Tag(0x0008,0x60), "OT" );

gdcm::Attribute<0x0028,0x7FE0> at;
at.SetValue( "http://dicom.example.com/jpipserver.cgi?target=img.jp2" );
ds.Insert( at.GetAsDataElement() );

// Need to retrieve the PixelFormat information from the given file

if (!w.Write() )
{
    std::cerr << "Could not write: " << outfilename << std::endl;
    return 1;
}

return 0;
}

```

12.47 DeriveSeries.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
#include "gdcmReader.h"
#include "gdcmWriter.h"
#include "gdcmAttribute.h"
#include "gdcmFileDerivation.h"
#include "gdcmUIDGenerator.h"

int main(int argc, char *argv[])
{
    if( argc < 3 )
    {
        return 1;
    }
    const char * ref = argv[1];
    const char * in = argv[2];

    gdcm::Reader r1;
    r1.SetFileName( ref );
    if( !r1.Read() ) return 1;

    gdcm::Reader r2;
    r2.SetFileName( in );
    if( !r2.Read() ) return 1;

    // Fix Spatial info:
    gdcm::DataSet & ds1 = r1.GetFile().GetDataSet();
    gdcm::File & file2 = r2.GetFile();
    gdcm::DataSet & ds2 = file2.GetDataSet();

```

```

//gdcm::Attribute<0x8,0x8> img_type = { "ORIGINAL", "PRIMARY" };
ds2.Replace( ds1.GetDataElement( gdcm::Tag(0x0008,0x0008) ));
ds2.Replace( ds1.GetDataElement( gdcm::Tag(0x0020,0x0032) ));
ds2.Replace( ds1.GetDataElement( gdcm::Tag(0x0020,0x0037) ));
ds2.Replace( ds1.GetDataElement( gdcm::Tag(0x0018,0x0088) )); // Spacing between slices
ds2.Replace( ds1.GetDataElement( gdcm::Tag(0x0020,0x0013) )); // Instance Number
ds2.Replace( ds1.GetDataElement( gdcm::Tag(0x0018,0x5100) )); // Patient Position
ds2.Replace( ds1.GetDataElement( gdcm::Tag(0x0018,0x0050) )); // Slice Thickness
ds2.Replace( ds1.GetDataElement( gdcm::Tag(0x0008,0x0070) )); // Manufacturer
ds2.Replace( ds1.GetDataElement( gdcm::Tag(0x0018,0x0081) )); // Echo Time
ds2.Replace( ds1.GetDataElement( gdcm::Tag(0x0020,0x1041) )); // Slice Location

gdcm::Attribute<0x8,0x16> sopclassuid;
sopclassuid.SetFromDataSet( ds1 );
gdcm::Attribute<0x8,0x18> sopinstanceuid;
sopinstanceuid.SetFromDataSet( ds1 );

// Step 2: DERIVED object
gdcm::FileDerivation fd;
fd.AddReference( sopclassuid.GetValue(), sopinstanceuid.GetValue() );

// http://dicom.nema.org/MEDICAL/dicom/current/output/chtml/part16/chapter_D.html#DCM_121321
// CID 7202 "Source Image Purposes of Reference"
// DCM 121321 "Mask image for image processing operation"
fd.SetPurposeOfReferenceCodeSequenceCodeValue( 121321 );
// CID 7203 "Image Derivation"
// DCM 113047 "Pixel by pixel mask"
fd.SetDerivationCodeSequenceCodeValue( 113047 );
fd.SetFile( file2 );
// If all Code Value are ok the filter will execute properly
if( !fd.Derive() )
{
    std::cerr << "Sorry could not derive using input info" << std::endl;
    return 1;
}

gdcm::Writer w;
w.SetFile( r2.GetFile() );
w.SetFileName( "derived.dcm" );
if( !w.Write() )
{
    return 1;
}

return 0;
}

```

12.48 DiffFile.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.
=====*/
#include "gdcmReader.h"

int main(int argc, char *argv[])
{
    if( argc < 3 )
    {
        std::cerr << argv[0] << " input1.dcm input2.dcm" << std::endl;
        return 1;
    }
    const char *filename1 = argv[1];
    const char *filename2 = argv[2];

    gdcm::Reader reader1;
    reader1.SetFileName( filename1 );

```

```

if( !reader1.Read() )
{
    return 1;
}

gdcm::Reader reader2;
reader2.SetFileName( filename2 );
if( !reader2.Read() )
{
    return 1;
}

const gdcm::File &file1 = reader1.GetFile();
const gdcm::File &file2 = reader2.GetFile();

const gdcm::DataSet &ds1 = file1.GetDataSet();
const gdcm::DataSet &ds2 = file2.GetDataSet();

gdcm::DataSet::ConstIterator it1 = ds1.Begin();
gdcm::DataSet::ConstIterator it2 = ds2.Begin();

const gdcm::DataElement &de1 = *it1;
const gdcm::DataElement &de2 = *it2;
if( de1 == de2 )
{
}
while( it1 != ds1.End() && it2 != ds2.End() && *it1 == *it2 )
{
    ++it1;
    ++it2;
}

if( it1 != ds1.End() || it2 != ds2.End() )
{
    std::cerr << "Problem with:" << std::endl;
    if( it1 != ds1.End() )
    {
        std::cerr << "ds1: " << *it1 << std::endl;
    }
    if( it2 != ds2.End() )
    {
        std::cerr << "ds2: " << *it2 << std::endl;
    }
    return 1;
}

return 0;
}

```

12.49 DiscriminateVolume.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
#include "gdcmScanner.h"
#include "gdcmTesting.h"
#include "gdcmIPPSorter.h"
#include "gdcmDirectionCosines.h"
#include <cmath>

/*
 * The following example is a basic sorted which should work in generic cases.
 * It sort files based on:
 * Study Instance UID
 * Series Instance UID
 * Frame of Reference UID
 */

```



```

*      Image Orientation (Patient)
*      Image Position (Patient) (Sorting based on IPP + IOP)
*/

namespace gdcm {
    const Tag t1(0x0020,0x000d); // Study Instance UID
    const Tag t2(0x0020,0x000e); // Series Instance UID
    const Tag t3(0x0020,0x0052); // Frame of Reference UID
    const Tag t4(0x0020,0x0037); // Image Orientation (Patient)

class DiscriminateVolume
{
private:
    std::vector< Directory::FileNamesType > SortedFiles;
    std::vector< Directory::FileNamesType > UnsortedFiles;

    Directory::FileNamesType GetAllFileNamesFromTagToValue(
        Scanner const & s, Directory::FileNamesType const & filesubset, Tag const & t, const char *valueref)
    {
        Directory::FileNamesType theReturn;
        if( valueref )
        {
            size_t len = strlen( valueref );
            Directory::FileNamesType::const_iterator file = filesubset.begin();
            for(; file != filesubset.end(); ++file)
            {
                const char *filename = file->c_str();
                const char * value = s.GetValue(filename, t);
                if( value && strncmp(value, valueref, len ) == 0 )
                {
                    theReturn.push_back( filename );
                }
            }
        }
        return theReturn;
    }

void ProcessAIOP(Scanner const & , Directory::FileNamesType const & subset, const char *iopval)
{
    std::cout << "IOP: " << iopval << std::endl;
    IPPSorter ipp;
    ipp.SetComputeZSpacing( true );
    ipp.SetZSpacingTolerance( 1e-3 ); // ??
    bool b = ipp.Sort( subset );
    if( !b )
    {
        // If you reach here this means you need one more parameter to discriminiat this
        // series. Eg. T1 / T2 intertwined. Multiple Echo (0018,0081)
        std::cerr << "Failed to sort: " << subset.begin()->c_str() << std::endl;
        for(
            Directory::FileNamesType::const_iterator file = subset.begin();
            file != subset.end(); ++file)
        {
            std::cerr << *file << std::endl;
        }
        UnsortedFiles.push_back( subset );
        return ;
    }
    ipp.Print( std::cout );
    SortedFiles.push_back( ipp.GetFileNames() );
}

void ProcessAFrameOfRef(Scanner const & s, Directory::FileNamesType const & subset, const char * frameuid)
{
    // In this subset of files (belonging to same series), let's find those
    // belonging to the same Frame ref UID:
    Directory::FileNamesType files = GetAllFileNamesFromTagToValue(
        s, subset, t3, frameuid);

    std::set< std::string > iopset;

    for(
        Directory::FileNamesType::const_iterator file = files.begin();
        file != files.end(); ++file)
    {
        //std::cout << *file << std::endl;
        const char * value = s.GetValue(file->c_str(), gdcm::t4 );
        gdcm_assert( value );
        iopset.insert( value );
    }
    size_t n = iopset.size();
}

```

```

if ( n == 0 )
{
    gdcm_assert( files.empty() );
    return;
}

std::cout << "Frame of Ref: " << frameuid << std::endl;
if ( n == 1 )
{
    ProcessAIOP(s, files, iopset.begin()->c_str() );
}
else
{
    const char *f = files.begin()->c_str();
    std::cerr << "More than one IOP: " << f << std::endl;
    // Make sure that there is actually 'n' different IOP
    gdcm::DirectionCosines ref;
    gdcm::DirectionCosines dc;
    for(
        std::set< std::string >::const_iterator it = iopset.begin();
        it != iopset.end(); ++it )
    {
        ref.SetFromString( it->c_str() );
        for(
            Directory::FileNamesType::const_iterator file = files.begin();
            file != files.end(); ++file )
        {
            std::string value = s.GetValue(file->c_str(), gdcm::t4 );
            if( value != it->c_str() )
            {
                dc.SetFromString( value.c_str() );
                const double crossdot = ref.CrossDot(dc);
                const double eps = std::fabs( 1. - crossdot );
                if( eps < 1e-6 )
                {
                    std::cerr << "Problem with IOP discrimination: " << file->c_str()
                        << " " << it->c_str() << std::endl;
                    return;
                }
            }
        }
    }
    // If we reach here this means there is actually 'n' different IOP
    for(
        std::set< std::string >::const_iterator it = iopset.begin();
        it != iopset.end(); ++it )
    {
        const char *iopvalue = it->c_str();
        Directory::FileNamesType iopfiles = GetAllFileNamesFromTagToValue(
            s, files, t4, iopvalue );
        ProcessAIOP(s, iopfiles, iopvalue );
    }
}

void ProcessASeries(Scanner const & s, const char * seriesuid)
{
    std::cout << "Series: " << seriesuid << std::endl;
    // let's find all files belonging to this series:
    Directory::FileNamesType seriesfiles = GetAllFileNamesFromTagToValue(
        s, s.GetFileNames(), t2, seriesuid);

    gdcm::Scanner::ValuesType vt3 = s.GetValues(t3);
    for(
        gdcm::Scanner::ValuesType::const_iterator it = vt3.begin()
        ; it != vt3.end(); ++it )
    {
        ProcessAFrameOfRef(s, seriesfiles, it->c_str());
    }
}

void ProcessAStudy(Scanner const & s, const char * studyuid)
{
    std::cout << "Study: " << studyuid << std::endl;
    gdcm::Scanner::ValuesType vt2 = s.GetValues(t2);
    for(
        gdcm::Scanner::ValuesType::const_iterator it = vt2.begin()
        ; it != vt2.end(); ++it )
    {
        ProcessASeries(s, it->c_str());
    }
}

```

```

}
public:

void Print( std::ostream & os )
{
    os << "Sorted Files: " << std::endl;
    for(
        std::vector< Directory::FilenameType >::const_iterator it = SortedFiles.begin();
        it != SortedFiles.end(); ++it )
    {
        os << "Group: " << std::endl;
        for(
            Directory::FilenameType::const_iterator file = it->begin();
            file != it->end(); ++file)
        {
            os << *file << std::endl;
        }
    }
    os << "Unsorted Files: " << std::endl;
    for(
        std::vector< Directory::FilenameType >::const_iterator it = UnsortedFiles.begin();
        it != UnsortedFiles.end(); ++it )
    {
        os << "Group: " << std::endl;
        for(
            Directory::FilenameType::const_iterator file = it->begin();
            file != it->end(); ++file)
        {
            os << *file << std::endl;
        }
    }
}

std::vector< Directory::FilenameType > const & GetSortedFiles() const { return SortedFiles; }
std::vector< Directory::FilenameType > const & GetUnsortedFiles() const { return UnsortedFiles; }

void ProcessIntoVolume( Scanner const & s )
{
    gdcm::Scanner::ValueType vt1 = s.GetValues( gdcm::t1 );
    for(
        gdcm::Scanner::ValueType::const_iterator it = vt1.begin()
        ; it != vt1.end(); ++it )
    {
        ProcessAStudy( s, it->c_str() );
    }
}

};

} // namespace gdcm

int main(int argc, char *argv[])
{
    std::string dirl;
    if( argc < 2 )
    {
        const char *extradataroot = nullptr;
#ifdef GDCM_BUILD_TESTING
        extradataroot = gdcm::Testing::GetDataExtraRoot();
#endif
        if( !extradataroot )
        {
            return 1;
        }
        dirl = extradataroot;
        dirl += "/gdcmSampleData/ForSeriesTesting/VariousIncidences/ST1";
    }
    else
    {
        dirl = argv[1];
    }

    gdcm::Directory d;
    d.Load( dirl, true ); // recursive !

    gdcm::Scanner s;
    s.AddTag( gdcm::t1 );
    s.AddTag( gdcm::t2 );
    s.AddTag( gdcm::t3 );

```

```

s.AddTag( gdcmm::t4 );
bool b = s.Scan( d.GetFilesNames() );
if( !b )
{
    std::cerr << "Scanner failed" << std::endl;
    return 1;
}

gdcmm::DiscriminateVolume dv;
dv.ProcessIntoVolume( s );
dv.Print( std::cout );

return 0;
}

```

12.50 DumpADAC.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcmm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.
=====*/

/*
 * the goal of this example is to mimic the behavior of disp_img_header
 * see http://www.gmccorp-usa.com/IM/NM/GC/ADAC/SV/adactechtips/Released_01Q3.pdf
 */
#include "gdcmmReader.h"
#include "gdcmmPrivateTag.h"
#include "gdcmmAttribute.h"
#include "gdcmmImageWriter.h"

#include <iostream>
#include <fstream>
#include <vector>

#include <string.h>
#include <assert.h>
#include <stdint.h>

struct dict
{
    uint16_t key;
    const char *name;
};

dict Array[] = {
    { 0x01, "Patient name" },
    { 0x02, "Patient ID" },
    { 0x03, "Patient sex" },
    { 0x04, "Patient age" },
    { 0x05, "Patient height" },
    { 0x06, "Patient weight" },
    { 0x07, "Exam date" },
    { 0x08, "Dose admin. time" },
    { 0x09, "Unique exam key" },
    { 0x0a, "Exam procedure" },
    { 0x0b, "Referring physician" },
    { 0x0c, "Attending physician" },
    { 0x0d, "Imaging modality" },
    { 0x0e, "Hospital ID" },
    { 0x0f, "Histogram crv file" },
    { 0x10, "Acq. start time" },
    { 0x11, "Object data type" },
    { 0x12, "Image viewid" },
    { 0x13, "Imaging device name" },
    { 0x14, "Device serial number" },
    { 0x15, "Collimator" },
    { 0x16, "Software version" },
}

```

```

{ 0x17, "Radiopharmaceutical #1" },
{ 0x18, "Energy window #1 center" },
{ 0x19, "Radiopharmaceutical #2" },
{ 0x1a, "Energy window #1 width" },
{ 0x1b, "Isotope imaging mode" },
{ 0x1c, "Energy window #2 center" },
{ 0x1d, "Energy window #2 width" },
{ 0x1e, "Energy window #3 center" },
{ 0x1f, "Energy window #3 width" },
{ 0x20, "Energy window #4 center" },
{ 0x21, "Energy window #4 width" },
{ 0x22, "??Energy window #5 center" },
{ 0x23, "??Energy window #5 width" },
{ 0x24, "Patient orientation" },
{ 0x25, "Spatial resolution" },
{ 0x26, "Slice thickness" },
{ 0x27, "Image X dimension" },
{ 0x28, "Image Y dimension" },
{ 0x29, "Image Z dimension" },
{ 0x2a, "Image pixel width" },
{ 0x2b, "Uniformity corr. file" },
{ 0x2c, "Acquisition zoom factor" },
{ 0x2d, "Total counts in set" },
{ 0x2e, "Time / frame" },
{ 0x2f, "Total acq. time" },
{ 0x30, "Maximum pixel value" },
{ 0x31, "Minimum pixel value" },
{ 0x32, "R-R interval time" },
{ 0x33, "Percent of cycle imaged" },
{ 0x34, "# of cycles accepted" },
{ 0x35, "# of cycles rejected" },
{ 0x36, "Approximate ED frame" },
{ 0x37, "Approximate ES frame" },
{ 0x38, "Approximate EF" },
{ 0x39, "Starting angle" },
{ 0x3a, "Degrees of rotation" },
{ 0x3b, "Direction of rotation" },
{ 0x3c, "Cont. or step/shoot" },
{ 0x3d, "Lim recon start frame" },
{ 0x3e, "Upper window grey shade" },
{ 0x3f, "Lower lvl grey shade" },
{ 0x40, "Associated color map" },
{ 0x41, "Custom color map file" },
{ 0x42, "Manipulated image" },
{ 0x43, "Axis of rotation corr." },
{ 0x44, "Reorientation azimuth" },
{ 0x45, "Reorientation elevation" },
{ 0x46, "Filter type" },
{ 0x47, "Filter order" },
{ 0x48, "Filter cutoff frequency" },
{ 0x49, "Reconstruction type" },
{ 0x4a, "Attenuation coefficient" },
{ 0x4b, "Associated parent file" },
{ 0x4c, "Unique patient key" },
{ 0x52, "Normalization crv file" },
{ 0x53, "Unique object key" },
{ 0x54, "This phase of VFR is" },
{ 0x55, "True color value" },
{ 0x56, "# of sets of x,y,z grps" },
{ 0x57, "Scale factor of set" },
{ 0x6d, "Date of birth" },
{ 0x6e, "Directional orientation" },
{ 0x6f, "Number of VFR studies" },
{ 0x70, "R-R low tolerance" },
{ 0x71, "R-R high tolerance" },
{ 0x72, "Prog specific results:" },

{ 0x99, nullptr }
};

void printname( int , int , uint16_t v )
{
    if( v == 0x1 )
    {
        std::cout << "DATABASE PARAMETERS" << std::endl;
        std::cout << "_____ " << std::endl;
    }
    else if( v == 0x27 )
    {
        std::cout << "IMAGE PARAMETERS" << std::endl;
        std::cout << "_____ " << std::endl;
    }
}

```

```

    }
    else if( v == 0x13 )
    {
        std::cout << "EXTRA PARAMETERS" << std::endl;
        std::cout << "_____ " << std::endl;
    }
    else if( v == 0x2e )
    {
        std::cout << "*** NOT CURRENTLY USED : " << std::endl;
    }
    static const unsigned int n = sizeof( Array ) / sizeof( *Array ) - 1;
    for( unsigned int i = 0; i < n; ++i )
    {
        if( v == Array[i].key )
        {
            std::cout << /*" " << std::dec << len << ", " << mult << " " << */ Array[i].name;
            std::cout << " : ";
            return;
        }
    }
    std::cout << /*"\t# " << std::dec << len << ", " << mult << */ std::hex << v << "\t: ";
}

uint16_t readint16(std::istream &is )
{
    uint16_t val;
    is.read( (char*)&val, sizeof( val ));
    return (uint16_t)((val>>8) | (val<<8));
}

uint32_t readint32(std::istream &is )
{
    uint32_t val;
    is.read( (char*)&val, sizeof( val ));
    val = ((val<<8)&0xFF00FF00) | ((val>>8)&0x00FF00FF);
    return (val>>16) | (val<<16);
}

float readfloat32(std::istream &is )
{
    union { uint32_t val; float f; } dual;
    dual.val = readint32(is);
    return dual.f;
}

struct el
{
    uint16_t v1;
    uint16_t v2;
    uint16_t v3;
    void read( std::istream & is )
    {
        v1 = readint16(is);
        v2 = readint16(is);
        v3 = readint16(is);
    }
    void print( std::ostream & os )
    {
        os << std::hex << v1 << "\t" << v2 << "\t" << v3 << std::endl;
    }
};

std::vector<el> Vel;

void readelement( std::istream & is )
{
    el e;
    e.read( is );
    Vel.push_back( e );
}

void printascii( uint16_t tag, const char *buffer, size_t len )
{
    std::ostream & os = std::cout;
    if( tag == 0x72 )
    {
        os << "\n ";
        for(size_t i = 0; i < len; ++i)
        {
            const char &c = buffer[i];
            if( c == 0x0 ) os << "!";

```

```

        else if( c == 0x0f ) os << " ";
        else if( c == 0x17 ) os << " ";
        else if( c == 0x14 ) os << " ";
        else if( c == 0x10 ) os << " ";
        else if( c == 0x16 ) os << " ";
        else if( c == 0x08 ) os << " ";
        else if( c == 0x0b ) os << " ";
        else if( c == 0x0e ) os << " ";
        else if( c == 0x07 ) os << " ";
        else os << c;
    }
    os << " ";
}
else
{
    (void)len;
    os << " " << buffer << " ";
}
}

bool DumpADAC( std::istream & is )
{
    std::ostream &os = std::cout;

    char magic[6 + 1];
    magic[6] = 0;
    is.read( magic, 6);
    // std::cout << magic << " ";
    gdcmm_assert( strcmp( magic, "adac01" ) == 0 );
    int c = is.get();
    gdcmm_assert( c == 0 ); (void)c;
    c = is.get();
    gdcmm_assert( c == 'X' );

    uint16_t v;
    v = readint16(is);
    // std::cout << v << std::endl;
    gdcmm_assert( v == 512 ); (void)v; // ??

    int nel = 87;
    for (int i = 0; i <= nel; ++i )
    {
        readelement( is );
    }

    char buffer[512];
    for( int i = 0; i <= nel; ++i )
    {
        const el &e = Vel[i];
        int diff;
        if( i == nel )
        {
            diff = 2048 - e.v3;
            if( diff > 512 ) diff = 512;
        }
        else
        {
            const el &enext = Vel[i+1];
            diff = enext.v3 - e.v3;
        }
        is.seekg( e.v3, std::ios::beg );
        //std::cout << "(" << std::hex << std::setw( 2 ) << std::setfill( '0' ) << e.v1 << ")" << " " << std::hex << std::setw( 3 )
        // << std::setfill( '0' ) << e.v2 << " ";
        printname( diff, 0, e.v1 );
        int mult = 1;
        if( e.v2 == 0 )
        {
            is.read( buffer, diff);
            buffer[ diff ] = 0;
            printascii( e.v1, buffer, diff);
        }
        else if( e.v2 == 0x100 )
        {
            mult = diff / 2;
            gdcmm_assert( diff == 2 * mult );
            for ( int ii = 0; ii < mult; ++ii )
            {
                if ( ii ) os << "\\ ";
                uint16_t val = readint16(is);
                os << " " << std::dec << val << " ";
            }
        }
    }
}

```

```

    }
    else if( e.v2 == 0x200 )
    {
        gdcmm_assert( diff == 4 );
        uint32_t val = readint32(is);
        os << "" << std::dec << val << "";
    }
    else if( e.v2 == 0x300 )
    {
        gdcmm_assert( diff == 4 );
        float val = readfloat32(is);
        os << "" << std::dec << val << "";
    }
    else
    {
        gdcmm_assert( 0 );
    }
    os << std::endl;
}
return true;
}

int main(int argc, char *argv[])
{
    if( argc < 2 ) return 1;
    const char *filename = argv[1];
    gdcmm::Reader reader;
    reader.SetFileName( filename );
    if( !reader.Read() )
    {
        std::cerr << "Failed to read: " << filename << std::endl;
        return 1;
    }
    const gdcmm::DataSet& ds = reader.GetFile().GetDataSet();

    // (0019,1061) UN (OB) 61\64\61\63\30          # 2048,1 Ver200 ADAC Pegasys Headers
    const gdcmm::PrivateTag tver200adacpegasysheaders(0x0019,0x61,"ADAC_IMG");
    if( !ds.FindDataElement( tver200adacpegasysheaders ) ) return 1;
    const gdcmm::DataElement& ver200adacpegasysheaders = ds.GetDataElement( tver200adacpegasysheaders );
    if ( ver200adacpegasysheaders.IsEmpty() ) return 1;
    const gdcmm::ByteValue * bv = ver200adacpegasysheaders.GetByteValue();

    // (0019,1021) US 1          # 2,1 Ver200 Number of ADAC Headers
    // TODO

    // (0019,1041) IS [2048\221184 ] # 12,1-n Ver200 ADAC Header/Image Size
    if( bv->GetLength() != 2048 ) return 1;

    gdcmm::Element<gdcmm::VR::IS,gdcmm::VM::VM2> el;
    const gdcmm::PrivateTag tver200adacheaderimagesize(0x0019,0x41,"ADAC_IMG");
    if( !ds.FindDataElement( tver200adacheaderimagesize ) ) return 1;
    const gdcmm::DataElement& ver200adacheaderimagesize = ds.GetDataElement( tver200adacheaderimagesize );
    el.SetFromDataElement( ver200adacheaderimagesize );
    if( el.GetValue(0) != 2048 ) return 1;

    std::stringstream is;
    std::string dup( bv->GetPointer(), bv->GetLength() );
    is.str( dup );
    bool b = DumpADAC( is );
    if( !b ) return 1;

    return 0;
}

```

12.51 DumpExamCard.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcmm.sourceforge.net/Copyright.html for details.

```



```

    This software is distributed WITHOUT ANY WARRANTY; without even
    the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
    PURPOSE. See the above copyright notice for more information.

=====*/
/*

    Try to extract contents of Philips RAW storage class:

(0002,0002) UI [1.2.840.10008.5.1.4.1.1.66]          # 26,1 Media Storage SOP Class UID
(0002,0003) UI [1.3.46.670589.11.17240.5.23.4.1.3012.2010032409482568018] # 56,1 Media Storage SOP
    Instance UID
(0002,0010) UI [1.2.840.10008.1.2.1]                # 20,1 Transfer Syntax UID
(0002,0012) UI [1.3.46.670589.11.0.0.51.4.4.1]      # 30,1 Implementation Class UID
(0002,0013) SH [MR DICOM 4.1]                      # 12,1 Implementation Version Name

* Everything done in this code is for the sole purpose of writing interoperable
* software under Sect. 1201 (f) Reverse Engineering exception of the DMCA.
* If you believe anything in this code violates any law or any of your rights,
* please contact us (gdcm-developers@lists.sourceforge.net) so that we can
* find a solution.
*
* Everything you do with this code is at your own risk, since decompression
* algorithm was not written from specification documents.
*
* Special thanks to:
* Triplett, William T for bringing to your attention on this ExamCard stuff
*/
#include "gdcmReader.h"
#include "gdcmDataSet.h"
#include "gdcmPrivateTag.h"
#include "gdcmBase64.h"

#include <iomanip>

static bool compfn(const char *s1, const char *s2)
{
    return strcmp(s1,s2) < 0 ? true : false;
}

static const char *PDFStrings[] = { // Keep me ordered please
    "COILSTATE", // series of string ?
    "HARDWARE_CONFIG", // series of number ?
    "PDF_CONTROL_GEN_PARS",
    "PDF_CONTROL_PREP_PARS",
    "PDF_CONTROL_RECON_PARS",
    "PDF_CONTROL_SCAN_PARS",
    "PDF_EXAM_PARS",
    "PDF_HARDWARE_PARS",
    "PDF_PREP_PARS",
    "PDF_PRESCAN_COIL_PARS",
    "PDF_SPT_PARS",
};

static bool isvalidpdfstring( const char *pdfstring )
{
    gdcm_assert( pdfstring );
    static const size_t n = sizeof( PDFStrings ) / sizeof( *PDFStrings );
    static const char **begin = PDFStrings;
    static const char **end = begin + n;
    return std::binary_search(begin, end, pdfstring, compfn);
}

typedef enum
{
    param_float = 0,
    param_integer = 1, // 1 << 0
    param_string = 2, // 1 << 1
    param_3, // ??
    param_enum = 4 // 1 << 2
} param_type;

static const char *gettypenamefromtype( int i)
{
    const char *ret = nullptr;
    param_type e = (param_type)i;
    switch( e )
    {
        case param_float:
            ret = "float";
            break;
    }
}

```

```

    case param_integer:
        ret = "int";
        break;
    case param_string:
        ret = "string";
        break;
    case param_3:
        ret = "??";
        break;
    case param_enum:
        ret = "enum";
        break;
    }
    gdcmm_assert( ret );
    return ret;
}

struct header
{
    /*
     * TODO:
     * Looks as if we could read all int*, float* and string* at once...
     */
    int32_t v1; // offset to int pointer array ?
    uint16_t nints; // number of ints (max number?)
    uint16_t v3; // always 0 ?
    int32_t v4; // offset to float pointer array ?
    uint32_t nfloats;
    int32_t v6; // offset to string pointer array ?
    uint32_t nstrings;
    int32_t v8; // always 8 ??
    uint32_t numparams;
    uint32_t getnints() const { return nints; }
    uint32_t getnfloats() const { return nfloats; }
    uint32_t getnstrings() const { return nstrings; }
    uint32_t getnparams() const { return numparams; }
    void read( std::istream & is )
    {
        is.read( (char*)&v1, sizeof(v1));
        if( v1 == 0x01 ) {
            // direct (FIXME how should we detect this, much like TIFF ???)
            nints = 0;
            v3 = 0;
            v4 = 0;
            nfloats = 0;
            v6 = 0;
            nstrings = 0;
            v8 = 0;
            numparams = 0;
            uint32_t bla;
            is.read( (char*)&bla, sizeof(bla) );
            gdcmm_assert( bla == 0x2 || bla == 0x3 );
            nstrings = 1;
            numparams = 1;
        } else {
            // indirect
            is.read( (char*)&nints, sizeof(nints));
            is.read( (char*)&v3, sizeof(v3));
            gdcmm_assert( v3 == 0 ); // looks like this is always 0
            is.read( (char*)&v4, sizeof(v4));
            is.read( (char*)&nfloats, sizeof(nfloats));
            is.read( (char*)&v6, sizeof(v6));
            is.read( (char*)&nstrings, sizeof(nstrings));
            is.read( (char*)&v8, sizeof(v8));
            gdcmm_assert( v8 == 8 );
            is.read( (char*)&numparams, sizeof(numparams));
        }
    }
}

void print( std::ostream & os )
{
    os << v1 << ", ";
    os << nints << ", ";
    os << v3 << ", ";
    os << v4 << ", ";
    os << nfloats << ", ";
    os << v6 << ", ";
    os << nstrings << ", ";
    os << v8 << ", ";
    os << numparams << std::endl;
}

```

```

};

struct param
{
    char name[32+1];
    uint8_t boolean;
    int32_t type;
    uint32_t dim;
    union {
        uint32_t val;
        char * ptr; } v4;
    int32_t /*std::streamoff*/ offset;
    param_type gettype() const { return (param_type)type; }
    uint32_t getdim() const { return dim; }
    void read_direct_int( std::istream & is ) {
        uint32_t bla;
        int max = 9;
        std::vector<uint32_t> v;
        for( int i = 0; i < max; ++i ) {
            is.read( (char*)&bla, sizeof(bla) );
            v.push_back( bla );
        }
        is.read( (char*)&bla, sizeof(bla) );
        char name0[32];
        memset(name0,0,sizeof(name0));
        gdcmm_assert( bla < sizeof(name0) );
        is.read( name0, bla );
        size_t l = strlen(name0);
        gdcmm_assert( l == bla ); (void)l;
        char * ptr = strdup( name0 );
        v4.ptr = ptr;
        type = param_string;
        dim = 1;
        offset = 0; // important !
    }
    void read_direct_string( std::istream & is ) {
        uint32_t bla;
        is.read( (char*)&bla, sizeof(bla) );
        char name0[32];
        memset(name0,0,sizeof(name0));
        gdcmm_assert( bla < sizeof(name0) );
        is.read( name0, bla );
        size_t l = strlen(name0);
        gdcmm_assert( l == bla ); (void)l;
        memcpy( this->name, name0, bla );
        is.read( (char*)&bla, sizeof(bla) );
        gdcmm_assert( bla == 0x1 );
        is.read( (char*)&bla, sizeof(bla) );
        char value[32];
        memset(value,0,sizeof(value));
        gdcmm_assert( bla < sizeof(value) );
        is.read( value, bla );
        is.read( (char*)&bla, sizeof(bla) );
        gdcmm_assert( bla == 0 ); // trailing stuff ?
        is.read( (char*)&bla, sizeof(bla) );
        gdcmm_assert( bla == 0 ); // trailing stuff ?
        const uint32_t cur = (uint32_t)is.tellg();
        std::cerr << "offset:" << cur << std::endl;
        if( cur == 65 )
            is.read( (char*)&bla, 1 );
        else if( cur == 66 )
            is.read( (char*)&bla, 1 );
        else if( cur == 122 )
            is.read( (char*)&bla, 2 );
        else
            gdcmm_assert(0);
        type = param_string;
        dim = 1;
        // FIXME: store the value in v4 for now:
        char * ptr = strdup( value );
        v4.ptr = ptr;
        offset = 0; // important !
    }
}

void read( std::istream & is )
{
    is.read( name, 32 + 1 );
    // This is always the same issue the string can contains garbage from previous run,
    // we need to print only until the first \0 character:
    gdcmm_assert( strlen( name ) <= 32 );
    is.read( (char*)&boolean,1);
    gdcmm_assert( boolean == 0 || boolean == 1 || boolean == 0x69 ); // some kind of bool, or digital trash ?

```

```

    is.read( (char*)&type, sizeof( type ) );
    gdcmm_assert( gettypenamefromtype( type ) );
    is.read( (char*)&dim, sizeof( dim ) ); // number of elements
    is.read( (char*)&v4.val, sizeof( v4.val ) );
    //gdcmm_assert( v4.val == 0 ); // always 0 ? sometimes not...
    const uint32_t cur = (uint32_t)is.tellg();
    is.read( (char*)&offset, sizeof( offset ) );
    gdcmm_assert( offset != 0 );
    offset += cur;
}

void print( std::ostream & os ) const
{
    os << name << ",";
    os << (int)boolean << ",";
    os << type << ",";
    os << dim << ",";
    os << v4.val << ",";
    os << offset << std::endl;
}

void printvalue( std::ostream & os, std::istream & is ) const
{
    if( offset ) {
        is.seekg( offset );
        switch( type )
        {
            case param_float:
            {
                os.precision(2);
                os << std::fixed;
                for( uint32_t idx = 0; idx < dim; ++idx )
                {
                    if( idx ) os << ",";
                    float v;
                    is.read( (char*)&v, sizeof(v) );
                    os << v; // what if the string contains \0 ?
                }
            }
            break;
            case param_integer:
            {
                int32_t v;
                for( uint32_t idx = 0; idx < dim; ++idx )
                {
                    if( idx ) os << ",";
                    is.read( (char*)&v, sizeof(v) );
                    os << v;
                }
            }
            break;
            case param_string:
            {
                int size = 81;
                std::string v;
                v.resize( size );
                for( uint32_t idx = 0; idx < dim; ++idx )
                {
                    if( idx ) os << ",";
                    is.read( &v[0], size );
                    os << v.c_str();
                }
            }
            break;
            case param_enum:
            {
                int32_t v;
                for( uint32_t idx = 0; idx < dim; ++idx )
                {
                    if( idx ) os << ",";
                    is.read( (char*)&v, sizeof(v) );
                    os << v;
                }
            }
            break;
        }
    }
    else {
        #if 1
        // direct
        assert ( type == param_string );
        char * ptr = v4.ptr;
        //std::string v;

```

```

        //v.resize( dim );
        //is.read( &v[0], dim );
        os << ptr;
#endif
    }

    }

void printxml( std::ostream & os, std::istream & is ) const
{
    // <Attribute Name="CGEN_force_par_mode" Type="enum">0</Attribute>
    os << " <Attribute";
    os << " Name=\"" << name << "\"";
    os << " Type=\"" << gettypenamefromtype(type) << "\"";
    if( dim != 1 )
    {
        os << " ArraySize=\"" << dim << "\"";
    }
    os << ">";
    printvalue( os, is );
    os << "</Attribute>\n";
}

void printcsv( std::ostream & os, std::istream & is ) const
{
    os << std::setw(32) << std::left << name << ",";
    os << std::setw(7) << std::right << gettypenamefromtype(type) << ",";
    os << std::setw(4) << dim << ",";
    os << " ";
    printvalue( os, is );
    os << ",\n";
}

};

static bool ProcessNested( gdcm::DataSet & ds )
{
    /*
    TODO:
    Looks like the real length of the blob is stored here:
    (2005,1132) SQ                                     # u/1,1 ?
    (fffe,e000) na (Item with undefined length)
    (2005,0011) LO [Philips MR Imaging DD 002 ]         # 26,1 Private Creator
    (2005,1143) SL 3103                                # 4,1 ?

    Wotsit ?
    (2005,1132) SQ                                     # u/1,1 ?
    (fffe,e000) na (Item with undefined length)
    (2005,0011) LO [Philips MR Imaging DD 002 ]         # 26,1 Private Creator
    (2005,1147) CS [Y ]                                # 2,1 ?
    */
    bool ret = false;

    // (2005,1137) PN (LO) [PDF_CONTROL_GEN_PARS]       # 20,1 Protocol Data Name
    const gdcm::PrivateTag pt0(0x2005,0x37,"Philips MR Imaging DD 002");
    if( !ds.FindDataElement( pt0 ) ) return false;
    const gdcm::DataElement &de0 = ds.GetDataElement( pt0 );
    if( de0.IsEmpty() ) return false;
    const gdcm::ByteValue * bv0 = de0.GetByteValue();
    std::string s0( bv0->GetPointer() , bv0->GetLength() );

    // (2005,1139) LO [IEEE_PDF]                       # 8,1 Protocol Data Type
    const gdcm::PrivateTag pt1(0x2005,0x39,"Philips MR Imaging DD 002");
    if( !ds.FindDataElement( pt1 ) ) return false;
    const gdcm::DataElement &de1 = ds.GetDataElement( pt1 );

    // (2005,1143) SL 53                                # 4,1 Protocol Data Block Length (non-padded)
    const gdcm::PrivateTag pt2(0x2005,0x43,"Philips MR Imaging DD 002");
    if( !ds.FindDataElement( pt2 ) ) return false;
    const gdcm::DataElement &de2 = ds.GetDataElement( pt2 );

    // (2005,1147) CS [Y ]                              # 2,1 Protocol Data Boolean
    const gdcm::PrivateTag pt3(0x2005,0x47,"Philips MR Imaging DD 002");
    if( !ds.FindDataElement( pt3 ) ) return false;
    const gdcm::DataElement &de3 = ds.GetDataElement( pt3 );
    (void)de3;

    // (2005,1144) OW 00\00\00\00\05\00\00\00\35\2e\31\2e\37\00 # 54,1 Protocol Data Block
    const gdcm::PrivateTag pt(0x2005,0x44,"Philips MR Imaging DD 002");
    if( !ds.FindDataElement( pt ) ) return false;
    const gdcm::DataElement &de = ds.GetDataElement( pt );
    if( de.IsEmpty() ) return false;

```

```

const gdcmm::ByteValue * bv = de.GetByteValue();

if( s0 == "ExamCardBlob" )
{
    gdcmm_assert( del.IsEmpty() );

    std::string fn = gdcmm::LOComp::Trim( s0.c_str() ); // remove trailing space
    fn += ".xml";
    std::ofstream out( fn.c_str() );

    // remove trailing \0
    size_t len = strlen( bv->GetPointer() );
    out.write( bv->GetPointer() , len );
    out.close();

    // Extract binary64 thingy (this is a ugly hack, better use an XML parser)
    std::string dup( bv->GetPointer(), len );
    std::string::size_type pos1 = dup.find( "<ExamCardBlob>" );
    std::string::size_type pos2 = dup.find( "</ExamCardBlob>" );

    std::string b64( bv->GetPointer() + pos1 + 14, pos2 - (pos1 + 14) );

    // ugly hack to remove \r\n from input base64:
    std::string::iterator r_pos = std::remove(b64.begin(), b64.end(), '\r');
    b64.erase(r_pos, b64.end());
    std::string::iterator n_pos = std::remove(b64.begin(), b64.end(), '\n');
    b64.erase(n_pos, b64.end());
}
if 0
{
    std::ofstream out2( "debug" );
    out2.write( b64.c_str(), b64.size() );
    out2.close();
}
endif

const size_t dlen = gdcmm::Base64::GetDecodeLength(b64.c_str(), b64.size() );

std::string decoded;
decoded.resize( dlen );
gdcmm::Base64::Decode( &decoded[0], decoded.size(), b64.c_str(), b64.size() );

std::ofstream f64( "soap.xml" );
f64.write( decoded.c_str(), decoded.size() );
f64.close();

ret = true;
}
else
{
    if( del.IsEmpty() ) return false;
    const gdcmm::ByteValue * bv1 = del.GetByteValue();
    gdcmm::Element<gdcmm::VR::SL,gdcmm::VM::VML> dlen = {{0L}};
    dlen.SetFromDataElement( de2 );
    std::string s1( bv1->GetPointer() , bv1->GetLength() );

    if( s1 == "IEEE_PDF" )
    {
        std::istream is;
        gdcmm_assert( bv->GetLength() == (size_t)dlen.GetValue() || bv->GetLength() == (size_t)(dlen.GetValue() + 1) );
        std::string dup( bv->GetPointer(), dlen.GetValue() /*bv->GetLength()*/ );
        is.str( dup );

        header h;
        h.read( is );
        //gdcmm_assert( is.peek() && is.eof() );
    }
    if 1
    {
        static int c = 0;
        std::string fn0 = gdcmm::LOComp::Trim( s1.c_str() ); // remove trailing space
        std::stringstream ss;
        ss << fn0 << "_" << c++;
        if( h.v1 == 0x01 )
            ss << ".direct";
        else
            ss << ".indirect";
        std::cout << "fn0=" << ss.str() << " Len= " << bv->GetLength() << std::endl;
        std::ofstream out( ss.str().c_str() );
        out.write( bv->GetPointer(), bv->GetLength() );
        out.close();
    }
}
endif
if 1
    std::cout << dup.c_str() << std::endl;

```

```

        h.print( std::cout );
#endif

    std::vector< param > params;
    if( h.v1 == 0x01 ) {
        for( uint32_t i = 0; i < 1 /* h.getnparams() */; ++i ) {
            param p;
            if( s0 == "HARDWARE_CONFIG " )
            {
                p.read_direct_int( is );
            }
            else if( s0 == "COILSTATE " )
            {
                p.read_direct_string( is );
            }
            else
            {
                gdcmm_assert(0);
            }
            params.push_back( p );
        }
    } else {
        gdcmm_assert( is.tellg() == std::streampos(0x20) );
        is.seekg( 0x20 );

        param p;
        for( uint32_t i = 0; i < h.getnparams(); ++i )
        {
            p.read( is );
            //p.print( std::cout );
            params.push_back( p );
        }
    }

    std::string fn = gdcmm::LOComp::Trim( s0.c_str() ); // remove trailing space
    bool b1 = isvalidpdfstring( fn.c_str() );
    gdcmm_assert( b1 ); (void)b1;
    fn += ".csv";
    //fn += ".xml";
    std::ofstream csv( fn.c_str() );

    // let's do some bookkeeping:
    uint32_t nfloats = 0;
    uint32_t nints = 0;
    uint32_t nstrings = 0;
    for( std::vector<param>::const_iterator it = params.begin();
        it != params.end(); ++it )
    {
        param_type type = it->gettype();
        switch( type )
        {
            {
            case param_float:
                nfloats += it->getdim();
                break;
            case param_integer:
                nints += it->getdim();
                break;
            case param_string:
                nstrings += it->getdim();
                break;
            default:
                ;
            }
        }
    }

    #if 0
    std::cout << "Stats:" << std::endl;
    std::cout << "nfloats:" << nfloats << std::endl;
    std::cout << "nints:" << nints << std::endl;
    std::cout << "nstrings:" << nstrings << std::endl;
    #endif

    gdcmm_assert( h.getnints() >= nints );
    gdcmm_assert( h.getnfloats() >= nfloats );
    gdcmm_assert( h.getnstrings() >= nstrings );

    for( uint32_t i = 0; i < h.getnparams(); ++i )
    {
        params[i].printcsv( csv, is );
        //params[i].printxml( csv, is );
    }
    csv.close();
    ret = true;

```

```

    }
    else if( s1 == "ASCII " )
    {
#ifdef 0
        std::cerr << "ASCII is not handled" << std::endl;
        std::string fn = gdcm::LOComp::Trim( s0.c_str() ); // remove trailing space
        fn += ".asc";
        std::ofstream out( fn.c_str() );
        out.write( bv->GetPointer() , bv->GetLength() );
        out.close();
#endif
        std::string fn = gdcm::LOComp::Trim( s0.c_str() ); // remove trailing space
        fn += ".sin";
        std::ofstream sin( fn.c_str() );

        const char *beg = bv->GetPointer();
        const char *end = beg + bv->GetLength();
        gdcm_assert( *beg == 0 );
        const char *p = beg + 1; // skip first \0
        size_t prev = 0;
        for( ; p != end; ++p )
        {
            if( *p == 0 )
            {
                const char *s = beg + prev + 1;
                if( *s )
                {
                    sin << s << std::endl;
                }
                else
                {
                    sin << std::endl;
                }
                prev = p - beg;
            }
        }
        sin.close();

        ret = true;
    }
    else if( s1 == "BINARY" )
    {
        std::cerr << "BINARY is not handled" << std::endl;
        std::string fn = gdcm::LOComp::Trim( s0.c_str() ); // remove trailing space
        fn += ".bin";
        std::ofstream out( fn.c_str() );
        //out.write( bv->GetPointer() + 512, bv->GetLength() - 512);
        out.write( bv->GetPointer() , bv->GetLength() );
        out.close();

#ifdef 0
        int array[ 128 ];
        memcpy( array, bv->GetPointer(), 512 );
        for( int i = 0; i < 14; ++i )
        {
            std::cout << array[i] << std::endl;
        }
#endif

        ret = true;
    }
    // else -> ret == false
    gdcm_assert( ret );

    return ret;
}

int main(int argc, char *argv[])
{
    if( argc < 2 ) return 1;
    const char *filename = argv[1];
    gdcm::Reader reader;
    reader.SetFileName( filename );
    if( !reader.Read() )
    {
        std::cerr << "Failed to read: " << filename << std::endl;
        return 1;
    }
    const gdcm::DataSet& ds = reader.GetFile().GetDataSet();
}

```



```

(2005,1132) SQ                                     # u/1,1 ?
(fffe,e000) na (Item with undefined length)
(2005,0011) LO [Philips MR Imaging DD 002 ]        # 26,1 Private Creator
(2005,1137) PN (LO) [PDF_CONTROL_GEN_PARS]         # 20,1 ?
(2005,1138) PN (LO) (no value)                     # 0,1 ?
(2005,1139) PN (LO) [IEEE_PDF]                     # 8,1 ?
(2005,1140) PN (LO) (no value)                     # 0,1 ?
(2005,1141) PN (LO) (no value)                     # 0,1 ?
(2005,1143) SL 3103                                # 4,1 ?
(2005,1144) OW
66\05\00\00\3b\01\00\00\4a\0a\00\00\0e\00\00\00\7a\0a\00\00\95\01\00\00\08\00\00\00\1b\00\00\00\43\47\45\4e\5f\75\73\65\72\5
# 3104,1 ?
(2005,1147) CS [Y ]                                # 2,1 ?
(fffe,e00d)
*/
const gdcm::PrivateTag pt(0x2005,0x32,"Philips MR Imaging DD 002");
if( !ds.FindDataElement( pt ) ) return 1;
const gdcm::DataElement &de = ds.GetDataElement( pt );
if( de.IsEmpty() ) return 1;

gdcm::SequenceOfItems *sqi = de.GetValueAsSQ();
if ( !sqi ) return 1;
gdcm::SequenceOfItems::SizeType s = sqi->GetNumberOfItems();
for( gdcm::SequenceOfItems::SizeType i = 1; i <= s; ++i )
{
    gdcm::Item &item = sqi->GetItem(i);

    gdcm::DataSet &nestedds = item.GetNestedDataSet();

    if( !ProcessNested( nestedds ) ) {
        std::cerr << "Error processing Item #" << i << std::endl;
    }
}

return 0;
}

```

12.52 DumpGEMSMovieGroup.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
#include "gdcmReader.h"
#include "gdcmImage.h"
#include "gdcmImageWriter.h"
#include "gdcmDataElement.h"
#include "gdcmPrivateTag.h"
#include "gdcmUIDGenerator.h"

#include <iostream>
#include <string>

#include <map>

bool PrintNameValueMapping( gdcm::SequenceOfItems *sqi_values,
gdcm::SequenceOfItems *sqi_names, std::string const & indent )
{
    using namespace gdcm;
    // prepare names mapping:
    typedef VRToType<VR::UL>::Type UL;
    std::map< UL, std::string > names;
    gdcm_assert( sqi_names );
    gdcm_assert( sqi_values );
    SequenceOfItems::SizeType s = sqi_names->GetNumberOfItems();
    PrivateTag tindex(0x7fe1,0x71,"GEMS_Ultrasound_MovieGroup_001");
    PrivateTag tname (0x7fe1,0x72,"GEMS_Ultrasound_MovieGroup_001");

```

```

// First sequence contains all possible names (this is a dict)
for( SequenceOfItems::SizeType i = 1; i <= s; ++i )
{
    const Item & item = sqi_names->GetItem( i );
    const DataSet & ds = item.GetNestedDataSet();
    if( !ds.FindDataElement( tindex )
        || !ds.FindDataElement( tname ) )
    {
        gdcmm_assert( 0 );
        return false;
    }
    const DataElement & index = ds.GetDataElement( tindex );
    const DataElement & name = ds.GetDataElement( tname );
    if( index.IsEmpty() || name.IsEmpty() )
    {
        gdcmm_assert( 0 );
        return false;
    }
    gdcmm::Element<VR::UL, VM::VM1> el1;
    el1.SetFromDataElement( index );

    gdcmm::Element<VR::LO, VM::VM1> el2;
    el2.SetFromDataElement( name );
    //      std::cout << el1.GetValue() << " " << el2.GetValue() << std::endl;
    names.insert( std::make_pair( el1.GetValue(), el2.GetValue() ) );
}

SequenceOfItems::SizeType s2 = sqi_values->GetNumberOfItems();
gdcmm_assert( s2 <= s );
PrivateTag tindex2(0x7fel,0x48,"GEMS_Ultrasound_MovieGroup_001");
for( SequenceOfItems::SizeType i = 1; i <= s2; ++i )
{
    const Item & item = sqi_values->GetItem( i );
    const DataSet & ds = item.GetNestedDataSet();
    if( !ds.FindDataElement( tindex2 ) )
    {
        gdcmm_assert( 0 );
        return false;
    }
    const DataElement & index2 = ds.GetDataElement( tindex2 );
    if( index2.IsEmpty() )
    {
        gdcmm_assert( 0 );
        return false;
    }
    gdcmm::Element<VR::FD, VM::VM1_2> el1;
    el1.SetFromDataElement( index2 );

    UL copy = (UL)el1.GetValue();
    #if 1
        std::cout << indent;
        std::cout << "( " << names[ copy ];
    #endif
    // (7fel,1052) FD 1560 # 8,1 ?
    // (7fel,1057) LT [MscSkelSup] # 10,1 ?
    //PrivateTag tvalue(0x7fel,0x52,"GEMS_Ultrasound_MovieGroup_001");
    PrivateTag tvalueint(0x7fel,0x49,"GEMS_Ultrasound_MovieGroup_001"); // UL
    PrivateTag tvaluefloat1(0x7fel,0x51,"GEMS_Ultrasound_MovieGroup_001"); // FL
    PrivateTag tvaluefloat(0x7fel,0x52,"GEMS_Ultrasound_MovieGroup_001"); // FD
    PrivateTag tvalueul(0x7fel,0x53,"GEMS_Ultrasound_MovieGroup_001"); // UL
    PrivateTag tvaluesl(0x7fel,0x54,"GEMS_Ultrasound_MovieGroup_001"); // SL
    PrivateTag tvalueob(0x7fel,0x55,"GEMS_Ultrasound_MovieGroup_001"); // OB
    PrivateTag tvaluetext(0x7fel,0x57,"GEMS_Ultrasound_MovieGroup_001"); // LT
    PrivateTag tvaluefd(0x7fel,0x77,"GEMS_Ultrasound_MovieGroup_001"); // FD / 1-N
    PrivateTag tvaluesl3(0x7fel,0x79,"GEMS_Ultrasound_MovieGroup_001"); // SL / 1-N
    PrivateTag tvaluesl2(0x7fel,0x86,"GEMS_Ultrasound_MovieGroup_001"); // SL ??
    PrivateTag tvaluefdl(0x7fel,0x87,"GEMS_Ultrasound_MovieGroup_001"); // FD / 1-N
    PrivateTag tvaluefloat2(0x7fel,0x88,"GEMS_Ultrasound_MovieGroup_001"); // FD ??
    #if 1
        std::cout << " ) = ";
    #endif
    if( ds.FindDataElement( tvalueint ) )
    {
        const DataElement & value = ds.GetDataElement( tvalueint );
        gdcmm::Element<VR::UL,VM::VM1> el2;
        el2.SetFromDataElement( value );
        std::cout << el2.GetValue() << std::endl;
    }
    else if( ds.FindDataElement( tvaluefloat1 ) )
    {
        const DataElement & value = ds.GetDataElement( tvaluefloat1 );

```

```

        gdcmm::Element<VR::FL,VM::VM1> el2;
        el2.SetFromDataElement( value );
        std::cout << el2.GetValue() << std::endl;
    }
    else if( ds.FindDataElement( tvaluefloat ) )
    {
        const DataElement & value = ds.GetDataElement( tvaluefloat );
        gdcmm::Element<VR::FD,VM::VM1> el2;
        el2.SetFromDataElement( value );
        std::cout << el2.GetValue() << std::endl;
    }
    else if( ds.FindDataElement( tvaluesl ) )
    {
        const DataElement & value = ds.GetDataElement( tvaluesl );
        gdcmm::Element<VR::SL,VM::VM1> el2;
        el2.SetFromDataElement( value );
        std::cout << el2.GetValue() << std::endl;
    }
    else if( ds.FindDataElement( tvalueul ) )
    {
        const DataElement & value = ds.GetDataElement( tvalueul );
        gdcmm::Element<VR::UL,VM::VM1_n> el2;
        el2.SetFromDataElement( value );
        gdcmm_assert( el2.GetLength() == 1 );
        std::cout << el2.GetValue() << std::endl;
    }
    else if( ds.FindDataElement( tvalueob ) )
    {
        const DataElement & value = ds.GetDataElement( tvalueob );
        gdcmm::Element<VR::SL,VM::VM1> el2;
        // el2.SetFromDataElement( value );
        // std::cout << el2.GetValue() << std::endl;
        std::cout << value << std::endl;
    }
    else if( ds.FindDataElement( tvaluetext ) )
    {
        const DataElement & value = ds.GetDataElement( tvaluetext );
        gdcmm::Element<VR::LT,VM::VM1> el2;
        el2.SetFromDataElement( value );
        std::cout << el2.GetValue() << std::endl;
    }
    else if( ds.FindDataElement( tvaluesl2 ) )
    {
        const DataElement & value = ds.GetDataElement( tvaluesl2 );
        gdcmm::Element<VR::SL,VM::VM1_n> el2;
        el2.SetFromDataElement( value );
        el2.Print( std::cout );
        gdcmm_assert( el2.GetLength() == 4 );
        std::cout << std::endl;
    }
    else if( ds.FindDataElement( tvaluesl3 ) )
    {
        const DataElement & value = ds.GetDataElement( tvaluesl3 );
        gdcmm::Element<VR::SL,VM::VM1_n> el2;
        el2.SetFromDataElement( value );
        el2.Print( std::cout );
        // gdcmm_assert( el2.GetLength() == 4 );
        std::cout << std::endl;
    }
    else if( ds.FindDataElement( tvaluefd ) )
    {
        const DataElement & value = ds.GetDataElement( tvaluefd );
        gdcmm::Element<VR::FD,VM::VM1_n> el2;
        el2.SetFromDataElement( value );
        el2.Print( std::cout );
        // gdcmm_assert( el2.GetLength() == 4 || el2.GetLength() == 3 || el2.GetLength() == 8 );
        std::cout << std::endl;
    }
    else if( ds.FindDataElement( tvaluefloat2 ) )
    {
        const DataElement & value = ds.GetDataElement( tvaluefloat2 );
        gdcmm::Element<VR::FD,VM::VM1_n> el2;
        el2.SetFromDataElement( value );
        el2.Print( std::cout );
        gdcmm_assert( el2.GetLength() == 2 );
        std::cout << std::endl;
    }
    else if( ds.FindDataElement( tvaluefd1 ) )
    {
        const DataElement & value = ds.GetDataElement( tvaluefd1 );
        gdcmm::Element<VR::FD,VM::VM1_n> el2;

```

```

        el2.SetFromDataElement( value );
        el2.Print( std::cout );
        gdcmm_assert( el2.GetLength() == 4 );
        std::cout << std::endl;
    }
    else
    {
        std::cout << "(no value)" << std::endl;
        std::cout << ds << std::endl;
        gdcmm_assert( ds.Size() == 2 );
    }
}
return true;
}

bool PrintNameValueMapping2( gdcmm::PrivateTag const & privtag, const gdcmm::DataSet & ds,
    gdcmm::SequenceOfItems *sqi_names, std::string const & indent )
{
    if( !ds.FindDataElement( privtag ) ) return false;
    const gdcmm::DataElement& seq_values = ds.GetDataElement( privtag );
    gdcmm::SmartPointer<gdcmm::SequenceOfItems> sqi = seq_values.GetValueAsSQ();

    return PrintNameValueMapping( sqi, sqi_names, indent);
}

bool PrintNameValueMapping3( gdcmm::PrivateTag const & privtag1, gdcmm::PrivateTag const & privtag2, const
    gdcmm::DataSet & ds,
    gdcmm::SequenceOfItems *sqi_names, std::string const & indent )
{
    if( !ds.FindDataElement( privtag1 ) )
    {
        gdcmm_assert( 0 );
        return false;
    }
    const gdcmm::DataElement& values10name = ds.GetDataElement( privtag1 );
    gdcmm::Element<gdcmm::VR::LO,gdcmm::VM::VM1> el;
    el.SetFromDataElement( values10name );
    std::cout << std::endl;
    std::cout << " <" << el.GetValue().c_str() << ">" << std::endl;

    return PrintNameValueMapping2( privtag2, ds, sqi_names, indent);
}

bool print73( gdcmm::DataSet const & ds10, gdcmm::SequenceOfItems *sqi_dict, std::string const & indent )
{
    const gdcmm::PrivateTag tseq_values73(0x7fel,0x73,"GEMS_Ultrasound_MovieGroup_001");
    if( !ds10.FindDataElement( tseq_values73 ) )
    {
        std::cout << indent << "No group 73" << std::endl;
        return false;
    }
    const gdcmm::DataElement& seq_values73 = ds10.GetDataElement( tseq_values73 );
    gdcmm::SmartPointer<gdcmm::SequenceOfItems> sqi_values73 = seq_values73.GetValueAsSQ();

    size_t ni3 = sqi_values73->GetNumberOfItems();
    for( size_t i3 = 1; i3 <= ni3; ++i3 )
    {
        gdcmm::Item &item_73 = sqi_values73->GetItem(i3);
        gdcmm::DataSet &ds73 = item_73.GetNestedDataSet();
        gdcmm_assert( ds73.Size() == 3 );

        const gdcmm::PrivateTag tseq_values74name(0x7fel,0x74,"GEMS_Ultrasound_MovieGroup_001");
        const gdcmm::PrivateTag tseq_values75(0x7fel,0x75,"GEMS_Ultrasound_MovieGroup_001");
        PrintNameValueMapping3( tseq_values74name, tseq_values75, ds73, sqi_dict, indent);
        std::cout << std::endl;
    }
    return true;
}

bool print36( gdcmm::DataSet const & ds10, gdcmm::SequenceOfItems *sqi_dict, std::string const & indent )
{
    (void)sqi_dict;
    const gdcmm::PrivateTag tseq_values36(0x7fel,0x36,"GEMS_Ultrasound_MovieGroup_001");
    if( !ds10.FindDataElement( tseq_values36 ) )
    {
        std::cout << indent << "No group 36" << std::endl;
        return false;
    }
    const gdcmm::DataElement& seq_values36 = ds10.GetDataElement( tseq_values36 );

```

```

gdcmm::SmartPointer<gdcmm::SequenceOfItems> sqi_values36 = seq_values36.GetValueAsSQ();

size_t ni3 = sqi_values36->GetNumberOfItems();
gdcmm_assert( ni3 >= 1 );
for( size_t i3 = 1; i3 <= ni3; ++i3 )
{
    gdcmm::Item &item_36 = sqi_values36->GetItem(i3);
    gdcmm::DataSet &ds36 = item_36.GetNestedDataSet();
    gdcmm_assert( ds36.Size() == 4 );

    // (7fe1,1037) UL 47 # 4,1 US MovieGroup Number of Frames
    // (7fe1,1043) OB 40\00\1c\c4\67\2f\0b\11\40 # 376,1 ?
    // (7fe1,1060) OB 4e\4e\49\4f\4e\47\46\43\2a # 4562714,1 US MovieGroup Image Data
    //
    const gdcmm::PrivateTag timagedata(0x7fe1,0x60,"GEMS_Ultrasound_MovieGroup_001");
    gdcmm_assert( ds36.FindDataElement( timagedata ) );
    gdcmm::DataElement const & imagedata = ds36.GetDataElement( timagedata );

    const gdcmm::ByteValue * bv = imagedata.GetByteValue();
    gdcmm_assert( bv );
    static int c = 0;
    std::stringstream ss;
    ss << "/tmp/debug";
    ss << c++;
    std::ofstream os( ss.str().c_str(), std::ios::binary );
    os.write( bv->GetPointer(), bv->GetLength() );
    os.close();

    //const gdcmm::PrivateTag tseq_values85(0x7fe1,0x85,"GEMS_Ultrasound_MovieGroup_001");
    //PrintNameValueMapping3( tseq_values84name, tseq_values85, ds83, sqi_dict, indent);
    //std::cout << std::endl;
}
return true;
}

bool print83( gdcmm::DataSet const & ds10, gdcmm::SequenceOfItems *sqi_dict, std::string const & indent )
{
    const gdcmm::PrivateTag tseq_values83(0x7fe1,0x83,"GEMS_Ultrasound_MovieGroup_001");
    if( !ds10.FindDataElement( tseq_values83 ) )
    {
        std::cout << indent << "No group 83" << std::endl;
        return false;
    }
    const gdcmm::DataElement& seq_values83 = ds10.GetDataElement( tseq_values83 );
    gdcmm::SmartPointer<gdcmm::SequenceOfItems> sqi_values83 = seq_values83.GetValueAsSQ();

    size_t ni3 = sqi_values83->GetNumberOfItems();
    for( size_t i3 = 1; i3 <= ni3; ++i3 )
    {
        gdcmm::Item &item_83 = sqi_values83->GetItem(i3);
        gdcmm::DataSet &ds83 = item_83.GetNestedDataSet();
        gdcmm_assert( ds83.Size() == 3 );

        const gdcmm::PrivateTag tseq_values84name(0x7fe1,0x84,"GEMS_Ultrasound_MovieGroup_001");
        const gdcmm::PrivateTag tseq_values85(0x7fe1,0x85,"GEMS_Ultrasound_MovieGroup_001");
        PrintNameValueMapping3( tseq_values84name, tseq_values85, ds83, sqi_dict, indent);
        std::cout << std::endl;
    }
    return true;
}

bool PrintNameValueMapping4( gdcmm::PrivateTag const & privtag0, const gdcmm::DataSet & subds, gdcmm::PrivateTag
    const & privtag1, gdcmm::PrivateTag const & privtag2,
    gdcmm::SequenceOfItems *sqi_dict, std::string const & indent )
{
    (void)indent;
    if( !subds.FindDataElement( privtag0 ) )
    {
        gdcmm_assert( 0 );
        return false;
    }
    const gdcmm::DataElement& seq_values10 = subds.GetDataElement( privtag0 );
    gdcmm::SmartPointer<gdcmm::SequenceOfItems> sqi_values10 = seq_values10.GetValueAsSQ();

    size_t nil = sqi_values10->GetNumberOfItems();
    // gdcmm_assert( nil == 1 );
    for( size_t i1 = 1; i1 <= nil; ++i1 )
    {
        gdcmm::Item &item_10 = sqi_values10->GetItem(i1);
        gdcmm::DataSet &ds10 = item_10.GetNestedDataSet();
        gdcmm_assert( ds10.Size() == 2 + 3 );
        // (7fe1,0010)

```

```

    // (7fe1,1012)
    // (7fe1,1018)
    // (7fe1,1020)
    // (7fe1,1083)

    PrintNameValueMapping3( privtag1, privtag2, ds10, sqi_dict, " " );
    std::cout << std::endl;

    const gdcm::PrivateTag tseq_values20(0x7fe1,0x20,"GEMS_Ultrasound_MovieGroup_001");
    if( !ds10.FindDataElement( tseq_values20 ) )
    {
        gdcm_assert( 0 );
        return false;
    }
    const gdcm::DataElement& seq_values20 = ds10.GetDataElement( tseq_values20 );
    gdcm::SmartPointer<gdcm::SequenceOfItems> sqi_values20 = seq_values20.GetValueAsSQ();

    size_t ni2 = sqi_values20->GetNumberOfItems();
    //gdcm_assert( ni == 1 );
    for( size_t i2 = 1; i2 <= ni2; ++i2 )
    {
        gdcm::Item &item_20 = sqi_values20->GetItem(i2);
        gdcm::DataSet &ds20 = item_20.GetNestedDataSet();
        size_t count = ds20.Size(); (void)count;
        gdcm_assert( ds20.Size() == 2 + 3 || ds20.Size() == 2 + 2 );
        // (7fe1,0010)
        // (7fe1,1024)
        // (7fe1,1026)
        // (7fe1,1036)
        // (7fe1,103a)
        // (7fe1,1083) (*)

        const gdcm::PrivateTag tseq_values20name(0x7fe1,0x24,"GEMS_Ultrasound_MovieGroup_001");
        const gdcm::PrivateTag tseq_values26(0x7fe1,0x26,"GEMS_Ultrasound_MovieGroup_001");
        PrintNameValueMapping3( tseq_values20name, tseq_values26, ds20, sqi_dict, " " );
        std::cout << std::endl;

        print36(ds20, sqi_dict, " ");
        print83(ds20, sqi_dict, " ");
    }

    print83(ds10, sqi_dict, " ");
}
return true;
}

int main(int argc, char *argv[])
{
    if( argc < 2 ) return 1;
    using namespace gdcm;
    const char *filename = argv[1];
    gdcm::Reader reader;
    reader.SetFileName( filename );
    if( !reader.Read() ) return 1;

    gdcm::File &file = reader.GetFile();
    gdcm::DataSet &ds = file.GetDataSet();
    const PrivateTag tseq(0x7fe1,0x1,"GEMS_Ultrasound_MovieGroup_001");

    if( !ds.FindDataElement( tseq ) ) return 1;
    const DataElement& seq = ds.GetDataElement( tseq );

    SmartPointer<SequenceOfItems> sqi = seq.GetValueAsSQ();
    gdcm_assert( sqi->GetNumberOfItems() == 1 );

    Item &item = sqi->GetItem(1);
    DataSet &subds = item.GetNestedDataSet();

    const PrivateTag tseq_dict(0x7fe1,0x70,"GEMS_Ultrasound_MovieGroup_001");
    if( !subds.FindDataElement( tseq_dict ) ) return 1;
    const DataElement& seq_dict = subds.GetDataElement( tseq_dict );
    SmartPointer<SequenceOfItems> sqi_dict = seq_dict.GetValueAsSQ();

    const PrivateTag tseq_values8(0x7fe1,0x8,"GEMS_Ultrasound_MovieGroup_001");
    if( !subds.FindDataElement( tseq_values8 ) ) return 1;
    const DataElement& seq_values8 = subds.GetDataElement( tseq_values8 );
    SmartPointer<SequenceOfItems> sqi_values8 = seq_values8.GetValueAsSQ();

    const PrivateTag tseq_values8name(0x7fe1,0x2,"GEMS_Ultrasound_MovieGroup_001");
    if( !subds.FindDataElement( tseq_values8name ) ) return 1;
    const DataElement& values8name = subds.GetDataElement( tseq_values8name );

```

```

{
    Element<VR::LO,VM::VM1> el;
    el.SetFromDataElement( values8name );
    std::cout << el.GetValue() << std::endl;
}

size_t count = subds.Size(); (void)count;
gdcm_assert( subds.Size() == 3 + 2 + 1 || subds.Size() == 3 + 2 + 2);

// (7fe1,0010) # 30,1 Private Creator
// (7fe1,1002) # 8,1 US MovieGroup Value 0008 Name
// (7fe1,1003) # 4,1 ?
// (7fe1,1008) # 8140,1 US MovieGroup Value 0008 Sequence
// (7fe1,1010) # 1372196,1 ?
// (7fe1,1070) # 33684,1 US MovieGroup Dict
// (7fe1,1073) (*)
PrintNameValueMapping( sqi_values8, sqi_dict, " ");

const PrivateTag tseq_values10(0x7fe1,0x10,"GEMS_Ultrasound_MovieGroup_001");
const PrivateTag tseq_values10name(0x7fe1,0x12,"GEMS_Ultrasound_MovieGroup_001");
const PrivateTag tseq_values18(0x7fe1,0x18,"GEMS_Ultrasound_MovieGroup_001");
PrintNameValueMapping4( tseq_values10, subds, tseq_values10name, tseq_values18, sqi_dict, " ");

print73( subds, sqi_dict, " " );

#if 0
gdcm::DataSet::ConstIterator it = subds.Begin();
for( ; it != subds.End(); ++it )
{
    const gdcm::DataElement &de = *it;
    std::cout << de.GetTag() << std::endl;
}
#endif

return 0;
}

```

12.53 DumpImageHeaderInfo.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
/*
 * Dump TOSHIBA MDW HEADER / Image Header Info
 */
#include "gdcmReader.h"
#include "gdcmPrivateTag.h"
#include "gdcmAttribute.h"
#include "gdcmImageWriter.h"

#include <iostream>
#include <fstream>
#include <vector>

#include <string.h>
#include <assert.h>
#include <stdint.h>

struct element
{
    std::istream & read( std::istream & is );
};

std::istream & element::read( std::istream & is )
{
    static const uint32_t ref = 0xe000fffe;
    std::ostream &os = std::cout;

```



```

// TUSNONIMAGESTAM (5176)
// TUSREMEASUREMEN (1352)
// TUSBSINGLELAYOU (16)
// TUSCLIPPARAMETE (104)

element el;
while( el.read( is ) )
{
}
//size_t pos = is.tellg();
//gdcmm_assert( pos == reflen );
(void)reflen;

return true;
}

int main(int argc, char *argv[])
{
    if( argc < 2 ) return 1;
    const char *filename = argv[1];
    gdcmm::Reader reader;
    reader.SetFileName( filename );
    if( !reader.Read() )
    {
        std::cerr << "Failed to read: " << filename << std::endl;
        return 1;
    }
    const gdcmm::DataSet& ds = reader.GetFile().GetDataSet();

    const gdcmm::PrivateTag timageheaderinfo(0x0029,0x10,"TOSHIBA MDW HEADER");
    if( !ds.FindDataElement( timageheaderinfo ) ) return 1;
    const gdcmm::DataElement& imageheaderinfo = ds.GetDataElement( timageheaderinfo );
    if ( imageheaderinfo.IsEmpty() ) return 1;
    const gdcmm::ByteValue *bv = imageheaderinfo.GetByteValue();

    std::stringstream is;
    std::string dup( bv->GetPointer(), bv->GetLength() );
    is.str( dup );
    bool b = DumpImageHeaderInfo( is, bv->GetLength() );
    if( !b ) return 1;

#ifdef 0
    const float d1 = 0.00416666668839752674; // 89 88 88 3B // 0x44c
    //const float d1 = 0.053231674455417881;
    const float d2 = 0.10828025639057159; // 0A C2 DD 3D // 0x1ac
    //const float d1 = 0.17869562069272813;
    //const unsigned int d2 = 4294967280;
    const float d3 = 0.10828025639057159; // 0A C2 DD 3D // 0x15c
    const int32_t d4 = 134;
    const uint32_t d5 = 1153476;
    std::ofstream t("/tmp/debug", std::ios::binary );
    //t.write( (char*)&d0, sizeof( d0 ) );
    t.write( (char*)&d1, sizeof( d1 ) );
    t.write( (char*)&d2, sizeof( d2 ) );
    t.write( (char*)&d3, sizeof( d3 ) );
    t.write( (char*)&d4, sizeof( d4 ) );
    t.write( (char*)&d5, sizeof( d5 ) );
    t.close();
#endif

    return 0;
}

```

12.54 DumpPhilipsECHO.cxx

```

/*=====

Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcmm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

```

```

=====*/
#include "gdcmReader.h"
#include "gdcmDeflateStream.h"
#include "gdcm_zlib.h"

/*
 * This example extract the ZLIB compressed US image from a Philips private tag
 *
 * Everything done in this code is for the sole purpose of writing interoperable
 * software under Sect. 1201 (f) Reverse Engineering exception of the DMCA.
 * If you believe anything in this code violates any law or any of your rights,
 * please contact us (gdcm-developers@lists.sourceforge.net) so that we can
 * find a solution.
 *
 * Everything you do with this code is at your own risk, since decompression
 * algorithm was not written from specification documents.
 *
 * Usage:
 *
 * $ DumpPhilipsECHO private_us.dcm raw_us_img.raw
 * $ gdcming --sop-class-uid 1.2.840.10008.5.1.4.1.1.3.1 --size 608,427,88 raw_us_img.raw raw_us_img.dcm
 */

// header:
struct hframe
{
    uint32_t val0; // 800 increment ?
    uint16_t val1[2];
    uint16_t val2[2];
    uint32_t imgsize;

    bool operator==(const hframe &h) const
    {
        return val0 == h.val0 &&
            val1[0] == h.val1[0] &&
            val1[1] == h.val1[1] &&
            val2[0] == h.val2[0] &&
            val2[1] == h.val2[1] &&
            imgsize == h.imgsize;
    }
};

static bool ProcessDeflate( const char *outfilename, const int nslices, const
    int buf_size, const char *buf, const std::streampos len,
    const char *crdbuf, const size_t crclen )
{
    std::vector< hframe > crchheaders;
    crchheaders.reserve( nslices );
    {
        std::istream is;
        is.str( std::string( crdbuf, crclen ) );
        hframe header;
        for( int r = 0; r < nslices; ++r )
        {
            is.read( (char*)&header, sizeof( header ));
            #if 0
                std::cout << header.val0
                    << " " << header.val1[0]
                    << " " << header.val1[1]
                    << " " << header.val2[0]
                    << " " << header.val2[1]
                    << " " << header.imgsize << std::endl;
            #endif
            crchheaders.push_back( header );
        }

        std::istream is;
        is.str( std::string( buf, (size_t)len ) );

        std::streamoff totalsize;
        is.read( (char*)&totalsize, sizeof( totalsize ));
        gdcm_assert( totalsize == len );

        uint32_t nframes;
        is.read( (char*)&nframes, sizeof( nframes ));
        gdcm_assert( nframes == (uint32_t)nslices );

        std::vector< std::streamoff > offsets;

```

```

offsets.reserve( nframes );
for( uint32_t frame = 0; frame < nframes ; ++frame )
{
    uint32_t offset;
    is.read( (char*)&offset, sizeof( offset ));
    offsets.push_back( offset );
}

std::vector<char> outbuf;

const int size[2] = { 608, 427 }; // FIXME: where does it comes from ?
std::stringstream ss;
ss << outfilename;
ss << '_';
//ss << crchheaders[0].imgsize; // FIXME: Assume all header are identical !
ss << size[0];
ss << '_';
ss << size[1];
ss << '_';
ss << nframes;
ss << ".raw";
std::ofstream os( ss.str().c_str(), std::ios::binary );

gdcmm_assert( buf_size >= size[0] * size[1] );
outbuf.resize( buf_size );

hframe header;
//uint32_t prev = 0;
for( unsigned int r = 0; r < nframes; ++r )
{
    is.read( (char*)&header, sizeof( header ));

    gdcmm_assert( header == crchheaders[r] );
    gdcmm_assert( header.val1[0] == 2000 );
    gdcmm_assert( header.val1[1] == 3 );
    gdcmm_assert( header.val2[0] == 1 );
    gdcmm_assert( header.val2[1] == 1280 );

    uLongf destLen = buf_size; // >= 608,427
    Bytef *dest = (Bytef*)outbuf.data();
    gdcmm_assert( is.tellg() == offsets[r] + 16 );
    const Bytef *source = (const Bytef*)buf + offsets[r] + 16;
    uLong sourceLen;
    if( r + 1 == nframes )
        sourceLen = (uLong)totalsize - (uLong)offsets[r] - 16;
    else
        sourceLen = (uLong)offsets[r+1] - (uLong)offsets[r] - 16;
    // FIXME: in-memory decompression:
    int ret = uncompress (dest, &destLen, source, sourceLen);
    gdcmm_assert( ret == Z_OK ); (void)ret;
    gdcmm_assert( destLen >= (uLongf)size[0] * size[1] ); // 16bytes padding ?
    gdcmm_assert( header.imgsize == (uint32_t)size[0] * size[1] );
    //os.write( &outbuf[0], outbuf.size() );
    os.write( outbuf.data(), size[0] * size[1] );

    // skip data:
    is.seekg( sourceLen, std::ios::cur );
}
os.close();
gdcmm_assert( is.tellg() == totalsize );

return true;
}

static bool ProcessNone( const char *outfilename, const int nslices, const
int buf_size, const char *buf, const std::streampos len,
const char *crdbuf, const size_t crclen )
{
    std::vector< hframe > crchheaders;
    crchheaders.reserve( nslices );
    {
        std::stringstream is;
        is.str( std::string( crdbuf, crclen ) );
        hframe header;
        for( int r = 0; r < nslices; ++r )
        {
            is.read( (char*)&header, sizeof( header ));
        }
    }
    #if 0
        std::cout << header.val0
            << " " << header.val1[0]
            << " " << header.val1[1]

```

```

        « " " « header.val2[0]
        « " " « header.val2[1]
        « " " « header.imgsize « std::endl;
#endif
        crchheaders.push_back( header );
    }
}

std::istream is;
is.str( std::string( buf, (size_t)len ) );

std::streampos totalsize;
is.read( (char*)&totalsize, sizeof( totalsize ) );
gdcm_assert( totalsize == len );

uint32_t nframes;
is.read( (char*)&nframes, sizeof( nframes ) );
gdcm_assert( nframes == (uint32_t)nslices );

std::vector< uint32_t > offsets;
offsets.reserve( nframes );
for( uint32_t frame = 0; frame < nframes ; ++frame )
{
    uint32_t offset;
    is.read( (char*)&offset, sizeof( offset ) );
    offsets.push_back( offset );
    //std::cout « offset « std::endl;
}

std::vector<char> outbuf;
// No idea how to present the data, I'll just append everything, and present it as 2D
std::stringstream ss;
ss « outfilename;
ss « '_';
ss « crchheaders[0].imgsize; // FIXME: Assume all header are identical !
ss « '_';
ss « nframes;
ss « ".raw";
std::ofstream os( ss.str().c_str(), std::ios::binary );
outbuf.resize( buf_size ); // overallocated + 16
char *buffer = outbuf.data();

hframe header;
for( unsigned int r = 0; r < nframes; ++r )
{
    is.read( (char*)&header, sizeof( header ) );
}
if 0
    std::cout « header.val0
        « " " « header.val1[0]
        « " " « header.val1[1]
        « " " « header.val2[0]
        « " " « header.val2[1]
        « " " « header.imgsize « std::endl;
#endif
    gdcm_assert( header == crchheaders[r] );

    is.read( buffer, buf_size - 16 );
    os.write( buffer, header.imgsize );
}
gdcm_assert( is.tellg() == totalsize );
os.close();

return true;
}

#ifdef NDEBUG
static const char * const UDM_USD_DATATYPE_STRINGS[] = {
    "UDM_USD_DATATYPE_DIN_2D_ECHO",
    "UDM_USD_DATATYPE_DIN_2D_ECHO_CONTRAST",
    "UDM_USD_DATATYPE_DIN_DOPPLER_CW",
    "UDM_USD_DATATYPE_DIN_DOPPLER_PW",
    "UDM_USD_DATATYPE_DIN_DOPPLER_PW_TDI",
    "UDM_USD_DATATYPE_DIN_2D_COLOR_FLOW",
    "UDM_USD_DATATYPE_DIN_2D_COLOR_PMI",
    "UDM_USD_DATATYPE_DIN_2D_COLOR_CPA",
    "UDM_USD_DATATYPE_DIN_2D_COLOR_TDI",
    "UDM_USD_DATATYPE_DIN_MMODE_ECHO",
    "UDM_USD_DATATYPE_DIN_MMODE_COLOR",
    "UDM_USD_DATATYPE_DIN_MMODE_COLOR_TDI",
    "UDM_USD_DATATYPE_DIN_PARAM_BLOCK",
    "UDM_USD_DATATYPE_DIN_2D_COLOR_VELOCITY",

```

```

"UDM_USD_DATATYPE_DIN_2D_COLOR_POWER",
"UDM_USD_DATATYPE_DIN_2D_COLOR_VARIANCE",
"UDM_USD_DATATYPE_DIN_DOPPLER_AUDIO",
"UDM_USD_DATATYPE_DIN_DOPPLER_HIGHQ",
"UDM_USD_DATATYPE_DIN_PHYSIO",
"UDM_USD_DATATYPE_DIN_2D_COLOR_STRAIN",
"UDM_USD_DATATYPE_DIN_COMPOSITE_RGB",
"UDM_USD_DATATYPE_DIN_XFOV_REALTIME_GRAPHICS",
"UDM_USD_DATATYPE_DIN_XFOV_MOSAIC",
"UDM_USD_DATATYPE_DIN_COMPOSITE_R",
"UDM_USD_DATATYPE_DIN_COMPOSITE_G",
"UDM_USD_DATATYPE_DIN_COMPOSITE_B",
"UDM_USD_DATATYPE_DIN_MMODE_COLOR_VELOCITY",
"UDM_USD_DATATYPE_DIN_MMODE_COLOR_POWER",
"UDM_USD_DATATYPE_DIN_MMODE_COLOR_VARIANCE",
"UDM_USD_DATATYPE_DIN_2D_ELASTO",
};

static inline bool is_valid( const char * datatype_str )
{
    static const int n = sizeof( UDM_USD_DATATYPE_STRINGS ) / sizeof( *UDM_USD_DATATYPE_STRINGS );
    bool found = false;
    if( datatype_str )
    {
        for( int i = 0; !found && i < n; ++i )
        {
            found = strcmp( datatype_str, UDM_USD_DATATYPE_STRINGS[i] ) == 0;
        }
    }
    return found;
}
#endif

int main(int argc, char *argv[])
{
    if( argc < 2 ) return 1;
    using namespace gdcm;
    const char *filename = argv[1];
    gdcm::Reader reader;
    reader.SetFileName( filename );
    if( !reader.Read() ) return 1;

    gdcm::File &file = reader.GetFile();
    gdcm::DataSet &dsl = file.GetDataSet();

    const PrivateTag tseq1(0x200d,0x3cf8,"Philips US Imaging DD 045");
    if( !dsl.FindDataElement( tseq1 ) ) return 1;
    const DataElement& seq1 = dsl.GetDataElement( tseq1 );

    SmartPointer<SequenceOfItems> sq1 = seq1.GetValueAsSQ();
    gdcm_assert( sq1->GetNumberOfItems() >= 1 );

    const size_t nitems = sq1->GetNumberOfItems();
    for( size_t item = 1; item < nitems; ++item )
    {
        Item &item1 = sq1->GetItem(item);
        DataSet &ds2 = item1.GetNestedDataSet();

        // (200d,300d) IO 28 UDM_USD_DATATYPE_DIN_2D_ECHO
        const PrivateTag tdatatype(0x200d,0x300d,"Philips US Imaging DD 033");
        if( !ds2.FindDataElement( tdatatype ) ) return 1;
        const DataElement& datatype = ds2.GetDataElement( tdatatype );
        const ByteValue *bvdatatype = datatype.GetByteValue();
        if( !bvdatatype ) return 1;

        const PrivateTag tseq2(0x200d,0x3cf1,"Philips US Imaging DD 045");
        if( !ds2.FindDataElement( tseq2 ) ) return 1;
        const DataElement& seq2 = ds2.GetDataElement( tseq2 );

        SmartPointer<SequenceOfItems> sq2 = seq2.GetValueAsSQ();
        gdcm_assert( sq2->GetNumberOfItems() >= 1 );

        // FIXME: what if not in first Item ?
        gdcm_assert( sq2->GetNumberOfItems() == 1 );
        Item &item2 = sq2->GetItem(1);
        DataSet &ds3 = item2.GetNestedDataSet();

        const PrivateTag tzlib(0x200d,0x3cfa,"Philips US Imaging DD 045");
        if( !ds3.FindDataElement( tzlib ) ) return 1;

```

```

const DataElement& zlib = ds3.GetDataElement( tzlib );

const ByteValue *bv = zlib.GetByteValue();
if( !bv ) return 1;
if( bv->GetLength() != 4 ) return 1;

// (200d,3010) IS 2 88
const PrivateTag tnslices(0x200d,0x3010,"Philips US Imaging DD 033");
if( !ds3.FindDataElement( tnslices ) ) return 1;
const DataElement& nslices = ds3.GetDataElement( tnslices );
Element<VR::IS,VM::VM1> elnslices;
elnslices.SetFromDataElement( nslices );
const int nslicesref = elnslices.GetValue();
gdcm_assert( nslicesref >= 0 );
// (200d,3011) IS 6 259648
const PrivateTag tzalloc(0x200d,0x3011,"Philips US Imaging DD 033");
if( !ds3.FindDataElement( tzalloc ) ) return 1;
const DataElement& zalloc = ds3.GetDataElement( tzalloc );
Element<VR::IS,VM::VM1> elzalloc;
elzalloc.SetFromDataElement( zalloc );
const int zallocref = elzalloc.GetValue();
gdcm_assert( zallocref >= 0 );
// (200d,3021) IS 2 0
const PrivateTag tzero(0x200d,0x3021,"Philips US Imaging DD 033");
if( !ds3.FindDataElement( tzero ) ) return 1;
const DataElement& zero = ds3.GetDataElement( tzero );
Element<VR::IS,VM::VM1> elzero;
elzero.SetFromDataElement( zero );
const int zerocref = elzero.GetValue();
gdcm_assert( zerocref == 0 ); (void)zerocref;

// (200d,3cf3) OB
const PrivateTag tdeflate(0x200d,0x3cf3,"Philips US Imaging DD 045");
if( !ds3.FindDataElement( tdeflate ) ) return 1;
const DataElement& deflate = ds3.GetDataElement( tdeflate );
const ByteValue *bv2 = deflate.GetByteValue();

// (200d,3cfb) OB
const PrivateTag tcrc(0x200d,0x3cfb,"Philips US Imaging DD 045");
if( !ds3.FindDataElement( tcrc ) ) return 1;
const DataElement& crc = ds3.GetDataElement( tcrc );
const ByteValue *bv3 = crc.GetByteValue();

std::string outfile = std::string( bvdatatype->GetPointer(), bvdatatype->GetLength() );
outfile = LOComp::Trim( outfile.c_str() );
const char *outfilename = outfile.c_str();
#ifdef NDEBUG
    gdcm_assert( is_valid(outfilename) );
#endif
if( bv2 )
{
    gdcm_assert( bv3 );
    gdcm_assert( zallocref > 0 );
    gdcm_assert( nslicesref > 0 );
    std::cout << ds2 << std::endl;

    if( strncmp(bv->GetPointer(), "ZLib", 4) == 0 )
    {
        if( !ProcessDeflate( outfile, nslicesref, zallocref, bv2->GetPointer(),
            std::streampos(bv2->GetLength()), bv3->GetPointer(), bv3->GetLength() ) )
        {
            return 1;
        }
    }
    else if( strncmp(bv->GetPointer(), "None", 4) == 0 )
    {
        if( !ProcessNone( outfile, nslicesref, zallocref, bv2->GetPointer(),
            std::streampos(bv2->GetLength()), bv3->GetPointer(), bv3->GetLength() ) )
        {
            return 1;
        }
    }
    else
    {
        std::string str( bv->GetPointer(), bv->GetLength() );
        std::cerr << "Unhandled: " << str << std::endl;
        return 1;
    }
}

```

```

    }

    return 0;
}

```

12.55 DumpSiemensBase64.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.
=====*/

/*
 * https://groups.google.com/forum/#!msg/comp.protocols.dicom/2kZ2lLP8EcM/WzjFrtjnAgAJ
 */
#include "gdcmReader.h"
#include "gdcmPrivateTag.h"
#include "gdcmPrinter.h"
#include "gdcmDictPrinter.h"
#include "gdcmCSAHeader.h"
#include "gdcmBase64.h"
#include "gdcmExplicitDataElement.h"
#include "gdcmSwapper.h"

#include <iostream>
#include <fstream>
#include <vector>

#include <assert.h>

int main(int argc, char *argv[])
{
    if( argc < 2 ) return 1;
    const char *filename = argv[1];
    gdcm::Reader reader;
    reader.SetFileName( filename );
    if( !reader.Read() )
    {
        std::cerr << "Failed to read: " << filename << std::endl;
        return 1;
    }
    const gdcm::DataSet& ds = reader.GetFile().GetDataSet();

    gdcm::CSAHeader csa;
    const gdcm::PrivateTag &t1 = csa.GetCSAImageHeaderInfoTag();
    if( !ds.FindDataElement( t1 ) ) return 1;
    csa.LoadFromDataElement( ds.GetDataElement( t1 ) );

    //const char name[] = "MRDiffusion";
    const char name[] = "MR_AS_L";
    if( csa.FindCSAElementByName( name ) )
    {
        const gdcm::CSAElement &el = csa.GetCSAElementByName( name );
        const gdcm::ByteValue* bv = el.GetByteValue();
        std::string str( bv->GetPointer(), bv->GetLength() );
        str.erase( std::remove( str.begin(), str.end(), '\n' ), str.end() );
        size_t dl = gdcm::Base64::GetDecodeLength( str.c_str(), str.size() );
        std::vector<char> buf;
        buf.resize( dl );
        size_t dl2 = gdcm::Base64::Decode( buf.data(), buf.size(), str.c_str(), str.size() );
        (void)dl2;
        std::stringstream ss;
        ss.str( std::string( buf.data(), buf.size() ) );
        gdcm::File file;
        gdcm::DataSet &ds2 = file.GetDataSet();
        gdcm::DataElement xde;
        try
        {

```

```

        while( xde.Read<gdcm::ExplicitDataElement, gdcm::SwapperNoOp>( ss ) )
        {
            ds2.Insert( xde );
        }
        gdcm_assert( ss.eof() );
    }
    catch( std::exception & )
    {
        return 1;
    }
    gdcm::Printer p;
    p.SetFile( file );
    p.Print( std::cout );
}

return 0;
}

```

12.56 DumpToSQLITE3.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
/*
 * Ref:
 * http://massmail.spl.harvard.edu/public-archives/slicer-devel/2010/004408.html
 *
 * Implementation details:
 * http://www.sqlite.org/c3ref/bind_blob.html
 * http://www.adp-gmbh.ch/sqlite/bind_insert.html
 */
#include "gdcmScanner.h"
#include "gdcmDirectory.h"
#include "gdcmTag.h"
#include "gdcmTrace.h"

#include "sqlite3.h"

#include <stdio.h>
#include <time.h>

int main(int argc, char *argv[])
{
    if( argc < 2 )
    {
        return 1;
    }
    time_t time_start = time(nullptr);

    gdcm::Trace::SetDebug( false );
    gdcm::Trace::SetWarning( false );
    const char *inputdirectory = argv[1];

    gdcm::Directory d;
    unsigned int nfiles = d.Load( inputdirectory, true );

    gdcm::Scanner s;
    using gdcm::Tag;
    s.AddTag( Tag(0x20,0xd) ); // Study Instance UID
    s.AddTag( Tag(0x20,0xe) ); // Series Instance UID

    bool b0 = s.Scan( d.GetFileNames() );
    if( !b0 ) return 1;
}

```



```

time_t time_scanner = time(nullptr);

std::cout << "Finished loading data from : " << nfiles << " files" << std::endl;

// MappingType const &mappings = s.GetMappings();

sqlite3* db;
sqlite3_open("../dicom.db", &db);

if(db == nullptr)
{
    std::cerr << "Could not open database." << std::endl;
    return 1;
}

const char sql_stmt[] = "create table browser (seriesuid, studyuid)";
int ret;

char *errmsg;
ret = sqlite3_exec(db, sql_stmt, nullptr, nullptr, &errmsg);

if(ret != SQLITE_OK)
{
    printf("Error in statement: %s [%s].\n", sql_stmt, errmsg);
    return 1;
}
using gdcm::Directory;
using gdcm::Scanner;
const Directory::FileNamesType& files = d.GetFilesNames();
Directory::FileNamesType::const_iterator file = files.begin();

sqlite3_stmt *stmt;
if ( sqlite3_prepare(
    db,
    "insert into browser values (?,?)", // stmt
    -1, // If than zero, then stmt is read up to the first nul terminator
    &stmt,
    nullptr // Pointer to unused portion of stmt
)
    != SQLITE_OK)
{
    printf("\nCould not prepare statement.");
    return 1;
}
//printf("\nThe statement has %d wildcards\n", sqlite3_bind_parameter_count(stmt));
for(; file != files.end(); ++file)
{
    const char *filename = file->c_str();
    bool b = s.IsKey(filename);
    if( b )
    {
        const Scanner::TagToValue &mapping = s.GetMapping(filename);
        Scanner::TagToValue::const_iterator it = mapping.begin();

        sqlite3_reset(stmt);

        for( int index = 1; it != mapping.end(); ++it, ++index)
        {
            //const Tag &tag = it->first;
            const char *value = it->second;

            if (sqlite3_bind_text (
                stmt,
                index, // Index of wildcard
                value,
                (int)strlen(value), // length of text
                SQLITE_STATIC // SQLite assumes that the information is in static
            )
                != SQLITE_OK)
            {
                printf("\nCould not bind int.\n");
                return 1;
            }
        }
        if (sqlite3_step(stmt) != SQLITE_DONE)
        {
            printf("\nCould not step (execute) stmt.\n");
            return 1;
        }
    }
}

```

```

    }

    sqlite3_close(db);

    time_t time_sqlite = time(nullptr);

    std::cout << "Time to scan DICOM files: " << (time_scanner - time_start) << std::endl;
    std::cout << "Time to build SQLITE3: " << (time_sqlite - time_scanner) << std::endl;

    return 0;
}

```

12.57 DumpToshibaDTI.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcml.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.
=====*/
/*
 * https://groups.google.com/d/msg/comp.protocols.dicom/7IaIkT0ZG5U/k7LPu81VvAMJ
 */
#include "gdcmlReader.h"
#include "gdcmlPrivateTag.h"
#include "gdcmlPrinter.h"
#include "gdcmlDictPrinter.h"

#include <iostream>
#include <fstream>
#include <vector>

#include <assert.h>

static bool DumpToshibaDTI( const char * input, size_t len )
{
    static int i = 0;
    ++i;
    if( len % 2 ) return false;

    std::vector<char> copy( input, input + len );
    std::reverse( copy.begin(), copy.end() );

    #if 0
    std::ostringstream f;
    f << "debug" << i;
    std::ofstream of( f.str().c_str(), std::ios::binary );
    of.write( &copy[0], copy.size() );
    of.close();
    #else

    std::istringstream is;
    std::string dup( copy.data(), copy.size() );
    is.str( dup );

    gdcml::File file;
    gdcml::FileMetaInformation & fmi = file.GetHeader();
    fmi.SetDataSetTransferSyntax( gdcml::TransferSyntax::ExplicitVRLittleEndian );
    gdcml::DataSet & ds = file.GetDataSet();
    ds.Read<gdcml::ExplicitDataElement, gdcml::SwapperNoOp>( is );

    //gdcml::DictPrinter p;
    gdcml::Printer p;
    p.SetFile( file );
    p.SetColor( true );
    p.Print( std::cout );
    #endif

    return true;
}

```

```

}

int main(int argc, char *argv[])
{
    if( argc < 2 ) return 1;
    const char *filename = argv[1];
    gdcm::Reader reader;
    reader.SetFileName( filename );
    if( !reader.Read() )
    {
        std::cerr << "Failed to read: " << filename << std::endl;
        return 1;
    }
    const gdcm::DataSet& ds = reader.GetFile().GetDataSet();

    // (0029,0010) ?? (LO) [PMTF INFORMATION DATA ]           # 22,1 Private Creator
    // (0029,1001) ?? (SQ) (Sequence with undefined length)    # u/l,1 ?

    const gdcm::PrivateTag tpmtf(0x0029,0x1,"PMTF INFORMATION DATA");
    if( !ds.FindDataElement( tpmtf ) ) return 1;
    const gdcm::DataElement& pmtf = ds.GetDataElement( tpmtf );
    if ( pmtf.IsEmpty() ) return 1;
    gdcm::SmartPointer<gdcm::SequenceOfItems> seq = pmtf.GetValueAsSQ();
    if ( !seq || !seq->GetNumberOfItems() ) return 1;

    size_t n = seq->GetNumberOfItems();
    for( size_t i = 1; i <= n; ++i )
    {
        gdcm::Item &item = seq->GetItem(i);
        gdcm::DataSet &subds = item.GetNestedDataSet();
        // (0029,0010) ?? (LO) [PMTF INFORMATION DATA ]           # 22,1 Private Creator
        // (0029,1090) ?? (OB) 00\05\00\13\00\12\00\22\           # 202,1 ?
        const gdcm::PrivateTag tseq(0x0029,0x90,"PMTF INFORMATION DATA");

        if( subds.FindDataElement( tseq ) )
        {
            const gdcm::DataElement &de = subds.GetDataElement( tseq );
            const gdcm::ByteValue *bv = de.GetByteValue();
            if( !bv ) return 1;

            bool b = DumpToshibaDTI( bv->GetPointer(), bv->GetLength() );
            if( !b ) return 1;
        }
    }

    return 0;
}

```

12.58 DumpToshibaDTI2.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
/*
 *      https://gazelle.ihe.net/EVSCClient/dicomResult.seam;jsessionid=x+Rf9Zs+ip49P+jC3L8SLZb8?&oid=1.3.6.1.4.1.12559.11.1.2.1.4.16
 */
#include "gdcmReader.h"
#include "gdcmPrivateTag.h"
#include "gdcmPrinter.h"
#include "gdcmDictPrinter.h"

#include <iostream>
#include <fstream>

```

```

#include <vector>

#include <assert.h>

static bool DumpToshibaDTI2( const char * input, size_t len )
{
    static int i = 0;
    ++i;
    if( len % 2 ) return false;

    std::vector<char> copy( input, input + len );
    std::reverse( copy.begin(), copy.end() );

    #if 0
        std::ostringstream f;
        f << "debug" << i;
        std::ofstream of( f.str().c_str(), std::ios::binary );
        of.write( &copy[0], copy.size() );
        of.close();
    #else

        std::istringstream is;
        std::string dup( copy.data(), copy.size() );
        is.str( dup );

        gdcm::File file;
        gdcm::FileMetaInformation & fmi = file.GetHeader();
        fmi.SetDataSetTransferSyntax( gdcm::TransferSyntax::ExplicitVRLittleEndian );
        gdcm::DataSet & ds = file.GetDataSet();
        ds.Read<gdcm::ExplicitDataElement, gdcm::SwapperNoOp>( is );

        //gdcm::DictPrinter p;
        gdcm::Printer p;
        p.SetFile( file );
        p.SetColor( true );
        p.Print( std::cout );
    #endif

    return true;
}

int main(int argc, char *argv[])
{
    if( argc < 2 ) return 1;
    const char *filename = argv[1];
    gdcm::Reader reader;
    reader.SetFileName( filename );
    if( !reader.Read() )
    {
        std::cerr << "Failed to read: " << filename << std::endl;
        return 1;
    }
    const gdcm::DataSet& ds = reader.GetFile().GetDataSet();

    /*
(0029,1001) SQ (Sequence with explicit length #=6)          # 18746, 1 Unknown Tag & Data
  (fffe,e000) na (Item with explicit length #=2)            # 206, 1 Item
    (0029,0010) LO [TOSHIBA_MEC_MR3]                          # 16, 1 PrivateCreator
    (0029,1090) OB 00\07\00\06\00\05\00\04\00\03\00\02\00\0c\00\01\00\00\00\00\00\12... # 170, 1 Unknown Tag &
    Data
  (fffe,e00d) na (ItemDelimitationItem for re-encoding)      # 0, 0 ItemDelimitationItem
  (fffe,e000) na (Item with explicit length #=2)              # 866, 1 Item
    (0029,0010) LO [TOSHIBA_MEC_MR3]                          # 16, 1 PrivateCreator
    (0029,1090) OB 45\4e\49\50\53\4c\20\52\41\5c\45\4e\49\50\53\4c\54\5c\52\45\53\55... # 830, 1 Unknown Tag &
    Data
[... ]
(0029,1002) SQ (Sequence with explicit length #=1)          # 120, 1 Unknown Tag & Data
  (fffe,e000) na (Item with explicit length #=2)            # 112, 1 Item
    (0029,0010) LO [TOSHIBA_MEC_MR3]                          # 16, 1 PrivateCreator
    (0029,1090) OB 00\10\00\02\53\55\10\80\70\0d\30\31\5e\33\52\4d\5f\43\45\4d\5f\41... # 76, 1 Unknown Tag &
    Data
  (fffe,e00d) na (ItemDelimitationItem for re-encoding)      # 0, 0 ItemDelimitationItem
*/

    const gdcm::PrivateTag tmecmr3(0x0029,0x1,"TOSHIBA_MEC_MR3");
    if( !ds.FindDataElement( tmecmr3 ) ) return 1;
    const gdcm::DataElement& mecmr3 = ds.GetDataElement( tmecmr3 );
    if ( mecmr3.IsEmpty() ) return 1;
    gdcm::SmartPointer<gdcm::SequenceOfItems> seq = mecmr3.GetValueAsSQ();

```

```

if ( !seq || !seq->GetNumberOfItems() ) return 1;

size_t n = seq->GetNumberOfItems();
for( size_t i = 1; i <= n; ++i )
{
    gdcm::Item &item = seq->GetItem(i);
    gdcm::DataSet &subds = item.GetNestedDataSet();
    const gdcm::PrivateTag tseq(0x0029,0x90,"TOSHIBA_MEC_MR3");

    if( subds.FindDataElement( tseq ) )
    {
        const gdcm::DataElement &de = subds.GetDataElement( tseq );
        const gdcm::ByteValue *bv = de.GetByteValue();
        if( !bv ) return 1;

        bool b = DumpToshibaDTI2( bv->GetPointer(), bv->GetLength() );
        if( !b ) return 1;
    }
}

return 0;
}

```

12.59 DumpVisusChange.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.
=====*/

#include "gdcmReader.h"
#include "gdcmDirectory.h"
#include "gdcmStringFilter.h"

#include <vector>
#include <algorithm>

/*
*/
static bool process( std::vector<gdcm::DataElement> &ms, const char * filename)
{
    using namespace gdcm;
    Tag pd(0x7fe0,0x0000);
    std::set<gdcm::Tag> skiptags;
    skiptags.insert( pd );

    gdcm::Reader reader;
    reader.SetFileName( filename );
    if( !reader.ReadUpToTag( pd, skiptags ) )
    {
        std::cerr << "Failure to read: " << filename << std::endl;
        return false;
    }

    gdcm::File &file = reader.GetFile();
    gdcm::DataSet &dsl = file.GetDataSet();

    const gdcm::PrivateTag tseq1(0x5533,0x33,"Visus Change");
    if( !dsl.FindDataElement( tseq1 ) ) return true;
    const gdcm::DataElement& seq1 = dsl.GetDataElement( tseq1 );

    SmartPointer<SequenceOfItems> sqil = seq1.GetValueAsSQ();

    const size_t nitems = sqil->GetNumberOfItems();
    for( size_t item = 1; item < nitems; ++item )
    {
        Item &item1 = sqil->GetItem(item);
    }
}

```

```

    DataSet &ds2 = item1.GetNestedDataSet();
    for(DataSet::ConstIterator it = ds2.Begin(); it != ds2.End(); ++it )
    {
        DataElement const &de = *it;
        // cannot simply use std::set here, see there is a discrepancy in between
        // operator== and operator<.
        // So only use operator== here:
        std::vector<DataElement>::iterator vit = std::find(ms.begin(), ms.end(), de);
        if( vit == ms.end() )
            ms.push_back(de);
    }
}
return true;
}

int main(int argc, char *argv[])
{
    bool usefastpath = true;

    if( argc < 2 ) return 1;
    using namespace gdcm;
    const char *filename = argv[1];
    gdcm::Directory::FileNamesType filenames;
    if( !gdcm::System::FileExists(filename) )
    {
        std::cerr << "Could not find file: " << filename << std::endl;
        return 1;
    }

    gdcm::Directory dir;
    if( gdcm::System::FileIsDirectory(filename) )
    {
        unsigned int nfiles = dir.Load(filename, false);
        if( nfiles == 0 )
        {
            std::cerr << "Could not find files: " << filename << std::endl;
            return 1;
        }
        filenames = dir.GetFilesNames();
    }
    else
    {
        filenames.push_back( filename );
    }
    gdcm::StringFilter sf;

    Tag pd(0x7fe0,0x0000);
    std::set<gdcm::Tag> skiptags;
    skiptags.insert( pd );

    gdcm::Reader reader;
    reader.SetFileName( filenames[0].c_str() );
    if( !reader.ReadUpToTag( pd, skiptags ) )
    {
        std::cerr << "Could not read file: " << filename << std::endl;
        return 1;
    }
    gdcm::File &file = reader.GetFile();
    sf.SetFile(file);

    if( usefastpath ) {
        // Heuristic, assume if private tag cannot be found in first file, skip the directory
        gdcm::DataSet &ds1 = file.GetDataSet();

        const gdcm::PrivateTag tseq1(0x5533,0x33,"Visus Change");
        if( !ds1.FindDataElement( tseq1 ) ){
            std::cerr << "Could not find private tag in first file skipping whole directory: " << filename << std::endl;
            return 0;
        }
    }
    std::vector<DataElement> ms;
    for(gdcm::Directory::FileNamesType::const_iterator cit = filenames.begin(); cit != filenames.end(); ++cit )
    {
        if( !process(ms, cit->c_str()) ) {
            return 1;
        }
    }

    if( !ms.empty() ) {
        std::sort(ms.begin(), ms.end());
        std::cout << filename << ",\n";
    }
}

```

```

    for(std::vector<DataElement>::const_iterator it = ms.begin(); it != ms.end(); ++it )
    {
        DataElement const & de = *it;
        std::string const & s = sf.ToString( de );
        std::cout << de.GetTag() << " " << s << std::endl;
    }
    std::cout << "\"" << std::endl;
}

return 0;
}

```

12.60 DuplicatePCDE.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcml.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
#include "gdcmlReader.h"
#include "gdcmlWriter.h"
#include "gdcmlItem.h"
#include "gdcmlImageReader.h"
#include "gdcmlSequenceOfItems.h"
#include "gdcmlFile.h"
#include "gdcmlTag.h"
/*
Usage:
DuplicatePCDE gdcmlData/D_CLUNIE_CT1_J2KI.dcm out.dcm

aka:
medical.nema.org/medical/dicom/DataSets/WG04/IMAGES/J2KI/CT1_J2KI

See:
gdcmlConformanceTests/CT1_J2KI_DuplicatePCDE.dcm

Original thread can be found at:

http://groups.google.com/group/comp.protocols.dicom/browse_thread/thread/82f28c4db28963af

Question:
1.
There is no restriction for a specific Private Creator Data Element
(PCDE) to be unique within the same group, right ?
Decoders of Private Data would have to handle the case where a PCDE
would be repeated and should NOT stop on the first instance of a
particular PCDE, right ?

Eg. when searching for the tag associated with
(0x0029,0x0010,"SIEMENS CSA HEADER") in the following (pseudo)
dataset:

(0029,0010) LO [SIEMENS CSA HEADER] # 18, 1
PrivateCreator
(0029,0011) LO [SIEMENS MEDCOM HEADER] # 22, 1
PrivateCreator
(0029,0012) LO [SIEMENS MEDCOM HEADER2] # 22, 1
PrivateCreator
(0029,0013) LO [SIEMENS CSA HEADER] # 18, 1
PrivateCreator
(0029,1008) CS [IMAGE NUM 4] # 12, 1
CSAImageHeaderType
(0029,1009) LO [20050723] # 8, 1
CSAImageHeaderVersion
(0029,1010) OB 53\56\31\30\04\03\02\01\38\00\00\00\4d
\00\00\00\45\63\68\6f\4c\69... # 6788, 1 CSAImageHeaderInfo
(0029,1018) CS [MR] # 2, 1

```

```

CSASeriesHeaderType
(0029,1019) LO [20050723] # 8, 1
CSASeriesHeaderVersion
(0029,1020) OB 53\56\31\30\04\03\02\01\2c\00\00\00\4d
\00\00\00\55\73\65\64\50\61... # 51520, 1 CSASeriesHeaderInfo
(0029,1131) LO [4.0.163088300] # 14, 1
PMTFInformation1
(0029,1132) UL 32768 # 4, 1
PMTFInformation2
(0029,1133) UL 0 # 4, 1
PMTFInformation3
(0029,1134) CS [DB TO DICOM] # 12, 1
PMTFInformation4
(0029,1260) ?? 63\6f\6d\20 # 4, 1
Unknown Tag & Data
(0029,1310) OB 53\56\31\30\04\03\02\01\38\00\00\00\4d
\00\00\00\45\63\68\6f\4c\69... # 6788, 1 CSAImageHeaderInfo

```

one should return two instances, correct ?

Answer:

I would say that this is covered in principle by the PS 3.5 7.1
 "The Data Elements ... shall occur at most once in a Data Set"
 rule, since the data element is defined by the tuple
 (private creator,gggg,ee) where xxee is the element
 number and xx is arbitrary and has no inherent meaning and
 does not serve to disambiguate the data element.

E.g.:

```

(0019,0030) Private Creator ID = "Smith"
...
(0019,0032) Private Creator ID = "Smith"
...
(0019,3015) Fractal Index = "32"
...
(0019,3215) Fractal Index = "32"

```

would be illegal because even though they are assigned different
 (completely arbitrary) blocks, with the same group, element
 number and private creator, (0019,3015) and (0019,3215) are the
 "same" data element.

*/

```

int main(int argc, char *argv[])
{
    if( argc < 3 )
    {
        std::cerr << argv[0] << " input.dcm output.dcm" << std::endl;
        return 1;
    }
    const char *filename = argv[1];
    const char *outfilename = argv[2];
    gdcm::Reader reader;
    reader.SetFileName( filename );
    if( !reader.Read() )
    {
        return 1;
    }

    gdcm::File &file = reader.GetFile();
    gdcm::DataSet &ds = file.GetDataSet();

    // Let's get all private element from group 0x9:
    /*
    (0009,0010) LO [GEMS_IDEN_01] # 12,1 Private Creator
    (0009,1001) LO [GE_GENESIS_FF ] # 14,1 Full fidelity
    (0009,1002) SH [CT01] # 4,1 Suite id
    (0009,1004) SH [HiSpeed CT/i] # 12,1 Product id
    (0009,1027) SL 862399669 # 4,1 Image actual date
    (0009,1030) SH (no value) # 0,1 Service id
    (0009,1031) SH (no value) # 0,1 Mobile location number
    (0009,10e6) SH [05] # 2,1 Genesis Version - now
    (0009,10e7) UL 973283917 # 4,1 Exam Record checksum
    (0009,10e9) SL 862399669 # 4,1 Actual series data time stamp
    */
    gdcm::Tag start(0x0009,0x0);
    // Create a temporary duplicate dataset, since we cannot insert data element as we go over them (std::set
    // would reorganize itself as we go over it ...)
    gdcm::DataSet dup;

```



```

gdcmm::Tag new_private(0x0009,0x0);
while (start.GetGroup() == 0x9 )
{
    const gdcmm::DataElement& de = ds.FindNextDataElement(start);
    const gdcmm::Tag &t = de.GetTag();
    if( t.IsPrivateCreator() )
    {
        std::cout << t << std::endl;
        // Ok let's duplicate into the next available attribute:
        gdcmm::DataElement duplicate = de;
        duplicate.GetTag().SetElement( (uint16_t)(t.GetElement() + 1) );
        dup.Insert( duplicate );
        new_private = duplicate.GetTag();
    }
    else if( t.IsPrivate() && !t.IsPrivateCreator() )
    {
        //std::cout << de << std::endl;
        std::string owner = ds.GetPrivateCreator( de.GetTag() );
        //std::cout << owner << std::endl;
        gdcmm::DataElement duplicate = de;
        duplicate.GetTag().SetPrivateCreator( new_private );
        if( const gdcmm::ByteValue *bv = duplicate.GetByteValue() )
        {
            // Warning: when doing : duplicate = de, only the pointer to the ByteValue is passed
            // (to avoid large memory duplicate). We need to explicitly duplicate the bytevalue ourselves:
            gdcmm::ByteValue *dupbv = new gdcmm::ByteValue( bv->GetPointer(),
                bv->GetLength() );
            // Let's recognize the duplicated ASCII-type elements:
            if( duplicate.GetVR() & gdcmm::VR::VRASCII )
                dupbv->Fill( 'X' );
            duplicate.SetValue( *dupbv );
        }
        dup.Insert( duplicate );
    }
    start = t;
    // move to next possible 'public' element
    start.SetElement( (uint16_t)(start.GetElement() + 1) );
}

gdcmm::DataSet::ConstIterator it = dup.Begin();
for( ; it != dup.End(); ++it )
{
    ds.Insert( *it );
}

gdcmm::Writer w;
w.SetFile( file );
w.SetFileName( outfilename );
if ( !w.Write() )
{
    return 1;
}

return 0;
}

```

12.61 ELSCINT1WaveToText.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcmm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
#include "gdcmmReader.h"
#include "gdcmmPrivateTag.h"

/*
 * This example shows how to read a Wave Information tag from ELSCINT1

```

```

* The wave information is stored in Tag (01e1,18,ELSCINT1) hidden in a
* Secondary Capture Image Storage (usually a 'N' Symbol is shown)
*
* Everything done in this code is for the sole purpose of writing interoperable
* software under Sect. 1201 (f) Reverse Engineering exception of the DMCA.
* If you believe anything in this code violates any law or any of your rights,
* please contact us (gdcmm-developers@lists.sourceforge.net) so that we can
* find a solution.
*
* Everything you do with this code is at your own risk, since decompression
* algorithm was not written from specification documents.
*
* Special thanks to:
* Gauthier Bouilhol
*/

template <typename T>
bool dumpargs(std::ostream & os, T c1, T c2, T c3, T c4, T c5, T c6, T c7, T c8)
{
    static const char sep = '\t';
    os << c1 << sep << c2 << sep << c3 << sep << c4 << sep << c5 << sep << c6 << sep << c7 << sep << c8;
    os << std::endl;
    return true;
}

bool wave2stream( std::ostream &text_file, const char *in, size_t len )
{
    const short * buffer = (const short*)in;
    size_t length = len / sizeof( short );
    text_file << "COMPLETE_WAVE" << '\t' << "MASK" << '\t' << "AQUISITION_PROFIL" << '\t' << "END-INHALE" << '\t' <<
    "END-EXHALE" << '\t' << "AQUISITION_WAVE" << '\t' << "WAVE_STATISTICS" << '\t' << "MASK" << std::endl;
    for (size_t i=0; i<length-76; i+=2)
    {
        if ( i < 74 )
        {
            if (buffer[i+75] == 0)
                text_file << buffer[i+74] << '\t' << buffer[i+75] << '\t' << 0 << '\t' << " " << '\t' << buffer[i+1] <<
                '\t' << " " << '\t' << " " << '\t' << buffer[i] << '\t' << buffer[i+1] <<
                std::endl;
            if (buffer[i+75] == 16384)
                text_file << buffer[i+74] << '\t' << buffer[i+75] << '\t' << 0 << '\t' << buffer[i+74] <<
                '\t' << " " << '\t' << " " << '\t' << buffer[i] << '\t' << buffer[i+1] <<
                std::endl;
            if (buffer[i+75] == 256)
                text_file << buffer[i+74] << '\t' << buffer[i+75] << '\t' << 0 << '\t' << " " << '\t' << buffer[i] <<
                '\t' << buffer[i+1] <<
                std::endl;
            if (buffer[i+75] == -32768)
                text_file << buffer[i+74] << '\t' << buffer[i+75] << '\t' << 1 << '\t' << " " << '\t' << buffer[i] <<
                '\t' << " " << '\t' << buffer[i+74] << '\t' << buffer[i] << '\t' << buffer[i+1] <<
                std::endl;
            if (buffer[i+75] == -16384)
                text_file << buffer[i+74] << '\t' << buffer[i+75] << '\t' << 1 << '\t' << buffer[i+74] <<
                '\t' << " " << '\t' << buffer[i+74] << '\t' << buffer[i] << '\t' << buffer[i+1] <<
                std::endl;
            if (buffer[i+75] == -32512)
                text_file << buffer[i+74] << '\t' << buffer[i+75] << '\t' << 1 << '\t' << " " << '\t' << " " <<
                '\t' << buffer[i+74] << '\t' << buffer[i+74] << '\t' << buffer[i] << '\t' << buffer[i+1] <<
                std::endl;
        }
        else
        {
            if (buffer[i+75] == 0)
                text_file << buffer[i+74] << '\t' << buffer[i+75] << '\t' << 0 << '\t' << " " << '\t' << " " <<
                '\t' << " " << '\t' << " " << '\t' << " " <<
                std::endl;
            if (buffer[i+75] == 16384)
                text_file << buffer[i+74] << '\t' << buffer[i+75] << '\t' << 0 << '\t' << buffer[i+74] <<
                '\t' << " " << '\t' << " " << '\t' << " " << '\t' << " " <<
                std::endl;
            if (buffer[i+75] == 256)
                text_file << buffer[i+74] << '\t' << buffer[i+75] << '\t' << 0 << '\t' << " " << '\t' << " " <<
                '\t' << " " << '\t' << " " <<
                std::endl;
            if (buffer[i+75] == -32768)
                text_file << buffer[i+74] << '\t' << buffer[i+75] << '\t' << 1 << '\t' << " " << '\t' << " " <<
                '\t' << " " << '\t' << " " <<
                std::endl;
            if (buffer[i+75] == -16384)
                text_file << buffer[i+74] << '\t' << buffer[i+75] << '\t' << 1 << '\t' << buffer[i+74] <<
                '\t' << " " << '\t' << buffer[i+74] << '\t' << " " <<
        }
    }
}

```

```

        std::endl;
        if (buffer[i+75] == -32512)
            text_file << buffer[i+74] << '\t' << buffer[i+75] << '\t' << 1
            << '\t' << buffer[i+74] << '\t' << buffer[i+74] << '\t' << " " <<
            << '\t' << " " << " " << " " <<
        std::endl;
    }
}

return true;
}

int main(int argc, char *argv [])
{
    if( argc < 3 ) return 1;
    const char *filename = argv[1];
    const char *outfilename = argv[2];
    gdcm::Reader reader;
    reader.SetFileName( filename );
    if( !reader.Read() )
    {
        std::cerr << "Failed to read: " << filename << std::endl;
        return 1;
    }
    const gdcm::DataSet& ds = reader.GetFile().GetDataSet();

    const gdcm::PrivateTag twave(0x01e1,0x18,"ELSCINT1");
    if( !ds.FindDataElement( twave ) ) return 1;
    const gdcm::DataElement& wave = ds.GetDataElement( twave );
    if ( wave.IsEmpty() ) return 1;
    const gdcm::ByteValue *bv = wave.GetByteValue();
    gdcm_assert( bv );

    std::ofstream os( outfile, std::ios::binary );
    // Dump that to a CSV file:
    wave2stream( os, bv->GetPointer(), bv->GetLength() );
    os.close();

    return 0;
}

```

12.62 EmptyMask.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
#include "gdcmEmptyMaskGenerator.h"

#include <string>
#include <cstring>

int main( int argc, char *argv[] )
{
    std::string inputdir;
    std::string outputdir;
    bool input_sopclassuid = true;
    bool grayscale_secondary_sopclassuid = false;
    if( argc < 3 ) return 1;
    inputdir = argv[1];
    outputdir = argv[2];
    // input_sopclassuid -> Use original SOP Class UID from input DICOM (Default).
    // grayscale_secondary_sopclassuid -> Use Grayscale Secondary Image Storage SOP Class UID.
    if( argc >= 3 )
    {
        input_sopclassuid = false;
        if( strcmp("input_sopclassuid", argv[3]) == 0 )
            input_sopclassuid = true;
    }
}

```

```

    else if (strcmp("grayscale_secondary_sopclassuid", argv[3]) == 0 ) {
        grayscale_secondary_sopclassuid = true;
    }
}

//
gdcm::EmptyMaskGenerator emg;
if( input_sopclassuid )
    emg.SetSOPClassUIDMode( gdcm::EmptyMaskGenerator::UseOriginalSOPClassUID );
else if( grayscale_secondary_sopclassuid )
    emg.SetSOPClassUIDMode( gdcm::EmptyMaskGenerator::UseGrayscaleSecondaryImageStorage );
emg.SetInputDirectory( inputdir.c_str() );
emg.SetOutputDirectory( outputdir.c_str() );
if( !emg.Execute() )
{
    return 1;
}

return 0;
}

```

12.63 EncapsulateFileInRawData.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
#include "gdcmAnonymizer.h"
#include "gdcmWriter.h"
#include "gdcmUIDGenerator.h"
#include "gdcmFile.h"
#include "gdcmTag.h"
#include "gdcmSystem.h"

#include "magic.h" // libmagic, API to file command line tool

/*
 * Let say you want to encapsulate a file type that is not defined in DICOM (exe, zip, png)
 * PNG is a bad example, unless it contains transparency (which has been deprecated).
 * It will take care of dispatching each chunk to an appropriate data item (pretty much like
 * WaveformData)
 *
 * Usage:
 * ./EncapsulateFileInRawData large_input_file.exe large_input_file.dcm
 */

// TODO:
// $ file -bi /tmp/gdcm-2.1.0.pdf
int main(int argc, char *argv[])
{
    if( argc < 3 )
    {
        std::cerr << argv[0] << " inputfile output.dcm" << std::endl;
        return 1;
    }
    const char *filename = argv[1];
    const char *outfilename = argv[2];

    if( !gdcm::System::FileExists( filename ) ) return 1;

    size_t s = gdcm::System::FileSize(filename);
    if( !s ) return 1;

    magic_t cookie = magic_open(MAGIC_NONE);
    const char * file_type = magic_file(cookie, filename);
    if( !file_type ) return 1;

```

```

magic_close(cookie);

gdcmm::Writer w;
gdcmm::File &file = w.GetFile();
//gdcmm::DataSet &ds = file.GetDataSet();
//w.SetCheckFileMetaInformation( true );
w.SetFileName( outfilename );

file.GetHeader().SetDataSetTransferSyntax( gdcmm::TransferSyntax::ImplicitVRLittleEndian );

gdcmm::Anonymizer anon;
anon.SetFile( file );

gdcmm::MediaStorage ms = gdcmm::MediaStorage::RawDataStorage;

gdcmm::UIDGenerator gen;
anon.Replace( gdcmm::Tag(0x0008,0x16), ms.GetString() );
std::cout << ms.GetString() << std::endl;
anon.Replace( gdcmm::Tag(0x0008,0x18), gen.Generate() );

if ( !w.Write() )
{
    std::cerr << "Could not write: " << outfilename << std::endl;
    return 1;
}

return 0;
}

```

12.64 ExtractEncryptedContent.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcmm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
#include "gdcmmReader.h"

#include <fstream>

/*

openssl smime -encrypt -binary -aes256 -in outputfile.dcm -inform DER -out outputfile.der -outform DER
../trunk/Testing/Source/Data/certificate.pem

openssl smime -decrypt -binary -in out.der -inform DER -out outputfile.dcm -outform DER -inkey
../trunk/Testing/Source/Data/privatekey.pem ../trunk/Testing/Source/Data/certificate.pem

*/

int main(int argc, char *argv[])
{
    if( argc < 3 )
    {
        std::cerr << argv[0] << " input.dcm output.der" << std::endl;
        return 1;
    }
    const char *filename = argv[1];
    const char *outfilename = argv[2];

    gdcmm::Reader reader;
    reader.SetFileName( filename );
    if( !reader.Read() )
    {
        return 1;
    }

    gdcmm::File &file = reader.GetFile();

```

```

gdcM::DataSet &ds = file.GetDataSet();

const gdcM::DataElement &EncryptedAttributesSequence = ds.GetDataElement( gdcM::Tag( 0x0400,0x0500 ) );

gdcM::SequenceOfItems *sqi = EncryptedAttributesSequence.GetValueAsSQ();

if ( !sqi || sqi->GetNumberOfItems() != 1 ) return 1;

gdcM::Item &item = sqi->GetItem(1);

gdcM::DataSet &nesteddds = item.GetNestedDataSet();

if( ! nesteddds.FindDataElement( gdcM::Tag( 0x0400,0x0520 ) ) ) return 1;

const gdcM::DataElement &EncryptedContent = nesteddds.GetDataElement( gdcM::Tag( 0x0400,0x0520 ) );

const gdcM::ByteValue *bv = EncryptedContent.GetByteValue();

std::ofstream of( outfilename, std::ios::binary );
of.write( bv->GetPointer(), bv->GetLength() );
of.close();

return 0;
}

```

12.65 ExtractIconFromFile.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcM.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
/*
 * This example shows how to either retrieve an Icon if present somewhere
 * in the file, or else generate one.
 */
#include "gdcMImageReader.h"
#include "gdcMPNMCodec.h"
#include "gdcMIconImageFilter.h"
#include "gdcMIconImageGenerator.h"

bool WriteIconAsPNM(const char* filename, const gdcM::IconImage& icon)
{
    gdcM::PNMCodec pnm;
    pnm.SetDimensions( icon.GetDimensions() );
    pnm.SetPixelFormat( icon.GetPixelFormat() );
    pnm.SetPhotometricInterpretation( icon.GetPhotometricInterpretation() );
    pnm.SetLUT( icon.GetLUT() );
    const gdcM::DataElement& in = icon.GetDataElement();
    bool b = pnm.Write( filename, in );
    gdcM_assert(b);
    return b;
}

int main(int argc, char *argv [])
{
    if( argc < 2 ) return 1;
    const char *filename = argv[1];
    gdcM::ImageReader reader;
    reader.SetFileName( filename );
    if( !reader.Read() )
    {
        std::cerr << "Failed to read (or not image): " << filename << std::endl;
        return 1;
    }

    gdcM::IconImageFilter iif;
    iif.SetFile( reader.GetFile() );

```

```

bool b = iif.Extract();

if( b )
{
    const gdcm::IconImage &icon = iif.GetIconImage(0);
    icon.Print( std::cout );

    if( !icon.GetTransferSyntax().IsEncapsulated() )
    {
        // Let's write out this icon as PNM file
        WriteIconAsPNM("icon.ppm", icon);
    }
    else if( icon.GetTransferSyntax() == gdcm::TransferSyntax::JPEGBaselineProcess1
    || icon.GetTransferSyntax() == gdcm::TransferSyntax::JPEGEExtendedProcess2_4
    )
    {
        const gdcm::DataElement& in = icon.GetDataElement();
        const gdcm::ByteValue *bv = in.GetByteValue();
        gdcm_assert( bv );
        std::ofstream out( "icon.jpg", std::ios::binary );
        out.write( bv->GetPointer(), bv->GetLength() );
        out.close();
    }
}
else
{
    gdcm_assert( iif.GetNumberOfIconImages() == 0 );
    std::cerr << "No Icon Found anywhere in file" << std::endl;

    const gdcm::Image &img = reader.GetImage();
    gdcm::IconImageGenerator iig;
    iig.AutoPixelMinMax(true);
    iig.SetPixmap( img );
    const unsigned int idims[2] = { 64, 64 };
    iig.SetOutputDimensions( idims );
    //iig.SetPixelMinMax(60, 868);
    if( !iig.Generate() ) return 1;
    const gdcm::IconImage & icon = iig.GetIconImage();
    WriteIconAsPNM("icon.ppm", icon);
}

return 0;
}

```

12.66 Extracting_All_Resolution.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
// This work was realised during the GSOC 2011 by Manoj Alwani

#include <fstream>
#include <stdint.h>
#include <string.h>
#include <assert.h>
#include <gdcm_j2k.h>
#include <gdcm_jp2.h>
#include <iostream>
#include <cstring>
#include <stdio.h>
#include <string.h>
#include <stdlib.h>
#include <math.h>
#include "gdcmImageReader.h"
#include "gdcmSequenceOfItems.h"
#include "gdcmSystem.h"

```

```

#include <fstream>

#include "gdcm_openjpeg.h"
#include "gdcmMediaStorage.h"
#include "gdcmWriter.h"
#include "gdcmItem.h"
#include "gdcmImageReader.h"
#include "gdcmAttribute.h"
#include "gdcmFile.h"
#include "gdcmTag.h"
#include "gdcmTransferSyntax.h"
#include "gdcmUIDGenerator.h"
#include "gdcmAnonymizer.h"
#include "gdcmStreamImageWriter.h"
#include "gdcmImageHelper.h"
#include "gdcmTrace.h"

void error_callback(const char *msg, void *) {
    (void)msg;
}
void warning_callback(const char *msg, void *) {
    (void)msg;
}
void info_callback(const char *msg, void *) {
    (void)msg;
}

bool Write_Resolution(gdcm::StreamImageWriter & theStreamWriter, const char *filename, int res, std::ostream&
    of, int flag, gdcm::SequenceOfItems *sq, int No_Of_Resolutions)
{
    std::ifstream is;
    is.open( filename, std::ios::binary );
    opj_dparameters_t parameters; /* decompression parameters */
    opj_event_mgr_t event_mgr; /* event manager */
    opj_dinfo_t* dinfo; /* handle to a decompressor */
    opj_cio_t *cio;
    opj_image_t *image = NULL;
    //FIXME: Do some stupid work:
    is.seekg( 0, std::ios::end);
    std::streampos buf_size = is.tellg();
    char *dummy_buffer = new char[(unsigned int)buf_size];
    is.seekg(0, std::ios::beg);
    is.read( dummy_buffer, buf_size);
    unsigned char *src = (unsigned char*)dummy_buffer;
    uint32_t file_length = (uint32_t)buf_size; // 32bits truncation should be ok since DICOM cannot have larger
        than 2Gb image

    /* configure the event callbacks (not required) */
    memset(&event_mgr, 0, sizeof(opj_event_mgr_t));
    event_mgr.error_handler = error_callback;
    event_mgr.warning_handler = warning_callback;
    event_mgr.info_handler = info_callback;

    /* set decoding parameters to default values */
    opj_set_default_decoder_parameters(&parameters);

    // default blindly copied
    parameters.cp_layer=0;
    parameters.cp_reduce= res;
    // parameters.decode_format=-1;
    // parameters.cod_format=-1;

    const char jp2magic[] = "\x00\x00\x00\x0C\x6A\x50\x20\x20\x0D\x0A\x87\x0A";
    if( memcmp( src, jp2magic, sizeof(jp2magic) ) == 0 )
    {
        /* JPEG-2000 compressed image data ... sigh */
        // gdcmData/ELSCINT1_JP2vsJ2K.dcm
        // gdcmData/MAROTTECH_CT_JP2Lossy.dcm
        //gdcmWarningMacro( "J2K start like JPEG-2000 compressed image data instead of codestream" );
        parameters.decode_format = 1; //JP2_CFMT;
        //gdcm_assert(parameters.decode_format == JP2_CFMT);
    }
    else
    {
        /* JPEG-2000 codestream */
        //parameters.decode_format = J2K_CFMT;
        //gdcm_assert(parameters.decode_format == J2K_CFMT);
    }
}

```



```

    gdcmm_assert( 0 );
}
parameters.cod_format = 11; // PGX_DFMT;
//gdcmm_assert(parameters.cod_format == PGX_DFMT);

/* get a decoder handle */
dinfo = opj_create_decompress(CODEC_JP2);

/* catch events using our callbacks and give a local context */
opj_set_event_mgr((opj_common_ptr)dinfo, &event_mgr, NULL);

/* setup the decoder decoding parameters using user parameters */
opj_setup_decoder(dinfo, &parameters);

/* open a byte stream */
cio = opj_cio_open((opj_common_ptr)dinfo, src, file_length);

/* decode the stream and fill the image structure */
image = opj_decode(dinfo, cio);
if(!image) {
    opj_destroy_decompress(dinfo);
    opj_cio_close(cio);
    //gdcmmErrorMacro( "opj_decode failed" );
    return 1;
}

    opj_cp_t * cp = ((opj_jp2_t*)dinfo->jp2_handle)->j2k->cp;
    opj_tcp_t *tcp = &cp->tcps[0];
    opj_tccp_t *tccp = &tcp->tccps[0];
    /*      std::cout << "\n No of Cols In Image" << image->x1;
    std::cout << "\n No of Rows In Image" << image->y1;
    std::cout << "\n No of Components in Image" << image->numcomps;
    std::cout << "\n No of Resolutions" << tccp->numresolutions << "\n";
*/
    opj_j2k_t* j2k = NULL;
    opj_jp2_t* jp2 = NULL;
    jp2 = (opj_jp2_t*)dinfo->jp2_handle;
    int reversible = jp2->j2k->cp->tcps->tccps->qmfbid;
    //std::cout << reversible;
    int compno = 0;
    opj_image_comp_t *comp = &image->comps[compno];
    int Dimensions[2];
    Dimensions[0] = comp->w;
    Dimensions[1] = comp->h;
    opj_cio_close(cio);
    unsigned long len = Dimensions[0]*Dimensions[1] * image->numcomps;
    //std::cout << "\nTest" <<image->comps[0].factor;
    char *raw = new char[len];
    for (unsigned int compno = 0; compno < (unsigned int)image->numcomps; compno++)
    {
        opj_image_comp_t *comp = &image->comps[compno];

        int w = image->comps[compno].w;
        int h = image->comps[compno].h;
        uint8_t *data8 = (uint8_t*)raw + compno;
        for (int i = 0; i < w * h; i++)
        {
            int v = image->comps[compno].data[i];
            *data8 = (uint8_t)v;
            data8 += image->numcomps;
        }
    }

    gdcmm::Writer w;
    gdcmm::File &file = w.GetFile();
    gdcmm::DataSet &ds = file.GetDataSet();

    file.GetHeader().SetDataSetTransferSyntax( gdcmm::TransferSyntax::ExplicitVRLittleEndian );

    gdcmm::UIDGenerator uid;
    gdcmm::DataElement de( gdcmm::Tag(0x8,0x18) ); // SOP Instance UID
    de.SetVR( gdcmm::VR::UI );
    const char *u = uid.Generate();
    de.SetByteValue( u, strlen(u) );
    ds.Insert( de );

    gdcmm::DataElement del( gdcmm::Tag(0x8,0x16) );
    del.SetVR( gdcmm::VR::UI );
    gdcmm::MediaStorage ms( gdcmm::MediaStorage::CTImageStorage );
    del.SetByteValue( ms.GetString(), strlen(ms.GetString()) );

```

```

ds.Insert( del );

const char mystr[] = "MONOCHROME2 ";
gdcm::DataElement de2( gdcm::Tag(0x28,0x04) );
//de.SetTag(gdcm::Tag(0x28,0x04));
de2.SetVR( gdcm::VR::CS );
de2.SetByteValue(mystr, strlen(mystr));
ds.Insert( de2 );

gdcm::Attribute<0x0028,0x0010> row = {image->comps[0].w};
//row.SetValue(512);
ds.Insert( row.GetAsDataElement() );
// w.SetCheckFileMetaInformation( true );
gdcm::Attribute<0x0028,0x0011> col = {image->comps[0].h};
ds.Insert( col.GetAsDataElement() );
gdcm::Attribute<0x0028,0x0008> Number_Of_Frames = {1};
ds.Insert( Number_Of_Frames.GetAsDataElement() );

gdcm::Attribute<0x0028,0x0100> at = {8};
ds.Insert( at.GetAsDataElement() );

gdcm::Attribute<0x0028,0x0002> at1 = {image->numcomps};
ds.Insert( at1.GetAsDataElement() );

gdcm::Attribute<0x0028,0x0101> at2 = {8};
ds.Insert( at2.GetAsDataElement() );

gdcm::Attribute<0x0028,0x0102> at3 = {7};
ds.Insert( at3.GetAsDataElement() );

if (flag == 1)
{
    for (int i=0; i < No_Of_Resolutions; i++)
    {
        int a = 1;
        int b =1;

        while(a!=(No_Of_Resolutions)-i))
        {
            b = b*2;
            a = a+1;
        }
        uint16_t row = (image->y1)/b;
        uint16_t col = (image->x1)/b;
        //std::cout << row;
        gdcm::Element<gdcm::VR::IS, gdcm::VM::VM1> el2;
        el2.SetValue(i+1);
        gdcm::DataElement rfn = el2.GetAsDataElement(); //ulr --> upper left row
        rfn.SetTag( gdcm::Tag(0x0008,0x1160) );

        gdcm::Element<gdcm::VR::US, gdcm::VM::VM2> el;
        el.SetValue(1,0);
        el.SetValue(1,1);
        gdcm::DataElement ulr = el.GetAsDataElement(); //ulr --> upper left col/row
        ulr.SetTag( gdcm::Tag(0x0048,0x0201) );

        gdcm::Element<gdcm::VR::US, gdcm::VM::VM2> el1;
        el1.SetValue(col,0);
        el1.SetValue(row,1);
        gdcm::DataElement brr = el1.GetAsDataElement();
        brr.SetTag( gdcm::Tag(0x0048,0x0202) ); //brr --> bottom right col/row
        gdcm::Item it;
        gdcm::DataSet &nds = it.GetNestedDataSet();
        nds.Insert( rfn );
        nds.Insert( ulr );
        nds.Insert( brr );

        sq->AddItem(it);
    }

    gdcm::Writer w1;
    gdcm::File &file1 = w1.GetFile();
    gdcm::DataSet &ds1 = file1.GetDataSet();
    file1.GetHeader().SetDataSetTransferSyntax( gdcm::TransferSyntax::ExplicitVRLittleEndian );

    gdcm::UIDGenerator uid1;
    gdcm::DataElement dea( gdcm::Tag(0x8,0x18) ); // SOP Instance UID

```

```

    dea.SetVR( gdcm::VR::UI );
    const char *ul = uid1.Generate();
    dea.SetByteValue( ul, strlen(ul) );
    ds1.Insert( dea );

    gdcm::DataElement deb( gdcm::Tag(0x8,0x16) );
    deb.SetVR( gdcm::VR::UI );
    gdcm::MediaStorage msl( gdcm::MediaStorage::VLWholeSlideMicroscopyImageStorage );
    deb.SetByteValue( msl.GetString(), strlen( msl.GetString() ) );
    ds1.Insert( deb );

    const char mystr1[] = "MONOCHROME2 ";
    gdcm::DataElement dec( gdcm::Tag(0x28,0x04) );
    //de.SetTag(gdcm::Tag(0x28,0x04));
    dec.SetVR( gdcm::VR::CS );
    dec.SetByteValue(mystr, strlen(mystr1));
    ds1.Insert( dec );

    gdcm::Attribute<0x0028,0x0010> row1 = {image->y1};
    //row.SetValue(512);
    ds1.Insert( row1.GetAsDataElement() );
    // w.SetCheckFileMetaInformation( true );
    gdcm::Attribute<0x0028,0x0011> col1 = {image->x1};
    ds1.Insert( col1.GetAsDataElement() );
    gdcm::Attribute<0x0028,0x0008> Number_Of_Frames1 = {tccp->numresolutions};
    ds1.Insert( Number_Of_Frames1.GetAsDataElement() );

    gdcm::Attribute<0x0028,0x0100> ata = {8};
    ds1.Insert( ata.GetAsDataElement() );

    gdcm::Attribute<0x0028,0x0002> atb = {image->numcomps};
    ds1.Insert( atb.GetAsDataElement() );

    gdcm::Attribute<0x0028,0x0101> atc = {8};
    ds1.Insert( atc.GetAsDataElement() );

    gdcm::Attribute<0x0028,0x0102> atd = {7};
    ds1.Insert( atd.GetAsDataElement() );

    theStreamWriter.SetFile(file1);

    gdcm::DataElement des( gdcm::Tag(0x0048,0x0200) );
    des.SetVR(gdcm::VR::SQ);
    //des.SetVR(gdcm::VM::VM1);
    des.SetValue(*sq);
    des.SetVLToUndefined();

    ds1.Insert( des );

    if (!theStreamWriter.WriteImageInformation()){
        std::cerr << "unable to write image information" << std::endl;
        return 1; //the CanWrite function should prevent getting here, else,
        //that's a test failure
    }
}

theStreamWriter.SetFile(file);

if (!theStreamWriter.CanWriteFile()){
    delete [] raw;
    std::cout << "Not able to write";
    return 0; //this means that the file was unwritable, period.
    //very similar to a ReadImageInformation failure
}
else
    std::cout<<"\nable to read";

// Important to write here
std::vector<unsigned int> extent = gdcm::ImageHelper::GetDimensionsValue(file);

    unsigned short xmax = extent[0];
    unsigned short ymax = extent[1];
    unsigned short theChunkSize = 4;
    unsigned short ychunk = extent[1]/theChunkSize; //go in chunk sizes of theChunkSize
    unsigned short zmax = extent[2];
    std::cout << "\n" << xmax << "\n" << ymax << "\n" << zmax << "\n" << image->numcomps << "\n";

    if (xmax == 0 || ymax == 0)

```

```

    {
        std::cerr << "Image has no size, unable to write zero-sized image." << std::endl;
        return 0;
    }

    int z, y, nexty;
    unsigned long prevLen = 0; //when going through the char buffer, make sure to grab
    //the bytes sequentially. So, store how far you got in the buffer with each iteration.
    for (z = 0; z < zmax; ++z){
        for (y = 0; y < ymax; y += ychunk){
            nexty = y + ychunk;
            if (nexty > ymax) nexty = ymax;
            theStreamWriter.DefinePixelExtent(0, xmax, y, nexty, z, z+1);
            unsigned long len = theStreamWriter.DefineProperBufferLength();
            std::cout << "\n" << len;
            char* finalBuffer = new char[len];
            memcpy(finalBuffer, &(raw[prevLen]), len);
            std::cout << "\nable to write";
            if (!theStreamWriter.Write(finalBuffer, len)){
                std::cerr << "writing failure:" << "output.dcm" << " at y = " << y << " and z = " << z << std::endl;
                delete [] raw;
                delete [] finalBuffer;
                return 1;
            }
            delete [] finalBuffer;
            prevLen += len;
        }
        delete raw;
    }
    delete[] src; //FIXME

    if(dinfo) {
        opj_destroy_decompress(dinfo);
    }

    opj_image_destroy(image);

    return true;
}

bool Different_Resolution( gdcm::StreamImageWriter & theStreamWriter, const char *filename, int res,
    std::ostream& of)
{
    //std::vector<std::string>::const_iterator it = filenames.begin();
    bool b = true;
    int flag = 1;

    gdcm::SmartPointer<gdcm::SequenceOfItems> sq = new gdcm::SequenceOfItems();
    sq->SetLengthToUndefined();

    for(int i = res-1 ; i>=0; --i)
    {
        b = b && Write_Resolution( theStreamWriter, filename, i, of ,flag,sq,res);
        // b = b && Get_Resolution( theStreamWriter, filename, i, of ,0);
        flag = 0;
    }
    //b = b && Get_Lowest_Resolution( writer, sq, filename, res-1 );
    //b = b && PopulateSingeFile( writer, sq, jpeg, filename2 );
    //image.SetDimension(2, res )
    return b;
}

int main(int argc, char *argv[])
{
    if( argc < 4 )
    {
        std::cerr << argv[0] << " input.jp2 output.dcm No. Of Resolutions " << std::endl;
        return 1;
    }
    const char *filename = argv[1];
    const char *outfilename = argv[2];
    char *resolutions = argv[3];
    int res = int((*(resolutions)-48));
    //std:: cout << "\nres"<< res;

```

```

gdcmm::StreamImageWriter theStreamWriter;

std::ofstream of;
of.open( outfile, std::ios::out | std::ios::binary );
theStreamWriter.SetStream(of);

if( !Different_Resolution( theStreamWriter, filename,res,of ) ) return 1;

uint16_t firstTag1 = 0xffff;
uint16_t secondTag1 = 0xe0dd;
uint32_t thirdTag1 = 0x00000000;
//uint16_t fourthTag1 = 0xffff;
const int theBufferSize = 2*sizeof(uint16_t)+sizeof(uint32_t);
char* tmpBuffer2 = new char[theBufferSize];
memcpy(&(tmpBuffer2[0]), &firstTag1, sizeof(uint16_t));
memcpy(&(tmpBuffer2[sizeof(uint16_t)]), &secondTag1, sizeof(uint16_t));
memcpy(&(tmpBuffer2[2*sizeof(uint16_t)]), &thirdTag1, sizeof(uint32_t));
//memcpy(&(tmpBuffer2[3*sizeof(uint16_t)]), &fourthTag1, sizeof(uint16_t));
gdcmm_assert( of && !of.eof() && of.good() );
of.write(tmpBuffer2, theBufferSize);
of.flush();
gdcmm_assert( of );

return 0;
}

```

12.67 Fake_Image_Using_Stream_Image_Writer.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcmm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
// This work was realised during the GSOC 2011 by Manoj Alwani

#include "gdcmmReader.h"
#include "gdcmmMediaStorage.h"
#include "gdcmmWriter.h"
#include "gdcmmItem.h"
#include "gdcmmImageReader.h"
#include "gdcmmAttribute.h"
#include "gdcmmFile.h"
#include "gdcmmTag.h"
#include "gdcmmTransferSyntax.h"
#include "gdcmmUIDGenerator.h"
#include "gdcmmAnonymizer.h"
#include "gdcmmStreamImageWriter.h"
#include "gdcmmImageHelper.h"
#include "gdcmmTrace.h"

int main(int, char *[])
{
    char * buffer = new char[ 256 * 256 * 3 ];
    // *p = (uint8_t*)buffer;
    char * p = buffer;

    gdcmm::Trace::DebugOn();
    gdcmm::Trace::WarningOn();

    for(int row = 0; row < 256; ++row)
    {
        for(int col = 0; col < 256; ++col)
            //for(int b = 0; b < 256; ++b)
            {
                *p++ = 255;
            }
    }
}

```

```

        *p++ = 0;
        *p++ = 0;
    }

    gdcm::Writer w;
    gdcm::File &file = w.GetFile();
    gdcm::DataSet &ds = file.GetDataSet();

    file.GetHeader().SetDataSetTransferSyntax( gdcm::TransferSyntax::ExplicitVRLittleEndian );

    gdcm::UIDGenerator uid;
    gdcm::DataElement de( gdcm::Tag(0x8,0x18) ); // SOP Instance UID
    de.SetVR( gdcm::VR::UI );
    const char *u = uid.Generate();
    de.SetByteValue( u, strlen(u) );
    ds.Insert( de );

    gdcm::DataElement del( gdcm::Tag(0x8,0x16) );
    del.SetVR( gdcm::VR::UI );
    gdcm::MediaStorage ms( gdcm::MediaStorage::VLWholeSlideMicroscopyImageStorage );
    del.SetByteValue( ms.GetString(), strlen(ms.GetString()) );
    ds.Insert( del );

    const char mystr[] = "RGB";
    gdcm::DataElement de2( gdcm::Tag(0x28,0x04) );
    //de.SetTag(gdcm::Tag(0x28,0x04));
    de2.SetVR( gdcm::VR::CS );
    de2.SetByteValue(mystr, strlen(mystr));
    ds.Insert( de2 );

    gdcm::Attribute<0x0028,0x0010> row = {256};
    //row.SetValue(512);
    ds.Insert( row.GetAsDataElement() );
    // w.SetCheckFileMetaInformation( true );
    gdcm::Attribute<0x0028,0x0011> col = {256};
    ds.Insert( col.GetAsDataElement() );

    gdcm::Attribute<0x0028,0x0008> Number_Of_Frames = {1};
    ds.Insert( Number_Of_Frames.GetAsDataElement() );

    gdcm::Attribute<0x0028,0x0100> at = {8};
    ds.Insert( at.GetAsDataElement() );

    gdcm::Attribute<0x0028,0x0002> at1 = {3}; //bits per pixel
    ds.Insert( at1.GetAsDataElement() );

    gdcm::Attribute<0x0028,0x0101> at2 = {8};
    ds.Insert( at2.GetAsDataElement() );

    gdcm::Attribute<0x0028,0x0102> at3 = {7};
    ds.Insert( at3.GetAsDataElement() );

    gdcm::Attribute<0x0028,0x0006> at4 = {0};
    ds.Insert( at4.GetAsDataElement() );

    gdcm::Attribute<0x0028,0x0103> at5 = {0};
    ds.Insert( at5.GetAsDataElement() );

    //de.SetTag(gdcm::Tag(0x7fe0,0x0010));
    //ds.Insert( de );

    gdcm::StreamImageWriter theStreamWriter;
    gdcm::SmartPointer<gdcm::SequenceOfItems> sq = new gdcm::SequenceOfItems();
    sq->SetLengthToUndefined();

    uint16_t row1 = 256;
    uint16_t col1 = 256;
    //std::cout << row;

    gdcm::Element<gdcm::VR::IS, gdcm::VM::VM1> el2;
    el2.SetValue(1);
    gdcm::DataElement rfn = el2.GetAsDataElement(); //rfn ---> reference frame number
    rfn.SetTag( gdcm::Tag(0x0008,0x1160) );

    gdcm::Element<gdcm::VR::US, gdcm::VM::VM2> el;
    el.SetValue(1,0);
    el.SetValue(1,1);
    gdcm::DataElement ulr = el.GetAsDataElement(); //ulr --> upper left col/row

```

```

    ulr.SetTag( gdcm::Tag(0x0048,0x0201) );

    gdcm::Element<gdcm::VR::US,gdcm::VM::VM2> e11;
    e11.SetValue(coll,0);
    e11.SetValue(row1,1);
    gdcm::DataElement brr = e11.GetAsDataElement();
    brr.SetTag( gdcm::Tag(0x0048,0x0202) );           //brr --> bottom right col/row

    gdcm::Item it;
    gdcm::DataSet &nds = it.GetNestedDataSet();
    nds.Insert( rfn );
    nds.Insert(ulr);
    nds.Insert(brr);

    sq->AddItem(it);

    gdcm::DataElement des( gdcm::Tag(0x0048,0x0200) );
    des.SetVR(gdcm::VR::SQ);
    des.SetValue(*sq);
    des.SetVLToUndefined();

    ds.Insert( des );

    theStreamWriter.SetFile(file);

    std::ofstream of;
    of.open( "output.dcm", std::ios::out | std::ios::binary );
    theStreamWriter.SetStream(of);

    if (!theStreamWriter.CanWriteFile()){
        delete [] buffer;
        std::cout << "Not able to write";
        return 0; //this means that the file was unwritable, period.
        //very similar to a ReadImageInformation failure
    }
    else
        std::cout<<"\nable to read";

    if (!theStreamWriter.WriteImageInformation()){
        std::cerr << "unable to write image information" << std::endl;
        delete [] buffer;
        return 1; //the CanWrite function should prevent getting here, else,
        //that's a test failure
    }

    std::vector<unsigned int> extent =
        gdcm::ImageHelper::GetDimensionsValue(file);

    unsigned short xmax = extent[0];
    unsigned short ymax = extent[1];
    unsigned short theChunkSize = 1;
    unsigned short ychunk = extent[1]/theChunkSize; //go in chunk sizes of theChunkSize
    unsigned short zmax = extent[2];

    std::cout << xmax << ymax << zmax;

    if (xmax == 0 || ymax == 0)
    {
        std::cerr << "Image has no size, unable to write zero-sized image." << std::endl;
        return 0;
    }

    int z, y, nexty;
    unsigned long prevLen = 0; //when going through the char buffer, make sure to grab
    //the bytes sequentially. So, store how far you got in the buffer with each iteration.
    for (z = 0; z < zmax; ++z){
        for (y = 0; y < ymax; y += ychunk){
            nexty = y + ychunk;
            if (nexty > ymax) nexty = ymax;
            theStreamWriter.DefinePixelExtent(0, xmax, y, nexty, z, z+1);
            unsigned long len = theStreamWriter.DefineProperBufferLength();
            std::cout << "\n" << len;
            char* finalBuffer = new char[len];
            memcpy(finalBuffer, &(buffer[prevLen]), len);
            std::cout << "\nable to write";
            if (!theStreamWriter.Write(finalBuffer, len)){
                std::cerr << "writing failure:" << "output.dcm" << " at y = " << y << " and z = " << z << std::endl;
                delete [] buffer;
                delete [] finalBuffer;
            }
        }
    }

```

```

        return 1;
    }
    delete [] finalBuffer;
    prevLen += len;
}
delete buffer;

uint16_t firstTag1 = 0xfffe;
uint16_t secondTag1 = 0xe0dd;
uint32_t thirdTag1 = 0x00000000;
//uint16_t fourthTag1 = 0xffff;
const int theBufferSize = 2*sizeof(uint16_t)+sizeof(uint32_t);
char* tmpBuffer2 = new char[theBufferSize];
memcpy(&(tmpBuffer2[0]), &firstTag1, sizeof(uint16_t));
memcpy(&(tmpBuffer2[sizeof(uint16_t)]), &secondTag1, sizeof(uint16_t));
memcpy(&(tmpBuffer2[2*sizeof(uint16_t)]), &thirdTag1, sizeof(uint32_t));
//memcpy(&(tmpBuffer2[3*sizeof(uint16_t)]), &fourthTag1, sizeof(uint16_t));
gdcM_assert( of && !of.eof() && of.good() );
of.write(tmpBuffer2, theBufferSize);
of.flush();
gdcM_assert( of );

return 0;
}

```

12.68 FixBrokenJ2K.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcM.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
#include "gdcMReader.h"
#include "gdcMWriter.h"
#include "gdcMImageReader.h"
#include "gdcMSequenceOfFragments.h"
#include "gdcMFile.h"

// http://www.lost.in.ua/dicom/c.dcm
//
// -> BuggyJ2Kvvvua-fixed2-j2k.dcm

/*
 * This program attempts to fix a broken J2K/DICOM:
 * It contains 2 bugs:
 * 1. The first 8 bytes seems to be random bytes: remove them
 * 2. YCC is set to 1, while image is grayscale need to set it back to 0
 *
 * Ref:
 * It's a software from http://rentgenprom.ru/ , shipped with universal digital radiographic units
 * "ProScan-2000". The Ukrainian manufacturer developed own digital radiographic unit and it is
 * compatible with software from "ProScan-2000".
 * Information found in DICOM file is:
 *
 * (0008,0070) LO [ZAO "Renthenprom" (JSC Rentgenprom) ]          # 36,1 Manufacturer
 * (0018,1020) LO [2.13.1.7]                                       # 8,1-n Software Version(s)
 *
 */
int main(int argc, char *argv[])
{
    if( argc < 3 )
    {
        std::cerr << argv[0] << " input.dcm output.dcm" << std::endl;
        return 1;
    }
    const char *filename = argv[1];

```



```

const char *outfilename = argv[2];
gdcm::Reader reader;
reader.SetFileName( filename );
if( !reader.Read() )
{
    return 1;
}

gdcm::File &file = reader.GetFile();
const gdcm::DataElement &pixeldata0 = file.GetDataSet().GetDataElement( gdcm::Tag(0x7fe0,0x0010) );
const gdcm::SequenceOfFragments *sqf = pixeldata0.GetSequenceOfFragments();
if( !sqf )
{
    return 1;
}
const gdcm::Fragment &frag0 = sqf->GetFragment(0);

gdcm::ByteValue *bv = const_cast<gdcm::ByteValue*>(frag0.GetByteValue());
char *ptr = (char*)bv->GetVoidPointer();
size_t len = bv->GetLength();

static const unsigned char sig[] = {0,0,0,0,0x6A,0x70,0x32,0x63};
if( memcmp(ptr, sig, sizeof(sig)) != 0 )
{
    std::cerr << "magic random signature not found" << std::endl;
    return 1;
}

// Apparently the flag to enable a color transform on 3 color components is set in
// the COD marker. (YCC is byte[6] in the COD marker)
// we need to disable this flag;
char *cod_marker = ptr + 0x35; /* 0x2d + 0x8 */ // FIXME
if( cod_marker[0] == (char)0xff && cod_marker[1] == 0x52 )
{
    // found start of COD
    if( cod_marker[6+2] == 1 )
    {
        // Change in place:
        *((char*)cod_marker + 6+2) = 0;
        // Prepare a new DataElement:
        gdcm::DataElement pixeldata( gdcm::Tag(0x7fe0,0x0010) );
        pixeldata.SetVR( gdcm::VR::OB );
        gdcm::SmartPointer<gdcm::SequenceOfFragments> sq = new gdcm::SequenceOfFragments;

        gdcm::Fragment frag;
        // remove 8 first bytes:
        frag.SetByteValue( ptr + 8, (uint32_t)(len - 8) );
        sq->AddFragment( frag );
        pixeldata.SetValue( *sq );
        file.GetDataSet().Replace( pixeldata );
    }
    else
    {
        return 1;
    }
}
else
{
    std::cerr << "COD not found" << (int)cod_marker[0] << std::endl;
    return 1;
}

gdcm::Writer writer;
writer.SetFile( reader.GetFile() );
writer.SetFileName( outfile );
writer.CheckFileMetaInformationOff();
if( !writer.Write() )
{
    std::cerr << "Could not write" << std::endl;
}

// paranoid check:
gdcm::ImageReader ireader;
ireader.SetFileName( outfile );
if( !ireader.Read() )
{
    std::cerr << "file written is still not valid, please report" << std::endl;
    return 1;
}

```

```

    }

    return 0;
}

```

12.69 FixJAIBugJPEGLS.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcml.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.
=====*/
#include "gdcmlReader.h"
#include "gdcmlWriter.h"
#include "gdcmlImageReader.h"

#include <fstream>

#include "gdcml_charls.h"

/*
 * This small example should show how one can handle the famous JAI-JPEGLS bug
 * It will take in as invalid DICOM/JAI-JPEG-LS and write out as Explicit Little
 * Endian. One can use `gdcmlconv --jpegls` to recompress properly
 *
 * References:
 * http://charls.codeplex.com/discussions/230307?ProjectName=charls
 * http://charls.codeplex.com/workitem/7297
 * http://www.dcm4che.org/jira/browse/DCM-442
 * http://www.dcm4che.org/jira/browse/DCMEE-1144
 * http://java.net/jira/browse/JAI_IMAGEIO_CORE-183
 *
 * Explanation of the issue:
 *
 * Seems, the error is in the calculation of the default values for thresholds T1,
 * T2, T3, in particular min(MAXVAL, 4095) is not applied in
 *
 * FACTOR = (min(MAXVAL, 4095) + 128)/256
 *
 * as specified in http://www.itu.int/rec/T-REC-T.87-199806-I/en .
 */
int main(int argc, char *argv[])
{
    if( argc < 3 )
    {
        std::cerr << argv[0] << " input.dcm output.dcm" << std::endl;
        return 1;
    }
    const char *filename = argv[1];
    const char *outfilename = argv[2];
    gdcml::FileMetaInformation::SetSourceApplicationEntityTitle( "FixJAIBugJPEGLS" );

    gdcml::ImageReader reader;
    reader.SetFileName( filename );
    if( !reader.Read() )
    {
        return 1;
    }

    gdcml::Image &image = reader.GetImage();
    //unsigned long len = image.GetBufferLength();
    const gdcml::DataElement &in =
        reader.GetFile().GetDataSet().GetDataElement( gdcml::Tag(0x7fe0,0x0010) );
    const gdcml::SequenceOfFragments *sf = in.GetSequenceOfFragments();
    if( !sf )
    {

```

```

        std::cerr << "No pixel data (or not encapsulated)" << std::endl;
        return 1;
    }
    const unsigned int *dims = image.GetDimensions();
    if ( sf->GetNumberOfFragments() != dims[2] )
    {
        std::cerr << "Unsupported" << std::endl;
        return 1;
    }

// unsigned long totalLen = sf->ComputeByteLength();
std::vector<unsigned char> rgbyteOutall;
for(unsigned int i = 0; i < sf->GetNumberOfFragments(); ++i)
{
    const gdcm::Fragment &frag = sf->GetFragment(i);
    if( frag.IsEmpty() ) return 1;
    const gdcm::ByteValue *bv = frag.GetByteValue();
    if( !bv ) return 1;
    unsigned long totalLen = bv->GetLength();

    std::vector<char> vbuffer;
    vbuffer.resize( totalLen );
    char *buffer = vbuffer.data();
    bv->GetBuffer(buffer, totalLen);
    const unsigned char* pbyteCompressed0 = (const unsigned char*)buffer;
    while( totalLen > 0 && pbyteCompressed0[totalLen-1] != 0xd9 )
    {
        totalLen--;
    }

    JlsParameters metadata;
    char errorMsg[256+1]={'\0'};
    if (JpegLsReadHeader(buffer, totalLen, &metadata, errorMsg) != charls::ApiResult::OK)
    {
        std::cerr << "Can't parse jpegls: " << errorMsg << std::endl;
        return 1;
    }

    std::cout << metadata.width << std::endl;
    std::cout << metadata.height << std::endl;
    std::cout << metadata.bitsPerSample << std::endl;

    gdcm::PixelFormat const & pf = image.GetPixelFormat();
    std::cout << pf << std::endl;

    // http://charls.codeplex.com/discussions/230307?ProjectName=charls
    unsigned char marker_lse_13[] = {
        0xFF, 0xF8, 0x00, 0x0D,
        0x01,
        0x1F, 0xFF,
        0x00, 0x22, // T1 = 34
        0x00, 0x83, // T2 = 131
        0x02, 0x24, // T3 = 548
        0x00, 0x40
    };

    unsigned char marker_lse_14[] = {
        0xFF, 0xF8, 0x00, 0x0D,
        0x01,
        0x3F, 0xFF,
        0x00, 0x42, // T1 = 66
        0x01, 0x03, // T2 = 259
        0x04, 0x44, // T3 = 1092
        0x00, 0x40
    };

    unsigned char marker_lse_15[] = {
        0xFF, 0xF8, 0x00, 0x0D,
        0x01,
        0x7F, 0xFF,
        0x00, 0x82, // T1 = 130
        0x02, 0x03, // T2 = 515
        0x08, 0x84, // T3 = 2180
        0x00, 0x40
    };

    unsigned char marker_lse_16[] = {
        0xFF, 0xF8, 0x00, 0x0D,
        0x01,
        0xFF, 0xFF,
        0x01, 0x02, // T1 = 258
    };

```

```

    0x04, 0x03, // T2 = 1027
    0x11, 0x04, // T3 = 4356
    0x00, 0x40
};

const unsigned char *marker_lse = nullptr;
switch( metadata.bitsPerSample )
{
case 13:
    marker_lse = marker_lse_13;
    break;
case 14:
    marker_lse = marker_lse_14;
    break;
case 15:
    marker_lse = marker_lse_15;
    break;
case 16:
    marker_lse = marker_lse_16;
    break;
}
if( !marker_lse )
{
    std::cerr << "Can't handle: " << metadata.bitsPerSample << std::endl;
    return 1;
}

// FIXME: One should recompute the value for 0x0F
vbuffer.insert( vbuffer.begin() + 0x0F, marker_lse, marker_lse+15);

#if 0
    std::ofstream of( "/tmp/d.jls", std::ios::binary );
    of.write( &vbuffer[0], vbuffer.size() );
    of.close();
#endif

const char *pbyteCompressed = vbuffer.data();
size_t cbyteCompressed = vbuffer.size(); // updated length

JlsParameters params;
JpegLsReadHeader( pbyteCompressed, cbyteCompressed, &params, nullptr);

std::vector<unsigned char> rgbyteOut;
//rgbyteOut.resize( image.GetBufferLength() );
rgbyteOut.resize( params.height * params.width * ((params.bitsPerSample + 7)
    / 8) * params.components);

CharlsApiResultType result =
    JpegLsDecode( rgbyteOut.data(), rgbyteOut.size(), pbyteCompressed, cbyteCompressed, &params, errorMsg );
if (result != charls::ApiResult::OK)
{
    std::cerr << "Could not patch JAI-JPEGLS: " << errorMsg << std::endl;
    return 1;
}
rgbyteOutall.insert( rgbyteOutall.end(), rgbyteOut.begin(), rgbyteOut.end() );
}

gdcm::DataElement pixeldata( gdcm::Tag(0x7fe0,0x0010) );
pixeldata.SetVR( gdcm::VR::OW );
pixeldata.SetByteValue( (char*)rgbyteOutall.data(), (uint32_t)rgbyteOutall.size() );

// Add the pixel data element
reader.GetFile().GetDataSet().Replace( pixeldata );
reader.GetFile().GetHeader().SetDataSetTransferSyntax(
    gdcm::TransferSyntax::ExplicitVRLittleEndian);

gdcm::Writer writer;
writer.SetFileName( outfilename );
writer.SetFile( reader.GetFile() );
writer.Write();

std::cout << "Success !" << std::endl;

return 0;
}

```

12.70 FixOrientation.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.
=====*/
#include "gdcmReader.h"
#include "gdcmWriter.h"
#include "gdcmFile.h"
#include "gdcmOrientation.h"
#include "gdcmAttribute.h"

// Very simple orientation changer, fix invalid dataset
int main(int argc, char* argv[] )
{
    // assume AXIAL input for now
    if( argc < 3 )
    {
        std::cerr << argv[0] << " input.dcm output.dcm" << std::endl;
        return 1;
    }
    const char *filename = argv[1];
    const char *outfilename = argv[2];

    gdcm::Reader reader;
    reader.SetFileName( filename );
    if (! reader.Read() )
    {
        return 1;
    }

    const double axial[] = { 1,0,0, 0,1,0 };
    (void)axial;
    const double coronal[] = { 0,0,1, 1,0,0 };
    (void)coronal;
    const double sagittal[] = { 0,1,0, 0,0,1 };
    (void)sagittal;
    gdcm::Attribute<0x0020,0x0032> at1; // IPP
    (void)at1;
    gdcm::Attribute<0x0020,0x0037> at2; // IOP
    (void)at2;

    gdcm::File & f = reader.GetFile();
    gdcm::DataSet & ds = f.GetDataSet();
    at1.SetFromDataSet( ds );
#ifdef 0
    at2.SetFromDataSet( ds );
    const double * iop = at2.GetValues();
    if( !std::equal(iop, iop + 6, axial) )
    {
        gdcm::Orientation::OrientationType type = gdcm::Orientation::GetType ( iop );
        std::cerr << "Wrong orientation: " << gdcm::Orientation::GetLabel( type ) << std::endl;
        return 1;
    }
    at2.SetValues( sagittal );
    ds.Replace( at2.GetAsDataElement() );
#endif

    // for sagittal: swap element 0 & 2
    const double tmp0 = at1.GetValue(0);
    const double tmp2 = at1.GetValue(2);
    (void)tmp2;
    //at1.SetValue(tmp2, 0);
    //at1.SetValue(tmp0, 2);
    at1.SetValue( - tmp0 );
    ds.Replace( at1.GetAsDataElement() );

    gdcm::Writer writer;
    writer.SetFile( f );
    writer.SetFileName( outfile );
    if ( !writer.Write() )

```

```

    {
        return 1;
    }

    return 0;
}

```

12.71 GenAllVR.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
#include "gdcmReader.h"
#include "gdcmGlobal.h"
#include "gdcmDummyValueGenerator.h"
#include "gdcmMediaStorage.h"
#include "gdcmWriter.h"
#include "gdcmItem.h"
#include "gdcmImageReader.h"
#include "gdcmSequenceOfItems.h"
#include "gdcmFile.h"
#include "gdcmTag.h"
#include "gdcmDict.h"
#include "gdcmDictEntry.h"
#include "gdcmDicts.h"
#include "gdcmTransferSyntax.h"
#include "gdcmUIDGenerator.h"
#include "gdcmFileExplicitFilter.h"

#include <cstdlib>
#include <cstring>

gdcm::Tag FindTagFromVR(gdcm::Dict const &dict, gdcm::VR const &vr)
{
    using gdcm::Dict;
    Dict::ConstIterator beg = dict.Begin();
    Dict::ConstIterator end = dict.End();
    Dict::ConstIterator it;
    for( it = beg; it != end; ++it)
    {
        const gdcm::Tag &t = it->first;
        const gdcm::DictEntry &de = it->second;
        const gdcm::VR &vr_de = de.GetVR();
        if( vr == vr_de && !de.GetRetired() && t.GetGroup() >= 0x8 )
        {
            return t;
        }
    }
    return gdcm::Tag(0xffff,0xffff);
}

struct rnd_gen {
    rnd_gen(char const* r = "abcdefghijklmnopqrstuvwxyz0123456789")
        : range(r, len(std::strlen(r))) { }

    char operator ()() const {
        return range[static_cast<std::size_t>(std::rand() * (1.0 / ((double)RAND_MAX + 1.0)) * (double)len)];
    }
private:
    char const* range;
    std::size_t len;
};

/*
*/

```

```

int main(int argc, char *argv[])
{
    if( argc < 2 )
    {
        std::cerr << argv[0] << " output.dcm" << std::endl;
        return 1;
    }
    const char *outfilename = argv[1];
    static const gdcm::Global &g = gdcm::Global::GetInstance();
    static const gdcm::Dicts &dicts = g.GetDicts();
    static const gdcm::Dict &pubdict = dicts.GetPublicDict();
    using gdcm::VR;
    using gdcm::Tag;

    gdcm::Writer w;

    gdcm::File &f = w.GetFile();
    gdcm::DataSet &ds = f.GetDataSet();

    gdcm::FileExplicitFilter fef;
    //fef.SetChangePrivateTags( true );
    fef.SetFile( w.GetFile() );
    if( !fef.Change() )
    {
        std::cerr << "Failed to change" << std::endl;
        return 1;
    }

    gdcm::SmartPointer<gdcm::SequenceOfItems> sq = new gdcm::SequenceOfItems();
    sq->SetLengthToUndefined();

    // gdcm::DummyValueGenerator dv;

    const std::size_t len = 10;
    char ss[len+1];
    ss[len] = '\0';

    const char owner_str[] = "GDCM CONFORMANCE TESTS";
    gdcm::DataElement owner( gdcm::Tag(0x4d4d, 0x10) );
    owner.SetByteValue(owner_str, (uint32_t)strlen(owner_str));
    owner.SetVR( gdcm::VR::LO );

    // Create an item
    gdcm::Item it;
    it.SetVLToUndefined();
    gdcm::DataSet &nds = it.GetNestedDataSet();
    // nds.Insert(owner);
    // nds.Insert(de);

    // Insert sequence into data set
    gdcm::DataElement des( gdcm::Tag(0x4d4d, 0x1001) );
    des.SetVR(gdcm::VR::SQ);
    des.SetValue(*sq);
    des.SetVLToUndefined();

    ds.Insert(owner);
    ds.Insert(des);

    // avoid INVALID = 0
    for(int i = 1; i < 27; ++i)
    {
        VR vr = (VR::VRType)(1LL << i);
        Tag t = FindTagFromVR( pubdict, vr );
        if( vr != VR::UN && vr != VR::SQ )
        {
            gdcm_assert( t != Tag(0xffff, 0xffff) );
            gdcm::DataElement de( t );
            std::generate_n(ss, len, rnd_gen());
            de.SetVR( vr );
            de.SetByteValue( ss, (uint32_t)std::strlen( ss ) );
            nds.Insert( de );
        }
    }
    sq->AddItem(it);

    // Make sure to override any UID stuff
    gdcm::UIDGenerator uid;
    gdcm::DataElement de( Tag(0x8, 0x18) ); // SOP Instance UID
    de.SetVR( VR::UI );
    const char *u = uid.Generate();
    de.SetByteValue( u, (uint32_t)strlen(u) );

```

```

ds.Insert( de );

de.SetTag( Tag(0x8,0x16) ); // SOP Class UID
de.SetVR( VR::UI );
gdcm::MediaStorage ms( gdcm::MediaStorage::RawDataStorage );
de.SetByteValue( ms.GetString(), (uint32_t)strlen(ms.GetString()));
ds.Insert( de );

gdcm::FileMetaInformation &fmi = f.GetHeader();
//fmi.SetDataSetTransferSyntax( gdcm::TransferSyntax::ImplicitVRLittleEndian );
fmi.SetDataSetTransferSyntax( gdcm::TransferSyntax::ExplicitVRLittleEndian );

w.SetCheckFileMetaInformation( true );
w.SetFileName( outfilename );
if ( !w.Write() )
{
    return 1;
}

return 0;
}

```

12.72 GenFakeIdentifyFile.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
#include "gdcmReader.h"
#include "gdcmGlobal.h"
#include "gdcmDummyValueGenerator.h"
#include "gdcmMediaStorage.h"
#include "gdcmWriter.h"
#include "gdcmItem.h"
#include "gdcmImageReader.h"
#include "gdcmSequenceOfItems.h"
#include "gdcmAttribute.h"
#include "gdcmFile.h"
#include "gdcmTag.h"
#include "gdcmDict.h"
#include "gdcmDictEntry.h"
#include "gdcmDicts.h"
#include "gdcmTransferSyntax.h"
#include "gdcmUIDGenerator.h"
#include "gdcmAnonymizer.h"

#include <cstdlib>
#include <cstring>

gdcm::DataElement CreateFakeElement(gdcm::Tag const &tag, bool toremove)
{
    static const gdcm::Global &g = gdcm::Global::GetInstance();
    static const gdcm::Dicts &dicts = g.GetDicts();
    static const gdcm::Dict &pubdict = dicts.GetPublicDict();
    static size_t countglobal = 0;
    static std::vector<gdcm::Tag> balcptags =
        gdcm::Anonymizer::GetBasicApplicationLevelConfidentialityProfileAttributes();
    size_t count = countglobal % balcptags.size();

    const gdcm::DictEntry &dictentry = pubdict.GetDictEntry(tag);

    gdcm::DataElement de;
    de.SetTag( tag );
    using gdcm::VR;
    const VR &vr = dictentry.GetVR();
    //if( vr != VR::INVALID )
    if( vr.IsDual() )

```



```

{
    if( vr == VR::US_SS )
    {
        de.SetVR( VR::US );
    }
    else if( vr == VR::US_SS_OW )
    {
        de.SetVR( VR::OW );
    }
    else if( vr == VR::OB_OW )
    {
        de.SetVR( VR::OB );
    }
}
else
{
    de.SetVR( vr );
}
const char str[] = "BasicApplicationLevelConfidentialityProfileAttributes";
const char safe[] = "This is safe to keep";
if( de.GetVR() != VR::SQ )
{
    if( toremove )
        de.SetByteValue( str, (uint32_t)strlen(str) );
    else
        de.SetByteValue( safe, (uint32_t)strlen(safe) );
}
else
{
    // Create an item
    gdcmm::Item it;
    it.SetVLToUndefined();
    gdcmm::DataSet &nds = it.GetNestedDataSet();
    // Insert sequence into data set
    gdcmm::assert( de.GetVR() == gdcmm::VR::SQ );
    gdcmm::SmartPointer<gdcmm::SequenceOfItems> sq = new gdcmm::SequenceOfItems();
    sq->SetLengthToUndefined();
    de.SetValue(*sq);
    de.SetVLToUndefined();
    //ds.Insert( de );

    if( !toremove )
    {
        nds.Insert( CreateFakeElement( balcptags[count], true ) );
        countglobal++;
    }
    else
    {
        gdcmm::Attribute<0x0008,0x0000> at1 = { 0 }; // This element has no reason to be 'anonymized'...
        nds.Insert( at1.GetAsDataElement() );
        gdcmm::Attribute<0x000a,0x0000> at2 = { 0 };
        nds.Insert( at2.GetAsDataElement() );
    }
    sq->AddItem(it);
}
return de;
}

/*
*/
int main(int argc, char *argv[])
{
    if( argc < 2 )
    {
        std::cerr << argv[0] << " output.dcm" << std::endl;
        return 1;
    }
    using gdcmm::Tag;
    using gdcmm::VR;
    const char *outfilename = argv[1];

    std::vector<gdcmm::Tag> balcptags =
        gdcmm::Anonymizer::GetBasicApplicationLevelConfidentialityProfileAttributes();

    gdcmm::Writer w;
    gdcmm::File &f = w.GetFile();
    gdcmm::DataSet &ds = f.GetDataSet();

    // Add attribute that need to be anonymized:
    std::vector<gdcmm::Tag>::const_iterator it = balcptags.begin();
    for( ; it != balcptags.end(); ++it)

```

```

    {
        ds.Insert( CreateFakeElement( *it, true ) );
    }

    // Add attribute that do NOT need to be anonymized:
    static const gdcm::Global &g = gdcm::Global::GetInstance();
    static const gdcm::Dicts &dicts = g.GetDicts();
    static const gdcm::Dict &pubdict = dicts.GetPublicDict();

    using gdcm::Dict;
    Dict::ConstIterator dictit = pubdict.Begin();
    for(; dictit != pubdict.End(); ++dictit)
    {
        const gdcm::Tag &dicttag = dictit->first;
        if( dicttag == Tag(0x6e65,0x6146) ) break;
        //const gdcm::DictEntry &dictentry = dictit->second;
        ds.Insert( CreateFakeElement( dicttag, false ) );
    }
    ds.Remove( gdcm::Tag(0x400,0x500) );
    ds.Remove( gdcm::Tag(0x12,0x62) );
    ds.Remove( gdcm::Tag(0x12,0x63) );

    // Make sure to override any UID stuff
    gdcm::UIDGenerator uid;
    gdcm::DataElement de( Tag(0x8,0x18) ); // SOP Instance UID
    de.SetVR( VR::UI );
    const char *u = uid.Generate();
    de.SetByteValue( u, (uint32_t)strlen(u) );
    //ds.Insert( de );
    ds.Replace( de );

    de.SetTag( Tag(0x8,0x16) ); // SOP Class UID
    de.SetVR( VR::UI );
    gdcm::MediaStorage ms( gdcm::MediaStorage::RawDataStorage );
    de.SetByteValue( ms.GetString(), (uint32_t)strlen(ms.GetString()) );
    ds.Replace( de ); // replace !

    gdcm::FileMetaInformation &fmi = f.GetHeader();
    //fmi.SetDataSetTransferSyntax( gdcm::TransferSyntax::ImplicitVRLittleEndian );
    fmi.SetDataSetTransferSyntax( gdcm::TransferSyntax::ExplicitVRLittleEndian );

    w.SetCheckFileMetaInformation( true );
    w.SetFileName( outfilename );
    if ( !w.Write() )
    {
        return 1;
    }

    return 0;
}

```

12.73 GenLongSeqs.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
#include "gdcmReader.h"
#include "gdcmWriter.h"
#include "gdcmItem.h"
#include "gdcmImageReader.h"
#include "gdcmSequenceOfItems.h"
#include "gdcmFile.h"
#include "gdcmTag.h"

/*
 * This example is used to generate the file:

```

```

*
*
* There is a flaw in the DICOM design were it is assumed that Sequence can be
* either represented as undefined length or defined length. This should work
* in most case, but the undefined length is a little more general and can
* store sequence of items that a defined length cannot.
* We need to make sure that we can store numerous Item in a SQ
*
* Warning: do not try to compute the group length elements !
* Warning: You may need a 64bits machine for this example to work.
*/
int main(int argc, char *argv[])
{
    if( argc < 3 )
    {
        std::cerr << argv[0] << " input.dcm output.dcm" << std::endl;
        return 1;
    }
    const char *filename = argv[1];
    const char *outfilename = argv[2];
    gdcm::Reader reader;
    reader.SetFileName( filename );
    if( !reader.Read() )
    {
        return 1;
    }

    gdcm::File &file = reader.GetFile();
    gdcm::DataSet &ds = file.GetDataSet();

    // Create a Sequence
    gdcm::SmartPointer<gdcm::SequenceOfItems> sq = new gdcm::SequenceOfItems();
    sq->SetLengthToUndefined();

    const char owner_str[] = "GDCM CONFORMANCE TESTS";
    gdcm::DataElement owner( gdcm::Tag(0x4d4d, 0x10) );
    owner.SetByteValue(owner_str, (uint32_t)strlen(owner_str));
    owner.SetVR( gdcm::VR::LO );

    size_t nitems = 1000;
    nitems += std::numeric_limits<uint32_t>::max();
    for(unsigned int idx = 0; idx < nitems; ++idx)
    {
        // Create a dataelement
        //gdcm::DataElement de( gdcm::Tag(0x4d4d, 0x1002) );
        //de.SetByteValue(ptr, ptr_len);
        //de.SetVR( gdcm::VR::OB );

        // Create an item
        gdcm::Item it;
        it.SetVLToUndefined();
        //gdcm::DataSet &nds = it.GetNestedDataSet();
        //nds.Insert(owner);
        //nds.Insert(de);

        sq->AddItem(it);
    }

    // Insert sequence into data set
    gdcm::DataElement des( gdcm::Tag(0x4d4d, 0x1001) );
    des.SetVR(gdcm::VR::SQ);
    des.SetValue(*sq);
    des.SetVLToUndefined();

    ds.Insert(owner);
    ds.Insert(des);

    gdcm::Writer w;
    w.SetFile( file );
    //w.SetCheckFileMetaInformation( true );
    w.SetFileName( outfile );
    if( !w.Write() )
    {
        return 1;
    }

    return 0;
}

```

12.74 GenSeqs.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
#include "gdcmReader.h"
#include "gdcmWriter.h"
#include "gdcmItem.h"
#include "gdcmImageReader.h"
#include "gdcmSequenceOfItems.h"
#include "gdcmFile.h"
#include "gdcmTag.h"

/*
 * This example is used to generate the file:
 *
 * gdcmConformanceTests/SequenceWithUndefinedLengthNotConvertibleToDefinedLength.dcm
 *
 * There is a flaw in the DICOM design where it is assumed that Sequence can be
 * either represented as undefined length or defined length. This should work
 * in most cases, but the undefined length is a little more general and can
 * store sequence of items that a defined length cannot.
 * Deflated syntax was used in this case since this synthetic example can be
 * nicely compressed using this transfer syntax.
 *
 * Warning: do not try to compute the group length elements !
 * Warning: You may need a 64bits machine for this example to work.
 */
int main(int argc, char *argv[])
{
    if( argc < 3 )
    {
        std::cerr << argv[0] << " input.dcm output.dcm" << std::endl;
        return 1;
    }
    const char *filename = argv[1];
    const char *outfilename = argv[2];
    gdcm::Reader reader;
    reader.SetFileName( filename );
    if( !reader.Read() )
    {
        return 1;
    }

    gdcm::File &file = reader.GetFile();
    gdcm::DataSet &ds = file.GetDataSet();

    //const unsigned int nitems = 1000;
    const unsigned int ptr_len = 42; /*94967296 / nitems; */
    //gdcm_assert( ptr_len == 42949672 );
    char *ptr = new char[ptr_len];
    memset(ptr,0,ptr_len);

    // Create a Sequence
    gdcm::SmartPointer<gdcm::SequenceOfItems> sq = new gdcm::SequenceOfItems();
    sq->SetLengthToUndefined();

    const char owner_str[] = "GDCM CONFORMANCE TESTS";
    gdcm::DataElement owner( gdcm::Tag(0x4d4d, 0x10) );
    owner.SetByteValue(owner_str, (uint32_t)strlen(owner_str));
    owner.SetVR( gdcm::VR::LO );

    for(unsigned int idx = 0; idx < 10/* nitems*/; ++idx)
    {
        // Create a dataelement
        gdcm::DataElement de( gdcm::Tag(0x4d4d, 0x1002) );
        de.SetByteValue(ptr, ptr_len);
        de.SetVR( gdcm::VR::OB );

        // Create an item

```

```

    gdcm::Item it;
    it.SetVLToUndefined();
    gdcm::DataSet &nds = it.GetNestedDataSet();
    nds.Insert(owner);
    nds.Insert(de);

    sq->AddItem(it);
}

// Insert sequence into data set
gdcm::DataElement des( gdcm::Tag(0x4d4d,0x1001) );
des.SetVR(gdcm::VR::SQ);
des.SetValue(*sq);
des.SetVLToUndefined();

ds.Insert(owner);
ds.Insert(des);

gdcm::Writer w;
w.SetFile( file );
//w.SetCheckFileMetaInformation( true );
w.SetFileName( outfilename );
if (!w.Write() )
{
    return 1;
}

return 0;
}

```

12.75 GenerateStandardSOPClasses.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
/*
*/

#include "gdcmDefs.h"
#include "gdcmUIDs.h"
#include "gdcmGlobal.h"
#include "gdcmMediaStorage.h"
#include "gdcmSOPClassUIDToIOD.h"

int main(int , char *[])
{
    using gdcm::MediaStorage;
    gdcm::Global& g = gdcm::Global::GetInstance();
    if( !g.LoadResourcesFiles() )
    {
        std::cerr << "Could not LoadResourcesFiles" << std::endl;
        return 1;
    }

    const gdcm::Defs &defs = g.GetDefs();

    int ret = 0;

    //std::cout << "Table B.5-1 STANDARD SOP CLASSES" << std::endl;
    std::cout << "SOP Class Name,SOP Class UID,IOD Specification (defined in PS 3.3)" << std::endl;

    gdcm::MediaStorage::MSType mst;
    for ( mst = gdcm::MediaStorage::MediaStorageDirectoryStorage; mst < gdcm::MediaStorage::MS_END;
          mst = (gdcm::MediaStorage::MSType)(mst + 1) )
    {

```

```

const char *iod = defs.GetIODNameFromMediaStorage(mst);
gdc::UIDs uid;
uid.SetFromUID( gdc::MediaStorage::GetMSString(mst) /*mst.GetString()*/ );
if( iod )
{
    const char *iod_ref = gdc::SOPClassUIDToIOD::GetIOD(uid);
    if( iod_ref )
    {
        std::string iod_ref_str = iod_ref;
        //iod_ref_str += " IOD Modules";
        //if( iod_ref_str != iod )
        {
            //std::cout << "UID: " << uid << " ";
            std::cout << "'" << uid.GetName() << "' << ", " << "'" << uid.GetString() << "' << ", " << "'" << iod << "' <<
            std::endl;
            //std::cout << "Incompatible IODs: [" << iod << "] versus ref= [" << iod_ref_str << "]" << std::endl;
            ++ret;
        }
    }
}
}

return 0;
}

```

12.76 GetJPEGSamplePrecision.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
/*
 * This example is a little helper to detect the famous SIEMENS JPEG lossless compressed image
 * where DICOM is declared as:
 *
 * (0028,0100) US 16                                # 2,1 Bits Allocated
 * (0028,0101) US 12                                # 2,1 Bits Stored
 * (0028,0102) US 11                                # 2,1 High Bit
 * (0028,0103) US 0                                  # 2,1 Pixel Representation
 *
 * But where JPEG is:
 *
 *     JPEG_SOF_Parameters:
 *         SamplePrecision = 16
 *         nLines = 192
 *         nSamplesPerLine = 192
 *         nComponentsInFrame = 1
 *         component 0
 *             ComponentIdentifier = 1
 *             HorizontalSamplingFactor = 1
 *             VerticalSamplingFactor = 1
 *             QuantizationTableDestinationSelector = 0
 *
 * This case is valid. One simply has to use the 16bits jpeg decoder to decode the 12bits stored image.
 * This used to be an issue in GDCM 1.2.x (fixed in GDCM 1.2.5)
 *
 * The main return 0 (no error) when the file read is actually a potential problem. At the end of the main
 * function, the jpeg stream is stored in the filename specified as second argument
 */

#include "gdcmImageReader.h"
#include "gdcmSequenceOfFragments.h"
#include "gdcmJPEGCodec.h"

#include <iostream>

```

```

#include <fstream>

int main(int argc, char *argv[])
{
    if( argc < 3 )
    {
        std::cerr << argv[0] << " input.dcm output.jpg" << std::endl;
        return 1;
    }
    const char *filename = argv[1];
    const char *outfilename = argv[2];

    gdcm::ImageReader reader;
    reader.SetFileName( filename );
    if( !reader.Read() )
    {
        std::cerr << "Could not read: " << filename << std::endl;
        return 1;
    }

    // The output of gdcm::Reader is a gdcm::File
    const gdcm::File &file = reader.GetFile();
    const gdcm::Image &image = reader.GetImage();

    const gdcm::TransferSyntax &ts = file.GetHeader().GetDataSetTransferSyntax();

    if( ts != gdcm::TransferSyntax::JPEGLosslessProcess14 && ts != gdcm::TransferSyntax::JPEGLosslessProcess14_1 )
    {
        std::cerr << "Input is not a lossless JPEG" << std::endl;
        return 1;
    }

    // the dataset is the the set of element we are interested in:
    const gdcm::DataSet &ds = file.GetDataSet();

    const gdcm::Tag rawTag(0x7fe0, 0x0010); // Default to Pixel Data
    const gdcm::DataElement& pdde = ds.GetDataElement( rawTag );
    const gdcm::SequenceOfFragments *sf = pdde.GetSequenceOfFragments();
    if( sf )
    {
        std::ofstream output(outfilename, std::ios::binary);
        sf->WriteBuffer(output);
    }
    else
    {
        std::cerr << "Error" << std::endl;
        return 1;
    }

    gdcm::JPEGCodec jpeg;
    std::ifstream is(outfilename, std::ios::binary);
    gdcm::PixelFormat pf ( gdcm::PixelFormat::UINT8 ); // let's pretend it's a 8bits jpeg
    jpeg.SetPixelFormat( pf );
    gdcm::TransferSyntax ts_jpg;
    bool b = jpeg.GetHeaderInfo( is, ts_jpg );
    if( !b )
    {
        return 1;
    }

    //jpeg.Print( std::cout );
    if( jpeg.GetPixelFormat().GetBitsAllocated() != image.GetPixelFormat().GetBitsAllocated()
    || jpeg.GetPixelFormat().GetBitsStored() != image.GetPixelFormat().GetBitsStored() )
    {
        std::cerr << "There is a mismatch in between DICOM declared Pixel Format and Sample Precision used in the
        JPEG stream" << std::endl;
        return 0;
    }

    std::cout << jpeg.GetPixelFormat() << std::endl;
    std::cout << image.GetPixelFormat() << std::endl;

    return 1;
}

```

12.77 GetSequenceUltrasound.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
#include "gdcmReader.h"
#include "gdcmAttribute.h"

bool Region ( char* nomefile, unsigned int* X_min, unsigned int* Y_min, unsigned int* X_max, unsigned int* Y_max
);

int main(int argc, char* argv[] )
{
    // Controllo del numero di argomenti introdotti da riga di comando
    if( argc < 2 )
    {
        std::cerr << "Usage: " << std::endl;
        std::cerr << argv[0] << " inputImageFile " << std::endl;
        return EXIT_FAILURE;
    }

    unsigned int x_min = 1;
    unsigned int y_min = 1;
    unsigned int x_max = 1;
    unsigned int y_max = 1;

    if( Region ( argv[1], &x_min, &y_min, &x_max, &y_max ) )
    {
        std::cout << "x_min = " << x_min << std::endl;
        std::cout << "y_min = " << y_min << std::endl;
        std::cout << "x_max = " << x_max << std::endl;
        std::cout << "y_max = " << y_max << std::endl;
    }

    else
    {
        std::cout << "no\n";
    }
}

bool Region ( char* nomefile, unsigned int* X_min, unsigned int* Y_min, unsigned int* X_max, unsigned int* Y_max
)
{
    gdcm::Reader reader;
    reader.SetFileName( nomefile );
    if( !reader.Read() )
    {
        std::cerr << "Could not read: " << nomefile << std::endl;
        return false;
    }

    gdcm::File &file = reader.GetFile();
    gdcm::DataSet &ds = file.GetDataSet();

    gdcm::Tag tsqr(0x0018,0x6011);
    if( !ds.FindDataElement( tsqr ) )
    {
        return false;
    }

    const gdcm::DataElement &sqr= ds.GetDataElement( tsqr );
    //std::cout << sqr << std::endl;
    const gdcm::SequenceOfItems *sqi = sqr.GetValueAsSQ();
    if( !sqi || !sqi->GetNumberOfItems() )
    {
        return false;
    }
}

```



```

//std::cout << sqi << std::endl;

const gdcm::Item & item = sqi->GetItem(1);
//std::cout << item << std::endl;
const gdcm::DataSet& nestedds = item.GetNestedDataSet();
//std::cout << nestedds << std::endl;

gdcm::Tag tX0(0x0018,0x6018);
gdcm::Tag tY0(0x0018,0x601a);
gdcm::Tag tX1(0x0018,0x601c);
gdcm::Tag tY1(0x0018,0x601e);

if( (!nestedds.FindDataElement( tX0 ))||(!nestedds.FindDataElement( tY0 ))||(!nestedds.FindDataElement( tX1
))||(!nestedds.FindDataElement( tY1 )) )
{
    return false;
}

const gdcm::DataElement& deX0 = nestedds.GetDataElement( tX0 );
const gdcm::DataElement& deY0 = nestedds.GetDataElement( tY0 );
const gdcm::DataElement& deX1 = nestedds.GetDataElement( tX1 );
const gdcm::DataElement& deY1 = nestedds.GetDataElement( tY1 );
//std::cout << deX0 << std::endl << deY0 << std::endl << deX1 << std::endl << deY1 << std::endl;

//const gdcm::ByteValue *bvX0 = deX0.GetByteValue();
//const gdcm::ByteValue *bvY0 = deY0.GetByteValue();
//const gdcm::ByteValue *bvX1 = deX1.GetByteValue();
//const gdcm::ByteValue *bvY1 = deY1.GetByteValue();
//std::cout << bvX0 << std::endl << bvY0 << std::endl << bvX1 << std::endl << bvY1 << std::endl;

gdcm::Attribute<0x0018,0x6018> atX0;
gdcm::Attribute<0x0018,0x601a> atY0;
gdcm::Attribute<0x0018,0x601c> atX1;
gdcm::Attribute<0x0018,0x601e> atY1;
atX0.SetFromDataElement( deX0 );
atY0.SetFromDataElement( deY0 );
atX1.SetFromDataElement( deX1 );
atY1.SetFromDataElement( deY1 );
uint32_t X0 = atX0.GetValue();
uint32_t Y0 = atY0.GetValue();
uint32_t X1 = atX1.GetValue();
uint32_t Y1 = atY1.GetValue();
std::cout << X0 << std::endl << Y0 << std::endl << X1 << std::endl << Y1 << std::endl;

*X_min = static_cast<unsigned int>(X0);
*Y_min = static_cast<unsigned int>(Y0);
*X_max = static_cast<unsigned int>(X1);
*Y_max = static_cast<unsigned int>(Y1);

//std::cout << "X_min = " << *X_min << std::endl;
//std::cout << "Y_min = " << *Y_min << std::endl;
//std::cout << "X_max = " << *X_max << std::endl;
//std::cout << "Y_max = " << *Y_max << std::endl;

return true;
}

```

12.78 GetSubSequenceData.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
#include "gdcmReader.h"
#include "gdcmImage.h"
#include "gdcmImageWriter.h"
#include "gdcmDataElement.h"

```

```

#include "gdcmPrivateTag.h"
#include "gdcmUIDGenerator.h"

#include <iostream>
#include <sstream>
#include <string>

#include <map>

/*
 * This example will extract the Movie from the private group of
 * GEMS_Ultrasound_MovieGroup_001 See Attribute
 * (7fel,60,GEMS_Ultrasound_MovieGroup_001)
 *
 * The output file will be stored in `outvid.dcm` as
 * MultiframeGrayscaleByteSecondaryCaptureImageStorage
 */

using namespace gdcm;
static bool processgroup(Item & item3, std::string const & outfilename)
{
    // Item &item3 = sqi3->GetItem(1);
    DataSet &subds3 = item3.GetNestedDataSet();

    const PrivateTag tseq6(0x7fel,0x26,"GEMS_Ultrasound_MovieGroup_001");
    if( !subds3.FindDataElement( tseq6 ) ) return true;
    const DataElement& seq6 = subds3.GetDataElement( tseq6 );
    SmartPointer<SequenceOfItems> sqi6 = seq6.GetValueAsSQ();
    size_t ni6= sqi6->GetNumberOfItems();
    gdcm_assert( sqi6->GetNumberOfItems() >= 1 );
    const PrivateTag tseq7(0x7fel,0x86,"GEMS_Ultrasound_MovieGroup_001");
    int dimx = 0, dimy = 0;
    for( size_t i6 = 1; i6 <= ni6; ++i6 )
    {
        Item &item6 = sqi6->GetItem(i6);
        DataSet &subds6 = item6.GetNestedDataSet();

        if( subds6.FindDataElement( tseq7 ) )
        {
            Element<VR::SL, VM::VM4> el;
            el.SetFromDataElement( subds6.GetDataElement( tseq7 ) );
            dimx = el.GetValue(0);
            dimy = el.GetValue(1);
            std::cout << "Dims= " << dimx << " " << dimy << std::endl;
        }
    }

    const PrivateTag tseq3(0x7fel,0x36,"GEMS_Ultrasound_MovieGroup_001");
    if( !subds3.FindDataElement( tseq3 ) ) return true;
    const DataElement& seq3 = subds3.GetDataElement( tseq3 );

    // std::cout << seq3 << std::endl;

    SmartPointer<SequenceOfItems> sqi4 = seq3.GetValueAsSQ();
    size_t ni4= sqi4->GetNumberOfItems();
    gdcm_assert( sqi4->GetNumberOfItems() >= 1 );
    const PrivateTag tseq8(0x7fel,0x37,"GEMS_Ultrasound_MovieGroup_001");
    const PrivateTag tseq4(0x7fel,0x43,"GEMS_Ultrasound_MovieGroup_001");
    const PrivateTag tseq5(0x7fel,0x60,"GEMS_Ultrasound_MovieGroup_001");

    std::vector<char> imbuffer;
    int dimz = 0;
    for( size_t i4 = 1; i4 <= ni4; ++i4 )
    {
        Item &item4 = sqi4->GetItem(i4);
        DataSet &subds4 = item4.GetNestedDataSet();

        if( !subds4.FindDataElement( tseq8 ) ) return true;
        const DataElement& de8 = subds4.GetDataElement( tseq8 );
        Element<VR::UL, VM::VM1> ldimz;
        ldimz.SetFromDataElement( de8 );
        std::cout << "ldimz: " << ldimz.GetValue() << std::endl;
        dimz += ldimz.GetValue();
        if( !subds4.FindDataElement( tseq4 ) ) return true;
        const DataElement& seq4 = subds4.GetDataElement( tseq4 );
        if( !subds4.FindDataElement( tseq5 ) ) return true;
        const DataElement& seq5 = subds4.GetDataElement( tseq5 );

        // std::cout << seq4 << std::endl;
    }
}

```

```

//      std::cout << seq5 << std::endl;

const ByteValue *bv4 = seq4.GetByteValue();
(void)bv4;
Element<VR::FD, VM::VM1_n> e10;
e10.SetFromDataElement( seq4 );
std::cout << "TimeStamp ( " << e10.GetLength() << " ): ";
// Seems like the 3D volumes is split into chunks of max 100 frames...
gdcm_assert( ldimz.GetValue() == e10.GetLength() );
for( unsigned long i = 0; i < e10.GetLength(); ++i ) {
    if(i) std::cout << ",";
    std::cout << e10.GetValue(i);
}
std::cout << std::endl;
#if 0
{
    std::ofstream out( "/tmp/mo4", std::ios::binary );
    out.write( bv4->GetPointer(), bv4->GetLength());
    out.close();
}
#endif
const ByteValue *bv5 = seq5.GetByteValue();
#if 0
{
    std::ofstream out( "/tmp/mo5", std::ios::binary );
    out.write( bv5->GetPointer(), bv5->GetLength());
    out.close();
}
#endif

std::cout << bv5->GetLength() << std::endl;
imbuffer.insert( imbuffer.begin(), bv5->GetPointer(), bv5->GetPointer() + bv5->GetLength() );
}
DataElement fakedata;
fakedata.SetByteValue( imbuffer.data(), (uint32_t)imbuffer.size() );

gdcm::SmartPointer<gdcm::Image> im = new gdcm::Image;
im->SetNumberOfDimensions( 3 );

im->SetDimension(0, dimx );
im->SetDimension(1, dimy );
im->SetDimension(2, dimz );
size_t l1 = imbuffer.size();
(void)l1;
size_t l2 = im->GetBufferLength();
(void)l2;
gdcm_assert( im->GetBufferLength() == imbuffer.size() );
im->SetPhotometricInterpretation( gdcm::PhotometricInterpretation::MONOCHROME2 );

im->SetDataElement( fakedata );

gdcm::ImageWriter w;
w.SetImage( *im );
DataSet &dataset = w.GetFile().GetDataSet();

gdcm::UIDGenerator uid;
gdcm::DataElement de( Tag(0x8,0x18) ); // SOP Instance UID
de.SetVR( VR::UI );
const char *u = uid.Generate();
de.SetByteValue( u, (uint32_t)strlen(u) );
//ds.Insert( de );
dataset.Replace( de );

de.SetTag( Tag(0x8,0x16) ); // SOP Class UID
de.SetVR( VR::UI );
gdcm::MediaStorage ms(
    gdcm::MediaStorage::MultiframeGrayscaleByteSecondaryCaptureImageStorage );
de.SetByteValue( ms.GetString(), (uint32_t)strlen(ms.GetString()) );
dataset.Replace( de ); // replace !

w.SetFileName( outfilename.c_str() );
if( !w.Write() )
{
    return false;
}
return true;
}

int main(int argc, char *argv[])
{

```

```

if( argc < 2 ) return 1;
const char *filename = argv[1];
gdcm::Reader reader;
reader.SetFileName( filename );
reader.Read();

gdcm::File &file = reader.GetFile();
gdcm::DataSet &ds = file.GetDataSet();
const PrivateTag tseq(0x7fe1,0x1,"GEMS_Ultrasound_MovieGroup_001");

if( !ds.FindDataElement( tseq ) ) return 1;
const DataElement& seq = ds.GetDataElement( tseq );

SmartPointer<SequenceOfItems> sqi = seq.GetValueAsSQ();
gdcm_assert( sqi->GetNumberOfItems() == 1 );
Item &item = sqi->GetItem(1);
DataSet &subds = item.GetNestedDataSet();

const PrivateTag tseq1(0x7fe1,0x10,"GEMS_Ultrasound_MovieGroup_001");

if( !subds.FindDataElement( tseq1 ) ) return 1;
const DataElement& seq1 = subds.GetDataElement( tseq1 );

SmartPointer<SequenceOfItems> sqi2 = seq1.GetValueAsSQ();
gdcm_assert( sqi2->GetNumberOfItems() == 1 );
//int n = sqi2->GetNumberOfItems();
int index = 1;
Item &item2 = sqi2->GetItem(index);
DataSet &subds2 = item2.GetNestedDataSet();

const PrivateTag tseq2(0x7fe1,0x20,"GEMS_Ultrasound_MovieGroup_001");

if( !subds2.FindDataElement( tseq2 ) ) return 1;
const DataElement& seq2 = subds2.GetDataElement( tseq2 );

//      std::cout << seq2 << std::endl;

SmartPointer<SequenceOfItems> sqi3 = seq2.GetValueAsSQ();
size_t ni3 = sqi3->GetNumberOfItems(); (void)ni3;
gdcm_assert( sqi3->GetNumberOfItems() >= 1 );
std::cout << "#Groups = " << sqi3->GetNumberOfItems() << std::endl;
for( SequenceOfItems::SizeType i = 1; i <= sqi3->GetNumberOfItems(); ++i) {
    Item &item3 = sqi3->GetItem(i);
    std::ostringstream os;
    os << "outvid";
    os << i;
    os << ".dcm";
    processgroup(item3, os.str());
}

return 0;
}

```

12.79 HelloVizWorld.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.
=====*/

/*
 * Basic example for dealing with a DICOM file that contains an Image
 * (read: Pixel Data element)
 */

#include "gdcmImageReader.h"
#include "gdcmImageWriter.h"
#include "gdcmImage.h"

```

```

#include "gdcmPhotometricInterpretation.h"

#include <iostream>

int main(int argc, char *argv[])
{
    if( argc < 3 )
    {
        std::cerr << argv[0] << " input.dcm output.dcm" << std::endl;
        return 1;
    }
    const char *filename = argv[1];
    const char *outfilename = argv[2];

    // Instantiate the image reader:
    gdcm::ImageReader reader;
    reader.SetFileName( filename );
    if( !reader.Read() )
    {
        std::cerr << "Could not read: " << filename << std::endl;
        return 1;
    }
    // If we reach here, we know for sure 2 things:
    // 1. It is a valid DICOM
    // 2. And it contains an Image !

    // The output of superclass gdcm::Reader is a gdcm::File
    //gdcm::File &file = reader.GetFile();

    // The other output of gdcm::ImageReader is a gdcm::Image
    const gdcm::Image &image = reader.GetImage();

    // Let's get some property from the image:
    unsigned int ndim = image.GetNumberOfDimensions();
    // Dimensions of the image:
    const unsigned int *dims = image.GetDimensions();
    // Origin
    const double *origin = image.GetOrigin();
    const gdcm::PhotometricInterpretation &pi = image.GetPhotometricInterpretation();
    for(unsigned int i = 0; i < ndim; ++i)
    {
        std::cout << "Dim(" << i << "): " << dims[i] << std::endl;
    }
    for(unsigned int i = 0; i < ndim; ++i)
    {
        std::cout << "Origin(" << i << "): " << origin[i] << std::endl;
    }
    std::cout << "PhotometricInterpretation: " << pi << std::endl;

    // Write the modified DataSet back to disk
    gdcm::ImageWriter writer;
    writer.SetImage( image );
    writer.SetFileName( outfile );
    //writer.SetFile( file ); // We purposely NOT copy the meta information from the input
    // file, and instead only pass the image
    if( !writer.Write() )
    {
        std::cerr << "Could not write: " << outfile << std::endl;
        return 1;
    }

    return 0;
}

```

12.80 HelloWorld.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR

```

```

    PURPOSE. See the above copyright notice for more information.

=====*/
/*
 * This example is ... guess what this is for :)
 */

#include "gdcmReader.h"
#include "gdcmWriter.h"
#include "gdcmAttribute.h"

#include <iostream>

int main(int argc, char *argv[])
{
    if( argc < 3 )
    {
        std::cerr << argv[0] << " input.dcm output.dcm" << std::endl;
        return 1;
    }
    const char *filename = argv[1];
    const char *outfilename = argv[2];

    // Instantiate the reader:
    gdcm::Reader reader;
    reader.SetFileName( filename );
    if( !reader.Read() )
    {
        std::cerr << "Could not read: " << filename << std::endl;
        return 1;
    }

    // If we reach here, we know for sure only 1 thing:
    // It is a valid DICOM file (potentially an old ACR-NEMA 1.0/2.0 file)
    // (Maybe, it's NOT a Dicom image -could be a DICOMDIR, a RTSTRUCT, etc-)

    // The output of gdcm::Reader is a gdcm::File
    gdcm::File &file = reader.GetFile();

    // the dataset is the the set of element we are interested in:
    gdcm::DataSet &ds = file.GetDataSet();

    // Construct a static(*) type for Image Comments :
    gdcm::Attribute<0x0020,0x4000> imagecomments;
    imagecomments.SetValue( "Hello, World !" );

    // Now replace the Image Comments from the dataset with our:
    ds.Replace( imagecomments.GetAsDataElement() );

    // Write the modified DataSet back to disk
    gdcm::Writer writer;
    writer.CheckFileMetaInformationOff(); // Do not attempt to reconstruct the file meta to preserve the file
                                         // as close to the original as possible.
    writer.SetFileName( outfile );
    writer.SetFile( file );
    if( !writer.Write() )
    {
        std::cerr << "Could not write: " << outfile << std::endl;
        return 1;
    }

    return 0;
}

/*
 * (*) static type, means that extra DICOM information VR & VM are computed at compilation time.
 * The compiler is deducing those values from the template arguments of the class.
 */

```

12.81 LargeVRDSExplicit.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre

```

All rights reserved.
See Copyright.txt or <http://gdcm.sourceforge.net/Copyright.html> for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

```

=====*/
#include "gdcmReader.h"
#include "gdcmWriter.h"
#include "gdcmAttribute.h"
#include "gdcmFileExplicitFilter.h"
#include "gdcmSequenceOfItems.h"

bool interpolate(const double * pts, size_t npts, std::vector<double> &out )
{
    out.clear();
    for(size_t i = 0; i < 2*npts; ++i )
    {
        const size_t j = i / 2;
        if( i % 2 )
        {
            if( j != npts - 1 )
            {
                gdcm_assert( 3*j+5 < 3*npts );
                const double midpointx = (pts[3*j+0] + pts[3*j+3]) / 2;
                const double midpointy = (pts[3*j+1] + pts[3*j+4]) / 2;
                const double midpointz = (pts[3*j+2] + pts[3*j+5]) / 2;
                out.push_back( midpointx );
                out.push_back( midpointy );
                out.push_back( midpointz );
            }
        }
        else
        {
            gdcm_assert( j < npts );
            out.push_back( pts[3*j+0] );
            out.push_back( pts[3*j+1] );
            out.push_back( pts[3*j+2] );
        }
    }
    gdcm_assert( out.size() == 2 * npts * 3 - 3 );
    return true;
}

int main(int argc, char *argv[])
{
    if( argc < 3 )
    {
        std::cerr << argv[0] << " input.dcm output.dcm" << std::endl;
        return 1;
    }
    const char *filename = argv[1];
    const char *outfilename = argv[2];
    gdcm::Reader reader;
    reader.SetFileName( filename );
    if( !reader.Read() )
    {
        return 1;
    }

    gdcm::File &file = reader.GetFile();
    gdcm::DataSet &ds = file.GetDataSet();

    gdcm::FileExplicitFilter fef;
    //fef.SetChangePrivateTags( changeprivatetags );
    fef.SetFile( reader.GetFile() );
    if( !fef.Change() )
    {
        std::cerr << "Failed to change: " << filename << std::endl;
        return 1;
    }

    // (3006,0039) SQ (Sequence with undefined length #=4)      # u/l, 1 ROIContourSequence
    gdcm::Tag tag(0x3006,0x0039);

    const gdcm::DataElement &roicsq = ds.GetDataElement( tag );
    gdcm::SmartPointer<gdcm::SequenceOfItems> sqi = roicsq.GetValueAsSQ();
    //sqi->SetNumberOfItems( 1 );
    const gdcm::Item &item = sqi->GetItem(1); // Item start at #1

```

```

const gdcm::DataSet& nestedds = item.GetNestedDataSet();

gdcm::Tag tcsq(0x3006,0x0040);
if( !nestedds.FindDataElement( tcsq ) )
{
    return 0;
}
const gdcm::DataElement& csq = nestedds.GetDataElement( tcsq );
gdcm::SmartPointer<gdcm::SequenceOfItems> sqi2 = csq.GetValueAsSQ();
if( !sqi2 || !sqi2->GetNumberOfItems() )
{
    return 0;
}
//unsigned int nitems = sqi2->GetNumberOfItems();
gdcm::Item & item2 = sqi2->GetItem(1); // Item start at #1

gdcm::DataSet& nestedds2 = item2.GetNestedDataSet();
//item2.SetVLToUndefined();
//std::cout << nestedds2 << std::endl;
// (3006,0050) DS [43.57636\65.52504\ -10.0\46.043102\62.564945\ -10.0\49.126537\60.714... # 398,48 ContourData
gdcm::Tag tcontourdata(0x3006,0x0050);
const gdcm::DataElement & contourdata = nestedds2.GetDataElement( tcontourdata );
//std::cout << contourdata << std::endl;

//const gdcm::ByteValue *bv = contourdata.GetByteValue();
gdcm::Attribute<0x3006,0x0046> ncontourpoints;
ncontourpoints.Set( nestedds2 );

gdcm::Attribute<0x3006,0x0050> at;
at.SetFromDataElement( contourdata );
const double* pts = at.GetValues();
unsigned int npts = at.GetNumberOfValues() / 3;

std::vector<double> out( pts, pts + npts * 3 );
std::vector<double> out2;

//const unsigned int niter = 7;
const unsigned int niter = 8;
for( unsigned int i = 0; i < niter; ++i)
{
    //bool b =
    interpolate(out.data(), out.size() / 3, out2);
    //const double *pout = &out[0];
    out = out2;
    out2.clear();
}
gdcm_assert( out.size() % 3 == 0 );

gdcm::Attribute<0x3006,0x0050> at_interpolate;
at_interpolate.SetNumberOfValues( (unsigned int)(out.size() / 3) );
at_interpolate.SetValues( out.data(), (uint32_t)out.size() );

ncontourpoints.SetValue( at_interpolate.GetNumberOfValues() / 3 );
nestedds2.Replace( at_interpolate.GetAsDataElement() );
nestedds2.Replace( ncontourpoints.GetAsDataElement() );

//gdcm_assert(0);

// Let's take item one and subdivide it

gdcm::TransferSyntax ts = gdcm::TransferSyntax::ImplicitVRLittleEndian;
ts = gdcm::TransferSyntax::ExplicitVRLittleEndian;

gdcm::FileMetaInformation &fmi = file.GetHeader();
const char *tsuid = gdcm::TransferSyntax::GetTSString( ts );
// const char * is ok since padding is \0 anyway...
gdcm::DataElement de( gdcm::Tag(0x0002,0x0010) );
de.SetByteValue( tsuid, (uint32_t)strlen(tsuid) );
de.SetVR( gdcm::Attribute<0x0002, 0x0010>::GetVR() );
fmi.Replace( de );
fmi.Remove( gdcm::Tag(0x0002,0x0012) ); // will be regenerated
fmi.Remove( gdcm::Tag(0x0002,0x0013) ); // ' ' ' '
fmi.SetDataSetTransferSyntax(ts);

gdcm::Writer w;
w.SetFile( file );
w.SetFileName( outfilename );
if ( !w.Write() )
{
    return 1;
}

```



```

    }
    return 0;
}

```

12.82 MakeTemplate.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.
=====*/
#include "gdcmFileAnonymizer.h"
#include "gdcmReader.h"
#include "gdcmWriter.h"

int main(int argc, char *argv[])
{
    if( argc < 3 ) return 1;
    const char* filename = argv[1];
    const char* outfilename = argv[2];

    //gdcm::Trace::DebugOn();

    // Remove Pixel Data element:
    gdcm::FileAnonymizer fa;
    fa.SetInputFileName( filename );
    fa.SetOutputFileName( outfilename );

    fa.Empty( gdcm::Tag(0x7fe0,0x10) );
    // cannot replace in-place DICOM header:
    //fa.Replace( gdcm::Tag(0x2,0x2), "1.2.840.10008.5.1.4.1.1.7" );

    if( !fa.Write() )
    {
        std::cerr << "impossible to remove Pixel Data attribute" << std::endl;
        return 1;
    }

    // Update the DICOM Header:
    gdcm::Reader reader;
    reader.SetFileName( outfilename );
    if( !reader.Read() )
    {
        std::cerr << "could not read back" << std::endl;
        return 1;
    }

    gdcm::File & file = reader.GetFile();
    gdcm::FileMetaInformation &fmi = file.GetHeader();
    gdcm::TransferSyntax ts = gdcm::TransferSyntax::ImplicitVRLittleEndian;
    ts = gdcm::TransferSyntax::ExplicitVRLittleEndian;
    fmi.SetDataSetTransferSyntax(ts);

    gdcm::Writer writer;
    writer.SetFile( file );
    writer.SetFileName( outfilename ); // warning overwrite file !
    if( !writer.Write() )
    {
        std::cerr << "could not write back" << std::endl;
        return 1;
    }

    return 0;
}

```

12.83 MergeTwoFiles.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcms.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.
=====*/
/*
 * This example will show how one can read in two DICOM files, use the dataset
 * from file1 and use image from file2 to save it in a 3rd file.
 *
 * Eg:
 * MergeTwoFiles gdcmData/012345.002.050.dcm gdcmData/test.acr merge.dcm
 */

#include "gdcmReader.h"
#include "gdcmImageReader.h"
#include "gdcmImageWriter.h"
#include "gdcmWriter.h"
#include "gdcmDataSet.h"
#include "gdcmAttribute.h"

int main(int argc, char *argv[])
{
    if( argc < 3 )
    {
        return 1;
    }
    const char *file1 = argv[1];
    const char *file2 = argv[2];
    const char *file3 = argv[3];

    // Read file1
    gdcm::ImageReader reader1;
    reader1.SetFileName( file1 );
    if( !reader1.Read() )
    {
        return 1;
    }

    // Read file2
    gdcm::ImageReader reader2;
    reader2.SetFileName( file2 );
    if( !reader2.Read() )
    {
        return 1;
    }

    // Ok now let's take the DataSet from file1 and the Image from file2
    // Warning: if file2 is -for example- a Secondary Capture Storage, then it has no
    // Image Orientation (Patient) thus any Image Orientation (Patient) from file1
    // will be discarded...

    // let's be fancy. In case reader2 contains explicit, but reader1 is implicit
    // we would rather see an implicit output
    if( reader1.GetFile().GetHeader().GetDataSetTransferSyntax() == gdcm::TransferSyntax::ImplicitVRLittleEndian )
    {
        reader2.GetImage().SetTransferSyntax( gdcm::TransferSyntax::ImplicitVRLittleEndian );
    }

    gdcm::ImageWriter writer;
    writer.SetFileName( file3 );
    writer.SetFile( reader1.GetFile() );
    // ImageWriter will always use all of gdcm::Image information and override anything wrong from
    // reader1.GetFile(), including the Transfer Syntax
    writer.SetImage( reader2.GetImage() );

    gdcm::DataSet &ds = reader1.GetFile().GetDataSet();

    // Make sure that SOPInstanceUID are different
    // Simply removing it is sufficient as gdcm::ImageWriter will generate one by default
    // if not found.

```

```

ds.Remove( gdcmm::Tag(0x0008,0x0018) );
if( !writer.Write() )
{
    return 1;
}

return 0;
}

```

12.84 MrProtocol.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcmm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
/*
 *
 */
/*
28 - 'MrProtocol' VM 1, VR UN, SyngoDT 0, NoOfItems 6, Data '### ASCCONV BEGIN ###'
ulVersion                                = 0xbee332
tSequenceFileName                        = "%SiemensSeq%\fl_fq_shphs"
tProtocolName                            = "flash+AF8-100+AF8-through-plane+AF8-V"
tReferenceImage0                         = "1.3.12.2.1107.5.2.9.16041.30000007062106100181200004658"
tReferenceImage1                         = "1.3.12.2.1107.5.2.9.16041.30000007062106100181200004635"
tReferenceImage2                         = "1.3.12.2.1107.5.2.9.16041.30000007062106100181200004683"
ucScanRegionPosValid                    = 0x1
sProtConsistencyInfo.tBaselineString     = "N4_VB11A_LATEST_20031004"
sProtConsistencyInfo.flNominalB0         = 1.494
sProtConsistencyInfo.flGMax              = 22
sProtConsistencyInfo.flRiseTime          = 10
sGRADSPEC.sEddyCompensationX.aflAmplitude[0] = 0.0141111
sGRADSPEC.sEddyCompensationX.aflAmplitude[1] = 0.057038
sGRADSPEC.sEddyCompensationX.aflAmplitude[2] = -0.00986504
sGRADSPEC.sEddyCompensationX.aflAmplitude[3] = 0.00247627
sGRADSPEC.sEddyCompensationX.aflAmplitude[4] = 0.0026377
sGRADSPEC.sEddyCompensationX.aflTimeConstant[0] = 1.53826
sGRADSPEC.sEddyCompensationX.aflTimeConstant[1] = 0.746617
sGRADSPEC.sEddyCompensationX.aflTimeConstant[2] = 0.339236
sGRADSPEC.sEddyCompensationX.aflTimeConstant[3] = 0.0309809
sGRADSPEC.sEddyCompensationX.aflTimeConstant[4] = 0.00067694
sGRADSPEC.sEddyCompensationY.aflAmplitude[0] = 0.0156411
sGRADSPEC.sEddyCompensationY.aflAmplitude[1] = 0.0440623
sGRADSPEC.sEddyCompensationY.aflAmplitude[2] = -0.00782663
sGRADSPEC.sEddyCompensationY.aflAmplitude[3] = 0.00186828
sGRADSPEC.sEddyCompensationY.aflAmplitude[4] = 0.00154504
sGRADSPEC.sEddyCompensationY.aflTimeConstant[0] = 1.47145
sGRADSPEC.sEddyCompensationY.aflTimeConstant[1] = 0.750538
sGRADSPEC.sEddyCompensationY.aflTimeConstant[2] = 0.339397
sGRADSPEC.sEddyCompensationY.aflTimeConstant[3] = 0.0312962
sGRADSPEC.sEddyCompensationY.aflTimeConstant[4] = 0.000895133
sGRADSPEC.sEddyCompensationZ.aflAmplitude[0] = 0.00618504
sGRADSPEC.sEddyCompensationZ.aflAmplitude[1] = 0.00313121
sGRADSPEC.sEddyCompensationZ.aflAmplitude[2] = 0.000289346
sGRADSPEC.sEddyCompensationZ.aflAmplitude[3] = -0.00019677
sGRADSPEC.sEddyCompensationZ.aflAmplitude[4] = 7.66445e-005
sGRADSPEC.sEddyCompensationZ.aflTimeConstant[0] = 3.37462
sGRADSPEC.sEddyCompensationZ.aflTimeConstant[1] = 0.999351
sGRADSPEC.sEddyCompensationZ.aflTimeConstant[2] = 0.0174646
sGRADSPEC.sEddyCompensationZ.aflTimeConstant[3] = 0.0110094
sGRADSPEC.sEddyCompensationZ.aflTimeConstant[4] = 0.00199922
sGRADSPEC.bEddyCompensationValid        = 1
sGRADSPEC.sB0CompensationX.aflAmplitude[0] = 0.307474
sGRADSPEC.sB0CompensationX.aflAmplitude[1] = 0.029337
sGRADSPEC.sB0CompensationX.aflAmplitude[2] = -0.187118
sGRADSPEC.sB0CompensationX.aflTimeConstant[0] = 0.98583

```

```

sGRADSPEC.sB0CompensationX.aflTimeConstant[1] = 0.0308443
sGRADSPEC.sB0CompensationX.aflTimeConstant[2] = 0.000466792
sGRADSPEC.sB0CompensationY.aflAmplitude[0] = 0.365257
sGRADSPEC.sB0CompensationY.aflAmplitude[1] = -0.318647
sGRADSPEC.sB0CompensationY.aflAmplitude[2] = -0.0118978
sGRADSPEC.sB0CompensationY.aflTimeConstant[0] = 0.61535
sGRADSPEC.sB0CompensationY.aflTimeConstant[1] = 0.488831
sGRADSPEC.sB0CompensationY.aflTimeConstant[2] = 0.00199991
sGRADSPEC.sB0CompensationZ.aflAmplitude[0] = -0.44647
sGRADSPEC.sB0CompensationZ.aflAmplitude[1] = -0.0455154
sGRADSPEC.sB0CompensationZ.aflAmplitude[2] = -0.0304901
sGRADSPEC.sB0CompensationZ.aflTimeConstant[0] = 0.959231
sGRADSPEC.sB0CompensationZ.aflTimeConstant[1] = 0.0720189
sGRADSPEC.sB0CompensationZ.aflTimeConstant[2] = 0.00190141
sGRADSPEC.bB0CompensationValid = 1
sGRADSPEC.sCrossTermCompensationXY.aflAmplitude[0] = 0.00105046
sGRADSPEC.sCrossTermCompensationXY.aflTimeConstant[0] = 0.842014
sGRADSPEC.sCrossTermCompensationXZ.aflAmplitude[0] = -0.00150189
sGRADSPEC.sCrossTermCompensationXZ.aflTimeConstant[0] = 0.736169
sGRADSPEC.sCrossTermCompensationYX.aflAmplitude[0] = -5.5278e-005
sGRADSPEC.sCrossTermCompensationYX.aflTimeConstant[0] = 0.228697
sGRADSPEC.sCrossTermCompensationYZ.aflAmplitude[0] = 0.000307999
sGRADSPEC.sCrossTermCompensationYZ.aflTimeConstant[0] = 1.19431
sGRADSPEC.sCrossTermCompensationZX.aflAmplitude[0] = -0.000286868
sGRADSPEC.sCrossTermCompensationZX.aflTimeConstant[0] = 0.665979
sGRADSPEC.sCrossTermCompensationZY.aflAmplitude[0] = 0.000355175
sGRADSPEC.sCrossTermCompensationZY.aflTimeConstant[0] = 0.844189
sGRADSPEC.bCrossTermCompensationValid = 1
sGRADSPEC.lOffsetX = 25
sGRADSPEC.lOffsetY = 84
sGRADSPEC.lOffsetZ = 47
sGRADSPEC.bOffsetValid = 1
sGRADSPEC.lDelayX = 12
sGRADSPEC.lDelayY = 11
sGRADSPEC.lDelayZ = 9
sGRADSPEC.bDelayValid = 1
sGRADSPEC.flSensitivityX = 0.000264087
sGRADSPEC.flSensitivityY = 0.000272009
sGRADSPEC.flSensitivityZ = 0.000272677
sGRADSPEC.bSensitivityValid = 1
sGRADSPEC.alShimCurrent[0] = 183
sGRADSPEC.alShimCurrent[1] = -25
sGRADSPEC.alShimCurrent[2] = -85
sGRADSPEC.alShimCurrent[3] = 378
sGRADSPEC.alShimCurrent[4] = 82
sGRADSPEC.bShimCurrentValid = 1
sGRADSPEC.ucMode = 0x2
sTXSPEC.asNucleusInfo[0].tNucleus = "1H"
sTXSPEC.asNucleusInfo[0].lFrequency = 63684693
sTXSPEC.asNucleusInfo[0].bFrequencyValid = 1
sTXSPEC.asNucleusInfo[0].flReferenceAmplitude = 359.734
sTXSPEC.asNucleusInfo[0].bReferenceAmplitudeValid = 1
sTXSPEC.asNucleusInfo[0].flAmplitudeCorrection = 1
sTXSPEC.asNucleusInfo[0].bAmplitudeCorrectionValid = 1
sTXSPEC.asNucleusInfo[1].bFrequencyValid = 1
sTXSPEC.asNucleusInfo[1].bReferenceAmplitudeValid = 1
sTXSPEC.asNucleusInfo[1].bAmplitudeCorrectionValid = 1
sTXSPEC.arFPULSE[0].tName = "03GreFCE"
sTXSPEC.arFPULSE[0].bAmplitudeValid = 0x1
sTXSPEC.arFPULSE[0].flAmplitude = 147.095
sTXSPEC.arFPULSE[1].tName = "02GreFCE"
sTXSPEC.arFPULSE[1].bAmplitudeValid = 0x1
sTXSPEC.arFPULSE[1].flAmplitude = 147.095
sTXSPEC.arFPULSE[2].tName = "01GreFCE"
sTXSPEC.arFPULSE[2].bAmplitudeValid = 0x1
sTXSPEC.arFPULSE[2].flAmplitude = 147.095
sTXSPEC.lNoOfTraPulses = 3
sTXSPEC.lBTB1ParallelCapacity = 2
sTXSPEC.lBTB1SerialCapacity = 24
sTXSPEC.lBTB2ParallelCapacity = 2
sTXSPEC.lBTB2SerialCapacity = 26
sTXSPEC.bBTBValid = 1
sTXSPEC.flKDynMagnitudeMin = 0.5
sTXSPEC.flKDynMagnitudeMax = 1.5
sTXSPEC.flKDynMagnitudeClipLow = 0.96
sTXSPEC.flKDynMagnitudeClipHigh = 1.04
sTXSPEC.flKDynPhaseMax = 0.698132
sTXSPEC.flKDynPhaseClip = 0.174533
sTXSPEC.bKDynValid = 1
sTXSPEC.ucRFPulseType = 0x1
sTXSPEC.ucExcitMode = 0x1

```

```

sTXSPEC.ucSimultaneousExcitation      = 0x1
sRXSPEC.lGain                          = 1
sRXSPEC.bGainValid                    = 1
sRXSPEC.aFFT_SCALE[0].lRxChannel       = 1
sRXSPEC.aFFT_SCALE[0].flFactor         = 1.06857
sRXSPEC.aFFT_SCALE[0].bValid           = 1
sRXSPEC.aFFT_SCALE[1].lRxChannel       = 2
sRXSPEC.aFFT_SCALE[1].flFactor         = 1.07454
sRXSPEC.aFFT_SCALE[1].bValid           = 1
sRXSPEC.aFFT_SCALE[2].lRxChannel       = 3
sRXSPEC.aFFT_SCALE[2].flFactor         = 1.06622
sRXSPEC.aFFT_SCALE[2].bValid           = 1
sRXSPEC.aFFT_SCALE[3].lRxChannel       = 4
sRXSPEC.aFFT_SCALE[3].flFactor         = 1.06524
sRXSPEC.aFFT_SCALE[3].bValid           = 1
sRXSPEC.aFFT_SCALE[4].lRxChannel       = 5
sRXSPEC.aFFT_SCALE[4].flFactor         = 0.982692
sRXSPEC.aFFT_SCALE[4].bValid           = 1
sRXSPEC.aFFT_SCALE[5].lRxChannel       = 6
sRXSPEC.aFFT_SCALE[5].flFactor         = 0.988603
sRXSPEC.aFFT_SCALE[5].bValid           = 1
sRXSPEC.aFFT_SCALE[6].lRxChannel       = 7
sRXSPEC.aFFT_SCALE[6].flFactor         = 0.981538
sRXSPEC.aFFT_SCALE[6].bValid           = 1
sRXSPEC.aFFT_SCALE[7].lRxChannel       = 8
sRXSPEC.aFFT_SCALE[7].flFactor         = 1.00856
sRXSPEC.aFFT_SCALE[7].bValid           = 1
sRXSPEC.bVariCapVoltagesValid         = 1
sRXSPEC.alDwellTime[0]                 = 8500
sAdjFreSpec.ulMode                     = 0x1
sAdjFreSpec.ucAdjWithBC                = 0x1
sAdjTraSpec.ucAdjWithBC                = 0x1
sAdjShimSpec.ulMode                    = 0x1
sAdjShimSpec.ucAdjWithBC               = 0x1
sAdjWatSupSpec.ulMode                  = 0x1
sAdjWatSupSpec.ucAdjWithBC             = 0x1
alTR[0]                                = 37000
lContrasts                             = 1
alTE[0]                                = 4000
acFlowComp[0]                          = 1
lCombinedEchoes                        = 1
sSliceArray.asSlice[0].sPosition.dSag   = 35.31199581
sSliceArray.asSlice[0].sPosition.dCor    = -8.387765754
sSliceArray.asSlice[0].sPosition.dTra    = -23.13178296
sSliceArray.asSlice[0].sNormal.dSag      = 0.771051253
sSliceArray.asSlice[0].sNormal.dCor      = 0.5863890019
sSliceArray.asSlice[0].sNormal.dTra      = -0.2482496801
sSliceArray.asSlice[0].dThickness        = 6
sSliceArray.asSlice[0].dPhaseFOV         = 187.5
sSliceArray.asSlice[0].dReadoutFOV       = 250
sSliceArray.lSize                       = 1
sSliceArray.lSag                        = 1
sSliceArray.lConc                       = 1
sSliceArray.ucMode                      = 0x1
sSliceArray.sTSat.dThickness            = 40
sSliceArray.sTSat.dGap                  = 10
sGroupArray.asGroup[0].nSize            = 1
sGroupArray.asGroup[0].dDistFact        = 0.2
sGroupArray.anMember[1]                 = -1
sGroupArray.lSize                       = 1
sGroupArray.sPSat.dThickness            = 50
sGroupArray.sPSat.dGap                  = 10
sAutoAlign.dAAMatrix[0]                 = 1
sAutoAlign.dAAMatrix[5]                 = 1
sAutoAlign.dAAMatrix[10]                = 1
sAutoAlign.dAAMatrix[15]                = 1
sNavigatorPara.ucRespComp                = 0x4
sPrepPulses.ucFatSat                     = 0x4
sPrepPulses.ucWaterSat                   = 0x4
sPrepPulses.ucInversion                  = 0x4
sPrepPulses.ucSatRecovery                = 0x1
sPrepPulses.ucFatSatMode                 = 0x2
sKSpace.lBaseResolution                  = 256
sKSpace.lPhaseEncodingLines              = 192
sKSpace.dPhaseResolution                  = 1
sKSpace.lPartitions                      = 32
sKSpace.lImagesPerSlab                   = 32
sKSpace.dSliceResolution                  = 1
sKSpace.ucPhasePartialFourier             = 0x10
sKSpace.ucSlicePartialFourier             = 0x10
sKSpace.ucAveragingMode                   = 0x2

```

```

sKSpace.ucMultiSliceMode           = 0x1
sKSpace.ucDimension                 = 0x2
sKSpace.ucAsymmetricEchoAllowed    = 0x1
sKSpace.unReordering                = 0x1
sFastImaging.lEPIFactor             = 1
sFastImaging.lTurboFactor           = 1
sFastImaging.lSegments              = 3
sFastImaging.ulEnableRFSpoiling     = 0x1
sPhysioImaging.lSignal1             = 2
sPhysioImaging.lMethod1             = 2
sPhysioImaging.lSignal2            = 1
sPhysioImaging.lMethod2            = 1
sPhysioImaging.lPhases              = 21
sPhysioImaging.lRetroGatedImages    = 16
sPhysioImaging.sPhysioECG.lScanWindow = 805
sPhysioImaging.sPhysioECG.lTriggerPulses = 1
sPhysioImaging.sPhysioECG.lTriggerWindow = 5
sPhysioImaging.sPhysioECG.lArrhythmiaDetection = 1
sPhysioImaging.sPhysioECG.lCardiacGateOnThreshold = 100000
sPhysioImaging.sPhysioECG.lCardiacGateOffThreshold = 700000
sPhysioImaging.sPhysioPulse.lTriggerPulses = 1
sPhysioImaging.sPhysioPulse.lTriggerWindow = 5
sPhysioImaging.sPhysioPulse.lCardiacGateOnThreshold = 100000
sPhysioImaging.sPhysioPulse.lCardiacGateOffThreshold = 700000
sPhysioImaging.sPhysioExt.lTriggerPulses = 1
sPhysioImaging.sPhysioExt.lTriggerWindow = 5
sPhysioImaging.sPhysioExt.lCardiacGateOnThreshold = 100000
sPhysioImaging.sPhysioExt.lCardiacGateOffThreshold = 700000
sPhysioImaging.sPhysioResp.lRespGateThreshold = 20
sPhysioImaging.sPhysioResp.lRespGatePhase = 2
sPhysioImaging.sPhysioResp.dGatingRatio = 0.3
sSpecPara.lPhaseCyclingType        = 1
sSpecPara.lPhaseEncodingType       = 1
sSpecPara.lRFExcitationBandwidth    = 1
sSpecPara.ucRemoveOversampling      = 0x1
sSpecPara.lDecouplingType           = 1
sSpecPara.lNOEType                  = 1
sSpecPara.lExcitationType           = 1
sSpecPara.lSpectralSuppression      = 1
sDiffusion.ulMode                   = 0x1
sAngio.sFlowArray.asElm[0].nVelocity = 100
sAngio.sFlowArray.asElm[0].nDir     = 0x4
sAngio.sFlowArray.lSize              = 1
sAngio.ucPCFlowMode                 = 0x2
sAngio.ucTOFInflow                   = 0x4
sAngio.ucRephasedImage               = 0x1
sAngio.ucPhaseImage                  = 0x1
sEllipticalFilter.ucMode             = 0x1
sPat.lAccelFactPE                    = 1
sPat.lAccelFact3D                    = 1
sPat.ucPATMode                       = 0x1
sPat.ucRefScanMode                   = 0x1
ucAutoMovie                          = 0x1
ucDisableChangeStoreImages           = 0x1
ucReconstructionMode                 = 0x1
ucPHAPSMode                          = 0x1
ucDixon                             = 0x1
lAverages                            = 2
adFlipAngleDegree[0]                 = 30
lScanTimeSec                         = 103
lTotalScanTimeSec                    = 112
dRefSNR                              = 165404.1473
dRefSNR_VOI                          = 165404.1473
tdefaultEVAProt                      = "%SiemensEvaDefProt%\Inline\Inline.evp"
tcurrentEVAProt                      = "%CURRENTEVAPROT%\EVA2A5.tmp"
sCOIL_SELECT_MEAS.asList[0].sCoilElementID.tCoilID = "6_Ch_Body_P"
sCOIL_SELECT_MEAS.asList[0].sCoilElementID.lCoilCopy = 1
sCOIL_SELECT_MEAS.asList[0].sCoilElementID.tElement = "PP6"
sCOIL_SELECT_MEAS.asList[0].lElementSelected = 1
sCOIL_SELECT_MEAS.asList[0].lRxChannelConnected = 1
sCOIL_SELECT_MEAS.asList[1].sCoilElementID.tCoilID = "6_Ch_Body_P"
sCOIL_SELECT_MEAS.asList[1].sCoilElementID.lCoilCopy = 1
sCOIL_SELECT_MEAS.asList[1].sCoilElementID.tElement = "PP5"
sCOIL_SELECT_MEAS.asList[1].lElementSelected = 1
sCOIL_SELECT_MEAS.asList[1].lRxChannelConnected = 1
sCOIL_SELECT_MEAS.asList[2].sCoilElementID.tCoilID = "6_Ch_Body_P"
sCOIL_SELECT_MEAS.asList[2].sCoilElementID.lCoilCopy = 1
sCOIL_SELECT_MEAS.asList[2].sCoilElementID.tElement = "PP3"
sCOIL_SELECT_MEAS.asList[2].lElementSelected = 1
sCOIL_SELECT_MEAS.asList[2].lRxChannelConnected = 2
sCOIL_SELECT_MEAS.asList[3].sCoilElementID.tCoilID = "6_Ch_Body_P"

```

```

sCOIL_SELECT_MEAS.asList[3].sCoilElementID.lCoilCopy = 1
sCOIL_SELECT_MEAS.asList[3].sCoilElementID.tElement = "PP4"
sCOIL_SELECT_MEAS.asList[3].lElementSelected = 1
sCOIL_SELECT_MEAS.asList[3].lRxChannelConnected = 3
sCOIL_SELECT_MEAS.asList[4].sCoilElementID.tCoilID = "6_Ch_Body_P"
sCOIL_SELECT_MEAS.asList[4].sCoilElementID.lCoilCopy = 1
sCOIL_SELECT_MEAS.asList[4].sCoilElementID.tElement = "PP2"
sCOIL_SELECT_MEAS.asList[4].lElementSelected = 1
sCOIL_SELECT_MEAS.asList[4].lRxChannelConnected = 4
sCOIL_SELECT_MEAS.asList[5].sCoilElementID.tCoilID = "6_Ch_Body_P"
sCOIL_SELECT_MEAS.asList[5].sCoilElementID.lCoilCopy = 1
sCOIL_SELECT_MEAS.asList[5].sCoilElementID.tElement = "PP1"
sCOIL_SELECT_MEAS.asList[5].lElementSelected = 1
sCOIL_SELECT_MEAS.asList[5].lRxChannelConnected = 4
sCOIL_SELECT_MEAS.asList[6].sCoilElementID.tCoilID = "6_Ch_Body_A"
sCOIL_SELECT_MEAS.asList[6].sCoilElementID.lCoilCopy = 1
sCOIL_SELECT_MEAS.asList[6].sCoilElementID.tElement = "PA6"
sCOIL_SELECT_MEAS.asList[6].lElementSelected = 1
sCOIL_SELECT_MEAS.asList[6].lRxChannelConnected = 5
sCOIL_SELECT_MEAS.asList[7].sCoilElementID.tCoilID = "6_Ch_Body_A"
sCOIL_SELECT_MEAS.asList[7].sCoilElementID.lCoilCopy = 1
sCOIL_SELECT_MEAS.asList[7].sCoilElementID.tElement = "PA5"
sCOIL_SELECT_MEAS.asList[7].lElementSelected = 1
sCOIL_SELECT_MEAS.asList[7].lRxChannelConnected = 5
sCOIL_SELECT_MEAS.asList[8].sCoilElementID.tCoilID = "6_Ch_Body_A"
sCOIL_SELECT_MEAS.asList[8].sCoilElementID.lCoilCopy = 1
sCOIL_SELECT_MEAS.asList[8].sCoilElementID.tElement = "PA3"
sCOIL_SELECT_MEAS.asList[8].lElementSelected = 1
sCOIL_SELECT_MEAS.asList[8].lRxChannelConnected = 6
sCOIL_SELECT_MEAS.asList[9].sCoilElementID.tCoilID = "6_Ch_Body_A"
sCOIL_SELECT_MEAS.asList[9].sCoilElementID.lCoilCopy = 1
sCOIL_SELECT_MEAS.asList[9].sCoilElementID.tElement = "PA4"
sCOIL_SELECT_MEAS.asList[9].lElementSelected = 1
sCOIL_SELECT_MEAS.asList[9].lRxChannelConnected = 7
sCOIL_SELECT_MEAS.asList[10].sCoilElementID.tCoilID = "6_Ch_Body_A"
sCOIL_SELECT_MEAS.asList[10].sCoilElementID.lCoilCopy = 1
sCOIL_SELECT_MEAS.asList[10].sCoilElementID.tElement = "PA2"
sCOIL_SELECT_MEAS.asList[10].lElementSelected = 1
sCOIL_SELECT_MEAS.asList[10].lRxChannelConnected = 8
sCOIL_SELECT_MEAS.asList[11].sCoilElementID.tCoilID = "6_Ch_Body_A"
sCOIL_SELECT_MEAS.asList[11].sCoilElementID.lCoilCopy = 1
sCOIL_SELECT_MEAS.asList[11].sCoilElementID.tElement = "PA1"
sCOIL_SELECT_MEAS.asList[11].lElementSelected = 1
sCOIL_SELECT_MEAS.asList[11].lRxChannelConnected = 8
sCOIL_SELECT_MEAS.sCOILPLUGS.aulPlugId[0] = 0xff
sCOIL_SELECT_MEAS.sCOILPLUGS.aulPlugId[1] = 0x76
sCOIL_SELECT_MEAS.sCOILPLUGS.aulPlugId[2] = 0x78
sCOIL_SELECT_MEAS.sCOILPLUGS.aulPlugId[3] = 0x87
sCOIL_SELECT_MEAS.sCOILPLUGS.aulPlugId[4] = 0x67
sCOIL_SELECT_MEAS.sCOILPLUGS.auiNmbrOfNibbles[0] = 0x2
sCOIL_SELECT_MEAS.sCOILPLUGS.auiNmbrOfNibbles[1] = 0x2
sCOIL_SELECT_MEAS.sCOILPLUGS.auiNmbrOfNibbles[2] = 0x2
sCOIL_SELECT_MEAS.sCOILPLUGS.auiNmbrOfNibbles[3] = 0x2
sCOIL_SELECT_MEAS.sCOILPLUGS.auiNmbrOfNibbles[4] = 0x2
sEFISPEC.bEFIDataValid = 1
### ASCCONV END ###
,
*/

/*
 * Table of equivalence:
 *
ulVersion = 0xbe332
<=
27 - 'MrProtocolVersion' VM 1, VR IS, SyngoDT 6, NoOfItems 6, Data '12510002'
*/

#include "gdcmReader.h"
#include "gdcmImageReader.h"
#include "gdcmImageWriter.h"
#include "gdcmCSAHeader.h"
#include "gdcmAttribute.h"
#include "gdcmGlobal.h"
#include "gdcmDicts.h"

#include <map>

#include <math.h>

int main(int argc, char *argv [])
{

```

```

if( argc < 2 ) return 1;
const char *filename = argv[1];
gdcm::ImageReader reader;
reader.SetFileName( filename );
if( !reader.Read() )
{
    std::cerr << "Failed to read: " << filename << std::endl;
    return 1;
}

gdcm::CSAHeader csa;
const gdcm::DataSet& ds = reader.GetFile().GetDataSet();

//const gdcm::PrivateTag &t1 = csa.GetCSAImageHeaderInfoTag();
const gdcm::PrivateTag &t2 = csa.GetCSASeriesHeaderInfoTag();

if( ds.FindDataElement( t2 ) )
{
    csa.LoadFromDataElement( ds.GetDataElement( t2 ) );
    //csa.Print( std::cout );
}

if( !csa.FindCSAElementByName( "MrProtocol" ) )
{
    return 1;
}
const gdcm::CSAElement &csael = csa.GetCSAElementByName( "MrProtocol" );
//std::cout << csael << std::endl;

const gdcm::ByteValue *bv = csael.GetByteValue();
if( !bv )
{
    return 1;
}
std::string str(bv->GetPointer(), bv->GetLength());
std::istringstream is(str);
std::string s;
typedef std::map< std::string, std::string > MyMapType;
MyMapType mymap;
while( std::getline(is, s) )
{
    std::string::size_type pos = s.find( '=' );
    if( pos != std::string::npos )
    {
        std::string sub1 = s.substr(0, pos);
        sub1.erase( sub1.find_last_not_of(' ') + 1);
        std::string sub2 = s.substr(pos+1); // skip the '=' char
        sub2.erase( 0, sub2.find_first_not_of(' '));
        //std::cout << sub1 << std::endl;
        mymap.insert( MyMapType::value_type(sub1, sub2) );
    }
    else
    {
        // ### ASCCONV BEGIN ###
        // ### ASCCONV END ###
    }
}

const char fourierstr[] = "sKSpace.ucSlicePartialFourier";
const gdcm::CSAHeaderDict &csadict = gdcm::Global::GetInstance().GetDicts().GetCSAHeaderDict();
const gdcm::CSAHeaderDictEntry &fourier = csadict.GetCSAHeaderDictEntry( fourierstr );
std::cout << fourier << std::endl;
MyMapType::const_iterator it = mymap.find( fourierstr );
if( it == mymap.end() ) return 1;
//std::cout << it->second << std::endl;
const std::string &partial_fourier = it->second;
if( partial_fourier == "0x1" )
{
    std::cout << "partial fourier is 4/8" << std::endl;
}
else if( partial_fourier == "0x2" )
{
    std::cout << "partial fourier is 5/8" << std::endl;
}
else if( partial_fourier == "0x4" )
{
    std::cout << "partial fourier is 6/8" << std::endl;
}
else if( partial_fourier == "0x8" )
{
    std::cout << "partial fourier is 7/8" << std::endl;
}

```



```

else if( partial_fourier == "0x10" )
{
    std::cout << "partial fourier is 8/8" << std::endl;
}
else
{
    std::cerr << "Impossible: " << partial_fourier << std::endl;
    return 1;
}
}

/*
This is the Flip Angle:
adFlipAngleDegree[0]                = 30

One can find it also in the protocol:

...
    <ParamFunctor."<TlmapFunctor">
    {
        <Class> "<TlmapFunctor@IceImagePostProcFunctors">

        <ParamBool."<EXECUTE"> { }
        <ParamDouble."<Flip1_deg"> { <Precision> 16 14.7378520000000000 }
    }
...

*/
// Below is an attempt to play with the CSAHeader dict:
#if 0
const char gspec[] = "sGRADSPEC.flSensitivityX";
it = mymap.find( gspec );
if( it == mymap.end() ) return 1;
const std::string &dummy = it->second;
std::cout << dummy << std::endl;

const gdcm::CSAHeaderDictEntry &csaentry = csadict.GetCSAHeaderDictEntry( gspec );
std::cout << csaentry << std::endl;
#endif

/*
sSliceArray.ucMode -- should be in (1, 2, 4)
enum SeriesMode
{
    ASCENDING    = 0x01,
    DESCENDING   = 0x02,
    INTERLEAVED  = 0x04
};
*/
const char sliceorderstr[] = "sSliceArray.ucMode";
const gdcm::CSAHeaderDictEntry &sliceorder = csadict.GetCSAHeaderDictEntry( sliceorderstr );
std::cout << sliceorder << std::endl;

it = mymap.find( sliceorderstr );
if( it == mymap.end() ) return 1;
const std::string &slice_order = it->second;
if( slice_order == "0x1" )
{
    std::cout << "slice_order: ASCENDING" << std::endl;
}
else if( slice_order == "0x2" )
{
    std::cout << "slice_order: DESCENDING" << std::endl;
}
else if( slice_order == "0x4" )
{
    std::cout << "slice_order: INTERLEAVED" << std::endl;
}
else
{
    std::cerr << "Impossible: " << slice_order << std::endl;
    return 1;
}

gdcm::MrProtocol mrprot;
if( csa.GetMrProtocol(ds, mrprot) )
{
    std::cout << mrprot << std::endl;
}

return 0;
}

```

12.85 PrintLUT.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
/*
*/

#include "gdcmImageReader.h"
#include "gdcmImageWriter.h"
#include "gdcmImage.h"
#include "gdcmPhotometricInterpretation.h"

#include <iostream>

int main(int argc, char *argv[])
{
    if( argc < 2 )
    {
        std::cerr << argv[0] << " input.dcm" << std::endl;
        return 1;
    }
    const char *filename = argv[1];

    // Instantiate the image reader:
    gdcm::ImageReader reader;
    reader.SetFileName( filename );
    if( !reader.Read() )
    {
        std::cerr << "Could not read: " << filename << std::endl;
        return 1;
    }
    const gdcm::Image &image = reader.GetImage();

    const gdcm::LookupTable &lut = image.GetLUT();
    lut.Print( std::cout );

    return 0;
}

```

12.86 PublicDict.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
/*
 * Dummy example to show GDCM Dict(s) API (Part 6) + Collected Private Attributes:
 */

#include "gdcmGlobal.h"
#include "gdcmDicts.h"
#include "gdcmDict.h"
#include "gdcmCSAHeader.h"
#include "gdcmPrivateTag.h"

int main(int , char *[])

```

```

{
    const gdcm::Global& g = gdcm::Global::GetInstance(); // sum of all knowledge !
    const gdcm::Dicts &dicts = g.GetDicts();
    const gdcm::Dict &pub = dicts.GetPublicDict(); // Part 6

    //std::cout << pub << std::endl;

    // 3 different ways to access the same information

    // 1. From the public dict only:
    gdcm::Tag patient_name(0x10,0x10);
    const gdcm::DictEntry &entry1 = pub.GetDictEntry(patient_name);
    std::cout << entry1 << std::endl;

    // 2. From all dicts:
    const gdcm::DictEntry &entry2 = dicts.GetDictEntry(patient_name);
    std::cout << entry2 << std::endl;

    // 3. This solution is the most flexible solution as you can request using the same
    // API either a public tag or a private tag
    const char *strowner = nullptr;
    const gdcm::DictEntry &entry3 = dicts.GetDictEntry(patient_name,strowner);
    std::cout << entry3 << std::endl;

    // Private attributes:

    // try with a private tag now:
    const gdcm::PrivateTag &private_tag = gdcm::CSAHeader::GetCSAImageHeaderInfoTag();
    //std::cout << private_tag << std::endl;
    const gdcm::DictEntry &entry4 = dicts.GetDictEntry(private_tag,private_tag.GetOwner());
    std::cout << entry4 << std::endl;

    // Let's pretend that private lookup is on 0x10xx elements:
    gdcm::PrivateTag dummy = private_tag;
    dummy.SetElement( (uint16_t) (0x1000 + dummy.GetElement()) );
    const gdcm::DictEntry &entry5 = dicts.GetDictEntry(dummy,dummy.GetOwner());
    std::cout << entry5 << std::endl;

    return 0;
}

```

12.87 QIDO-RS.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
#include "gdcmReader.h"
#include "gdcmWriter.h"
#include "gdcmJSON.h"

/*
 * Simple QIDO-RS round-trip to test implementation of gdcm::JSON
 * See Supl66 for details
 */
int main(int argc, char *argv[])
{
    if( argc < 2 ) return 1;
    using namespace gdcm;
    const char *filename = argv[1];
    gdcm::Reader reader;
    reader.SetFileName( filename );
    if( !reader.Read() ) return 1;

    gdcm::JSON json;
    json.PrettyPrintOn();
}

```

```

std::stringstream ss;
const gdcm::File & f = reader.GetFile();
json.Code( f.GetDataSet(), ss);

std::cout << ss.str() << std::endl;

gdcm::Writer w;
gdcm::File & ff = w.GetFile();
ff.GetHeader().SetDataSetTransferSyntax( gdcm::TransferSyntax::ExplicitVRLittleEndian );
if( !json.Decode(ss, ff.GetDataSet() ) )
{
    std::cerr << "Could not decode" << std::endl;
    return 1;
}
w.SetFileName( "/tmp/debug.dcm" );
if( !w.Write() ) return 1;

return 0;
}

```

12.88 ReadAndDumpDICOMDIR.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
/*
 * This example shows how to read and dump a DICOMDIR File
 *
 * Thanks:
 * Tom Marynowski (lordglub gmail) for contributing this example
 */
#include "gdcmReader.h"
#include "gdcmMediaStorage.h"

typedef std::set<gdcm::DataElement> DataElementSet;
typedef DataElementSet::const_iterator ConstIterator;

int main(int argc, char *argv [])
{
    if( argc < 2 ) return 1;
    const char *filename = argv[1];

    gdcm::Reader reader;
    reader.SetFileName( filename);
    if( !reader.Read() )
    {
        std::cerr << "Could not read: " << filename << std::endl;
        return 1;
    }
    std::stringstream strm;

    gdcm::File &file = reader.GetFile();
    gdcm::DataSet &ds = file.GetDataSet();
    gdcm::FileMetaInformation &fmi = file.GetHeader();

    gdcm::MediaStorage ms;
    ms.SetFromFile(file);
    if( ms != gdcm::MediaStorage::MediaStorageDirectoryStorage )
    {
        std::cout << "This file is not a DICOMDIR" << std::endl;
        return 1;
    }

    if ( fmi.FindDataElement( gdcm::Tag (0x0002, 0x0002)))
    {
        strm.str("");
        fmi.GetDataElement( gdcm::Tag (0x0002, 0x0002) ).GetValue().Print(strm);
    }
}

```

```

    }
else
{
    std::cerr << " Media Storage Sop Class UID not present" << std::endl;
}

//TODO il faut trimer strm.str() avant la comparaison au cas ou...
if ("1.2.840.10008.1.3.10"!=strm.str())
{
    std::cout << "This file is not a DICOMDIR" << std::endl;
    return 1;
}

ConstIterator it = ds.GetDES().begin();

for( ; it != ds.GetDES().end(); ++it)
{
    if (it->GetTag()==gdcm::Tag (0x0004, 0x1220))
    {
        const gdcm::DataElement &de = (*it);
        // ne pas utiliser GetSequenceOfItems pour extraire les items
        gdcm::SmartPointer<gdcm::SequenceOfItems> sqi =de.GetValueAsSQ();
        unsigned int itemused = 1;
        while (itemused<=sqi->GetNumberOfItems())
        {
            strm.str("");

            if (sqi->GetItem(itemused).FindDataElement(gdcm::Tag (0x0004, 0x1430)))
                sqi->GetItem(itemused).GetDataElement(gdcm::Tag (0x0004, 0x1430)).GetValue().Print(strm);

            //TODO il faut trimer strm.str() avant la comparaison
            while((strm.str()=="PATIENT")||((strm.str()=="PATIENT ")))
            {
                std::cout << strm.str() << std::endl;
                strm.str("");
                if (sqi->GetItem(itemused).FindDataElement(gdcm::Tag (0x0010, 0x0010)))
                    sqi->GetItem(itemused).GetDataElement(gdcm::Tag (0x0010, 0x0010)).GetValue().Print(strm);
                std::cout << "PATIENT NAME : " << strm.str() << std::endl;

                //PATIENT ID
                strm.str("");
                if (sqi->GetItem(itemused).FindDataElement(gdcm::Tag (0x0010, 0x0020)))
                    sqi->GetItem(itemused).GetDataElement(gdcm::Tag (0x0010, 0x0020)).GetValue().Print(strm);
                std::cout << "PATIENT ID : " << strm.str() << std::endl;

                /*ADD TAG TO READ HERE*/
                std::cout << "===== " << std::endl;
                itemused++;
                strm.str("");
                if (sqi->GetItem(itemused).FindDataElement(gdcm::Tag (0x0004, 0x1430)))
                    sqi->GetItem(itemused).GetDataElement(gdcm::Tag (0x0004, 0x1430)).GetValue().Print(strm);

                //TODO il faut trimer strm.str() avant la comparaison
                while((strm.str()=="STUDY")||((strm.str()=="STUDY ")))
                {
                    std::cout << " " << strm.str() << std::endl;
                    //UID
                    strm.str("");
                    if (sqi->GetItem(itemused).FindDataElement(gdcm::Tag (0x0020, 0x000d)))
                        sqi->GetItem(itemused).GetDataElement(gdcm::Tag (0x0020, 0x000d)).GetValue().Print(strm);
                    std::cout << "          STUDY UID : " << strm.str() << std::endl;

                    //STUDY DATE
                    strm.str("");
                    if (sqi->GetItem(itemused).FindDataElement(gdcm::Tag (0x0008, 0x0020)))
                        sqi->GetItem(itemused).GetDataElement(gdcm::Tag (0x0008, 0x0020)).GetValue().Print(strm);
                    std::cout << "          STUDY DATE : " << strm.str() << std::endl;

                    //STUDY DESCRIPTION
                    strm.str("");
                    if (sqi->GetItem(itemused).FindDataElement(gdcm::Tag (0x0008, 0x1030)))
                        sqi->GetItem(itemused).GetDataElement(gdcm::Tag (0x0008, 0x1030)).GetValue().Print(strm);
                    std::cout << "          STUDY DESCRIPTION : " << strm.str() << std::endl;

                    /*ADD TAG TO READ HERE*/

```

```

std::cout << "          " << "===== " << std::endl;

itemused++;
strm.str("");
if (sqi->GetItem(itemused).FindDataElement(gdcm::Tag (0x0004, 0x1430)))
    sqi->GetItem(itemused).GetDataElement(gdcm::Tag (0x0004, 0x1430)).GetValue().Print(strm);

//TODO il faut trimer strm.str() avant la comparaison
while((strm.str()=="SERIES")||((strm.str()=="SERIES ")))
{
    std::cout << "          " << strm.str() << std::endl;
    strm.str("");
    if (sqi->GetItem(itemused).FindDataElement(gdcm::Tag (0x0020, 0x000e)))
        sqi->GetItem(itemused).GetDataElement(gdcm::Tag (0x0020, 0x000e)).GetValue().Print(strm);
    std::cout << "          SERIE UID" << strm.str() << std::endl;

    //SERIE MODALITY
    strm.str("");
    if (sqi->GetItem(itemused).FindDataElement(gdcm::Tag (0x0008, 0x0060)))
        sqi->GetItem(itemused).GetDataElement(gdcm::Tag (0x0008, 0x0060)).GetValue().Print(strm);
    std::cout << "          SERIE MODALITY" << strm.str() << std::endl;

    //SERIE DESCRIPTION
    strm.str("");
    if (sqi->GetItem(itemused).FindDataElement(gdcm::Tag (0x0008, 0x103e)))
        sqi->GetItem(itemused).GetDataElement(gdcm::Tag (0x0008, 0x103e)).GetValue().Print(strm);
    std::cout << "          SERIE DESCRIPTION" << strm.str() << std::endl;

    /*ADD TAG TO READ HERE*/

    std::cout << "          " << "===== " << std::endl;
    itemused++;
    strm.str("");
    if (sqi->GetItem(itemused).FindDataElement(gdcm::Tag (0x0004, 0x1430)))
        sqi->GetItem(itemused).GetDataElement(gdcm::Tag (0x0004, 0x1430)).GetValue().Print(strm);

    //TODO il faut trimer strm.str() avant la comparaison
    while ((strm.str()=="IMAGE")||((strm.str()=="IMAGE ")))
        // if(tmp=="IMAGE")
        {
            std::cout << "          " << strm.str() << std::endl;

            //UID
            strm.str("");
            if (sqi->GetItem(itemused).FindDataElement(gdcm::Tag (0x0004, 0x1511)))
                sqi->GetItem(itemused).GetDataElement(gdcm::Tag (0x0004, 0x1511)).GetValue().Print(strm);
            std::cout << "          IMAGE UID : " << strm.str() << std::endl;

            //PATH de l'image
            strm.str("");
            if (sqi->GetItem(itemused).FindDataElement(gdcm::Tag (0x0004, 0x1500)))
                sqi->GetItem(itemused).GetDataElement(gdcm::Tag (0x0004, 0x1500)).GetValue().Print(strm);
            std::cout << "          IMAGE PATH : " << strm.str() << std::endl;
            /*ADD TAG TO READ HERE*/

            if(itemused < sqi->GetNumberOfItems())
            {
                itemused++;
            }else{break;}

            strm.str("");

            if (sqi->GetItem(itemused).FindDataElement(gdcm::Tag (0x0004, 0x1430)))
                sqi->GetItem(itemused).GetDataElement(gdcm::Tag (0x0004, 0x1430)).GetValue().Print(strm);

            }
        }
    }
    itemused++;
}
}
return 0;
}

```

12.89 ReadAndDumpDICOMDIR2.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2017 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.
=====*/

/*
 * This example shows how to read and dump a DICOMDIR File
 *
 * Thanks:
 *   Tom Marynowski (lordglub gmail) for contributing the original
 *   ReadAndDumpDICOMDIR.cxx example
 *   Mihail Isakov for contributing offset calculation code here:
 *   https://sourceforge.net/p/gdcm/mailman/gdcm-developers/?viewmonth=201707&viewday=15
 *   Tod Baudais for combining the above and cleaning up this example
 */

#include <string>
#include <unordered_map>
#include <iostream>
#include <memory>

#include "gdcmReader.h"
#include "gdcmAttribute.h"
#include "gdcmDirectory.h"

//=====
//=====

#define TAG_MEDIA_STORAGE_SOP_CLASS_UID 0x0002,0x0002
#define TAG_DIRECTORY_RECORD_SEQUENCE 0x0004,0x1220
#define TAG_DIRECTORY_RECORD_TYPE 0x0004,0x1430
#define TAG_PATIENTS_NAME 0x0010,0x0010
#define TAG_PATIENT_ID 0x0010,0x0020
#define TAG_STUDY_DATE 0x0008,0x0020
#define TAG_STUDY_DESCRIPTION 0x0008,0x1030
#define TAG_MODALITY 0x0008,0x0060
#define TAG_SERIES_DESCRIPTION 0x0008,0x103E
#define TAG_REFERENCED_FILE_ID 0x0004,0x1500
#define TAG_REFERENCED_LOWER_LEVEL_DIRECTORY_ENTITY_OFFSET 0x0004,0x1420
#define TAG_NEXT_DIRECTORY_RECORD_OFFSET 0x0004,0x1400

//=====
// Some handy utility functions
//=====

std::string left_trim(const std::string &s) {
    std::string ss(s);
    ss.erase(ss.begin(), std::find_if(ss.begin(), ss.end(), std::not1(std::ptr_fun<int, int>(std::isspace))));
    return ss;
}

std::string right_trim(const std::string &s) {
    std::string ss(s);
    ss.erase(std::find_if(ss.rbegin(), ss.rend(), std::not1(std::ptr_fun<int, int>(std::isspace))).base(),
              ss.end());
    return ss;
}

std::string trim(const std::string &s) {
    return left_trim(right_trim(s));
}

//=====
// This code could be put in a header file somewhere
//=====

class DICOMDIRReader {
public:
    DICOMDIRReader() {}
    DICOMDIRReader(const DICOMDIRReader &rhs) = delete;

```

```

        DICOMDIRReader & operator = (DICOMDIRReader &&rhs) = delete;
        DICOMDIRReader & operator = (const DICOMDIRReader &rhs) = delete;
        virtual ~DICOMDIRReader (DICOMDIRReader &&rhs) = delete;
        (void) {}

public:
    struct Common {
        int64_t child_offset;
        int64_t sibling_offset;
    };

    struct Image: public Common {
        std::string path;
    };

    struct Series: public Common {
        std::string modality;
        std::string description;

        std::vector<std::shared_ptr<Image>> children;
    };

    struct Study: public Common {
        std::string date;
        std::string description;

        std::vector<std::shared_ptr<Series>> children;
    };

    struct Patient: public Common {
        std::string name;
        std::string id;

        std::vector<std::shared_ptr<Study>> children;
    };

    struct Other: public Common {
    };

    const std::vector<std::shared_ptr<Patient>>& load (const std::string &path);

    const std::vector<std::shared_ptr<Patient>>& patients (void) { return _patients; }

private:
    template <class T>
    std::string get_string (const T &ds, const gdcm::Tag &tag)
    {
        std::stringstream strm;
        if (ds.FindDataElement(tag)) {
            auto &de = ds.GetDataElement(tag);
            if (!de.IsEmpty() && !de.IsUndefinedLength())
                de.GetValue().Print(strm);
        }
        return trim(strm.str());
    }

    template <class P, class C, class O>
    void reassemble_hierarchy (P &parent_offsets, C &child_offsets, O &other_offsets)
    {
        for (auto &parent : parent_offsets) {
            int64_t sibling_offset;
            auto c = child_offsets[parent.second->child_offset];
            if (!c) {
                auto o = other_offsets[parent.second->child_offset];
                if (!o) {
                    continue;
                } else {
                    sibling_offset = o->sibling_offset;
                }
            } else {
                parent.second->children.push_back(c);
                sibling_offset = c->sibling_offset;
            }

            // Get all siblings
            while (sibling_offset) {
                c = child_offsets[sibling_offset];
                if (!c) {
                    auto o = other_offsets[sibling_offset];
                    if (!o) {

```



```

        break;
    } else {
        sibling_offset = o->sibling_offset;
    }
} else {
    parent.second->children.push_back(c);
    sibling_offset = c->sibling_offset;
}
}
}

std::vector<std::shared_ptr<Patient> _patients;
};

//=====
// This code could be put in an implementation file somewhere
//=====

const std::vector<std::shared_ptr<DICOMDIRReader::Patient>>& DICOMDIRReader::load (const std::string &path)
{
    _patients.clear();

    //
    // Read the dataset from the DICOMDIR file
    //

    gdcm::Reader reader;
    reader.SetFileName(path.c_str());
    if(!reader.Read()) {
        throw std::runtime_error("Unable to read file");
    }

    // Retrieve information from file
    auto &file = reader.GetFile();
    auto &data_set = file.GetDataSet();
    auto &file_meta_information = file.GetHeader();

    // Retrieve and check the Media Storage class from file
    gdcm::MediaStorage media_storage;
    media_storage.SetFromFile(file);
    if(media_storage != gdcm::MediaStorage::MediaStorageDirectoryStorage) {
        throw std::runtime_error("This file is not a DICOMDIR");
    }

    auto media_storage_sop_class_uid = get_string(file_meta_information,
        gdcm::Tag(TAG_MEDIA_STORAGE_SOP_CLASS_UID));

    // Make sure we have a DICOMDIR file
    if (media_storage_sop_class_uid != "1.2.840.10008.1.3.10") {
        throw std::runtime_error("This file is not a DICOMDIR");
    }

    //
    // Offset to first item courtesy of Mihail Isakov
    //

    gdcm::VL first_item_offset = 0;
    auto it = data_set.Begin();
    for(; it != data_set.End() && it->GetTag() != gdcm::Tag(TAG_DIRECTORY_RECORD_SEQUENCE); ++it) {
        first_item_offset += it->GetLength<gdcm::ExplicitDataElement>();
    }
    // Tag (4 bytes)
    first_item_offset += it->GetTag().GetLength();
    // VR field
    first_item_offset += it->GetVR().GetLength();
    // VL field
    // For Explicit VR: adventitiously VL field length = VR field length,
    // for SQ 4 bytes:
    // http://dicom.nema.org/medical/dicom/current/output/html/part05.html#table_7.1-1
    first_item_offset += it->GetVR().GetLength();

    //
    // Iterate all data elements
    //

    // For each item in data set
    for(auto data_element : data_set.GetDES()) {

        // Only look at Directory sequence
        if (data_element.GetTag() != gdcm::Tag(TAG_DIRECTORY_RECORD_SEQUENCE))

```

```

        continue;

    auto item_sequence = data_element.GetValueAsSQ();
    auto num_items = item_sequence->GetNumberOfItems();

    //
    // Compute an offset table
    //

    // Start calculation of offset to each item courtesy of Mihail Isakov
    std::vector<int64_t> item_offsets(num_items+1);
    item_offsets[0] = file_meta_information.GetFullLength() + static_cast<int64_t>(first_item_offset);

    //
    // Extract out all of the items
    //

    std::unordered_map<int64_t, std::shared_ptr<Patient>> patient_offsets;
    std::unordered_map<int64_t, std::shared_ptr<Study>> study_offsets;
    std::unordered_map<int64_t, std::shared_ptr<Series>> series_offsets;
    std::unordered_map<int64_t, std::shared_ptr<Image>> image_offsets;
    std::unordered_map<int64_t, std::shared_ptr<Other>> other_offsets;

    for (uint32_t item_index = 1; item_index <= num_items; ++item_index) {
        auto &item = item_sequence->GetItem(item_index);

        // Add offset for item to offset table
        item_offsets[item_index] = item_offsets[item_index-1] + item.GetLength<gdcm::ExplicitDataElement>();

        // Child offset
        gdcm::Attribute<TAG_REFERENCED_LOWER_LEVEL_DIRECTORY_ENTITY_OFFSET> child_offset;
        child_offset.SetFromDataElement(item.GetDataElement(gdcm::Tag
(TAG_REFERENCED_LOWER_LEVEL_DIRECTORY_ENTITY_OFFSET)));

        // Sibling offset
        gdcm::Attribute<TAG_NEXT_DIRECTORY_RECORD_OFFSET> sibling_offset;
        sibling_offset.SetFromDataElement(item.GetDataElement(gdcm::Tag
(TAG_NEXT_DIRECTORY_RECORD_OFFSET)));

        // Record Type
        auto record_type = trim(get_string(item, gdcm::Tag (TAG_DIRECTORY_RECORD_TYPE)));

        // std::cout << "record_type " << record_type << " at " << item_offsets[item_index-1] << std::endl;
        // std::cout << " child_offset " << child_offset.GetValue() << std::endl;
        // std::cout << " sibling_offset " << sibling_offset.GetValue() << std::endl;

        // Extract patient information
        if (record_type == "PATIENT") {
            auto patient = std::make_shared<Patient>();
            patient->name = get_string(item, gdcm::Tag (TAG_PATIENTS_NAME));
            patient->id = get_string(item, gdcm::Tag (TAG_PATIENT_ID));

            patient->child_offset = child_offset.GetValue();
            patient->sibling_offset = sibling_offset.GetValue();
            patient_offsets[item_offsets[item_index-1]] = patient;

        // Extract study information
        } else if (record_type == "STUDY") {
            auto study = std::make_shared<Study>();
            study->date = get_string(item, gdcm::Tag (TAG_STUDY_DATE));
            study->description = get_string(item, gdcm::Tag (TAG_STUDY_DESCRIPTION));

            study->child_offset = child_offset.GetValue();
            study->sibling_offset = sibling_offset.GetValue();
            study_offsets[item_offsets[item_index-1]] = study;

        // Extract series information
        } else if (record_type == "SERIES") {
            auto series = std::make_shared<Series>();
            series->modality = get_string(item, gdcm::Tag (TAG_MODALITY));
            series->description = get_string(item, gdcm::Tag (TAG_SERIES_DESCRIPTION));

            series->child_offset = child_offset.GetValue();
            series->sibling_offset = sibling_offset.GetValue();
            series_offsets[item_offsets[item_index-1]] = series;

        // Extract image information
        } else if (record_type == "IMAGE") {
            auto image = std::make_shared<Image>();

```

```

        image->path = get_string(item, gdcm::Tag (TAG_REFERENCED_FILE_ID));

        image->child_offset = child_offset.GetValue();
        image->sibling_offset = sibling_offset.GetValue();
        image_offsets[item_offsets[item_index-1]] = image;
    } else {
        auto other = std::make_shared<Other>();

        other->child_offset = child_offset.GetValue();
        other->sibling_offset = sibling_offset.GetValue();
        other_offsets[item_offsets[item_index-1]] = other;
    }
}

// Check validity
if (patient_offsets.size() == 0)
    throw std::runtime_error("Unable to find patient record");

reassemble_hierarchy(series_offsets, image_offsets, other_offsets);
reassemble_hierarchy(study_offsets, series_offsets, other_offsets);
reassemble_hierarchy(patient_offsets, study_offsets, other_offsets);

// Set the new root
for (auto &patient : patient_offsets) {
    _patients.push_back(patient.second);
}

return _patients;
}

//=====
// Quick test
//=====

int main(int argc, const char *argv[]) {
    DICOMDIRReader reader;

    try {
        if (argc != 2)
            throw std::runtime_error("Wrong number of arguments");

        auto &patients = reader.load(argv[1]);

        for (auto &patient : patients) {

            std::cout << "PATIENT" << std::endl;
            std::cout << "NAME: " << patient->name << std::endl;
            std::cout << "ID: " << patient->id << std::endl;

            int x = 0;
            for (auto &study : patient->children) {
                std::cout << "    STUDY" << std::endl;
                std::cout << "        DESCRIPTION: " << study->description << std::endl;
                std::cout << "        DATE: " << study->date << std::endl;

                for (auto &series : study->children) {
                    x+=1;
                    std::cout << "            SERIES " << x << std::endl;
                    std::cout << "            DESCRIPTION: " << series->description << std::endl;
                    std::cout << "            MODALITY: " << series->modality << std::endl;

                    for (auto &image : series->children) {
                        std::cout << "                IMAGE PATH: " << image->path << std::endl;
                    }
                }
            }
        }
    }
    catch (...) {
        // TODO handle this
        return EXIT_FAILURE;
    }

    return EXIT_SUCCESS;
}

```

12.90 ReadAndPrintAttributes.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.
=====*/
/*
 * This small example will show how one can read and print
 * a DICOM Attribute using different technique (by tag or by name)
 */

#include "gdcmReader.h"
#include "gdcmGlobal.h"
#include "gdcmDicts.h"
#include "gdcmDict.h"
#include "gdcmAttribute.h"
#include "gdcmStringFilter.h"

#include <iostream>

int main(int argc, char *argv[])
{
    if( argc < 2 )
    {
        std::cerr << argv[0] << " input.dcm" << std::endl;
        return 1;
    }
    const char *filename = argv[1];

    // Instantiate the reader:
    gdcm::Reader reader;
    reader.SetFileName( filename );
    if( !reader.Read() )
    {
        std::cerr << "Could not read: " << filename << std::endl;
        return 1;
    }

    // The output of gdcm::Reader is a gdcm::File
    gdcm::File &file = reader.GetFile();

    // the dataset is the the set of element we are interested in:
    gdcm::DataSet &ds = file.GetDataSet();

    const gdcm::Global& g = gdcm::Global::GetInstance();
    const gdcm::Dicts &dicts = g.GetDicts();
    const gdcm::Dict &pubdict = dicts.GetPublicDict();

    using namespace gdcm;

    // In this example we will show why using name to lookup attribute can be
    // dangerous.
    Tag tPatientName(0x00,0x00);
    //const DictEntry &del =
    pubdict.GetDictEntryByName("Patient Name", tPatientName);

    std::cout << "Found: " << tPatientName << std::endl;

    // Indeed the attribute could not be found. Since DICOM 2003, Patient Name
    // has become Patient's Name.

    Tag tPatientsName;
    //const DictEntry &de2 =
    pubdict.GetDictEntryByName("Patient's Name", tPatientsName);

    std::cout << "Found: " << tPatientsName << std::endl;

    // Let's try to read an arbitrary DICOM Attribute:
    Tag tDoseGridScaling;
    //const DictEntry &de3 =

```

```

pubdict.GetDictEntryByName("Dose Grid Scaling", tDoseGridScaling);

std::cout << "Found: " << tDoseGridScaling << std::endl;

if( ds.FindDataElement( tDoseGridScaling ) )
{
    gdcm::StringFilter sf;
    sf.SetFile(file);
    std::cout << "Attribute Value as String: " << sf.ToString( tDoseGridScaling ) << std::endl;

    // Let's check the name again:
    std::pair<std::string, std::string> pss
        = sf.ToStringPair( tDoseGridScaling );
    std::cout << "Attribute Name Checked: " << pss.first << std::endl;
    std::cout << "Attribute Value (string): " << pss.second << std::endl;

    //const DataElement &dgs = ds.GetDataElement( tDoseGridScaling );

    // Let's assume for a moment we knew the tag number:
    Attribute<0x3004,0x000e> at;
    gdcm_assert( at.GetTag() == tDoseGridScaling );
    at.SetFromDataSet( ds );
    // For the sake of long term maintenance, we will not write
    // that this particular attribute is stored as a double. What if
    // a user made a mistake. It is much safer to rely on GDCM internal
    // mechanism to deduce the VR::DS type (represented as a iieee double)
    Attribute<0x3004,0x000e>::ArrayType v = at.GetValue();
    std::cout << "DoseGridScaling=" << v << std::endl;
}

return 0;
}

```

12.91 ReadExplicitLengthSQIVR.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
#include "gdcmByteValue.h"
#include "gdcmDataSet.h"
#include "gdcmImplicitDataElement.h"
#include "gdcmPrivateTag.h"
#include "gdcmReader.h"
#include "gdcmSequenceOfItems.h"

using namespace gdcm;

int main(int argc, char *argv[])
{
    if ( argc < 2 ) return 1;
    const char *filename = argv[1];
    gdcm::Reader r;
    r.SetFileName( filename );
    r.Read();

    //gdcm::PrivateTag pt(0x01,0x42,"ELSCINT1");
    //gdcm::Tag pt(0x88,0x200);
    gdcm::Tag pt(0x8,0x1140);
    DataSet &ds = r.GetFile().GetDataSet();
    const DataElement &de = ds.GetDataElement( pt );

    std::cout << de << std::endl;
    const ByteValue *bv = de.GetByteValue();
    SmartPointer<SequenceOfItems> sqi = new SequenceOfItems;
    sqi->SetLength( bv->GetLength() );
}

```

```

std::stringstream ss;
ss.str( std::string( bv->GetPointer(), bv->GetLength() ) );
sqi->Read<ImplicitDataElement, SwapperNoOp>( ss );

std::cout << *sqi << std::endl;

return 0;
}

```

12.92 ReadGEMSSDO.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcml.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
#include "gdcmlReader.h"
#include "gdcmlDataElement.h"
#include "gdcmlPrivateTag.h"

#include <iostream>
#include <string>

using namespace gdcml;

struct SDOElement
{
    typedef std::vector<std::string>::size_type SizeType;
    const char *GetData(SizeType index) const {
        return Data[index].c_str();
    }
    SizeType GetNumberOfData() const {
        return Data.size();
    }
    void SetData(SizeType index, const char *data) {
        Data[index] = data;
    }
    const char *GetDataFormat() const {
        return DataFormat.c_str();
    }
    void SetDataFormat(const char *dataformat, SizeType num) {
        DataFormat = dataformat;
        Data.resize( num );
    }
    void Print( std::ostream &os ) const {
        os << DataFormat << ":" << std::endl;
        std::vector<std::string>::const_iterator it = Data.begin();
        size_t s = 0;
        for( ; it != Data.end(); ++it )
        {
            os << " (" << s++ << ") " << *it << std::endl;
        }
    }
private:
    std::string DataFormat;
    std::vector<std::string> Data;
};

class SDOHeader
{
public:
    typedef std::vector<SDOElement> SDOElements;
    typedef SDOElements::size_type SizeType;
    SizeType GetNumberOfSDOElements() const {
        return InternalSDODataset.size();
    }
    void AddSDOElement(SDOElement const &sdoelement) {
        InternalSDODataset.push_back( sdoelement );
    }

```

```

    }
    const SDOElement &GetSDOElement(SizeType index) const {
        return InternalSDODataset[index];
    }
    const SDOElement &GetSDOElementByName(const char *) const {
        return InternalSDODataset[0];
    }
    void LoadFromAttributes(std::string const &s1, std::string const &s2)
    {
        std::string tok;
        std::string tok2;
        std::stringstream strstr(s1);
        std::stringstream strstr2(s2);

        SDOElement element;
        // Do format
        size_t count = 0;
        while ( std::getline ( strstr2, tok, '\\') )
        {
            //std::cout << tok << " ";
            std::getline ( strstr2, tok2, '\\') ;
            //std::cout << tok2 << std::endl;
            count += atoi( tok2.c_str() );
            element.SetDataFormat( tok.c_str(), atoi( tok2.c_str() ) );
            for( size_t t = 0; t < element.GetNumberOfData(); ++t )
            {
                std::getline ( strstr, tok, '\\') ;
                element.SetData(t, tok.c_str() );
            }
            AddSDOElement( element );
        }
        //while ( std::getline ( strstr, tok, '^') )
        // while ( std::getline ( strstr, tok, '\\') )
        // {
        //     std::cout << tok << std::endl;
        //     count++;
        // }
        // std::cout << "Count: " << count << std::endl;
        // count = 0;

        // std::cout << "Count: " << count << std::endl;

    }
    void Print( std::ostream &os ) const {
        SDOElements::const_iterator it = InternalSDODataset.begin();
        for( ; it != InternalSDODataset.end(); ++it )
        {
            it->Print ( os );
        }
    }
private:
    SDOElements InternalSDODataset;
};

bool sdo_decode( DataElement const &stringdata, DataElement const &stringdataformat )
{
    const char *sd = stringdata.GetByteValue()->GetPointer();
    const size_t len_sd = stringdata.GetByteValue()->GetLength();

    std::string s1 = std::string( sd, len_sd );

    const char *sdf = stringdataformat.GetByteValue()->GetPointer();
    const size_t len_sdf = stringdataformat.GetByteValue()->GetLength();

    std::string s2 = std::string( sdf, len_sdf );

    // std::cout << s1 << std::endl;
    // std::cout << s2 << std::endl;

    SDOHeader header;
    header.LoadFromAttributes( s1, s2 );

    header.Print( std::cout );

    return true;
}

int main(int argc, char *argv[])
{
    if( argc < 2 )
    {

```

```

        std::cerr << argv[0] << " input.dcm" << std::endl;
        return 1;
    }
    const char *filename = argv[1];
    Reader reader;
    reader.SetFileName( filename );
    if( !reader.Read() )
    {
        return 1;
    }

    File &file = reader.GetFile();
    DataSet &ds = file.GetDataSet();

    // StringData (0033,xx1F) 3 "GEMS_GENIE_1" List of SDO parameters stored as
    // list of strings
    const PrivateTag tstringdata(0x33,0x1f,"GEMS_GENIE_1");
    // StringDataFormat (0033,xx23) 3 "GEMS_GENIE_1" Format of string parameters;
    // contains information about name and number of strings in list
    const PrivateTag tstringdataformat(0x33,0x23,"GEMS_GENIE_1");

    if( !ds.FindDataElement( tstringdata ) ) return 1;
    const DataElement& stringdata = ds.GetDataElement( tstringdata );
    if( !ds.FindDataElement( tstringdataformat ) ) return 1;
    const DataElement& stringdataformat = ds.GetDataElement( tstringdataformat );

    sdo_decode( stringdata, stringdataformat );

    return 0;
}

```

12.93 ReadMultiTimesException.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
// The intention of this sample program is to provoke bad_alloc exceptions in gdcm code

#include "gdcmImageReader.h"

int main(int argc, char* argv[])
{
    // We pre-allocate some memory (about 1Gb) to help the issue to show up earlier
    char *dummyBuffer = new char[1024*1024*1100]; (void)dummyBuffer;
    // Check the number of parameters given
    if (argc < 3)
    {
        std::cerr << "Usage: " << argv[0] << " Filename numberOfTries" << std::endl;
        return 1;
    }

    std::cout << "We are going to read the file: " << argv[1] << " " << argv[2] << " times" << std::endl;
    // We hold the pointers in an array to avoid the memory to be released
    // We read the input file n-times
    for (int i = 0; i < atoi(argv[2]); ++i)
    {
        gdcm::ImageReader reader;
        std::cout << "Reading try: " << i << std::endl;
        // Read files
        reader.SetFileName(argv[1]);
        try
        {
            reader.Read();
            gdcm::Image &img = reader.GetImage();
            unsigned long len = img.GetBufferLength();
            char *buffer = new char[ len ];

```



```

        img.GetBuffer( buffer ); // do NOT de-allocate buffer !
    }
    catch (std::bad_alloc &ba)
    {
        (void)ba;
        std::cerr << "BAD ALLOC Exception caught!" << std::endl;
    }
    catch (...)
    {
        std::cerr << "Exception caught!" << std::endl;
    }
}

return 0;
}

```

12.94 ReadUTF8QtDir.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
/*
 * GDCM API expect a const char * as input for SetFileName
 * In order to use this API from Qt, here is a simple test that
 * shows how to do it in a portable manner:
 *
 * http://doc.qt.nokia.com/latest/qdir.html#navigation-and-directory-operations
 */

#include "gdcmReader.h"
#include "gdcmDirectory.h"

#include <QDir>
#include <QString>
#include <QCoreApplication>

#include <string>
#include <fstream>

#include <stdio.h> // fopen

static int TestBothFuncs(const char *info , const char *ba_str)
{
    int res = 0;
    FILE *f = fopen( ba_str, "r" );
    if( f )
    {
        std::cout << info << " fopen: " << ba_str << std::endl;
        fclose(f);
        ++res;
    }
    gdcm::Reader reader;
    std::ifstream is( ba_str, std::ios::binary );
    if( is.is_open() )
    {
        std::cout << info << " is_open: " << ba_str << std::endl;
        ++res;
    }
    reader.SetStream( is );
    if( reader.CanRead() == true )
    {
        std::cout << info << " SetStream/CanRead:" << ba_str << std::endl;
        ++res;
    }
    is.close();
    reader.SetFileName( ba_str );
}

```

```

    if( reader.CanRead() == true )
    {
        std::cout << info << " SetFileName/CanRead:" << ba_str << std::endl;
        ++res;
    }
    return 4 - res;
}

static int scanFolder(const char dirname[])
{
    int res = 0;
    gdcm::Directory dir;
    unsigned int nfiles = dir.Load( dirname, true );
    const gdcm::Directory::FileNamesType &filenames = dir.GetFileNames();

    for( unsigned int i = 0; i < nfiles; ++i )
    {
        const char *ba_str = filenames[i].c_str();
        res += TestBothFuncs("GDCM",ba_str);
    }
    return res;
}

static int scanFolderQt(QDir const &dir, QStringList& files)
{
    int res = 0;
    QFileInfoList children = dir.entryInfoList(QDir::AllEntries|QDir::NoDotAndDotDot);
    for ( int i=0; i<children.count(); i++ ) {
        QFileInfo file = children.at(i);
        if ( file.isDir() == true ) {
            res += scanFolderQt(QDir(file.absoluteFilePath()), files);
            continue;
        }
        // Convert back from the internal representation to 8bits
        // toLocal8Bit() returns by copy. Need to store explicitly the QByteArray
        QByteArray str = file.absoluteFilePath().toLocal8Bit();
        const char *ba_str1 = str.constData();
        res += TestBothFuncs("QString", ba_str1);
    }
    return res;
}

int main(int argc, char *argv[])
{
    // very important:
    QCoreApplication qCoreApp( argc , argv );
    if( argc < 2 )
    {
        std::cerr << argv[0] << " dir " << std::endl;
        return 1;
    }

    int res = 0;
    const char *dirname = argv[1];
    res += scanFolder( dirname );

    QDir dir( QString::fromLocal8Bit(dirname) );
    QStringList files;
    res += scanFolderQt( dir, files);

    if( res )
        std::cerr << "Problem with UTF-8" << std::endl;
    else
        std::cerr << "Success with UTF-8" << std::endl;

    return res;
}

```

12.95 SimpleScanner.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.

```

See Copyright.txt or <http://gdcm.sourceforge.net/Copyright.html> for details.

This software is distributed WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the above copyright notice for more information.

```

=====*/
/*
 * Simple example to show how to use Scanner API.
 * It exposes the three different cases:
 * - DICOM Attribute is present and has a value
 * - DICOM Attribute is present and has no value
 * - DICOM Attribute is not present at all
 * It also shows the purpose of the function 'IsKey' to detect whether or
 * not the file has been read by the gdcm::Scanner. Technically most of the time
 * if a file is not a 'Key' this is because it is not a DICOM file. You need to use
 * gdcm::System::FileExists to decide whether or not the file actually exist on the disk.
 *
 * It was tested on this particular image:
 * ./SimpleScanner gdcmData/012345.002.050.dcm
 */

#include "gdcmStrictScanner.h"
#include "gdcmSimpleSubjectWatcher.h"
#include "gdcmFileNameEvent.h"

class MyFileWatcher : public gdcm::SimpleSubjectWatcher
{
public:
    MyFileWatcher(gdcm::Subject * s, const char *comment = ""):
        gdcm::SimpleSubjectWatcher(s,comment){}
    void ShowFileName(gdcm::Subject *, const gdcm::Event &evt) override
    {
        const gdcm::FileNameEvent &pe = dynamic_cast<const gdcm::FileNameEvent&>(evt);
        const char *fn = pe.GetFileName();
        std::cout << "FileName: " << fn << " FileSize: " << gdcm::System::FileSize( fn ) << std::endl;
    }
};

int main(int argc, char *argv[])
{
    if( argc < 2 )
    {
        return 1;
    }
    const char *filename = argv[1];
    const char filename_invalid[] = "this is a file that may not exist on this disk.dcm";

    gdcm::SmartPointer<gdcm::StrictScanner> sp = new gdcm::StrictScanner;
    gdcm::StrictScanner &s = *sp;
    //gdcm::SimpleSubjectWatcher w(&s, "TestFileName" );
    MyFileWatcher w(&s, "TestFileName" );

    const gdcm::Tag tag_array[] = {
        gdcm::Tag(0x8,0x50),
        gdcm::Tag(0x8,0x51),
        gdcm::Tag(0x8,0x60),
        gdcm::Tag(0x8,0x80),
    };
    s.AddTag( tag_array[0] );
    s.AddTag( tag_array[1] );
    s.AddTag( tag_array[2] );
    s.AddTag( tag_array[3] );

    gdcm::Directory::FileNamesType filenames;
    filenames.push_back( filename );
    filenames.push_back( filename_invalid );

    if( !s.Scan( filenames ) )
    {
        return 1;
    }

    //s.Print( std::cout );

    for(gdcm::Directory::FileNamesType::const_iterator it = filenames.begin();
        it != filenames.end(); ++it )
    {
        if( s.IsKey( it->c_str() ) )

```

```

    {
        std::cout << "INFO:" << it->c_str() << " is a proper Key for the Scanner (this is a DICOM file)" << std::endl;
    }
    else
    {
        std::cout << "INFO:" << it->c_str() << " is not a proper Key for the Scanner (this is either not a DICOM file
        or file does not exist)" << std::endl;
    }
}

gdcM::StrictScanner::TagToValue const &ttv = s.GetMapping(filename);

const gdcM::Tag *ptag = tag_array;
for( ; ptag != tag_array + 3; ++ptag )
{
    gdcM::StrictScanner::TagToValue::const_iterator it = ttv.find( *ptag );
    if( it != ttv.end() )
    {
        std::cout << *ptag << " was properly found in this file" << std::endl;
        // it contains a pair of value. the first one is the actual tag, so the following is always true:
        // *ptag == it->first
        // The second part is the actual value (stored as RAW strings). You will have to reinterpret this string
        // if VR for *ptag is not VR::VRASCII !
        const char *value = it->second;
        if( *value )
        {
            std::cout << " It has the value: " << value << std::endl;
        }
        else
        {
            std::cout << " It has no value (empty)" << std::endl;
        }
    }
    else
    {
        std::cout << "Sorry " << *ptag << " could not be found in this file" << std::endl;
    }
}

return 0;
}

```

12.96 SortImage.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcM.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
/*
*/
#include "gdcMSorter.h"
#include "gdcMScanner.h"
#include "gdcMDataSet.h"
#include "gdcMAttribute.h"

bool mysort(gdcM::DataSet const & ds1, gdcM::DataSet const & ds2 )
{
    //gdcM::Attribute<0x0020,0x0013> at1; // Instance Number
    gdcM::Attribute<0x0018,0x1060> at1; // Trigger Time
    gdcM::Attribute<0x0020,0x0032> at11; // Image Position (Patient)
    at1.Set( ds1 );
    at11.Set( ds1 );
    //gdcM::Attribute<0x0020,0x0013> at2;
    gdcM::Attribute<0x0018,0x1060> at2;
    gdcM::Attribute<0x0020,0x0032> at22;
    at2.Set( ds2 );
}

```

```

    at22.Set( ds2 );
    if( at11 == at22 )
    {
        return at1 < at2;
    }
    return at11 < at22;
}

bool mysort_part1(gdcm::DataSet const & ds1, gdcm::DataSet const & ds2 )
{
    gdcm::Attribute<0x0018,0x1060> at1;
    at1.Set( ds1 );
    gdcm::Attribute<0x0018,0x1060> at2;
    at2.Set( ds2 );
    return at1 < at2;
}

bool mysort_part2(gdcm::DataSet const & ds1, gdcm::DataSet const & ds2 )
{
    gdcm::Attribute<0x0020,0x0032> at1;
    at1.Set( ds1 );
    gdcm::Attribute<0x0020,0x0032> at2;
    at2.Set( ds2 );
    return at1 < at2;
}

// technically all files are in the same Frame of Reference, so this function
// should be a no-op
bool mysort_dummy(gdcm::DataSet const & ds1, gdcm::DataSet const & ds2 )
{
    gdcm::Attribute<0x0020,0x0052> at1; // FrameOfReferenceUID
    at1.Set( ds1 );
    gdcm::Attribute<0x0020,0x0052> at2;
    at2.Set( ds2 );
    return at1 < at2;
}

int main(int argc, char *argv[])
{
    if (argc < 2 ) return 1;
    const char *dirname = argv[1];
    gdcm::Directory dir;
    unsigned int nfiles = dir.Load( dirname );

    dir.Print( std::cout );

    gdcm::Sorter sorter;
    sorter.SetSortFunction( mysort );
    sorter.Sort( dir.GetFilesNames() );

    std::cout << "Sorter:" << std::endl;
    sorter.Print( std::cout );

    gdcm::Sorter sorter2;
    sorter2.SetSortFunction( mysort_part1 );
    sorter2.StableSort( dir.GetFilesNames() );
    sorter2.SetSortFunction( mysort_part2 );
    sorter2.StableSort( sorter2.GetFilesNames() ); // IMPORTANT
    sorter2.SetSortFunction( mysort_dummy );
    sorter2.StableSort( sorter2.GetFilesNames() ); // IMPORTANT

    std::cout << "Sorter2:" << std::endl;
    sorter2.Print( std::cout );

    gdcm::Scanner s;
    s.AddTag( gdcm::Tag(0x20,0x32) ); // Image Position (Patient)
    //s.AddTag( gdcm::Tag(0x20,0x37) ); // Image Orientation (Patient)
    s.Scan( dir.GetFilesNames() );

    //s.Print( std::cout );

    // Count how many different IPP there are:
    const gdcm::Scanner::ValueType &values = s.GetValues();
    size_t nvalues = values.size();
    std::cout << "There are " << nvalues << " different type of values" << std::endl;

    //std::cout << "nfiles=" << nfiles << std::endl;
    if( nfiles % nvalues != 0 )
    {
        std::cerr << "Impossible: this is a not a proper series" << std::endl;
        return 1;
    }
}

```

```

    }
    std::cout << "Series is composed of " << (nfiles/nvalues) << " different 3D volumes" << std::endl;

    return 0;
}

```

12.97 StreamImageReaderTest.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcml.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
// This work was realised during the GSOC 2011 by Manoj Alwani

#include "gdcmlStreamImageReader.h"
#include "gdcmlFileMetaInformation.h"
#include "gdcmlSystem.h"
#include "gdcmlFilename.h"
#include "gdcmlByteSwap.h"
#include "gdcmlTrace.h"
#include "gdcmlTesting.h"
#include "gdcmlImageHelper.h"
#include "gdcmlImageReader.h"
#include "gdcmlImage.h"
#include "gdcmlMediaStorage.h"
#include "gdcmlRAWCodec.h"
#include "gdcmlJPEGLSCodec.h"
#include "gdcmlUIDGenerator.h"
#include "gdcmlStreamImageWriter.h"
#include "gdcmlAttribute.h"
#include "gdcmlFile.h"
#include "gdcmlTag.h"

bool StreamImageRead(gdcml::StreamImageWriter & theStreamWriter,
    const char* filename, const char* outfilename, int resolution)
{
    gdcml::StreamImageReader reader;

    reader.SetFileName( filename );

    if (!reader.ReadImageInformation())
    {
        std::cerr << "unable to read image information" << std::endl;
        return 1; //unable to read tags as expected.
    }
    //let's be tricky; each image will be read in portions, first the top half, then the bottom
    //that way, we can test how the stream handles fragmentation of the data
    //we could also loop this to get various different size combinations, but I'm not sure
    //that's useful, yet.
    std::vector<unsigned int> extent =
        gdcml::ImageHelper::GetDimensionsValue(reader.GetFile());
    // std::cout << extent[0];
    //at this point, these values aren't used, but may be in the future
    //unsigned short xmin = 0;
    //unsigned short xmax = extent[0];
    //unsigned short ymin = 0;
    //unsigned short ymax = extent[1];
    //unsigned short zmin = 0;
    //unsigned short zmax = extent[2];

    std::cout<< "\n Row: " << extent[0] << "\n Col : " << extent[1] << "\n Resolution : " << extent[2] << std::endl;

    int a = 1;
    for (int i=1; i<=(extent[2]-resolution);++i)

```

```

    a = a*2;

    reader.DefinePixelExtent(0, extent[0]/a, 0, extent[1]/a, resolution-1, resolution);

    unsigned long len = reader.DefineProperBufferLength();
    char* finalBuffer = new char[len];
    memset(finalBuffer, 0, sizeof(char)*len);

    if (reader.CanReadImage())
    {
        bool result = reader.Read(finalBuffer, len);
        if( !result )
        {
            std::cout << "res2 failure:" << filename << std::endl;
            delete [] finalBuffer;
            return 1;
        }
        else
        {
            std::cout<< "Able to read";
        }
    }
    else
    {
        std::cerr<< "Not able to put in buffer"<< std::endl;
    }
    /*
    //now, read in smaller buffer extents
    reader.DefinePixelExtent(xmin, xmax, ymin, ymax);
    len = reader.DefineProperBufferLength();

    char* buffer = new char[len];
    bool res2 = reader.Read(buffer, len);
    if( !res2 ){
        std::cerr << "res2 failure:" << filename << std::endl;
        return 1;
    }
    //copy the result into finalBuffer
    memcpy(finalBuffer, buffer, len);

    //now read the next half of the image
    ymin = ymax;
    ymax = extent[1];

    reader.DefinePixelExtent(xmin, xmax, ymin, ymax);

    //std::cerr << "Success to read image from file: " << filename << std::endl;
    unsigned long len2 = reader.DefineProperBufferLength();

    char* buffer2 = new char[len2];
    bool res3 = reader.Read(buffer2, len2);
    if( !res3 ){
        std::cerr << "res3 failure:" << filename << std::endl;
        return 1;
    }
    //copy the result into finalBuffer
    memcpy(&(finalBuffer[len]), buffer2, len2);

    delete [] buffer;
    delete [] buffer2;
    */

    gdcm::Writer w;
    gdcm::File &file = w.GetFile();
    gdcm::DataSet &ds = file.GetDataSet();

    file.GetHeader().SetDataSetTransferSyntax( gdcm::TransferSyntax::ExplicitVRLittleEndian );

    gdcm::UIDGenerator uid;
    gdcm::DataElement de( gdcm::Tag(0x8,0x18) ); // SOP Instance UID
    de.SetVR( gdcm::VR::UI );
    const char *u = uid.Generate();
    de.SetByteValue( u, strlen(u) );
    ds.Insert( de );

    gdcm::DataElement del( gdcm::Tag(0x8,0x16) );
    del.SetVR( gdcm::VR::UI );
    gdcm::MediaStorage ms( gdcm::MediaStorage::VLWholeSlideMicroscopyImageStorage );
    del.SetByteValue( ms.GetString(), strlen(ms.GetString()) );

```

```

ds.Insert( del );

const char mystr[] = "MONOCHROME2 ";
gdcm::DataElement de2( gdcm::Tag(0x28,0x04) );
//de.SetTag(gdcm::Tag(0x28,0x04));
de2.SetVR( gdcm::VR::CS );
de2.SetByteValue(mystr, strlen(mystr));
ds.Insert( de2 );

gdcm::Attribute<0x0028,0x0008> Number_Of_Frames = {1};
ds.Insert( Number_Of_Frames.GetAsDataElement() );

gdcm::Attribute<0x0028,0x0010> row = {extent[0]/a};//
ds.Insert( row.GetAsDataElement() );

gdcm::Attribute<0x0028,0x0011> col = {extent[1]/a};//
ds.Insert( col.GetAsDataElement() );

gdcm::Attribute<0x0028,0x0100> at = {8};
ds.Insert( at.GetAsDataElement() );

gdcm::Attribute<0x0028,0x0002> at1 = {1};//
ds.Insert( at1.GetAsDataElement() );

gdcm::Attribute<0x0028,0x0101> at2 = {8};
ds.Insert( at2.GetAsDataElement() );

gdcm::Attribute<0x0028,0x0102> at3 = {7};
ds.Insert( at3.GetAsDataElement() );
/*
ds1.Remove( gdcm::Tag(0x0028,0x0008) );

gdcm::Attribute<0x0028,0x0008> Number_Of_Frames = {1};
ds1.Insert( Number_Of_Frames.GetAsDataElement() );
*/
theStreamWriter.SetFile(file);

if (!theStreamWriter.WriteImageInformation())
{
    std::cerr << "unable to write image information" << std::endl;
    return 1; //the CanWrite function should prevent getting here, else,
    //that's a test failure
}
std::vector<unsigned int> extent1 = gdcm::ImageHelper::GetDimensionsValue(file);

unsigned short xmax = extent1[0];
unsigned short ymax = extent1[1];
unsigned short theChunkSize = 1;
unsigned short ychunk = extent1[1]/theChunkSize; //go in chunk sizes of theChunkSize
unsigned short zmax = 1;

std::cout << "\n Row: " << extent1[0] << "\n Col : " << extent1[1] << "\n Resolution : " << extent1[2] << std::endl;

if (xmax == 0 || ymax == 0)
{
    std::cerr << "Image has no size, unable to write zero-sized image." << std::endl;
    return 0;
}

int z, y, nexty;
unsigned long prevLen = 0; //when going through the char buffer, make sure to grab
//the bytes sequentially. So, store how far you got in the buffer with each iteration.

for (z = 0; z < zmax; ++z){
    for (y = 0; y < ymax; y += ychunk){
        nexty = y + ychunk;
        if (nexty > ymax) nexty = ymax;
        theStreamWriter.DefinePixelExtent(0, xmax, y, nexty, z, z+1);
        unsigned long len = theStreamWriter.DefineProperBufferLength();
        std::cout << "\n" << len;
        char* finalBuffer1 = new char[len];
        memcpy(finalBuffer1, &(finalBuffer[prevLen]), len);
        std::cout << "\nable to write";

        if (!theStreamWriter.Write(finalBuffer1, len)){
            std::cerr << "writing failure:" << "output.dcm" << " at y = " << y << " and z = " << z << std::endl;
            delete [] finalBuffer1;
            delete [] finalBuffer;
            return 1;
        }
        delete [] finalBuffer1;
    }
}

```



```

        prevLen += len;
    }
}
delete [] finalBuffer;
std::cout << "all is set";

return true;
}

int main(int argc, char *argv[])
{
    if( argc < 3 )
    {
        std::cerr << argv[0] << " input.dcm output.dcm Resolution" << std::endl;
        return 1;
    }

    const char *filename = argv[1];
    const char *outfilename = argv[2];
    char *res = argv[3];

    int resolution = atoi(res);

    gdcm::StreamImageWriter theStreamWriter;

    std::ofstream of;
    of.open( outfile, std::ios::out | std::ios::binary );
    theStreamWriter.SetStream(of);

    // else
    // First of get rid of warning/debug message
    gdcm::Trace::DebugOn();
    gdcm::Trace::WarningOn();

    if(!StreamImageRead( theStreamWriter, filename, outfile, resolution))
        return 1;

    uint16_t firstTag1 = 0xfffe;
    uint16_t secondTag1 = 0x00dd;
    uint32_t thirdTag1 = 0x00000000;
    //uint16_t fourthTag1 = 0xffff;
    const int theBufferSize = 2*sizeof(uint16_t)+sizeof(uint32_t);
    char* tmpBuffer2 = new char[theBufferSize];
    memcpy(&(tmpBuffer2[0]), &firstTag1, sizeof(uint16_t));
    memcpy(&(tmpBuffer2[sizeof(uint16_t)]), &secondTag1, sizeof(uint16_t));
    memcpy(&(tmpBuffer2[2*sizeof(uint16_t)]), &thirdTag1, sizeof(uint32_t));
    //memcpy(&(tmpBuffer2[3*sizeof(uint16_t)]), &fourthTag1, sizeof(uint16_t));
    gdcm_assert( of && !of.eof() && of.good() );
    of.write(tmpBuffer2, theBufferSize);
    of.flush();
    gdcm_assert( of );

    return 0;
}

```

12.98 TemplateEmptyImage.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
#include "gdcmFileStreamer.h"
#include "gdcmTag.h"
#include "gdcmTrace.h"
#include "gdcmImageRegionReader.h"
#include "gdcmImageHelper.h"

```

```

#include "gdcmWriter.h"
#include "gdcmImageWriter.h"
#include "gdcmTagKeywords.h"
#include "gdcmUIDGenerator.h"

int main(int argc, char *argv[])
{
    if( argc < 2 ) return 1;
    const char * filename = argv[1];
    gdcm::ImageRegionReader irr;
    irr.SetFileName( filename );
    const bool b3 = irr.ReadInformation();
    std::cout << b3 << std::endl;
    gdcm::Image & img = irr.GetImage();
    std::cout << img << std::endl;
    // const gdcm::Region & r = irr.GetRegion();
    // std::cout << r << std::endl;
    gdcm::ImageWriter w;
    gdcm::File & file = w.GetFile();
    gdcm::DataSet & ds = file.GetDataSet();

    gdcm::UIDGenerator uid;
    namespace kwd = gdcm::Keywords;
    kwd::FrameOfReferenceUID frameref;
    frameref.SetValue( uid.Generate() );
    // ContentDate
    char date[22];
    const size_t datelen = 8;
    int res = gdcm::System::GetCurrentDateTime( date );
    (void)res;
    kwd::ContentDate contentdate;
    // Do not copy the whole cstring:
    contentdate.SetValue( gdcm::DAComp( date, datelen ) );
    ds.Insert( contentdate.GetAsDataElement() );
    // ContentTime
    const size_t timelen = 6 + 1 + 6; // time + milliseconds
    kwd::ContentTime contenttime;
    // Do not copy the whole cstring:
    contenttime.SetValue( gdcm::TMComp( date+datelen, timelen ) );
    ds.Insert( contenttime.GetAsDataElement() );
    gdcm::MediaStorage ms0 = w.ComputeTargetMediaStorage();
    std::cout << ms0 << std::endl;
    kwd::SeriesNumber seriesnumber = { 1 };
    kwd::InstanceNumber instancenum = { 1 };
    kwd::StudyID studyid = { "St1" };
    kwd::PatientID patientid = { "P1" };
    kwd::SOPClassUID sopclassuid;
    kwd::PositionReferenceIndicator pri;
    //kwd::Laterality lat;
    //kwd::BodyPartExamined bodypartex = { "HEAD" };
    kwd::BodyPartExamined bodypartex = { "ANKLE" };
    kwd::PatientOrientation pator;
    kwd::BurnedInAnnotation bia = { "NO" };
    kwd::ConversionType convtype = { "SYN" };
    kwd::PresentationLUTShape plutshape = { "IDENTITY" }; // MONOCHROME2
    // gdcm will pick the Word in case Byte class is not compatible:
    gdcm::MediaStorage ms = gdcm::MediaStorage::MultiframeGrayscaleByteSecondaryCaptureImageStorage;
    sopclassuid.SetValue( ms.GetString() );
    ds.Insert( instancenum.GetAsDataElement() );
    ds.Insert( sopclassuid.GetAsDataElement() );
    ds.Insert( seriesnumber.GetAsDataElement() );
    ds.Insert( patientid.GetAsDataElement() );
    ds.Insert( studyid.GetAsDataElement() );
    ds.Insert( frameref.GetAsDataElement() );
    ds.Insert( pri.GetAsDataElement() );
    //ds.Insert( lat.GetAsDataElement() );
    ds.Insert( bodypartex.GetAsDataElement() );
    ds.Insert( pator.GetAsDataElement() );
    ds.Insert( bia.GetAsDataElement() );
    ds.Insert( convtype.GetAsDataElement() );
    ds.Insert( plutshape.GetAsDataElement() );
    // gdcm::MediaStorage ms1 = w.ComputeTargetMediaStorage();
    // std::cout << ms1 << std::endl;
    std::cout << ds << std::endl;
    gdcm::PixelFormat & pf = img.GetPixelFormat();
    pf.SetPixelRepresentation(0); // always overwrite
    img.SetSlope(1);
    img.SetIntercept(0);
    w.SetImage( img );
    w.SetFileName( "TemplateImage.dcm" );
    if( !w.Write() )

```

```

    {
        return 1;
    }

    return 0;
}

```

12.99 TraverseModules.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.
=====*/
/*
*/

#include "gdcmDefs.h"
#include "gdcmGlobal.h"
#include "gdcmIODs.h"
#include "gdcmIOD.h"
#include "gdcmMacros.h"
#include "gdcmIODEntry.h"
#include "gdcmModules.h"
#include "gdcmModule.h"
#include "gdcmAnonymizer.h"
#include "gdcmDicts.h"

int main(int , char *[])
{
    using namespace gdcm;
    static Global &g = Global::GetInstance();

    if( !g.LoadResourcesFiles() )
    {
        return 1;
    }

    static const Defs &defs = g.GetDefs();
    static const Modules &modules = defs.GetModules();
    static const IODs &iods = defs.GetIODs();
    static const Macros &macros = defs.GetMacros();
    static const Dicts &dicts = g.GetDicts();

    std::vector<Tag> tags = gdcm::Anonymizer::GetBasicApplicationLevelConfidentialityProfileAttributes();
    for( std::vector<Tag>::const_iterator tit = tags.begin(); tit != tags.end(); ++tit )
    {
        const Tag &tag = *tit;
        const DictEntry &dictentry = dicts.GetDictEntry(tag);
        std::cout << "Processing Attribute: " << tag << " " << dictentry << std::endl;

        IODs::IODMapTypeConstIterator it = iods.Begin();
        for( ; it != iods.End(); ++it )
        {
            const IODs::IODName &name = it->first;
            const IOD &iod = it->second;

            const size_t niods = iod.GetNumberOfIODs();
            // Iterate over each iod entry in order:
            for(unsigned int idx = 0; idx < niods; ++idx)
            {
                const IODEntry &iodentry = iod.GetIODEntry(idx);
                const char *ref = iodentry.GetRef();
                //Usage::UsageType ut = iodentry.GetUsageType();

                const Module &module = modules.GetModule( ref );
                if( module.FindModuleEntryInMacros(macros, tag) )

```

```

        {
            const ModuleEntry &module_entry = module.GetModuleEntryInMacros(macros,tag);
            Type type = module_entry.GetType();
            std::cout << "IOD Name: " << name << std::endl;
            std::cout << "Type: " << type << std::endl;
        }
    }
}

return 0;
}

```

12.100 VolumeSorter.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.
=====*/
/*
*/
#include "gdcmSorter.h"
#include "gdcmIPPSorter.h"
#include "gdcmScanner.h"
#include "gdcmDataSet.h"
#include "gdcmAttribute.h"
#include "gdcmTesting.h"

bool mysort1(gdcm::DataSet const & ds1, gdcm::DataSet const & ds2 )
{
    gdcm::Attribute<0x0020,0x000d> at1;
    at1.Set( ds1 );
    gdcm::Attribute<0x0020,0x000d> at2;
    at2.Set( ds2 );
    return at1 < at2;
}

bool mysort2(gdcm::DataSet const & ds1, gdcm::DataSet const & ds2 )
{
    gdcm::Attribute<0x0020,0x000e> at1;
    at1.Set( ds1 );
    gdcm::Attribute<0x0020,0x000e> at2;
    at2.Set( ds2 );
    return at1 < at2;
}

bool mysort3(gdcm::DataSet const & ds1, gdcm::DataSet const & ds2 )
{
    // This is a floating point number is the comparison ok ?
    gdcm::Attribute<0x0020,0x0037> at1;
    at1.Set( ds1 );
    gdcm::Attribute<0x0020,0x0037> at2;
    at2.Set( ds2 );
    return at1 < at2;
}

bool mysort4(gdcm::DataSet const & ds1, gdcm::DataSet const & ds2 )
{
    // Do the IPP sorting here
    gdcm::Attribute<0x0020,0x0032> ipp1;
    gdcm::Attribute<0x0020,0x0037> iop1;
    ipp1.Set( ds1 );
    iop1.Set( ds1 );
    gdcm::Attribute<0x0020,0x0032> ipp2;
    gdcm::Attribute<0x0020,0x0037> iop2;

```

```

ipp2.Set( ds2 );
iop2.Set( ds2 );
if( iop1 != iop2 )
{
    return false;
}

// else
double normal[3];
normal[0] = iop1[1]*iop1[5] - iop1[2]*iop1[4];
normal[1] = iop1[2]*iop1[3] - iop1[0]*iop1[5];
normal[2] = iop1[0]*iop1[4] - iop1[1]*iop1[3];
double dist1 = 0;
for( int i = 0; i < 3; ++i) dist1 += normal[i]*ipp1[i];
double dist2 = 0;
for( int i = 0; i < 3; ++i) dist2 += normal[i]*ipp2[i];

std::cout << dist1 << "," << dist2 << std::endl;
return dist1 < dist2;
}

int main(int argc, char *argv[])
{
    const char *extradataroot = gdcm::Testing::GetDataExtraRoot();
    std::string dir1;
    if( argc < 2 )
    {
        if( !extradataroot )
        {
            return 1;
        }
        dir1 = extradataroot;
        dir1 += "/gdcmSampleData/ForSeriesTesting/VariousIncidences/ST1";
    }
    else
    {
        dir1 = argv[1];
    }

    gdcm::Directory d;
    d.Load( dir1, true ); // recursive !
    const gdcm::Directory::FileNamesType &l1 = d.GetFileNames();
    const size_t nfiles = l1.size();
    std::cout << nfiles << std::endl;

    //if( nfiles != 280 )
    // {
    //     return 1;
    // }

    //d.Print( std::cout );

    gdcm::Scanner s0;
    const gdcm::Tag t1(0x0020,0x000d); // Study Instance UID
    const gdcm::Tag t2(0x0020,0x000e); // Series Instance UID
    //const gdcm::Tag t3(0x0010,0x0010); // Patient's Name
    s0.AddTag( t1 );
    s0.AddTag( t2 );
    //s0.AddTag( t3 );
    //s0.AddTag( t4 );
    //s0.AddTag( t5 );
    //s0.AddTag( t6 );
    bool b = s0.Scan( d.GetFileNames() );
    if( !b )
    {
        std::cerr << "Scanner failed" << std::endl;
        return 1;
    }

    //s0.Print( std::cout );

    // Only get the DICOM files:
    gdcm::Directory::FileNamesType l2 = s0.GetKeys();
    const size_t nfiles2 = l2.size();
    std::cout << nfiles2 << std::endl;

    if ( nfiles2 > nfiles )
    {
        return 1;
    }
}

```

```

    }

    gdcmm::Sorter sorter;
    sorter.SetSortFunction( mysort1 );
    sorter.StableSort( 12 );

    sorter.SetSortFunction( mysort2 );
    sorter.StableSort( sorter.GetFileNames() );

    sorter.SetSortFunction( mysort3 );
    sorter.StableSort( sorter.GetFileNames() );

    sorter.SetSortFunction( mysort4 );
    sorter.StableSort( sorter.GetFileNames() );

    //sorter.Print( std::cout );

    // Let's try to check our result:
    // assume that IPP is precise enough so that we can test floating point equality:
    size_t nvalues = 0;
{
    gdcmm::Scanner s;
    s.AddTag( gdcmm::Tag(0x20,0x32) ); // Image Position (Patient)
    //s.AddTag( gdcmm::Tag(0x20,0x37) ); // Image Orientation (Patient)
    s.Scan( d.GetFileNames() );

    //s.Print( std::cout );

    const gdcmm::Scanner::ValueType &values = s.GetValues();
    nvalues = values.size();
    std::cout << "There are " << nvalues << " different type of values" << std::endl;
    gdcmm::assert( nfiles2 % nvalues == 0 );
    std::cout << "Series is composed of " << (nfiles/nvalues) << " different 3D volumes" << std::endl;
}

    gdcmm::Directory::FileNamesType sorted_files = sorter.GetFileNames();

    // Which means we can take nvalues files at a time and execute gdcmm::IPPSorter on it:
    gdcmm::IPPSorter ippsorter;
    gdcmm::Directory::FileNamesType sub( sorted_files.begin(), sorted_files.begin() + nvalues);
    std::cout << sub.size() << std::endl;
    std::cout << sub[0] << std::endl;
    std::cout << sub[nvalues-1] << std::endl;
    ippsorter.SetComputeZSpacing( false );
    if( !ippsorter.Sort( sub ) )
    {
        std::cerr << "Could not sort" << std::endl;
        return 1;
    }

    std::cout << "IPPSorter:" << std::endl;
    ippsorter.Print( std::cout );

    return 0;
}

```

12.101 csa2img.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcmm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
/*
 * I do not know what the format is, just guessing from info found on the net:
 */

```

```

* http://atonal.ucdavis.edu/matlab/fmri/spm5/spm_dicom_convert.m
*
* This example is an attempt at understanding the format used by SIEMENS
* their "SIEMENS CSA NON-IMAGE" DICOM file (1.3.12.2.1107.5.9.1)
*
* Everything done in this code is for the sole purpose of writing interoperable
* software under Sect. 1201 (f) Reverse Engineering exception of the DMCA.
* If you believe anything in this code violates any law or any of your rights,
* please contact us (gdcm-developers@lists.sourceforge.net) so that we can
* find a solution.
*
*/
#include "gdcmReader.h"
#include "gdcmImageReader.h"
#include "gdcmImageWriter.h"
#include "gdcmCSAHeader.h"
#include "gdcmAttribute.h"
#include "gdcmPrivateTag.h"

#include <math.h>

int main(int argc, char *argv [])
{
    if( argc < 2 ) return 1;
    // gdcmDataExtra/gdcmNonImageData/exCSA_Non-Image_Storage.dcm
    // PHANTOM.MR.CARDIO_COEUR_S_SEQUENCE_DE_REP_RAGE.9.257.2008.03.20.14.53.25.578125.43151705.IMA
    const char *filename = argv[1];

    gdcm::Reader reader; // Do not use ImageReader
    reader.SetFileName( filename );
    if( !reader.Read() )
    {
        std::cerr << "Failed to read: " << filename << std::endl;
        return 1;
    }

    gdcm::CSAHeader csa;
    const gdcm::DataSet& ds = reader.GetFile().GetDataSet();

    const gdcm::PrivateTag &t1 = csa.GetCSAImageHeaderInfoTag();
    //std::cout << t1 << std::endl;
    //const gdcm::PrivateTag &t2 = csa.GetCSASeriesHeaderInfoTag();

    if( ds.FindDataElement( t1 ) )
    {
        csa.LoadFromDataElement( ds.GetDataElement( t1 ) );
        csa.Print( std::cout );
    }

    int dims[2] = {};
    if( csa.FindCSAElementByName( "Columns" ) )
    {
        const gdcm::CSAElement &cсаel = csa.GetCSAElementByName( "Columns" );
        std::cout << cсаel << std::endl;
        //const gdcm::ByteValue *bv = cсаel.GetByteValue();
        gdcm::Element<gdcm::VR::IS, gdcm::VM::VM1> el;
        el.Set( cсаel.GetValue() );
        dims[0] = el.GetValue();
        std::cout << "Columns:" << el.GetValue() << std::endl;
    }

    if( csa.FindCSAElementByName( "Rows" ) )
    {
        const gdcm::CSAElement &cсаel2 = csa.GetCSAElementByName( "Rows" );
        std::cout << cсаel2 << std::endl;
        gdcm::Element<gdcm::VR::IS, gdcm::VM::VM1> el2;
        el2.Set( cсаel2.GetValue() );
        dims[1] = el2.GetValue();
        std::cout << "Rows:" << el2.GetValue() << std::endl;
    }

    double spacing[2] = { 1. , 1. };
    bool spacingfound = false;
    if( csa.FindCSAElementByName( "PixelSpacing" ) )
    {
        const gdcm::CSAElement &cсаel3 = csa.GetCSAElementByName( "PixelSpacing" );
        if( !cсаel3.IsEmpty() )
        {
            std::cout << cсаel3 << std::endl;
            gdcm::Element<gdcm::VR::DS, gdcm::VM::VM2> el3;
            el3.Set( cсаel3.GetValue() );
            spacing[0] = el3.GetValue();

```

```

        spacing[1] = el3.GetValue(1);
        std::cout << "PixelSpacing:" << el3.GetValue() << ", " << el3.GetValue(1) << std::endl;
        spacingfound = true;
    }
}

if( !spacingfound )
{
    std::cerr << "Problem with PixelSpacing" << std::endl;
    //return 1;
}
if( !dims[0] || !dims[1] )
{
    std::cerr << "Problem with dims" << std::endl;
    return 1;
}

gdcm::ImageWriter writer;

gdcm::Image &image = writer.GetImage();
image.SetNumberOfDimensions( 2 ); // good default
image.SetDimension(0, dims[0] );
image.SetDimension(1, dims[1] );
image.SetSpacing(0, spacing[0] );
image.SetSpacing(1, spacing[1] );
gdcm::PixelFormat pixeltype = gdcm::PixelFormat::INT16; // bytewidth = spm_type('int16','bits')/8;

//unsigned long l = image.GetBufferLength();
//const int p = 1 / (dims[0] * dims[1]);

//image.SetNumberOfDimensions( 3 );
//image.SetDimension(2, p / pixeltype.GetPixelSize() );

gdcm::PhotometricInterpretation pi;
pi = gdcm::PhotometricInterpretation::MONOCHROME2;
//pixeltype.SetSamplesPerPixel( );
image.SetPhotometricInterpretation( pi );
image.SetPixelFormat( pixeltype );
//image.SetIntercept( inputimage.GetIntercept() );
//image.SetSlope( inputimage.GetSlope() );

//gdcm::DataElement pixeldata( gdcm::Tag(0x7fe1,0x1010) );
//pixeldata.SetByteValue( &outbuf[0], outbuf.size() );
gdcm::PrivateTag csanonimaget(0x7fe1,0x10,"SIEMENS CSA NON-IMAGE");
const gdcm::DataElement &pixeldata = ds.GetDataElement( csanonimaget );
image.SetDataElement( pixeldata );

std::string outfilename = "outcsa.dcm";
//writer.SetFile( reader.GetFile() );
writer.SetFileName( outfilename.c_str() );
if( !writer.Write() )
{
    std::cerr << "could not write: " << outfilename << std::endl;
    return 1;
}

return 0;
}

```

12.102 iU22tomultisc.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
/*

```



```

* iU22 Raw Data extractor
*/
#include "gdcmReader.h"
#include "gdcmImageWriter.h"
#include "gdcmAttribute.h"
#include "gdcmPrivateTag.h"

#include <math.h>

int main(int argc, char *argv [])
{
    if( argc < 2 ) return 1;
    // IM_001
    const char *filename = argv[1];

    gdcm::Reader reader; // Do not use ImageReader
    reader.SetFileName( filename );
    if( !reader.Read() )
    {
        std::cerr << "Failed to read: " << filename << std::endl;
        return 1;
    }

    // * The data is simply 8-bit unsigned in the obvious x/y/z order
    // * 200D,300B contains the data
    // * 200D,3001 contains the no. of voxels (416,412,256 in this case)
    // * 200D,3003 contains the voxel sizes (0.156184527398215 /
    // 0.1223749613981957 / 0.328479990704639 in this case)

    const gdcm::File &file = reader.GetFile();
    const gdcm::DataSet &ds = file.GetDataSet();
    const gdcm::PrivateTag trawdataus( 0x200d, 0x0b, "Philips US Imaging DD 033" );
    const gdcm::DataElement &rawdataus = ds.GetDataElement( trawdataus );

    const gdcm::PrivateTag tcolsrowsframes( 0x200d, 0x01, "Philips US Imaging DD 036" );
    const gdcm::DataElement &colsrowsframes = ds.GetDataElement( tcolsrowsframes );
    // const gdcm::PrivateTag tcolsrowsframes( 0x200d, 0x02, "Philips US Imaging DD 036" );
    // this is just a duplicate previous tag.
    const gdcm::PrivateTag tvoxelspacing( 0x200d, 0x03, "Philips US Imaging DD 036" );
    const gdcm::DataElement &voxelspacing = ds.GetDataElement( tvoxelspacing );

    gdcm::Element<gdcm::VR::DS,gdcm::VM::VM3> dims; // Use DS to interpret value stored in LO
    dims.SetFromDataElement( colsrowsframes );

    gdcm::Element<gdcm::VR::DS,gdcm::VM::VM3> spacing;
    spacing.SetFromDataElement( voxelspacing );

    gdcm::ImageWriter writer;

    gdcm::Image &image = writer.GetImage();
    image.SetNumberOfDimensions( 3 ); // good default
    image.SetDimension(0, (unsigned int)dims[0] );
    image.SetDimension(1, (unsigned int)dims[1] );
    image.SetDimension(2, (unsigned int)dims[2] );
    image.SetSpacing(0, spacing[0] );
    image.SetSpacing(1, spacing[1] );
    image.SetSpacing(2, spacing[2] );
    gdcm::PixelFormat pixeltype = gdcm::PixelFormat::UINT8;

    gdcm::PhotometricInterpretation pi;
    pi = gdcm::PhotometricInterpretation::MONOCHROME2;
    image.SetPhotometricInterpretation( pi );
    image.SetPixelFormat( pixeltype );

    image.SetDataElement( rawdataus );

    std::string outfilename = "outiu22.dcm";

    gdcm::DataElement de( gdcm::Tag(0x8,0x16) ); // SOP Class UID
    de.SetVR( gdcm::VR::UI );
    gdcm::MediaStorage ms(
        gdcm::MediaStorage::UltrasoundMultiFrameImageStorage );
    // gdcm::MediaStorage::MultiframeGrayscaleByteSecondaryCaptureImageStorage );
    de.SetByteValue( ms.GetString(), (uint32_t)strlen(ms.GetString()) );
    writer.GetFile().GetDataSet().Replace( de );

    writer.SetFileName( outfilename.c_str() );
    if( !writer.Write() )
    {
        std::cerr << "could not write: " << outfilename << std::endl;
        return 1;
    }
}

```

```

    }

    return 0;
}

```

12.103 pmsct_rgb1.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcml.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.
=====*/

/*
 * This example shows how to rewrite a ELSCINT1/PMSCT_RGB1 compressed
 * image so that it is readable by most 3rd party software (DICOM does
 * not specify this particular encoding).
 * This is required for the sake of interoperability with any standard
 * conforming DICOM system.
 *
 * Everything done in this code is for the sole purpose of writing interoperable
 * software under Sect. 1201 (f) Reverse Engineering exception of the DMCA.
 * If you believe anything in this code violates any law or any of your rights,
 * please contact us (gdcml-developers@lists.sourceforge.net) so that we can
 * find a solution.
 *
 * Everything you do with this code is at your own risk, since decompression
 * algorithm was not written from specification documents.
 *
 * Special thanks to:
 * Jean-Pierre Roux for providing the sample datasets
 */
#include "gdcmlReader.h"
#include "gdcmlPrivateTag.h"
#include "gdcmlAttribute.h"
#include "gdcmlImageWriter.h"

void delta_decode(const unsigned char *data_in, size_t data_size,
                  std::vector<unsigned char> &new_stream, unsigned short pc, size_t w, size_t h)
{
    const size_t plane_size = h * w;
    const size_t outputlen = 3 * plane_size;
    new_stream.resize( outputlen );

    gdcml_assert( data_size != outputlen );
    if( data_size == outputlen )
    {
        return;
    }
    typedef unsigned char byte;
    enum {
        COLORMODE   = 0x81,
        ESCMODE     = 0x82,
        REPEATMODE  = 0x83
    };

    const byte* src = (const byte*)data_in;
    byte* dest = (byte*)new_stream.data();
    union { byte gray; byte rgb[3]; } pixel;
    pixel.rgb[0] = pixel.rgb[1] = pixel.rgb[2] = 0;
    // always start in grayscale mode
    bool graymode = true;
    size_t dx = 1;
    size_t dy = 3;
    // algorithm works with both planar configuration
    // It does produce surprising greenish background color for planar
    // configuration is 0, while the nested Icon SQ display a nice black
    // background

```

```

if (pc)
{
    dx = plane_size;
    dy = 1;
}
size_t ps = plane_size;

// The following is highly unoptimized as we have nested if statement in a while loop
// we need to switch from one algorithm to the other (RGB <-> GRAY)
while (ps)
{
    // next byte:
    byte b = *src++;
    gdcn_assert( src < data_in + data_size );
    // mode selection:
    switch ( b )
    {
        case ESCMODE:
            // Used to treat a byte 81/82/83 as a normal byte
            if (graymode)
            {
                pixel.gray += *src++;
                dest[0*dx] = pixel.gray;
                dest[1*dx] = pixel.gray;
                dest[2*dx] = pixel.gray;
            }
            else
            {
                pixel.rgb[0] += *src++;
                pixel.rgb[1] += *src++;
                pixel.rgb[2] += *src++;
                dest[0*dx] = pixel.rgb[0];
                dest[1*dx] = pixel.rgb[1];
                dest[2*dx] = pixel.rgb[2];
            }
            dest += dy;
            ps--;
            break;
        case REPEATMODE:
            // repeat mode (RLE)
            b = *src++;
            ps -= b;
            if (graymode)
            {
                while (b-- > 0)
                {
                    dest[0*dx] = pixel.gray;
                    dest[1*dx] = pixel.gray;
                    dest[2*dx] = pixel.gray;
                    dest += dy;
                }
            }
            else
            {
                while (b-- > 0)
                {
                    dest[0*dx] = pixel.rgb[0];
                    dest[1*dx] = pixel.rgb[1];
                    dest[2*dx] = pixel.rgb[2];
                    dest += dy;
                }
            }
            break;
        case COLORMODE:
            // We are switching from one mode to the other. The stream contains an intermixed
            // compression of RGB codec and GRAY codec. Each one not knowing of the other
            // reset old value to 0.
            if (graymode)
            {
                graymode = false;
                pixel.rgb[0] = pixel.rgb[1] = pixel.rgb[2] = 0;
            }
            else
            {
                graymode = true;
                pixel.gray = 0;
            }
            break;
        default:
            // This is identical to ESCMODE, it would be nicer to use fall-through
            if (graymode)

```

```

        {
            pixel.gray += b;
            dest[0*dx] = pixel.gray;
            dest[1*dx] = pixel.gray;
            dest[2*dx] = pixel.gray;
        }
        else
        {
            pixel.rgb[0] += b;
            pixel.rgb[1] += *src++;
            pixel.rgb[2] += *src++;
            dest[0*dx] = pixel.rgb[0];
            dest[1*dx] = pixel.rgb[1];
            dest[2*dx] = pixel.rgb[2];
        }
        dest += dy;
        ps--;
        break;
    } // end switch
} // end while
}

int main(int argc, char *argv [])
{
    if( argc < 2 ) return 1;
    const char *filename = argv[1];
    gdcm::Reader reader;
    reader.SetFileName( filename );
    if( !reader.Read() )
    {
        std::cerr << "Failed to read: " << filename << std::endl;
        return 1;
    }
    const gdcm::DataSet& ds = reader.GetFile().GetDataSet();

    // (07a1,1011) CS [PMSCT_RGB1] # 10,1 Tamar Compression Type
    const gdcm::PrivateTag tcompressiontype(0x07a1,0x0011,"ELSCINT1");
    if( !ds.FindDataElement( tcompressiontype ) ) return 1;
    const gdcm::DataElement& compressiontype = ds.GetDataElement( tcompressiontype );
    if ( compressiontype.IsEmpty() ) return 1;
    const gdcm::ByteValue * bv = compressiontype.GetByteValue();
    std::string comprle = "PMSCT_RLE1";
    std::string comprgb = "PMSCT_RGB1";
    bool isrle = false;
    bool isrgb = false;
    if( strncmp( bv->GetPointer(), comprle.c_str(), comprle.size() ) == 0 )
    {
        isrle = true;
        return 1;
    }
    if( strncmp( bv->GetPointer(), comprgb.c_str(), comprgb.size() ) == 0 )
    {
        isrgb = true;
    }
    if( !isrgb && !isrle ) return 1;

    const gdcm::PrivateTag tcompressedpixeldata(0x07a1,0x000a,"ELSCINT1");
    if( !ds.FindDataElement( tcompressedpixeldata ) ) return 1;
    const gdcm::DataElement& compressionpixeldata = ds.GetDataElement( tcompressedpixeldata );
    if ( compressionpixeldata.IsEmpty() ) return 1;
    const gdcm::ByteValue * bv2 = compressionpixeldata.GetByteValue();

    gdcm::Attribute<0x0028,0x0006> at0;
    at0.SetFromDataSet( ds );
    gdcm::Attribute<0x0028,0x0010> at1;
    at1.SetFromDataSet( ds );
    gdcm::Attribute<0x0028,0x0011> at2;
    at2.SetFromDataSet( ds );

    std::vector<unsigned char> buffer;
    delta_decode((const unsigned char*)bv2->GetPointer(), bv2->GetLength(), buffer,
        at0.GetValue(), at1.GetValue(), at2.GetValue() );

    gdcm::DataElement pixeldata( gdcm::Tag(0x7fe0,0x0010) );
    pixeldata.SetVR( gdcm::VR::OW );
    pixeldata.SetByteValue( (char*)buffer.data(), (uint32_t)buffer.size() );
    // TODO we should check that decompress byte buffer match the expected size (row*col*...)

    // Add the pixel data element

```

```

reader.GetFile().GetDataSet().Replace( pixeldata );

reader.GetFile().GetHeader().SetDataSetTransferSyntax(
    gdcm::TransferSyntax::ExplicitVRLittleEndian);
gdcm::Writer writer;
writer.SetFile( reader.GetFile() );

// Cleanup stuff:
// remove the compressed pixel data:
// FIXME: should I remove more private tags ? all of them ?
// oh well this is just an example
// use gdcm::Anonymizer::RemovePrivateTags if needed...
writer.GetFile().GetDataSet().Remove( compressionpixeldata.GetTag() );
std::string outfilename;
if (argc > 2)
    outfilename = argv[2];
else
    outfilename = "outrgb.dcm";
writer.SetFileName( outfilename.c_str() );
if( !writer.Write() )
{
    std::cerr << "Failed to write" << std::endl;
    return 1;
}

std::cout << "success !" << std::endl;

return 0;
}

```

12.104 rle2img.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.
=====*/
/*
 * This example shows how to rewrite a ELSCINT1/PMSCT_RLE1 compressed
 * image so that it is readable by most 3rd party software (DICOM does
 * not specify this particular encoding).
 * This is required for the sake of interoperability with any standard
 * conforming DICOM system.
 *
 * Everything done in this code is for the sole purpose of writing interoperable
 * software under Sect. 1201 (f) Reverse Engineering exception of the DMCA.
 * If you believe anything in this code violates any law or any of your rights,
 * please contact us (gdcm-developers@lists.sourceforge.net) so that we can
 * find a solution.
 *
 * Everything you do with this code is at your own risk, since decompression
 * algorithm was not written from specification documents.
 *
 * Special thanks to:
 * Mauro Maiorca for bringing to our attention on this new ELSCINT1
 * compression algorithm : PMSCT_RLE1 (different from the 'LOSSLESS RICE')
 * See post at:
 * http://groups.google.com/group/comp.protocols.dicom/msg/f2b99bf706a7f8ca
 *
 * Thanks to Jesus Spinola, for more datasets,
 * http://www.itk.org/pipermail/insight-users/2008-April/025571.html
 *
 * And last but not least, a very big thank to Ivo van Poorten, without
 * whom we would still be looking at this compressed byte stream as if
 * it was RLE compressed.
 */
#include "gdcmReader.h"
#include "gdcmPrivateTag.h"

```

```

#include "gdcmAttribute.h"
#include "gdcmImageWriter.h"

/* FIXME: Why is PhilipsLosslessRice.dcm a 512x512 image ... */
void delta_decode(const char *inbuffer, size_t length, std::vector<unsigned short> &output)
{
    // RLE pass
    std::vector<char> temp;
    for(size_t i = 0; i < length; ++i)
    {
        if( inbuffer[i] == (char)0xa5 )
        {
            //unsigned char repeat = (unsigned char)inbuffer[i+1] + 1;
            //gdcm_assert( (unsigned char)inbuffer[i+1] != 255 );
            int repeat = (unsigned char)inbuffer[i+1] + 1;
            char value = inbuffer[i+2];
            while(repeat)
            {
                temp.push_back( value );
                --repeat;
            }
            i+=2;
        }
        else
        {
            temp.push_back( inbuffer[i] );
        }
    }

    // Delta encoding pass
    unsigned short delta = 0;
    for(size_t i = 0; i < temp.size(); ++i)
    {
        if( temp[i] == 0x5a )
        {
            unsigned char v1 = (unsigned char)temp[i+1];
            unsigned char v2 = (unsigned char)temp[i+2];
            unsigned short value = (unsigned short)(v2 * 256 + v1);
            output.push_back( value );
            delta = value;
            i+=2;
        }
        else
        {
            unsigned short value = (unsigned short)((signed char)temp[i] + delta);
            output.push_back( value );
            delta = value;
        }
        //gdcm_assert( output[output.size()-1] == ref[output.size()-1] );
    }

    if ( output.size() % 2 )
    {
        output.resize( output.size() - 1 );
    }
    std::cout << length << " -> " << output.size() * 2 << std::endl;
}

int main(int argc, char *argv [])
{
    if( argc < 2 )
    {
        std::cerr << argv[0] << "input.dcm [output.dcm]" << std::endl;
        std::cerr << "will default to 'out.rle.dcm' unless output.dcm is specified."
        << std::endl;
        return 1;
    }
    const char *filename = argv[1];
    gdcm::Reader reader;
    reader.SetFileName( filename );
    if( !reader.Read() )
    {
        std::cerr << "Failed to read: " << filename << std::endl;
        return 1;
    }
    const gdcm::DataSet& ds = reader.GetFile().GetDataSet();

    // (07a1,1011) CS [PMSCT_RLE1] # 10,1 Tamar Compression Type
    const gdcm::PrivateTag tcompressiontype(0x07a1,0x0011,"ELSCINT1");
    if( !ds.FindDataElement( tcompressiontype ) ) return 1;
    const gdcm::DataElement& compressiontype = ds.GetDataElement( tcompressiontype );

```

```

if ( compressiontype.IsEmpty() ) return 1;
const gdcm::ByteValue * bv = compressiontype.GetByteValue();
std::string comprle = "PMSCT_RLE1";
std::string comprgb = "PMSCT_RGB1";
bool isrle = false;
bool isrgb = false;
if( strcmp( bv->GetPointer(), comprle.c_str(), comprle.size() ) == 0 )
{
    isrle = true;
}
if( strcmp( bv->GetPointer(), comprgb.c_str(), comprgb.size() ) == 0 )
{
    isrgb = true;
    std::cerr << "See: pmsct_rgb1.cxx instead" << std::endl;
    return 1;
}
if( !isrgb && !isrle ) return 1;

// check if compressed pixel data reside in private or standard tag
const gdcm::PrivateTag tprivatepixeldata(0x07a1,0x100a,"ELSCINT1");
const gdcm::Tag tstandardpixeldata(0x7fe0, 0x0010);
gdcm::Tag tpixeldata;
if(ds.FindDataElement(tprivatepixeldata)) tpixeldata = tprivatepixeldata;
else if(ds.FindDataElement(tstandardpixeldata)) tpixeldata = tstandardpixeldata;
if(!ds.FindDataElement(tpixeldata)) return 1;

const gdcm::DataElement& compressionpixeldata = ds.GetDataElement( tpixeldata);
if ( compressionpixeldata.IsEmpty() ) return 1;
const gdcm::ByteValue * bv2 = compressionpixeldata.GetByteValue();

gdcm::Attribute<0x0028,0x0010> at1;
at1.SetFromDataSet( ds );
gdcm::Attribute<0x0028,0x0011> at2;
at2.SetFromDataSet( ds );

gdcm::DataElement pixeldata;
// if standard voxel data element does not exist, create it
if( !reader.GetFile().GetDataSet().FindDataElement( tpixeldata ) )
{
    pixeldata = gdcm::DataElement( tpixeldata, 0, gdcm::VR::OW );
}
else{
    pixeldata = reader.GetFile().GetDataSet().GetDataElement( tpixeldata );
}

pixeldata.SetVR( gdcm::VR::OW );
gdcm::VL bv2l = bv2->GetLength();
gdcm::VL at1l = at1.GetValue() * at2.GetValue() * 2; /* sizeof(unsigned short) == 2 */
// Handle special case that is not compressed:
if( bv2l == at1l )
{
    pixeldata.SetByteValue( bv2->GetPointer(), bv2->GetLength() );
}
else
{
    std::vector<unsigned short> buffer;
    delta_decode(bv2->GetPointer(), bv2->GetLength(), buffer);
    pixeldata.SetByteValue( (char*)buffer.data(), (uint32_t)(buffer.size() * sizeof( unsigned short )) );
}
// TODO we should check that decompress byte buffer match the expected size (row*col*...)

// Add the pixel data element
if( reader.GetFile().GetDataSet().FindDataElement( tpixeldata ) )
{
    reader.GetFile().GetDataSet().Replace( pixeldata );
}
else
{
    reader.GetFile().GetDataSet().ReplaceEmpty( pixeldata );
}

reader.GetFile().GetHeader().SetDataSetTransferSyntax(
    gdcm::TransferSyntax::ExplicitVRLittleEndian);
gdcm::Writer writer;
writer.SetFile( reader.GetFile() );

// Cleanup stuff:
// This makes the code equivalent to Philips workstation IntelliSpace Portal
if( writer.GetFile().GetDataSet().FindDataElement( tcompressiontype ) )
{

```

```

    writer.GetFile().GetDataSet().Remove( gdcm::Tag(0x07a1,0x1011) );
}
if( writer.GetFile().GetDataSet().FindDataElement( tprivatepixeldata ) )
{
    writer.GetFile().GetDataSet().Remove( gdcm::Tag(0x07a1,0x100a) );
}

std::string outfilename;
if (argc > 2)
    outfilename = argv[2];
else
    outfilename = "outrole.dcm";
writer.SetFileName( outfilename.c_str() );
if( !writer.Write() )
{
    std::cerr << "Failed to write" << std::endl;
    return 1;
}

std::cout << "success !" << std::endl;

return 0;
}

```

12.105 uid_unique.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.
=====*/
#include "gdcmUIDGenerator.h"

#include <iostream>
#include <string>
#include <set>

int main()
{
    gdcm::UIDGenerator uid;
    //const char myroot[] = "9876543210.9876543210.9876543210.9876543210.9876543210"; // fails in ~40000 tries
    const char myroot[] = "9876543210.9876543210.9876543210";
    uid.SetRoot( myroot );
    std::set<std::string> uids;
    uint64_t wrap = 0;
    uint64_t c = 0;
    while(true)
    {
        const char *unique = uid.Generate();
        //std::cout << unique << std::endl;
        if( c % 10000 == 0 )
        {
            std::cout << "wrap=" << wrap << ",c=" << c << std::endl;
        }
        ++c;
        if( c == 0 )
        {
            wrap++;
        }
        if ( uids.count(unique) == 1 )
        {
            std::cerr << "Failed with: " << unique << std::endl;
            return 1;
        }
        uids.insert( unique );
    }
}

```


12.106 DecompressImage.java

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.
=====*/

/*
 * This example will take in a DICOM file, and tries to decompress it (actually write it
 * as ImplicitVRLittleEndian Transfer Syntax).
 *
 * Compilation:
 * $ CLASSPATH=gdcm.jar javac ../../gdcm/Examples/Java/DecompressImage.java -d .
 *
 * Usage:
 * $ LD_LIBRARY_PATH=. CLASSPATH=gdcm.jar:. java DecompressImage gdcmData/012345.002.050.dcm out.dcm
 */
import gdcm.*;

public class DecompressImage
{
    public static void main(String[] args) throws Exception
    {
        String file1 = args[0];
        String file2 = args[1];
        ImageReader reader = new ImageReader();
        reader.SetFileName( file1 );
        boolean ret = reader.Read();
        if( !ret )
        {
            throw new Exception("Could not read: " + file1 );
        }

        ImageChangeTransferSyntax change = new ImageChangeTransferSyntax();
        change.SetTransferSyntax( new TransferSyntax(TransferSyntax.TSType.ImplicitVRLittleEndian) );
        change.SetInput( reader.GetImage() );
        if( !change.Change() )
        {
            throw new Exception("Could not change: " + file1 );
        }

        Image out = change.GetOutput();
        System.out.println( out.toString() );

        // Set the Source Application Entity Title
        FileMetaInformation.SetSourceApplicationEntityTitle( "Just For Fun" );

        ImageWriter writer = new ImageWriter();
        writer.SetFileName( file2 );
        writer.SetFile( reader.GetFile() );
        writer.SetImage( out );
        ret = writer.Write();
        if( !ret )
        {
            throw new Exception("Could not write: " + file2 );
        }
    }
}

```

12.107 DecompressPixmap.java

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre

```

All rights reserved.
See Copyright.txt or <http://gdcm.sourceforge.net/Copyright.html> for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

```

=====*/

/*
 * This example will take in a DICOM file, and tries to decompress it (actually write it
 * as ImplicitVRLittleEndian Transfer Syntax).
 *
 * Compilation:
 * $ CLASSPATH=gdcm.jar javac ../../gdcm/Examples/Java/DecompressPixmap.java -d .
 *
 * Usage:
 * $ LD_LIBRARY_PATH=. CLASSPATH=gdcm.jar:. java DecompressPixmap gdcmData/012345.002.050.dcm out.dcm
 */
import gdcm.*;

public class DecompressPixmap
{
    public static void main(String[] args) throws Exception
    {
        String file1 = args[0];
        String file2 = args[1];
        PixmapReader reader = new PixmapReader();
        reader.SetFileName( file1 );
        boolean ret = reader.Read();
        if( !ret )
        {
            throw new Exception("Could not read: " + file1 );
        }

        ImageChangeTransferSyntax change = new ImageChangeTransferSyntax();
        change.SetTransferSyntax( new TransferSyntax(TransferSyntax.TSType.ImplicitVRLittleEndian) );
        PixmapToPixmapFilter filter = (PixmapToPixmapFilter)change;
        filter.SetInput( reader.GetPixmap() );
        if( !change.Change() )
        {
            throw new Exception("Could not change: " + file1 );
        }

        // The following does not work in Java/swig 2.0.7
        //Pixmap p = ((PixmapToPixmapFilter)change).GetOutput();
        Pixmap p = change.GetOutputAsPixmap(); // be explicit
        //System.out.println( p.toString() );

        // Set the Source Application Entity Title
        FileMetaInformation.SetSourceApplicationEntityTitle( "Just For Fun" );

        PixmapWriter writer = new PixmapWriter();
        writer.SetFileName( file2 );
        writer.SetFile( reader.GetFile() );
        writer.SetImage( p );
        ret = writer.Write();
        if( !ret )
        {
            throw new Exception("Could not write: " + file2 );
        }
    }
}

```

12.108 ExtractImageRegion.java

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even

```

```

        the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
        PURPOSE. See the above copyright notice for more information.

=====*/

/*
 * This small code shows how to use the gdcm.ImageRegionReader API
 * In this example we are taking each frame by frame and dump them to
 * /tmp/frame.raw.
 *
 * Usage:
 * $ LD_LIBRARY_PATH=. CLASSPATH=gdcm.jar:. java ExtractImageRegion input.dcm
 */
import gdcm.*;
import java.io.FileOutputStream;

public class ExtractImageRegion
{
    public static void main(String[] args) throws Exception
    {
        String filename = args[0];

        // instantiate the reader:
        ImageRegionReader reader = new ImageRegionReader();
        reader.SetFileName( filename );

        // pull DICOM info:
        if (!reader.ReadInformation()) return;
        // Get file infos
        File f = reader.GetFile();

        // get some info about image
        UIntArrayType dims = ImageHelper.GetDimensionsValue(f);
        PixelFormat pf = ImageHelper.GetPixelFormatValue (f);
        int pixelsize = pf.GetPixelSize();

        // buffer to get the pixels
        long buffer_length = dims.get(0) * dims.get(1) * pixelsize;
        byte[] buffer = new byte[ (int)buffer_length ];

        // define a simple box region.
        BoxRegion box = new BoxRegion();
        for (int z = 0; z < dims.get(2); z++)
        {
            // Define that I want the image 0, full size (dimx x dimy pixels)
            // and do that for each z:
            box.SetDomain(0, dims.get(0) - 1, 0, dims.get(1) - 1, z, z);
            //System.Console.WriteLine( box.toString() );
            reader.SetRegion( box );

            // reader will try to load the uncompressed image region into buffer.
            // the call returns an error when buffer.Length is too small. For instance
            // one can call:
            // long buf_len = reader.ComputeBufferLength(); // take into account pixel size
            // to get the exact size of minimum buffer
            if (reader.ReadIntoBuffer(buffer, buffer_length))
            {
                FileOutputStream fos = new FileOutputStream("/tmp/frame.raw");
                fos.write(buffer);
                fos.close();
            }
            else
            {
                throw new Exception("can't read pixels error");
            }
        }
    }
}

```

12.109 FileAnonymize.java

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

```

Copyright (c) 2006-2011 Mathieu Malaterre
 All rights reserved.
 See Copyright.txt or <http://gdc.sourceforge.net/Copyright.html> for details.

This software is distributed WITHOUT ANY WARRANTY; without even
 the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
 PURPOSE. See the above copyright notice for more information.

```

=====*/

import gdc.*;

public class FileAnonymize
{
    public static class MyWatcher extends SimpleSubjectWatcher
    {
        public MyWatcher(Subject s) { super(s,"Override String"); }
        protected void ShowProgress(Subject caller, Event evt)
        {
            ProgressEvent pe = ProgressEvent.Cast(evt);
            System.out.println( "This is my progress: " + pe.GetProgress() );
        }
    }

    public static void main(String[] args) throws Exception
    {
        String input = args[0];
        String output = args[1];

        FileAnonymizer fa = new FileAnonymizer();
        fa.SetInputFileName( input );
        fa.SetOutputFileName( output );

        // Empty Operations
        // It will create elements, since those tags are non-registered public elements (2011):
        fa.Empty( new Tag(0x0008,0x1313) );
        fa.Empty( new Tag(0x0008,0x1317) );
        // Remove Operations
        // The following Tag are actually carefully chosen, since they refer to SQ:
        fa.Remove( new Tag(0x0008,0x2112) );
        fa.Remove( new Tag(0x0008,0x9215) );
        // Replace Operations
        // do not call replace operation on SQ attribute !
        fa.Replace( new Tag(0x0018,0x5100), "MYVALUE " );
        fa.Replace( new Tag(0x0008,0x1160), "MYOTHERVAL" );

        if( !fa.Write() )
        {
            System.out.println( "Could not write" );
            return;
        }

        System.out.println( "success" );
    }
}

```

12.110 HelloSimple.java

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdc.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/

/*
 * Compilation:
 * $ CLASSPATH=gdc.jar javac ../../gdc/Examples/Java/HelloSimple.java -d .
 *
 * Usage:

```

```

* $ LD_LIBRARY_PATH=. CLASSPATH=gdcml.jar:. java HelloSimple gdcmlData/012345.002.050.dcm
*/
import gdcml.*;

public class HelloSimple
{
    public static void main(String[] args) throws Exception
    {
        String filename = args[0];
        Reader reader = new Reader();
        reader.SetFileName( filename );
        boolean ret = reader.Read();
        if( !ret )
        {
            throw new Exception("Could not read: " + filename );
        }
        File f = reader.GetFile();
        DataSet ds = f.GetDataSet();

        System.out.println( ds.toString() );

        System.out.println("Success reading: " + filename );
    }
}

```

12.111 ReadFiles.java

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcml.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.
=====*/
import gdcml.*;
import java.io.File;

public class ReadFiles
{
    static int i = 0;
    public static void process(String path)
    {
        //String path = file.getPath();
        assert PosixEmulation.FileExists(path) : "Problem converting to 8bits";

        System.out.println("Reading: " + path );
        System.out.println("File: " + i++);
        Reader r = new Reader();
        try
        {
            r.SetFileName( path );
            TagSetType skip = new TagSetType();
            skip.insert( new Tag(0x7fe0,0x10) );
            boolean b = r.ReadUpToTag( new Tag(0x88,0x200), skip );
            //System.out.println("DS:\n" + r.GetFile().GetDataSet().toString() );
        }
        finally
        {
            r.delete(); // will properly call C++ destructor and close file descriptor
        }
    }

    // Process only files under dir
    public static void visitAllFiles(File dir)
    {
        if (dir.isDirectory())
        {
            String[] children = dir.list();
            for (int i=0; i<children.length; i++)
            {

```

```

        visitAllFiles(new File(dir, children[i]));
    }
}
else
{
    process(dir.getPath());
}
}

public static void waiting (int n)
{
    long t0, t1;
    t0 = System.currentTimeMillis();
    do
    {
        t1 = System.currentTimeMillis();
    }
    while ((t1 - t0) < (n * 1000));
}

public static void main(String[] args) throws Exception
{
    String directory = args[0];

    Directory gdir = new Directory();
    long n = gdir.Load( directory, true );
    System.out.println( gdir.toString() );
    FilenamesType files = gdir.GetFilenames();
    for( long i = 0; i < n; ++i )
    {
        String path = files.get( (int)i );
        process( path );
    }

    System.out.println( "Java API" );

    //waiting( 10 );
    for( int i = 0; i < 2; ++i )
    {
        File dir = new File(directory);
        visitAllFiles(dir);
    }
}
}

```

12.112 ScanDirectory.java

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/

import gdcm.*;
import gdcm.Reader;
import gdcm.LookupTable;
import java.io.File;
import java.io.*;
import java.awt.image.*;
import javax.imageio.ImageIO;

public class ScanDirectory
{
    public static class MyWatcher extends SimpleSubjectWatcher
    {
        public MyWatcher(Subject s) { super(s,"Override String"); }
        protected void ShowProgress(Subject caller, Event evt)
        {

```

```

        ProgressEvent pe = ProgressEvent.Cast(evt);
        System.out.println( "This is my progress: " + pe.GetProgress() );
    }
}

public static byte[] GetAsByte(Bitmap input)
{
    long len = input.GetBufferLength();
    byte[] buffer = new byte[ (int)len ];
    PhotometricInterpretation pi = input.GetPhotometricInterpretation();
    if( pi.GetType() == PhotometricInterpretation.PIType.MONOCHROME1 )
    {
        ImageChangePhotometricInterpretation icpi = new ImageChangePhotometricInterpretation();
        icpi.SetInput( input );
        icpi.SetPhotometricInterpretation(
            new PhotometricInterpretation(
                PhotometricInterpretation.PIType.MONOCHROME2 ) );
        if( icpi.Change() )
        {
            Bitmap output = icpi.GetOutput();
            output.GetArray( buffer );
        }
        return buffer;
    }
    else
    {
        input.GetArray( buffer );
        return buffer;
    }
}

public static short[] GetAsShort(Bitmap input)
{
    long len = input.GetBufferLength(); // length in bytes
    short[] buffer = new short[ (int)len / 2 ];
    PhotometricInterpretation pi = input.GetPhotometricInterpretation();
    if( pi.GetType() == PhotometricInterpretation.PIType.MONOCHROME1 )
    {
        ImageChangePhotometricInterpretation icpi = new ImageChangePhotometricInterpretation();
        icpi.SetInput( input );
        icpi.SetPhotometricInterpretation(
            new PhotometricInterpretation(
                PhotometricInterpretation.PIType.MONOCHROME2 ) );
        if( icpi.Change() )
        {
            Bitmap output = icpi.GetOutput();
            output.GetArray( buffer );
        }
        return buffer;
    }
    else
    {
        input.GetArray( buffer );
        return buffer;
    }
}

public static boolean WritePNG(Bitmap input, String outfilename )
{
    int imageType = BufferedImage.TYPE_CUSTOM;
    PixelFormat pf = input.GetPixelFormat();
    PhotometricInterpretation pi = input.GetPhotometricInterpretation();
    // We need to handle both public and private icon
    // It could well be that we are getting an RGB Icon or 16 bits Icon:
    ColorModel colorModel = null;
    if( pf.GetSamplesPerPixel() == 1 )
    {
        if( pi.GetType() == PhotometricInterpretation.PIType.MONOCHROME1
            || pi.GetType() == PhotometricInterpretation.PIType.MONOCHROME2 )
        {
            if( pf.GetScalarType() == PixelFormat.ScalarType.UINT8 )
            {
                imageType = BufferedImage.TYPE_BYTE_GRAY;
            }
            else if( pf.GetScalarType() == PixelFormat.ScalarType.UINT12 )
            {
                imageType = BufferedImage.TYPE_USHORT_GRAY;
            }
            else if( pf.GetScalarType() == PixelFormat.ScalarType.UINT16 )
            {
                imageType = BufferedImage.TYPE_USHORT_GRAY;
            }
        }
    }
}

```

```

else if( pi.GetType() == PhotometricInterpretation.PIType.PALETTE_COLOR )
{
    LookupTable lut = input.GetLUT();
    long r1 = lut.GetLUTLength( LookupTable.LookupTableType.RED );
    byte[] rbuf = new byte[ (int)r1 ];
    long r12 = lut.GetLUT( LookupTable.LookupTableType.RED, rbuf );
    assert r1 == r12;
    long g1 = lut.GetLUTLength( LookupTable.LookupTableType.GREEN );
    byte[] gbuf = new byte[ (int)g1 ];
    long g12 = lut.GetLUT( LookupTable.LookupTableType.GREEN, gbuf );
    assert g1 == g12;
    long b1 = lut.GetLUTLength( LookupTable.LookupTableType.BLUE );
    byte[] bbuf = new byte[ (int)b1 ];
    long b12 = lut.GetLUT( LookupTable.LookupTableType.BLUE, bbuf );
    assert b1 == b12;
    colorModel = new IndexColorModel(8, (int)r1, rbuf, gbuf, bbuf);
    // For code below
    imageType = BufferedImage.TYPE_BYTE_GRAY;
}
}
else if( pf.GetSamplesPerPixel() == 3 )
{
    if( pf.GetScalarType() == PixelFormat.ScalarType.UINT8 )
    {
        // FIXME should be TYPE_3BYTE_RGB
        imageType = BufferedImage.TYPE_3BYTE_BGR;
    }
}
//System.out.println( "pf: " + pf.toString() );
//System.out.println( "pi: " + pi.toString() );
long width = input.GetDimension(0);
long height = input.GetDimension(0);
BufferedImage bi;
if( pi.GetType() == PhotometricInterpretation.PIType.PALETTE_COLOR )
{
    bi = new BufferedImage(colorModel,
        colorModel.createCompatibleWritableRaster((int)width, (int)height),
        false, null);
}
else
{
    bi = new BufferedImage((int)width, (int)height, imageType);
}
WritableRaster wr = bi.getRaster();
//System.out.println( "imagetype: " + imageType );
if( imageType == BufferedImage.TYPE_BYTE_GRAY
    || imageType == BufferedImage.TYPE_3BYTE_BGR )
{
    byte[] buffer = GetAsByte( input );
    wr.setDataElements (0, 0, (int)width, (int)height, buffer);
}
else if( imageType == BufferedImage.TYPE_USHORT_GRAY )
{
    short[] buffer = GetAsShort( input );
    wr.setDataElements (0, 0, (int)width, (int)height, buffer);
}

File outputfile = new File( outfilename );
try {
    ImageIO.write(bi, "png", outputfile);
} catch (IOException e) {
    return false;
}
return true;
}

public static void main(String[] args) throws Exception
{
    String directory = args[0];

    Directory d = new Directory();
    long nfiles = d.Load( directory, true );
    if(nfiles == 0)
    {
        throw new Exception("No files found");
    }
    // System.out.println( "Files:\n" + d.toString() );
    FileNamesType fns = d.GetFileNames();

    //Scanner s = new Scanner();
    SmartPtrScan sscan = Scanner.New();

```



```

Scanner s = sscan.__ref__();
//SimpleSubjectWatcher watcher = new SimpleSubjectWatcher(s, "MySimple");
MyWatcher watcher = new MyWatcher(s);
Tag[] tagarray = {
    new Tag(0x0010, 0x0010),    // PatientName
    new Tag(0x0010, 0x0020),    // PatientID
    new Tag(0x0010, 0x0030),    // PatientBirthDate
    new Tag(0x0010, 0x0040),    // PatientSex
    new Tag(0x0010, 0x1010),    // PatientAge
    new Tag(0x0020, 0x000d),    // StudyInstanceUID
    new Tag(0x0020, 0x0010),    // StudyID
    new Tag(0x0008, 0x0020),    // StudyDate
    new Tag(0x0008, 0x1030),    // StudyDescription
    new Tag(0x0020, 0x000e),    // SeriesInstanceUID
    new Tag(0x0020, 0x0011),    // SeriesNumber
    new Tag(0x0008, 0x0021),    // SeriesDate
    new Tag(0x0008, 0x103e),    // SeriesDescription
    new Tag(0x0008, 0x0090),    // ReferringPhysicianName
    new Tag(0x0008, 0x0060),    // Modality
    new Tag(0x0054, 0x0400),    // ImageID ?? Should be Instance number ??
    new Tag(0x0008, 0x0018),    // SOPInstanceUID
    new Tag(0x0008, 0x0032),    // AcquisitionTime
    new Tag(0x0008, 0x0033),    // ContentTime
    new Tag(0x0020, 0x0013),    // InstanceNumber
    new Tag(0x0020, 0x1041),    // SliceLocation
    new Tag(0x0018, 0x0050),    // SliceThickness ?? Eg. Enhanced MR Image Storage
    new Tag(0x0008, 0x0080),    // InstitutionName
    new Tag(0x0028, 0x1050),    // WindowCenter
    new Tag(0x0028, 0x1051),    // WindowWidth
};
for( Tag t : tagarray ) {
    //System.out.println( "Tag: " + t.toString() );
    s.AddTag( t );
}
boolean b = s.Scan( fns );
if(!b)
{
    throw new Exception("Could not scan");
}
String fn0 = fns.get(0);
TagToValue mappings = s.GetMapping( fn0 );
System.out.println( "mappings size: " + mappings.size() );
for( Tag tag : tagarray ) {
    if( mappings.has_key( tag ) ) {
        String val = mappings.get( tag );
        System.out.println( "tag/val: " + tag + "->" + val );
    }
}

for( long idx = 0; idx < fns.size(); ++idx )
{
    Reader r = new Reader();
    String fn = fns.get( (int)idx );
    String outfn = fn + ".png";
    r.SetFileName( fn );
    TagSetType tst = new TagSetType();
    tst.insert( new Tag(0x7fe0,0x10) );
    b = r.ReadUpToTag( new Tag(0x88,0x200), tst );
    UIntArrayType dims = ImageHelper.GetDimensionsValue( r.GetFile() );
    if( b )
    {
        IconImageFilter iif = new IconImageFilter();
        System.out.println( "Processing: " + fn );

        iif.SetFile( r.GetFile() );
        b = iif.Extract();
        if( b )
        {
            Bitmap icon = iif.GetIconImage(0);
            WritePNG(icon, outfn);
        }
        else
        {
            ImageReader ir = new ImageReader();
            ir.SetFileName( fn );
            if( ir.Read() )
            {
                Image img = ir.GetImage();
                StringFilter sf = new StringFilter();
                sf.SetFile( r.GetFile() );
                String strval = sf.ToString( new Tag(0x0028,0x0120) );
            }
        }
    }
}

```

```

        IconImageGenerator iig = new IconImageGenerator();
        iig.SetPixmap( img );
        iig.AutoPixelMinMax( true );
        try {
            double val = Double.parseDouble( strval );
            iig.SetOutsideValuePixel( val );
        }
        catch ( NumberFormatException e ) {
        }
        iig.ConvertRGBToPaletteColor( false );
        long idims[] = { 128, 128 };
        iig.SetOutputDimensions( idims );
        iig.Generate();
        Bitmap icon = iig.GetIconImage();
        WritePNG( icon, outfn );
    }
}
}

System.out.println( "Scan:\n" + s.toString() );

System.out.println( "success" );
}
}

```

12.113 SimplePrint.java

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
/*
 * Compilation:
 * $ CLASSPATH=gdcm.jar javac ../../gdcm/Examples/Java/SimplePrint.java -d .
 *
 * Usage:
 * $ LD_LIBRARY_PATH=. CLASSPATH=gdcm.jar:. java SimplePrint gdcmData/012345.002.050.dcm
 */
import gdcm.*;

public class SimplePrint
{
    public static void RecurseDataSet( File f, DataSet ds, String indent )
    {
        JavaDataSet cds = new JavaDataSet( ds );
        while( !cds.IsAtEnd() )
        {
            DataElement de = cds.GetCurrent();
            // Compute VR from the toplevel file, and the currently processed dataset:
            VR vr = DataSetHelper.ComputeVR( f, ds, de.GetTag() );

            if( vr.Compatible( new VR( VRType.SQ ) ) )
            {
                long uvl = de.GetVL().GetValueLength(); // Test cast is ok
                System.out.println( indent + de.GetTag().toString() + ":" + uvl ); // why not ?
                //SequenceOfItems sq = de.GetSequenceOfItems();
                // GetValueAsSQ handle more cases than GetSequenceOfItems
                SmartPtrSQ sq = de.GetValueAsSQ();
                long n = sq.GetNumberOfItems();
                for( long i = 1; i <= n; i++ ) // item starts at 1, not 0
                {
                    Item item = sq.GetItem( i );
                    DataSet nested = item.GetNestedDataSet();
                    RecurseDataSet( f, nested, indent + "  " );
                }
            }
        }
    }
}

```

```

        else
        {
            System.out.println( indent + de.toString() );
        }
        cds.Next();
    }
}

public static void main(String[] args) throws Exception
{
    String filename = args[0];
    Reader reader = new Reader();
    reader.SetFileName( filename );
    boolean ret = reader.Read();
    if( !ret )
    {
        throw new Exception("Could not read: " + filename );
    }
    File f = reader.GetFile();
    DataSet ds = f.GetDataSet();

    RecurseDataSet( f, ds, "" );
}
}

```

12.114 AddPrivateAttribute.py

```

00001
00014
00015 """
00016 Usage:
00017
00018     python AddPrivateAttribute.py input.dcm output.dcm
00019
00020
00021 """
00022
00023 import sys
00024 import gdcm
00025
00026 if __name__ == "__main__":
00027
00028     file1 = sys.argv[1]
00029     file2 = sys.argv[2]
00030
00031     r = gdcm.Reader()
00032     r.SetFileName( file1 )
00033     if not r.Read():
00034         sys.exit(1)
00035
00036     f = r.GetFile()
00037     ds = f.GetDataSet()
00038
00039     # Create a dataelement
00040     de = gdcm.DataElement(gdcm.Tag(0x0051, 0x1011))
00041     de.SetByteStringValue("p2")
00042     de.SetVR(gdcm.VR(gdcm.VR.SH))
00043
00044     ds.Insert(de)
00045
00046     w = gdcm.Writer()
00047     w.SetFile( f )
00048     w.SetFileName( file2 )
00049     if not w.Write():
00050         sys.exit(1)

```

12.115 ConvertMPL.py

```

00001
00014
00015 """
00016 display a DICOM image with matplotlib via numpy

```

```

00017
00018 Caveats:
00019 - Does not support UINT12/INT12
00020
00021 Usage:
00022
00023 python ConvertNumpy.py "IM000000"
00024
00025 Thanks:
00026 plotting example - Ray Schumacher 2009
00027 """
00028
00029 import gdc
00030 import numpy
00031 from pylab import *
00032
00033
00034 def get_gdcm_to_numpy_typemap():
00035     """Returns the GDCM Pixel Format to numpy array type mapping."""
00036     _gdcm_np = {gdcm.PixelFormat.UINT8 :numpy.int8,
00037                 gdcm.PixelFormat.INT8 :numpy.uint8,
00038                 gdcm.PixelFormat.UINT16 :numpy.uint16,
00039                 gdcm.PixelFormat.INT16 :numpy.int16,
00040                 gdcm.PixelFormat.UINT32 :numpy.uint32,
00041                 gdcm.PixelFormat.INT32 :numpy.int32,
00042                 gdcm.PixelFormat.FLOAT32:numpy.float32,
00043                 gdcm.PixelFormat.FLOAT64:numpy.float64 }
00044     return _gdcm_np
00045
00046 def get_numpy_array_type(gdcm_pixel_format):
00047     """Returns a numpy array typecode given a GDCM Pixel Format."""
00048     return get_gdcm_to_numpy_typemap()[gdcm_pixel_format]
00049
00050 def gdcm_to_numpy(image):
00051     """Converts a GDCM image to a numpy array.
00052     """
00053     pf = image.GetPixelFormat().GetScalarType()
00054     print 'pf', pf
00055     print image.GetPixelFormat().GetScalarTypeAsString()
00056     assert pf in get_gdcm_to_numpy_typemap().keys(), \
00057         "Unsupported array type %s"%pf
00058     d = image.GetDimension(0), image.GetDimension(1)
00059     print 'Image Size: %d x %d' % (d[0], d[1])
00060     dtype = get_numpy_array_type(pf)
00061     gdcm_array = image.GetBuffer()
00062
00063     result = numpy.frombuffer(gdcm_array, dtype=dtype).astype(float)
00064
00065     result.shape = d
00066     return result
00067
00068
00069
00070
00071 if __name__ == "__main__":
00072     import sys
00073     r = gdcm.ImageReader()
00074     filename = sys.argv[1]
00075     r.SetFileName( filename )
00076     if not r.Read(): sys.exit(1)
00077     numpy_array = gdcm_to_numpy( r.GetImage() )
00078
00079     subplot(111)# one plot, on left
00080     title(filename)
00081
00082     imshow(numpy_array, interpolation='bilinear', cmap=cm.jet)
00083
00084     subplots_adjust(bottom=0.1, right=0.8, top=0.9)
00085     cax = axes([0.85, 0.1, 0.075, 0.8])
00086     colorbar(cax=cax)
00087     title('values')
00088     get_current_fig_manager().window.title('plot')
00089     show()

```

12.116 ConvertNumpy.py

```

00001
00014
00015 """

```

```

00016 This module add support for converting a gdcm.Image to a numpy array.
00017
00018 Caveats:
00019 - Does not support UINT12/INT12
00020
00021 Removed:
00022 - float16 is defined in GDCM API but no implementation exist for it ...
00023 """
00024
00025 import gdcm
00026 import numpy
00027
00028 def get_gdcm_to_numpy_typemap():
00029     """Returns the GDCM Pixel Format to numpy array type mapping."""
00030     _gdcm_np = {gdcm.PixelFormat.UINT8 :numpy.uint8,
00031                 gdcm.PixelFormat.INT8 :numpy.int8,
00032                 #gdcm.PixelFormat.UINT12 :numpy.uint12,
00033                 #gdcm.PixelFormat.INT12 :numpy.int12,
00034                 gdcm.PixelFormat.UINT16 :numpy.uint16,
00035                 gdcm.PixelFormat.INT16 :numpy.int16,
00036                 gdcm.PixelFormat.UINT32 :numpy.uint32,
00037                 gdcm.PixelFormat.INT32 :numpy.int32,
00038                 #gdcm.PixelFormat.FLOAT16:numpy.float16,
00039                 gdcm.PixelFormat.FLOAT32:numpy.float32,
00040                 gdcm.PixelFormat.FLOAT64:numpy.float64 }
00041     return _gdcm_np
00042
00043 def get_numpy_array_type(gdcm_pixel_format):
00044     """Returns a numpy array typecode given a GDCM Pixel Format."""
00045     return get_gdcm_to_numpy_typemap()[gdcm_pixel_format]
00046
00047 def gdcm_to_numpy(image):
00048     """Converts a GDCM image to a numpy array.
00049     """
00050     pf = image.GetPixelFormat()
00051
00052     assert pf.GetScalarType() in get_gdcm_to_numpy_typemap().keys(), \
00053         "Unsupported array type %s"%pf
00054
00055     shape = image.GetDimension(0) * image.GetDimension(1), pf.GetSamplesPerPixel()
00056     if image.GetNumberOfDimensions() == 3:
00057         shape = shape[0] * image.GetDimension(2), shape[1]
00058
00059     dtype = get_numpy_array_type(pf.GetScalarType())
00060     gdcm_array = image.GetBuffer()
00061     result = numpy.frombuffer(gdcm_array, dtype=dtype)
00062     result.shape = shape
00063     return result
00064
00065 if __name__ == "__main__":
00066     import sys
00067     r = gdcm.ImageReader()
00068     filename = sys.argv[1]
00069     r.SetFileName( filename )
00070     if not r.Read():
00071         sys.exit(1)
00072
00073     numpy_array = gdcm_to_numpy( r.GetImage() )
00074     print numpy_array

```

12.117 ConvertPIL.py

```

00001
00014
00015 """
00016 save a DICOM image with PIL via numpy
00017
00018 Caveats:
00019 - Does not support UINT12/INT12
00020
00021 Usage:
00022
00023 python ConvertNumpy.py "IM000000"
00024
00025 Thanks:
00026 plotting example - Ray Schumacher 2009

```

```

00027 """
00028
00029 import gdcm
00030 import numpy
00031 from PIL import Image, ImageOps
00032
00033
00034 def get_gdcm_to_numpy_typemap():
00035     """Returns the GDCM Pixel Format to numpy array type mapping."""
00036     _gdcm_np = {gdcm.PixelFormat.UINT8 :numpy.int8,
00037                 gdcm.PixelFormat.INT8 :numpy.uint8,
00038                 gdcm.PixelFormat.UINT16 :numpy.uint16,
00039                 gdcm.PixelFormat.INT16 :numpy.int16,
00040                 gdcm.PixelFormat.UINT32 :numpy.uint32,
00041                 gdcm.PixelFormat.INT32 :numpy.int32,
00042                 gdcm.PixelFormat.FLOAT32:numpy.float32,
00043                 gdcm.PixelFormat.FLOAT64:numpy.float64 }
00044     return _gdcm_np
00045
00046 def get_numpy_array_type(gdcm_pixel_format):
00047     """Returns a numpy array typecode given a GDCM Pixel Format."""
00048     return get_gdcm_to_numpy_typemap()[gdcm_pixel_format]
00049
00050 def gdcm_to_numpy(image):
00051     """Converts a GDCM image to a numpy array.
00052     """
00053     pf = image.GetPixelFormat().GetScalarType()
00054     print 'pf', pf
00055     print image.GetPixelFormat().GetScalarTypeAsString()
00056     assert pf in get_gdcm_to_numpy_typemap().keys(), \
00057         "Unsupported array type %s"%pf
00058     d = image.GetDimension(0), image.GetDimension(1)
00059     print 'Image Size: %d x %d' % (d[0], d[1])
00060     dtype = get_numpy_array_type(pf)
00061     gdcm_array = image.GetBuffer()
00062     result = numpy.frombuffer(gdcm_array, dtype=dtype)
00063     maxV = float(result[result.argmax()])
00064
00065     result = numpy.log(result+50)
00066     maxV = float(result[result.argmax()])
00067     result = result*(2.**8/maxV)
00068     result.shape = d
00069     return result
00070
00071 if __name__ == "__main__":
00072     import sys
00073     r = gdcm.ImageReader()
00074     filename = sys.argv[1]
00075     r.SetFileName( filename )
00076     if not r.Read(): sys.exit(1)
00077     numpy_array = gdcm_to_numpy( r.GetImage() )
00078
00079     pilImage = Image.frombuffer('L',
00080                                numpy_array.shape,
00081                                numpy_array.astype(numpy.uint8),
00082                                'raw','L',0,1)
00083
00084     pilImage = ImageOps.autocontrast(pilImage, cutoff=.1)
00085     pilImage.save(sys.argv[1]+' .jpg')

```

12.118 CreateRAWStorage.py

```

00001
00014
00015 """
00016     <uid value="1.2.840.10008.5.1.4.1.1.66" name="Raw Data Storage" type="SOP Class" part="PS 3.4"
00017     retired="false"/>
00018 """
00019 import gdcm
00020 import sys,os
00021
00022 if __name__ == "__main__":
00023     r = gdcm.Reader()
00024     # Will require Testing...
00025     dataroot = gdcm.Testing.GetDataRoot()

```

```
00026 filename = os.path.join( dataroot, '012345.002.050.dcm' )
00027 r.SetFileName( filename )
00028 r.Read()
00029 f = r.GetFile()
00030 ds = f.GetDataSet()
00031
00032 uid = "1.2.840.10008.5.1.4.1.1.66"
00033 # f = gdcm.File()
00034 # ds = f.GetDataSet()
00035 de = gdcm.DataElement( gdcm.Tag(0x0008,0x0016) )
00036 de.SetByteStringValue( uid )
00037 vr = gdcm.VR( gdcm.VR.UI )
00038 de.SetVR( vr )
00039 ds.Replace( de )
00040
00041 ano = gdcm.Anonymizer()
00042 ano.SetFile( r.GetFile() )
00043 ano.RemovePrivateTags()
00044 ano.RemoveGroupLength()
00045 taglist = [
00046     gdcm.Tag(0x0008,0x0008),
00047     gdcm.Tag(0x0008,0x0022),
00048     gdcm.Tag(0x0008,0x0032),
00049     gdcm.Tag(0x0008,0x2111),
00050     gdcm.Tag(0x0008,0x1150),
00051     gdcm.Tag(0x0008,0x1155),
00052     gdcm.Tag(0x0008,0x0100),
00053     gdcm.Tag(0x0008,0x0102),
00054     gdcm.Tag(0x0008,0x0104),
00055     gdcm.Tag(0x0040,0xa170),
00056     gdcm.Tag(0x0008,0x2112),
00057     gdcm.Tag(0x0008,0x0100),
00058     gdcm.Tag(0x0008,0x0102),
00059     gdcm.Tag(0x0008,0x0104),
00060     gdcm.Tag(0x0008,0x9215),
00061     gdcm.Tag(0x0018,0x0010),
00062     gdcm.Tag(0x0018,0x0022),
00063     gdcm.Tag(0x0018,0x0050),
00064     gdcm.Tag(0x0018,0x0060),
00065     gdcm.Tag(0x0018,0x0088),
00066     gdcm.Tag(0x0018,0x0090),
00067     gdcm.Tag(0x0018,0x1040),
00068     gdcm.Tag(0x0018,0x1100),
00069     gdcm.Tag(0x0018,0x1110),
00070     gdcm.Tag(0x0018,0x1111),
00071     gdcm.Tag(0x0018,0x1120),
00072     gdcm.Tag(0x0018,0x1130),
00073     gdcm.Tag(0x0018,0x1150),
00074     gdcm.Tag(0x0018,0x1151),
00075     gdcm.Tag(0x0018,0x1152),
00076     gdcm.Tag(0x0018,0x1160),
00077     gdcm.Tag(0x0018,0x1190),
00078     gdcm.Tag(0x0018,0x1210),
00079     gdcm.Tag(0x0020,0x0012),
00080     gdcm.Tag(0x0020,0x0032),
00081     gdcm.Tag(0x0020,0x0037),
00082     gdcm.Tag(0x0020,0x1041),
00083     gdcm.Tag(0x0020,0x4000),
00084     gdcm.Tag(0x0028,0x0002),
00085     gdcm.Tag(0x0028,0x0004),
00086     gdcm.Tag(0x0028,0x0010),
00087     gdcm.Tag(0x0028,0x0011),
00088     gdcm.Tag(0x0028,0x0030),
00089     gdcm.Tag(0x0028,0x0100),
00090     gdcm.Tag(0x0028,0x0101),
00091     gdcm.Tag(0x0028,0x0102),
00092     gdcm.Tag(0x0028,0x0103),
00093     gdcm.Tag(0x0028,0x1052),
00094     gdcm.Tag(0x0028,0x1053),
00095     gdcm.Tag(0x0028,0x2110),
00096     gdcm.Tag(0x0028,0x2112),
00097     gdcm.Tag(0x7fe0,0x0010),
00098     gdcm.Tag(0x0018,0x0020),
00099     gdcm.Tag(0x0018,0x0021),
00100     gdcm.Tag(0x0018,0x0023),
00101     gdcm.Tag(0x0018,0x0025),
00102     gdcm.Tag(0x0018,0x0080),
00103     gdcm.Tag(0x0018,0x0081),
00104     gdcm.Tag(0x0018,0x0083),
00105     gdcm.Tag(0x0018,0x0084),
00106     gdcm.Tag(0x0018,0x0085),
```

```

00107     gdc.Tag(0x0018,0x0086),
00108     gdc.Tag(0x0018,0x0087),
00109     gdc.Tag(0x0018,0x0091),
00110     gdc.Tag(0x0018,0x0093),
00111     gdc.Tag(0x0018,0x0094),
00112     gdc.Tag(0x0018,0x0095),
00113     gdc.Tag(0x0018,0x1088),
00114     gdc.Tag(0x0018,0x1090),
00115     gdc.Tag(0x0018,0x1094),
00116     gdc.Tag(0x0018,0x1250),
00117     gdc.Tag(0x0018,0x1251),
00118     gdc.Tag(0x0018,0x1310),
00119     gdc.Tag(0x0018,0x1312),
00120     gdc.Tag(0x0018,0x1314),
00121     gdc.Tag(0x0018,0x1315),
00122     gdc.Tag(0x0018,0x1316),
00123     gdc.Tag(0x0020,0x0110),
00124     gdc.Tag(0x0028,0x0120),
00125     gdc.Tag(0x0028,0x1050),
00126     gdc.Tag(0x0028,0x1051)
00127 ]
00128 for tag in taglist:
00129     #print tag
00130     ano.Remove( tag )
00131
00132 # special handling
00133 gen = gdc.UIDGenerator()
00134 ano.Replace( gdc.Tag(0x0008,0x9123), gen.Generate() )
00135 #ano.Empty( gdc.Tag(0x0040,0x0555) )
00136
00137
00138 #
00139 # uid = gen.Generate()
00140 # de.SetTag( gdc.Tag(0x0008,0x0018) )
00141 # de.SetByteStringValue( uid )
00142 # ds.Insert( de )
00143
00144 # init FMI now:
00145 #fmi = f.GetHeader()
00146 #ts = gdc.TransferSyntax()
00147 #print ts
00148 #fmi.SetDataSetTransferSyntax( ts ) # default
00149 #print fmi.GetDataSetTransferSyntax()
00150 #de.SetTag( gdc.Tag(0x0002,0x0010) )
00151 #uid = "1.2.840.10008.1.2"
00152 #de.SetByteStringValue( uid )
00153 #fmi.Insert( de )
00154 # f.SetHeader( r.GetFile().GetHeader() )
00155
00156 writer = gdc.Writer()
00157 writer.SetFile( ano.GetFile() )
00158 writer.SetFileName( "rawstorage.dcm" );
00159 writer.Write()

```

12.119 DecompressImage.py

```

00001
00014
00015 """
00016 Usage:
00017
00018 python DecompressImage.py gdcData/012345.002.050.dcm decompress.dcm
00019 """
00020
00021 import gdc
00022 import sys
00023
00024 if __name__ == "__main__":
00025
00026     file1 = sys.argv[1]
00027     file2 = sys.argv[2]
00028
00029     r = gdc.ImageReader()
00030     r.SetFileName( file1 )
00031     if not r.Read():
00032         sys.exit(1)

```



```

00033
00034 # check GetFragment API:
00035 pd = r.GetFile().GetDataSet().GetDataElement(gdcm.Tag(0x7fe0, 0x0010))
00036 frags = pd.GetSequenceOfFragments();
00037 frags.GetFragment(0);
00038
00039 ir = r.GetImage()
00040 w = gdcm.ImageWriter()
00041 image = w.GetImage()
00042
00043 image.SetNumberOfDimensions( ir.GetNumberOfDimensions() );
00044 dims = ir.GetDimensions();
00045 print ir.GetDimension(0);
00046 print ir.GetDimension(1);
00047 print "Dims:",dims
00048
00049 # Just for fun:
00050 dircos = ir.GetDirectionCosines()
00051 t = gdcm.Orientation.GetType(tuple(dircos))
00052 l = gdcm.Orientation.GetLabel(t)
00053 print "Orientation label:",l
00054
00055 image.SetDimension(0, ir.GetDimension(0) );
00056 image.SetDimension(1, ir.GetDimension(1) );
00057
00058 pixeltype = ir.GetPixelFormat();
00059 image.SetPixelFormat( pixeltype );
00060
00061 pi = ir.GetPhotometricInterpretation();
00062 image.SetPhotometricInterpretation( pi );
00063
00064 pixeldata = gdcm.DataElement( gdcm.Tag(0x7fe0,0x0010) )
00065 str1 = ir.GetBuffer()
00066 #print ir.GetBufferLength()
00067 pixeldata.SetByteStringValue( str1 )
00068 image.SetDataElement( pixeldata )
00069
00070 w.SetFileName( file2 )
00071 w.SetFile( r.GetFile() )
00072 w.SetImage( image )
00073 if not w.Write():
00074     sys.exit(1)

```

12.120 DumbAnonymizer.py

```

00001
00014
00015 """
00016 This example shows how one can use the gdcm.Anonymizer in 'dumb' mode.
00017 This class becomes really handy when one knows which particular tag to fill in.
00018
00019 Usage:
00020
00021 python DumbAnonymizer.py gdcmData/012345.002.050.dcm out.dcm
00022
00023 """
00024
00025 import gdcm
00026
00027 # http://www.oid-info.com/get/1.3.6.1.4.17434
00028 THERALYS_ORG_ROOT = "1.3.6.1.4.17434"
00029
00030 tag_rules={
00031     # Value
00032     (0x0012,0x0010):("Value","MySponsorName"),
00033     (0x0012,0x0020):("Value","MyProtocolID"),
00034     (0x0012,0x0021):("Value","MyProtocolName"),
00035     (0x0012,0x0062):("Value","YES"),
00036     (0x0012,0x0063):("Value","MyDeidentificationMethod"),
00037
00038     # Method
00039     (0x0002,0x0003):("Method","GenerateMSOPId"),
00040     (0x0008,0x1155):("Method","GenerateMSOPId"),
00041     (0x0008,0x0018):("Method","GenerateMSOPId"),
00042     (0x0010,0x0010):("Method","GetSponsorInitials"),
00043     (0x0010,0x0020):("Method","GetSponsorId"),

```

```

00044 (0x0012,0x0030):("Method","GetSiteId"),
00045 (0x0012,0x0031):("Method","GetSiteName"),
00046 (0x0012,0x0040):("Method","GetSponsorId"),
00047 (0x0012,0x0050):("Method","GetTPId"),
00048 (0x0018,0x0022):("Method","KeepIfExist"),
00049 (0x0018,0x1315):("Method","KeepIfExist"),
00050 (0x0020,0x000d):("Method","GenerateStudyId"),
00051 (0x0020,0x000e):("Method","GenerateSeriesId"),
00052 (0x0020,0x1002):("Method","GetNumberOfFrames"),
00053 (0x0020,0x0020):("Method","GetPatientOrientation"),
00054 # Other:
00055 (0x0012,0x0051):("Patient Field","Type Examen"),
00056 (0x0018,0x1250):("Sequence Field","Receive Coil"),
00057 (0x0018,0x0088):("Sequence Field","Spacing Between Slice"),
00058 (0x0018,0x0095):("Sequence Field","Pixel Bandwidth"),
00059 (0x0018,0x0082):("Sequence Field","Inversion Time"),
00060 }
00061
00062 class MyAnon:
00063     def __init__(self):
00064         self.studyuid = None
00065         self.seriesuid = None
00066         generator = gdcm.UIDGenerator()
00067         if not self.studyuid:
00068             self.studyuid = generator.Generate()
00069         if not self.seriesuid:
00070             self.seriesuid = generator.Generate()
00071     def GetSponsorInitials(self):
00072         return "dummy^foobar"
00073     def GenerateStudyId(self):
00074         return self.studyuid
00075     def GenerateSeriesId(self):
00076         return self.seriesuid
00077     #def GenerateMSOPIId(self):
00078     def GenerateMSOPIId(self):
00079         generator = gdcm.UIDGenerator()
00080         return generator.Generate()
00081     def GetSiteId(self):
00082         return "MySiteId"
00083     def GetSiteName(self):
00084         return "MySiteName"
00085     def GetSponsorId(self):
00086         return "MySponsorId"
00087     def GetTPId(self):
00088         return "MyTP"
00089
00090 if __name__ == "__main__":
00091     import sys
00092     gdcm.FileMetaInformation.SetSourceApplicationEntityTitle( "DumbAnonymizer" )
00093     gdcm.UIDGenerator.SetRoot( THERALYS_ORG_ROOT )
00094
00095     r = gdcm.Reader()
00096     filename = sys.argv[1]
00097     r.SetFileName( filename )
00098     if not r.Read(): sys.exit(1)
00099
00100     obj = MyAnon()
00101
00102     w = gdcm.Writer()
00103     ano = gdcm.Anonymizer()
00104     ano.SetFile( r.GetFile() )
00105     ano.RemoveGroupLength()
00106     for tag,rule in tag_rules.items():
00107         if rule[0] == 'Value':
00108             print tag,rule
00109             ano.Replace( gdcm.Tag( tag[0], tag[1] ), rule[1] )
00110         elif rule[0] == 'Method':
00111             print tag,rule
00112             # result = locals()[rule[1]]()
00113             methodname = rule[1]
00114             if hasattr(obj, methodname):
00115                 _member = getattr(obj, methodname)
00116                 result = _member()
00117                 ano.Replace( gdcm.Tag( tag[0], tag[1] ), result )
00118             else:
00119                 print "Problem with: ", methodname
00120
00121     outfilename = sys.argv[2]
00122     w.SetFileName( outfilename )
00123     w.SetFile( ano.GetFile() )
00124     if not w.Write(): sys.exit(1)

```

12.121 ExtractImageRegion.py

```

00001
00014
00015 """
00016
00017 This small code shows how to use the gdcm.ImageRegionReader API
00018 In this example we are taking each frame by frame and dump them to
00019 /tmp/frame.raw.
00020
00021 Usage:
00022 $ ExtractImageRegion.py input.dcm
00023
00024 Example:
00025 $ ExtractImageRegion.py gdcmData/012345.002.050.dcm
00026 $ md5sum /tmp/frame.raw
00027 d594a5e2fde12f32b6633ca859b4d4a6 /tmp/frame.raw
00028 $ gdcminfo --md5sum gdcmData/012345.002.050.dcm
00029 [...]
00030 md5sum: d594a5e2fde12f32b6633ca859b4d4a6
00031 """
00032
00033 import gdcm
00034
00035 if __name__ == "__main__":
00036     import sys
00037     filename = sys.argv[1]
00038
00039     file_size = gdcm.System.FileSize(filename);
00040
00041     # instantiate the reader:
00042     reader = gdcm.ImageRegionReader();
00043     reader.SetFileName( filename );
00044
00045     # pull DICOM info:
00046     if not reader.ReadInformation():
00047         sys.exit(1)
00048
00049     # store current offset:
00050     cur_pos = reader.GetStreamCurrentPosition();
00051
00052     remaining = file_size - cur_pos;
00053
00054     print("Remaining bytes to read (Pixel Data): %d" % remaining );
00055
00056     # Get file infos
00057     f = reader.GetFile();
00058
00059     # get some info about image
00060     dims = gdcm.ImageHelper.GetDimensionsValue(f);
00061     print(dims)
00062     pf = gdcm.ImageHelper.GetPixelFormatValue(f);
00063     pixelsize = pf.GetPixelSize();
00064     pi = gdcm.ImageHelper.GetPhotometricInterpretationValue(f);
00065     print( pi );
00066
00067     # buffer to get the pixels
00068     buffer = bytearray( dims[0] * dims[1] * pixelsize )
00069
00070     # define a simple box region.
00071     box = gdcm.BoxRegion();
00072     for z in range(0, dims[2]):
00073         # Define that I want the image 0, full size (dimx x dimy pixels)
00074         # and do that for each z:
00075         box.SetDomain(0, dims[0] - 1, 0, dims[1] - 1, z, z);
00076         #print( box.toString() );
00077         reader.SetRegion( box );
00078
00079     # reader will try to load the uncompressed image region into buffer.
00080     # the call returns an error when buffer.Length is too small. For instance
00081     # one can call:
00082     # uint buf_len = reader.ComputeBufferLength(); // take into account pixel size
00083     # to get the exact size of minimum buffer
00084     if reader.ReadIntoBuffer(buffer):
00085         open('/tmp/frame.raw', 'wb').write(buffer)
00086     else:
00087         #throw new Exception("can't read pixels error");
00088         sys.exit(1)

```

12.122 FindAllPatientName.py

```

00001
00014 """
00015 This example shows how one can use the gdcml.CompositeNetworkFunctions class
00016 for executing a C-FIND query
00017 It will print the list of patient name found
00018
00019 Usage:
00020
00021 python FindAllPatientName.py
00022
00023 """
00024
00025 import gdcml
00026
00027 # Patient Name
00028 tag = gdcml.Tag(0x10,0x10)
00029 de = gdcml.DataElement(tag)
00030
00031 # Search all patient name where string match 'F*'
00032 de.SetByteStringValue('F*')
00033
00034 ds = gdcml.DataSet()
00035 ds.Insert(de)
00036
00037 cnf = gdcml.CompositeNetworkFunctions()
00038 theQuery = cnf.ConstructQuery(gdcml.ePatientRootType,gdcml.ePatient,ds)
00039
00040 #print theQuery.ValidateQuery()
00041
00042 # prepare the variable for output
00043 ret = gdcml.DataSetArrayType()
00044
00045 # Execute the C-FIND query
00046 cnf.CFind('dicom.example.com',11112,theQuery,ret,'GDCM_PYTHON','ANY-SCP')
00047
00048 for i in range(0,ret.size()):
00049     print "Patient #",i
00050     print ret[i]

```

12.123 FixCommaBug.py

```

00001
00014 """
00015 Using LC_NUMERIC set to something not compatible with "C" it is possible to write out "," instead of
00016 "." as required by the DICOM standard
00017 Issue is still current (IMHO) with gdcml 2.0.9
00018 """
00019
00020
00021 import gdcml
00022 import sys
00023
00024 filename = sys.argv[1]
00025 outname = sys.argv[2]
00026
00027 # read
00028 r = gdcml.Reader()
00029 r.SetFileName( filename )
00030 if not r.Read():
00031     print "not valid"
00032     sys.exit(1)
00033
00034 file = r.GetFile()
00035 dataset = file.GetDataSet()
00036
00037 ano = gdcml.Anonymizer()
00038 ano.SetFile( file )
00039
00040 tags = [
00041     gdcml.Tag(0x0018,0x1164),
00042     gdcml.Tag(0x0018,0x0088),
00043     gdcml.Tag(0x0018,0x0050),
00044     gdcml.Tag(0x0028,0x0030),
00045 ]

```

```

00046
00047 for tag in tags:
00048     print tag
00049     if dataset.FindElement( tag ):
00050         pixelspacing = dataset.GetDataElement( tag )
00051         #print pixelspacing
00052         bv = pixelspacing.GetByteValue()
00053         str = bv.GetBuffer()
00054         #print bv.GetLength()
00055         #print len(str)
00056         new_str = str.replace(",",".")
00057         # Need to explicitly pass bv.GetLength() to remove any trailing garbage
00058         ano.Replace( tag, new_str, bv.GetLength() )
00059
00060 #print dataset
00061
00062 w = gdcm.Writer()
00063 w.SetFile( file )
00064 w.SetFileName( outname )
00065 if not w.Write():
00066     print "Cannot write"
00067     sys.exit(1)
00068
00069 # paranoid:
00070 image_reader = gdcm.ImageReader()
00071 image_reader.SetFileName( outname )
00072 if not image_reader.Read():
00073     print "there is still a comma"
00074     sys.exit(1)
00075
00076 print "Success!"
00077 sys.exit(0) # success

```

12.124 GetPortionCSAHeader.py

```

00001
00014
00015 """
00016 Usage:
00017
00018 python GetPortionCSAHeader.py input.dcm
00019
00020 Footnote:
00021 SIEMENS is not publishing any information on the CSA header. So any info extracted
00022 is at your own risk.
00023 """
00024
00025 import sys
00026 import gdcm
00027
00028 if __name__ == "__main__":
00029
00030     file = sys.argv[1]
00031
00032     r = gdcm.Reader()
00033     r.SetFileName( file )
00034     if not r.Read():
00035         sys.exit(1)
00036
00037     ds = r.GetFile().GetDataSet()
00038     csa_t1 = gdcm.CSAHeader()
00039     csa_t2 = gdcm.CSAHeader()
00040     #print csa
00041     t1 = csa_t1.GetCSAImageHeaderInfoTag();
00042     print t1
00043     t2 = csa_t2.GetCSASeriesHeaderInfoTag();
00044     print t2
00045     # Let's do it for t1:
00046     if ds.FindElement( t1 ):
00047         csa_t1.LoadFromDataElement( ds.GetDataElement( t1 ) )
00048         print csa_t1
00049
00050     # Now let's pretend we are only interested in B_value and DiffusionGradientDirection entries:
00051     bvalues = csa_t1.GetCSAElementByName( "B_value" ) # WARNING: it is case sensitive !
00052     print bvalues
00053

```

```

00054 diffgraddir = csa_t1.GetCSAElementByName( "DiffusionGradientDirection" ) # WARNING: it is case sensitive
!
00055 print diffgraddir
00056
00057 # repeat for t2 if you like it:
00058 if ds.FindDataElement( t2 ):
00059     csa_t2.LoadFromDataElement( ds.GetDataElement( t2 ) )
00060     # print csa_t2
00061
00062 gdt = csa_t2.GetCSAElementByName( "GradientDelayTime" )
00063 print gdt
00064
00065 bv = gdt.GetByteValue();
00066 #print bv
00067 str = bv.GetPointer()
00068 print str.split("\\")

```

12.125 HelloWorld.py

```

00001
00014
00015 """
00016 Hello World !
00017 """
00018
00019 import gdcm
00020 import sys
00021
00022 if __name__ == "__main__":
00023
00024     # verbosity:
00025     #gdcm.Trace.DebugOn()
00026     #gdcm.Trace.WarningOn()
00027     #gdcm.Trace.ErrorOn()
00028
00029     # Get the filename from the command line
00030     filename = sys.argv[1]
00031
00032     # Instantiate a gdcm.Reader
00033     # This is the main class to handle any type of DICOM object
00034     # You should check for gdcm.ImageReader for reading specifically DICOM Image file
00035     r = gdcm.Reader()
00036     r.SetFileName( filename )
00037     # If the reader fails to read the file, we should stop !
00038     if not r.Read():
00039         print "Not a valid DICOM file"
00040         sys.exit(1)
00041
00042     # Get the DICOM File structure
00043     file = r.GetFile()
00044
00045     # Get the DataSet part of the file
00046     dataset = file.GetDataSet()
00047
00048     # Ok let's print it !
00049     print dataset
00050
00051     # Use StringFilter to print a particular Tag:
00052     sf = gdcm.StringFilter()
00053     sf.SetFile(r.GetFile())
00054
00055     # Check if Attribute exist
00056     print dataset.FindElement( gdcm.Tag(0x0028,0x0010) )
00057
00058     # Let's print it as string pair:
00059     print sf.ToStringPair(gdcm.Tag(0x0028,0x0010))

```

12.126 ManipulateFile.py

```

00001
00014
00015 """

```

```

00016 Usage:
00017
00018 python ManipulateFile.py input.dcm output.dcm
00019
00020 Footnote:
00021 GDCM 1.2.x would create incorrect Multiframe MR Image Storage file. Try to recover from
00022 the issues to recreate a MultiframeGrayscaleByteSecondaryCaptureImageStorage file.
00023 e.g:
00024
00025 python ManipulateFile.py Insight/Testing/Temporary/itkGDCMImageIOTest5-j2k.dcm manipulated.dcm
00026 """
00027
00028 import sys
00029 import gdcm
00030
00031 if __name__ == "__main__":
00032
00033     file1 = sys.argv[1]
00034     file2 = sys.argv[2]
00035
00036     r = gdcm.Reader()
00037     r.SetFileName( file1 )
00038     if not r.Read():
00039         sys.exit(1)
00040
00041     ano = gdcm.Anonymizer()
00042     ano.SetFile( r.GetFile() )
00043     ano.RemovePrivateTags()
00044     ano.Remove( gdcm.Tag(0x0032,0x1030) )
00045     ano.Remove( gdcm.Tag(0x008,0x14) )
00046     ano.Remove( gdcm.Tag(0x008,0x1111) )
00047     ano.Remove( gdcm.Tag(0x008,0x1120) )
00048     ano.Remove( gdcm.Tag(0x008,0x1140) )
00049     ano.Remove( gdcm.Tag(0x10,0x21b0) )
00050     ano.Empty( gdcm.Tag(0x10,0x10) )
00051     ano.Empty( gdcm.Tag(0x10,0x20) )
00052     ano.Empty( gdcm.Tag(0x10,0x30) )
00053     ano.Empty( gdcm.Tag(0x20,0x10) )
00054     ano.Empty( gdcm.Tag(0x32,0x1032) )
00055     ano.Empty( gdcm.Tag(0x32,0x1033) )
00056     ano.Empty( gdcm.Tag(0x40,0x241) )
00057     ano.Empty( gdcm.Tag(0x40,0x254) )
00058     ano.Empty( gdcm.Tag(0x40,0x253) )
00059     ano.Empty( gdcm.Tag(0x40,0x1001) )
00060     ano.Empty( gdcm.Tag(0x8,0x80) )
00061     ano.Empty( gdcm.Tag(0x8,0x50) )
00062     ano.Empty( gdcm.Tag(0x8,0x1030) )
00063     ano.Empty( gdcm.Tag(0x8,0x103e) )
00064     ano.Empty( gdcm.Tag(0x18,0x1030) )
00065     ano.Empty( gdcm.Tag(0x38,0x300) )
00066     g = gdcm.UIDGenerator()
00067     ano.Replace( gdcm.Tag(0x0008,0x0018), g.Generate() )
00068     ano.Replace( gdcm.Tag(0x0020,0x00d), g.Generate() )
00069     ano.Replace( gdcm.Tag(0x0020,0x00e), g.Generate() )
00070     ano.Replace( gdcm.Tag(0x0020,0x052), g.Generate() )
00071     #ano.Replace( gdcm.Tag(0x0008,0x0016), "1.2.840.10008.5.1.4.1.1.7.2" )
00072     """
00073     ano.Remove( gdcm.Tag(0x0018,0x0020) ) # ScanningSequence
00074     ano.Remove( gdcm.Tag(0x0018,0x0021) ) # SequenceVariant
00075     ano.Remove( gdcm.Tag(0x0018,0x0022) ) # ScanOptions
00076     ano.Remove( gdcm.Tag(0x0018,0x0023) ) # MRAcquisitionType
00077     ano.Remove( gdcm.Tag(0x0018,0x0050) ) # SliceThickness
00078     ano.Remove( gdcm.Tag(0x0018,0x0080) ) # RepetitionTime
00079     ano.Remove( gdcm.Tag(0x0018,0x0081) ) # EchoTime
00080     ano.Remove( gdcm.Tag(0x0018,0x0088) ) # SpacingBetweenSlices
00081     ano.Remove( gdcm.Tag(0x0018,0x0091) ) # EchoTrainLength
00082     ano.Remove( gdcm.Tag(0x0018,0x1164) ) # ImagerPixelSpacing
00083
00084     ano.Remove( gdcm.Tag(0x0020,0x0032) ) # Image Position (Patient)
00085     ano.Remove( gdcm.Tag(0x0020,0x0037) ) # Image Orientation (Patient)
00086     ano.Remove( gdcm.Tag(0x0020,0x0052) ) # Frame of Reference UID
00087     ano.Remove( gdcm.Tag(0x0020,0x1040) ) # Position Reference Indicator
00088
00089     ano.Replace( gdcm.Tag(0x0028,0x0301), "NO" ) # Burned In Annotation
00090
00091     ano.Empty( gdcm.Tag(0x0020,0x0020) )
00092
00093     ano.Remove( gdcm.Tag(0x7fe0,0x0000) )
00094
00095     #ano.Empty( gdcm.Tag(0x0028,0x0009) ) # Frame Increment Pointer
00096

```

```

00097     #ano.Empty( gdcm.Tag(0x0028,0x1052) )  #<entry group="0028" element="1052" vr="DS" vm="1" name="Rescale
Intercept"/>
00098     #ano.Empty( gdcm.Tag(0x0028,0x1053) )  #<entry group="0028" element="1053" vr="DS" vm="1" name="Rescale
Slope"/>
00099     #ano.Replace( gdcm.Tag(0x0028,0x1054), "US" )  #<entry group="0028" element="1054" vr="LO" vm="1"
name="Rescale Type"/>
00100
00101     ano.Replace( gdcm.Tag(0x2050, 0x0020), "IDENTITY")
00102     ""
00103
00104     w = gdcm.Writer()
00105     w.SetFile( ano.GetFile() )
00106     w.SetFileName( file2 )
00107     if not w.Write():
00108         sys.exit(1)

```

12.127 ManipulateSequence.py

```

00001
00014
00015 """
00016 Usage:
00017
00018     python ManipulateSequence.py input.dcm output.dcm
00019
00020 This was tested using:
00021
00022     python ManipulateSequence.py gdcmData/D_CLUNIE_CT1_J2KI.dcm myoutput.dcm
00023
00024 This is a dummy example on how to modify a value set in a nested-nested dataset
00025
00026 WARNING:
00027 Do not use as-is in production, this is just an example
00028 This example works in an undefined length Item only (you need to explicitly recompute the length
otherwise)
00029 """
00030
00031 import sys
00032 import gdcm
00033
00034 if __name__ == "__main__":
00035
00036     file1 = sys.argv[1]
00037     file2 = sys.argv[2]
00038
00039     r = gdcm.Reader()
00040     r.SetFileName( file1 )
00041     if not r.Read():
00042         sys.exit(1)
00043
00044     f = r.GetFile()
00045     ds = f.GetDataSet()
00046     tsis = gdcm.Tag(0x0008,0x2112) # SourceImageSequence
00047     if ds.FindDataElement( tsis ):
00048         sis = ds.GetDataElement( tsis )
00049         #sqsis = sis.GetSequenceOfItems()
00050         # GetValueAsSQ handle more cases
00051         sqsis = sis.GetValueAsSQ()
00052         if sqsis.GetNumberOfItems():
00053             item1 = sqsis.GetItem(1)
00054             nestedds = item1.GetNestedDataSet()
00055             tprcs = gdcm.Tag(0x0040,0xa170) # PurposeOfReferenceCodeSequence
00056             if nestedds.FindDataElement( tprcs ):
00057                 prcs = nestedds.GetDataElement( tprcs )
00058                 sqprcs = prcs.GetSequenceOfItems()
00059                 if sqprcs.GetNumberOfItems():
00060                     item2 = sqprcs.GetItem(1)
00061                     nestedds2 = item2.GetNestedDataSet()
00062                     # (0008,0104) LO [Uncompressed predecessor] # 24, 1 CodeMeaning
00063                     tcm = gdcm.Tag(0x0008,0x0104)
00064                     if nestedds2.FindDataElement( tcm ):
00065                         cm = nestedds2.GetDataElement( tcm )
00066                         mystr = "GDCM was here"
00067                         cm.SetByteStringValue( mystr )
00068
00069     w = gdcm.Writer()

```



```

00070     w.SetFile( f )
00071     w.SetFileName( file2 )
00072     if not w.Write():
00073         sys.exit(1)

```

12.128 MergeFile.py

```

00001
00014
00015 """
00016 Usage:
00017
00018     python MergeFile.py input1.dcm input2.dcm
00019
00020     It will produce a 'merge.dcm' output file, which contains all meta information from input1.dcm
00021     and copy the Stored Pixel values from input2.dcm
00022     This script even works when input2.dcm is a Secondary Capture and does not contains information
00023     such as IOP and IPP...
00024 """
00025
00026 import sys
00027 import gdcm
00028
00029 if __name__ == "__main__":
00030
00031     file1 = sys.argv[1]
00032     file2 = sys.argv[2]
00033
00034     r1 = gdcm.ImageReader()
00035     r1.SetFileName( file1 )
00036     if not r1.Read():
00037         sys.exit(1)
00038
00039     r2 = gdcm.ImageReader()
00040     r2.SetFileName( file2 )
00041     if not r2.Read():
00042         sys.exit(1)
00043
00044     # Image from r2 could be Secondary Capture and thus would not contains neither IPP nor IOP
00045     # Instead always prefer to only copy the Raw Data Element.
00046     # Warning ! Image need to be identical ! Only the value of Stored Pixel can be different.
00047     r1.GetImage().SetDataElement( r2.GetImage().GetDataElement() )
00048
00049     w = gdcm.ImageWriter()
00050     w.SetFile( r1.GetFile() )
00051     #w.SetImage( r2.GetImage() ) # See comment above
00052     w.SetImage( r1.GetImage() )
00053
00054     w.SetFileName( "merge.dcm" )
00055     if not w.Write():
00056         sys.exit(1)
00057
00058     sys.exit(0)

```

12.129 NewSequence.py

```

00001
00014
00015 """
00016 Usage:
00017
00018     python NewSequence.py input.dcm output.dcm
00019
00020
00021 Thanks to Robert Irie for code
00022 """
00023
00024 import sys
00025 import gdcm
00026
00027 if __name__ == "__main__":
00028

```

```

00029 file1 = sys.argv[1]
00030 file2 = sys.argv[2]
00031
00032 r = gdcm.Reader()
00033 r.SetFileName( file1 )
00034 if not r.Read():
00035     sys.exit(1)
00036
00037 f = r.GetFile()
00038 ds = f.GetDataSet()
00039 #tsis = gdcm.Tag(0x0008,0x2112) # SourceImageSequence
00040
00041 # Create a dataelement
00042 de = gdcm.DataElement(gdcm.Tag(0x0010, 0x2180))
00043 de.SetByteStringValue("Occupation")
00044 de.SetVR(gdcm.VR(gdcm.VR.SH))
00045
00046 # Create an item
00047 it=gdcm.Item()
00048 it.SetVLToUndefined() # Needed to not popup error message
00049 #it.InsertDataElement(de)
00050 nds=it.GetNestedDataSet()
00051 nds.Insert(de)
00052
00053 # Create a Sequence
00054 sq=gdcm.SequenceOfItems().New()
00055 sq.SetLengthToUndefined()
00056 sq.AddItem(it)
00057
00058 # Insert sequence into data set
00059 des=gdcm.DataElement(gdcm.Tag(0x0400,0x0550))
00060 des.SetVR(gdcm.VR(gdcm.VR.SQ))
00061 des.SetValue(sq.__ref__())
00062 des.SetVLToUndefined()
00063
00064 ds.Insert(des)
00065
00066 w = gdcm.Writer()
00067 w.SetFile( f )
00068 w.SetFileName( file2 )
00069 if not w.Write():
00070     sys.exit(1)

```

12.130 PhilipsPrivateRescaleInterceptSlope.py

```

00001
00014
00015 """
00016 Usage:
00017
00018 python
00019 """
00020
00021 import gdcm
00022 import sys
00023
00024 filename = sys.argv[1]
00025 tmpfile = "/tmp/philips_rescaled.dcm"
00026
00027
00028 # Need to access some private tags, read the file :
00029 reader = gdcm.Reader()
00030 reader.SetFileName( filename )
00031 if not reader.Read():
00032     sys.exit(1)
00033
00034 ds = reader.GetFile().GetDataSet()
00035
00036 #print ds
00037 # (2005,1409)      DS      4      0.0
00038 # (2005,140a)      DS      16     1.52283272283272
00039
00040 # (2005,0014)      LO      26     Philips MR Imaging DD 005
00041 tag1 = gdcm.PrivateTag(0x2005,0x09,"Philips MR Imaging DD 005")
00042 tag2 = gdcm.PrivateTag(0x2005,0x0a,"Philips MR Imaging DD 005")
00043 print tag1

```

```

00044 print tag2
00045
00046 # make sure to do a copy, we want the private tag to remain
00047 # otherwise gdcm gives us a reference
00048 e11 = gdcm.DataElement( ds.GetDataElement( tag1 ) )
00049 print e11
00050 e12 = gdcm.DataElement( ds.GetDataElement( tag2 ) )
00051 print e12
00052
00053 # (0028,1052) DS [-1000] # 6, 1 RescaleIntercept
00054 # (0028,1053) DS [1] # 2, 1 RescaleSlope
00055
00056 e11.SetTag( gdcm.Tag(0x0028,0x1052) )
00057 e12.SetTag( gdcm.Tag(0x0028,0x1053) )
00058
00059 ds.Insert( e11 )
00060 ds.Insert( e12 )
00061
00062 w = gdcm.Writer()
00063 w.SetCheckFileMetaInformation( False )
00064 w.SetFileName( tmpfile )
00065 w.SetFile( reader.GetFile() )
00066 if not w.Write():
00067     sys.exit(1)
00068
00069 print "success"

```

12.131 PlaySound.py

```

00001
00014
00015 """
00016 Usage:
00017
00018 python PlaySound.py input.dcm
00019 """
00020
00021 import gdcm
00022 import sys
00023
00024 #filename = "/home/mmalaterre/Creatis/gdcmDataExtra/gdcmNonImageData/audio_from_rafael_sanguinetti.dcm"
00025 filename = sys.argv[1]
00026 print filename
00027
00028 r = gdcm.Reader()
00029 r.SetFileName( filename )
00030 if not r.Read():
00031     sys.exit(1)
00032
00033 ds = r.GetFile().GetDataSet()
00034
00035 waveformtag = gdcm.Tag(0x5400,0x0100)
00036 waveformsq = ds.GetDataElement( waveformtag )
00037 #print waveformsq
00038
00039 #print dir(waveformsq)
00040
00041 items = waveformsq.GetSequenceOfItems()
00042
00043 if not items.GetNumberOfItems():
00044     sys.exit(1)
00045
00046 item = items.GetItem(1)
00047 #print item
00048
00049 waveformds = item.GetNestedDataSet()
00050 #print waveformds
00051
00052 waveformdatatag = gdcm.Tag(0x5400,0x1010)
00053 waveformdata = waveformds.GetDataElement( waveformdatatag )
00054
00055 #print waveformdata.GetPointer()
00056 bv = waveformdata.GetByteValue()
00057 print dir(bv)
00058
00059 #print bv.GetPointer()

```

```

00060 print bv.GetLength()
00061 l = 116838
00062
00063 file='test.wav'
00064 myfile = open(file, "wb")
00065 s = bv.GetPointer()
00066 for i in range(0, l):
00067     myfile.write(s[i])
00068 myfile.close()
00069
00070 # http://mail.python.org/pipermail/python-list/2004-October/288905.html
00071 if sys.platform.startswith('win'):
00072     from winsound import PlaySound, SND_FILENAME, SND_ASYNC
00073     PlaySound(file, SND_FILENAME|SND_ASYNC)
00074 elif sys.platform.find('linux')>-1:
00075     from wave import open as waveOpen
00076     from ossaudiodev import open as ossOpen
00077     s = waveOpen(file,'rb')
00078     (nc,sw,fr,nf,comptype, compname) = s.getparams( )
00079     dsp = ossOpen('/dev/dsp','w')
00080     try:
00081         from ossaudiodev import AFMT_S16_NE
00082     except ImportError:
00083         if byteorder == "little":
00084             AFMT_S16_NE = ossaudiodev.AFMT_S16_LE
00085         else:
00086             AFMT_S16_NE = ossaudiodev.AFMT_S16_BE
00087     dsp.setparameters(AFMT_S16_NE, nc, fr)
00088     data = s.readframes(nf)
00089     s.close()
00090     dsp.write(data)
00091     dsp.close()

```

12.132 PrivateDict.py

```

00001
00014
00015 """
00016 """
00017
00018 import gdcmm
00019 import sys,os
00020
00021 if __name__ == "__main__":
00022     #gdcmm.Trace.DebugOn()
00023     globInst = gdcmm.Global.GetInstance()
00024     # Try to load Part3.xml file
00025     # This file is too big for being accessible directly at runtime.
00026     globInst.LoadResourcesFiles()
00027
00028
00029 # Get a private tag from the runtime dicts. LoadResourcesFiles could
00030 # have failed but this has no impact on the private dict
00031
00032 d = globInst.GetDicts()
00033 print d.GetDictEntry( gdcmm.Tag(0x0029,0x0010) ,"SIEMENS CSA HEADER" )
00034 pd = d.GetPrivateDict()
00035 print pd.GetDictEntry( gdcmm.PrivateTag(0x0029,0x0010,"SIEMENS CSA HEADER") )

```

12.133 ReWriteSCAsMR.py

```

00001
00014
00015 """
00016 GDCM 1.x would write out MR Image Storage as Secondary Capture Object while still setting Rescale
00017 Slope/Intercept
00018 and saving the Pixel Spacing in (0028,0030)
00019 """
00020
00021 import gdcmm
00022 import sys,os
00023
00024

```

```

00023 def CheckSecondaryCaptureObjectIsMRImageStorage(r):
00024     ds = r.GetFile().GetDataSet()
00025     # Check Source Image Sequence
00026     if ds.FindDataElement( gdcm.Tag(0x0008,0x2112) ):
00027         sis = ds.GetDataElement( gdcm.Tag(0x0008,0x2112) )
00028         sqsis = sis.GetSequenceOfItems()
00029         if sqsis.GetNumberOfItems():
00030             item1 = sqsis.GetItem(1)
00031             nestedds = item1.GetNestedDataSet()
00032             if nestedds.FindDataElement( gdcm.Tag(0x0008,0x1150) ):
00033                 ReferencedSOPClassUID = nestedds.GetDataElement( gdcm.Tag(0x0008,0x1150) )
00034                 raw = ReferencedSOPClassUID.GetByteValue().GetPointer()
00035                 uids = gdcm.UIDs()
00036                 # what is the actual object we are looking at ?
00037                 ms = gdcm.MediaStorage()
00038                 ms.SetFromDataSet(ds)
00039                 msuid = ms.GetString()
00040                 uids.SetFromUID( msuid )
00041                 msuidname = uids.GetName() # real Media Storage Name
00042                 uids.SetFromUID( raw )
00043                 sqmsuidname = uids.GetName() # Source Image Sequence Media Storage Name
00044                 # If object is SC and Source derivation is MRImageStorage then we can assume 'Pixel Spacing' is
correct
00045                 if( sqmsuidname == 'MR Image Storage' and msuidname == 'Secondary Capture Image Storage' ):
00046                     return True
00047                 # in all other case simply return the currentspacing:
00048                 return False
00049
00050 if __name__ == "__main__":
00051     r = gdcm.ImageReader()
00052     filename = sys.argv[1]
00053     r.SetFileName( filename )
00054     if not r.Read():
00055         sys.exit(1)
00056     f = r.GetFile()
00057
00058     if( CheckSecondaryCaptureObjectIsMRImageStorage(r) ):
00059         # Special handling of the spacing:
00060         # GDCM 1.2.0 would not rewrite correctly DICOM Object and would always set them as 'Secondary Capture
Image Storage'
00061         # while we would rather have 'MR Image Storage'
00062         gdcm.ImageHelper.SetForcePixelSpacing( True )
00063         mrspacing = gdcm.ImageHelper.GetSpacingValue( r.GetFile() )
00064         # TODO: I cannot do simply the following:
00065         #image.SetSpacing( mrspacing )
00066         image.SetSpacing(0, mrspacing[0] )
00067         image.SetSpacing(1, mrspacing[1] )
00068         image.SetSpacing(2, mrspacing[2] )
00069         gdcm.ImageHelper.SetForceRescaleInterceptSlope( True )
00070         ris = gdcm.ImageHelper.GetRescaleInterceptSlopeValue( r.GetFile() )
00071         image.SetIntercept( ris[0] )
00072         image.SetSlope( ris[1] )
00073
00074     outfilename = sys.argv[2]
00075     w = gdcm.ImageWriter()
00076     w.SetFileName( outfilename )
00077     w.SetFile( r.GetFile() )
00078     w.SetImage( image )
00079     if not w.Write():
00080         sys.exit(1)
00081
00082     sys.exit(0)

```

12.134 ReadAndDumpDICOMDIR.py

```

00001
00023
00024
00025
00026 import sys
00027 import gdcm
00028
00029 if __name__ == "__main__":
00030     # Check arguments
00031     if (len(sys.argv) < 2):
00032         # No filename passed

```

```

00033         print "No input filename found"
00034         quit()
00035
00036     filename = sys.argv[1]
00037
00038
00039     # Read file
00040     reader = gdcm.Reader()
00041     reader.SetFileName(filename)
00042     if (not reader.Read()):
00043         print "Unable to read %s" % (filename)
00044         quit()
00045
00046     file = reader.GetFile()
00047
00048     # Retrieve header information
00049     fileMetaInformation = file.GetHeader()
00050     print fileMetaInformation
00051
00052     # Retrieve data set
00053     dataSet = file.GetDataSet()
00054     #print dataSet
00055
00056     # Check media storage
00057     mediaStorage = gdcm.MediaStorage()
00058     mediaStorage.SetFromFile(file)
00059     if (gdcm.MediaStorage.GetMSType(str(mediaStorage)) != gdcm.MediaStorage.MediaStorageDirectoryStorage):
00060         # File is not a DICOMDIR
00061         print "This file is not a DICOMDIR (Media storage type: %s)" % (str(mediaStorage))
00062         quit()
00063
00064     # Check Media Storage SOP Class
00065     if (fileMetaInformation.FindDataElement(gdcm.Tag(0x0002, 0x0002))):
00066         sopClassUid = str(fileMetaInformation.GetDataElement(gdcm.Tag(0x0002, 0x0002)).GetValue())
00067         # Check SOP UID
00068         if (sopClassUid != "1.2.840.10008.1.3.10"):
00069             # File is not a DICOMDIR
00070             print "This file is not a DICOMDIR"
00071     else:
00072         # Not present
00073         print "Media Storage SOP Class not present"
00074         quit()
00075
00076     # Iterate through the DICOMDIR data set
00077     iterator = dataSet.GetDES().begin()
00078     while (not iterator.equal(dataSet.GetDES().end())):
00079         dataElement = iterator.next()
00080
00081         # Check the element tag
00082         if (dataElement.GetTag() == gdcm.Tag(0x004, 0x1220)):
00083             # The 'Directory Record Sequence' element
00084             sequence = dataElement.GetValueAsSQ()
00085
00086             # Loop through the sequence items
00087             itemNr = 1
00088             while (itemNr < sequence.GetNumberOfItems()):
00089                 item = sequence.GetItem(itemNr)
00090
00091                 # Check the element tag
00092                 if (item.FindDataElement(gdcm.Tag(0x0004, 0x1430))):
00093                     # The 'Directory Record Type' element
00094                     value = str(item.GetDataElement(gdcm.Tag(0x0004, 0x1430)).GetValue())
00095
00096                     # PATIENT
00097                     while (value.strip() == "PATIENT"):
00098                         print value.strip()
00099                         # Print patient name
00100                         if (item.FindDataElement(gdcm.Tag(0x0010, 0x0010))):
00101                             value = str(item.GetDataElement(gdcm.Tag(0x0010, 0x0010)).GetValue())
00102                             print value
00103
00104                         # Print patient ID
00105                         if (item.FindDataElement(gdcm.Tag(0x0010, 0x0020))):
00106                             value = str(item.GetDataElement(gdcm.Tag(0x0010, 0x0020)).GetValue())
00107                             print value
00108
00109                     # Next
00110                     itemNr = itemNr + 1
00111                     item = sequence.GetItem(itemNr)
00112                 if (item.FindDataElement(gdcm.Tag(0x0004, 0x1430))):
00113                     value = str(item.GetDataElement(gdcm.Tag(0x0004, 0x1430)).GetValue())

```

```

00114
00115         # STUDY
00116         while (value.strip() == "STUDY"):
00117             print value.strip()
00118
00119             # Print study UID
00120             if (item.FindDataElement(gdcm.Tag(0x0020, 0x000d))):
00121                 value = str(item.GetDataElement(gdcm.Tag(0x0020, 0x000d)).GetValue())
00122                 print value
00123
00124             # Print study date
00125             if (item.FindDataElement(gdcm.Tag(0x0008, 0x0020))):
00126                 value = str(item.GetDataElement(gdcm.Tag(0x0008, 0x0020)).GetValue())
00127                 print value
00128
00129             # Print study description
00130             if (item.FindDataElement(gdcm.Tag(0x0008, 0x1030))):
00131                 value = str(item.GetDataElement(gdcm.Tag(0x0008, 0x1030)).GetValue())
00132                 print value
00133
00134             # Next
00135             itemNr = itemNr + 1
00136             item = sequence.GetItem(itemNr)
00137             if (item.FindDataElement(gdcm.Tag(0x0004, 0x1430))):
00138                 value = str(item.GetDataElement(gdcm.Tag(0x0004, 0x1430)).GetValue())
00139
00140             # SERIES
00141             while (value.strip() == "SERIES"):
00142                 print value.strip()
00143
00144                 # Print series UID
00145                 if (item.FindDataElement(gdcm.Tag(0x0020, 0x000e))):
00146                     value = str(item.GetDataElement(gdcm.Tag(0x0020, 0x000e)).GetValue())
00147                     print value
00148
00149                 # Print series modality
00150                 if (item.FindDataElement(gdcm.Tag(0x0008, 0x0060))):
00151                     value = str(item.GetDataElement(gdcm.Tag(0x0008, 0x0060)).GetValue())
00152                     print "Modality"
00153                     print value
00154
00155                 # Print series description
00156                 if (item.FindDataElement(gdcm.Tag(0x0008, 0x103e))):
00157                     value = str(item.GetDataElement(gdcm.Tag(0x0008, 0x103e)).GetValue())
00158                     print "Description"
00159                     print value
00160
00161                 # Next
00162                 itemNr = itemNr + 1
00163                 item = sequence.GetItem(itemNr)
00164                 if (item.FindDataElement(gdcm.Tag(0x0004, 0x1430))):
00165                     value = str(item.GetDataElement(gdcm.Tag(0x0004, 0x1430)).GetValue())
00166
00167                 # IMAGE
00168                 while (value.strip() == "IMAGE"):
00169                     print value.strip()
00170
00171                     # Print image UID
00172                     if (item.FindDataElement(gdcm.Tag(0x0004, 0x1511))):
00173                         value = str(item.GetDataElement(gdcm.Tag(0x0004,
00174                         0x1511)).GetValue())
00175                         print value
00176
00177                     # Next
00178                     if (itemNr < sequence.GetNumberOfItems()):
00179                         itemNr = itemNr + 1
00180                     else:
00181                         break
00182
00183                     item = sequence.GetItem(itemNr)
00184                     if (item.FindDataElement(gdcm.Tag(0x0004, 0x1430))):
00185                         value = str(item.GetDataElement(gdcm.Tag(0x0004,
00186                         0x1430)).GetValue())
00187
00188                     # Next
00189                     itemNr = itemNr + 1

```

12.135 RemovePrivateTags.py

```

00001
00014
00015 """
00016 Usage:
00017
00018     python RemovePrivateTags.py input.dcm output.dcm
00019 """
00020
00021 import sys
00022 import gdcm
00023
00024
00025 if __name__ == "__main__":
00026
00027     file1 = sys.argv[1]
00028     file2 = sys.argv[2]
00029
00030     # Instantiate the reader.
00031     r = gdcm.Reader()
00032     r.SetFileName( file1 )
00033     if not r.Read():
00034         sys.exit(1)
00035
00036     # Remove private tags
00037     ano = gdcm.Anonymizer()
00038     ano.SetFile( r.GetFile() )
00039     if not ano.RemovePrivateTags():
00040         sys.exit(1)
00041
00042     # Write DICOM file
00043     w = gdcm.Writer()
00044     w.SetFile( ano.GetFile() )
00045     #w.CheckFileMetaInformationOff() # Do not attempt to check meta header
00046     w.SetFileName( file2 )
00047     if not w.Write():
00048         sys.exit(1)
00049
00050     # It is usually a good idea to exit the script with an error, as gdcm does not remove partial
    (incorrect) DICOM file
00051     # (application level)

```

12.136 ScanDirectory.py

```

00001
00014
00015 import gdcm
00016 import sys,os
00017
00018 class ProgressWatcher(gdcm.SimpleSubjectWatcher):
00019     def ShowProgress(self, sender, event):
00020         pe = gdcm.ProgressEvent.Cast(event)
00021         print pe.GetProgress()
00022     def EndFilter(self):
00023         print "Yay ! I am done"
00024
00025 if __name__ == "__main__":
00026     directory = sys.argv[1]
00027
00028     # Define the set of tags we are interested in
00029     t1 = gdcm.Tag(0x8,0x8);
00030     t2 = gdcm.Tag(0x10,0x10);
00031
00032     # Iterate over directory
00033     d = gdcm.Directory();
00034     nfiles = d.Load( directory );
00035     if(nfiles == 0): sys.exit(1);
00036     # System.Console.WriteLine( "Files:\n" + d.toString() );
00037
00038     filenames = d.GetFilenames()
00039
00040     # Get rid of any Warning while parsing the DICOM files
00041     gdcm.Trace.WarningOff()
00042
00043     # instantiate Scanner:

```



```

00044 sp = gdcms.Scanner.New();
00045 s = sp.__ref__()
00046 w = ProgressWatcher(s, 'Watcher')
00047
00048 s.AddTag( t1 );
00049 s.AddTag( t2 );
00050 b = s.Scan( filenames );
00051 if(not b): sys.exit(1);
00052
00053 print "success" ;
00054 #print s
00055
00056 pttv = gdcms.PythonTagToValue( s.GetMapping( filenames[1] ) )
00057 pttv.Start()
00058 # iterate until the end:
00059 while( not pttv.IsAtEnd() ):
00060     # get current value for tag and associated value:
00061     # if tag was not found, then it was simply not added to the internal std::map
00062     # Warning value can be None
00063     tag = pttv.GetCurrentTag()
00064     value = pttv.GetCurrentValue()
00065     print tag,"->",value
00066     # increment iterator
00067     pttv.Next()
00068
00069 sys.exit(0)

```

12.137 SortImage.py

```

00001
00014
00015 """
00016 Usage:
00017
00018 python SortImage.py dirname
00019 """
00020
00021 import gdcms
00022 import sys
00023
00024 def PrintProgress(object, event):
00025     assert event == "ProgressEvent"
00026     print "Progress:", object.GetProgress()
00027
00028 def MySort(ds1, ds2):
00029     # compare ds1
00030     return False
00031
00032 if __name__ == "__main__":
00033
00034     dirname = sys.argv[1]
00035     d = gdcms.Directory()
00036     d.Load( dirname )
00037
00038     print d
00039
00040     sorter = gdcms.Sorter()
00041     sorter.SetSortFunction( MySort )
00042     #sorter.AddObserver( "ProgressEvent", PrintProgress )
00043     sorter.Sort( d.GetFilenames() )
00044
00045     print "Sorter:"
00046     print sorter

```

12.138 WriteBuffer.py

```

00001
00014
00015 """
00016 Usage:
00017
00018 http://chuckhahm.com/Ischem/Zurich/XX_0134

```

```

00019
00020 (2005,1132) SQ (Sequence with undefined length #=8) # u/1, 1 Unknown Tag & Data
00021 (ffff,e000) na (Item with undefined length #=9) # u/1, 1 Item
00022 (2005,0011) LO [Philips MR Imaging DD 002] # 26, 1 PrivateCreator
00023 (2005,1137) PN [PDF_CONTROL_GEN_PARS] # 20, 1 Unknown Tag & Data
00024 (2005,1138) PN (no value available) # 0, 0 Unknown Tag & Data
00025 (2005,1139) PN [IEEE_PDF] # 8, 1 Unknown Tag & Data
00026 (2005,1140) PN (no value available) # 0, 0 Unknown Tag & Data
00027 (2005,1141) PN (no value available) # 0, 0 Unknown Tag & Data
00028 (2005,1143) SL 3103 # 4, 1 Unknown Tag & Data
00029 (2005,1144) OW 0566\0000\013b\0000\0a4a\0000\000e\0000\0a7a\0000\0195\0000\0008... # 3104, 1 Unknown
Tag & Data
00030 (2005,1147) CS [Y] # 2, 1 Unknown Tag & Data
00031 (ffff,e00d) na (ItemDelimitationItem) # 0, 0 ItemDelimitationItem
00032 (ffff,e000) na (Item with undefined length #=9) # u/1, 1 Item
00033 (2005,0011) LO [Philips MR Imaging DD 002] # 26, 1 PrivateCreator
00034 (2005,1137) PN [PDF_CONTROL_PREP_PARS] # 22, 1 Unknown Tag & Data
00035 (2005,1138) PN (no value available) # 0, 0 Unknown Tag & Data
00036 (2005,1139) PN [IEEE_PDF] # 8, 1 Unknown Tag & Data
00037 (2005,1140) PN (no value available) # 0, 0 Unknown Tag & Data
00038 (2005,1141) PN (no value available) # 0, 0 Unknown Tag & Data
00039 (2005,1143) SL 7934 # 4, 1 Unknown Tag & Data
00040 (2005,1144) OW 19b6\0000\005f\0000\1b2a\0000\00f3\0000\1eee\0000\0000\0000\0008... # 7934, 1 Unknown
Tag & Data
00041 (2005,1147) CS [Y] # 2, 1 Unknown Tag & Data
00042 (ffff,e00d) na (ItemDelimitationItem) # 0, 0 ItemDelimitationItem
00043 ...
00044 ""
00045
00046 import sys
00047 import gdcm
00048
00049 if __name__ == "__main__":
00050
00051     file1 = sys.argv[1]
00052     file2 = sys.argv[2]
00053
00054     r = gdcm.Reader()
00055     r.SetFileName( file1 )
00056     if not r.Read():
00057         sys.exit(1)
00058
00059     fg = gdcm.FileNameGenerator()
00060     f = r.GetFile()
00061     ds = f.GetDataSet()
00062     tsis = gdcm.Tag(0x2005,0x1132) #
00063     if ds.FindDataElement( tsis ):
00064         sis = ds.GetDataElement( tsis )
00065         #sqsis = sis.GetSequenceOfItems()
00066         # GetValueAsSQ handle more cases
00067         sqsis = sis.GetValueAsSQ()
00068         if sqsis.GetNumberOfItems():
00069             nitems = sqsis.GetNumberOfItems();
00070             fg.SetNumberOfFileNames( nitems )
00071             fg.SetPrefix( file2 )
00072             if not fg.Generate():
00073                 print "problem"
00074                 sys.exit(1)
00075             for i in range(0,nitems):
00076                 item1 = sqsis.GetItem(i+1) # Item start at 1
00077                 nestedds = item1.GetNestedDataSet()
00078                 tprcs = gdcm.Tag(0x2005,0x1144) #
00079                 if nestedds.FindDataElement( tprcs ):
00080                     prcs = nestedds.GetDataElement( tprcs )
00081                     bv = prcs.GetByteValue()
00082                     print bv
00083                     f = open( fg.GetFilename(i) , "w" )
00084                     f.write( bv.WriteBuffer() )

```

12.139 HelloActiviz.cs

```
/*=====
```

Program: GDCM (Grassroots DICOM) . A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre

All rights reserved.
See Copyright.txt or <http://gdcm.sourceforge.net/Copyright.html> for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

```
=====*/
using vtkgdcm;
using Kitware.VTK;
using System;
using System.Runtime.InteropServices;

/*
 * This example shows how vtkgdcm can be connected to Kitware.VTK Activiz product.
 * Three (3) arguments are required:
 * 1. Input DICOM file (SWIG)
 * 2. Temporary PNG (intermediate) file (Activiz)
 * 3. Final DICOM file (SWIG)
 *
 * $ export MONO_PATH=/usr/lib/cli/Activiz.NET:/usr/lib/cli/Kitware.mummy.Runtime-1.0
 * $ mono ./bin/HelloActiviz.exe ~/Creatis/gdcmData/test.acr out.png toto.dcm
 *
 * Footnote:
 * this test originally used vtkBMPWriter / vtkBMPReader combination to store intermediate
 * image file, but BMP file are 24bits by default. Instead use PNG format which supports seems
 * to be closer to what was expected in this simple test.
 */
public class HelloActiviz
{
    // Does not work with Activiz.NET-5.4.0.455-Linux-x86_64-Personal
    /*
    static void ConnectSWIGToActiviz(Kitware.VTK.vtkImageExport imgin, Kitware.VTK.vtkImageImport imgout)
    {
        imgout.SetUpdateInformationCallback(imgin.GetUpdateInformationCallback());
        imgout.SetPipelineModifiedCallback(imgin.GetPipelineModifiedCallback());
        imgout.SetWholeExtentCallback(imgin.GetWholeExtentCallback());
        imgout.SetSpacingCallback(imgin.GetSpacingCallback());
        imgout.SetOriginCallback(imgin.GetOriginCallback());
        imgout.SetScalarTypeCallback(imgin.GetScalarTypeCallback());
        imgout.SetNumberOfComponentsCallback(imgin.GetNumberOfComponentsCallback());
        imgout.SetPropagateUpdateExtentCallback(imgin.GetPropagateUpdateExtentCallback());
        imgout.SetUpdateDataCallback(imgin.GetUpdateDataCallback());
        imgout.SetDataExtentCallback(imgin.GetDataExtentCallback());
        imgout.SetBufferPointerCallback(imgin.GetBufferPointerCallback());
        imgout.SetCallbackUserData(imgin.GetCallbackUserData());
    }
    */

    static Kitware.VTK.vtkImageData ConnectSWIGToActiviz(vtkgdcm.vtkImageData imgin)
    {
        HandleRef rawCppThis = imgin.GetCppThis();
        Kitware.VTK.vtkImageData imgout = new Kitware.VTK.vtkImageData( rawCppThis.Handle, false, false);
        return imgout;
    }

    static vtkgdcm.vtkImageData ConnectActivizToSWIG(Kitware.VTK.vtkImageData imgin)
    {
        HandleRef rawCppThis = imgin.GetCppThis();
        vtkgdcm.vtkImageData imgout = new vtkgdcm.vtkImageData( rawCppThis );
        return imgout;
    }

    public static int Main(string[] args)
    {
        string filename = args[0];
        string outfilename = args[1];

        // Step 1. Test SWIG -> Activiz
        vtkGDCMImageReader reader = vtkGDCMImageReader.New();
        reader.SetFileName( filename );
        //reader.Update(); // DO NOT call Update to check pipeline execution

        Kitware.VTK.vtkImageData imgout = ConnectSWIGToActiviz(reader.GetOutput());

        System.Console.WriteLine( imgout.ToString() ); // not initialized as expected

        vtkPNGWriter writer = new vtkPNGWriter();
        writer.SetInput( imgout );
        writer.SetFileName( outfilename );
    }
}
```

```

writer.Write();

// Step 2. Test Activiz -> SWIG
vtkPNGReader bmpreader = new vtkPNGReader();
bmpreader.SetFileName( outfilename );
//bmpreader.Update(); // DO NOT update to check pipeline execution

System.Console.WriteLine( bmpreader.GetOutput().ToString() ); // not initialized as expected

vtkgdcml.vtkImageData imgout2 = ConnectActivizToSWIG(bmpreader.GetOutput());

System.Console.WriteLine( imgout2.ToString() ); // not initialized as expected

Kitware.VTK.vtkMedicalImageProperties prop = new Kitware.VTK.vtkMedicalImageProperties();
prop.SetModality( "MR" );

string outfilename2 = args[2];
vtkGDCMImageWriter writer2 = vtkGDCMImageWriter.New();
writer2.SetMedicalImageProperties( prop.CastToActiviz() );
writer2.SetFileName( outfilename2 );
writer2.SetInput( imgout2 );
writer2.Write();

return 0;
}
}

```

12.140 HelloActiviz2.cs

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
using Kitware.VTK;
using Kitware.VTK.GDCM;

/*
 * Usage:
 * $ export MONO_PATH=/usr/lib/cli/Activiz.NET:/usr/lib/cli/Kitware.mummy.Runtime-1.0
 * $ mono ./bin/HelloActiviz2.exe gdcmlData/test.acr bla.png bla2.dcm
 */

/*
 * From the outside view, no-one can detect that object pass to/from
 * vtkGDCMImageWriter/vtkGDCMImageReader are not Activiz object.
 *
 * TODO: Test Command/Observer
 */
public class HelloActiviz2
{
    public static int Main(string[] args)
    {
        string filename = args[0];
        string outfilename = args[1];
        string outfilename2 = args[2];

        vtkGDCMImageReader reader = new Kitware.VTK.GDCM.vtkGDCMImageReader();
        reader.SetFileName( filename );

        // When calling multiple times creation of C# object from the same C++ object it triggers a:
        //error: potential refcounting error: Duplicate rawCppThis - weak reference that is still alive. Attempting to
        //    add '0x00b2dc10' again.
        //    Allowing new wrapped object to take over table key...
        //    Original object should *not* have been destroyed while we still had it in our table without notifying
        //    us...
        //reader.GetOutput();
    }
}

```

```

//reader.GetOutput();

System.Console.WriteLine( reader.ToString() ); // Test the ToString compat with Activiz

vtkGDCMImageWriter writer = new vtkGDCMImageWriter();
writer.SetInput( reader.GetOutput() );
writer.SetFileName( outfilename2 );
writer.Write();

System.Console.WriteLine( reader.GetOutput().ToString() ); // Test the ToString compat with Activiz

System.Console.WriteLine( writer.ToString() ); // Test the ToString compat with Activiz

vtkPNGWriter pngwriter = new vtkPNGWriter();
pngwriter.SetInput( reader.GetOutput() );
pngwriter.SetFileName( outfilename );
pngwriter.Write();

// at that point the .Write() should have triggered an Update() on the reader:
if( reader.GetImageFormat() == vtkgdc.VTK_LUMINANCE ) // MONOCHROME2
{
    System.Console.WriteLine( "Image is MONOCHROME2" ); //
}

vtkPNGReader bmpreader = new vtkPNGReader();
bmpreader.SetFileName( outfilename );

vtkMedicalImageProperties prop = new vtkMedicalImageProperties();
prop.SetModality( "MR" );

vtkMatrix4x4 dircos = reader.GetDirectionCosines();
dircos.Invert();

vtkGDCMImageWriter writer2 = new vtkGDCMImageWriter();
writer2.SetFileName( outfilename2 );
writer2.SetDirectionCosines( dircos );
writer2.SetMedicalImageProperties( prop );
writer2.SetInput( bmpreader.GetOutput() );
writer2.Write();

return 0;
}
}

```

12.141 HelloActiviz3.cs

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdc.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.
=====*/
using Kitware.VTK;
using Kitware.VTK.GDCM;

/*
 * $ export MONO_PATH=/usr/lib/cli/Activiz.NET:/usr/lib/cli/Kitware.mummy.Runtime-1.0
 * $ mono ./bin/HelloActiviz3.exe ~/Creatis/gdcmData/test.acr
 */
public class HelloActiviz3
{
    public static int Main(string[] args)
    {
        string filename = args[0];

        vtkGDCMImageReader reader = vtkGDCMImageReader.New();
        vtkStringArray array = vtkStringArray.New();
        array.InsertNextValue(filename);

        reader.SetFileNames(array);
    }
}

```

```

        reader.Update();

        //System.Console.WriteLine(reader.GetOutput());

        vtkRenderWindowInteractor iren = vtkRenderWindowInteractor.New();

        vtkImageViewer2 viewer = vtkImageViewer2.New();
        viewer.SetInput(reader.GetOutput());
        viewer.SetupInteractor(iren);
        viewer.SetSize(600, 600);
        viewer.Render();

        iren.Initialize();
        iren.Start();

        return 0;
    }
}

```

12.142 HelloActiviz4.cs

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.
=====*/
using Kitware.VTK;
using Kitware.VTK.GDCM;

/*
 * $ export MONO_PATH=/usr/lib/cli/Activiz.NET:/usr/lib/cli/Kitware.mummy.Runtime-1.0
 * $ mono ./bin/HelloActiviz4.exe ~/Creatis/gdcmData/test.acr
 */
public class HelloActiviz4
{
    public static int Main(string[] args)
    {
        string filename = args[0];

        vtkGDCMImageReader reader = new vtkGDCMImageReader();
        vtkStringArray array = vtkStringArray.New();
        array.InsertNextValue(filename);

        reader.SetFileNames(array);
        reader.Update();

        //System.Console.WriteLine(reader.GetOutput());

        vtkRenderWindowInteractor iren = vtkRenderWindowInteractor.New();

        vtkImageViewer viewer = vtkImageViewer.New();
        viewer.SetInput(reader.GetOutput());
        viewer.SetupInteractor(iren);
        viewer.SetSize(600, 600);
        viewer.Render();

        iren.Initialize();
        iren.Start();

        return 0;
    }
}

```

12.143 HelloActiviz5.cs

```

/*=====

```

```

Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
using Kitware.VTK;
using Kitware.VTK.GDCM;

// The command line arguments are:
// -I      => run in interactive mode; unless this is used, the program will
//          not allow interaction and exit
// -D <path> => path to the data; the data should be in <path>/Data/

/*
 * $ export MONO_PATH=/usr/lib/cli/Activiz.NET:/usr/lib/cli/Kitware.mummy.Runtime-1.0
 * $ mono ./bin/HelloActiviz5.exe -I
 */
public class HelloActiviz5
{
    public static int Main(string[] args)
    {
        vtkTesting testHelper = vtkTesting.New();
        for ( int cc = 0; cc < args.Length; cc++ )
        {
            //testHelper.AddArguments(argc,const_cast<const char **>(argv));
            //System.Console.Write( "args: " + args[cc] + "\n" );
            testHelper.AddArgument( args[cc] );
        }
        if ( testHelper.IsFlagSpecified("-D") != 0 )
        {
            string VTK_DATA_ROOT = vtkGDCMTesting.GetVTKDataRoot();
            if( VTK_DATA_ROOT != null )
            {
                //System.Console.Write( "VTK_DATA_ROOT: " + VTK_DATA_ROOT + "\n" );
                testHelper.SetDataRoot(VTK_DATA_ROOT);
                testHelper.AddArgument("-D");
                testHelper.AddArgument(VTK_DATA_ROOT);
            }
        }

        string dataRoot = testHelper.GetDataRoot();
        string filename = dataRoot;
        filename += "/Data/mr.001";

        vtkDirectory dir = vtkDirectory.New();
        if( dir.FileIsDirectory( dataRoot ) == 0 )
        {
            filename = vtkGDCMTesting.GetGDCMDataRoot() + "/test.acr";
        }
        //System.Console.Write( "dataRoot: " + dataRoot + "\n" );
        System.Console.Write( "filename being used is: " + filename + "\n" );

        vtkGDCMImageReader reader = vtkGDCMImageReader.New();
        vtkStringArray array = vtkStringArray.New();
        array.InsertNextValue(filename);
        reader.SetFileNames(array);
        reader.Update();

        System.Console.Write(reader.GetOutput());

        vtkRenderWindowInteractor iren = vtkRenderWindowInteractor.New();

        vtkRenderer ren1 = vtkRenderer.New();
        vtkRenderWindow renWin = vtkRenderWindow.New();
        renWin.AddRenderer(ren1);

        vtkImageActor actor = vtkImageActor.New();

        vtkImageMapToWindowLevelColors coronalColors = vtkImageMapToWindowLevelColors.New();
        coronalColors.SetInput(reader.GetOutput());

        actor.SetInput(coronalColors.GetOutput());

        ren1.AddActor(actor);
    }
}

```

```

    iren.SetRenderWindow(renWin);

    iren.Initialize();

    renWin.Render();

    int retVal = testHelper.IsInteractiveModeSpecified();

    if( retVal != 0 )
    {
        iren.Start();
    }

    return 0;
}

```

12.144 HelloVTKWorld.cs

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.
=====*/
using vtkgdcm;

/*
 * This test only test the SWIG/VTK part, you do not need Activiz
 */
public class HelloVTKWorld
{
    public static int Main(string[] args)
    {
        string filename = args[0];
        vtkGDCMImageReader reader = vtkGDCMImageReader.New();
        reader.SetFileName( filename );
        reader.Update();

        vtkMedicalImageProperties prop = reader.GetMedicalImageProperties();
        System.Console.WriteLine( prop.GetPatientName() ); //

        if( reader.GetImageFormat() == vtkgdcm.vtkgdcm.VTK_LUMINANCE ) // MONOCHROME2
        {
            System.Console.WriteLine( "Image is MONOCHROME2" ); //
        }

        // Just for fun, invert the direction cosines, output should reflect that:
        vtkMatrix4x4 dircos = reader.GetDirectionCosines();
        dircos.Invert();

        string outfilename = args[1];
        vtkGDCMImageWriter writer = vtkGDCMImageWriter.New();
        writer.SetMedicalImageProperties( reader.GetMedicalImageProperties() );
        writer.SetDirectionCosines( dircos );
        writer.SetShift( reader.GetShift() );
        writer.SetScale( reader.GetScale() );
        writer.SetImageFormat( reader.GetImageFormat() );
        writer.SetFileName( outfilename );
        writer.SetInputConnection( reader.GetOutputPort() );
        writer.Write();

        return 0;
    }
}

```


12.145 HelloVTKWorld2.cs

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.
=====*/
using vtkgdcm;

/*
 * This test only test the SWIG/VTK part, you do not need Activiz
 */
public class HelloVTKWorld2
{
    public static int Main(string[] args)
    {
        string VTK_DATA_ROOT = vtkGDCMTesting.GetVTKDataRoot();

        vtkVolume16Reader reader = vtkVolume16Reader.New();
        reader.SetDataDimensions(64, 64);
        reader.SetDataByteOrderToLittleEndian();
        reader.SetFilePrefix(VTK_DATA_ROOT + "/Data/headsq/quarter");
        reader.SetImageRange(1, 93);
        reader.SetDataSpacing(3.2, 3.2, 1.5);

        vtkImageCast cast = vtkImageCast.New();
        cast.SetInputConnection( reader.GetOutputPort() );
        cast.SetOutputScalarTypeToUnsignedChar();

        // By default this is creating a Multiframe Grayscale Word Secondary Capture Image Storage
        vtkGDCMImageWriter writer = vtkGDCMImageWriter.New();
        writer.SetFileName( "headsq.dcm" );
        writer.SetInputConnection( reader.GetOutputPort() );
        // cast -> Multiframe Grayscale Byte Secondary Capture Image Storage
        // writer.SetInputConnection( cast.GetOutputPort() );
        writer.SetFileDimensionality( 3 );
        writer.Write();

        return 0;
    }
}

```

12.146 MetaImageMD5Activiz.cs

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.
=====*/
using Kitware.VTK;
using Kitware.VTK.GDCM;
using gdcm;

/*
 * $ export MONO_PATH=/usr/lib/cli/Activiz.NET:/usr/lib/cli/Kitware.mummy.Runtime-1.0
 * $ mono ./bin/MetaImageMD5Activiz.exe gdcmData/012345.002.050.dcm
 */
public class MetaImageMD5Activiz
{
    public static int ProcessOneMHDMD5(string filename)

```

```

{
    vtkGDCMImageReader reader = vtkGDCMImageReader.New();
    reader.FileLowerLeftOn();
    reader.DebugOff();
    int canread = reader.CanReadFile( filename );
    if( canread == 0 )
    {
        string refms = gdcm.Testing.GetMediaStorageFromFile(filename);
        if( gdcm.MediaStorage.IsImage( gdcm.MediaStorage.GetMSType(refms) ) )
        {
            System.Console.Write( "Problem with file: " + filename + "\n" );
            return 1;
        }
        // not an image
        return 0;
    }

    reader.SetFileName( filename );
    reader.Update();

    // System.Console.Write(reader.GetOutput());

    vtkMetaImageWriter writer = vtkMetaImageWriter.New();
    writer.SetCompression( false );
    writer.SetInput( reader.GetOutput() );
    string subdir = "MetaImageMD5Activiz";
    string tmpdir = gdcm.Testing.GetTempDirectory( subdir );
    if( !gdcm.PosixEmulation.FileIsDirectory( tmpdir ) )
    {
        gdcm.PosixEmulation.MakeDirectory( tmpdir );
    }
    string mhdfile = gdcm.Testing.GetTempFilename( filename, subdir );

    string rawfile = mhdfile;
    mhdfile += ".mhd";
    rawfile += ".raw";
    writer.SetFileName( mhdfile );
    writer.Write();

    string digestmhd = gdcm.Testing.ComputeFileMD5( mhdfile );
    string digestraw = gdcm.Testing.ComputeFileMD5( rawfile );

    string mhdref = vtkGDCMTesting.GetMHDMD5FromFile(filename);
    string rawref = vtkGDCMTesting.GetRAWMD5FromFile(filename);

    if( mhdref != digestmhd )
    {
        System.Console.Write( "Problem with mhd file: " + filename + "\n" );
        System.Console.Write( digestmhd );
        System.Console.Write( "\n" );
        System.Console.Write( mhdref );
        System.Console.Write( "\n" );
        return 1;
    }
    if( rawref != digestraw )
    {
        System.Console.Write( "Problem with raw file: " + filename + "\n" );
        System.Console.Write( digestraw );
        System.Console.Write( "\n" );
        System.Console.Write( rawref );
        System.Console.Write( "\n" );
        return 1;
    }

    return 0;
}

public static int Main(string[] args)
{
    if ( args.Length == 1 )
    {
        string filename = args[0];
        return ProcessOneMHDMD5( filename );
    }

    // Loop over all gdcmData
    gdcm.Trace.DebugOff();
    gdcm.Trace.WarningOff();
    gdcm.Trace.ErrorOff();

    uint n = gdcm.Testing.GetNumberOfFileNames();
    int ret = 0;
    for( uint i = 0; i < n; ++i )

```

```

    {
        string filename = gdcm.Testing.GetFileName( i );
        ret += ProcessOneMHDMD5( filename );
    }
    return ret;
}

```

12.147 RefCounting.cs

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
using Kitware.VTK;
using Kitware.VTK.GDCM;

/*
 * this is not so much an example but simply a test to make sure ctor / dctor work as expected
 * and call the ::New and ->Delete() of VTK style.
 */
public class RefCounting
{
    public static int Main(string[] args)
    {
        vtkGDCMTesting testing1 = vtkGDCMTesting.New();
        vtkGDCMTesting testing2 = new vtkGDCMTesting(); // just in case people do not read STYLE documentation

        vtkGDCMImageReader reader1 = vtkGDCMImageReader.New();
        vtkGDCMImageReader reader2 = new vtkGDCMImageReader();

        vtkGDCMImageWriter writer1 = vtkGDCMImageWriter.New();
        vtkGDCMImageWriter writer2 = new vtkGDCMImageWriter();

        using (vtkGDCMTesting testing3 = new vtkGDCMTesting())
        {
            System.Console.WriteLine( "GetReferenceCount: " + testing1.GetReferenceCount() + "\n");
            System.Console.WriteLine( "GetReferenceCount: " + testing2.GetReferenceCount() + "\n");
            System.Console.WriteLine( "GetReferenceCount: " + testing3.GetReferenceCount() + "\n");
        }

        using (vtkGDCMImageReader reader3 = new vtkGDCMImageReader())
        {
            System.Console.WriteLine( "GetReferenceCount: " + reader3.GetReferenceCount() + "\n");
        }

        using (vtkGDCMImageWriter writer3 = vtkGDCMImageWriter.New())
        {
            System.Console.WriteLine( "GetReferenceCount: " + writer3.GetReferenceCount() + "\n");
        }

        // C# destructor will call ->Delete on all C++ object as expected.
        return 0;
    }
}

```

12.148 Compute3DSpacing.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre

```

All rights reserved.
See Copyright.txt or <http://gdcm.sourceforge.net/Copyright.html> for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

```

=====*/
#include "vtkGDCMImageReader2.h"
#include "vtkImageChangeInformation.h"
#include "vtkStringArray.h"
#include "vtkVersion.h"
#include "gdcmIPPSorter.h"

#ifdef vtkFloatingPointType
#define vtkFloatingPointType double
#endif

/*
 * Simple example to check computation of spacing within vtkGDCMImageReader2
 * This is a direct implementation of:
 *
 *      http://gdcm.sourceforge.net/wiki/index.php/Using_GDCM_API#Automatic_ordering_of_slices_for_vtkGDCMImageReader.SetFileNames
 *
 * For more advanced information on how 3D spacing is being computed see:
 *
 * - http://gdcm.sourceforge.net/html/classgdcm_1_1IPPSorter.html
 *
 * Usage:
 *
 * $ Compute3DSpacing SIEMENS_MAGNETOM-12-MONO2-FileSeq0.dcm \
 *   SIEMENS_MAGNETOM-12-MONO2-FileSeq1.dcm \
 *   SIEMENS_MAGNETOM-12-MONO2-FileSeq2.dcm \
 *   SIEMENS_MAGNETOM-12-MONO2-FileSeq3.dcm
 */

int main(int argc, char *argv[])
{
    if( argc < 2 ) return 1;

    std::vector<std::string> filenames;
    for( int i = 1; i < argc; ++i )
    {
        filenames.push_back( argv[i] );
    }

    gdcm::IPPSorter s;
    s.SetComputeZSpacing( true );
    s.SetZSpacingTolerance( 1e-3 );
    bool b = s.Sort( filenames );
    if( !b )
    {
        std::cerr << "Failed to sort files" << std::endl;
        return 1;
    }
    std::cout << "Sorting succeeded:" << std::endl;
    //s.Print( std::cout );

    std::cout << "Found z-spacing:" << std::endl;
    std::cout << s.GetZSpacing() << std::endl;
    const double ipzspacing = s.GetZSpacing();

    const std::vector<std::string> & sorted = s.GetFileNames();
    vtkGDCMImageReader2 * reader = vtkGDCMImageReader2::New();
    vtkStringArray *files = vtkStringArray::New();
    std::vector< std::string >::const_iterator it = sorted.begin();
    for( ; it != sorted.end(); ++it )
    {
        const std::string &f = *it;
        files->InsertNextValue( f.c_str() );
    }
    reader->SetFileNames( files );
    reader->Update();

    const vtkFloatingPointType *spacing = reader->GetOutput()->GetSpacing();
    vtkImageChangeInformation *v16 = vtkImageChangeInformation::New();
    #if (VTK_MAJOR_VERSION >= 6)
    v16->SetInputConnection( reader->GetOutputPort() );
    #else
    v16->SetInput( reader->GetOutput() );
    #endif
}

```

```

#endif
v16->SetOutputSpacing( spacing[0], spacing[1], ippzspacing );
v16->Update();

v16->GetOutput()->Print( std::cout );

return 0;
}

```

12.149 Convert16BitsTo8Bits.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcml.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
#include "vtkGDCMImageReader.h"
#include "vtkGDCMImageWriter.h"
#include "vtkImageData.h"
#include "vtkImageCast.h"
#include "vtkVersion.h"

#include "gdcmlTesting.h"
// The following file is 16/16/15 but the scalar range of the image is [0,192]
// it could be safely stored as 8bits instead:
// gdcmlData/012345.002.050.dcm

int main(int, char *[])
{
    const char *directory = gdcml::Testing::GetDataRoot();
    if(!directory) return 1;
    std::string file = std::string(directory) + "/012345.002.050.dcm";
    std::cout << file << std::endl;

    vtkGDCMImageReader *reader = vtkGDCMImageReader::New();
    reader->SetFileName( file.c_str() );
    reader->Update();
    //reader->GetOutput()->Print( std::cout );

    vtkImageCast *cast = vtkImageCast::New();
    #if (VTK_MAJOR_VERSION >= 6)
        cast->SetInputConnection( reader->GetOutputPort() );
    #else
        cast->SetInput( reader->GetOutput() );
    #endif
    cast->SetOutputScalarTypeToUnsignedChar();

    vtkGDCMImageWriter *writer = vtkGDCMImageWriter::New();
    writer->SetFileName( "/tmp/cast.dcm" );
    #if (VTK_MAJOR_VERSION >= 6)
        writer->SetInputConnection( cast->GetOutputPort() );
    #else
        writer->SetInput( cast->GetOutput() );
    #endif
    writer->SetImageFormat( reader->GetImageFormat() );
    writer->SetMedicalImageProperties( reader->GetMedicalImageProperties() );
    writer->SetDirectionCosines( reader->GetDirectionCosines() );
    writer->SetShift( reader->GetShift() );
    writer->SetScale( reader->GetScale() );
    writer->Write();

    reader->Delete();
    cast->Delete();
    writer->Delete();

    return 0;
}

```

12.150 ConvertMultiFrameToSingleFrame.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
#include "vtkGDCMImageReader.h"
#include "vtkGDCMImageWriter.h"
#include "vtkImageData.h"
#include "vtkStringArray.h"
#include "vtkVersion.h"

#include "gdcmTesting.h"
#include "gdcmFilenameGenerator.h"

int main(int argc, char *argv[])
{
    std::string filename;
    if( argc <= 1 )
    {
        const char *directory = gdcm::Testing::GetDataRoot();
        if(!directory) return 1;
        std::string file = std::string(directory) + "/US-PAL-8-10x-echo.dcm";
        filename = file;
    }
    else
    {
        filename = argv[1];
    }
    std::cout << "file: " << filename << std::endl;

    vtkGDCMImageReader *reader = vtkGDCMImageReader::New();
    reader->SetFileName( filename.c_str() );
    reader->Update();
    //reader->GetOutput()->Print( std::cout );

    int dims[3];
    reader->GetOutput()->GetDimensions( dims );

    std::ostream os;
    os << "singleframe";
    os << "%04d.dcm";
    gdcm::FilenameGenerator fg;
    fg.SetPattern( os.str().c_str() );
    unsigned int nfiles = dims[2];
    fg.SetNumberOfFiles( nfiles );
    bool b = fg.Generate();
    if( !b )
    {
        std::cerr << "FilenameGenerator::Generate() failed" << std::endl;
        return 1;
    }
    if( !fg.GetNumberOfFiles() )
    {
        std::cerr << "FilenameGenerator::Generate() failed somehow..." << std::endl;
        return 1;
    }

    // By default write them as Secondary Capture (for portability)
    vtkGDCMImageWriter *writer = vtkGDCMImageWriter::New();
    vtkStringArray *filenames = vtkStringArray::New();
    for(unsigned int i = 0; i < fg.GetNumberOfFiles(); ++i)
    {
        filenames->InsertNextValue( fg.GetFilename(i) );
    }
    assert( filenames->GetNumberOfValues() == (int)fg.GetNumberOfFiles() );
    writer->SetFileNames( filenames );
    filenames->Delete();
    writer->SetFileDimensionality( 2 );
    #if (VTK_MAJOR_VERSION >= 6)
        writer->SetInputConnection( reader->GetOutputPort() );
    #endif
}

```

```

#else
    writer->SetInput( reader->GetOutput() );
#endif
    writer->SetImageFormat( reader->GetImageFormat() );
    writer->Write();

    reader->Delete();
    writer->Delete();

    return 0;
}

```

12.151 ConvertRGBToLuminance.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdc.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.
=====*/
#include "vtkGDCMImageReader.h"
#include "vtkGDCMImageWriter.h"
#include "vtkImageData.h"
#include "vtkImageLuminance.h"
#include "vtkVersion.h"

#include "gdcTesting.h"

// There is no such thing as MR Image Storage + Photometric Interpretation = RGB
// let's rewrite that into a proper single component image:
int main(int, char *[])
{
    const char *directory = gdc::Testing::GetDataRoot();
    if(!directory) return 1;
    std::string file = std::string(directory) + "/SIEMENS-MR-RGB-16Bits.dcm";
    std::cout << file << std::endl;

    vtkGDCMImageReader *reader = vtkGDCMImageReader::New();
    reader->SetFileName( file.c_str() );
    reader->Update();
    //reader->GetOutput()->Print( std::cout );

    vtkImageLuminance *luminance = vtkImageLuminance::New();
    #if (VTK_MAJOR_VERSION >= 6)
        luminance->SetInputConnection( reader->GetOutputPort() );
    #else
        luminance->SetInput( reader->GetOutput() );
    #endif

    vtkGDCMImageWriter *writer = vtkGDCMImageWriter::New();
    writer->SetFileName( "/tmp/bla.dcm" );
    #if (VTK_MAJOR_VERSION >= 6)
        writer->SetInputConnection( luminance->GetOutputPort() );
    #else
        writer->SetInput( luminance->GetOutput() );
    #endif
    //writer->SetImageFormat( reader->GetImageFormat() ); // Do NOT pass image format
    writer->SetMedicalImageProperties( reader->GetMedicalImageProperties() );
    writer->SetDirectionCosines( reader->GetDirectionCosines() );
    writer->SetShift( reader->GetShift() );
    writer->SetScale( reader->GetScale() );
    writer->Write();

    // TODO:
    //vtkImageAppendComponents.h

    reader->Delete();
    luminance->Delete();
}

```

```

writer->Delete();

return 0;
}

```

12.152 ConvertSingleBitTo8Bits.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.
=====*/

#include "vtkGDCMImageReader.h"
#include "vtkGDCMImageWriter.h"
#include "vtkImageData.h"
#include "vtkImageCast.h"
#include "vtkPointData.h"
#include "vtkBitArray.h"
#include "vtkUnsignedCharArray.h"
#include "vtkVersion.h"

int main(int argc, char *argv[])
{
    if( argc < 3 )
    {
        return 1;
    }
    const char *filename = argv[1];
    const char *outfilename = argv[2];

    vtkGDCMImageReader *reader = vtkGDCMImageReader::New();
    reader->SetFileName( filename );
    reader->Update();
    //reader->GetOutput()->Print( std::cout );

    vtkDataArray* array = reader->GetOutput()->GetPointData()->GetScalars();
    vtkBitArray *barray = vtkBitArray::SafeDownCast( array );
    if( !barray ) return false;
    vtkIdType nvalues = array->GetNumberOfTuples();
    vtkUnsignedCharArray *uarray = vtkUnsignedCharArray::New();
    uarray->SetNumberOfTuples( nvalues );
    for(vtkIdType i = 0; i < nvalues; ++i)
    {
        uarray->SetValue( i, (unsigned char)barray->GetValue(i) );
    }

    vtkImageData *copy = vtkImageData::New();
    // http://www.vtk.org/Wiki/VTK/VTK_6_Migration/Changes_to_Scalars_Manipulation_Functions#AllocateScalars.28.29
    copy->SetExtent( reader->GetOutput()->GetExtent() );
    #if (VTK_MAJOR_VERSION >= 6)
        copy->AllocateScalars(VTK_UNSIGNED_CHAR, 3);
    #else
        copy->SetScalarType( VTK_UNSIGNED_CHAR );
        copy->AllocateScalars();
    #endif

    //uarray->Print( std::cout );
    //copy->GetPointData()->GetScalars()->Print( std::cout );
    copy->GetPointData()->SetScalars( uarray );
    uarray->Delete();

    vtkGDCMImageWriter *writer = vtkGDCMImageWriter::New();
    writer->SetFileName( outfile );
    //writer->SetInput( cast->GetOutput() );
    #if (VTK_MAJOR_VERSION >= 6)
        writer->SetInputData( copy );
    #else
        writer->SetInput( copy );
    #endif
}

```



```

#endif
writer->SetImageFormat( reader->GetImageFormat() );
writer->SetMedicalImageProperties( reader->GetMedicalImageProperties() );
writer->SetDirectionCosines( reader->GetDirectionCosines() );
writer->SetShift( reader->GetShift() );
writer->SetScale( reader->GetScale() );
writer->SetFileDimensionality( reader->GetFileDimensionality() );
writer->Write();

reader->Delete();
copy->Delete();
writer->Delete();

return 0;
}

```

12.153 CreateFakePET.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
#include "vtkGDCMImageWriter.h"
#include "vtkImageReader.h"
#include "vtkImageCast.h"
#include "vtkImageData.h"
#include "vtkPointData.h"
#include "vtkDataArray.h"
#include "vtkMedicalImageProperties.h"
#include "vtkStringArray.h"
#include "vtkVersion.h"

#include "gdcmTrace.h"
#include "gdcmReader.h"
#include "gdcmWriter.h"
#include "gdcmAttribute.h"
#include "gdcmFilenameGenerator.h"

/*
 * Minimal example to create a fake RTDOSE file. The data contains a sphere
 * just for testing.
 * The vtkMedicalImageProperties is not properly filled, but only contains a
 * single field which is required to set the proper SOP Class
 */
int main(int, char *[])
{
    gdcm::Trace::DebugOn();

    const vtkIdType xSize = 512;
    const vtkIdType ySize = 512;
    const vtkIdType zSize = 512;

    // Create the filenames in advance to supply to the vtkGDCMImageWriter
    std::ostream os;
    os << "PT";
    os << "%03d.dcm";
    gdcm::FilenameGenerator fg;
    fg.SetPattern( os.str().c_str() );
    unsigned int nfiles = zSize;
    fg.SetNumberOfFilenames( nfiles );
    bool b = fg.Generate();
    if( !b )
    {
        std::cerr << "FilenameGenerator::Generate() failed" << std::endl;
        return 1;
    }
    if( !fg.GetNumberOfFilenames() )

```

```

    {
        std::cerr << "FilenameGenerator::Generate() failed somehow..." << std::endl;
        return 1;
    }

    vtkStringArray *filenames = vtkStringArray::New();
    for(unsigned int i = 0; i < fg.GetNumberOfFileNames(); ++i)
    {
        filenames->InsertNextValue( fg.GetFilename(i) );
    }

    vtkImageData *image = vtkImageData::New();
    image->SetDimensions(xSize,ySize,zSize);
    image->SetOrigin(-350.684,350.0,890.76);
    image->SetSpacing(5.4688,-5.4688,-3.27);
    #if VTK_MAJOR_VERSION <= 5
        image->SetNumberOfScalarComponents(1);
        image->SetScalarTypeToDouble();
    #else
        image->AllocateScalars(VTK_DOUBLE,1);
    #endif

    double pt[3];
    for( int z = 0; z < zSize; ++z )
        for( int y = 0; y < ySize; ++y )
            for( int x = 0; x < xSize; ++x )
            {
                pt[0] = x;
                pt[1] = y;
                pt[2] = z;
                pt[0] -= xSize / 2;
                pt[1] -= ySize / 2;
                pt[2] -= zSize / 2;
                pt[0] /= xSize / 2;
                pt[1] /= ySize / 2;
                pt[2] /= zSize / 2;
                const double unit = pt[0] * pt[0] + pt[1] * pt[1] + pt[2] * pt[2];
                const double inval = unit <= 1. ? (3 * unit + 7) : 0.; // just for fun => max == 10.
                double* pixel= static_cast<double*>(image->GetScalarPointer(x,y,z));
                pixel[0] = inval;
            }

    vtkGDCMImageWriter *writer = vtkGDCMImageWriter::New();
    writer->SetFileDimensionality( 2 );
    writer->SetFileNames(filenames);
    #if (VTK_MAJOR_VERSION >= 6)
        writer->SetInputData( image );
    #else
        writer->SetInput( image );
    #endif
    writer->GetMedicalImageProperties()->SetSliceThickness("1.5");
    writer->GetMedicalImageProperties()->SetModality( "PT" );
    writer->SetScale( 0.0042 ); // why not
    writer->Write();

    image->Delete();
    writer->Delete();

    return 0;
}

```

12.154 CreateFakeRTDOSE.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.
=====

```

```

===== */
#include "vtkGDCMImageWriter.h"
#include "vtkImageReader.h"
#include "vtkImageCast.h"
#include "vtkImageData.h"
#include "vtkPointData.h"
#include "vtkDataArray.h"
#include "vtkMedicalImageProperties.h"
#include "vtkVersion.h"

#include "gdcmTrace.h"
#include "gdcmReader.h"
#include "gdcmWriter.h"
#include "gdcmAttribute.h"

/*
 * Minimal example to create a fake RTDOSE file. The data contains a sphere
 * just for testing.
 * The vtkMedicalImageProperties is not properly filled, but only contains a
 * single field which is required to set the proper SOP Class
 */
int main(int, char *[])
{
    //gdcm::Trace::DebugOn();

    const vtkIdType xSize = 512;
    const vtkIdType ySize = 512;
    const vtkIdType zSize = 512;

    vtkImageData *image = vtkImageData::New();
    image->SetDimensions(xSize,ySize,zSize);
    image->SetOrigin(-350.684,350.0,890.76);
    image->SetSpacing(5.4688,-5.4688,-3.27);
    #if VTK_MAJOR_VERSION <= 5
        image->SetNumberOfScalarComponents(1);
        image->SetScalarTypeToDouble();
    #else
        image->AllocateScalars(VTK_DOUBLE,1);
    #endif

    double pt[3];
    for( int z = 0; z < zSize; ++z )
        for( int y = 0; y < ySize; ++y )
            for( int x = 0; x < xSize; ++x )
            {
                pt[0] = x;
                pt[1] = y;
                pt[2] = z;
                pt[0] -= xSize / 2;
                pt[1] -= ySize / 2;
                pt[2] -= zSize / 2;
                pt[0] /= xSize / 2;
                pt[1] /= ySize / 2;
                pt[2] /= zSize / 2;
                const double unit = pt[0] * pt[0] + pt[1] * pt[1] + pt[2] * pt[2];
                const double inval = unit <= 1. ? (3 * unit + 7) : 0.; // just for fun => max == 10.
                double* pixel= static_cast<double*>(image->GetScalarPointer(x,y,z));
                pixel[0] = inval;
            }

    vtkGDCMImageWriter *writer = vtkGDCMImageWriter::New();
    writer->SetFileDimensionality( 3 );
    writer->SetFileName( "rtdose.dcm" );
    #if (VTK_MAJOR_VERSION >= 6)
        writer->SetInputData( image );
    #else
        writer->SetInput( image );
    #endif
    writer->GetMedicalImageProperties()->SetSliceThickness("1.5");
    writer->GetMedicalImageProperties()->AddUserDefinedValue( "Dose Units", "GY");
    writer->GetMedicalImageProperties()->AddUserDefinedValue( "Dose Summation Type", "PLAN");
    writer->GetMedicalImageProperties()->AddUserDefinedValue( "Dose Type", "PHYSICAL");
    writer->GetMedicalImageProperties()->AddUserDefinedValue( "Frame of Reference UID",
        "1.3.12.2.1107.5.6.1.68100.30270111041215391275000000001");
    writer->GetMedicalImageProperties()->SetModality( "RTDOSE" );
    //writer->GetMedicalImageProperties()->SetModality( "PT" ); // debug
    writer->SetScale( 0.0042 ); // why not
    writer->Write();

    image->Delete();
}

```

```

writer->Delete();

// BEGIN HACK
// In GDCM version 2.4.3 and before, the following tag was missing which caused issue with some RTDose
// software:

// Open the DICOM file that was temporarily created. This will allows me to used
// GDCM to append specific tags that allows the RTDOSE to be associated with the
// relevant CT images.
gdcmm::Reader reader2;
reader2.SetFileName("rtdose.dcm" );
reader2.Read();
gdcmm::File &file = reader2.GetFile();
gdcmm::DataSet &ds = file.GetDataSet();

// Required by some software and not automagically added by GDCM in old version
gdcmm::Attribute<0x0028,0x0009> framePointer;
framePointer.SetNumberOfValues(1);
framePointer.SetValue( gdcmm::Tag(0x3004,0x000C) );
ds.Replace( framePointer.GetAsDataElement() );

gdcmm::Writer writer2;
writer2.CheckFileMetaInformationOff();
writer2.SetFileName("rtdose2.dcm");
writer2.SetFile( file );
writer2.Write();
// END HACK

return 0;
}

```

12.155 GenerateRTSTRUCT.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcmm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
#include "vtkGDCMPolyDataWriter.h"
#include "vtkGDCMPolyDataReader.h"
#include "vtkPolyData.h"
#include "vtkPolyDataReader.h"
#include "vtkMedicalImageProperties.h"
#include "vtkRTStructSetProperties.h"
#include "vtkStringArray.h"
#include "vtkAppendPolyData.h"
#include "vtkPolyDataWriter.h"
#include "vtkPolyDataMapper.h"
#include "vtkPolyDataMapper2D.h"
#include "vtkActor2D.h"
#include "vtkRenderWindowInteractor.h"
#include "vtkMedicalImageProperties.h"
#include "vtkRenderWindow.h"
#include "vtkRenderer.h"
#include "vtkCamera.h"
#include "vtkProperty.h"
#include "vtkProperty2D.h"
#include "vtkImageData.h"
#include "vtkVersion.h"

#include <algorithm> //for std::find

#include "gdcmmDirectoryHelper.h"

using namespace gdcmm;

//view each organ independently of the others, to make sure that

```

```

//organ names correspond to actual segmentations.
void ShowOrgan(vtkPolyData* inData)
{
    // Now we'll look at it.
    vtkPolyDataMapper *cubeMapper = vtkPolyDataMapper::New();
    #if (VTK_MAJOR_VERSION >= 6)
        cubeMapper->SetInputData( inData );
    #else
        cubeMapper->SetInput( inData );
    #endif
    cubeMapper->SetScalarRange(0,7);
    vtkActor *cubeActor = vtkActor::New();
    cubeActor->SetMapper(cubeMapper);
    vtkProperty *property = cubeActor->GetProperty();
    property->SetRepresentationToWireframe();

    vtkRenderer *renderer = vtkRenderer::New();
    vtkRenderWindow *renWin = vtkRenderWindow::New();
    renWin->AddRenderer(renderer);

    vtkRenderWindowInteractor *iren = vtkRenderWindowInteractor::New();
    iren->SetRenderWindow(renWin);

    renderer->AddActor(cubeActor);
    renderer->ResetCamera();
    renderer->SetBackground(1,1,1);

    renWin->SetSize(300,300);

    renWin->Render();
    iren->Start();

    cubeMapper->Delete();
    cubeActor->Delete();
    renderer->Delete();
    renWin->Delete();
    iren->Delete();
}

/*
 * Full application which ... RTSTRUCT
 */
int main(int argc, char *argv[])
{
    if( argc < 2 )
    {
        std::cerr << argv[0] << " directory-with-rtstruct-and-ct-images\n";
        return 1;
    }
    std::string theDirName(argv[1]);
    Directory::FileNamesType theRTSeries =
        DirectoryHelper::GetRTStructSeriesUIDs(theDirName);

    gdcm::Directory theDir;
    theDir.Load(argv[1]);

    if (theRTSeries.empty())
    {
        std::cerr << "No RTStructs found for the test, ending." << std::endl;
        return 1;
    }

    for (size_t q = 0; q < theRTSeries.size(); q++)
    {
        Directory::FileNamesType theRTNames =
            DirectoryHelper::GetFileNamesFromSeriesUIDs(theDirName, theRTSeries[q]);

        if (theRTNames.empty()){
            std::cerr << "Unable to load RT Series " << theRTSeries[q] << ", continuing. " << std::endl;
            continue;
        }

        vtkGDCMPolyDataReader * reader = vtkGDCMPolyDataReader::New();
        reader->SetFileName( theRTNames[0].c_str() );
        reader->Update();

        //std::cout << reader->GetMedicalImageProperties()->GetStudyDate() << std::endl;

        vtkGDCMPolyDataWriter * writer = vtkGDCMPolyDataWriter::New();
        int numMasks = reader->GetNumberOfOutputPorts() + 1; //add a blank one in
        writer->SetNumberOfInputPorts( numMasks );
    }
}

```

```

std::string thePotentialName = theDirName + "/" + "GDCMTestRTStruct." + theRTSeries[q] + ".dcm";
gdcm::Directory::FileNamesType theFileNames = theDir.GetFilesNames();
//keep renaming the output until we get something that doesn't overwrite what was there already
int count = 0;
while (std::find(theFileNames.begin(), theFileNames.end(), thePotentialName) != theFileNames.end())
{
    char buff[255];
    snprintf(buff, sizeof(buff), "%d", count);
    thePotentialName = theDirName + "/" + "GDCMTestRTStruct." + buff + "." + theRTSeries[q] + ".dcm";
}
writer->SetFileName( thePotentialName.c_str());
writer->SetMedicalImageProperties( reader->GetMedicalImageProperties() );
//this line is cheating, we won't have the same stuff, and may not have a struct
//to start with.
//have to go back to the original data to reconstruct the RTStructureSetProperties
//writer->SetRTStructSetProperties( reader->GetRTStructSetProperties() );
//writer->Write();

//loop through the outputs in order to write them out as if they had been created and appended
vtkStringArray* roiNames = vtkStringArray::New();
vtkStringArray* roiAlgorithms = vtkStringArray::New();
vtkStringArray* roiTypes = vtkStringArray::New();
roiNames->SetNumberOfValues(numMasks);
roiAlgorithms->SetNumberOfValues(numMasks);
roiTypes->SetNumberOfValues(numMasks);
vtkAppendPolyData* append = vtkAppendPolyData::New();

//ok, now we'll add a blank organ
//the blank organ is to test to ensure that blank organs work; there have been crash reports
//this code is added at the beginning to ensure that the blank organs are read
//and preserved as individual organs.
vtkPolyData* blank = vtkPolyData::New();
#if (VTK_MAJOR_VERSION >= 6)
writer->SetInputData(0, blank);
#else
writer->SetInput(0, blank);
#endif
roiNames->InsertValue(0, "blank");
roiAlgorithms->InsertValue(0, "blank");
roiTypes->InsertValue(0, "ORGAN");

//note the offsets used to place the blank rtstruct at the beginning of the newly generated RT.
//the idea is to run the program twice; first to generate an rtstruct with a blank mask (making
//sure that that functionality works), and then a second time to make sure that everything is
//being read properly. Multiple organs with the same name could cause some strangenesses.
for (int i = 1; i < numMasks; ++i)
{
    if (VTK_MAJOR_VERSION >= 6)
        writer->SetInputConnection(i, reader->GetOutputPort(i-1));
    else
        writer->SetInput(i, reader->GetOutput(i-1));
    append->AddInputConnection(reader->GetOutputPort(i-1));
    else
        writer->SetInput(i, reader->GetOutput(i-1));
    append->AddInput(reader->GetOutput(i-1));
    endif
    std::string theString = reader->GetRTStructSetProperties()->GetStructureSetROIName(i-1);
    roiNames->InsertValue(i, theString);
    theString = reader->GetRTStructSetProperties()->GetStructureSetROIGenerationAlgorithm(i-1);
    roiAlgorithms->InsertValue(i, theString);
    theString = reader->GetRTStructSetProperties()->GetStructureSetRTROIInterpretedType(i-1);
    roiTypes->InsertValue(i, theString);

    ShowOrgan(reader->GetOutput(i-1));
}

vtkRTStructSetProperties* theProperties = vtkRTStructSetProperties::New();
writer->SetRTStructSetProperties(theProperties);
writer->InitializeRTStructSet(theDirName,
    reader->GetRTStructSetProperties()->GetStructureSetLabel(),
    reader->GetRTStructSetProperties()->GetStructureSetName(),
    roiNames, roiAlgorithms, roiTypes);

writer->SetRTStructSetProperties(theProperties);
writer->Write();

// print reader output:
reader->Print( std::cout );
// print first output:
reader->GetOutput()->Print( std::cout );

reader->Delete();
append->Delete();

```

```

        roiNames->Delete();
        roiTypes->Delete();
        theProperties->Delete();
        roiAlgorithms->Delete();
        blank->Delete();

        writer->Delete();
    }
    return 0;
}

```

12.156 MagnifyFile.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
#include "vtkGDCMImageReader.h"
#include "vtkGDCMImageWriter.h"
#include "vtkImageData.h"
#include "vtkImageMagnify.h"
#include "vtkImageCast.h"
#include "vtkVersion.h"

#include "gdcmTesting.h"
#include "gdcmSystem.h"

// This is a simple test to magnify an image that is known to give excellent
// compression ratio. This will be our test for those large image
int main(int, char *[])
{
    const char *directory = gdcm::Testing::GetDataRoot();
    if(!directory) return 1;
    std::string file = std::string(directory) + "/test.acr";
    std::cout << file << std::endl;
    if( !gdcm::System::FileExists( file.c_str() ) ) return 1;

    vtkGDCMImageReader *reader = vtkGDCMImageReader::New();
    reader->SetFileName( file.c_str() );
    reader->Update();
    //reader->GetOutput()->Print( std::cout );

    vtkImageCast *cast = vtkImageCast::New();
    if (VTK_MAJOR_VERSION >= 6)
        cast->SetInputConnection( reader->GetOutputPort() );
    #else
        cast->SetInput( reader->GetOutput() );
    #endif
    cast->SetOutputScalarTypeToUnsignedShort();

    vtkImageMagnify *magnify = vtkImageMagnify::New();
    if (VTK_MAJOR_VERSION >= 6)
        magnify->SetInputConnection( cast->GetOutputPort() );
    #else
        magnify->SetInput( cast->GetOutput() );
    #endif
    magnify->SetInterpolate( 1 );
    magnify->SetInterpolate( 0 );
    int factor = 100;
    magnify->SetMagnificationFactors (factor, factor, 1);

    vtkGDCMImageWriter *writer = vtkGDCMImageWriter::New();
    writer->SetFileName( "/tmp/bla.dcm" );
    if (VTK_MAJOR_VERSION >= 6)
        writer->SetInputConnection( magnify->GetOutputPort() );
    #else
        writer->SetInput( magnify->GetOutput() );

```

```

#endif
writer->SetImageFormat( reader->GetImageFormat() );
writer->SetMedicalImageProperties( reader->GetMedicalImageProperties() );
writer->SetDirectionCosines( reader->GetDirectionCosines() );
writer->SetShift( reader->GetShift() );
writer->SetScale( reader->GetScale() );
writer->Write();

// TODO:
//vtkImageAppendComponents.h

reader->Delete();
magnify->Delete();
writer->Delete();

return 0;
}

```

12.157 gdcmmorthoplanes.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcmm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/

#include "vtkActor.h"
#include "vtkCamera.h"
#include "vtkMatrix4x4.h"
#include "vtkTransform.h"
#include "vtkAssembly.h"
#include "vtkCellPicker.h"
#include "vtkCommand.h"
#include "vtkImageActor.h"
#include "vtkImageMapToColors.h"
#include "vtkImageOrthoPlanes.h"
#include "vtkImagePlaneWidget.h"
#include "vtkImageReader.h"
#include "vtkInteractorEventRecorder.h"
#include "vtkLookupTable.h"
#include "vtkOutlineFilter.h"
#include "vtkPolyDataMapper.h"
#include "vtkProperty.h"
#include "vtkRenderWindow.h"
#include "vtkRenderWindowInteractor.h"
#include "vtkRenderer.h"
#include "vtkVolume16Reader.h"
#include "vtkImageData.h"
#include "vtkImageChangeInformation.h"
#include "vtkOrientationMarkerWidget.h"
#include "vtkAnnotatedCubeActor.h"
#include "vtkAxesActor.h"
#include "vtkCaptionActor2D.h"
#include "vtkTextProperty.h"
#include "vtkPropAssembly.h"

#include "vtkGDCMImageReader.h"
#include "vtkGDCMImageWriter.h"
#include "vtkStringArray.h"
#include "vtkVersion.h"

#include "gdcmmSystem.h"
#include "gdcmmDirectory.h"
#include "gdcmmIPPSorter.h"

#ifdef vtkFloatingPointType
#define vtkFloatingPointType double

```



```

#endif

//-----
class vtkOrthoPlanesCallback : public vtkCommand
{
public:
    static vtkOrthoPlanesCallback *New()
    { return new vtkOrthoPlanesCallback; }

    void Execute( vtkObject *caller, unsigned long vtkNotUsed( event ),
                  void *callData )
    {
        vtkImagePlaneWidget* self =
            reinterpret_cast< vtkImagePlaneWidget* >( caller );
        if(!self) return;

        double* wl = static_cast<double*>( callData );

        if ( self == this->WidgetX )
        {
            this->WidgetY->SetWindowLevel(wl[0],wl[1],1);
            this->WidgetZ->SetWindowLevel(wl[0],wl[1],1);
        }
        else if( self == this->WidgetY )
        {
            this->WidgetX->SetWindowLevel(wl[0],wl[1],1);
            this->WidgetZ->SetWindowLevel(wl[0],wl[1],1);
        }
        else if (self == this->WidgetZ)
        {
            this->WidgetX->SetWindowLevel(wl[0],wl[1],1);
            this->WidgetY->SetWindowLevel(wl[0],wl[1],1);
        }
    }

    vtkOrthoPlanesCallback():WidgetX( 0 ), WidgetY( 0 ), WidgetZ ( 0 ) {}

    vtkImagePlaneWidget* WidgetX;
    vtkImagePlaneWidget* WidgetY;
    vtkImagePlaneWidget* WidgetZ;
};

int main( int argc, char *argv[] )
{
    //char* fname = vtkTestUtilities::ExpandDataFileName(argc, argv, "Data/headsq/quarter");

    //vtkVolume16Reader* v16 = vtkVolume16Reader::New();
    // v16->SetDataDimensions( 64, 64);
    // v16->SetDataByteOrderToLittleEndian();
    // v16->SetImageRange( 1, 93);
    // v16->SetDataSpacing( 3.2, 3.2, 1.5);
    // v16->SetFilePrefix( fname );
    // v16->SetDataMask( 0x7fff);
    // v16->Update();
    std::vector<std::string> filenames;
    if( argc < 2 )
    {
        std::cerr << argv[0] << " filename1.dcm [filename2.dcm ...]\n";
        return 1;
    }
    else
    {
        // Is it a single directory ? If so loop over all files contained in it:
        const char *filename = argv[1];
        if( argc == 2 && gdcm::System::FileIsDirectory( filename ) )
        {
            std::cout << "Loading directory: " << filename << std::endl;
            bool recursive = false;
            gdcm::Directory d;
            d.Load(filename, recursive);
            gdcm::Directory::FileNamesType const &files = d.GetFiles();
            for( gdcm::Directory::FileNamesType::const_iterator it = files.begin(); it != files.end(); ++it )
            {
                filenames.push_back( it->c_str() );
            }
        }
        else // list of files passed directly on the cmd line:
            // discard non-existing or directory
        {
            for(int i=1; i < argc; ++i)
            {

```

```

        filename = argv[i];
        if( gdcm::System::FileExists( filename ) )
        {
            if( gdcm::System::FileIsDirectory( filename ) )
            {
                std::cerr << "Discarding directory: " << filename << std::endl;
            }
            else
            {
                filenames.push_back( filename );
            }
        }
        else
        {
            std::cerr << "Discarding non existing file: " << filename << std::endl;
        }
    }
    //names->Print( std::cout );
}

vtkGDCMImageReader * reader = vtkGDCMImageReader::New();
double ippzspacing;
if( filenames.size() > 1 )
{
    //gdcm::Trace::DebugOn();
    //gdcm::Trace::WarningOn();
    gdcm::IPPSorter s;
    s.SetComputeZSpacing( true );
    s.SetZSpacingTolerance( 1e-3 );
    bool b = s.Sort( filenames );
    if( !b )
    {
        std::cerr << "Failed to sort files" << std::endl;
        return 1;
    }
    std::cout << "Sorting succeeded:" << std::endl;
    s.Print( std::cout );

    std::cout << "Found z-spacing:" << std::endl;
    std::cout << s.GetZSpacing() << std::endl;
    ippzspacing = s.GetZSpacing();

    const std::vector<std::string> & sorted = s.GetFilesNames();
    vtkStringArray *files = vtkStringArray::New();
    std::vector< std::string >::const_iterator it = sorted.begin();
    for( ; it != sorted.end(); ++it )
    {
        const std::string &f = *it;
        files->InsertNextValue( f.c_str() );
    }
    reader->SetFileNames( files );
    //reader->SetFileLowerLeft( 1 );
    reader->Update(); // important
    files->Delete();
}
else
{
    reader->SetFileName( argv[1] );
    reader->Update(); // important
    ippzspacing = reader->GetOutput()->GetSpacing()[2];
    ippzspacing = 4;
}

//reader->GetOutput()->Print( std::cout );
//vtkFloatingPointType range[2];
//reader->GetOutput()->GetScalarRange(range);
//std::cout << "Range: " << range[0] << " " << range[1] << std::endl;

const vtkFloatingPointType *spacing = reader->GetOutput()->GetSpacing();

    vtkImageChangeInformation *v16 = vtkImageChangeInformation::New();
    #if (VTK_MAJOR_VERSION >= 6)
    v16->SetInputConnection( reader->GetOutputPort() );
    #else
    v16->SetInput( reader->GetOutput() );
    #endif
    v16->SetOutputSpacing( spacing[0], spacing[1], ippzspacing );
    v16->Update();

    #if 0

```

```

    vtkGDCMImageWriter *writer = vtkGDCMImageWriter::New();
    writer->SetInput( v16->GetOutput() );
    writer->SetFileLowerLeft( reader->GetFileLowerLeft() );
    writer->SetDirectionCosines( reader->GetDirectionCosines() );
    writer->SetImageFormat( reader->GetImageFormat() );
    writer->SetFileDimensionality( 3 ); //reader->GetFileDimensionality();
    writer->SetMedicalImageProperties( reader->GetMedicalImageProperties() );
    writer->SetShift( reader->GetShift() );
    writer->SetScale( reader->GetScale() );
    writer->SetFileName( "out.dcm" );
    writer->Write();
#endif

    vtkOutlineFilter* outline = vtkOutlineFilter::New();
    outline->SetInputConnection(v16->GetOutputPort());

    vtkPolyDataMapper* outlineMapper = vtkPolyDataMapper::New();
    outlineMapper->SetInputConnection(outline->GetOutputPort());

    vtkActor* outlineActor = vtkActor::New();
    outlineActor->SetMapper( outlineMapper);

    vtkRenderer* ren1 = vtkRenderer::New();
    vtkRenderer* ren2 = vtkRenderer::New();

    vtkRenderWindow* renWin = vtkRenderWindow::New();
    renWin->AddRenderer(ren2);
    renWin->AddRenderer(ren1);

    vtkRenderWindowInteractor* iren = vtkRenderWindowInteractor::New();
    iren->SetRenderWindow(renWin);

    vtkCellPicker* picker = vtkCellPicker::New();
    picker->SetTolerance(0.005);

    vtkProperty* ipwProp = vtkProperty::New();
    //assign default props to the ipw's texture plane actor

    vtkImagePlaneWidget* planeWidgetX = vtkImagePlaneWidget::New();
    planeWidgetX->SetInteractor( iren);
    planeWidgetX->SetKeyPressActivationValue('x');
    planeWidgetX->SetPicker(picker);
    planeWidgetX->RestrictPlaneToVolumeOn();
    planeWidgetX->GetPlaneProperty()->SetColor(1,0,0);
    planeWidgetX->SetTexturePlaneProperty(ipwProp);
    planeWidgetX->TextureInterpolateOff();
    planeWidgetX->SetResliceInterpolateToNearestNeighbour();
    if (VTK_MAJOR_VERSION >= 6)
        planeWidgetX->SetInputConnection(v16->GetOutputPort());
    else
        planeWidgetX->SetInput(v16->GetOutput());
    endif
    planeWidgetX->SetPlaneOrientationToXAxes();
    //planeWidgetX->SetSliceIndex(32);
    planeWidgetX->DisplayTextOn();
    planeWidgetX->On();
    planeWidgetX->InteractionOff();
    planeWidgetX->InteractionOn();

    vtkImagePlaneWidget* planeWidgetY = vtkImagePlaneWidget::New();
    planeWidgetY->SetInteractor( iren);
    planeWidgetY->SetKeyPressActivationValue('y');
    planeWidgetY->SetPicker(picker);
    planeWidgetY->GetPlaneProperty()->SetColor(1,1,0);
    planeWidgetY->SetTexturePlaneProperty(ipwProp);
    planeWidgetY->TextureInterpolateOn();
    planeWidgetY->SetResliceInterpolateToLinear();
    if (VTK_MAJOR_VERSION >= 6)
        planeWidgetY->SetInputConnection(v16->GetOutputPort());
    else
        planeWidgetY->SetInput(v16->GetOutput());
    endif
    planeWidgetY->SetPlaneOrientationToYAxes();
    //planeWidgetY->SetSlicePosition(102.4);
    planeWidgetY->SetLookupTable( planeWidgetX->GetLookupTable());
    planeWidgetY->DisplayTextOn();
    planeWidgetY->UpdatePlacement();
    planeWidgetY->On();

    vtkImagePlaneWidget* planeWidgetZ = vtkImagePlaneWidget::New();

```

```

    planeWidgetZ->SetInteractor( iren);
    planeWidgetZ->SetKeyPressActivationValue('z');
    planeWidgetZ->SetPicker(picker);
    planeWidgetZ->GetPlaneProperty()->SetColor(0,0,1);
    planeWidgetZ->SetTexturePlaneProperty(ipwProp);
    planeWidgetZ->TextureInterpolateOn();
    planeWidgetZ->SetResliceInterpolateToCubic();
    #if (VTK_MAJOR_VERSION >= 6)
        planeWidgetZ->SetInputConnection(vl6->GetOutputPort());
    #else
        planeWidgetZ->SetInput(vl6->GetOutput());
    #endif
    planeWidgetZ->SetPlaneOrientationToZAxes();
    //planeWidgetZ->SetSliceIndex(25);
    planeWidgetZ->SetLookupTable( planeWidgetX->GetLookupTable());
    planeWidgetZ->DisplayTextOn();
    planeWidgetZ->On();

    vtkImageOrthoPlanes *orthoPlanes = vtkImageOrthoPlanes::New();
    orthoPlanes->SetPlane(0, planeWidgetX);
    orthoPlanes->SetPlane(1, planeWidgetY);
    orthoPlanes->SetPlane(2, planeWidgetZ);
    orthoPlanes->ResetPlanes();

    vtkOrthoPlanesCallback* cbk = vtkOrthoPlanesCallback::New();
    cbk->WidgetX = planeWidgetX;
    cbk->WidgetY = planeWidgetY;
    cbk->WidgetZ = planeWidgetZ;
    planeWidgetX->AddObserver( vtkCommand::EndWindowLevelEvent, cbk );
    planeWidgetY->AddObserver( vtkCommand::EndWindowLevelEvent, cbk );
    planeWidgetZ->AddObserver( vtkCommand::EndWindowLevelEvent, cbk );
    cbk->Delete();

    double wl[2];
    planeWidgetZ->GetWindowLevel(wl);

    // Add a 2D image to test the GetReslice method
    //
    vtkImageMapToColors* colorMap = vtkImageMapToColors::New();
    colorMap->PassAlphaToOutputOff();
    colorMap->SetActiveComponent(0);
    colorMap->SetOutputFormatToLuminance();
    #if (VTK_MAJOR_VERSION >= 6)
        colorMap->SetInputData(planeWidgetZ->GetResliceOutput());
    #else
        colorMap->SetInput(planeWidgetZ->GetResliceOutput());
    #endif
    colorMap->SetLookupTable(planeWidgetX->GetLookupTable());

    vtkImageActor* imageActor = vtkImageActor::New();
    imageActor->PickableOff();
    #if (VTK_MAJOR_VERSION >= 6)
        imageActor->SetInputData(colorMap->GetOutput());
    #else
        imageActor->SetInput(colorMap->GetOutput());
    #endif

    // Add the actors
    //
    ren1->AddActor( outlineActor);
    ren2->AddActor( imageActor);

    ren1->SetBackground( 0.1, 0.1, 0.2);
    ren2->SetBackground( 0.2, 0.1, 0.2);

    renWin->SetSize( 600, 350);

    ren1->SetViewport(0,0,0.58333,1);
    ren2->SetViewport(0.58333,0,1,1);

    // Set the actors' positions
    //
    renWin->Render();
    //iren->SetEventPosition( 175,175);
    //iren->SetKeyCode('r');
    //iren->InvokeEvent(vtkCommand::CharEvent,NULL);
    //iren->SetEventPosition( 475,175);
    //iren->SetKeyCode('r');
    //iren->InvokeEvent(vtkCommand::CharEvent,NULL);

```

```

//renWin->Render();

//ren1->GetActiveCamera()->Elevation(110);
//ren1->GetActiveCamera()->SetViewUp(0, 0, -1);
//ren1->GetActiveCamera()->Azimuth(45);
//ren1->GetActiveCamera()->Dolly(1.15);
ren1->ResetCameraClippingRange();

vtkAnnotatedCubeActor* cube = vtkAnnotatedCubeActor::New();
cube->SetXPlusFaceText ( "R" );
cube->SetXMinusFaceText ( "L" );
cube->SetYPlusFaceText ( "A" );
cube->SetYMinusFaceText ( "P" );
cube->SetZPlusFaceText ( "H" );
cube->SetZMinusFaceText ( "F" );
cube->SetFaceTextScale( 0.666667 );

vtkAxesActor* axes2 = vtkAxesActor::New();

vtkMatrix4x4 *invert = vtkMatrix4x4::New();
invert->DeepCopy( reader->GetDirectionCosines() );
invert->Invert();

// simulate a left-handed coordinate system
//
vtkTransform *transform = vtkTransform::New();
transform->Identity();
//transform->RotateY(90);
transform->Concatenate(invert);
axes2->SetShaftTypeToCylinder();
axes2->SetUserTransform( transform );
cube->GetAssembly()->SetUserTransform( transform );

axes2->SetTotalLength( 1.5, 1.5, 1.5 );
axes2->SetCylinderRadius( 0.500 * axes2->GetCylinderRadius() );
axes2->SetConeRadius ( 1.025 * axes2->GetConeRadius() );
axes2->SetSphereRadius ( 1.500 * axes2->GetSphereRadius() );

vtkTextProperty* tprop = axes2->GetXAxisCaptionActor2D()->
    GetCaptionTextProperty();
tprop->ItalicOn();
tprop->ShadowOn();
tprop->SetFontFamilyToTimes();

axes2->GetYAxisCaptionActor2D()->GetCaptionTextProperty()->ShallowCopy( tprop );
axes2->GetZAxisCaptionActor2D()->GetCaptionTextProperty()->ShallowCopy( tprop );

vtkPropAssembly* assembly = vtkPropAssembly::New();
assembly->AddPart( axes2 );
assembly->AddPart( cube );

vtkOrientationMarkerWidget* widget = vtkOrientationMarkerWidget::New();
widget->SetOutlineColor( 0.9300, 0.5700, 0.1300 );
widget->SetOrientationMarker( assembly );
widget->SetInteractor( iren );
widget->SetViewport( 0.0, 0.0, 0.4, 0.4 );
widget->SetEnabled( 1 );
widget->InteractiveOff();
widget->InteractiveOn();

// Playback recorded events
//
//vtkInteractorEventRecorder *recorder = vtkInteractorEventRecorder::New();
//recorder->SetInteractor(iren);
//recorder->ReadFromInputStringOn();
//recorder->SetInputString( IOEventLog );

// Interact with data
// Render the image
//
iren->Initialize();
renWin->Render();

// Test SetKeyPressActivationValue for one of the widgets
//
//iren->SetKeyCode('z');
//iren->InvokeEvent(vtkCommand::CharEvent,NULL);
//iren->SetKeyCode('z');
//iren->InvokeEvent(vtkCommand::CharEvent,NULL);

//int retVal = vtkRegressionTestImage( renWin );

```

```

//
//if ( retVal == vtkRegressionTester::DO_INTERACTOR)
//{
//    iren->Start();
//}

// Clean up
//
//recorder->Off();
//recorder->Delete();

ipwProp->Delete();
orthoPlanes->Delete();
planeWidgetX->Delete();
planeWidgetY->Delete();
planeWidgetZ->Delete();
colorMap->Delete();
imageActor->Delete();
picker->Delete();
outlineActor->Delete();
outlineMapper->Delete();
outline->Delete();
iren->Delete();
renWin->Delete();
ren1->Delete();
ren2->Delete();
v16->Delete();
reader->Delete();

return 0;
}

```

12.158 gdcmreslice.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
#include "vtkGDCMImageReader.h"

#include "vtkRenderer.h"
#include "vtkAssembly.h"
#include "vtkImageFlip.h"
#include "vtkImageReslice.h"
#include "vtkRenderWindow.h"
#include "vtkAnnotatedCubeActor.h"
#include "vtkTransform.h"
#include "vtkAxesActor.h"
#include "vtkTextProperty.h"
#include "vtkCaptionActor2D.h"
#include "vtkPropAssembly.h"
#include "vtkOrientationMarkerWidget.h"
#include "vtkRenderWindowInteractor.h"
#include "vtkPolyDataMapper.h"
#include "vtkActor.h"
#include "vtkImageData.h"
#include "vtkLookupTable.h"
#include "vtkTexture.h"
#include "vtkPlaneSource.h"
#include "vtkVersion.h"

int main( int argc, char *argv[] )
{
    if( argc < 2 ) return 1;
    vtkGDCMImageReader *reader = vtkGDCMImageReader::New();
    reader->SetFileName( argv[1] );
    //reader->FileLowerLeftOn();
}

```

```

reader->Update();

vtkImageFlip *flip = vtkImageFlip::New();
#if (VTK_MAJOR_VERSION >= 6)
    flip->SetInputConnection(reader->GetOutputPort());
#else
    flip->SetInput(reader->GetOutput());
#endif
flip->SetFilteredAxis(0);
flip->Update();

vtkImageReslice *reslice = vtkImageReslice::New();
//reslice->SetInput(reader->GetOutput());
#if (VTK_MAJOR_VERSION >= 6)
    reslice->SetInputConnection(flip->GetOutputPort());
#else
    reslice->SetInput(flip->GetOutput());
#endif
//reslice->SetResliceAxesDirectionCosines()
reader->GetDirectionCosines()->Print(std::cout);
vtkMatrix4x4 *invert = vtkMatrix4x4::New();
invert->DeepCopy( reader->GetDirectionCosines() );
invert->Invert();

//reslice->SetResliceAxes( reader->GetDirectionCosines() );
reslice->SetResliceAxes( invert );
reslice->Update();
vtkImageData* ima = reslice->GetOutput();

vtkLookupTable* table = vtkLookupTable::New();
table->SetNumberOfColors(1000);
table->SetTableRange(0,1000);
table->SetSaturationRange(0,0);
table->SetHueRange(0,1);
table->SetValueRange(0,1);
table->SetAlphaRange(1,1);
table->Build();

// Texture
vtkTexture* texture = vtkTexture::New();
#if (VTK_MAJOR_VERSION >= 6)
    texture->SetInputData(ima);
#else
    texture->SetInput(ima);
#endif
texture->InterpolateOn();
texture->SetLookupTable(table);

// PlaneSource
vtkPlaneSource* plane = vtkPlaneSource::New();

// PolyDataMapper
vtkPolyDataMapper *planeMapper = vtkPolyDataMapper::New();
#if (VTK_MAJOR_VERSION >= 6)
    planeMapper->SetInputConnection(plane->GetOutputPort());
#else
    planeMapper->SetInput(plane->GetOutput());
#endif

// Actor
vtkActor* planeActor = vtkActor::New();
planeActor->SetTexture(texture);
planeActor->SetMapper(planeMapper);
planeActor->PickableOn();

// Final rendering with simple interactor:
vtkRenderer *ren = vtkRenderer::New();
vtkRenderWindow *renwin = vtkRenderWindow::New();
renwin->AddRenderer(ren);
vtkRenderWindowInteractor *iren = vtkRenderWindowInteractor::New();
iren->SetRenderWindow(renwin);
ren->AddActor(planeActor);
ren->SetBackground(0,0,0.5);

// DICOM is RAH:
vtkAnnotatedCubeActor* cube = vtkAnnotatedCubeActor::New();
cube->SetXPlusFaceText ( "R" );
cube->SetXMinusFaceText ( "L" );
cube->SetYPlusFaceText ( "A" );
cube->SetYMinusFaceText ( "P" );
cube->SetZPlusFaceText ( "H" );

```

```

cube->SetZMinusFaceText( "F" );

vtkAxesActor* axes2 = vtkAxesActor::New();

vtkTransform *transform = vtkTransform::New();
transform->Identity();
//reader->GetDirectionCosines()->Print(std::cout);
transform->Concatenate(invert);
//axes2->SetShaftTypeToCylinder();
axes2->SetUserTransform( transform );
cube->GetAssembly()->SetUserTransform( transform ); // can't get it to work

vtkPropAssembly* assembly = vtkPropAssembly::New();
assembly->AddPart( axes2 );
assembly->AddPart( cube );

vtkOrientationMarkerWidget* widget = vtkOrientationMarkerWidget::New();
widget->SetOrientationMarker( assembly );
widget->SetInteractor( iren );
widget->SetEnabled( 1 );
widget->InteractiveOff();
widget->InteractiveOn();

renwin->Render();
iren->Start();

// Clean up:
reader->Delete();
table->Delete();
texture->Delete();
plane->Delete();
planeMapper->Delete();
planeActor->Delete();
ren->Delete();
renwin->Delete();
iren->Delete();

return 0;
}

```

12.159 gdcmrtnionplan.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
#include "vtkImageData.h"
#include "vtkPointData.h"
#include "vtkPolyData.h"
#include "vtkProperty.h"
#include "vtkPolyDataMapper.h"
#include "vtkActor.h"
#include "vtkRenderer.h"
#include "vtkCellArray.h"
#include "vtkPoints.h"
#include "vtkDoubleArray.h"
#include <vtkXMLImageDataWriter.h>
#include <vtkXMLPolyDataWriter.h>
#include <vtkRenderWindowInteractor.h>
#include <vtkImageColorViewer.h>
#include "vtkVersion.h"

#include "gdcmReader.h"
#include "gdcmAttribute.h"

/*
This example is just for fun. We found a RT Ion Plan Storage and simply extracted the viz stuff for VTK

```



```

    RTIonPlanStorage, // 1.2.840.10008.5.1.4.1.1.481.8
*/
int main(int argc, char *argv[])
{
    if( argc < 3 )
    {
        std::cerr << argv[0] << " filename.dcm outfile.vti\n";
        return 1;
    }
    const char * filename = argv[1];
    const char * outfilename = argv[2];
    const char * outfilename2 = argv[3];

    gdcm::Reader reader;
    reader.SetFileName( filename );
    if( !reader.Read() )
    {
        return 1;
    }

    gdcm::MediaStorage ms;
    ms.SetFromFile( reader.GetFile() );
    if( ms != gdcm::MediaStorage::RTIonPlanStorage )
    {
        return 1;
    }

    /*
(300a,03a2) SQ                                     # u/l,1 Ion Beam Sequence
(fffe,e000) na (Item with undefined length)
(0008,1040) LO [Test]                               # 4,1 Institutional Department Name
(300a,00b2) SH (no value)                           # 0,1 Treatment Machine Name
(300a,00b3) CS [MU]                                  # 2,1 Primary Dosimeter Unit
(300a,00c0) IS [1 ]                                 # 2,1 Beam Number
(300a,00c2) LO [1 ]                                 # 2,1 Beam Name
(300a,00c4) CS [STATIC]                             # 6,1 Beam Type
(300a,00c6) CS [PROTON]                             # 6,1 Radiation Type
(300a,00ce) CS [TREATMENT ]                         # 10,1 Treatment Delivery Type
(300a,00d0) IS [0 ]                                 # 2,1 Number of Wedges
(300a,00e0) IS [1 ]                                 # 2,1 Number of Compensators
(300a,00ed) IS [0 ]                                 # 2,1 Number of Boli
(300a,00f0) IS [1 ]                                 # 2,1 Number of Blocks
(300a,0110) IS [2 ]                                 # 2,1 Number of Control Points
(300a,02ea) SQ                                       # u/l,1 Ion Range Compensator Sequence
(fffe,e000) na (Item with undefined length)
(300a,00e1) SH [lucite]                             # 6,1 Material ID
(300a,00e4) IS [1 ]                                 # 2,1 Compensator Number
(300a,00e5) SH [75hdhe5 ]                           # 8,1 Compensator ID
(300a,00e7) IS [35]                                 # 2,1 Compensator Rows
(300a,00e8) IS [37]                                 # 2,1 Compensator Columns
(300a,00e9) DS [3.679991\4.249288 ]                 # 18,2 Compensator Pixel Spacing
(300a,00ea) DS [-76.00\62.50]                       # 12,2 Compensator Position
(300a,00ec) DS
[52.13\52.13\52.13\53.18\54.04\54.04\47.11\40.06\40.06\38.79\34.87\33.28\33.28\33.28\33.28\35.43\35.43\34.54\34.54\34.71\36.
# 7618,1-n Compensator Thickness Data
(300a,02e0) CS [ABSENT]                             # 6,1 Compensator Divergence
(300a,02e1) CS [SOURCE_SIDE ]                       # 12,1 Compensator Mounting Position
(300a,02e4) FL 39.2                                 # 4,1 Isocenter to Compensator Tray Distance
(300a,02e5) FL 2.12                                 # 4,1 Compensator Column Offset
(300a,02e8) FL 4.76                                 # 4,1 Compensator Milling Tool Diameter
(fffe,e00d)
*/
    const gdcm::DataSet& ds = reader.GetFile().GetDataSet();
    gdcm::Tag tbeamsq(0x300a,0x03a2);
    if( !ds.FindDataElement( tbeamsq ) )
    {
        return 1;
    }
    const gdcm::DataElement &tbeamsq = ds.GetDataElement( tbeamsq );
    //std::cout << beamsq << std::endl;
    gdcm::SmartPointer<gdcm::SequenceOfItems> sqi = beamsq.GetValueAsSQ();
    if( !sqi || !sqi->GetNumberOfItems() )
    {
        return 1;
    }

    //for(unsigned int pd = 0; pd < sqi->GetNumberOfItems(); ++pd)
    // {
    //     //const gdcm::Item &item = sqi->GetItem(1); // Item start at #1
    //     const gdcm::Item &item = sqi->GetItem(1); // Item start at #1
    // }

```

```

const gdcm::DataSet& nestedds = item.GetNestedDataSet();
//std::cout << nestedds << std::endl;
gdcm::Tag tcompensatorsq(0x300a,0x02ea);
if( !nestedds.FindDataElement( tcompensatorsq ) )
{
    return 1;
}
const gdcm::DataElement &compensatorsq = nestedds.GetDataElement( tcompensatorsq );
//std::cout << compensatorsq << std::endl;
gdcm::SmartPointer<gdcm::SequenceOfItems> ssqi = compensatorsq.GetValueAsSQ();
const gdcm::Item & item2 = ssqi->GetItem(1); // Item start at #1
const gdcm::DataSet& nestedds2 = item2.GetNestedDataSet();
//std::cout << nestedds2 << std::endl;
gdcm::Tag tcompensatorthicknessdata(0x300a,0x00ec);
if( !nestedds2.FindDataElement( tcompensatorthicknessdata ) )
{
    return 1;
}
const gdcm::DataElement &compensatorthicknessdata = nestedds2.GetDataElement( tcompensatorthicknessdata );
// std::cout << compensatorthicknessdata << std::endl;
gdcm::Attribute<0x300a,0x00ec> at;
at.SetFromDataElement( compensatorthicknessdata );
const double* pts = at.GetValues();
// (300a,00e7) IS [35] # 2,1 Compensator Rows
gdcm::Attribute<0x300a,0x00e7> at1;
const gdcm::DataElement &compensatorrows = nestedds2.GetDataElement( at1.GetTag() );
at1.SetFromDataElement( compensatorrows );
std::cout << at1.GetValue() << std::endl;
// (300a,00e8) IS [37] # 2,1 Compensator Columns
gdcm::Attribute<0x300a,0x00e8> at2;
const gdcm::DataElement &compensatorcols = nestedds2.GetDataElement( at2.GetTag() );
at2.SetFromDataElement( compensatorcols );
std::cout << at2.GetValue() << std::endl;

// (300a,00e9) DS [3.679991\4.249288 ] # 18,2 Compensator Pixel Spacing
gdcm::Attribute<0x300a,0x00e9> at3;
const gdcm::DataElement &compensatorpixelspacing = nestedds2.GetDataElement( at3.GetTag() );
at3.SetFromDataElement( compensatorpixelspacing );
std::cout << at3.GetValue(0) << std::endl;
// (300a,00ea) DS [-76.00\62.50] # 12,2 Compensator Position
gdcm::Attribute<0x300a,0x00ea> at4;
const gdcm::DataElement &compensatorposition = nestedds2.GetDataElement( at4.GetTag() );
at4.SetFromDataElement( compensatorposition );
std::cout << at4.GetValue(0) << std::endl;

vtkDoubleArray *d = vtkDoubleArray::New();
d->SetArray( const_cast<double*>(pts) , at1.GetValue() * at2.GetValue() , 0 );

vtkImageData *img = vtkImageData::New();
img->Initialize();
img->SetDimensions( at2.GetValue(), at1.GetValue(), 1 );
//imgb->SetExtent(1, xdim, 1, ydim, 1, zdim);
#if (VTK_MAJOR_VERSION >= 6)
    assert(0);
#else
    img->SetScalarTypeToDouble();
#endif
img->SetSpacing( at3.GetValue(1), at3.GetValue(0), 1); // FIXME image is upside down
img->SetOrigin( at4.GetValue(0), at4.GetValue(1), 1);
#if (VTK_MAJOR_VERSION >= 6)
    assert(0);
#else
    img->SetNumberOfScalarComponents(1);
#endif
img->GetPointData()->SetScalars(d);

#if (VTK_MAJOR_VERSION >= 6)
#else
    img->Update();
#endif
img->Print(std::cout);

vtkXMLImageDataWriter *writeb= vtkXMLImageDataWriter::New();
#if (VTK_MAJOR_VERSION >= 6)
    writeb->SetInputData( img );
#else
    writeb->SetInput( img );
#endif
writeb->SetFileName( outfilename );
writeb->Write();
/*

```

```

(300a,03a6) SQ # u/1,1 Ion Block Sequence
(fffe,e000) na (Item with undefined length)
(300a,00e1) SH [brass ] # 6,1 Material ID
(300a,00f7) FL 95.03 # 4,1 Isocenter to Block Tray Distance
(300a,00f8) CS [APERTURE] # 8,1 Block Type
(300a,00fa) CS [ABSENT] # 6,1 Block Divergence
(300a,00fb) CS [SOURCE_SIDE ] # 12,1 Block Mounting Position
(300a,00fc) IS [1 ] # 2,1 Block Number
(300a,0100) DS [50.00 ] # 6,1 Block Thickness
(300a,0104) IS [179 ] # 4,1 Block Number of Points
(300a,0106) DS
[1.7\50.0\14.3\50.0\16.7\49.4\18.7\48.2\19.4\47.7\20.1\47.1\21.0\47.0\22.3\47.0\23.7\46.8\25.7\46.2\27.0\45.6\27.2\45.4\28.2
2\37.4\43.0\37.1\44.7\36] # 1934,2-2n Block Data
(fffe,e00d)
(fffe,e0dd)

*/
gdcmm::Tag tblocksq(0x300a,0x03a6);
if( !nestedds.FindDataElement( tblocksq ) )
{
    return 1;
}
const gdcmm::DataElement &blocksq = nestedds.GetDataElement( tblocksq );
//std::cout << blocksq << std::endl;
gdcmm::SmartPointer<gdcmm::SequenceOfItems> sssqi = blocksq.GetValueAssSQ();
const gdcmm::Item & item3 = sssqi->GetItem(1); // Item start at #1
const gdcmm::DataSet& nestedds3 = item3.GetNestedDataSet();

gdcmm::Tag tblockdata(0x300a,0x0106);
if( !nestedds3.FindDataElement( tblockdata ) )
{
    return 1;
}
const gdcmm::DataElement &blockdata = nestedds3.GetDataElement( tblockdata );
// std::cout << blockdata << std::endl;
gdcmm::Attribute<0x300a,0x0106> at_;
at_.SetFromDataElement( blockdata );

vtkDoubleArray *scalars = vtkDoubleArray::New();
scalars->SetNumberOfComponents(3);

gdcmm::Attribute<0x300a,0x0104> bnpts; // IS [179 ] # 4,1 Block Number
of Points
if( !nestedds3.FindDataElement( bnpts.GetTag() ) )
{
    return 1;
}
const gdcmm::DataElement &blocknpts = nestedds3.GetDataElement( bnpts.GetTag() );
bnpts.SetFromDataElement( blocknpts );
//std::cout << bnpts.GetValue() << std::endl;

vtkPolyData *output = vtkPolyData::New();
vtkPoints *newPts = vtkPoints::New();
vtkCellArray *polys = vtkCellArray::New();
const double *ptr = at_.GetValues();
//unsigned int npts = bnpts.GetNumberOfValues() / 2;
unsigned int npts = bnpts.GetValue();
vtkIdType *ptIds = new vtkIdType[npts];
for(unsigned int i = 0; i < npts; ++i)
{
    float x[3] = {};
    x[0] = (float)ptr[2*i+0];
    x[1] = (float)ptr[2*i+1];
    //x[2] = ptr[i+2];
    vtkIdType ptId = newPts->InsertNextPoint( x );
    //std::cout << x[0] << " " << x[1] << " " << x[2] << std::endl;
    ptIds[i] = ptId;
}
vtkIdType cellId = polys->InsertNextCell(npts , ptIds);
(void)cellId;
delete[] ptIds;

output->SetPoints(newPts);
newPts->Delete();
output->SetPolys(polys);
polys->Delete();
//output->GetCellData()->SetScalars(scalars);
//scalars->Delete();
#if (VTK_MAJOR_VERSION >= 6)
#else
    output->Update();
#endif

```

```

#endif
    output->Print( std::cout );

    // }

    vtkRenderWindowInteractor *iren = vtkRenderWindowInteractor::New();

    vtkImageColorViewer *viewer = vtkImageColorViewer::New();
    #if (VTK_MAJOR_VERSION >= 6)
        viewer->SetInputData(img);
    #else
        viewer->SetInput(img);
    #endif
    viewer->SetupInteractor(iren);
    viewer->SetSize(600, 600);
    viewer->GetRenderer()->ResetCameraClippingRange();
    viewer->Render();
    viewer->GetRenderer()->ResetCameraClippingRange();

    vtkPolyDataMapper *cubeMapper = vtkPolyDataMapper::New();
    //vtkPolyDataMapper2D* cubeMapper = vtkPolyDataMapper2D::New();
    #if (VTK_MAJOR_VERSION >= 6)
        cubeMapper->SetInputData( output );
    #else
        cubeMapper->SetInput( output );
    #endif
    cubeMapper->SetScalarRange(0,7);
    vtkActor *cubeActor = vtkActor::New();
    //vtkActor2D* cubeActor = vtkActor2D::New();
    cubeActor->SetMapper(cubeMapper);
    vtkProperty * property = cubeActor->GetProperty();
    property->SetRepresentationToWireframe();

    viewer->GetRenderer()->AddActor( cubeActor );

    vtkXMLPolyDataWriter *writec= vtkXMLPolyDataWriter::New();
    #if (VTK_MAJOR_VERSION >= 6)
        writec->SetInputData( output );
    #else
        writec->SetInput( output );
    #endif
    writec->SetFileName( outfilename2 );
    writec->Write();

    iren->Initialize();
    iren->Start();

    return 0;
}

```

12.160 gdcmrtpplan.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcms.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
#include "vtkImageData.h"
#include "vtkPointData.h"
#include "vtkPolyData.h"
#include "vtkProperty.h"
#include "vtkPolyDataMapper.h"
#include "vtkActor.h"
#include "vtkRenderer.h"

```

```

#include "vtkCellArray.h"
#include "vtkPoints.h"
#include "vtkDoubleArray.h"
#include <vtkXMLImageDataWriter.h>
#include <vtkRenderWindowInteractor.h>
#include <vtkImageColorViewer.h>
#include "vtkVersion.h"

#include "gdcmReader.h"
#include "gdcmAttribute.h"

/*
This example is just for fun. We found a fake RT Ion Plan Storage and simply extracted the viz stuff for VTK
but this is rather a RT Plan storage
*/
int main(int argc, char *argv[])
{
    if( argc < 3 )
    {
        std::cerr << argv[0] << " filename.dcm outfile.vti\n";
        return 1;
    }
    const char * filename = argv[1];
    const char * outfilename = argv[2];

    gdcm::Reader reader;
    reader.SetFileName( filename );
    if( !reader.Read() )
    {
        return 1;
    }

    gdcm::MediaStorage ms;
    ms.SetFromFile( reader.GetFile() );
    if( ms != gdcm::MediaStorage::RTIonPlanStorage )
    {
        return 1;
    }

    /*
(300a,00b0) SQ                                     # u/1,1 Beam Sequence
  (fffe,e000) na (Item with undefined length)
    (300a,00b2) SH (no value)                       # 0,1 Treatment Machine Name
    (300a,00c0) IS [1 ]                             # 2,1 Beam Number
    (300a,00c2) LO [1 ]                             # 2,1 Beam Name
    (300a,00c4) CS [STATIC]                         # 6,1 Beam Type
    (300a,00c6) CS [PROTON]                         # 6,1 Radiation Type
    (300a,00ce) CS [TREATMENT ]                    # 10,1 Treatment Delivery Type
    (300a,00e0) IS [1 ]                             # 2,1 Number of Compensators
    (300a,00e3) SQ                                  # u/1,1 Compensator Sequence
      (fffe,e000) na (Item with undefined length)
        (300a,00e1) SH [lucite]                     # 6,1 Material ID
        (300a,00e4) IS [1 ]                         # 2,1 Compensator Number
        (300a,00e5) SH [75hdhe5 ]                   # 8,1 Compensator ID
        (300a,00e7) IS [35]                         # 2,1 Compensator Rows
        (300a,00e8) IS [37]                         # 2,1 Compensator Columns
        (300a,00e9) DS [3.679991\4.249288 ]         # 18,2 Compensator Pixel Spacing
        (300a,00ea) DS [-76.00\62.50]               # 12,2 Compensator Position
        (300a,00ec) DS
          [52.13\52.13\52.13\53.18\54.04\54.04\47.11\40.06\40.06\38.79\34.87\33.28\33.28\33.28\33.28\35.43\35.43\34.54\34.54\34.71\36.
          # 7618,1-n Compensator Thickness Data
          (300a,02e0) CS [ABSENT]                   # 6,1 Compensator Divergence
          (300a,02e1) CS [SOURCE_SIDE ]             # 12,1 Compensator Mounting Position
        (fffe,e00d)
        (fffe,e000) na (Item with undefined length)
        (fffe,e00d)
        (fffe,e0dd)
      */
    const gdcm::DataSet& ds = reader.GetFile().GetDataSet();
    gdcm::Tag tbeamsq(0x300a,0x00b0);
    if( !ds.FindDataElement( tbeamsq ) )
    {
        return 1;
    }
    const gdcm::DataElement &tbeamsq = ds.GetDataElement( tbeamsq );
    //std::cout << tbeamsq << std::endl;
    gdcm::SmartPointer<gdcm::SequenceOfItems> sqi = tbeamsq.GetValueAsSQ();
    if( !sqi || !sqi->GetNumberOfItems() )
    {
        return 1;
    }

```

```

    }

//for(unsigned int pd = 0; pd < sqi->GetNumberOfItems(); ++pd)
// {
//const gdcm::Item & item = sqi->GetItem(1); // Item start at #1
const gdcm::Item & item = sqi->GetItem(2); // Item start at #1
const gdcm::DataSet& nestedds = item.GetNestedDataSet();
//std::cout << nestedds << std::endl;
gdcm::Tag tcompensatorsq(0x300a,0x00e3);
if( !nestedds.FindDataElement( tcompensatorsq ) )
{
    return 1;
}
const gdcm::DataElement &compensatorsq = nestedds.GetDataElement( tcompensatorsq );
//std::cout << compensatorsq << std::endl;
gdcm::SmartPointer<gdcm::SequenceOfItems> ssqi = compensatorsq.GetValueAsSQ();
const gdcm::Item & item2 = ssqi->GetItem(1); // Item start at #1
const gdcm::DataSet& nestedds2 = item2.GetNestedDataSet();
//std::cout << nestedds2 << std::endl;
gdcm::Tag tcompensatorthicknessdata(0x300a,0x00ec);
if( !nestedds2.FindDataElement( tcompensatorthicknessdata ) )
{
    return 1;
}
const gdcm::DataElement &compensatorthicknessdata = nestedds2.GetDataElement( tcompensatorthicknessdata );
// std::cout << compensatorthicknessdata << std::endl;
gdcm::Attribute<0x300a,0x00ec> at;
at.SetFromDataElement( compensatorthicknessdata );
const double* pts = at.GetValues();
// (300a,00e7) IS [35] # 2,1 Compensator Rows
gdcm::Attribute<0x300a,0x00e7> at1;
const gdcm::DataElement &compensatorrows = nestedds2.GetDataElement( at1.GetTag() );
at1.SetFromDataElement( compensatorrows );
std::cout << at1.GetValue() << std::endl;
// (300a,00e8) IS [37] # 2,1 Compensator Columns
gdcm::Attribute<0x300a,0x00e8> at2;
const gdcm::DataElement &compensatorcols = nestedds2.GetDataElement( at2.GetTag() );
at2.SetFromDataElement( compensatorcols );
std::cout << at2.GetValue() << std::endl;

// (300a,00e9) DS [3.679991\4.249288 ] # 18,2 Compensator Pixel Spacing
gdcm::Attribute<0x300a,0x00e9> at3;
const gdcm::DataElement &compensatorpixelspacing = nestedds2.GetDataElement( at3.GetTag() );
at3.SetFromDataElement( compensatorpixelspacing );
std::cout << at3.GetValue(0) << std::endl;
// (300a,00ea) DS [-76.00\62.50] # 12,2 Compensator Position
gdcm::Attribute<0x300a,0x00ea> at4;
const gdcm::DataElement &compensatorposition = nestedds2.GetDataElement( at4.GetTag() );
at4.SetFromDataElement( compensatorposition );
std::cout << at4.GetValue(0) << std::endl;

vtkDoubleArray *d = vtkDoubleArray::New();
d->SetArray( const_cast<double*>(pts) , at1.GetValue() * at2.GetValue() , 0 );

vtkImageData *img = vtkImageData::New();
img->Initialize();
img->SetDimensions( at2.GetValue(), at1.GetValue(), 1 );
//img->SetExtent(1, xdim, 1, ydim, 1, zdim);
#if (VTK_MAJOR_VERSION >= 6)
    assert(0);
#else
    img->SetScalarTypeToDouble();
#endif
img->SetSpacing( at3.GetValue(1), at3.GetValue(0), 1); // FIXME image is upside down
img->SetOrigin( at4.GetValue(0), at4.GetValue(1), 1);
#if (VTK_MAJOR_VERSION >= 6)
    assert(0);
#else
    img->SetNumberOfScalarComponents(1);
#endif
img->GetPointData()->SetScalars(d);

vtkXMLImageDataWriter *writeb= vtkXMLImageDataWriter::New();
#if (VTK_MAJOR_VERSION >= 6)
    writeb->SetInputData( img );
#else
    writeb->SetInput( img );
#endif
writeb->SetFileName( outfilename );
writeb->Write();
/*

```

```

(300a,00f4) SQ                                     # u/1,1 Block Sequence
(fffe,e000) na (Item with undefined length)
(300a,00e1) SH [brass ]                           # 6,1 Material ID
(300a,00f8) CS [APERTURE]                         # 8,1 Block Type
(300a,00fa) CS [ABSENT]                           # 6,1 Block Divergence
(300a,00fb) CS [SOURCE_SIDE ]                    # 12,1 Block Mounting Position
(300a,00fc) IS [1 ]                               # 2,1 Block Number
(300a,0100) DS [50.00 ]                           # 6,1 Block Thickness
(300a,0104) IS [179 ]                             # 4,1 Block Number of Points
(300a,0106) DS
[1.7\50.0\14.3\50.0\16.7\49.4\18.7\48.2\19.4\47.7\20.1\47.1\21.0\47.0\22.3\47.0\23.7\46.8\25.7\46.2\27.0\45.6\27.2\45.4\28.2]
# 1934,2-2n Block Data
(fffe,e00d)
(fffe,e000) na (Item with undefined length)
(fffe,e00d)
(fffe,e0dd)
*/
gdcmm::Tag tblocksq(0x300a,0x00f4);
if( !nestedds.FindDataElement( tblocksq ) )
{
    return 1;
}
const gdcmm::DataElement &blocksq = nestedds.GetDataElement( tblocksq );
//std::cout << blocksq << std::endl;
gdcmm::SmartPointer<gdcmm::SequenceOfItems> sssqi = blocksq.GetValueAssSQ();
const gdcmm::Item & item3 = sssqi->GetItem(1); // Item start at #1
const gdcmm::DataSet& nestedds3 = item3.GetNestedDataSet();

gdcmm::Tag tblockdata(0x300a,0x0106);
if( !nestedds3.FindDataElement( tblockdata ) )
{
    return 1;
}
const gdcmm::DataElement &blockdata = nestedds3.GetDataElement( tblockdata );
// std::cout << blockdata << std::endl;
gdcmm::Attribute<0x300a,0x0106> at_;
at_.SetFromDataElement( blockdata );

vtkDoubleArray *scalars = vtkDoubleArray::New();
scalars->SetNumberOfComponents(3);

gdcmm::Attribute<0x300a,0x0104> bnpts; // IS [179 ] # 4,1 Block Number of Points
if( !nestedds3.FindDataElement( bnpts.GetTag() ) )
{
    return 1;
}
const gdcmm::DataElement &blocknpts = nestedds3.GetDataElement( bnpts.GetTag() );
bnpts.SetFromDataElement( blocknpts );
std::cout << bnpts.GetValue() << std::endl;

vtkPolyData *output = vtkPolyData::New();
vtkPoints *newPts = vtkPoints::New();
vtkCellArray *polys = vtkCellArray::New();
const double *ptr = at_.GetValues();
//unsigned int npts = bnpts.GetNumberOfValues() / 2;
unsigned int npts = bnpts.GetValue();
vtkIdType *ptIds = new vtkIdType[npts];
for(unsigned int i = 0; i < npts; ++i)
{
    float x[3] = {};
    x[0] = (float)ptr[2*i+0];
    x[1] = (float)ptr[2*i+1];
    //x[2] = ptr[i+2];
    vtkIdType ptId = newPts->InsertNextPoint( x );
    //std::cout << x[0] << ", " << x[1] << ", " << x[2] << std::endl;
    ptIds[i] = ptId;
}
vtkIdType cellId = polys->InsertNextCell(npts , ptIds);
(void)cellId;
delete[] ptIds;

output->SetPoints(newPts);
newPts->Delete();
output->SetPolys(polys);
polys->Delete();
//output->GetCellData()->SetScalars(scalars);
//scalars->Delete();
#if (VTK_MAJOR_VERSION >= 6)
#else
    output->Update();
#endif
#endif

```

```

    output->Print( std::cout );

    // }

    vtkRenderWindowInteractor *iren = vtkRenderWindowInteractor::New();

    vtkImageColorViewer *viewer = vtkImageColorViewer::New();
    #if (VTK_MAJOR_VERSION >= 6)
        viewer->SetInputData(img);
    #else
        viewer->SetInput(img);
    #endif
    viewer->SetupInteractor(iren);
    viewer->SetSize(600, 600);
    viewer->Render();

    vtkPolyDataMapper *cubeMapper = vtkPolyDataMapper::New();
    //vtkPolyDataMapper2D* cubeMapper = vtkPolyDataMapper2D::New();
    #if (VTK_MAJOR_VERSION >= 6)
        cubeMapper->SetInputData( output );
    #else
        cubeMapper->SetInput( output );
    #endif
    cubeMapper->SetScalarRange(0,7);
    vtkActor *cubeActor = vtkActor::New();
    //vtkActor2D* cubeActor = vtkActor2D::New();
    cubeActor->SetMapper(cubeMapper);
    vtkProperty *property = cubeActor->GetProperty();
    property->SetRepresentationToWireframe();

    viewer->GetRenderer()->AddActor( cubeActor );

    iren->Initialize();
    iren->Start();

    return 0;
}

```

12.161 gdcmscene.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcms.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
#include "vtkGDCMPolyDataReader.h"
// #include "vtkGDCMPolyDataWriter.h"

#include "vtkAppendPolyData.h"
#include "vtkPolyDataWriter.h"
#include "vtkPolyDataMapper.h"
#include "vtkPolyDataMapper2D.h"
#include "vtkActor2D.h"
#include "vtkRenderWindowInteractor.h"
#include "vtkRenderWindow.h"
#include "vtkRenderer.h"
#include "vtkCamera.h"
#include "vtkProperty.h"
#include "vtkProperty2D.h"
#include "vtkVersion.h"

// gdcmDataExtra/gdcmNonImageData/exRT_Structure_Set_Storage.dcm
// gdcmDataExtra/gdcmNonImageData/RTSTRUCT_1.3.6.1.4.1.22213.1.1396.2.dcm

```



```

// gdcmDataExtra/gdcmNonImageData/RT/RTStruct.dcm

int main(int argc, char *argv[])
{
    if( argc < 2 )
    {
        std::cerr << argv[0] << " filename1.dcm\n";
        return 1;
    }
    const char * filename = argv[1];

    vtkGDCMPolyDataReader * reader = vtkGDCMPolyDataReader::New();
    reader->SetFileName( filename );
    reader->Update();

    // vtkGDCMPolyDataWriter * writer2 = vtkGDCMPolyDataWriter::New();
    // for(int num = 0; num < reader->GetNumberOfOutputPorts(); ++num )
    //     writer2->SetInput( num, reader->GetOutput(num) );
    // writer2->SetFileName( "rtstruct.dcm" );
    // writer2->Write();

    // print reader output:
    reader->Print( std::cout );
    // print first output:
    reader->GetOutput()->Print( std::cout );

    vtkAppendPolyData *append = vtkAppendPolyData::New();
    int n = reader->GetNumberOfOutputPorts();
    for(int i = 0; i < n; ++i)
    {
#ifdef VTK_MAJOR_VERSION >= 6
        append->AddInputConnection( reader->GetOutputPort(i) );
#else
        append->AddInput( reader->GetOutput(i) );
#endif
    }

    vtkPolyDataWriter * writer = vtkPolyDataWriter::New();
#ifdef VTK_MAJOR_VERSION >= 6
    writer->SetInputConnection( reader->GetOutputPort() );
#else
    writer->SetInput( reader->GetOutput() );
#endif
    writer->SetFileName( "rtstruct.vtk" );
    //writer->Write();

    // Now we'll look at it.
    vtkPolyDataMapper *cubeMapper = vtkPolyDataMapper::New();
    //vtkPolyDataMapper2D* cubeMapper = vtkPolyDataMapper2D::New();
    //cubeMapper->SetInput( reader->GetOutput() );
#ifdef VTK_MAJOR_VERSION >= 6
    cubeMapper->SetInputConnection( append->GetOutputPort() );
#else
    cubeMapper->SetInput( append->GetOutput() );
#endif
    cubeMapper->SetScalarRange(0,7);
    vtkActor *cubeActor = vtkActor::New();
    //vtkActor2D* cubeActor = vtkActor2D::New();
    cubeActor->SetMapper(cubeMapper);
    vtkProperty * property = cubeActor->GetProperty();
    property->SetRepresentationToWireframe();
    //cubeActor->GetProperty()->SetColor(1, 0, 0);

    // The usual rendering stuff.
    // vtkCamera *camera = vtkCamera::New();
    //     camera->SetPosition(1,1,1);
    //     camera->SetFocalPoint(0,0,0);

    vtkRenderer *renderer = vtkRenderer::New();
    vtkRenderWindow *renWin = vtkRenderWindow::New();
    renWin->AddRenderer(renderer);

    vtkRenderWindowInteractor *iren = vtkRenderWindowInteractor::New();
    iren->SetRenderWindow(renWin);

    renderer->AddActor(cubeActor);
    //renderer->AddActor2D(cubeActor);
    //renderer->SetActiveCamera(camera);
    renderer->ResetCamera();

```

```

        renderer->SetBackground(1,1,1);

renWin->SetSize(300,300);

// interact with data
renWin->Render();
iren->Start();

reader->Delete();
append->Delete();
cubeMapper->Delete();
cubeActor->Delete();
// camera->Delete();
renderer->Delete();
renWin->Delete();
iren->Delete();

writer->Delete();

return 0;
}

```

12.162 gdcmttexture.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.
=====*/
#include "vtkGDCMImageReader.h"

#include "vtkRenderer.h"
#include "vtkAssembly.h"
#include "vtkRenderWindow.h"
#include "vtkAnnotatedCubeActor.h"
#include "vtkTransform.h"
#include "vtkAxesActor.h"
#include "vtkTextProperty.h"
#include "vtkCaptionActor2D.h"
#include "vtkPropAssembly.h"
#include "vtkOrientationMarkerWidget.h"
#include "vtkRenderWindowInteractor.h"
#include "vtkPolyDataMapper.h"
#include "vtkActor.h"
#include "vtkImageData.h"
#include "vtkLookupTable.h"
#include "vtkTexture.h"
#include "vtkPlaneSource.h"
#include "vtkVersion.h"

int main( int argc, char *argv[] )
{
    if( argc < 2 ) return 1;
    vtkGDCMImageReader *reader = vtkGDCMImageReader::New();
    reader->SetFileName( argv[1] );

    reader->Update();
    vtkImageData* ima = reader->GetOutput();

    vtkLookupTable* table = vtkLookupTable::New();
    table->SetNumberOfColors(1000);
    table->SetTableRange(0,1000);
    table->SetSaturationRange(0,0);
    table->SetHueRange(0,1);
    table->SetValueRange(0,1);
    table->SetAlphaRange(1,1);

```

```

table->Build();

// Texture
vtkTexture* texture = vtkTexture::New();
#if (VTK_MAJOR_VERSION >= 6)
    texture->SetInputData(ima);
#else
    texture->SetInput(ima);
#endif
texture->InterpolateOn();
texture->SetLookupTable(table);

// PlaneSource
vtkPlaneSource* plane = vtkPlaneSource::New();
plane->SetOrigin( -0.5, -0.5, 0.0);
plane->SetPoint1( 0.5, -0.5, 0.0);
plane->SetPoint2( -0.5, 0.5, 0.0);

// PolyDataMapper
vtkPolyDataMapper *planeMapper = vtkPolyDataMapper::New();
#if (VTK_MAJOR_VERSION >= 6)
    planeMapper->SetInputConnection(plane->GetOutputPort());
#else
    planeMapper->SetInput(plane->GetOutput());
#endif

// Actor
vtkActor* planeActor = vtkActor::New();
planeActor->SetTexture(texture);
planeActor->SetMapper(planeMapper);
planeActor->PickableOn();

// Final rendering with simple interactor:
vtkRenderer *ren = vtkRenderer::New();
vtkRenderWindow *renwin = vtkRenderWindow::New();
renwin->AddRenderer(ren);
vtkRenderWindowInteractor *iren = vtkRenderWindowInteractor::New();
iren->SetRenderWindow(renwin);
ren->AddActor(planeActor);
ren->SetBackground(0,0,0.5);

vtkAnnotatedCubeActor* cube = vtkAnnotatedCubeActor::New();
cube->SetXPlusFaceText ( "L" );
cube->SetXMinusFaceText ( "R" );
cube->SetYPlusFaceText ( "A" );
cube->SetYMinusFaceText ( "P" );
cube->SetZPlusFaceText ( "H" );
cube->SetZMinusFaceText ( "F" );

vtkAxesActor* axes2 = vtkAxesActor::New();
// simulate a left-handed coordinate system
//
vtkTransform *transform = vtkTransform::New();
transform->Identity();
//transform->RotateY(180);
reader->GetDirectionCosines()->Print(std::cout);
transform->Concatenate(reader->GetDirectionCosines());
//axes2->SetShaftTypeToCylinder();
axes2->SetUserTransform( transform );
//cube->SetUserTransform( transform ); // can't get it to work
cube->GetAssembly()->SetUserTransform( transform ); // can't get it to work

vtkPropAssembly* assembly = vtkPropAssembly::New();
assembly->AddPart( axes2 );
assembly->AddPart( cube );

vtkOrientationMarkerWidget* widget = vtkOrientationMarkerWidget::New();
//widget->SetOutlineColor( 0.9300, 0.5700, 0.1300 );
widget->SetOrientationMarker( assembly );
widget->SetInteractor( iren );
//widget->SetViewport( 0.0, 0.0, 0.4, 0.4 );
widget->SetEnabled( 1 );
widget->InteractiveOff();
widget->InteractiveOn();

renwin->Render();
iren->Start();

// Clean up:
reader->Delete();
table->Delete();

```

```

texture->Delete();
plane->Delete();
planeMapper->Delete();
planeActor->Delete();
ren->Delete();
renwin->Delete();
iren->Delete();

return 0;
}

```

12.163 gdcmvolume.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
#include "vtkVersion.h"
#include "vtkGDCMImageReader.h"
#include "vtkPiecewiseFunction.h"
#include "vtkColorTransferFunction.h"
#include "vtkVolume.h"
#include "vtkVolumeProperty.h"
#if VTK_MAJOR_VERSION < 7
#include "vtkVolumeTextureMapper3D.h"
#endif
#include "vtkFixedPointVolumeRayCastMapper.h"
#include "vtkInteractorStyleTrackballCamera.h"
#include "vtkRenderer.h"
#include "vtkRenderWindow.h"
#include "vtkImageClip.h"
#include "vtkRenderWindowInteractor.h"
#include "vtkVersion.h"

// gdcmvolume gdcmData/GE_DLX-8-MONO2-Multiframe-Jpeg_Lossless.dcm
int main(int argc, char *argv[])
{
    if( argc < 2 ) return 1;
    vtkGDCMImageReader *reader = vtkGDCMImageReader::New();
    reader->SetFileName( argv[1] );
    reader->Update();

    // Create the renderers, render window, and interactor
    vtkRenderWindow *renWin = vtkRenderWindow::New();
    vtkRenderWindowInteractor *iren = vtkRenderWindowInteractor::New();
    iren->SetRenderWindow(renWin);
    vtkRenderer *ren = vtkRenderer::New();
    renWin->AddRenderer(ren);

    // Create a transfer function mapping scalar value to opacity
    vtkPiecewiseFunction *oTFun = vtkPiecewiseFunction::New();
    //oTFun->AddSegment(0, 1.0, 256, 0.1);
    oTFun->AddSegment(0, 1.0, 240, 0.1);

    vtkColorTransferFunction *cTFun = vtkColorTransferFunction::New();
    cTFun->AddRGBPoint( 0, 1.0, 1.0, 1.0 );
    //cTFun->AddRGBPoint( 255, 1.0, 1.0, 1.0 );
    cTFun->AddRGBPoint( 240, 1.0, 1.0, 1.0 );

    // Need to crop to actually see minimum intensity
    vtkImageClip *clip = vtkImageClip::New();
    clip->SetInputConnection( reader->GetOutputPort() );
    clip->SetOutputWholeExtent(0,66,0,66,30,37);
    clip->ClipDataOn();

    vtkVolumeProperty *property = vtkVolumeProperty::New();

```

```

property->SetScalarOpacity(oTFun);
property->SetColor(cTFun);
property->SetInterpolationTypeToLinear();

vtkFixedPointVolumeRayCastMapper *mapper = vtkFixedPointVolumeRayCastMapper::New();
mapper->SetBlendModeToMinimumIntensity();
mapper->SetInputConnection( reader->GetOutputPort() );

vtkVolume *volume = vtkVolume::New();
volume->SetMapper(mapper);
volume->SetProperty(property);

ren->AddViewProp(volume);

renWin->Render();
{
    iren->Start();
}

volume->Delete();
mapper->Delete();
property->Delete();
clip->Delete();
cTFun->Delete();
oTFun->Delete();
reader->Delete();
renWin->Delete();
iren->Delete();
ren->Delete();

return 0;
}

```

12.164 offscreenimage.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
#include "vtkGDCMImageReader.h"
#include "vtkRenderWindow.h"
#include "vtkRenderer.h"
#include "vtkImageMapToWindowLevelColors.h"
#include "vtkImageActor.h"
#include "vtkPNGWriter.h"
#include "vtkWindowToImageFilter.h"
#include "vtkMedicalImageProperties.h"
#include "vtkVersion.h"

int main(int argc, char *argv[])
{
    if( argc < 2 )
    {
        return 1;
    }
    const char *filename = argv[1];

    vtkGDCMImageReader *reader = vtkGDCMImageReader::New();
    reader->SetFileName( filename );
    reader->Update(); // important to read the window/level info

    vtkMedicalImageProperties *prop = reader->GetMedicalImageProperties();

    vtkRenderWindow *renWin = vtkRenderWindow::New();

```

```

renWin->OffScreenRenderingOn();

vtkRenderer *renderer = vtkRenderer::New();
renWin->AddRenderer(renderer);

vtkImageMapToWindowLevelColors *windowlevel = vtkImageMapToWindowLevelColors::New();
#if (VTK_MAJOR_VERSION >= 6)
windowlevel->SetInputConnection( reader->GetOutputPort() );
#else
windowlevel->SetInput( reader->GetOutput() );
#endif
unsigned int n = prop->GetNumberOfWindowLevelPresets();
if( n )
{
    // Take the first one by default:
    const double *wl = prop->GetNthWindowLevelPreset(0);
    windowlevel->SetWindow( wl[0] );
    windowlevel->SetLevel( wl[1] );
}

vtkImageActor *actor = vtkImageActor::New();
#if (VTK_MAJOR_VERSION >= 6)
actor->SetInputData( windowlevel->GetOutput() );
#else
actor->SetInput( windowlevel->GetOutput() );
#endif

renderer->AddActor( actor );

renWin->Render();

vtkWindowToImageFilter *w2if = vtkWindowToImageFilter::New();
w2if->SetInput( renWin );

vtkPNGWriter *wr = vtkPNGWriter::New();
#if (VTK_MAJOR_VERSION >= 6)
wr->SetInputConnection( w2if->GetOutputPort() );
#else
wr->SetInput( w2if->GetOutput() );
#endif
wr->SetFileName( "offscreenimage.png" );
wr->Write();

reader->Delete();
renWin->Delete();
renderer->Delete();
windowlevel->Delete();
actor->Delete();
w2if->Delete();
wr->Delete();

return 0;
}

```

12.165 reslicesphere.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcms.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
//
// Load a DICOM series.
// Position a sphere within the volume.
// Allow the user to change between Axial, Sagittal, Coronal, and
// Oblique view of the images and move through the slices.
// The display should show the resliced image and the cross section
// of the sphere intersecting that plane.

```

```

//

/*
from Scott Johnson /Scott Johnson neuwave com/
to VTK /vtkusers vtk.org/
date Tue, May 11, 2010 at 7:01 PM
*/
#include <string>

#include <vtkDICOMImageReader.h>
#include <vtkStringArray.h>
#include <vtkDirectory.h>
#include <vtkImageThreshold.h>
#include <vtkImageShiftScale.h>
#include <vtkImageReslice.h>
#include <vtkRenderWindowInteractor.h>
#include <vtkImageViewer2.h>
#include <vtkSphereSource.h>
#include <vtkPolyDataMapper.h>
#include <vtkPlane.h>
#include <vtkCutter.h>
#include <vtkActor.h>
#include <vtkCommand.h>
#include <vtkSmartPointer.h>
#include <vtkMatrix4x4.h>
#include <vtkInteractorObserver.h>
#include <vtkProperty.h>
#include <vtkRenderer.h>
#include <vtkImageData.h>
#include <vtkImageActor.h>
#include "vtkTransformPolyDataFilter.h"
#include <vtkCamera.h>
#include <vtkMath.h>
#include <vtkTransform.h>
#include <vtkTextActor.h>
#include <vtkActor2D.h>
#include <vtkPolyDataMapper2D.h>
#include <vtkProperty2D.h>
#include <vtkGDCMImageReader.h>
#include <vtkImageChangeInformation.h>
#include <vtkVersion.h>

#include "gdcmdirctory.h"
#include "gdcmtesting.h"
#include "gdcmppsorter.h"

// Change to match the path to find Raw_0.vti or provide
// the parameter when starting ResliceSphere.

const double sphereCenter[3]={74, 219, 70};

// Angles (0, 0, 0)
const double AxialMatrix[] = { 1.0, 0.0, 0.0, 0.0,
                               0.0, 1.0, 0.0, 0.0,
                               0.0, 0.0, 1.0, 0.0,
                               0.0, 0.0, 0.0, 1.0 };

// Angles (0, 90, 0)
const double SagittalMatrix[] = { 0.0, 0.0, 1.0, 0.0,
                                   0.0, 1.0, 0.0, 0.0,
                                   -1.0, 0.0, 0.0, 0.0,
                                   0.0, 0.0, 0.0, 1.0 };

// Angles (-90, 0, 0)
const double CoronalMatrix[] = { 1.0, 0.0, 0.0, 0.0,
                                  0.0, 0.0, 1.0, 0.0,
                                  0.0, -1.0, 0.0, 0.0,
                                  0.0, 0.0, 0.0, 1.0 };

// Angles (0, 90, 31)
const double ObliqueMatrix[] = { 0.0, -0.515038, 0.857167, 0.0,
                                  0.0, 0.857167, 0.515038, 0.0,
                                  -1.0, 0.0, 0.0, 0.0,
                                  0.0, 0.0, 0.0, 1.0 };

class ResliceRender;

// Class to handle key press events.
class KeyCallback : public vtkCommand
{
public:
    static KeyCallback* New()
    {

```

```

        return new KeyCallback();
    }

    void Execute(vtkObject* caller, unsigned long eventId, void *calldata);
    void SetCallbackData(ResliceRender* reslice);

protected:
    ResliceRender* _reslice;
};

class ResliceRender
{
public:
    typedef enum _ORIENTATION
    {
        AXIAL = 0,
        SAGITTAL = 1,
        CORONAL = 2,
        OBLIQUE = 3
    } ORIENTATION;

    ResliceRender()
    {
        _orientation=AXIAL;
    }

    ~ResliceRender()
    {
        _transform->Delete();
        _reader->Delete();
        _reslice->Delete();
        _interactor->Delete();
        _imageViewer->Delete();

        _sphere->Delete();
        _sphereMapper->Delete();
        _sphereActor->Delete();

        _plane->Delete();
        _cutter->Delete();
        _polyTransform->Delete();
        _ROIMapper->Delete();
        _ROIActor->Delete();

        _annotation->Delete();
    }

    void CreatePipeline(const char* fileName)
    {
        vtkProperty2D* props;

        //_reader=vtkXMLImageDataReader::New();
        //_reader->SetFileName(fileName);
        //_reader->Update();

        //_reader=qzDICOMImageReader::New();
        _reader=vtkGDCMImageReader::New();

        //vtkDirectory *d = vtkDirectory::New();
        //d->Open(fileName);
        //d->Print( std::cout );
        gdcm::Directory d;
        d.Load(fileName);
        gdcm::Directory::FileNamesType const &files = d.GetFilesNames();

        gdcm::IPPSorter s;
        s.SetComputeZSpacing( true );
        s.SetZSpacingTolerance( 1e-3 );
        bool b = s.Sort( files );
        if( !b )
        {
            std::cerr << "Failed to sort:" << fileName << std::endl;
            //return ;
        }
        //std::cout << "Sorting succeeded:" << std::endl;
        //s.Print( std::cout );

        //std::cout << "Found z-spacing:" << std::endl;
        //std::cout << s.GetZSpacing() << std::endl;
    }

```



```

double ippzspacing = s.GetZSpacing();

const std::vector<std::string> & sorted = s.GetFileNames();
vtkStringArray *vtkfiles = vtkStringArray::New();
std::vector< std::string >::const_iterator it = sorted.begin();
for( ; it != sorted.end(); ++it)
{
    const std::string &f = *it;
    vtkfiles->InsertNextValue( f.c_str() );
}

    //_reader->SetDirectoryName(fileName);
    //_reader->SetFileNames( d->GetFiles() );
    _reader->SetFileNames( vtkfiles );
    _reader->Update();

#ifdef vtkFloatingPointType
#define vtkFloatingPointType double
#endif
    const vtkFloatingPointType *spacing = _reader->GetOutput()->GetSpacing();

    vtkImageChangeInformation *v16 = vtkImageChangeInformation::New();
    #if (VTK_MAJOR_VERSION >= 6)
        v16->SetInputConnection( _reader->GetOutputPort() );
    #else
        v16->SetInput( _reader->GetOutput() );
    #endif
    v16->SetOutputSpacing( spacing[0], spacing[1], ippzspacing );
    v16->Update();

    _threshold=vtkImageThreshold::New();
    _threshold->ThresholdByUpper(-3024.0);
    _threshold->ReplaceOutOn();
    _threshold->SetOutValue(0.0);
    _threshold->SetInputConnection(v16->GetOutputPort());

    _shift=vtkImageShiftScale::New();
    _shift->SetShift(0);
    _shift->SetScale(1);
    _shift->SetInputConnection(_threshold->GetOutputPort());

    // Initialize the reslice with an axial orientation.
    vtkSmartPointer<vtkMatrix4x4> matrix =
        vtkSmartPointer<vtkMatrix4x4>::New();
    matrix->Identity();

    _transform = vtkTransform::New();
    _transform->SetMatrix(matrix);

    _reslice = vtkImageReslice::New();
    _reslice->SetOutputDimensionality(3);

    // PROBLEM:
    // The original intent was to connect the same transform
    // to the vtkImageReslice and vtkTransformPolyDataFilter,
    // but the resulting reslices appear different using the
    // vtkTransform as opposed to explicitly setting the
    // reslice axes via SetResliceAxes. Also, if the vtkTransform
    // is connected and orientated other than axial, the extents
    // don't seem to update resulting in VTK believing the slice
    // is out of range.

    //_reslice->SetResliceTransform(_transform);
    _reslice->SetResliceAxes(matrix);
    //_reslice->SetInputConnection(_reader->GetOutputPort());
    _reslice->SetInputConnection(_shift->GetOutputPort());

    // Create the sphere target shape.
    _sphere=vtkSphereSource::New();
    _sphere->SetRadius(7.0);
    _sphere->SetThetaResolution(16);
    _sphere->SetPhiResolution(16);
    _sphere->SetCenter(sphereCenter[0], sphereCenter[1], sphereCenter[2]);

    _sphereMapper=vtkPolyDataMapper::New();
    _sphereMapper->SetInputConnection(_sphere->GetOutputPort());

    _sphereActor=vtkActor::New();
    _sphereActor->SetMapper(_sphereMapper);
    _sphereActor->PickableOff();

```

```

_sphereActor->GetProperty()->SetColor(1.0, 0.0, 0.0);
_sphereActor->GetProperty()->SetEdgeColor(1.0, 0.0, 0.0);
_sphereActor->GetProperty()->SetDiffuseColor(1.0, 0.0, 0.0);
_sphereActor->SetVisibility(true);

// Create the cutting pipeline.
// This plane will be positioned in the original image coordinate system.
_plane = vtkPlane::New();
_plane->SetNormal(0.0, 0.0, 1.0);

_cutter = vtkCutter::New();
_cutter->SetInputConnection(_sphere->GetOutputPort());
_cutter->SetCutFunction(_plane);
_cutter->GenerateCutScalarsOn();
_cutter->SetValue(0, 0.5);

// The transform attached to _polyTransform should move the cut
// ROI into the resliced coordinate system, which should be the
// same as the coordinate system of the resliced images.
// PROBLEM: It doesn't.
_polyTransform = vtkTransformPolyDataFilter::New();
_polyTransform->SetTransform(_transform);
_polyTransform->SetInputConnection(_cutter->GetOutputPort());

_ROIMapper = vtkPolyDataMapper2D::New();
_ROIMapper->SetInputConnection(_polyTransform->GetOutputPort());

vtkCoordinate* coordinate = vtkCoordinate::New();
coordinate->SetCoordinateSystemToWorld();
_ROIMapper->SetTransformCoordinate(coordinate);

_ROIActor = vtkActor2D::New();
_ROIActor->SetMapper(_ROIMapper);

// Make sure the cut can be seen, especially the edges.
props=_ROIActor->GetProperty();
props->SetLineWidth(2);
props->SetOpacity(1.0);
// props->EdgeVisibilityOn();
// props->SetDiffuse(0.8);
// props->SetSpecular(0.3);
// props->SetSpecularPower(20);
// props->SetRepresentationToSurface();
// props->SetDiffuseColor(1.0, 0.0, 0.0);
// props->SetEdgeColor(1.0, 0.0, 0.0);
props->SetColor(1.0, 0.0, 0.0);

_interactor = vtkRenderWindowInteractor::New();

// Create the image viewer and add the actor with the cut ROI.
_imageViewer = vtkImageViewer2::New();
_imageViewer->SetupInteractor(_interactor);
_imageViewer->SetSize(400, 400);
_imageViewer->SetColorWindow(1024);
_imageViewer->SetColorLevel(800);
_imageViewer->SetInputConnection(_reslice->GetOutputPort());
_imageViewer->GetImageActor()->SetOpacity(0.5);

_annotation = vtkTextActor::New();
_annotation->SetTextScaleModeToViewport();
_imageViewer->GetRenderer()->AddActor(_annotation);

// Add the cut shape actor to the renderer.
_imageViewer->GetRenderer()->AddActor(_ROIActor);

// Set up the key handler.
vtkSmartPointer<KeyCallback> callback = vtkSmartPointer<KeyCallback>::New();
callback->SetCallbackData(this);
_interactor->AddObserver(vtkCommand::KeyPressEvent, callback);

_interactor->Initialize();
}

void Start()
{
    _interactor->Start();
}

void ResetOrientation()
{
    vtkSmartPointer<vtkMatrix4x4> matrix =

```

```

        vtkSmartPointer<vtkMatrix4x4>::New();
        matrix->Identity();

        SetOrientation(matrix);
    }

    // Make sure the orientation of the vtkImageReslice and
    // vtkTransform are in sync.
    void SetOrientation(vtkMatrix4x4* matrix)
    {
        _reslice->SetResliceAxes(matrix);
        _reslice->Update();

        vtkMatrix4x4* inverse = vtkMatrix4x4::New();
        vtkMatrix4x4::Invert(matrix, inverse);

        _transform->SetMatrix(inverse);
        _transform->Update();
    }

    // Set the current slice of the current view.
    void SetSlice(int slice)
    {
        std::stringstream posString;

        double    center[3];
        double    spacing[3];
        double    origin[3];
        double    point[4];
        double    newPoint[4];

        vtkImageData* imageData;
        int newSlice;

        // Try to make sure the extents of the reslice are updated.
        // PROBLEM: It doesn't seem to work when changing the orientation.
        imageData=vtkImageData::SafeDownCast(_reslice->GetOutput());
#ifdef (VTK_MAJOR_VERSION >= 6)
        assert(0);
#else
        imageData->UpdateInformation();
#endif

        // Let vtkImageViewer2 handle the slice limits.
        _imageView->SetSlice(slice);
        newSlice=GetSlice();

        imageData->GetCenter(center);
        imageData->GetSpacing(spacing);
        imageData->GetOrigin(origin);

        // Compute the position of the center of the slice based on the
        // spacing of the slices. The resliced axis will always
        // be the "Z" axis.
        point[0]=center[0];
        point[1]=center[1];
        point[2]=(newSlice * spacing[2]) + origin[2];
        point[3]=1.0;

        // Convert the coordinate from the reslice coordinate system to the
        // original image coordinate system.
        // PROBLEM: Logically this seems like it should have been multiplied
        // by the inverse to translate from the resliced coordinate system to
        // the original coordinate system. However, multiplying by the inverse
        // sticks the plane in the wrong place completely. Using the original
        // matrix at least gets the Z coordinate right.
        vtkMatrix4x4* matrix=_reslice->GetResliceAxes();
        vtkSmartPointer<vtkMatrix4x4> inverse =
            vtkSmartPointer<vtkMatrix4x4>::New();
        vtkMatrix4x4::Invert(matrix, inverse);

        matrix->MultiplyPoint(point, newPoint);
        _plane->SetOrigin(newPoint[0], newPoint[1], newPoint[2]);

        // Annotate the image.
        posString << "Position: (" << newPoint[0] << ", " << newPoint[1]
            << ", " << newPoint[2] << ") Slice: " << newSlice;
        _annotation->SetInput(posString.str().c_str());

        _imageView->Render();
    }

```

```

    }

    int GetSlice()
    {
        return _imageView->GetSlice();
    }

    // Set the orientation of the view.
    void SetOrientation(ResliceRender::ORIENTATION orientation)
    {
        vtkCamera* camera=_imageView->GetRenderer()->GetActiveCamera();

        double spacing[3];
        double origin[3];
        double point[4];
        double newPoint[4];
        double initialPosition;
        double xDirCosine[3];
        double yDirCosine[3];
        double zDirCosine[3];
        double normal[3];

        vtkImageData* imageData;

        vtkSmartPointer<vtkMatrix4x4> matrix =
            vtkSmartPointer<vtkMatrix4x4>::New();

        _orientation=orientation;

        // Reset ViewUp
        camera->SetViewUp(0.0, 1.0, 0.0);

        // Compute the cut plane position to the input coordinate system.
        imageData=vtkImageData::SafeDownCast(_reslice->GetInput());
#ifdef (VTK_MAJOR_VERSION >= 6)
        assert(0);
#else
        imageData->UpdateInformation();
#endif
        imageData->GetSpacing(spacing);
        imageData->GetOrigin(origin);

        point[0]=origin[0];
        point[1]=origin[1];
        point[2]=origin[2];
        point[3]=1.0;

        switch (_orientation)
        {
            case AXIAL:
                matrix->DeepCopy(AxialMatrix);
                initialPosition=sphereCenter[2];
                break;

            case CORONAL:
                matrix->DeepCopy(CoronalMatrix);
                initialPosition=sphereCenter[1];
                break;

            case SAGITTAL:
                matrix->DeepCopy(SagittalMatrix);
                initialPosition=sphereCenter[0];
                break;

            case OBLIQUE:
                matrix->DeepCopy(ObliqueMatrix);
                initialPosition=sphereCenter[2];
                break;
        }

        // Move the origin from the original image coordinate system to the
        // resliced image coordinate system.
        matrix->MultiplyPoint(point, newPoint);
        matrix->SetElement(0, 3, newPoint[0]);
        matrix->SetElement(1, 3, newPoint[1]);
        matrix->SetElement(2, 3, newPoint[2]);

        ResetOrientation();
        SetOrientation(matrix);

        // Compute the cutting plane normal and set it.

```

```

        // PROBLEM: If the transformation is connected rather than
        // using SetResliceAxes, the Direction Cosines do not reflect
        // the orientation of the vtkImageReslice.
        _reslice->GetResliceAxesDirectionCosines(xDirCosine, yDirCosine,
                                                zDirCosine);
        vtkMath::Cross(xDirCosine, yDirCosine, normal);
        _plane->SetNormal(normal);

        // Set the extents and spacing of the reslice to account for
        // all of the data.
        _reslice->SetOutputExtentToDefault();
        _reslice->SetOutputSpacing(spacing[0], spacing[0], spacing[0]);

        // Force the vtkImageViewer2 to update.
        // PROBLEM: The whole extent does not seem to be set in time
        // for the first render. This results in an error because the
        // slice is positioned outside the old bounds.
        #if (VTK_MAJOR_VERSION >= 6)
            _imageView->SetInputData(NULL);
        #else
            _imageView->SetInput(NULL);
        #endif
        _imageView->SetInputConnection(_reslice->GetOutputPort());

        _imageView->GetRenderer()->ResetCameraClippingRange();
        _imageView->GetRenderer()->ResetCamera();

        // Set the initial slice to be at the center of the sphere.
        // Divide by the spacing because this will be undone in SetSlice.
        SetSlice( (int)(initialPosition / spacing[0]));
    }

    vtkRenderWindowInteractor* GetInteractor()
    {
        return _interactor;
    }

protected:
    ORIENTATION          _orientation;

    //qzDICOMImageReader*    _reader;
    vtkGDCMImageReader*    _reader;
    vtkImageThreshold*      _threshold;
    vtkImageShiftScale*     _shift;
    vtkImageReslice*        _reslice;
    vtkRenderWindowInteractor* _interactor;
    vtkImageViewer2*        _imageView;

    vtkSphereSource*        _sphere;
    vtkPolyDataMapper*      _sphereMapper;
    vtkActor*               _sphereActor;

    vtkPlane*               _plane;
    vtkCutter*              _cutter;
    vtkTransform*           _transform;
    vtkTransformPolyDataFilter* _polyTransform;
    vtkPolyDataMapper2D*    _ROIMapper;
    vtkActor2D*             _ROIActor;

    vtkTextActor*           _annotation;
};

// Catch KeyPress events.
// Up Arrow - increases the slice
// Down Arrow - decreases the slice
// 'A' - sets the view to Axial
// 'S' - sets the view to Sagittal
// 'C' - sets the view to Coronal
// 'O' - set the view to Oblique

void KeyCallback::Execute(vtkObject* caller, unsigned long eventId, void *calldata)
{
    (void)caller;
    (void)eventId;
    (void)calldata;
    std::string sym=_reslice->GetInteractor()->GetKeySym();

    if (!sym.compare("Up"))
    {
        _reslice->SetSlice(_reslice->GetSlice() + 1);
    }

```

```

    }
    else if (!sym.compare("Down"))
    {
        _reslice->SetSlice(_reslice->GetSlice() - 1);
    }
    else if ((!sym.compare("A")) || (!sym.compare("a")))
    {
        _reslice->SetOrientation(ResliceRender::AXIAL);
    }
    else if ((!sym.compare("C")) || (!sym.compare("c")))
    {
        _reslice->SetOrientation(ResliceRender::CORONAL);
    }
    else if ((!sym.compare("S")) || (!sym.compare("s")))
    {
        _reslice->SetOrientation(ResliceRender::SAGITTAL);
    }
    else if ((!sym.compare("O")) || (!sym.compare("o")))
    {
        _reslice->SetOrientation(ResliceRender::OBLIQUE);
    }
}

void KeyCallback::SetCallbackData(ResliceRender* reslice)
{
    _reslice=reslice;
}

// Usage: ResliceSphere [fileName]
int main(int argc, char *argv[])
{
    ResliceRender render;

    if (argc == 1)
    {
        const char *root = gdcm::Testing::GetDataExtraRoot();
        std::string dir3 = root;
        dir3 += "/gdcmSampleData/ForSeriesTesting/Dentist/images/";
        render.CreatePipeline(dir3.c_str());
    }
    else
    {
        render.CreatePipeline(argv[1]);
    }

    render.SetOrientation(ResliceRender::AXIAL);
    render.Start();

    return EXIT_SUCCESS;
}

```

12.166 rtstructapp.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
#include "vtkGDCMPolyDataReader.h"
#include "vtkGDCMPolyDataWriter.h"

#include "vtkPolyDataWriter.h"
#include "vtkPolyDataMapper.h"
#include "vtkPolyDataMapper2D.h"
#include "vtkActor2D.h"
#include "vtkRenderWindowInteractor.h"
#include "vtkMedicalImageProperties.h"
#include "vtkRenderWindow.h"

```

```

#include "vtkRenderer.h"
#include "vtkCamera.h"
#include "vtkProperty.h"
#include "vtkProperty2D.h"
#include "vtkAppendPolyData.h"
#include "vtkImageData.h"
#include "vtkVersion.h"

/*
 * Small example to read in a RTSTRUCT and write it out (displays it too).
 */

// gdcmDataExtra/gdcmNonImageData/exRT_Structure_Set_Storage.dcm
// gdcmDataExtra/gdcmNonImageData/RTSTRUCT_1.3.6.1.4.1.22213.1.1396.2.dcm
// gdcmDataExtra/gdcmNonImageData/RT/RTStruct.dcm

int main(int argc, char *argv[])
{
    if( argc < 3 )
    {
        std::cerr << argv[0] << " input.dcm output.dcm\n";
        return 1;
    }
    const char * filename = argv[1];
    const char * outfilename = argv[2];
    vtkGDCMPolyDataReader * reader = vtkGDCMPolyDataReader::New();
    reader->SetFileName( filename );
    reader->Update();

    //std::cout << reader->GetMedicalImageProperties()->GetStudyDate() << std::endl;

    vtkGDCMPolyDataWriter * writer = vtkGDCMPolyDataWriter::New();
    writer->SetNumberOfInputPorts( reader->GetNumberOfOutputPorts() );
    writer->SetFileName( outfilename );
    for(int num = 0; num < reader->GetNumberOfOutputPorts(); ++num )
    #if (VTK_MAJOR_VERSION >= 6)
        writer->SetInputConnection( num, reader->GetOutputPort( num) );
    #else
        writer->SetInput( num, reader->GetOutput( num) );
    #endif
    //doesn't look like the medical properties are actually written out
    writer->SetMedicalImageProperties( reader->GetMedicalImageProperties() );
    writer->SetRTStructSetProperties( reader->GetRTStructSetProperties() );
    writer->Write();

    // print reader output:
    reader->Print( std::cout );
    // print first output:
    reader->GetOutput()->Print( std::cout );

    vtkAppendPolyData *append = vtkAppendPolyData::New();

    int n = reader->GetNumberOfOutputPorts();
    for(int i = 0; i < n; ++i)
    {
    #if (VTK_MAJOR_VERSION >= 6)
        append->AddInputConnection( reader->GetOutputPort(i) );
    #else
        append->AddInput( reader->GetOutput(i) );
    #endif
    }

    // Now we'll look at it.
    vtkPolyDataMapper *cubeMapper = vtkPolyDataMapper::New();
    #if (VTK_MAJOR_VERSION >= 6)
        cubeMapper->SetInputConnection( append->GetOutputPort() );
    #else
        cubeMapper->SetInput( append->GetOutput() );
    #endif
    cubeMapper->SetScalarRange(0,7);
    vtkActor *cubeActor = vtkActor::New();
    cubeActor->SetMapper( cubeMapper );
    vtkProperty * property = cubeActor->GetProperty();
    property->SetRepresentationToWireframe();

    vtkRenderer *renderer = vtkRenderer::New();
    vtkRenderWindow *renWin = vtkRenderWindow::New();
    renWin->AddRenderer( renderer );

    vtkRenderWindowInteractor *iren = vtkRenderWindowInteractor::New();

```

```

    iren->SetRenderWindow(renWin);

    renderer->AddActor(cubeActor);
    renderer->ResetCamera();
    renderer->SetBackground(1,1,1);

    renWin->SetSize(300,300);

    renWin->Render();
    iren->Start();

    reader->Delete();
    append->Delete();
    cubeMapper->Delete();
    cubeActor->Delete();
    renderer->Delete();
    renWin->Delete();
    iren->Delete();
    writer->Delete();

    return 0;
}

```

12.167 threadgdcmm.cxx

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcmm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
#include "gdcmmReader.h"
#include "gdcmmImageReader.h"
#include "gdcmmDirectory.h"
#include "gdcmmSystem.h"

#include "vtkImageData.h"
#include "vtkStructuredPointsWriter.h"
#include "vtkVersion.h"

#include <pthread.h>

struct threadparams
{
    const char **filenames;
    size_t nfiles;
    char *scalarpointer;
// TODO I should also pass in the dim of the reference image just in case
};

void *ReadFilesThread(void *voidparams)
{
    const threadparams *params = static_cast<const threadparams *> (voidparams);

    const size_t nfiles = params->nfiles;
    for(unsigned int file = 0; file < nfiles; ++file)
    {
        /*
        // TODO: update progress
        pthread_mutex_lock(&params->lock);
        //section critique
        ReadingProgress+=params->stepProgress;
        pthread_mutex_unlock(&params->lock);
        */
        const char *filename = params->filenames[file];
        //std::cerr << filename << std::endl;

        gdcmm::ImageReader reader;
        reader.SetFileName( filename );
    }
}

```



```

    try
    {
        if( !reader.Read() )
        {
            std::cerr << "Failed to read: " << filename << std::endl;
            break;
        }
    }
    catch( ... )
    {
        std::cerr << "Failed to read: " << filename << std::endl;
        break;
    }

    const gdcm::Image &image = reader.GetImage();
    unsigned long len = image.GetBufferLength();
    char * pointer = params->scalarpointer;

#ifdef 0
    char *tempimage = new char[len];
    image.GetBuffer(tempimage);

    memcpy(pointer + file*len, tempimage, len);
    delete[] tempimage;
#else
    char *tempimage = pointer + file * len;
    image.GetBuffer(tempimage);
#endif
    }

    return voidparams;
}

void ShowFileNames(const threadparams &params)
{
    std::cout << "start" << std::endl;
    for(unsigned int i = 0; i < params.nfiles; ++i)
    {
        const char *filename = params.fileNames[i];
        std::cout << filename << std::endl;
    }
    std::cout << "end" << std::endl;
}

void ReadFiles(size_t nfiles, const char *fileNames[])
{
    // \precondition: nfiles > 0
    assert( nfiles > 0 );
    const char *reference= fileNames[0]; // take the first image as reference

    gdcm::ImageReader reader;
    reader.SetFileName( reference );
    if( !reader.Read() )
    {
        // That would be very bad...
        assert(0);
    }

    const gdcm::Image &image = reader.GetImage();
    gdcm::PixelFormat pixeltype = image.GetPixelFormat();
    unsigned long len = image.GetBufferLength();
    const unsigned int *dims = image.GetDimensions();
    unsigned short pixelSize = pixeltype.GetPixelSize();
    (void)pixelSize;
    assert( image.GetNumberOfDimensions() == 2 );

    vtkImageData *output = vtkImageData::New();
    output->SetDimensions(dims[0], dims[1], (int)nfiles);

#ifdef (VTK_MAJOR_VERSION >= 6)
    int numscal = pixeltype.GetSamplesPerPixel();
    switch( pixeltype )
    {
        case gdcm::PixelFormat::INT8:
            output->AllocateScalars( VTK_SIGNED_CHAR, numscal );
            break;
        case gdcm::PixelFormat::UINT8:
            output->AllocateScalars( VTK_UNSIGNED_CHAR, numscal );
            break;
        case gdcm::PixelFormat::INT16:
            output->AllocateScalars( VTK_SHORT, numscal );
            break;
    }
#endif
}

```

```

case gdcm::PixelFormat::UINT16:
    output->AllocateScalars( VTK_UNSIGNED_SHORT, numscal );
    break;
case gdcm::PixelFormat::INT32:
    output->AllocateScalars( VTK_INT, numscal );
    break;
case gdcm::PixelFormat::UINT32:
    output->AllocateScalars( VTK_UNSIGNED_INT, numscal );
    break;
default:
    assert(0);
}
#else
switch( pixeltype )
{
case gdcm::PixelFormat::INT8:
    #if (VTK_MAJOR_VERSION >= 5) || ( VTK_MAJOR_VERSION == 4 && VTK_MINOR_VERSION > 5 )
        output->SetScalarType ( VTK_SIGNED_CHAR );
    #else
        output->SetScalarType ( VTK_CHAR );
    #endif
    break;
case gdcm::PixelFormat::UINT8:
    output->SetScalarType ( VTK_UNSIGNED_CHAR );
    break;
case gdcm::PixelFormat::INT16:
    output->SetScalarType ( VTK_SHORT );
    break;
case gdcm::PixelFormat::UINT16:
    output->SetScalarType ( VTK_UNSIGNED_SHORT );
    break;
case gdcm::PixelFormat::INT32:
    output->SetScalarType ( VTK_INT );
    break;
case gdcm::PixelFormat::UINT32:
    output->SetScalarType ( VTK_UNSIGNED_INT );
    break;
default:
    assert(0);
}
output->SetNumberOfScalarComponents ( pixeltype.GetSamplesPerPixel() );
output->AllocateScalars();
#endif
char * scalarpointer = static_cast<char*>(output->GetScalarPointer());

const unsigned int nthreads = 4;
threadparams params[nthreads];

//pthread_mutex_t lock;
//pthread_mutex_init(&lock, NULL);

pthread_t *pthread = new pthread_t[nthreads];

// There is nfiles, and nThreads
assert( nfiles > nthreads );
const size_t partition = nfiles / nthreads;
for (unsigned int thread=0; thread < nthreads; ++thread)
{
    params[thread].filenames = filenames + thread * partition;
    params[thread].nfiles = partition;
    if( thread == nthreads - 1 )
    {
        // There is slightly more files to process in this thread:
        params[thread].nfiles += nfiles % nthreads;
    }
    assert( thread * partition < nfiles );
    params[thread].scalarpointer = scalarpointer + thread * partition * len;
    //assert( params[thread].scalarpointer < scalarpointer + 2 * dims[0] * dims[1] * dims[2] );
    // start thread:
    int res = pthread_create( &pthread[thread], NULL, ReadFilesThread, &params[thread]);
    if( res )
    {
        std::cerr << "Unable to start a new thread, pthread returned: " << res << std::endl;
        assert(0);
    }
    //ShowFilenames(params[thread]);
}
// DEBUG
size_t total = 0;
for (unsigned int thread=0; thread < nthreads; ++thread)
{

```

```

        total += params[thread].nfiles;
    }
    assert( total == nfiles );
// END DEBUG

    for (unsigned int thread=0;thread<nthreads;thread++)
    {
        pthread_join( pthread[thread], NULL);
    }
    delete[] pthread;

    //pthread_mutex_destroy(&lock);

    // For some reason writing down the file is painfully slow...
    vtkStructuredPointsWriter *writer = vtkStructuredPointsWriter::New();
#if (VTK_MAJOR_VERSION >= 6)
    writer->SetInputData( output );
#else
    writer->SetInput( output );
#endif
    writer->SetFileName( "/tmp/threadgdcm.vtk" );
    writer->SetFileTypeToBinary();
    //writer->Write();
    writer->Delete();

    //output->Print( std::cout );
    output->Delete();
}

int main(int argc, char *argv[])
{
    if( argc < 2 )
    {
        std::cerr << argv[0] << " [directory|list of filenames]\n";
        return 1;
    }

    // Check if user pass in a single directory
    if( argc == 2 && gdcm::System::FileIsDirectory( argv[1] ) )
    {
        gdcm::Directory d;
        d.Load( argv[1] );
        gdcm::Directory::FileNamesType l = d.GetFilesNames();
        const size_t nfiles = l.size();
        const char **filenames = new const char* [ nfiles ];
        for(unsigned int i = 0; i < nfiles; ++i)
        {
            filenames[i] = l[i].c_str();
        }
        ReadFiles(nfiles, filenames);
        delete[] filenames;
    }
    else
    {
        // Simply copy all filenames into the vector:
        const char **filenames = const_cast<const char**>(argv+1);
        const size_t nfiles = argc - 1;
        ReadFiles(nfiles, filenames);
    }

    return 0;
}

```

12.168 AWTMedical3.java

```

/*=====

Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR

```

```

    PURPOSE. See the above copyright notice for more information.

=====*/
package examples;

import vtk.*;
//import gdcm.*;

import vtk.util.VtkPanelContainer;
import vtk.util.VtkPanelUtil;
import vtk.util.VtkUtil;

import java.util.ArrayList;

import javax.swing.*;
import java.awt.*;
import java.io.File;

public class AWTMedical3 extends JComponent implements VtkPanelContainer {

    private vtkPanel renWin;

    vtkImageData ReadDataFile(File inSelectedFile){

        vtkImageData outImageData = null;
        Directory theDir = new Directory();

        String theInputDirectory = inSelectedFile.getPath();
        theDir.Load(theInputDirectory);

        Scanner theScanner = new Scanner();
        Tag theStudyTag = new Tag(0x0020,0x000d);
        Tag theSeriesTag = new Tag(0x0020,0x000e);
        theScanner.AddTag(theStudyTag);//get studies,
        theScanner.AddTag(theSeriesTag);//get studies,
        theScanner.Scan(theDir.GetFilesNames());

        FilenamesType theStudyValues = theScanner.GetOrderedValues(theStudyTag);
        long theNumStudies = theStudyValues.size();
        //for now, take the first study, and nothing else.
        //and the return is actually not FilenamesType, just a
        //vector of strings
        if (theNumStudies != 1)
            return outImageData;
        String theStudyVal = theStudyValues.get(0);
        //now, get all the values from the scanner that are in that
        //study, then from that get their different series
        FilenamesType theFilenames =
            theScanner.GetAllFilenamesFromTagToValue(theStudyTag, theStudyVal);

        //from that set of filenames, isolate individual series
        //conclude that singleton series = RT struct (can do further
        //checking for things like MIPs and the like)
        //and multiple series entries = volumetric data
        theScanner.Scan(theFilenames);
        FilenamesType theSeriesValues = theScanner.GetOrderedValues(theSeriesTag);
        String studyUID = theScanner.GetValue(theScanner.GetFilesNames().get(0), theStudyTag);
        long theNumSeries = theSeriesValues.size();
        for (int i = 0; i < theNumSeries; i++) {
            FilenamesType theSeriesFiles =
                theScanner.GetAllFilenamesFromTagToValue(theSeriesTag, theSeriesValues.get(i));
            long theNumFilesInSeries = theSeriesFiles.size();
            if (theNumFilesInSeries > 1) { //assume it's CT or volumetric data
                //for now, assume a single volume
                //could have multiples, like PET and CT

                IPPSorter sorter = new IPPSorter();
                sorter.SetComputeZSpacing(true);
                sorter.SetZSpacingTolerance(0.001);
                Boolean sorted = sorter.Sort(theSeriesFiles);
                if (!sorted){
                    //need some better way to handle failures here
                    return outImageData;
                }

                FilenamesType sortedFT = sorter.GetFilesNames();
                long theSize = sortedFT.size();
                vtkStringArray sa = new vtkStringArray();

```

```

        ArrayList<String> theStrings = new ArrayList<String>();

        vtkGDCMImageReader gdcmReader = new vtkGDCMImageReader();
        for (int j = 0; j < theSize; j++) {
            String theFileName = sortedFT.get(j);
            if (gdcmReader.CanReadFile(theFileName) > 0){
                theStrings.add(theFileName);
                sa.InsertNextValue(theFileName);
            } else {
                //this is a busted series
                //need some more appropriate error here
                return outImageData;
            }
        }

        gdcmReader.SetFileNames(sa);

        gdcmReader.Update();

        outImageData = gdcmReader.GetOutput(); //the zeroth output should be the image
    }
}

String theImageInfo = "";
if (outImageData != null){
    theImageInfo = outImageData.Print();
}
return outImageData;
}

//this function is a rewrite of Medical3 to see if data can
//be loaded via gdcm easily
public AWTMedical3(File inFile) {
    // Create the buttons.
    renWin = new vtkPanel();

    vtkImageData theImageData = ReadDataFile(inFile);

    // An isosurface, or contour value of 500 is known to correspond to the
    // skin of the patient. Once generated, a vtkPolyDataNormals filter is
    // is used to create normals for smooth surface shading during rendering.
    // The triangle stripper is used to create triangle strips from the
    // isosurface these render much faster on some systems.
    vtkContourFilter skinExtractor = new vtkContourFilter();
    skinExtractor.SetInput(theImageData);
    skinExtractor.SetValue(0, 500);
    vtkPolyDataNormals skinNormals = new vtkPolyDataNormals();
    skinNormals.SetInput(skinExtractor.GetOutput());
    skinNormals.SetFeatureAngle(60.0);
    //      vtkStripper skinStripper = new vtkStripper();
    //      skinStripper.SetInput(skinNormals.GetOutput());
    vtkPolyDataMapper skinMapper = new vtkPolyDataMapper();
    skinMapper.SetInput(skinNormals.GetOutput());
    skinMapper.ScalarVisibilityOff();
    vtkActor skin = new vtkActor();
    skin.SetMapper(skinMapper);
    skin.GetProperty().SetDiffuseColor(1, .49, .25);
    skin.GetProperty().SetSpecular(.3);
    skin.GetProperty().SetSpecularPower(20);

    // An isosurface, or contour value of 1150 is known to correspond to the
    // skin of the patient. Once generated, a vtkPolyDataNormals filter is
    // is used to create normals for smooth surface shading during rendering.
    // The triangle stripper is used to create triangle strips from the
    // isosurface these render much faster on some systems.
    vtkContourFilter boneExtractor = new vtkContourFilter();
    boneExtractor.SetInput(theImageData);
    boneExtractor.SetValue(0, 1150);
    vtkPolyDataNormals boneNormals = new vtkPolyDataNormals();
    boneNormals.SetInput(boneExtractor.GetOutput());
    boneNormals.SetFeatureAngle(60.0);
    vtkStripper boneStripper = new vtkStripper();
    boneStripper.SetInput(boneNormals.GetOutput());
    vtkPolyDataMapper boneMapper = new vtkPolyDataMapper();
    boneMapper.SetInput(boneStripper.GetOutput());
    boneMapper.ScalarVisibilityOff();
    vtkActor bone = new vtkActor();
    bone.SetMapper(boneMapper);
    bone.GetProperty().SetDiffuseColor(1, 1, .9412);

    // An outline provides context around the data.
    vtkOutlineFilter outlineData = new vtkOutlineFilter();

```

```

outlineData.SetInput(theImageData);
vtkPolyDataMapper mapOutline = new vtkPolyDataMapper();
mapOutline.SetInput(outlineData.GetOutput());
vtkActor outline = new vtkActor();
outline.SetMapper(mapOutline);
outline.GetProperty().SetColor(0, 0, 0);

// Now we are creating three orthogonal planes passing through the
// volume. Each plane uses a different texture map and therefore has
// different coloration.

// Start by creating a black/white lookup table.
vtkLookupTable bwLut = new vtkLookupTable();
bwLut.SetTableRange(0, 2000);
bwLut.SetSaturationRange(0, 0);
bwLut.SetHueRange(0, 0);
bwLut.SetValueRange(0, 1);
bwLut.Build();

// Now create a lookup table that consists of the full hue circle (from
// HSV);.
vtkLookupTable hueLut = new vtkLookupTable();
hueLut.SetTableRange(0, 2000);
hueLut.SetHueRange(0, 1);
hueLut.SetSaturationRange(1, 1);
hueLut.SetValueRange(1, 1);
hueLut.Build();

// Finally, create a lookup table with a single hue but having a range
// in the saturation of the hue.
vtkLookupTable satLut = new vtkLookupTable();
satLut.SetTableRange(0, 2000);
satLut.SetHueRange(.6, .6);
satLut.SetSaturationRange(0, 1);
satLut.SetValueRange(1, 1);
satLut.Build();

// Create the first of the three planes. The filter vtkImageMapToColors
// maps the data through the corresponding lookup table created above.
// The vtkImageActor is a type of vtkProp and conveniently displays an
// image on a single quadrilateral plane. It does this using texture
// mapping and as a result is quite fast. (Note: the input image has to
// be unsigned char values, which the vtkImageMapToColors produces.);
// Note also that by specifying the DisplayExtent, the pipeline
// requests data of this extent and the vtkImageMapToColors only
// processes a slice of data.
vtkImageMapToColors sagittalColors = new vtkImageMapToColors();
sagittalColors.SetInput(theImageData);
sagittalColors.SetLookupTable(bwLut);
vtkImageActor sagittal = new vtkImageActor();
sagittal.SetInput(sagittalColors.GetOutput());
sagittal.SetDisplayExtent(32, 32, 0, 63, 0, 92);

// Create the second (axial); plane of the three planes. We use the same
// approach as before except that the extent differs.
vtkImageMapToColors axialColors = new vtkImageMapToColors();
axialColors.SetInput(theImageData);
axialColors.SetLookupTable(hueLut);
vtkImageActor axial = new vtkImageActor();
axial.SetInput(axialColors.GetOutput());
axial.SetDisplayExtent(0, 63, 0, 63, 46, 46);

// Create the third (coronal); plane of the three planes. We use the same
// approach as before except that the extent differs.
vtkImageMapToColors coronalColors = new vtkImageMapToColors();
coronalColors.SetInput(theImageData);
coronalColors.SetLookupTable(satLut);
vtkImageActor coronal = new vtkImageActor();
coronal.SetInput(coronalColors.GetOutput());
coronal.SetDisplayExtent(0, 63, 32, 32, 0, 92);

// It is convenient to create an initial view of the data. The FocalPoint
// and Position form a vector direction. Later on (ResetCamera() method)
// this vector is used to position the camera to look at the data in
// this direction.
vtkCamera aCamera = new vtkCamera();
aCamera.SetViewUp(0, 0, -1);
aCamera.SetPosition(0, 1, 0);
aCamera.SetFocalPoint(0, 0, 0);

```

```

aCamera.ComputeViewPlaneNormal();

// Actors are added to the renderer. An initial camera view is created.
// The Dolly() method moves the camera towards the FocalPoint,
// thereby enlarging the image.
renWin.GetRenderer().AddActor(sagittal);
renWin.GetRenderer().AddActor(axial);
renWin.GetRenderer().AddActor(coronal);
renWin.GetRenderer().AddActor(outline);
renWin.GetRenderer().AddActor(skin);
renWin.GetRenderer().AddActor(bone);

// Turn off bone for this example.
bone.VisibilityOff();

// Set skin to semi-transparent.
skin.GetProperty().SetOpacity(0.5);

// An initial camera view is created. The Dolly() method moves
// the camera towards the FocalPoint, thereby enlarging the image.
renWin.GetRenderer().SetActiveCamera(aCamera);
renWin.GetRenderer().ResetCamera();
aCamera.Dolly(1.5);

// Set a background color for the renderer and set the size of the
// render window (expressed in pixels).
renWin.GetRenderer().SetBackground(1, 1, 1);
VtkPanelUtil.setSize(renWin, 640, 480);

// Note that when camera movement occurs (as it does in the Dolly()
// method), the clipping planes often need adjusting. Clipping planes
// consist of two planes: near and far along the view direction. The
// near plane clips out objects in front of the plane the far plane
// clips out objects behind the plane. This way only what is drawn
// between the planes is actually rendered.
renWin.GetRenderer().ResetCameraClippingRange();

// Setup panel
setLayout(new BorderLayout());
add(renWin, BorderLayout.CENTER);
}

public vtkPanel getRenWin() {
    return renWin;
}

public static void main(String s[]) {
    if (s.length == 0){
        return; //need a filename here
    }
    File theFile = new File(s[0]);
    //File theFile = new
    File("/Users/mmroden/Documents/MVSDownloadDirectory/Documents/1.2.840.113704.1.111.3384.1271766367.5/");
    AWTMedical3 panel = new AWTMedical3(theFile);

    JFrame frame = new JFrame("AWTMedical3");
    frame.setDefaultCloseOperation(JFrame.EXIT_ON_CLOSE);
    frame.getContentPane().add("Center", panel);
    frame.pack();
    frame.setVisible(true);
}
}

```

12.169 HelloVTKWorld.java

```

/*=====

Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcml.sourceforge.net/Copyright.html for details.

```

```

    This software is distributed WITHOUT ANY WARRANTY; without even
    the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
    PURPOSE. See the above copyright notice for more information.

=====*/
// We are required to call the package 'vtk' even though I (MM) would have preferred
// an import statement along the line of:
// import vtkgdcmm.*;
import vtk.*;

/*
 * Compilation:
 * CLASSPATH=vtkgdcmm.jar:/usr/share/java/vtk.jar javac HelloVTKWorld.java
 *
 * Usage:
 * LD_LIBRARY_PATH=/usr/lib/jvm/java-6-openjdk/jre/lib/amd64/xawt:/usr/lib/jni:.
 * CLASSPATH=/usr/share/java/vtk.jar:vtkgdcmm.jar:gdcmm.jar:. java HelloVTKWorld gdcmmData/012345.002.050.dcm
 * bla.dcm
 */
public class HelloVTKWorld
{
    static {
        System.loadLibrary("vtkCommonJava");
        System.loadLibrary("vtkFilteringJava");
        System.loadLibrary("vtkIOJava");
        System.loadLibrary("vtkImagingJava");
        System.loadLibrary("vtkGraphicsJava");
        System.loadLibrary("vtkgdcmmJava");
        try {
            System.loadLibrary("vtkRenderingJava");
        } catch (Throwable e) {
            System.out.println("cannot load vtkHybrid, skipping...");
        }
        try {
            System.loadLibrary("vtkHybridJava");
        } catch (Throwable e) {
            System.out.println("cannot load vtkHybrid, skipping...");
        }
        try {
            System.loadLibrary("vtkVolumeRenderingJava");
        } catch (Throwable e) {
            System.out.println("cannot load vtkVolumeRendering, skipping...");
        }
    }

    public static void main(String[] args)
    {
        String filename = args[0];
        vtkGDCMImageReader reader = new vtkGDCMImageReader();
        reader.SetFileName( filename );
        reader.Update();

        vtkMedicalImageProperties prop = reader.GetMedicalImageProperties();
        System.out.println( prop.GetPatientName() ); //

        // if( reader.GetImageFormat() == vtkgdcmm.vtkgdcmm.VTK_LUMINANCE ) // MONOCHROME2
        // {
        //     System.out.println( "Image is MONOCHROME2" ); //
        // }

        // Just for fun, invert the direction cosines, output should reflect that:
        vtkMatrix4x4 dircos = reader.GetDirectionCosines();
        dircos.Invert();

        // We need to maintain in sync information stored in vtkMedicalImageProperties:
        double[] cosines = new double[6];
        cosines[0] = dircos.GetElement(0,0);
        cosines[1] = dircos.GetElement(1,0);
        cosines[2] = dircos.GetElement(2,0);
        cosines[3] = dircos.GetElement(0,1);
        cosines[4] = dircos.GetElement(1,1);
        cosines[5] = dircos.GetElement(2,1);
        reader.GetMedicalImageProperties().SetDirectionCosine( cosines );

        String outfilename = args[1];
        vtkGDCMImageWriter writer = new vtkGDCMImageWriter();
        writer.SetMedicalImageProperties( reader.GetMedicalImageProperties() );
        writer.SetDirectionCosines( dircos );
        writer.SetShift( reader.GetShift() );
    }
}

```



```

        writer.SetScale( reader.GetScale() );
        writer.SetImageFormat( reader.GetImageFormat() );
        writer.SetFileName( outfilename );
        writer.SetInputConnection( reader.GetOutputPort() ); // new
        //writer.SetInput( reader.GetOutput() ); // old
        writer.Write();

        System.out.println("Success reading: " + filename );
    }
}

```

12.170 MIPViewer.java

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.
=====*/

import vtk.*;
import gdcm.*;
import java.io.File;
import java.awt.Canvas;

/*
 * Compilation:
 * CLASSPATH=vtkgdc.jar:/usr/share/java/vtk.jar javac MIPViewer.java
 *
 * Usage:
 * LD_LIBRARY_PATH=/usr/lib/jvm/java-6-openjdk/jre/lib/amd64/xawt:/usr/lib/jni:.
 * CLASSPATH=/usr/share/java/vtk.jar:vtkgdc.jar:gdcm.jar:. java MIPViewer BRAINX
 */
public class MIPViewer extends Canvas
{
    static {
        // VTK
        System.loadLibrary("vtkCommonJava");
        System.loadLibrary("vtkFilteringJava");
        System.loadLibrary("vtkIOJava");
        System.loadLibrary("vtkImagingJava");
        System.loadLibrary("vtkGraphicsJava");
        System.loadLibrary("vtkRenderingJava");
        System.loadLibrary("vtkVolumeRenderingJava"); // vtkSmartVolumeMapper
        System.loadLibrary("vtkWidgetsJava"); // vtkBoxWidget
        // VTK-GDCM
        System.loadLibrary("vtkgdcJava");
    }

    static FilenamesType fns = new FilenamesType();

    protected native int Lock();

    protected native int UnLock();

    public static void process(String path)
    {
        fns.add( path );
    }

    // Process only files under dir
    public static void visitAllFiles(File dir)
    {
        if (dir.isDirectory())
        {
            String[] children = dir.list();
            for (int i=0; i<children.length; i++)
            {
                visitAllFiles(new File(dir, children[i]));
            }
        }
    }
}

```

```

    }
}
else
{
    process(dir.getPath());
}
}

public static void main(String[] args) throws Exception
{
    String dirname = args[0];
    if( !PosixEmulation.FileIsDirectory( dirname ) )
    {
        return;
    }

    File dir = new File(dirname);
    visitAllFiles(dir);

    IPPSorter ipp = new IPPSorter();
    ipp.SetComputeZSpacing( true );
    ipp.SetZSpacingTolerance( 1e-3 );
    boolean b = ipp.Sort( fns );
    if(!b)
    {
        throw new Exception("Could not scan");
    }
    double ippzspacing = ipp.GetZSpacing();

    FilenamesType sorted = ipp.GetFilenames();
    vtkStringArray files = new vtkStringArray();
    long nfiles = sorted.size();
    //for( String f : sorted )
    for (int i = 0; i < nfiles; i++) {
        String f = sorted.get(i);
        files.InsertNextValue( f );
    }
    vtkGDCMImageReader reader = new vtkGDCMImageReader();
    reader.SetFileNames( files );
    reader.Update(); // get spacing value

    double[] spacing = reader.GetOutput().GetSpacing();

    vtkImageChangeInformation change = new vtkImageChangeInformation();
    change.SetInputConnection( reader.GetOutputPort() );
    change.SetOutputSpacing( spacing[0], spacing[1], ippzspacing );

    // Create our volume and mapper
    vtkVolume volume = new vtkVolume();
    vtkSmartVolumeMapper mapper = new vtkSmartVolumeMapper();

    vtkRenderWindowInteractor iren = new vtkRenderWindowInteractor();

    // Add a box widget if the clip option was selected
    vtkBoxWidget box = new vtkBoxWidget();
    box.SetInteractor(iren);
    box.SetPlaceFactor(1.01);
    box.SetInputConnection(change.GetOutputPort());

    //box.SetDefaultRenderer(renderer);
    box.InsideOutOn();
    box.PlaceWidget();
    //vtkBoxWidgetCallback callback = vtkBoxWidgetCallback::New();
    //callback.SetMapper(mapper);
    //box.AddObserver(vtkCommand::InteractionEvent, callback);
    //callback.Delete();
    // Lock();
    // box.EnabledOn();
    // Unlock();
    box.GetSelectedFaceProperty().SetOpacity(0.0);

    mapper.SetInputConnection( change.GetOutputPort() );

    // Create our transfer function
    vtkColorTransferFunction colorFun = new vtkColorTransferFunction();
    vtkPiecewiseFunction opacityFun = new vtkPiecewiseFunction();

    // Create the property and attach the transfer functions
    vtkVolumeProperty property = new vtkVolumeProperty();
    property.IndependentComponentsOn();
    property.SetColor( colorFun );

```

```

property.SetScalarOpacity( opacityFun );
property.SetInterpolationTypeToLinear();

// connect up the volume to the property and the mapper
volume.SetProperty( property );
volume.SetMapper( mapper );

vtkMedicalImageProperties medprop = reader.GetMedicalImageProperties();
int n = medprop.GetNumberOfWindowLevelPresets();
double opacityWindow = 4096;
double opacityLevel = 2048;

// Override default with value from DICOM files:
for( int i = 0; i < n; ++i )
{
    double wl[] = medprop.GetNthWindowLevelPreset(i);
    //System.out.println( "W/L: " + wl[0] + " " + wl[1] );
    opacityWindow = wl[0];
    opacityLevel = wl[1];
}

colorFun.AddRGBSegment(0.0, 1.0, 1.0, 1.0, 255.0, 1.0, 1.0, 1.0 );
opacityFun.AddSegment( opacityLevel - 0.5*opacityWindow, 0.0,
    opacityLevel + 0.5*opacityWindow, 1.0 );
mapper.SetBlendModeToMaximumIntensity();

// Create the RenderWindow, Renderer
vtkRenderer ren1 = new vtkRenderer();
vtkRenderWindow renWin = new vtkRenderWindow();
renWin.AddRenderer(ren1);

// Set the default window size
renWin.SetSize(600,600);

// Add the volume to the scene
ren1.AddVolume( volume );
ren1.ResetCamera();

iren.SetRenderWindow( renWin );

// interact with data
renWin.Render();

iren.Start();
}
}

```

12.171 MPRViewer.java

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
import vtk.*;
import gdcm.*;
import java.io.File;

/*
 * Compilation:
 * CLASSPATH=vtkgdcm.jar:/usr/share/java/vtk.jar javac MPRViewer.java
 *
 * Usage:
 * LD_LIBRARY_PATH=/usr/lib/jvm/java-6-openjdk/jre/lib/amd64/xawt:/usr/lib/jni:.
 * CLASSPATH=/usr/share/java/vtk.jar:vtkgdcm.jar:gdcm.jar:. java MPRViewer BRAINX
 *
 */
public class MPRViewer

```

```

{
    static {
        // VTK
        System.loadLibrary("vtkCommonJava");
        System.loadLibrary("vtkFilteringJava");
        System.loadLibrary("vtkIOJava");
        System.loadLibrary("vtkImagingJava");
        System.loadLibrary("vtkGraphicsJava");
        System.loadLibrary("vtkRenderingJava");
        // VTK-GDCM
        System.loadLibrary("vtkgdcmlJava");
    }

    static FilenamesType fns = new FilenamesType();

    public static void process(String path)
    {
        fns.add( path );
    }

    // Process only files under dir
    public static void visitAllFiles(File dir)
    {
        if (dir.isDirectory())
        {
            String[] children = dir.list();
            for (int i=0; i<children.length; i++)
            {
                visitAllFiles(new File(dir, children[i]));
            }
        }
        else
        {
            process(dir.getPath());
        }
    }

    public static void main(String[] args) throws Exception
    {
        String dirname = args[0];
        if( !PosixEmulation.FileIsDirectory( dirname ) )
        {
            return;
        }

        File dir = new File(dirname);
        visitAllFiles(dir);

        IPPSorter ipp = new IPPSorter();
        ipp.SetComputeZSpacing( true );
        ipp.SetZSpacingTolerance( 1e-3 );
        boolean b = ipp.Sort( fns );
        if(!b)
        {
            throw new Exception("Could not scan");
        }
        double ippzspacing = ipp.GetZSpacing();

        FilenamesType sorted = ipp.GetFilenames();
        vtkStringArray files = new vtkStringArray();
        long nfiles = sorted.size();
        //for( String f : sorted )
        for (int i = 0; i < nfiles; i++) {
            String f = sorted.get(i);
            files.InsertNextValue( f );
        }
        vtkGDCMImageReader reader = new vtkGDCMImageReader();
        reader.SetFileNames( files );
        reader.Update(); // get spacing value

        double[] spacing = reader.GetOutput().GetSpacing();

        vtkImageChangeInformation change = new vtkImageChangeInformation();
        change.SetInputConnection( reader.GetOutputPort() );
        change.SetOutputSpacing( spacing[0], spacing[1], ippzspacing );

        // A simple vtkInteractorStyleImage example for
        // 3D image viewing with the vtkImageResliceMapper.
        //
        // Drag Left mouse button to window/level
        // Shift-Left drag to rotate (oblique slice)
    }
}

```

```

// Shift-Middle drag to slice through image
// OR Ctrl-Right drag to slice through image

// Create the RenderWindow, Renderer
vtkRenderer ren1 = new vtkRenderer();
vtkRenderWindow renWin = new vtkRenderWindow();
renWin.AddRenderer(ren1);

vtkImageResliceMapper im = new vtkImageResliceMapper();
im.SetInputConnection(change.GetOutputPort());
im.SliceFacesCameraOn();
im.SliceAtFocalPointOn();
im.BorderOff();

vtkImageProperty ip = new vtkImageProperty();
ip.SetColorWindow(2000);
ip.SetColorLevel(1000);
ip.SetAmbient(0.0);
ip.SetDiffuse(1.0);
ip.SetOpacity(1.0);
ip.SetInterpolationTypeToLinear();

vtkImageSlice ia = new vtkImageSlice();
ia.SetMapper(im);
ia.SetProperty(ip);

ren1.AddViewProp(ia);
ren1.SetBackground(0.1, 0.2, 0.4);
renWin.SetSize(300, 300);

vtkRenderWindowInteractor iren = new vtkRenderWindowInteractor();
vtkInteractorStyleImage style = new vtkInteractorStyleImage();
style.SetInteractionModeToImage3D();
iren.SetInteractorStyle(style);
renWin.SetInteractor(iren);

// render the image
renWin.Render();
vtkCamera cam1 = ren1.GetActiveCamera();
cam1.ParallelProjectionOn();
ren1.ResetCameraClippingRange();
renWin.Render();

iren.Start();
}
}

```

12.172 MPRViewer2.java

```

/*=====
Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.
See Copyright.txt or http://gdcm.sourceforge.net/Copyright.html for details.

This software is distributed WITHOUT ANY WARRANTY; without even
the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the above copyright notice for more information.

=====*/
import vtk.*;
import gdcm.*;
import java.io.File;

/*
 * Compilation:
 * CLASSPATH=vtkgdcm.jar:/usr/share/java/vtk.jar javac MPRViewer2.java
 *
 * Usage:
 * LD_LIBRARY_PATH=/usr/lib/jvm/java-6-openjdk/jre/lib/amd64/xawt:/usr/lib/jni:.
 * CLASSPATH=/usr/share/java/vtk.jar:vtkgdcm.jar:gdcm.jar:. java MPRViewer2 BRAINX
 *
 */
public class MPRViewer2

```

```

{
    static {
        // VTK
        System.loadLibrary("vtkCommonJava");
        System.loadLibrary("vtkFilteringJava");
        System.loadLibrary("vtkIOJava");
        System.loadLibrary("vtkImagingJava");
        System.loadLibrary("vtkGraphicsJava");
        System.loadLibrary("vtkRenderingJava");
        System.loadLibrary("vtkHybridJava");
        System.loadLibrary("vtkWidgetsJava");
        // VTK-GDCM
        System.loadLibrary("vtkgdcmlib");
    }

    static FileNamesType fns = new FileNamesType();

    public static void process(String path)
    {
        fns.add( path );
    }

    // Process only files under dir
    public static void visitAllFiles(File dir)
    {
        if (dir.isDirectory())
        {
            String[] children = dir.list();
            for (int i=0; i<children.length; i++)
            {
                visitAllFiles(new File(dir, children[i]));
            }
        }
        else
        {
            process(dir.getPath());
        }
    }

    public void dointer(vtkImagePlaneWidget current_widget)
    {
        int cstat = current_widget.GetCursorDataStatus();
        double[] v = current_widget.GetCurrentCursorPosition();
        //System.out.println( cstat );
        //System.out.println( v[0] );
        //System.out.println( v[1] );
        //System.out.println( v[2] );
        planeWidgetX.SetSliceIndex( (int)v[0] );
        planeWidgetY.SetSliceIndex( (int)v[1] );
        planeWidgetZ.SetSliceIndex( (int)v[2] );
        planeWidgetX.GetCurrentRenderer().ResetCameraClippingRange();
        planeWidgetY.GetCurrentRenderer().ResetCameraClippingRange();
        planeWidgetZ.GetCurrentRenderer().ResetCameraClippingRange();
    }

    public void startinterX()
    {
        dointer( planeWidgetX );
    }

    public void interX()
    {
        dointer( planeWidgetX );
    }

    public void endinterX()
    {
    }

    public void startinterY()
    {
        dointer( planeWidgetY );
    }

    public void interY()
    {
        dointer( planeWidgetY );
    }

    public void endinterY()
    {
    }

    public void startinterZ()
    {
        dointer( planeWidgetZ );
    }

    public void interZ()

```

```

    {
        dointer( planeWidgetZ );
    }
public void endinterZ()
{
    //System.out.println( "endinter" );
}

public static void AlignCamera(int slice_number, vtkImagePlaneWidget current_widget)
{
    vtkImageData image = (vtkImageData)current_widget.GetInput();
    vtkRenderer ren = current_widget.GetCurrentRenderer();
    double[] origin = image.GetOrigin();
    double ox = origin[0];
    double oy = origin[1];
    double oz = origin[2];

    int dims[] = image.GetDimensions();
    int xmin = 0;
    int xmax = 1;
    int ymin = 2;
    int ymax = dims[0]-1;
    int zmin = dims[1]-1;
    int zmax = dims[2]-1;

    double[] spacing = image.GetSpacing();
    double sx = spacing[0];
    double sy = spacing[1];
    double sz = spacing[2];

    double cx = ox+(0.5*(xmax-xmin))*sx;
    double cy = oy+(0.5*(ymax-ymin))*sy;
    double cz = oz+(0.5*(zmax-zmin))*sz;
    double vx = 0, vy = 0, vz = 0;
    double nx = 0, ny = 0, nz = 0;
    int iaxis = current_widget.GetPlaneOrientation();
    if ( iaxis == 0 ) {
        vz = -1;
        nx = ox + xmax*sx;
        cx = ox + slice_number*sx;
    }
    else if ( iaxis == 1 ) {
        vz = -1;
        ny = oy+ymax*sy;
        cy = oy+slice_number*sy;
    }
    else {
        vy = 1;
        nz = oz+zmax*sz;
        cz = oz+slice_number*sz;
    }
    double px = cx+nx*2;
    double py = cy+ny*2;
    double pz = cz+nz*3;

    vtkCamera camera = ren.GetActiveCamera();
    camera.SetViewUp(vx, vy, vz);
    camera.SetFocalPoint(cx, cy, cz);
    camera.SetPosition(px, py, pz);
    camera.OrthogonalizeViewUp();
    ren.ResetCameraClippingRange();
}

private vtkImagePlaneWidget planeWidgetX = new vtkImagePlaneWidget();
private vtkImagePlaneWidget planeWidgetY = new vtkImagePlaneWidget();
private vtkImagePlaneWidget planeWidgetZ = new vtkImagePlaneWidget();

public void config()
{
    //System.out.println( "config" );
    planeWidgetX.GetCurrentRenderer().ResetCamera();
    planeWidgetY.GetCurrentRenderer().ResetCamera();
    planeWidgetZ.GetCurrentRenderer().ResetCamera();
}

public void Run(String dirname)
{
    File dir = new File(dirname);
    visitAllFiles(dir);

    IPPSorter ipp = new IPPSorter();

```

```

ipp.SetComputeZSpacing( true );
ipp.SetZSpacingTolerance( 1e-3 );
boolean b = ipp.Sort( fns );
if(!b)
{
    //throw new Exception("Could not scan");
}
double ippzspacing = ipp.GetZSpacing();

FileNamesType sorted = ipp.GetFileNames();
vtkStringArray files = new vtkStringArray();
long nfiles = sorted.size();
//for( String f : sorted )
for (int i = 0; i < nfiles; i++) {
    String f = sorted.get(i);
    files.InsertNextValue( f );
}
vtkGDCMImageReader reader = new vtkGDCMImageReader();
reader.SetFileNames( files );
reader.Update(); // get spacing value

double[] spacing = reader.GetOutput().GetSpacing();

vtkImageChangeInformation change = new vtkImageChangeInformation();
change.SetInputConnection( reader.GetOutputPort() );
change.SetOutputSpacing( spacing[0], spacing[1], ippzspacing );
change.Update();

System.out.println( change.GetOutput().toString() );

vtkRenderer ren1 = new vtkRenderer();
ren1.SetViewport(0., 0., 0.333, 1);
ren1.SetBackground(0.1,0.2,0.4);
vtkRenderer ren2 = new vtkRenderer();
ren2.SetViewport(0.333, 0., 0.667, 1);
ren2.SetBackground(0.1,0.2,0.4);
vtkRenderer ren3 = new vtkRenderer();
ren3.SetViewport(0.667, 0., 1., 1.);
ren3.SetBackground(0.1,0.2,0.4);

vtkRenderWindow renWin = new vtkRenderWindow();
renWin.AddRenderer(ren1);
renWin.AddRenderer(ren2);
renWin.AddRenderer(ren3);

vtkRenderWindowInteractor iren = new vtkRenderWindowInteractor();
iren.SetRenderWindow(renWin);

vtkInteractorStyleImage style = new vtkInteractorStyleImage();
iren.SetInteractorStyle( style );

vtkCellPicker picker = new vtkCellPicker();
picker.SetTolerance(0.005);

vtkProperty ipwProp = new vtkProperty();

//vtkImagePlaneWidget planeWidgetX = new vtkImagePlaneWidget();
planeWidgetX.SetInteractor(iren);
planeWidgetX.SetCurrentRenderer(ren1);
planeWidgetX.SetDefaultRenderer(ren1);
planeWidgetX.RestrictPlaneToVolumeOn();
planeWidgetX.SetTexturePlaneProperty(ipwProp);
//planeWidgetX.GetPlaneProperty().SetColor(1,0,0);
//planeWidgetX.TextureInterpolateOff();
//planeWidgetX.SetResliceInterpolateToNearestNeighbour();
planeWidgetX.SetInputConnection(change.GetOutputPort());
planeWidgetX.SetPlaneOrientationToXAxes();
planeWidgetX.SetSliceIndex(62);
planeWidgetX.SetPicker(picker);
planeWidgetX.SetKeyPressActivationValue('x');
planeWidgetX.On();
planeWidgetX.InteractionOn();

//vtkImagePlaneWidget planeWidgetY = new vtkImagePlaneWidget();
planeWidgetY.SetInteractor(iren);
planeWidgetY.SetCurrentRenderer(ren2);
planeWidgetY.SetDefaultRenderer(ren2);
planeWidgetY.RestrictPlaneToVolumeOn();
planeWidgetY.SetTexturePlaneProperty(ipwProp);
//planeWidgetY.GetPlaneProperty().SetColor(1,0,0);
//planeWidgetY.TextureInterpolateOff();

```



```

//planeWidgetY.SetResliceInterpolateToNearestNeighbour();
planeWidgetY.SetInputConnection(change.GetOutputPort());
planeWidgetY.SetLookupTable( planeWidgetX.GetLookupTable() );
planeWidgetY.SetPlaneOrientationToYAxes();
planeWidgetY.SetSliceIndex(32);
planeWidgetY.SetPicker(picker);
planeWidgetY.SetKeyPressActivationValue('y');
planeWidgetY.On();

//vtkImagePlaneWidget planeWidgetZ = new vtkImagePlaneWidget();
planeWidgetZ.SetInteractor(iren);
planeWidgetZ.SetCurrentRenderer(ren3);
planeWidgetZ.SetDefaultRenderer(ren3);
planeWidgetZ.RestrictPlaneToVolumeOn();
planeWidgetZ.SetTexturePlaneProperty(ipwProp);
//planeWidgetZ.GetPlaneProperty().SetColor(1,0,0);
//planeWidgetZ.TextureInterpolateOff();
//planeWidgetZ.SetResliceInterpolateToNearestNeighbour();
planeWidgetZ.SetInputConnection(change.GetOutputPort());
planeWidgetZ.SetLookupTable( planeWidgetX.GetLookupTable() );
planeWidgetZ.SetPlaneOrientationToZAxes();
planeWidgetZ.SetSliceIndex(32);
planeWidgetZ.SetPicker(picker);
planeWidgetZ.SetKeyPressActivationValue('z');
planeWidgetZ.On();

iren.Initialize();

renWin.Render();
AlignCamera(52, planeWidgetX);
AlignCamera(32, planeWidgetY);
AlignCamera(32, planeWidgetZ);

planeWidgetX.GetCurrentRenderer().ResetCamera();
planeWidgetY.GetCurrentRenderer().ResetCamera();
planeWidgetZ.GetCurrentRenderer().ResetCamera();

renWin.Render();

planeWidgetX.AddObserver("StartInteractionEvent", this,"startinterX");
planeWidgetX.AddObserver("InteractionEvent", this,"interX");
planeWidgetX.AddObserver("EndInteractionEvent", this,"endinterX");
planeWidgetY.AddObserver("StartInteractionEvent", this,"startinterY");
planeWidgetY.AddObserver("InteractionEvent", this,"interY");
planeWidgetY.AddObserver("EndInteractionEvent", this,"endinterY");
planeWidgetZ.AddObserver("StartInteractionEvent", this,"startinterZ");
planeWidgetZ.AddObserver("InteractionEvent", this,"interZ");
planeWidgetZ.AddObserver("EndInteractionEvent", this,"endinterZ");

iren.AddObserver("ConfigureEvent", this,"config");

iren.Start();
}

public static void main(String[] args) throws Exception
{
    String dirname = args[0];
    if( !PosixEmulation.FileIsDirectory( dirname ) )
    {
        return;
    }

    MPRViewer2 me = new MPRViewer2();
    me.Run( dirname );
}
}

```

12.173 ReadSeriesIntoVTK.java

```

/*=====

Program: GDCM (Grassroots DICOM). A DICOM library

Copyright (c) 2006-2011 Mathieu Malaterre
All rights reserved.

```

See Copyright.txt or <http://gdcm.sourceforge.net/Copyright.html> for details.

This software is distributed WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the above copyright notice for more information.

```

=====*/
// We are required to call the package 'vtk' even though I (MM) would have preferred
// an import statement along the line of:
// import vtkgdcm.*;
import vtk.*;

/*
 * Usage:
 * export LD_LIBRARY_PATH=/usr/lib/jvm/java-6-openjdk/jre/lib/amd64/xawt:.
 * java -classpath `pwd`/vtkgdcm.jar:/usr/share/java/vtk.jar:. ReadSeriesIntoVTK
 */
public class ReadSeriesIntoVTK
{
    static {
        System.loadLibrary("vtkCommonJava");
        System.loadLibrary("vtkFilteringJava");
        System.loadLibrary("vtkIOJava");
        System.loadLibrary("vtkImagingJava");
        System.loadLibrary("vtkGraphicsJava");
        System.loadLibrary("vtkgdcmJava");
        try {
            System.loadLibrary("vtkRenderingJava");
        } catch (Throwable e) {
            System.out.println("cannot load vtkHybrid, skipping...");
        }
        try {
            System.loadLibrary("vtkHybridJava");
        } catch (Throwable e) {
            System.out.println("cannot load vtkHybrid, skipping...");
        }
        try {
            System.loadLibrary("vtkVolumeRenderingJava");
        } catch (Throwable e) {
            System.out.println("cannot load vtkVolumeRendering, skipping...");
        }
    }

    public static void main(String[] args)
    {
        vtkFileOutputWindow outWin = new vtkFileOutputWindow();
        outWin.SetInstance(outWin);
        outWin.SetFileName("MVSVTKViewer.log");

        // See: http://review.source.kitware.com/#change,888
        // vtkWrapJava does not handle static keyword
        // String directory = vtkGDCMTesting.GetGDCMDataRoot();
        vtkGDCMTesting t = new vtkGDCMTesting();
        String directory = t.GetGDCMDataRoot();
        String file0 = directory + "/SIEMENS_MAGNETOM-12-MONO2-FileSeq0.dcm";
        String file1 = directory + "/SIEMENS_MAGNETOM-12-MONO2-FileSeq1.dcm";
        String file2 = directory + "/SIEMENS_MAGNETOM-12-MONO2-FileSeq2.dcm";
        String file3 = directory + "/SIEMENS_MAGNETOM-12-MONO2-FileSeq3.dcm";

        vtkStringArray s = new vtkStringArray();
        System.out.println("adding : " + file0 );
        s.InsertNextValue( file0 );
        s.InsertNextValue( file1 );
        s.InsertNextValue( file2 );
        s.InsertNextValue( file3 );

        vtkGDCMImageReader reader = new vtkGDCMImageReader();
        reader.SetFileNames( s );
        reader.Update();

        System.out.println("Success reading: " + file0 );

        vtkMetaImageWriter writer = new vtkMetaImageWriter();
        writer.DebugOn();
        writer.SetCompression( false );
        writer.SetInputConnection( reader.GetOutputPort() );
        writer.SetFileName( "ReadSeriesIntoVTK.mhd" );
        writer.Write();

        System.out.println("Success writing: " + writer.GetFileName() );
    }
}

```

```
}

```

12.174 CastConvertPhilips.py

```
00001
00014
00015 """
00016 Usage:
00017
00018 python --public /path/to/directory/
00019 or
00020 python --private /path/to/directory/
00021
00022 python --public --extension bak /path/to/directory/
00023
00024 rename -f 's/\.bak$//' *.bak
00025
00026 TODO:
00027 http://docs.python.org/library/optparse.html#module-optparse
00028 """
00029
00030 import vtkgdcmm
00031 import vtk
00032 import sys
00033 import gdcmm
00034
00035 def ProcessOneFilePublic(filename, outfilename, tmpfile):
00036     gdcmm.ImageHelper.SetForceRescaleInterceptSlope(True)
00037     vtkreader = vtkgdcmm.vtkGDCMImageReader()
00038     vtkreader.SetFileName( filename )
00039     vtkreader.Update()
00040
00041     cast = vtk.vtkImageCast()
00042     cast.SetInput( vtkreader.GetOutput() )
00043     cast.SetOutputScalarTypeToUnsignedShort()
00044
00045     # vtkGDCMImageWriter does not support Sequence, so let's write a tmp file first:
00046     # Some operation will actually be discarded (we simply need a temp storage)
00047     vtkwriter = vtkgdcmm.vtkGDCMImageWriter()
00048     vtkwriter.SetFileName( tmpfile )
00049     vtkwriter.SetMedicalImageProperties( vtkreader.GetMedicalImageProperties() )
00050     vtkwriter.SetDirectionCosines( vtkreader.GetDirectionCosines() )
00051     print "Format:", vtkreader.GetImageFormat()
00052     vtkwriter.SetImageFormat( vtkreader.GetImageFormat() )
00053     vtkwriter.SetInput( cast.GetOutput() )
00054     #vtkwriter.Update()
00055     vtkwriter.Write()
00056
00057     # ok now rewrite the exact same file as the original (keep all info)
00058     # but use the Pixel Data Element from the written file
00059     tmpreader = gdcmm.ImageReader()
00060     tmpreader.SetFileName( tmpfile )
00061     if not tmpreader.Read():
00062         sys.exit(1)
00063
00064     reader = gdcmm.Reader()
00065     reader.SetFileName( filename )
00066     if not reader.Read():
00067         sys.exit(1)
00068
00069     # Make sure to remove Slope/Rescale to avoid re-execution
00070     ds = reader.GetFile().GetDataSet()
00071     tags = [
00072         gdcmm.Tag(0x0028,0x1052),
00073         gdcmm.Tag(0x0028,0x1053),
00074         gdcmm.Tag(0x0028,0x1053),
00075     ]
00076     for tag in tags:
00077         ds.Remove( tag )
00078
00079     writer = gdcmm.ImageWriter()
00080     writer.SetFileName( outfilename )
00081     # Pass image from vtk written file
00082     writer.SetImage( tmpreader.GetImage() )
00083     # pass dataset from initial 'reader'
00084     writer.SetFile( reader.GetFile() )
```

```

00085     if not writer.Write():
00086         sys.exit(1)
00087
00088 def ProcessOneFilePrivate(filename, outfilename, tmpfile):
00089     vtkreader = vtkgdcmm.vtkGDCMImageReader()
00090     vtkreader.SetFileName( filename )
00091     vtkreader.Update()
00092
00093
00094     # (2005,1409)      DS      4      0.0
00095     # (2005,140a)      DS      16     1.52283272283272
00096
00097     # (2005,0014)      LO      26     Philips MR Imaging DD 005
00098     tag1 = gdcmm.PrivateTag(0x2005,0x09,"Philips MR Imaging DD 005")
00099     tag2 = gdcmm.PrivateTag(0x2005,0x0a,"Philips MR Imaging DD 005")
00100
00101
00102
00103     # Need to access some private tags, reread the file (for now):
00104     reader = gdcmm.Reader()
00105     reader.SetFileName( filename )
00106     if not reader.Read():
00107         sys.exit(1)
00108
00109     ds = reader.GetFile().GetDataSet()
00110
00111     e11 = ds.GetDataElement( tag1 )
00112     e12 = ds.GetDataElement( tag2 )
00113
00114
00115     #pf = gdcmm.PythonFilter()
00116     #pf.SetFile( reader.GetFile() )
00117     #print e11.GetTag()
00118
00119     print e11.GetByteValue()
00120     v1 = eval(e11.GetByteValue().GetBuffer())
00121     print e12.GetByteValue()
00122     v2 = eval(e12.GetByteValue().GetBuffer())
00123
00124     print v1
00125     shift = v1
00126     print v2
00127     scale = v2
00128
00129     ss = vtk.vtkImageShiftScale()
00130     ss.SetInput( vtkreader.GetOutput() )
00131     # because VTK image shift / scale convention is inverted from DICOM make sure shift is 0
00132     assert shift == 0
00133     ss.SetShift( shift )
00134     ss.SetScale( scale )
00135     ss.SetOutputScalarTypeToUnsignedShort()
00136     ss.Update()
00137
00138     # vtkGDCMImageWriter does not support Sequence, so let's write a tmp file first:
00139     # Some operation will actually be discarded (we simply need a temp storage)
00140     vtkwriter = vtkgdcmm.vtkGDCMImageWriter()
00141     vtkwriter.SetFileName( tmpfile )
00142     vtkwriter.SetMedicalImageProperties( vtkreader.GetMedicalImageProperties() )
00143     vtkwriter.SetDirectionCosines( vtkreader.GetDirectionCosines() )
00144     vtkwriter.SetImageFormat( reader.GetImageFormat() )
00145     # do not pass shift/scale again
00146     vtkwriter.SetInput( ss.GetOutput() )
00147     #vtkwriter.Update()
00148     vtkwriter.Write()
00149
00150     # ok now rewrite the exact same file as the original (keep all info)
00151     # but use the Pixel Data Element from the written file
00152     tmpreader = gdcmm.ImageReader()
00153     tmpreader.SetFileName( tmpfile )
00154     if not tmpreader.Read():
00155         sys.exit(1)
00156
00157     writer = gdcmm.ImageWriter()
00158     writer.SetFileName( outfilename )
00159     # Pass image from vtk written file
00160     writer.SetImage( tmpreader.GetImage() )
00161     # pass dataset from initial 'reader'
00162     writer.SetFile( reader.GetFile() )
00163     if not writer.Write():
00164         sys.exit(1)
00165

```

```
00166 if __name__ == "__main__":
00167
00168     gdcm.Trace.DebugOff()
00169     gdcm.Trace.WarningOff()
00170     #filename = sys.argv[1]
00171     #outfilename = sys.argv[2]
00172     tmpfile = "/tmp/philips_rescaled.dcm"
00173     #ProcessOneFile( filename, outfilename, tmpfile )
00174     rescaletype = sys.argv[1]
00175     assert rescaletype == "--public" or rescaletype == "--private"
00176     dirname = sys.argv[2]
00177     d = gdcm.Directory()
00178     d.Load( dirname )
00179
00180     for f in d.GetFileNames():
00181         #print f
00182         ProcessOneFilePublic( f, f + ".bak", tmpfile )
00183
00184
00185 print "success"
```

12.175 headsq2dcm.py

```
00001
00014
00015 """
00016 Usage:
00017 python headsq2dcm.py -D /path/to/VTKData
00018 """
00019
00020 import vtk
00021 import vtkgdc
00022 from vtk.util.misc import vtkGetDataRoot
00023 VTK_DATA_ROOT = vtkGetDataRoot()
00024
00025 reader = vtk.vtkVolume16Reader()
00026 reader.SetDataDimensions(64, 64)
00027 reader.SetDataByteOrderToLittleEndian()
00028 reader.SetFilePrefix(VTK_DATA_ROOT + "/Data/headsq/quarter")
00029 reader.SetImageRange(1, 93)
00030 reader.SetDataSpacing(3.2, 3.2, 1.5)
00031
00032 cast = vtk.vtkImageCast()
00033 cast.SetInput( reader.GetOutput() )
00034 cast.SetOutputScalarTypeToUnsignedChar()
00035
00036 # By default this is creating a Multiframe Grayscale Word Secondary Capture Image Storage
00037 writer = vtkgdc.vtkGDCMImageWriter()
00038 writer.SetFileName( "headsq.dcm" )
00039 writer.SetInput( reader.GetOutput() )
00040 # cast -> Multiframe Grayscale Byte Secondary Capture Image Storage
00041 #writer.SetInput( cast.GetOutput() )
00042 writer.SetFileDimensionality( 3 )
00043 writer.Write()
```


Index

- ~ASN1
 - gdcm::ASN1, [127](#)
- ~AnonymizeEvent
 - gdcm::AnonymizeEvent, [105](#)
- ~Anonymizer
 - gdcm::Anonymizer, [110](#)
- ~Attribute
 - gdcm::Attribute< Group, Element, TVR, VM::VM1_n
>, [161](#)
- ~AudioCodec
 - gdcm::AudioCodec, [192](#)
- ~BaseCompositeMessage
 - gdcm::network::BaseCompositeMessage, [197](#)
- ~BaseNormalizedMessage
 - gdcm::network::BaseNormalizedMessage, [199](#)
- ~BasePDU
 - gdcm::network::BasePDU, [201](#)
- ~BaseQuery
 - gdcm::BaseQuery, [204](#)
- ~BaseRootQuery
 - gdcm::BaseRootQuery, [209](#)
- ~Bitmap
 - gdcm::Bitmap, [223](#)
- ~BitmapToBitmapFilter
 - gdcm::BitmapToBitmapFilter, [236](#)
- ~BoxRegion
 - gdcm::BoxRegion, [239](#)
- ~ByteSwapFilter
 - gdcm::ByteSwapFilter, [245](#)
- ~ByteValue
 - gdcm::ByteValue, [249](#)
- ~CAPICryptographicMessageSyntax
 - gdcm::CAPICryptographicMessageSyntax, [258](#)
- ~CSAHeader
 - gdcm::CSAHeader, [321](#)
- ~Cleaner
 - gdcm::Cleaner, [271](#)
- ~Coder
 - gdcm::Coder, [282](#)
- ~Command
 - gdcm::Command, [289](#)
- ~CommandDataSet
 - gdcm::CommandDataSet, [293](#)
- ~CryptoFactory
 - gdcm::CryptoFactory, [307](#)
- ~CryptographicMessageSyntax
 - gdcm::CryptographicMessageSyntax, [309](#)
- ~Curve
 - gdcm::Curve, [336](#)
- ~DICOMDIRGenerator
 - gdcm::DICOMDIRGenerator, [388](#)
- ~DPath
 - gdcm::DPath, [422](#)
- ~DataEvent
 - gdcm::DataEvent, [356](#)
- ~DataSetEvent
 - gdcm::DataSetEvent, [373](#)
- ~Decoder
 - gdcm::Decoder, [376](#)
- ~Defs
 - gdcm::Defs, [379](#)
- ~DeltaEncodingCodec
 - gdcm::DeltaEncodingCodec, [385](#)
- ~DictConverter
 - gdcm::DictConverter, [396](#)
- ~DictPrinter
 - gdcm::DictPrinter, [405](#)
- ~Dicts
 - gdcm::Dicts, [407](#)
- ~DirectionCosines
 - gdcm::DirectionCosines, [413](#)
- ~Directory
 - gdcm::Directory, [416](#)
- ~Dumper
 - gdcm::Dumper, [426](#)
- ~EmptyMaskGenerator
 - gdcm::EmptyMaskGenerator, [471](#)
- ~Event
 - gdcm::Event, [483](#)
- ~Exception
 - gdcm::Exception, [486](#)
- ~File
 - gdcm::File, [499](#)
- ~FileAnonymizer
 - gdcm::FileAnonymizer, [504](#)
- ~FileChangeTransferSyntax
 - gdcm::FileChangeTransferSyntax, [508](#)
- ~FileDecompressLookupTable
 - gdcm::FileDecompressLookupTable, [512](#)
- ~FileDerivation

- gdcmm::FileDerivation, 514
- ~FileExplicitFilter
 - gdcmm::FileExplicitFilter, 518
- ~FileMetaInformation
 - gdcmm::FileMetaInformation, 524
- ~FileNameEvent
 - gdcmm::FileNameEvent, 535
- ~FileStreamer
 - gdcmm::FileStreamer, 545
- ~FilenameGenerator
 - gdcmm::FilenameGenerator, 538
- ~Global
 - gdcmm::Global, 565
- ~GroupDict
 - gdcmm::GroupDict, 568
- ~IconImageFilter
 - gdcmm::IconImageFilter, 571
- ~IconImageGenerator
 - gdcmm::IconImageGenerator, 574
- ~Image
 - gdcmm::Image, 582
- ~ImageApplyLookupTable
 - gdcmm::ImageApplyLookupTable, 588
- ~ImageChangePhotometricInterpretation
 - gdcmm::ImageChangePhotometricInterpretation, 592
- ~ImageChangePlanarConfiguration
 - gdcmm::ImageChangePlanarConfiguration, 597
- ~ImageChangeTransferSyntax
 - gdcmm::ImageChangeTransferSyntax, 602
- ~ImageCodec
 - gdcmm::ImageCodec, 608
- ~ImageConverter
 - gdcmm::ImageConverter, 618
- ~ImageFragmentSplitter
 - gdcmm::ImageFragmentSplitter, 621
- ~ImageReader
 - gdcmm::ImageReader, 632
- ~ImageRegionReader
 - gdcmm::ImageRegionReader, 637
- ~ImageToImageFilter
 - gdcmm::ImageToImageFilter, 641
- ~ImageWriter
 - gdcmm::ImageWriter, 645
- ~JPEG12Codec
 - gdcmm::JPEG12Codec, 681
- ~JPEG16Codec
 - gdcmm::JPEG16Codec, 686
- ~JPEG2000Codec
 - gdcmm::JPEG2000Codec, 690
- ~JPEG8Codec
 - gdcmm::JPEG8Codec, 699
- ~JPEGCodec
 - gdcmm::JPEGCodec, 704
- ~JPEGLSCodec
 - gdcmm::JPEGLSCodec, 712
- ~JSON
 - gdcmm::JSON, 717
- ~KAKADUCodec
 - gdcmm::KAKADUCodec, 721
- ~LookupTable
 - gdcmm::LookupTable, 728
- ~MemberCommand
 - gdcmm::MemberCommand< T >, 757
- ~MeshPrimitive
 - gdcmm::MeshPrimitive, 763
- ~ModuleEntry
 - gdcmm::ModuleEntry, 779
- ~MrProtocol
 - gdcmm::MrProtocol, 792
- ~Object
 - gdcmm::Object, 821
- ~OpenSSLCryptographicMessageSyntax
 - gdcmm::OpenSSLCryptographicMessageSyntax, 827
- ~OpenSSL7CryptographicMessageSyntax
 - gdcmm::OpenSSL7CryptographicMessageSyntax, 832
- ~Orientation
 - gdcmm::Orientation, 835
- ~Overlay
 - gdcmm::Overlay, 840
- ~PDBHeader
 - gdcmm::PDBHeader, 860
- ~PDFCodec
 - gdcmm::PDFCodec, 863
- ~PGXCodec
 - gdcmm::PGXCodec, 873
- ~PNMCodec
 - gdcmm::PNMCodec, 909
- ~PVRGCodec
 - gdcmm::PVRGCodec, 950
- ~ParseException
 - gdcmm::ParseException, 848
- ~Parser
 - gdcmm::Parser, 851
- ~Pixmap
 - gdcmm::Pixmap, 891
- ~PixmapReader
 - gdcmm::PixmapReader, 897
- ~PixmapToPixmapFilter
 - gdcmm::PixmapToPixmapFilter, 900
- ~PixmapWriter
 - gdcmm::PixmapWriter, 904
- ~Preamble
 - gdcmm::Preamble, 912
- ~Printer
 - gdcmm::Printer, 933
- ~PrivateDict
 - gdcmm::PrivateDict, 936

- ~ProgressEvent
 - gdcm::ProgressEvent, [945](#)
- ~PythonFilter
 - gdcm::PythonFilter, [952](#)
- ~QueryBase
 - gdcm::QueryBase, [954](#)
- ~RAWCodec
 - gdcm::RAWCodec, [970](#)
- ~RLECodec
 - gdcm::RLECodec, [990](#)
- ~Reader
 - gdcm::Reader, [975](#)
- ~Region
 - gdcm::Region, [981](#)
- ~Rescaler
 - gdcm::Rescaler, [984](#)
- ~SHA1
 - gdcm::SHA1, [1071](#)
- ~Scanner
 - gdcm::Scanner, [1000](#)
- ~Scanner2
 - gdcm::Scanner2, [1010](#)
- ~Segment
 - gdcm::Segment, [1019](#)
- ~SegmentReader
 - gdcm::SegmentReader, [1031](#)
- ~SegmentWriter
 - gdcm::SegmentWriter, [1036](#)
- ~SegmentedPaletteColorLookupTable
 - gdcm::SegmentedPaletteColorLookupTable, [1027](#)
- ~SerieHelper
 - gdcm::SerieHelper, [1057](#)
- ~ServiceClassUser
 - gdcm::ServiceClassUser, [1065](#)
- ~SimpleMemberCommand
 - gdcm::SimpleMemberCommand< T >, [1075](#)
- ~SimpleSubjectWatcher
 - gdcm::SimpleSubjectWatcher, [1078](#)
- ~SmartPointer
 - gdcm::SmartPointer< ObjectType >, [1084](#)
- ~Sorter
 - gdcm::Sorter, [1091](#)
- ~Spacing
 - gdcm::Spacing, [1095](#)
- ~SplitMosaicFilter
 - gdcm::SplitMosaicFilter, [1098](#)
- ~StreamImageReader
 - gdcm::StreamImageReader, [1104](#)
- ~StreamImageWriter
 - gdcm::StreamImageWriter, [1109](#)
- ~StrictScanner
 - gdcm::StrictScanner, [1118](#)
- ~StrictScanner2
 - gdcm::StrictScanner2, [1128](#)
- ~StringFilter
 - gdcm::StringFilter, [1139](#)
- ~Subject
 - gdcm::Subject, [1144](#)
- ~Surface
 - gdcm::Surface, [1150](#)
- ~SurfaceReader
 - gdcm::SurfaceReader, [1165](#)
- ~SurfaceWriter
 - gdcm::SurfaceWriter, [1170](#)
- ~Table
 - gdcm::Table, [1184](#)
- ~TableEntry
 - gdcm::TableEntry, [1186](#)
- ~TableReader
 - gdcm::TableReader, [1187](#)
- ~TableRow
 - gdcm::network::TableRow, [1191](#)
- ~TagPath
 - gdcm::TagPath, [1202](#)
- ~Testing
 - gdcm::Testing, [1205](#)
- ~Trace
 - gdcm::Trace, [1212](#)
- ~Transition
 - gdcm::network::Transition, [1224](#)
- ~ULAction
 - gdcm::network::ULAction, [1269](#)
- ~ULBasicCallback
 - gdcm::network::ULBasicCallback, [1310](#)
- ~ULConnection
 - gdcm::network::ULConnection, [1312](#)
- ~ULConnectionCallback
 - gdcm::network::ULConnectionCallback, [1317](#)
- ~ULConnectionManager
 - gdcm::network::ULConnectionManager, [1323](#)
- ~ULEvent
 - gdcm::network::ULEvent, [1328](#)
- ~ULWritingCallback
 - gdcm::network::ULWritingCallback, [1332](#)
- ~UserInformation
 - gdcm::network::UserInformation, [1347](#)
- ~Validate
 - gdcm::Validate, [1350](#)
- ~Value
 - gdcm::Value, [1353](#)
- ~Version
 - gdcm::Version, [1357](#)
- ~Writer
 - gdcm::Writer, [1501](#)
- ~XMLDictReader
 - gdcm::XMLDictReader, [1505](#)
- ~XMLPrinter
 - gdcm::XMLPrinter, [1508](#)

- ~XMLPrivateDictReader
 - gdcm::XMLPrivateDictReader, [1512](#)
- ~vtkGDCMImageReader
 - vtkGDCMImageReader, [1386](#)
- ~vtkGDCMImageReader2
 - vtkGDCMImageReader2, [1401](#)
- ~vtkGDCMImageWriter
 - vtkGDCMImageWriter, [1415](#)
- ~vtkGDCMMedicalImageProperties
 - vtkGDCMMedicalImageProperties, [1422](#)
- ~vtkGDCMPolyDataReader
 - vtkGDCMPolyDataReader, [1426](#)
- ~vtkGDCMPolyDataWriter
 - vtkGDCMPolyDataWriter, [1431](#)
- ~vtkGDCMTesting
 - vtkGDCMTesting, [1435](#)
- ~vtkGDCMThreadedImageReader
 - vtkGDCMThreadedImageReader, [1440](#)
- ~vtkGDCMThreadedImageReader2
 - vtkGDCMThreadedImageReader2, [1444](#)
- ~vtkImageColorViewer
 - vtkImageColorViewer, [1453](#)
- ~vtkImageMapToColors16
 - vtkImageMapToColors16, [1464](#)
- ~vtkImageMapToWindowLevelColors2
 - vtkImageMapToWindowLevelColors2, [1470](#)
- ~vtkImagePlanarComponentsToComponents
 - vtkImagePlanarComponentsToComponents, [1473](#)
- ~vtkImageRGBToYBR
 - vtkImageRGBToYBR, [1476](#)
- ~vtkImageYBRToRGB
 - vtkImageYBRToRGB, [1478](#)
- ~vtkLookupTable16
 - vtkLookupTable16, [1480](#)
- ~vtkRTStructSetProperties
 - vtkRTStructSetProperties, [1485](#)
- AAAbortPDU
 - gdcm::network::AAAbortPDU, [86](#)
- AAAssociateACPDU
 - gdcm::network::AAAssociateACPDU, [89](#)
 - gdcm::network::AAAssociateRQPDU, [99](#)
- AAAssociateRJPDU
 - gdcm::network::AAAssociateRJPDU, [93](#)
- AAAssociateRQPDU
 - gdcm::network::AAAssociateACPDU, [91](#)
 - gdcm::network::AAAssociateRQPDU, [96](#)
- AbstractMultiDimensionalImageModel
 - gdcm::UIDs, [1256](#)
- AbstractSyntax
 - gdcm::network::AbstractSyntax, [101](#)
 - gdcm::PresentationContext, [918](#)
- AcquisitionContextSRStorage
 - gdcm::UIDs, [1255](#)
- ActiveComponent
 - vtkImageMapToColors16, [1467](#)
- Add
 - gdcm::GroupDict, [569](#)
- add1
 - gdcm, [63](#)
- AddAcceptedPresentationContext
 - gdcm::network::ULConnection, [1312](#)
- AddContourReferencedFrameOfReference
 - vtkRTStructSetProperties, [1485](#)
- AddCSAHeaderDictEntry
 - gdcm::CSAHeaderDict, [326](#)
- AddDerivationDescription
 - gdcm::FileDerivation, [515](#)
- AddDictEntry
 - gdcm::Dict, [392](#)
 - gdcm::PrivateDict, [936](#)
- AddFile
 - gdcm::FileSet, [541](#)
 - gdcm::SerieHelper, [1057](#)
- AddFileName
 - gdcm::SerieHelper, [1057](#)
- AddFragment
 - gdcm::SequenceOfFragments, [1041](#)
- AddFromFile
 - gdcm::PresentationContextGenerator, [922](#)
- AddGroupLength
 - gdcm::DictConverter, [396](#)
- AddImageDirectoryRecord
 - gdcm::DICOmdirGenerator, [388](#)
- AddInput
 - vtkImageColorViewer, [1453](#)
- AddInputConnection
 - vtkImageColorViewer, [1453](#)
- AddIOD
 - gdcm::IODs, [663](#)
- AddIODEntry
 - gdcm::IOD, [657](#)
- AddItem
 - gdcm::SequenceOfItems, [1049](#)
- AddMacro
 - gdcm::Macros, [739](#)
 - gdcm::Module, [775](#)
- AddMacroEntry
 - gdcm::Macro, [737](#)
- AddModule
 - gdcm::Modules, [782](#)
- AddModuleEntry
 - gdcm::Module, [775](#)
 - gdcm::NestedModuleEntries, [805](#)
- AddNewUndefinedLengthItem
 - gdcm::SequenceOfItems, [1049](#)
- AddObserver
 - gdcm::Subject, [1145](#)

- AddPatientDirectoryRecord
 - gdcm::DICOMDIRGenerator, [388](#)
- AddPresentationContext
 - gdcm::network::AAssociateRQPDU, [96](#)
 - gdcm::PresentationContextGenerator, [922](#)
- AddPresentationContextAC
 - gdcm::network::AAssociateACPDU, [90](#)
- AddPresentationDataValue
 - gdcm::network::PDataTFPDU, [855](#)
- AddPrimitiveData
 - gdcm::MeshPrimitive, [763](#)
- AddPrivateTag
 - gdcm::Scanner, [1000](#)
 - gdcm::Scanner2, [1010](#)
 - gdcm::StrictScanner, [1118](#)
 - gdcm::StrictScanner2, [1128](#)
- AddPublicTag
 - gdcm::Scanner2, [1010](#)
 - gdcm::StrictScanner2, [1128](#)
- AddPurposeOfReferenceCodeSequence
 - gdcm::FileDerivation, [515](#)
- AddQueryDataSet
 - gdcm::BaseQuery, [204](#)
- AddReference
 - gdcm::FileDerivation, [515](#)
- AddReferencedFrameOfReference
 - vtkRTStructSetProperties, [1485](#)
- AddRestriction
 - gdcm::SerieHelper, [1057](#)
- AddRoleSelectionSub
 - gdcm::network::UserInformation, [1347](#)
- AddSegment
 - gdcm::SegmentWriter, [1036](#)
- AddSelect
 - gdcm::Sorter, [1091](#)
- AddSeriesDirectoryRecord
 - gdcm::DICOMDIRGenerator, [388](#)
- AddSkipTag
 - gdcm::Scanner, [1000](#)
 - gdcm::Scanner2, [1010](#)
 - gdcm::StrictScanner, [1118](#)
 - gdcm::StrictScanner2, [1128](#)
- AddSOPClassExtendedNegociationSub
 - gdcm::network::UserInformation, [1347](#)
- AddSourceImageSequence
 - gdcm::FileDerivation, [515](#)
- AddStructureSetROI
 - vtkRTStructSetProperties, [1485](#)
- AddStructureSetROIObservation
 - vtkRTStructSetProperties, [1486](#)
- AddStudyDirectoryRecord
 - gdcm::DICOMDIRGenerator, [388](#)
- AddSurface
 - gdcm::Segment, [1019](#)
- AddTag
 - gdcm::Scanner, [1000](#)
 - gdcm::StrictScanner, [1119](#)
- AddTransferSyntax
 - gdcm::network::PresentationContextRQ, [925](#)
 - gdcm::PresentationContext, [917](#)
- AdultMouseAnatomyOntology
 - gdcm::UIDs, [1253](#)
- AdvancedBlendingPresentationStateStorage
 - gdcm::UIDs, [1254](#)
- AE
 - gdcm::VR, [1371](#)
- AEComp
 - gdcm, [58](#)
- AES128_CIPHER
 - gdcm::CryptographicMessageSyntax, [309](#)
- AES192_CIPHER
 - gdcm::CryptographicMessageSyntax, [309](#)
- AES256_CIPHER
 - gdcm::CryptographicMessageSyntax, [309](#)
- AffectedSOPClassUID
 - gdcm::network::CEchoRQ, [262](#)
- AGFA
 - gdcm::EquipmentManufacturer, [481](#)
- ALGOType
 - gdcm::Segment, [1018](#)
- ALGOType_END
 - gdcm::Segment, [1019](#)
- Allocate
 - gdcm::LookupTable, [729](#)
- AmbulatoryECGWaveformStorage
 - gdcm::MediaStorage, [748](#)
 - gdcm::UIDs, [1250](#)
- AnatomicRegion
 - gdcm::Segment, [1023](#)
- AnatomicRegionModifiers
 - gdcm::Segment, [1023](#)
- AnonymizeEvent
 - gdcm::AnonymizeEvent, [105](#)
- Anonymizer
 - gdcm::Anonymizer, [110](#)
- Append
 - gdcm::ByteValue, [250](#)
 - gdcm::Global, [565](#)
- AppendFrameEncode
 - gdcm::ImageCodec, [608](#)
 - gdcm::JPEG2000Codec, [690](#)
 - gdcm::JPEGCodec, [704](#)
 - gdcm::JPEGLSCCodec, [713](#)
 - gdcm::RLECodec, [991](#)
- AppendImplementationClassUID
 - gdcm::FileMetaInformation, [525](#)
- AppendRowEncode
 - gdcm::ImageCodec, [608](#)

- gdcM::JPEG2000Codec, [690](#)
- gdcM::JPEGCodec, [704](#)
- gdcM::JPEGLSCCodec, [713](#)
- gdcM::RLECodec, [991](#)
- AppendToDataElement
 - gdcM::FileStreamer, [545](#)
- AppendToGroupDataElement
 - gdcM::FileStreamer, [545](#)
- ApplicationContext
 - gdcM::network::ApplicationContext, [117](#)
- Apply
 - gdcM::ImageApplyLookupTable, [589](#)
- ApplyInverseVideo
 - vtkGDCMImageReader, [1395](#)
 - vtkGDCMImageReader2, [1410](#)
- ApplyLookupTable
 - vtkGDCMImageReader, [1395](#)
 - vtkGDCMImageReader2, [1410](#)
- ApplyPlanarConfiguration
 - vtkGDCMImageReader, [1395](#)
 - vtkGDCMImageReader2, [1410](#)
- ApplyShiftScale
 - vtkGDCMImageReader, [1395](#)
 - vtkGDCMImageReader2, [1410](#)
- ApplyYBRToRGB
 - vtkGDCMImageReader, [1395](#)
 - vtkGDCMImageReader2, [1410](#)
- Area
 - gdcM::BoxRegion, [239](#)
 - gdcM::Region, [981](#)
- AReleaseRPPDU
 - gdcM::network::AReleaseRPPDU, [121](#)
- AReleaseRQPDU
 - gdcM::network::AReleaseRQPDU, [124](#)
- AreOverlaysInPixelData
 - gdcM::Bitmap, [223](#)
 - gdcM::Pixmap, [891](#)
- ARGB
 - gdcM::PhotometricInterpretation, [876](#)
- ArrayIncludeMacroType
 - gdcM::Macro, [736](#)
 - gdcM::Module, [774](#)
- ArrayType
 - gdcM::Attribute< Group, Element, TVR, TVM >, [131](#)
 - gdcM::Attribute< Group, Element, TVR, VM::VM1_>, [141](#)
 - gdcM::Attribute< Group, Element, TVR, VM::VM1_3 >, [149](#)
 - gdcM::Attribute< Group, Element, TVR, VM::VM1_8 >, [154](#)
 - gdcM::Attribute< Group, Element, TVR, VM::VM1_n >, [160](#)
 - gdcM::Attribute< Group, Element, TVR, VM::VM2_2n >, [169](#)
 - gdcM::Attribute< Group, Element, TVR, VM::VM2_n >, [175](#)
 - gdcM::Attribute< Group, Element, TVR, VM::VM3_3n >, [181](#)
 - gdcM::Attribute< Group, Element, TVR, VM::VM3_n >, [187](#)
- ArterialPulseWaveformStorage
 - gdcM::UIDs, [1254](#)
- ARTIMTimer
 - gdcM::network::ARTIMTimer, [125](#)
- AS
 - gdcM::VR, [1371](#)
- ASComp
 - gdcM, [58](#)
- ASN1
 - gdcM::ASN1, [127](#)
- AsynchronousOperationsWindowSub
 - gdcM::network::AsynchronousOperationsWindowSub, [128](#)
- AT
 - gdcM::VR, [1371](#)
- Attribute
 - gdcM::Attribute< Group, Element, TVR, VM::VM1_n >, [161](#)
 - gdcM::terminal, [81](#)
- Audio
 - gdcM::MediaStorage, [750](#)
- AudioCodec
 - gdcM::AudioCodec, [192](#)
- AudioSRStorageTrialRetired
 - gdcM::UIDs, [1251](#)
- AUTOMATIC
 - gdcM::Segment, [1019](#)
- AutoPixelMinMax
 - gdcM::IconImageGenerator, [574](#)
- AutorefractionMeasurementsStorage
 - gdcM::UIDs, [1254](#)
- AXIAL
 - gdcM::Orientation, [835](#)
- backslash
 - gdcM, [63](#)
- BadBigEndian
 - gdcM::SwapCode, [1172](#)
- BadLittleEndian
 - gdcM::SwapCode, [1172](#)
- BALCPPProtect
 - gdcM::Anonymizer, [110](#)
- Base64
 - gdcM::Base64, [194](#)
- BaseQuery
 - gdcM::BaseQuery, [204](#)
- BaseRootQuery
 - gdcM::BaseRootQuery, [209](#)

- BasicAnnotationBoxSOPClass
 - gdcm::UIDs, [1249](#)
- BasicApplicationLevelConfidentialityProfile
 - gdcm::Anonymizer, [110](#)
- BasicCodedEntry
 - gdcm::SegmentHelper::BasicCodedEntry, [214](#)
- BasicCodedEntryVector
 - gdcm::Segment, [1018](#)
- BasicColorImageBoxSOPClass
 - gdcm::UIDs, [1249](#)
- BasicColorPrintManagementMetaSOPClass
 - gdcm::UIDs, [1249](#)
- BasicFilmBoxSOPClass
 - gdcm::UIDs, [1249](#)
- BasicFilmSessionSOPClass
 - gdcm::UIDs, [1249](#)
- BasicGrayscaleImageBoxSOPClass
 - gdcm::UIDs, [1249](#)
- BasicGrayscalePrintManagementMetaSOPClass
 - gdcm::UIDs, [1249](#)
- BasicOffsetTable
 - gdcm::BasicOffsetTable, [219](#)
- BasicPrintImageOverlayBoxSOPClassRetired
 - gdcm::UIDs, [1249](#)
- BasicStructuredDisplayStorage
 - gdcm::UIDs, [1255](#)
- BasicStudyContentNotificationSOPClassRetired
 - gdcm::UIDs, [1248](#)
- BasicTextSR
 - gdcm::MediaStorage, [749](#)
- BasicTextSRStorage
 - gdcm::UIDs, [1251](#)
- BasicVoiceAudioWaveformStorage
 - gdcm::MediaStorage, [748](#)
 - gdcm::UIDs, [1250](#)
- Begin
 - gdcm::CSAHeaderDict, [326](#)
 - gdcm::DataSet, [362](#)
 - gdcm::Dict, [392](#)
 - gdcm::IODs, [663](#)
 - gdcm::Scanner, [1001](#)
 - gdcm::Scanner2, [1010](#)
 - gdcm::SequenceOfFragments, [1041](#)
 - gdcm::SequenceOfItems, [1049](#), [1050](#)
 - gdcm::StrictScanner, [1119](#)
 - gdcm::StrictScanner2, [1128](#)
- BigEndian
 - gdcm::SwapCode, [1172](#)
- Bitmap
 - gdcm::Bitmap, [223](#)
 - gdcm::JPEG2000Codec, [694](#)
 - gdcm::PixelFormat, [886](#)
- BitmapToBitmapFilter
 - gdcm::BitmapToBitmapFilter, [236](#)
- BitSample
 - gdcm::JPEGCodec, [709](#)
 - gdcm::LookupTable, [733](#)
- black
 - gdcm::terminal, [81](#)
- BlendingSoftcopyPresentationStateStorageSOPClass
 - gdcm::UIDs, [1250](#)
- blink
 - gdcm::terminal, [81](#)
- BLUE
 - gdcm::LookupTable, [728](#)
- blue
 - gdcm::terminal, [81](#)
- BOOL_FUNCTION_PFILE_PFILE_POINTER
 - gdcm, [58](#)
- BoundingBox
 - gdcm::BoxRegion, [239](#)
- BoxRegion
 - gdcm::BoxRegion, [239](#)
- BreakConnection
 - gdcm::network::ULConnectionManager, [1323](#)
- BreakConnectionNow
 - gdcm::network::ULConnectionManager, [1323](#)
- BreastImagingRelevantPatientInformationQuery
 - gdcm::UIDs, [1252](#)
- BreastProjectionXRayImageStorageForPresentation
 - gdcm::MediaStorage, [750](#)
 - gdcm::UIDs, [1254](#)
- BreastProjectionXRayImageStorageForProcessing
 - gdcm::MediaStorage, [750](#)
 - gdcm::UIDs, [1254](#)
- BreastTomosynthesisImageStorage
 - gdcm::MediaStorage, [749](#)
 - gdcm::UIDs, [1253](#)
- bright
 - gdcm::terminal, [81](#)
- Bug List, [7](#)
- Build
 - vtkLookupTable16, [1481](#)
- ByteBuffer
 - gdcm::ByteBuffer, [242](#)
- bytes
 - gdcm::Tag, [1201](#)
- ByteSwap
 - gdcm::ByteSwapFilter, [246](#)
- ByteSwapFilter
 - gdcm::ByteSwapFilter, [245](#), [246](#)
- ByteValue
 - gdcm::ByteValue, [249](#)
- C_CANCEL_RQ
 - gdcm::network::DIMSE, [411](#)
- C_ECHO_RQ
 - gdcm::network::DIMSE, [411](#)

- C_ECHO_RSP
 - gdcm::network::DIMSE, [411](#)
- C_FIND_RQ
 - gdcm::network::DIMSE, [411](#)
- C_FIND_RSP
 - gdcm::network::DIMSE, [411](#)
- C_GET_RQ
 - gdcm::network::DIMSE, [411](#)
- C_GET_RSP
 - gdcm::network::DIMSE, [411](#)
- C_MOVE_RQ
 - gdcm::network::DIMSE, [411](#)
- C_MOVE_RSP
 - gdcm::network::DIMSE, [411](#)
- C_STORE_RQ
 - gdcm::network::DIMSE, [411](#)
- C_STORE_RSP
 - gdcm::network::DIMSE, [411](#)
- CALIBRATED
 - gdcm::Spacing, [1095](#)
- CanCode
 - gdcm::AudioCodec, [193](#)
 - gdcm::Coder, [282](#)
 - gdcm::ImageCodec, [609](#)
 - gdcm::JPEG2000Codec, [691](#)
 - gdcm::JPEGCodec, [704](#)
 - gdcm::JPEGLSCodec, [713](#)
 - gdcm::KAKADUCodec, [721](#)
 - gdcm::PDFCodec, [864](#)
 - gdcm::PGXCodec, [873](#)
 - gdcm::PNMCodec, [909](#)
 - gdcm::PVRGCodec, [950](#)
 - gdcm::RAWCodec, [970](#)
 - gdcm::RLECodec, [991](#)
- CanDecode
 - gdcm::AudioCodec, [193](#)
 - gdcm::Decoder, [376](#)
 - gdcm::DeltaEncodingCodec, [385](#)
 - gdcm::ImageCodec, [609](#)
 - gdcm::JPEG2000Codec, [691](#)
 - gdcm::JPEGCodec, [704](#)
 - gdcm::JPEGLSCodec, [713](#)
 - gdcm::KAKADUCodec, [721](#)
 - gdcm::PDFCodec, [864](#)
 - gdcm::PGXCodec, [873](#)
 - gdcm::PNMCodec, [909](#)
 - gdcm::PVRGCodec, [950](#)
 - gdcm::RAWCodec, [970](#)
 - gdcm::RLECodec, [991](#)
- CanDisplay
 - gdcm::VR, [1372](#)
- CanEmptyTag
 - gdcm::Anonymizer, [110](#)
- CanRead
 - gdcm::Reader, [975](#)
- CanReadFile
 - vtkGDCMImageReader, [1386](#)
 - vtkGDCMImageReader2, [1401](#)
- CanReadImage
 - gdcm::StreamImageReader, [1105](#)
- CanStoreLossy
 - gdcm::TransferSyntax, [1219](#)
- CanWriteFile
 - gdcm::StreamImageWriter, [1110](#)
- CAPI
 - gdcm::CryptoFactory, [306](#)
- CAPICryptoFactory
 - gdcm::CAPICryptoFactory, [256](#)
- CAPICryptographicMessageSyntax
 - gdcm::CAPICryptographicMessageSyntax, [258](#)
- CardiacElectrophysiologyWaveformStorage
 - gdcm::MediaStorage, [748](#)
 - gdcm::UIDs, [1250](#)
- CardiacRelevantPatientInformationQuery
 - gdcm::UIDs, [1252](#)
- CEcho
 - gdcm::CompositeNetworkFunctions, [298](#)
- CFind
 - gdcm::CompositeNetworkFunctions, [298](#)
- Change
 - gdcm::FileChangeTransferSyntax, [509](#)
 - gdcm::FileDecompressLookupTable, [512](#)
 - gdcm::FileExplicitFilter, [518](#)
 - gdcm::ImageChangePhotometricInterpretation, [592](#)
 - gdcm::ImageChangePlanarConfiguration, [597](#)
 - gdcm::ImageChangeTransferSyntax, [602](#)
- ChangeFMI
 - gdcm::FileExplicitFilter, [518](#)
- ChangeMonochrome
 - gdcm::ImageChangePhotometricInterpretation, [592](#)
- ChangeRGB2YBR
 - gdcm::ImageChangePhotometricInterpretation, [592](#)
- ChangeYBR2RGB
 - gdcm::ImageChangePhotometricInterpretation, [592](#)
- CharacterDataHandler
 - gdcm::TableReader, [1188](#)
 - gdcm::XMLDictReader, [1506](#)
 - gdcm::XMLPrivateDictReader, [1512](#)
- CheckDataElement
 - gdcm::FileStreamer, [545](#)
- CheckEvent
 - gdcm::AnonymizeEvent, [105](#)
 - gdcm::DataEvent, [357](#)
 - gdcm::DataSetEvent, [373](#)
 - gdcm::Event, [483](#)
 - gdcm::FileNameEvent, [536](#)
 - gdcm::ProgressEvent, [946](#)
- CheckFileMetaInformationOff

- gdcm::Writer, [1501](#)
- CheckFileMetaInformationOn
 - gdcm::Writer, [1501](#)
- CheckTemplateFileName
 - gdcm::FileStreamer, [545](#)
- ChestCADSRStorage
 - gdcm::UIDs, [1251](#)
- CipherTypes
 - gdcm::CryptographicMessageSyntax, [308](#)
- Clamp
 - gdcm, [63](#)
- Clean
 - gdcm::Cleaner, [271](#)
- clean
 - gdcm, [63](#)
- Cleaner
 - gdcm::Cleaner, [271](#)
- CleanupUnusedBits
 - gdcm::ImageCodec, [609](#)
- Clear
 - gdcm::Anonymizer, [110](#)
 - gdcm::Bitmap, [223](#)
 - gdcm::ByteValue, [250](#)
 - gdcm::DataElement, [343](#)
 - gdcm::DataSet, [362](#)
 - gdcm::IOD, [657](#)
 - gdcm::IODs, [663](#)
 - gdcm::Item, [673](#)
 - gdcm::LookupTable, [729](#)
 - gdcm::Macro, [737](#)
 - gdcm::Macros, [739](#)
 - gdcm::Module, [775](#)
 - gdcm::Modules, [782](#)
 - gdcm::Preamble, [912](#)
 - gdcm::SequenceOfFragments, [1041](#)
 - gdcm::SequenceOfItems, [1050](#)
 - gdcm::SerieHelper, [1057](#)
 - gdcm::Value, [1354](#)
 - vtkGDCMMedicalImageProperties, [1423](#)
 - vtkRTStructSetProperties, [1486](#)
- ClearInternalUIDs
 - gdcm::Anonymizer, [111](#)
- ClearPrivateTags
 - gdcm::Scanner2, [1010](#)
 - gdcm::StrictScanner2, [1128](#)
- ClearPublicTags
 - gdcm::Scanner2, [1011](#)
 - gdcm::StrictScanner2, [1129](#)
- ClearSkipTags
 - gdcm::Scanner, [1001](#)
 - gdcm::Scanner2, [1011](#)
 - gdcm::StrictScanner, [1119](#)
 - gdcm::StrictScanner2, [1129](#)
- ClearTags
 - gdcm::Scanner, [1001](#)
 - gdcm::StrictScanner, [1119](#)
- Clone
 - gdcm::BoxRegion, [239](#)
 - gdcm::ImageCodec, [609](#)
 - gdcm::JPEG2000Codec, [691](#)
 - gdcm::JPEGCodec, [705](#)
 - gdcm::JPEGLSCodec, [713](#)
 - gdcm::KAKADUCodec, [721](#)
 - gdcm::PGXCodec, [874](#)
 - gdcm::PNMCodec, [910](#)
 - gdcm::PVRGCodec, [950](#)
 - gdcm::RAWCodec, [970](#)
 - gdcm::Region, [981](#)
 - gdcm::RLECodec, [991](#)
- CM
 - gdcm::SegmentHelper::BasicCodedEntry, [215](#)
- cMaxEventID
 - gdcm::network, [80](#)
- cMaxStateID
 - gdcm::network, [80](#)
- CMove
 - gdcm::CompositeNetworkFunctions, [299](#)
- CMYK
 - gdcm::PhotometricInterpretation, [876](#)
- Code
 - gdcm::Coder, [282](#)
 - gdcm::JPEG2000Codec, [691](#)
 - gdcm::JPEGCodec, [705](#)
 - gdcm::JPEGLSCodec, [714](#)
 - gdcm::JSON, [717](#)
 - gdcm::KAKADUCodec, [721](#)
 - gdcm::PVRGCodec, [951](#)
 - gdcm::RAWCodec, [971](#)
 - gdcm::RLECodec, [991](#)
- CodedEntryData
 - gdcm::Cleaner, [271](#)
- CodeMeaning
 - gdcm::RealWorldValueMappingContent, [980](#)
- CodeString
 - gdcm::CodeString, [285](#), [286](#)
- CodeValue
 - gdcm::RealWorldValueMappingContent, [980](#)
- ColonCADSRStorage
 - gdcm::UIDs, [1255](#)
- Color
 - gdcm::terminal, [81](#)
- ColorArray
 - gdcm::SurfaceHelper, [1159](#)
- ColorPaletteQueryRetrieveInformationModelFIND
 - gdcm::UIDs, [1256](#)
- ColorPaletteQueryRetrieveInformationModelGET
 - gdcm::UIDs, [1256](#)
- ColorPaletteQueryRetrieveInformationModelMOVE

- gdcM::UIDs, [1256](#)
- ColorPaletteStorage
 - gdcM::UIDs, [1256](#)
- ColorSoftcopyPresentationStateStorageSOPClass
 - gdcM::UIDs, [1250](#)
- Command
 - gdcM::Command, [289](#)
- CommandDataSet
 - gdcM::CommandDataSet, [293](#)
- CommandTypes
 - gdcM::network::DIMSE, [411](#)
- Compatible
 - gdcM::VM, [1367](#)
 - gdcM::VR, [1372](#)
- Component
 - gdcM::PersonName, [869](#)
- CompOperators
 - gdcM, [60](#)
- CompositeInstanceRetrieveWithoutBulkDataGET
 - gdcM::UIDs, [1255](#)
- CompositeInstanceRootRetrieveGET
 - gdcM::UIDs, [1255](#)
- CompositeInstanceRootRetrieveMOVE
 - gdcM::UIDs, [1255](#)
- CompositingPlanarMPRVolumetricPresentationStateStorageComputeMD5
 - gdcM::UIDs, [1254](#)
- Comprehensive3DSRStorage
 - gdcM::UIDs, [1255](#)
- ComprehensiveSR
 - gdcM::MediaStorage, [749](#)
- ComprehensiveSRStorage
 - gdcM::UIDs, [1251](#)
- ComprehensiveSRStorageTrialRetired
 - gdcM::UIDs, [1251](#)
- CompressionTypes
 - vtkGDCMImageWriter, [1415](#)
- Compute
 - gdcM::EquipmentManufacturer, [481](#)
 - gdcM::MD5, [742](#)
 - gdcM::SHA1, [1071](#)
- ComputeBoundingBox
 - gdcM::BoxRegion, [240](#)
 - gdcM::Region, [982](#)
- ComputeBufferLength
 - gdcM::ImageRegionReader, [638](#)
- ComputeByteLength
 - gdcM::SequenceOfFragments, [1041](#)
- ComputeCSAImageHeaderInfo
 - gdcM::SplitMosaicFilter, [1098](#)
- ComputeCSASeriesHeaderInfo
 - gdcM::SplitMosaicFilter, [1098](#)
- ComputeDataElement
 - gdcM::DataSet, [362](#)
- ComputeDataSetMediaStorageSOPClass
 - gdcM::FileMetaInformation, [525](#)
- ComputeDataSetTransferSyntax
 - gdcM::FileMetaInformation, [525](#)
- ComputeDistAlongNormal
 - gdcM::DirectionCosines, [413](#)
- ComputedRadiographyImageStorage
 - gdcM::MediaStorage, [748](#)
 - gdcM::UIDs, [1249](#)
- ComputeFile
 - gdcM::MD5, [742](#)
 - gdcM::SHA1, [1071](#)
- ComputeFileMD5
 - gdcM::Testing, [1206](#)
- ComputeGroupLength
 - gdcM::DataSet, [362](#)
- ComputeInterceptSlopePixelType
 - gdcM::Rescaler, [984](#)
- ComputeLength
 - gdcM::ByteValue, [250](#)
 - gdcM::Fragment, [562](#)
 - gdcM::SequenceOfFragments, [1042](#)
 - gdcM::SequenceOfItems, [1050](#)
- ComputeLossyFlag
 - gdcM::Bitmap, [223](#)
- ComputeMD5
 - gdcM::Testing, [1206](#)
- ComputeMediaStorageFromModality
 - gdcM::ImageHelper, [624](#)
- ComputeMOSAICDimensions
 - gdcM::SplitMosaicFilter, [1098](#)
- ComputeMOSAICImagePositionPatient
 - gdcM::SplitMosaicFilter, [1098](#)
- ComputeMOSAICSliceNormal
 - gdcM::SplitMosaicFilter, [1098](#)
- ComputeMOSAICSlicePosition
 - gdcM::SplitMosaicFilter, [1099](#)
- ComputeNumberOfSurfaces
 - gdcM::SurfaceWriter, [1170](#)
- ComputeOffsetTable
 - gdcM::JPEGCodec, [705](#)
- ComputePixelAspectRatioFromPixelSpacing
 - gdcM::Spacing, [1096](#)
- ComputePixelTypeFromMinMax
 - gdcM::Rescaler, [984](#)
- ComputeSpacingFromImagePositionPatient
 - gdcM::ImageHelper, [624](#)
- ComputeTargetMediaStorage
 - gdcM::ImageWriter, [645](#)
- ComputeVR
 - gdcM::DataSetHelper, [375](#)
- ComputeZSpacing
 - gdcM::IPPSorter, [669](#)
- ConcatenatePDVBlobs
 - gdcM::network::PresentationDataValue, [928](#)

- ConcatenatePDVBlobsAsExplicit
 - gdcn::network::PresentationDataValue, 928
- CONDENSED_STYLE
 - gdcn::Printer, 933
- Conditional
 - gdcn::Usage, 1343
- CONSOLE
 - gdcn::terminal, 83
- const
 - gdcn::SOPClassUIDToIOD, 1088
- const_iterator
 - gdcn::CodeString, 284
 - gdcn::LO, 724
 - gdcn::String< TDelimiter, TMaxLength, TPadChar >, 1135
- const_reference
 - gdcn::CodeString, 284
 - gdcn::LO, 724
 - gdcn::String< TDelimiter, TMaxLength, TPadChar >, 1135
- const_reverse_iterator
 - gdcn::CodeString, 284
 - gdcn::LO, 724
 - gdcn::String< TDelimiter, TMaxLength, TPadChar >, 1136
- ConstCharWrapper
 - gdcn::ConstCharWrapper, 301
- ConstIterator
 - gdcn::CSAHeaderDict, 325
 - gdcn::DataSet, 361
 - gdcn::Dict, 391
 - gdcn::Scanner, 999
 - gdcn::SequenceOfFragments, 1040
 - gdcn::SequenceOfItems, 1048
 - gdcn::StrictScanner, 1117
- Construct
 - gdcn::BaseRootQuery, 210
- ConstructAbortPDU
 - gdcn::network::PDUFactory, 865
- ConstructCEchoRQ
 - gdcn::network::CompositeMessageFactory, 296
- ConstructCFindRQ
 - gdcn::network::CompositeMessageFactory, 296
- ConstructCMoveRQ
 - gdcn::network::CompositeMessageFactory, 296
- ConstructCStoreRQ
 - gdcn::network::CompositeMessageFactory, 296
- ConstructCStoreRSP
 - gdcn::network::CompositeMessageFactory, 296
- ConstructFromString
 - gdcn::DPath, 422
 - gdcn::TagPath, 1203
- ConstructFromTagList
 - gdcn::TagPath, 1203
- ConstructNAction
 - gdcn::network::NormalizedMessageFactory, 813
- ConstructNCreate
 - gdcn::network::NormalizedMessageFactory, 813
- ConstructNDelete
 - gdcn::network::NormalizedMessageFactory, 814
- ConstructNEventReport
 - gdcn::network::NormalizedMessageFactory, 814
- ConstructNGet
 - gdcn::network::NormalizedMessageFactory, 814
- ConstructNSet
 - gdcn::network::NormalizedMessageFactory, 814
- ConstructorType
 - gdcn::Dicts, 407
- ConstructPDU
 - gdcn::network::PDUFactory, 865
- ConstructPDV
 - gdcn::network::BaseCompositeMessage, 197
 - gdcn::network::BaseNormalizedMessage, 199
 - gdcn::network::CEchoRQ, 262
 - gdcn::network::CFindRQ, 266
 - gdcn::network::CMoveRQ, 278
 - gdcn::network::CStoreRQ, 333
 - gdcn::network::CStoreRSP, 334
 - gdcn::network::NActionRQ, 795
 - gdcn::network::NCreateRQ, 798
 - gdcn::network::NDeleteRQ, 801
 - gdcn::network::NEventReportRQ, 807
 - gdcn::network::NGetRQ, 810
 - gdcn::network::NSetRQ, 818
- ConstructPDVByDataSet
 - gdcn::network::CEchoRSP, 263
 - gdcn::network::CFindCancelRQ, 265
 - gdcn::network::CFindRSP, 268
 - gdcn::network::CMoveCancelRq, 276
 - gdcn::network::CMoveRSP, 279
 - gdcn::network::NActionRSP, 796
 - gdcn::network::NCreateRSP, 799
 - gdcn::network::NDeleteRSP, 802
 - gdcn::network::NEventReportRSP, 809
 - gdcn::network::NGetRSP, 812
 - gdcn::network::NSetRSP, 819
- ConstructQuery
 - gdcn::CompositeNetworkFunctions, 299, 300
 - gdcn::NormalizedNetworkFunctions, 815
- ConstructReleasePDU
 - gdcn::network::PDUFactory, 865
- ContentAssessmentResultsStorage
 - gdcn::UIDs, 1255
- Convert
 - gdcn::DictConverter, 396
 - gdcn::ImageConverter, 618
- ConvertRGBToPaletteColor
 - gdcn::IconImageGenerator, 574

- ConvertToCXX
 - gdcm::DictConverter, [396](#)
- ConvertToUNC
 - gdcm::System, [1177](#)
- ConvertToXML
 - gdcm::DictConverter, [396](#)
- CornealTopographyMapStorage
 - gdcm::UIDs, [1255](#)
- CORONAL
 - gdcm::Orientation, [835](#)
- Create
 - gdcm::Preamble, [912](#)
- CreateCEchoPDU
 - gdcm::network::PDUFactory, [866](#)
- CreateCFindPDU
 - gdcm::network::PDUFactory, [866](#)
- CreateCMovePDU
 - gdcm::network::PDUFactory, [866](#)
- CreateCMSProvider
 - gdcm::CAPICryptoFactory, [256](#)
 - gdcm::CryptoFactory, [307](#)
 - gdcm::OpenSSLCryptoFactory, [825](#)
 - gdcm::OpenSSLP7CryptoFactory, [830](#)
- CreateCStoreRQPDU
 - gdcm::network::PDUFactory, [866](#)
- CreateCStoreRSPPDU
 - gdcm::network::PDUFactory, [866](#)
- CreateDefaultUniqueSeriesIdentifier
 - gdcm::SerieHelper, [1058](#)
- CreateNActionPDU
 - gdcm::network::PDUFactory, [866](#)
- CreateNCreatePDU
 - gdcm::network::PDUFactory, [866](#)
- CreateNDeletePDU
 - gdcm::network::PDUFactory, [867](#)
- CreateNEventReportPDU
 - gdcm::network::PDUFactory, [867](#)
- CreateNGetPDU
 - gdcm::network::PDUFactory, [867](#)
- CreateNSetPDU
 - gdcm::network::PDUFactory, [867](#)
- CreateUniqueSeriesIdentifier
 - gdcm::SerieHelper, [1058](#)
- Cross
 - gdcm::DirectionCosines, [413](#)
- CrossDot
 - gdcm::DirectionCosines, [413](#)
- CryptoFactory
 - gdcm::CryptoFactory, [307](#)
- CryptographicMessageSyntax
 - gdcm::CryptographicMessageSyntax, [309](#)
- CryptoLib
 - gdcm::CryptoFactory, [306](#)
- CS
 - gdcm::VR, [1371](#)
- CSAElement
 - gdcm::CSAElement, [313](#)
- CSAHeader
 - gdcm::CSAHeader, [321](#)
 - gdcm::DataSet, [370](#)
- CSAHeaderDict
 - gdcm::CSAHeaderDict, [326](#)
- CSAHeaderDictEntry
 - gdcm::CSAHeaderDictEntry, [329](#)
- CSAHeaderType
 - gdcm::CSAHeader, [321](#)
- CSANonImageStorage
 - gdcm::MediaStorage, [749](#)
- CSComp
 - gdcm, [58](#)
- CSD
 - gdcm::SegmentHelper::BasicCodedEntry, [215](#)
- CStore
 - gdcm::CompositeNetworkFunctions, [300](#)
- CSV
 - gdcm::SegmentHelper::BasicCodedEntry, [215](#)
- CT_private_ELE
 - gdcm::TransferSyntax, [1218](#)
- CTDefinedProcedureProtocolStorage
 - gdcm::UIDs, [1255](#)
- CTImageStorage
 - gdcm::MediaStorage, [748](#)
 - gdcm::UIDs, [1249](#)
- CTPerformedProcedureProtocolStorage
 - gdcm::UIDs, [1255](#)
- Curve
 - gdcm::Curve, [336](#)
 - vtkGDCMImageReader, [1395](#)
 - vtkGDCMImageReader2, [1410](#)
- Curves
 - gdcm::Pixmap, [893](#)
- CV
 - gdcm::SegmentHelper::BasicCodedEntry, [215](#)
- CXX
 - gdcm::Printer, [933](#)
- cyan
 - gdcm::terminal, [81](#)
- DA
 - gdcm::VR, [1371](#)
- DAComp
 - gdcm, [58](#)
- DataElement
 - gdcm::DataElement, [343](#)
 - gdcm::Value, [1355](#)
- DataElementSet
 - gdcm::DataSet, [361](#)
- DataElementType

- gdcmm::ModuleEntry, 780
- DataEvent
 - gdcmm::DataEvent, 356, 357
- DataField
 - gdcmm::CSAElement, 318
- DataPtr
 - gdcmm::CSAElement, 313
- DATASET_FORMAT
 - gdcmm::CSAHeader, 321
- DataSetEvent
 - gdcmm::DataSetEvent, 373
- DataSetHandled
 - gdcmm::network::ULConnectionCallback, 1317
- DataSetHandles
 - gdcmm::network::ULConnectionCallback, 1317
- DataSetMS
 - gdcmm::FileMetaInformation, 530
- DataSetTS
 - gdcmm::FileMetaInformation, 530
- DataWasPassed
 - vtkImageMapToColors16, 1467
- dCor
 - gdcmm::MrProtocol::Vector3, 1356
- DebugOff
 - gdcmm::Trace, 1212
- DebugOn
 - gdcmm::Trace, 1212
- Decode
 - gdcmm::AudioCodec, 193
 - gdcmm::Base64, 194
 - gdcmm::Curve, 337
 - gdcmm::Decoder, 376
 - gdcmm::DeltaEncodingCodec, 385
 - gdcmm::ImageCodec, 609
 - gdcmm::JPEG2000Codec, 691
 - gdcmm::JPEGCodec, 705
 - gdcmm::JPEGLSCodec, 714
 - gdcmm::JSON, 717
 - gdcmm::KAKADUCodec, 722
 - gdcmm::LookupTable, 729
 - gdcmm::PDFCodec, 864
 - gdcmm::PVRGCodec, 951
 - gdcmm::RAWCodec, 971
 - gdcmm::RLECodec, 992
- Decode8
 - gdcmm::LookupTable, 729
- DecodeByStreams
 - gdcmm::Decoder, 376
 - gdcmm::ImageCodec, 610
 - gdcmm::JPEG12Codec, 681
 - gdcmm::JPEG16Codec, 686
 - gdcmm::JPEG2000Codec, 692
 - gdcmm::JPEG8Codec, 699
 - gdcmm::JPEGCodec, 705
- gdcmm::RAWCodec, 971
- gdcmm::RLECodec, 992
- DecodeBytes
 - gdcmm::RAWCodec, 971
- DecodeExtent
 - gdcmm::JPEG2000Codec, 692
 - gdcmm::JPEGCodec, 706
 - gdcmm::JPEGLSCodec, 714
 - gdcmm::RLECodec, 992
- Decompress
 - gdcmm::Overlay, 841
- Decrypt
 - gdcmm::CAPICryptographicMessageSyntax, 258
 - gdcmm::CryptographicMessageSyntax, 309
 - gdcmm::OpenSSLCryptographicMessageSyntax, 827
 - gdcmm::OpenSSLP7CryptographicMessageSyntax, 832
- DeepCopy
 - vtkRTStructSetProperties, 1486
- DEFAULT
 - gdcmm::CryptoFactory, 306
- Default
 - gdcmm::FileMetaInformation, 525
- DefinedProcedureProtocolInformationModelFIND
 - gdcmm::UIDs, 1255
- DefinedProcedureProtocolInformationModelGET
 - gdcmm::UIDs, 1255
- DefinedProcedureProtocolInformationModelMOVE
 - gdcmm::UIDs, 1255
- DefinedTerms
 - gdcmm::DefinedTerms, 377
- DefinePixelExtent
 - gdcmm::StreamImageReader, 1105
 - gdcmm::StreamImageWriter, 1110
- DefineProperBufferLength
 - gdcmm::StreamImageReader, 1105
 - gdcmm::StreamImageWriter, 1110
- DeflatedExplicitVRLittleEndian
 - gdcmm::TransferSyntax, 1218
 - gdcmm::UIDs, 1247
- DeformableSpatialRegistrationStorage
 - gdcmm::UIDs, 1250
- Defs
 - gdcmm::Defs, 379
- DeleteDirectory
 - gdcmm::System, 1177
- DeltaEncodingCodec
 - gdcmm::DeltaEncodingCodec, 385
- Deprecated List, 5
- Derive
 - gdcmm::FileDerivation, 515
- DES3_CIPHER
 - gdcmm::CryptographicMessageSyntax, 309
- Description

gdcM::ModuleEntry, 778
 DescriptionField
 gdcM::ModuleEntry, 780
 DetachedInterpretationManagementSOPClassRetired
 gdcM::UIDs, 1249
 DetachedPatientManagementMetaSOPClassRetired
 gdcM::UIDs, 1248
 DetachedPatientManagementSOPClass
 gdcM::MediaStorage, 749
 DetachedPatientManagementSOPClassRetired
 gdcM::UIDs, 1248
 DetachedResultsManagementMetaSOPClassRetired
 gdcM::UIDs, 1249
 DetachedResultsManagementSOPClassRetired
 gdcM::UIDs, 1249
 DetachedStudyManagementMetaSOPClassRetired
 gdcM::UIDs, 1249
 DetachedStudyManagementSOPClass
 gdcM::MediaStorage, 749
 DetachedStudyManagementSOPClassRetired
 gdcM::UIDs, 1248
 DetachedVisitManagementSOPClass
 gdcM::MediaStorage, 749
 DetachedVisitManagementSOPClassRetired
 gdcM::UIDs, 1248
 DetailSRStorageTrialRetired
 gdcM::UIDs, 1251
 DETECTOR
 gdcM::Spacing, 1095
 DetermineEventByPDU
 gdcM::network::PDUFactory, 867
 dicomAETitle
 gdcM::UIDs, 1252
 dicomApplicationCluster
 gdcM::UIDs, 1252
 DICOMApplicationContextName
 gdcM::UIDs, 1248
 dicomAssociationAcceptor
 gdcM::UIDs, 1252
 dicomAssociationInitiator
 gdcM::UIDs, 1252
 dicomAuthorizedNodeCertificateReference
 gdcM::UIDs, 1253
 dicomConfigurationRoot
 gdcM::UIDs, 1253
 DICOMContentMappingResource
 gdcM::UIDs, 1256
 DICOMControlledTerminology
 gdcM::UIDs, 1248
 dicomDescription
 gdcM::UIDs, 1252
 dicomDevice
 gdcM::UIDs, 1253
 dicomDeviceName
 gdcM::UIDs, 1252
 dicomDeviceSerialNumber
 gdcM::UIDs, 1253
 dicomDevicesRoot
 gdcM::UIDs, 1253
 DICOMDIR
 gdcM::DICOMDIR, 386
 DICOMDIRGenerator
 gdcM::DICOMDIRGenerator, 388
 dicomHostname
 gdcM::UIDs, 1252
 dicomInstalled
 gdcM::UIDs, 1253
 dicomInstitutionAddress
 gdcM::UIDs, 1253
 dicomInstitutionDepartmentName
 gdcM::UIDs, 1253
 dicomInstitutionName
 gdcM::UIDs, 1253
 dicomIssuerOfPatientID
 gdcM::UIDs, 1253
 dicomManufacturer
 gdcM::UIDs, 1252
 dicomManufacturerModelName
 gdcM::UIDs, 1252
 dicomNetworkAE
 gdcM::UIDs, 1253
 dicomNetworkConnection
 gdcM::UIDs, 1253
 dicomNetworkConnectionReference
 gdcM::UIDs, 1252
 dicomPort
 gdcM::UIDs, 1252
 dicomPreferredCalledAETitle
 gdcM::UIDs, 1252
 dicomPreferredCallingAETitle
 gdcM::UIDs, 1253
 dicomPrimaryDeviceType
 gdcM::UIDs, 1252
 dicomRelatedDeviceReference
 gdcM::UIDs, 1252
 dicomSoftwareVersion
 gdcM::UIDs, 1252
 dicomSOPClass
 gdcM::UIDs, 1252
 dicomStationName
 gdcM::UIDs, 1253
 dicomSupportedCharacterSet
 gdcM::UIDs, 1253
 dicomThisNodeCertificateReference
 gdcM::UIDs, 1253
 dicomTLSCyphersuite
 gdcM::UIDs, 1253
 dicomTransferCapability

- gdcM::UIDs, [1253](#)
- dicomTransferRole
 - gdcM::UIDs, [1252](#)
- dicomTransferSyntax
 - gdcM::UIDs, [1252](#)
- DICOMUIDRegistry
 - gdcM::UIDs, [1248](#)
- dicomUniqueAETitle
 - gdcM::UIDs, [1253](#)
- dicomUniqueAETitlesRegistryRoot
 - gdcM::UIDs, [1253](#)
- dicomVendorData
 - gdcM::UIDs, [1252](#)
- DICOS2DAITStorage
 - gdcM::UIDs, [1255](#)
- DICOS3DAITStorage
 - gdcM::UIDs, [1255](#)
- DICOSCTImageStorage
 - gdcM::UIDs, [1255](#)
- DICOSDigitalXRayImageStorageForPresentation
 - gdcM::UIDs, [1255](#)
- DICOSDigitalXRayImageStorageForProcessing
 - gdcM::UIDs, [1255](#)
- DICOSQuadrupoleResonanceQRStorage
 - gdcM::UIDs, [1255](#)
- DICOSThreatDetectionReportStorage
 - gdcM::UIDs, [1255](#)
- Dict
 - gdcM::Dict, [391](#)
 - gdcM::DictEntry, [402](#)
- DICT_DEBUG
 - gdcM::DictConverter, [396](#)
- DICT_DEFAULT
 - gdcM::DictConverter, [396](#)
- DICT_XML
 - gdcM::DictConverter, [396](#)
- DictConverter
 - gdcM::DictConverter, [396](#)
- DictEntry
 - gdcM::DictEntry, [400](#)
- DictPrinter
 - gdcM::DictPrinter, [405](#)
- Dicts
 - gdcM::CSAHeaderDict, [327](#)
 - gdcM::Dict, [394](#)
 - gdcM::Dicts, [407](#)
 - gdcM::PrivateDict, [937](#)
- difference_type
 - gdcM::CodeString, [284](#)
 - gdcM::LO, [724](#)
 - gdcM::String< TDelimiter, TMaxLength, TPadChar
>, [1136](#)
- DigitalIntraoralXRayImageStorageForPresentation
 - gdcM::UIDs, [1249](#)
- DigitalIntraoralXRayImageStorageForPresentation
 - gdcM::MediaStorage, [748](#)
- DigitalIntraoralXRayImageStorageForProcessing
 - gdcM::MediaStorage, [748](#)
 - gdcM::UIDs, [1249](#)
- DigitalMammographyImageStorageForPresentation
 - gdcM::MediaStorage, [748](#)
- DigitalMammographyImageStorageForProcessing
 - gdcM::MediaStorage, [748](#)
- DigitalMammographyXRayImageStorageForPresentation
 - gdcM::UIDs, [1249](#)
- DigitalMammographyXRayImageStorageForProcessing
 - gdcM::UIDs, [1249](#)
- DigitalXRayImageStorageForPresentation
 - gdcM::MediaStorage, [748](#)
 - gdcM::UIDs, [1249](#)
- DigitalXRayImageStorageForProcessing
 - gdcM::MediaStorage, [748](#)
 - gdcM::UIDs, [1249](#)
- dim
 - gdcM::terminal, [81](#)
- Dimensions
 - gdcM::Bitmap, [233](#)
 - gdcM::ImageCodec, [616](#)
- DirCosTolerance
 - gdcM::IPPSorter, [669](#)
- DirectionCosines
 - gdcM::DirectionCosines, [412](#)
 - vtkGDCMImageReader, [1395](#)
 - vtkGDCMImageReader2, [1410](#)
- Directory
 - gdcM::Directory, [416](#)
- DisplaySystemSOPClass
 - gdcM::UIDs, [1254](#)
- DisplaySystemSOPInstance
 - gdcM::UIDs, [1254](#)
- DoByteSwap
 - gdcM::ImageCodec, [610](#)
- DolconImage
 - gdcM::PixmapWriter, [904](#)
- DoInvertMonochrome
 - gdcM::ImageCodec, [610](#)
- DoOverlayCleanup
 - gdcM::ImageCodec, [610](#)
- DoPaddedCompositePixelCode
 - gdcM::ImageCodec, [610](#)
- DoPlanarConfiguration
 - gdcM::ImageCodec, [610](#)
- doround
 - gdcM, [63](#)
- DoSimpleCopy
 - gdcM::ImageCodec, [611](#)
- Dot
 - gdcM::DirectionCosines, [413](#)

DoYBR
 gdcm::ImageCodec, [611](#)
 DoYBRFull422
 gdcm::ImageCodec, [611](#)
 DPath
 gdcm::DPath, [422](#)
 DropDuplicatePositions
 gdcm::IPPSorter, [669](#)
 DS
 gdcm::VR, [1371](#)
 dSag
 gdcm::MrProtocol::Vector3, [1356](#)
 DT
 gdcm::VR, [1371](#)
 DTComp
 gdcm, [59](#)
 dTra
 gdcm::MrProtocol::Vector3, [1356](#)
 Dumper
 gdcm::Dumper, [426](#)
 DuplicateAttributeError
 gdcm::Parser, [850](#)

 eAABORTPDUReturnedOpen
 gdcm::network, [79](#)
 eAABORTRequest
 gdcm::network, [79](#)
 eAASSOCIATE_RQPDUreceived
 gdcm::network, [78](#)
 eAASSOCIATERequestLocalUser
 gdcm::network, [78](#)
 eAASSOCIATEResponseAccept
 gdcm::network, [78](#)
 eAASSOCIATEResponseReject
 gdcm::network, [78](#)
 eArabic
 gdcm, [61](#)
 eARELEASE_RPPDUreceived
 gdcm::network, [79](#)
 eARELEASE_RQPDUreceivedOpen
 gdcm::network, [79](#)
 eARELEASERequest
 gdcm::network, [79](#)
 eARELEASEResponse
 gdcm::network, [79](#)
 eARTIMTimerExpired
 gdcm::network, [79](#)
 eASSOCIATE_ACPDUreceived
 gdcm::network, [78](#)
 eASSOCIATE_RJPDUreceived
 gdcm::network, [78](#)
 ECG12leadWaveformStorage
 gdcm::UIDs, [1250](#)
 ECharSet
 gdcm, [61](#)
 eCreateMMPS
 gdcm, [61](#)
 eCyrillic
 gdcm, [61](#)
 EddyCurrentImageStorage
 gdcm::UIDs, [1255](#)
 EddyCurrentMultiframeImageStorage
 gdcm::UIDs, [1255](#)
 EDGE
 gdcm::MeshPrimitive, [762](#)
 eEventDoesNotExist
 gdcm::network, [79](#)
 EEventID
 gdcm::network, [78](#)
 eFind
 gdcm, [62](#)
 eGB18030
 gdcm, [61](#)
 eGreek
 gdcm, [61](#)
 eHebrew
 gdcm, [61](#)
 eImage
 gdcm, [62](#)
 eJapanese
 gdcm, [61](#)
 eJapaneseKanjiMultibyte
 gdcm, [61](#)
 eJapaneseSupplementaryKanjiMultibyte
 gdcm, [61](#)
 eKoreanHangulHanjaMultibyte
 gdcm, [61](#)
 eLatin1
 gdcm, [61](#)
 eLatin2
 gdcm, [61](#)
 eLatin3
 gdcm, [61](#)
 eLatin4
 gdcm, [61](#)
 eLatin5
 gdcm, [61](#)
 eMove
 gdcm, [62](#)
 Empty
 gdcm::Anonymizer, [111](#)
 gdcm::BoxRegion, [240](#)
 gdcm::Cleaner, [271](#), [272](#)
 gdcm::DataElement, [343](#)
 gdcm::FileAnonymizer, [504](#)
 gdcm::Region, [982](#)
 EmptyMaskGenerator
 gdcm::EmptyMaskGenerator, [471](#)

- EmptyWhenScrubFails
 - gdcm::Cleaner, [272](#)
- EncapsulatedCDASStorage
 - gdcm::MediaStorage, [749](#)
 - gdcm::UIDs, [1251](#)
- EncapsulatedDocument
 - gdcm::EncapsulatedDocument, [473](#)
- EncapsulatedPDFStorage
 - gdcm::MediaStorage, [749](#)
 - gdcm::UIDs, [1251](#)
- EncapsulatedSTLStorage
 - gdcm::UIDs, [1255](#)
- Encode
 - gdcm::Base64, [194](#)
- EncodeBuffer
 - gdcm::JPEG12Codec, [681](#)
 - gdcm::JPEG16Codec, [686](#)
 - gdcm::JPEG8Codec, [699](#)
 - gdcm::JPEGCodec, [706](#)
- EncodeBytes
 - gdcm::System, [1177](#)
- Encrypt
 - gdcm::CAPICryptographicMessageSyntax, [258](#)
 - gdcm::CryptographicMessageSyntax, [309](#)
 - gdcm::OpenSSLCryptographicMessageSyntax, [827](#)
 - gdcm::OpenSSL7CryptographicMessageSyntax, [832](#)
- End
 - gdcm::CSAHeaderDict, [326](#)
 - gdcm::DataSet, [362](#)
 - gdcm::Dict, [392](#)
 - gdcm::IODs, [663](#)
 - gdcm::Scanner, [1001](#)
 - gdcm::Scanner2, [1011](#)
 - gdcm::SequenceOfFragments, [1042](#)
 - gdcm::SequenceOfItems, [1050](#)
 - gdcm::StrictScanner, [1119](#)
 - gdcm::StrictScanner2, [1129](#)
- EndElement
 - gdcm::TableReader, [1188](#)
 - gdcm::XMLDictReader, [1506](#)
 - gdcm::XMLPrivateDictReader, [1512](#)
- EndElementHandler
 - gdcm::Parser, [850](#)
- EndFilter
 - gdcm::SimpleSubjectWatcher, [1078](#)
- EndWith
 - gdcm::Filename, [531](#)
- EnhancedCTImageStorage
 - gdcm::MediaStorage, [748](#)
 - gdcm::UIDs, [1249](#)
- EnhancedMRColorImageStorage
 - gdcm::MediaStorage, [750](#)
 - gdcm::UIDs, [1256](#)
- EnhancedMRIImageStorage
 - gdcm::MediaStorage, [748](#)
 - gdcm::UIDs, [1250](#)
- EnhancedPETImageStorage
 - gdcm::MediaStorage, [749](#)
 - gdcm::UIDs, [1255](#)
- EnhancedSR
 - gdcm::MediaStorage, [749](#)
- EnhancedSRStorage
 - gdcm::UIDs, [1251](#)
- EnhancedUSVolumeStorage
 - gdcm::MediaStorage, [749](#)
 - gdcm::UIDs, [1253](#)
- EnhancedXAImageStorage
 - gdcm::MediaStorage, [749](#)
 - gdcm::UIDs, [1250](#)
- EnhancedXRImageStorage
 - gdcm::UIDs, [1250](#)
- ENQueryType
 - gdcm, [61](#)
- EnumeratedValues
 - gdcm::EnumeratedValues, [480](#)
- ePatient
 - gdcm, [62](#)
- ePatientRootType
 - gdcm, [62](#)
- ePDATArequest
 - gdcm::network, [78](#)
- ePDATATFPDU
 - gdcm::network, [78](#)
- EQueryLevel
 - gdcm, [61](#)
- EQueryType
 - gdcm, [62](#)
- ERootType
 - gdcm, [62](#)
- ErrorOff
 - gdcm::Trace, [1212](#)
- ErrorOn
 - gdcm::Trace, [1212](#)
- ErrorType
 - gdcm::Parser, [850](#)
- eSeries
 - gdcm, [62](#)
- eSetMMPS
 - gdcm, [61](#)
- eSta10ReleaseCollisionAc
 - gdcm::network, [79](#)
- eSta11ReleaseCollisionRq
 - gdcm::network, [79](#)
- eSta12ReleaseCollisionAcLocal
 - gdcm::network, [79](#)
- eSta13AwaitingClose
 - gdcm::network, [79](#)

- eSta1Idle
 - gdcm::network, [79](#)
- eSta2Open
 - gdcm::network, [79](#)
- eSta3WaitLocalAssoc
 - gdcm::network, [79](#)
- eSta4LocalAssocDone
 - gdcm::network, [79](#)
- eSta5WaitRemoteAssoc
 - gdcm::network, [79](#)
- eSta6TransferReady
 - gdcm::network, [79](#)
- eSta7WaitRelease
 - gdcm::network, [79](#)
- eSta8WaitLocalRelease
 - gdcm::network, [79](#)
- eSta9ReleaseCollisionRqLocal
 - gdcm::network, [79](#)
- EstablishConnection
 - gdcm::network::ULConnectionManager, [1323](#)
- EstablishConnectionMove
 - gdcm::network::ULConnectionManager, [1324](#)
- eStaDoesNotExist
 - gdcm::network, [79](#)
- EStateID
 - gdcm::network, [79](#)
- eStudy
 - gdcm, [62](#)
- eStudyRootType
 - gdcm, [62](#)
- eThai
 - gdcm, [61](#)
- eTransportConnConfirmLocal
 - gdcm::network, [78](#)
- eTransportConnectionClosed
 - gdcm::network, [79](#)
- eTransportConnIndicLocal
 - gdcm::network, [78](#)
- eUnrecognizedPDURceived
 - gdcm::network, [79](#)
- eUTF8
 - gdcm, [61](#)
- Event
 - gdcm::Event, [483](#)
- eWLMFind
 - gdcm, [62](#)
- Exception
 - gdcm::Exception, [486](#)
- Execute
 - gdcm::Command, [290](#)
 - gdcm::EmptyMaskGenerator, [471](#)
 - gdcm::MemberCommand< T >, [758](#)
 - gdcm::SimpleMemberCommand< T >, [1076](#)
- ExecuteData
 - vtkGDCMImageReader, [1386](#)
 - vtkGDCMThreadedImageReader, [1440](#)
- ExecuteInformation
 - vtkGDCMImageReader, [1387](#)
 - vtkGDCMThreadedImageReader, [1440](#)
- ExecuteQuery
 - gdcm::StringFilter, [1140](#)
- Explicit
 - gdcm::TransferSyntax, [1217](#)
- ExplicitVRBigEndian
 - gdcm::TransferSyntax, [1218](#)
 - gdcm::UIDs, [1247](#)
- ExplicitVRLittleEndian
 - gdcm::TransferSyntax, [1218](#)
 - gdcm::UIDs, [1247](#)
- Explore
 - gdcm::Directory, [417](#)
- ExtensibleSRStorage
 - gdcm::UIDs, [1255](#)
- Extract
 - gdcm::IconImageFilter, [572](#)
- ExtractIconImages
 - gdcm::IconImageFilter, [572](#)
- ExtractVeprolIconImages
 - gdcm::IconImageFilter, [572](#)
- F
 - gdcm::Printer, [935](#)
 - gdcm::Reader, [979](#)
 - gdcm::Validate, [1351](#)
 - gdcm::XMLPrinter, [1510](#)
- FACET
 - gdcm::MeshPrimitive, [762](#)
- FallColorPaletteSOPInstance
 - gdcm::UIDs, [1253](#)
- FD
 - gdcm::VR, [1371](#)
- Fiducials
 - gdcm::Fiducials, [497](#)
- File
 - gdcm::File, [499](#)
- FileAnonymizer
 - gdcm::FileAnonymizer, [504](#)
- FileChangeTransferSyntax
 - gdcm::FileChangeTransferSyntax, [508](#)
 - gdcm::ImageCodec, [615](#)
- FileDecompressLookupTable
 - gdcm::FileDecompressLookupTable, [512](#)
- FileDerivation
 - gdcm::FileDerivation, [514](#)
- FileExists
 - gdcm::System, [1177](#)
- FileExplicitFilter
 - gdcm::FileExplicitFilter, [518](#)

FilesDirectory
 gdcmm::System, 1177

FilesSymlink
 gdcmm::System, 1178

FileList
 gdcmm, 59

FileMetaInformation
 gdcmm::FileMetaInformation, 524, 525

FileName
 vtkGDCMPolyDataReader, 1428

Filename
 gdcmm::Filename, 531

filename
 gdcmm::FileWithName, 550

FileNameEvent
 gdcmm::FileNameEvent, 535

FilenameGenerator
 gdcmm::FilenameGenerator, 538

FileNameOrdering
 gdcmm::SerieHelper, 1058

FileNames
 vtkGDCMImageReader, 1396

Filenames
 gdcmm::Sorter, 1093

FilenamesType
 gdcmm::DICOMDIRGenerator, 388
 gdcmm::Directory, 416
 gdcmm::FilenameGenerator, 538

FilenameType
 gdcmm::DICOMDIRGenerator, 388
 gdcmm::Directory, 416
 gdcmm::FilenameGenerator, 538

FileSet
 gdcmm::FileSet, 541

FileSize
 gdcmm::System, 1178

FileStreamer
 gdcmm::FileStreamer, 545

FileType
 gdcmm::FileSet, 541

FileTime
 gdcmm::System, 1178

FileType
 gdcmm::FileSet, 541

FileWithName
 gdcmm::FileWithName, 550

Fill
 gdcmm::ByteValue, 250

FillFromDataSet
 gdcmm::FileMetaInformation, 525

FillMedicalImageInformation
 vtkGDCMImageReader, 1387
 vtkGDCMImageReader2, 1401
 vtkGDCMPolyDataReader, 1426

FindContext
 gdcmm::network::ULConnection, 1312

FindCSAElementByName
 gdcmm::CSAHeader, 322

FindDataElement
 gdcmm::DataSet, 363
 gdcmm::Item, 673
 gdcmm::SequenceOfItems, 1050

FindDictEntry
 gdcmm::PrivateDict, 936

FindMacroEntry
 gdcmm::Macro, 737

FindModuleEntryInMacros
 gdcmm::Module, 775

FindMrProtocolByName
 gdcmm::MrProtocol, 793

FindNextDataElement
 gdcmm::DataSet, 363

FindPatientRootQuery
 gdcmm::FindPatientRootQuery, 553

FindPDBElementByName
 gdcmm::PDBHeader, 860

FindStudyRootQuery
 gdcmm::FindStudyRootQuery, 557

FirstRender
 vtkImageColorViewer, 1461

FL
 gdcmm::VR, 1371

FLOAT16
 gdcmm::PixelFormat, 880

FLOAT32
 gdcmm::PixelFormat, 880

FLOAT64
 gdcmm::PixelFormat, 880

ForceRescale
 vtkGDCMImageReader, 1396
 vtkGDCMImageReader2, 1411

FormatDateTime
 gdcmm::System, 1178

Fragment
 gdcmm::Fragment, 562

FragmentVector
 gdcmm::SequenceOfFragments, 1040

FromString
 gdcmm::StringFilter, 1140

FUJI
 gdcmm::EquipmentManufacturer, 481

FujiPrivateCRImageStorage
 gdcmm::MediaStorage, 749

FujiPrivateMammoCRImageStorage
 gdcmm::MediaStorage, 750

gdcmm, 43
 add1, 63

- AEComp, [58](#)
- ASComp, [58](#)
- backslash, [63](#)
- BOOL_FUNCTION_PFILE_PFILE_POINTER, [58](#)
- Clamp, [63](#)
- clean, [63](#)
- CompOperators, [60](#)
- CSComp, [58](#)
- DAComp, [58](#)
- doround, [63](#)
- DTComp, [59](#)
- eArabic, [61](#)
- ECharSet, [61](#)
- eCreateMMPS, [61](#)
- eCyrillic, [61](#)
- eFind, [62](#)
- eGB18030, [61](#)
- eGreek, [61](#)
- eHebrew, [61](#)
- eImage, [62](#)
- eJapanese, [61](#)
- eJapaneseKanjiMultibyte, [61](#)
- eJapaneseSupplementaryKanjiMultibyte, [61](#)
- eKoreanHangulHanjaMultibyte, [61](#)
- eLatin1, [61](#)
- eLatin2, [61](#)
- eLatin3, [61](#)
- eLatin4, [61](#)
- eLatin5, [61](#)
- eMove, [62](#)
- ENQueryType, [61](#)
- ePatient, [62](#)
- ePatientRootType, [62](#)
- EQueryLevel, [61](#)
- EQueryType, [62](#)
- ERootType, [62](#)
- eSeries, [62](#)
- eSetMMPS, [61](#)
- eStudy, [62](#)
- eStudyRootType, [62](#)
- eThai, [61](#)
- eUTF8, [61](#)
- eWLMFind, [62](#)
- FileList, [59](#)
- GDCM_DIFFERENT, [61](#)
- GDCM_EQUAL, [61](#)
- GDCM_GREATER, [61](#)
- GDCM_GREATEROREQUAL, [61](#)
- GDCM_LESS, [61](#)
- GDCM_LESSEOREQUAL, [61](#)
- GetVRFromTag, [63](#)
- GlobalInstance, [74](#)
- IconImage, [59](#)
- LD_ALL, [62](#)
- LD_NOSEQ, [62](#)
- LD_NOSHADOW, [62](#)
- LD_NOSHADOWSEQ, [62](#)
- LOComp, [59](#)
- LodModeType, [62](#)
- LTComp, [59](#)
- MacroEntry, [59](#)
- NestedMacroEntries, [59](#)
- operator!=, [64](#)
- operator<<, [64–72](#)
- operator>>, [72, 73](#)
- operator==, [72](#)
- PNComp, [59](#)
- Round, [73](#)
- roundat, [73](#)
- SHComp, [60](#)
- STComp, [60](#)
- TMComp, [60](#)
- UCComp, [60](#)
- UIComp, [60](#)
- URComp, [60](#)
- UTComp, [60](#)
- x16printf, [73](#)
- GDCM Documentation, [1](#)
- gdcmm::AbortEvent, [99](#)
- gdcmm::AnonymizeEvent, [103](#)
 - ~AnonymizeEvent, [105](#)
- AnonymizeEvent, [105](#)
- CheckEvent, [105](#)
- GetEventName, [105](#)
- GetTag, [105](#)
- MakeObject, [105](#)
- operator=, [106](#)
- Self, [104](#)
- SetTag, [106](#)
- Superclass, [104](#)
- gdcmm::Anonymizer, [106](#)
 - ~Anonymizer, [110](#)
- Anonymizer, [110](#)
- BALCPPProtect, [110](#)
- BasicApplicationLevelConfidentialityProfile, [110](#)
- CanEmptyTag, [110](#)
- Clear, [110](#)
- ClearInternalUIDs, [111](#)
- Empty, [111](#)
- GetBasicApplicationLevelConfidentialityProfileAttributes, [111](#)
- GetCryptographicMessageSyntax, [111](#)
- GetFile, [112](#)
- New, [112](#)
- RecurseDataSet, [112](#)
- Remove, [112](#)
- RemoveGroupLength, [112](#)
- RemovePrivateTags, [113](#)

- RemoveRetired, [113](#)
- Replace, [113](#), [114](#)
- SetCryptographicMessageSyntax, [114](#)
- SetFile, [114](#)
- gdcmm::AnyEvent, [115](#)
- gdcmm::ApplicationEntity, [118](#)
 - Internal, [120](#)
 - IsValid, [119](#)
 - MaxLength, [120](#)
 - MaxNumberOfComponents, [120](#)
 - Padding, [120](#)
 - Print, [119](#)
 - Separator, [120](#)
 - SetBlob, [119](#)
 - Squeeze, [119](#)
- gdcmm::ASN1, [126](#)
 - ~ASN1, [127](#)
 - ASN1, [127](#)
 - operator=, [127](#)
 - ParseDump, [127](#)
 - ParseDumpFile, [127](#)
 - TestPBKDF2, [128](#)
- gdcmm::Attribute< Group, Element, TVR, TVM >, [129](#)
 - ArrayType, [131](#)
 - GDCM_STATIC_ASSERT, [132](#)
 - GetAsDataElement, [132](#)
 - GetDictVM, [133](#)
 - GetDictVR, [133](#)
 - GetNumberOfValues, [133](#)
 - GetTag, [133](#)
 - GetValue, [134](#)
 - GetValues, [134](#)
 - GetVM, [134](#)
 - GetVR, [135](#)
 - Internal, [138](#)
 - operator!=, [135](#)
 - operator<, [135](#)
 - operator==, [135](#)
 - operator[], [135](#), [136](#)
 - Print, [136](#)
 - Set, [136](#)
 - SetByteValue, [136](#)
 - SetByteValueNoSwap, [136](#)
 - SetFromDataElement, [137](#)
 - SetFromDataSet, [137](#)
 - SetValue, [137](#)
 - SetValues, [138](#)
 - VMType, [132](#)
- gdcmm::Attribute< Group, Element, TVR, VM::VM1 >, [139](#)
 - ArrayType, [141](#)
 - GDCM_STATIC_ASSERT, [142](#)
 - GetAsDataElement, [142](#)
 - GetDictVM, [142](#)
 - GetDictVR, [143](#)
 - GetNumberOfValues, [143](#)
 - GetTag, [143](#)
 - GetValue, [143](#)
 - GetValues, [143](#)
 - GetVM, [143](#)
 - GetVR, [144](#)
 - Internal, [146](#)
 - operator!=, [144](#)
 - operator<, [144](#)
 - operator==, [144](#)
 - operator[], [144](#)
 - Print, [144](#)
 - Set, [145](#)
 - SetByteValue, [145](#)
 - SetByteValueNoSwap, [145](#)
 - SetFromDataElement, [145](#)
 - SetFromDataSet, [145](#)
 - SetValue, [146](#)
 - SetValues, [146](#)
 - VMType, [142](#)
- gdcmm::Attribute< Group, Element, TVR, VM::VM1_3 >, [147](#)
 - ArrayType, [149](#)
 - GDCM_STATIC_ASSERT, [149](#)
 - GetAsDataElement, [149](#)
 - GetDictVM, [149](#)
 - GetDictVR, [149](#)
 - GetNumberOfValues, [150](#)
 - GetTag, [150](#)
 - GetValue, [150](#)
 - GetValues, [150](#)
 - GetVM, [150](#)
 - GetVR, [150](#)
 - Internal, [152](#)
 - operator!=, [150](#)
 - operator<, [150](#)
 - operator==, [150](#)
 - operator[], [151](#)
 - Print, [151](#)
 - Set, [151](#)
 - SetByteValue, [151](#)
 - SetByteValueNoSwap, [151](#)
 - SetFromDataElement, [151](#)
 - SetFromDataSet, [151](#)
 - SetValue, [151](#)
 - SetValues, [152](#)
- gdcmm::Attribute< Group, Element, TVR, VM::VM1_8 >, [152](#)
 - ArrayType, [154](#)
 - GDCM_STATIC_ASSERT, [155](#)
 - GetAsDataElement, [155](#)
 - GetDictVM, [155](#)
 - GetDictVR, [155](#)
 - GetNumberOfValues, [155](#)

- GetTag, [155](#)
- GetValue, [155](#)
- GetValues, [155](#)
- GetVM, [156](#)
- GetVR, [156](#)
- Internal, [158](#)
- operator!=, [156](#)
- operator<, [156](#)
- operator==, [156](#)
- operator[], [156](#)
- Print, [156](#)
- Set, [156](#)
- SetByteValue, [157](#)
- SetByteValueNoSwap, [157](#)
- SetFromDataElement, [157](#)
- SetFromDataSet, [157](#)
- SetValue, [157](#)
- SetValues, [157](#)
- gdcml::Attribute< Group, Element, TVR, VM::VM1_n >, [158](#)
 - ~Attribute, [161](#)
 - ArrayType, [160](#)
 - Attribute, [161](#)
 - GDCM_STATIC_ASSERT, [161](#)
 - GetAsDataElement, [161](#)
 - GetDictVM, [161](#)
 - GetDictVR, [162](#)
 - GetNumberOfValues, [162](#)
 - GetTag, [162](#)
 - GetValue, [162](#)
 - GetValues, [162](#)
 - GetVM, [163](#)
 - GetVR, [163](#)
 - operator!=, [163](#)
 - operator<, [163](#)
 - operator==, [163](#)
 - operator[], [163](#)
 - Print, [164](#)
 - Set, [164](#)
 - SetByteValue, [164](#)
 - SetByteValueNoSwap, [164](#)
 - SetFromDataElement, [164](#)
 - SetFromDataSet, [164](#)
 - SetNumberOfValues, [165](#)
 - SetValue, [165](#)
 - SetValues, [165](#)
- gdcml::Attribute< Group, Element, TVR, VM::VM2_2n >, [166](#)
 - ArrayType, [169](#)
 - GDCM_STATIC_ASSERT, [169](#)
 - GetAsDataElement, [169](#)
 - GetDictVM, [170](#)
 - GetDictVR, [170](#)
 - GetNumberOfValues, [170](#)
- GetTag, [170](#)
- GetValue, [170](#)
- GetValues, [170](#)
- GetVM, [170](#)
- GetVR, [170](#)
- Internal, [172](#)
- operator!=, [170](#)
- operator<, [171](#)
- operator==, [171](#)
- operator[], [171](#)
- Print, [171](#)
- Set, [171](#)
- SetByteValue, [171](#)
- SetByteValueNoSwap, [171](#)
- SetFromDataElement, [171](#)
- SetFromDataSet, [172](#)
- SetValue, [172](#)
- SetValues, [172](#)
- gdcml::Attribute< Group, Element, TVR, VM::VM2_n >, [173](#)
 - ArrayType, [175](#)
 - GDCM_STATIC_ASSERT, [175](#)
 - GetAsDataElement, [175](#)
 - GetDictVM, [175](#)
 - GetDictVR, [175](#)
 - GetNumberOfValues, [176](#)
 - GetTag, [176](#)
 - GetValue, [176](#)
 - GetValues, [176](#)
 - GetVM, [176](#)
 - GetVR, [176](#)
 - Internal, [178](#)
 - operator!=, [176](#)
 - operator<, [176](#)
 - operator==, [176](#)
 - operator[], [177](#)
 - Print, [177](#)
 - Set, [177](#)
 - SetByteValue, [177](#)
 - SetByteValueNoSwap, [177](#)
 - SetFromDataElement, [177](#)
 - SetFromDataSet, [177](#)
 - SetValue, [177](#)
 - SetValues, [178](#)
- gdcml::Attribute< Group, Element, TVR, VM::VM3_3n >, [178](#)
 - ArrayType, [181](#)
 - GDCM_STATIC_ASSERT, [182](#)
 - GetAsDataElement, [182](#)
 - GetDictVM, [182](#)
 - GetDictVR, [182](#)
 - GetNumberOfValues, [182](#)
 - GetTag, [182](#)
 - GetValue, [182](#)

- GetValues, [182](#)
- GetVM, [183](#)
- GetVR, [183](#)
- Internal, [185](#)
- operator!=, [183](#)
- operator<, [183](#)
- operator==, [183](#)
- operator[], [183](#)
- Print, [183](#)
- Set, [183](#)
- SetByteValue, [184](#)
- SetByteValueNoSwap, [184](#)
- SetFromDataElement, [184](#)
- SetFromDataSet, [184](#)
- SetValue, [184](#)
- SetValues, [184](#)
- gdcmm::Attribute< Group, Element, TVR, VM::VM3_n >, [185](#)
- ArrayType, [187](#)
- GDCM_STATIC_ASSERT, [188](#)
- GetAsDataElement, [188](#)
- GetDictVM, [188](#)
- GetDictVR, [188](#)
- GetNumberOfValues, [188](#)
- GetTag, [188](#)
- GetValue, [188](#)
- GetValues, [188](#)
- GetVM, [188](#)
- GetVR, [189](#)
- Internal, [190](#)
- operator!=, [189](#)
- operator<, [189](#)
- operator==, [189](#)
- operator[], [189](#)
- Print, [189](#)
- Set, [189](#)
- SetByteValue, [189](#)
- SetByteValueNoSwap, [190](#)
- SetFromDataElement, [190](#)
- SetFromDataSet, [190](#)
- SetValue, [190](#)
- SetValues, [190](#)
- gdcmm::AudioCodec, [191](#)
- ~AudioCodec, [192](#)
- AudioCodec, [192](#)
- CanCode, [193](#)
- CanDecode, [193](#)
- Decode, [193](#)
- gdcmm::Base64, [193](#)
- Base64, [194](#)
- Decode, [194](#)
- Encode, [194](#)
- GetDecodeLength, [195](#)
- GetEncodeLength, [195](#)
- operator=, [195](#)
- gdcmm::BaseQuery, [202](#)
- ~BaseQuery, [204](#)
- AddQueryDataSet, [204](#)
- BaseQuery, [204](#)
- GetAbstractSyntaxUID, [204](#)
- GetQueryDataSet, [205](#)
- GetSOPInstanceUID, [205](#)
- mDataSet, [207](#)
- mSopInstanceUID, [207](#)
- Print, [205](#)
- QueryFactory, [206](#)
- SetSearchParameter, [205](#)
- SetSOPInstanceUID, [206](#)
- ValidateQuery, [206](#)
- ValidDataSet, [206](#)
- WriteHelpFile, [206](#)
- WriteQuery, [206](#)
- gdcmm::BaseRootQuery, [207](#)
- ~BaseRootQuery, [209](#)
- BaseRootQuery, [209](#)
- Construct, [210](#)
- GetQueryLevelFromQueryRoot, [210](#)
- GetQueryLevelFromString, [210](#)
- GetQueryLevelString, [210](#)
- GetTagListByLevel, [210](#)
- InitializeDataSet, [210](#)
- mHelpDescription, [211](#)
- mImage, [211](#)
- mPatient, [212](#)
- mRootType, [212](#)
- mSeries, [212](#)
- mStudy, [212](#)
- QueryFactory, [211](#)
- ValidateQuery, [211](#)
- gdcmm::BasicOffsetTable, [216](#)
- BasicOffsetTable, [219](#)
- operator<<, [219](#)
- Read, [219](#)
- gdcmm::Bitmap, [220](#)
- ~Bitmap, [223](#)
- AreOverlaysInPixelData, [223](#)
- Bitmap, [223](#)
- Clear, [223](#)
- ComputeLossyFlag, [223](#)
- Dimensions, [223](#)
- GetBuffer, [224](#)
- GetBuffer2, [224](#)
- GetBufferLength, [224](#)
- GetColumns, [224](#)
- GetDataElement, [224](#)
- GetDimension, [225](#)
- GetDimensions, [225](#)
- GetLUT, [225](#)

- GetNeedByteSwap, [225](#)
- GetNumberOfDimensions, [226](#)
- GetPhotometricInterpretation, [226](#)
- GetPixelFormat, [226](#)
- GetPlanarConfiguration, [226](#)
- GetRows, [227](#)
- GetTransferSyntax, [227](#)
- ImageChangeTransferSyntax, [232](#)
- IsEmpty, [227](#)
- IsLossy, [227](#)
- IsTransferSyntaxCompatible, [227](#)
- LossyFlag, [233](#)
- LUT, [233](#)
- LUTPtr, [223](#)
- NeedByteSwap, [233](#)
- NumberOfDimensions, [233](#)
- PF, [233](#)
- PI, [233](#)
- PixelData, [234](#)
- PixmapReader, [232](#)
- PlanarConfiguration, [234](#)
- Print, [227](#)
- SetColumns, [228](#)
- SetDataElement, [228](#)
- SetDimension, [228](#)
- SetDimensions, [228](#)
- SetLossyFlag, [229](#)
- SetLUT, [229](#)
- SetNeedByteSwap, [229](#)
- SetNumberOfDimensions, [229](#)
- SetPhotometricInterpretation, [229](#)
- SetPixelFormat, [230](#)
- SetPlanarConfiguration, [230](#)
- SetRows, [230](#)
- SetTransferSyntax, [230](#)
- TryJPEG2000Codec, [231](#)
- TryJPEG2000Codec2, [231](#)
- TryJPEGCodec, [231](#)
- TryJPEGCodec2, [231](#)
- TryJPEGLSCodec, [231](#)
- TryKAKADUCodec, [231](#)
- TryPVRGCodec, [232](#)
- TryRAWCodec, [232](#)
- TryRLECodec, [232](#)
- TS, [234](#)
- UnusedBitsPresentInPixelData, [232](#)
- gdcm::BitmapToBitmapFilter, [234](#)
- ~BitmapToBitmapFilter, [236](#)
- BitmapToBitmapFilter, [236](#)
- GetOutput, [236](#)
- GetOutputAsBitmap, [236](#)
- Input, [236](#)
- Output, [236](#)
- SetInput, [236](#)
- gdcm::BoxRegion, [237](#)
- ~BoxRegion, [239](#)
- Area, [239](#)
- BoundingBox, [239](#)
- BoxRegion, [239](#)
- Clone, [239](#)
- ComputeBoundingBox, [240](#)
- Empty, [240](#)
- GetXMax, [240](#)
- GetXMin, [240](#)
- GetYMax, [240](#)
- GetYMin, [240](#)
- GetZMax, [240](#)
- GetZMin, [241](#)
- IsValid, [241](#)
- operator=, [241](#)
- Print, [241](#)
- SetDomain, [241](#)
- gdcm::ByteBuffer, [242](#)
- ByteBuffer, [242](#)
- Get, [242](#)
- GetStart, [242](#)
- ShiftEnd, [242](#)
- UpdatePosition, [243](#)
- gdcm::ByteSwap< T >, [243](#)
- Swap, [243](#)
- SwapFromSwapCodeIntoSystem, [243](#)
- SwapRange, [244](#)
- SwapRangeFromSwapCodeIntoSystem, [244](#)
- SystemIsBigEndian, [244](#)
- SystemIsLittleEndian, [244](#)
- gdcm::ByteSwapFilter, [245](#)
- ~ByteSwapFilter, [245](#)
- ByteSwap, [246](#)
- ByteSwapFilter, [245](#), [246](#)
- operator=, [246](#)
- SetByteSwapTag, [246](#)
- gdcm::ByteValue, [247](#)
- ~ByteValue, [249](#)
- Append, [250](#)
- ByteValue, [249](#)
- Clear, [250](#)
- ComputeLength, [250](#)
- Fill, [250](#)
- GetBuffer, [250](#)
- GetLength, [250](#)
- GetPointer, [251](#)
- GetVoidPointer, [251](#)
- IsEmpty, [251](#)
- IsPrintable, [252](#)
- operator const std::vector< char > &, [252](#)
- operator=, [252](#)
- operator==, [252](#)
- Print, [252](#)

- PrintASCII, [253](#)
- PrintASCIIXML, [253](#)
- PrintGroupLength, [253](#)
- PrintHex, [253](#)
- PrintHexXML, [253](#)
- PrintPNXML, [253](#)
- Read, [253](#), [254](#)
- SetLength, [254](#)
- SetLengthOnly, [254](#)
- Write, [254](#)
- WriteBuffer, [255](#)
- gdcmm::CAPICryptoFactory, [255](#)
 - CAPICryptoFactory, [256](#)
 - CreateCMSProvider, [256](#)
- gdcmm::CAPICryptographicMessageSyntax, [257](#)
 - ~CAPICryptographicMessageSyntax, [258](#)
 - CAPICryptographicMessageSyntax, [258](#)
 - Decrypt, [258](#)
 - Encrypt, [258](#)
 - GetCipherType, [259](#)
 - GetInitialized, [259](#)
 - ParseCertificateFile, [259](#)
 - ParseKeyFile, [259](#)
 - SetCipherType, [259](#)
 - SetPassword, [259](#)
- gdcmm::Cleaner, [268](#)
 - ~Cleaner, [271](#)
 - Clean, [271](#)
 - Cleaner, [271](#)
 - CodedEntryData, [271](#)
 - Empty, [271](#), [272](#)
 - EmptyWhenScrubFails, [272](#)
 - GetFile, [272](#)
 - New, [272](#)
 - Preserve, [273](#)
 - Remove, [273](#)
 - RemoveAllGroupLength, [273](#)
 - RemoveAllIllegal, [274](#)
 - RemoveAllMissingPrivateCreator, [274](#)
 - RemoveMissingPrivateCreator, [274](#)
 - ReplaceCodeMeaning, [274](#)
 - Scrub, [274](#), [275](#)
 - SetFile, [275](#)
- gdcmm::Codec, [280](#)
- gdcmm::Coder, [281](#)
 - ~Coder, [282](#)
 - CanCode, [282](#)
 - Code, [282](#)
 - InternalCode, [282](#)
- gdcmm::CodeString, [283](#)
 - CodeString, [285](#), [286](#)
 - const_iterator, [284](#)
 - const_reference, [284](#)
 - const_reverse_iterator, [284](#)
 - difference_type, [284](#)
 - GetAsString, [286](#)
 - IsValid, [286](#)
 - iterator, [285](#)
 - operator!=, [287](#)
 - operator<<, [287](#)
 - operator==, [287](#)
 - pointer, [285](#)
 - reference, [285](#)
 - reverse_iterator, [285](#)
 - Size, [286](#)
 - size_type, [285](#)
 - TrimInternal, [286](#)
 - value_type, [285](#)
- gdcmm::Command, [287](#)
 - ~Command, [289](#)
 - Command, [289](#)
 - Execute, [290](#)
 - operator=, [290](#)
- gdcmm::CommandDataSet, [291](#)
 - ~CommandDataSet, [293](#)
 - CommandDataSet, [293](#)
 - Insert, [294](#)
 - operator<<, [295](#)
 - Read, [294](#)
 - Replace, [294](#)
 - Write, [294](#)
- gdcmm::CompositeNetworkFunctions, [296](#)
 - CEcho, [298](#)
 - CFind, [298](#)
 - CMove, [299](#)
 - ConstructQuery, [299](#), [300](#)
 - CStore, [300](#)
 - KeyValuePairArrayType, [297](#)
 - KeyValuePairType, [297](#)
- gdcmm::ConstCharWrapper, [301](#)
 - ConstCharWrapper, [301](#)
 - operator const char *, [301](#)
- gdcmm::CP246ExplicitDataElement, [302](#)
 - GetLength, [304](#)
 - Read, [304](#)
 - ReadPreValue, [305](#)
 - ReadValue, [305](#)
 - ReadWithLength, [305](#)
- gdcmm::CryptoFactory, [305](#)
 - ~CryptoFactory, [307](#)
 - CAPI, [306](#)
 - CreateCMSProvider, [307](#)
 - CryptoFactory, [307](#)
 - CryptoLib, [306](#)
 - DEFAULT, [306](#)
 - GetFactoryInstance, [307](#)
 - OPENSSL, [306](#)
 - OPENSSL7, [306](#)

- gdcmm::CryptographicMessageSyntax, 308
 - ~CryptographicMessageSyntax, 309
 - AES128_CIPHER, 309
 - AES192_CIPHER, 309
 - AES256_CIPHER, 309
 - CipherTypes, 308
 - CryptographicMessageSyntax, 309
 - Decrypt, 309
 - DES3_CIPHER, 309
 - Encrypt, 309
 - GetCipherType, 310
 - operator=, 310
 - ParseCertificateFile, 310
 - ParseKeyFile, 310
 - SetCipherType, 310
 - SetPassword, 311
- gdcmm::CSAElement, 311
 - CSAElement, 313
 - DataField, 318
 - DataPtr, 313
 - GetByteValue, 314
 - GetKey, 314
 - GetName, 314
 - GetNoOfItems, 314
 - GetSyngoDT, 314
 - GetValue, 315
 - GetVM, 315
 - GetVR, 315
 - IsEmpty, 315
 - KeyField, 318
 - NameField, 318
 - NoOfItemsField, 318
 - operator<, 316
 - operator<<, 318
 - operator=, 316
 - operator==, 316
 - SetByteValue, 316
 - SetKey, 316
 - SetName, 317
 - SetNoOfItems, 317
 - SetSyngoDT, 317
 - SetValue, 317
 - SetVM, 317
 - SetVR, 317
 - SyngoDTField, 318
 - ValueMultiplicityField, 319
 - VRField, 319
- gdcmm::CSAHeader, 319
 - ~CSAHeader, 321
 - CSAHeader, 321
 - CSAHeaderType, 321
 - DATASET_FORMAT, 321
 - FindCSAElementByName, 322
 - GetCSADatInfo, 322
 - GetCSAEEnd, 322
 - GetCSAElementByName, 322
 - GetCSAImageHeaderInfoTag, 322
 - GetCSASeriesHeaderInfoTag, 323
 - GetDataSet, 323
 - GetFormat, 323
 - GetInterfile, 323
 - GetMrProtocol, 323
 - INTERFILE, 321
 - LoadFromDataElement, 324
 - NOMAGIC, 321
 - operator<<, 324
 - Print, 324
 - SV10, 321
 - UNKNOWN, 321
 - ZEROED_OUT, 321
- gdcmm::CSAHeaderDict, 325
 - AddCSAHeaderDictEntry, 326
 - Begin, 326
 - ConstIterator, 325
 - CSAHeaderDict, 326
 - Dicts, 327
 - End, 326
 - GetCSAHeaderDictEntry, 326
 - IsEmpty, 327
 - Iterator, 325
 - LoadDefault, 327
 - MapCSAHeaderDictEntry, 326
 - operator<<, 327
 - operator=, 327
- gdcmm::CSAHeaderDictEntry, 328
 - CSAHeaderDictEntry, 329
 - GetDescription, 329
 - GetName, 329
 - GetVM, 329
 - GetVR, 329
 - operator<, 329
 - operator<<, 330
 - SetDescription, 330
 - SetName, 330
 - SetVM, 330
 - SetVR, 330
- gdcmm::CSAHeaderDictException, 331
- gdcmm::Curve, 334
 - ~Curve, 336
 - Curve, 336
 - Decode, 337
 - GetAsPoints, 337
 - GetCurveDataDescriptor, 337
 - GetDataValueRepresentation, 337
 - GetDimensions, 337
 - GetGroup, 337
 - GetNumberOfCurves, 337
 - GetNumberOfPoints, 337

- GetTypeInfoData, [337](#)
- GetTypeInfoDataDescription, [338](#)
- IsEmpty, [338](#)
- Print, [338](#)
- SetCoordinateStartValue, [338](#)
- SetCoordinateStepValue, [338](#)
- SetCurve, [338](#)
- SetCurveDataDescriptor, [338](#)
- SetCurveDescription, [338](#)
- SetDataValueRepresentation, [339](#)
- SetDimensions, [339](#)
- SetGroup, [339](#)
- SetNumberOfPoints, [339](#)
- SetTypeInfoData, [339](#)
- Update, [339](#)
- gdcm::DataElement, [340](#)
 - Clear, [343](#)
 - DataElement, [343](#)
 - Empty, [343](#)
 - GetByteValue, [343](#)
 - GetLength, [344](#)
 - GetSequenceOfFragments, [344](#)
 - GetTag, [344](#), [345](#)
 - GetValue, [345](#)
 - GetValueAsSQ, [345](#)
 - GetVL, [346](#)
 - GetVR, [346](#)
 - IsEmpty, [347](#)
 - IsUndefinedLength, [347](#)
 - operator<, [347](#)
 - operator<<, [352](#)
 - operator=, [348](#)
 - operator==, [348](#)
 - Read, [348](#)
 - ReadOrSkip, [348](#)
 - ReadPreValue, [348](#)
 - ReadValue, [349](#)
 - ReadValueWithLength, [349](#)
 - ReadWithLength, [349](#)
 - SetByteValue, [349](#)
 - SetTag, [350](#)
 - SetValue, [350](#)
 - SetValueFieldLength, [351](#)
 - SetVL, [351](#)
 - SetVLToUndefined, [351](#)
 - SetVR, [351](#)
 - TagField, [353](#)
 - ValueField, [353](#)
 - ValueLengthField, [353](#)
 - ValuePtr, [343](#)
 - VRField, [353](#)
 - Write, [352](#)
- gdcm::DataElementException, [354](#)
- gdcm::DataEvent, [354](#)
 - ~DataEvent, [356](#)
 - CheckEvent, [357](#)
 - DataEvent, [356](#), [357](#)
 - GetData, [357](#)
 - GetDataLength, [357](#)
 - GetEventName, [357](#)
 - MakeObject, [357](#)
 - operator=, [357](#)
 - Self, [356](#)
 - SetData, [358](#)
 - Superclass, [356](#)
- gdcm::DataSet, [358](#)
 - Begin, [362](#)
 - Clear, [362](#)
 - ComputeDataElement, [362](#)
 - ComputeGroupLength, [362](#)
 - ConstIterator, [361](#)
 - CSAHeader, [370](#)
 - DataElementSet, [361](#)
 - End, [362](#)
 - FindDataElement, [363](#)
 - FindNextDataElement, [363](#)
 - GetDataElement, [363](#), [364](#)
 - GetDEEnd, [364](#)
 - GetDES, [364](#)
 - GetLength, [365](#)
 - GetMediaStorage, [365](#)
 - GetPrivateCreator, [365](#)
 - GetPrivateTag, [365](#)
 - Insert, [365](#)
 - InsertDataElement, [366](#)
 - IsEmpty, [366](#)
 - Iterator, [361](#)
 - operator<<, [370](#)
 - operator(), [366](#)
 - operator=, [366](#)
 - operator[], [367](#)
 - Print, [367](#)
 - Read, [367](#)
 - ReadNested, [367](#)
 - ReadSelectedPrivateTags, [367](#)
 - ReadSelectedPrivateTagsWithLength, [367](#)
 - ReadSelectedTags, [368](#)
 - ReadSelectedTagsWithLength, [368](#)
 - ReadUpToTag, [368](#)
 - ReadUpToTagWithLength, [368](#)
 - ReadWithLength, [368](#)
 - Remove, [369](#)
 - Replace, [369](#)
 - ReplaceEmpty, [369](#)
 - Size, [369](#)
 - SizeType, [361](#)
 - Write, [370](#)
- gdcm::DataSetEvent, [371](#)

- ~DataSetEvent, [373](#)
- CheckEvent, [373](#)
- DataSetEvent, [373](#)
- GetDataSet, [373](#)
- GetEventName, [373](#)
- m_DataSet, [374](#)
- MakeObject, [373](#)
- operator=, [374](#)
- Self, [372](#)
- Superclass, [372](#)
- gdcmm::DataSetHelper, [374](#)
 - ComputeVR, [375](#)
- gdcmm::Decoder, [375](#)
 - ~Decoder, [376](#)
 - CanDecode, [376](#)
 - Decode, [376](#)
 - DecodeByStreams, [376](#)
- gdcmm::DefinedTerms, [377](#)
 - DefinedTerms, [377](#)
- gdcmm::Defs, [378](#)
 - ~Defs, [379](#)
 - Defs, [379](#)
 - GetIODFromFile, [379](#)
 - GetIODNameFromMediaStorage, [379](#)
 - GetIODs, [379](#)
 - GetMacros, [380](#)
 - GetModules, [380](#)
 - GetTypeFromTag, [380](#)
 - Global, [381](#)
 - IsEmpty, [380](#)
 - LoadDefaults, [381](#)
 - LoadFromFile, [381](#)
 - operator=, [381](#)
 - Verify, [381](#)
- gdcmm::DeltaEncodingCodec, [382](#)
 - ~DeltaEncodingCodec, [385](#)
 - CanDecode, [385](#)
 - Decode, [385](#)
 - DeltaEncodingCodec, [385](#)
- gdcmm::DICOMDIR, [385](#)
 - DICOMDIR, [386](#)
- gdcmm::DICOMDIRGenerator, [386](#)
 - ~DICOMDIRGenerator, [388](#)
 - AddImageDirectoryRecord, [388](#)
 - AddPatientDirectoryRecord, [388](#)
 - AddSeriesDirectoryRecord, [388](#)
 - AddStudyDirectoryRecord, [388](#)
 - DICOMDIRGenerator, [388](#)
 - FilenameType, [388](#)
 - FilenameType, [388](#)
 - Generate, [388](#)
 - GetFile, [389](#)
 - GetScanner, [389](#)
 - SetDescriptor, [389](#)
 - SetFile, [389](#)
 - SetFilenames, [389](#)
 - SetRootDirectory, [390](#)
- gdcmm::Dict, [390](#)
 - AddDictEntry, [392](#)
 - Begin, [392](#)
 - ConstIterator, [391](#)
 - Dict, [391](#)
 - Dicts, [394](#)
 - End, [392](#)
 - GetDictEntry, [392](#)
 - GetDictEntryByKeyword, [392](#)
 - GetDictEntryByName, [393](#)
 - GetKeywordFromTag, [393](#)
 - IsEmpty, [393](#)
 - Iterator, [391](#)
 - LoadDefault, [393](#)
 - MapDictEntry, [391](#)
 - operator<<, [394](#)
 - operator=, [393](#)
- gdcmm::DictConverter, [394](#)
 - ~DictConverter, [396](#)
 - AddGroupLength, [396](#)
 - Convert, [396](#)
 - ConvertToCXX, [396](#)
 - ConvertToXML, [396](#)
 - DICT_DEBUG, [396](#)
 - DICT_DEFAULT, [396](#)
 - DICT_XML, [396](#)
 - DictConverter, [396](#)
 - GetDictName, [396](#)
 - GetInputFilename, [397](#)
 - GetOutputFilename, [397](#)
 - GetOutputType, [397](#)
 - OutputTypes, [395](#)
 - Readuint16, [397](#)
 - ReadVM, [397](#)
 - ReadVR, [397](#)
 - SetDictName, [397](#)
 - SetInputFileName, [397](#)
 - SetOutputFileName, [398](#)
 - SetOutputType, [398](#)
 - WriteFooter, [398](#)
 - WriteHeader, [398](#)
- gdcmm::DictEntry, [398](#)
 - Dict, [402](#)
 - DictEntry, [400](#)
 - GetKeyword, [400](#)
 - GetName, [400](#)
 - GetRetired, [400](#)
 - GetVM, [400](#)
 - GetVR, [400](#)
 - IsUnique, [401](#)
 - operator<<, [402](#)

- SetElementXX, [401](#)
- SetGroupXX, [401](#)
- SetKeyword, [401](#)
- SetName, [401](#)
- SetRetired, [401](#)
- SetVM, [402](#)
- SetVR, [402](#)
- gdcm::DictPrinter, [403](#)
 - ~DictPrinter, [405](#)
 - DictPrinter, [405](#)
 - Print, [405](#)
 - PrintDataElement2, [405](#)
 - PrintDataSet2, [405](#)
- gdcm::Dicts, [406](#)
 - ~Dicts, [407](#)
 - ConstructorType, [407](#)
 - Dicts, [407](#)
 - GEMS, [407](#)
 - GetConstructorString, [408](#)
 - GetCSAHeaderDict, [408](#)
 - GetDictEntry, [408](#)
 - GetPrivateDict, [408](#)
 - GetPublicDict, [409](#)
 - Global, [409](#)
 - IsEmpty, [409](#)
 - LoadDefaults, [409](#)
 - operator<<, [409](#)
 - operator=, [409](#)
 - PHILIPS, [407](#)
 - SIEMENS, [407](#)
- gdcm::DirectionCosines, [411](#)
 - ~DirectionCosines, [413](#)
 - ComputeDistAlongNormal, [413](#)
 - Cross, [413](#)
 - CrossDot, [413](#)
 - DirectionCosines, [412](#)
 - Dot, [413](#)
 - IsValid, [414](#)
 - Norm, [414](#)
 - Normalize, [414](#)
 - operator const double *, [414](#)
 - Print, [414](#)
 - SetFromString, [414](#)
- gdcm::Directory, [415](#)
 - ~Directory, [416](#)
 - Directory, [416](#)
 - Explore, [417](#)
 - FilenameType, [416](#)
 - FilenameType, [416](#)
 - GetDirectories, [417](#)
 - GetFilenames, [417](#)
 - GetToplevel, [417](#)
 - Load, [417](#)
 - operator<<, [418](#)
 - Print, [418](#)
- gdcm::DirectoryHelper, [419](#)
 - GetCTImageSeriesUIDs, [419](#)
 - GetFilenamesFromSeriesUIDs, [419](#)
 - GetFrameOfReference, [419](#)
 - GetMRImageSeriesUIDs, [420](#)
 - GetRTStructSeriesUIDs, [420](#)
 - GetSeriesUIDsBySOPClassUID, [420](#)
 - GetSOPClassUID, [420](#)
 - GetStringValueFromTag, [420](#)
 - LoadImageFromFiles, [420](#)
 - RetrieveSOPInstanceUIDFromIndex, [420](#)
 - RetrieveSOPInstanceUIDFromZPosition, [421](#)
- gdcm::DPath, [421](#)
 - ~DPath, [422](#)
 - ConstructFromString, [422](#)
 - DPath, [422](#)
 - IsValid, [422](#)
 - Match, [422](#)
 - operator<, [422](#)
 - operator<<, [423](#)
 - Print, [423](#)
- gdcm::DummyValueGenerator, [423](#)
 - Generate, [424](#)
- gdcm::Dumper, [424](#)
 - ~Dumper, [426](#)
 - Dumper, [426](#)
- gdcm::Element< TVR, TVM >, [427](#)
 - GetAsDataElement, [429](#)
 - GetLength, [429](#)
 - GetValue, [430](#)
 - GetValues, [430](#)
 - GetVM, [430](#)
 - GetVR, [430](#)
 - Internal, [433](#)
 - operator[], [431](#)
 - Print, [431](#)
 - Read, [431](#)
 - Set, [431](#)
 - SetFromDataElement, [431](#)
 - SetNoSwap, [432](#)
 - SetValue, [432](#)
 - Type, [429](#)
 - Write, [432](#)
- gdcm::Element< TVR, VM::VM1_2 >, [433](#)
 - GetAsDataElement, [436](#)
 - GetLength, [436](#)
 - GetValue, [436](#)
 - GetValues, [436](#)
 - GetVM, [436](#)
 - GetVR, [436](#)
 - Internal, [438](#)
 - operator[], [437](#)
 - Parent, [436](#)

- Print, [437](#)
- Read, [437](#)
- Set, [437](#)
- SetFromDataElement, [437](#)
- SetLength, [437](#)
- SetNoSwap, [437](#)
- SetValue, [437](#)
- Type, [436](#)
- Write, [438](#)
- gdcmm::Element< TVR, VM::VM2_2n >, [438](#)
 - GetAsDataElement, [441](#)
 - GetLength, [441](#)
 - GetValue, [441](#)
 - GetValues, [441](#)
 - GetVM, [441](#)
 - GetVR, [441](#)
 - Internal, [443](#)
 - operator[], [442](#)
 - Parent, [441](#)
 - Print, [442](#)
 - Read, [442](#)
 - Set, [442](#)
 - SetFromDataElement, [442](#)
 - SetLength, [442](#)
 - SetNoSwap, [442](#)
 - SetValue, [442](#)
 - Type, [441](#)
 - Write, [443](#)
- gdcmm::Element< TVR, VM::VM3_3n >, [443](#)
 - GetAsDataElement, [446](#)
 - GetLength, [446](#)
 - GetValue, [446](#)
 - GetValues, [446](#)
 - GetVM, [446](#)
 - GetVR, [446](#)
 - Internal, [448](#)
 - operator[], [447](#)
 - Parent, [446](#)
 - Print, [447](#)
 - Read, [447](#)
 - Set, [447](#)
 - SetFromDataElement, [447](#)
 - SetLength, [447](#)
 - SetNoSwap, [447](#)
 - SetValue, [447](#)
 - Type, [446](#)
 - Write, [448](#)
- gdcmm::Element< TVR, VM::VM3_4 >, [448](#)
 - GetAsDataElement, [451](#)
 - GetLength, [451](#)
 - GetValue, [451](#)
 - GetValues, [451](#)
 - GetVM, [451](#)
 - GetVR, [451](#)
- Internal, [453](#)
- operator[], [452](#)
- Parent, [451](#)
- Print, [452](#)
- Read, [452](#)
- Set, [452](#)
- SetFromDataElement, [452](#)
- SetLength, [452](#)
- SetNoSwap, [452](#)
- SetValue, [452](#)
- Type, [451](#)
- Write, [453](#)
- gdcmm::Element< VR::AS, VM::VM5 >, [453](#)
 - GetAsDataElement, [455](#)
 - GetLength, [455](#)
 - GetValue, [455](#)
 - GetValues, [455](#)
 - GetVM, [455](#)
 - GetVR, [456](#)
 - Internal, [457](#)
 - operator[], [456](#)
 - Print, [456](#)
 - Read, [456](#)
 - Set, [456](#)
 - SetFromDataElement, [456](#)
 - SetNoSwap, [456](#)
 - SetValue, [456](#)
 - Type, [455](#)
 - Write, [457](#)
- gdcmm::Element< VR::OB, VM::VM1 >, [457](#)
 - GetAsDataElement, [460](#)
 - GetLength, [460](#)
 - GetValue, [460](#)
 - GetValues, [460](#)
 - GetVM, [460](#)
 - GetVR, [460](#)
 - Internal, [462](#)
 - operator[], [460](#)
 - Print, [461](#)
 - Read, [461](#)
 - Set, [461](#)
 - SetFromDataElement, [461](#)
 - SetNoSwap, [461](#)
 - SetValue, [461](#)
 - Type, [460](#)
 - Write, [461](#)
- gdcmm::Element< VR::OW, VM::VM1 >, [462](#)
 - GetAsDataElement, [465](#)
 - GetLength, [465](#)
 - GetValue, [465](#)
 - GetValues, [465](#)
 - GetVM, [465](#)
 - GetVR, [465](#)
 - Internal, [467](#)

- operator[], 465
- Print, 466
- Read, 466
- Set, 466
- SetFromDataElement, 466
- SetNoSwap, 466
- SetValue, 466
- Type, 465
- Write, 466
- gdcmm::ElementDisableCombinations< TVR, TVM >, 467
- gdcmm::ElementDisableCombinations< VR::OB, VM::VM1_n
>, 468
- gdcmm::ElementDisableCombinations< VR::OW, VM::VM1_n
>, 469
- gdcmm::EmptyMaskGenerator, 470
 - ~EmptyMaskGenerator, 471
 - EmptyMaskGenerator, 471
 - Execute, 471
 - SetInputDirectory, 471
 - SetOutputDirectory, 471
 - SetSOPClassUIDMode, 472
 - SOPClassUIDMode, 471
 - UseGrayscaleSecondaryImageStorage, 471
 - UseOriginalSOPClassUID, 471
- gdcmm::EncapsulatedDocument, 472
 - EncapsulatedDocument, 473
- gdcmm::EncodingImplementation< T >, 473
- gdcmm::EncodingImplementation< VR::VRASCII >, 474
 - Read, 475
 - ReadComputeLength, 475
 - ReadNoSwap, 475
 - Write, 475, 476
- gdcmm::EncodingImplementation< VR::VRBINARY >, 476
 - Read, 477
 - ReadComputeLength, 477
 - ReadNoSwap, 477
 - Write, 478
- gdcmm::EndEvent, 478
- gdcmm::EnumeratedValues, 479
 - EnumeratedValues, 480
- gdcmm::EquipmentManufacturer, 480
 - AGFA, 481
 - Compute, 481
 - FUJI, 481
 - GEMS, 481
 - HITACHI, 481
 - KODAK, 481
 - MARCONI, 481
 - PMS, 481
 - SAMSUNG, 481
 - SIEMENS, 481
 - TOSHIBA, 481
 - Type, 481
 - TypeToString, 481
 - UIH, 481
 - UNKNOWN, 481
- gdcmm::Event, 482
 - ~Event, 483
 - CheckEvent, 483
 - Event, 483
 - GetEventName, 483
 - MakeObject, 484
 - operator=, 484
 - Print, 484
- gdcmm::Exception, 485
 - ~Exception, 486
 - Exception, 486
 - GetDescription, 486
 - what, 486
- gdcmm::ExitEvent, 487
- gdcmm::ExplicitDataElement, 488
 - GetLength, 491
 - Read, 491
 - ReadPreValue, 491
 - ReadValue, 492
 - ReadWithLength, 492
 - Write, 492
- gdcmm::ExplicitImplicitDataElement, 492
 - GetLength, 495
 - Read, 495
 - ReadPreValue, 495
 - ReadValue, 496
 - ReadWithLength, 496
- gdcmm::Fiducials, 496
 - Fiducials, 497
- gdcmm::File, 497
 - ~File, 499
 - File, 499
 - GetDataSet, 499
 - GetHeader, 500
 - operator<<, 501
 - Read, 500
 - SetDataSet, 500
 - SetHeader, 501
 - Write, 501
- gdcmm::FileAnonymizer, 502
 - ~FileAnonymizer, 504
 - Empty, 504
 - FileAnonymizer, 504
 - Remove, 504
 - Replace, 505
 - SetInputFileName, 505
 - SetOutputFileName, 505
 - Write, 506
- gdcmm::FileChangeTransferSyntax, 506
 - ~FileChangeTransferSyntax, 508
 - Change, 509
 - FileChangeTransferSyntax, 508

- GetCodec, [509](#)
- New, [509](#)
- SetInputFileName, [509](#)
- SetOutputFileName, [509](#)
- SetTransferSyntax, [510](#)
- gdcmm::FileDecompressLookupTable, [510](#)
- ~FileDecompressLookupTable, [512](#)
- Change, [512](#)
- FileDecompressLookupTable, [512](#)
- GetFile, [512](#)
- GetPixmap, [513](#)
- SetFile, [513](#)
- SetPixmap, [513](#)
- gdcmm::FileDerivation, [513](#)
- ~FileDerivation, [514](#)
- AddDerivationDescription, [515](#)
- AddPurposeOfReferenceCodeSequence, [515](#)
- AddReference, [515](#)
- AddSourceImageSequence, [515](#)
- Derive, [515](#)
- FileDerivation, [514](#)
- GetFile, [515](#), [516](#)
- SetAppendDerivationHistory, [516](#)
- SetDerivationCodeSequenceCodeValue, [516](#)
- SetDerivationDescription, [516](#)
- SetFile, [516](#)
- SetPurposeOfReferenceCodeSequenceCodeValue, [517](#)
- gdcmm::FileExplicitFilter, [517](#)
- ~FileExplicitFilter, [518](#)
- Change, [518](#)
- ChangeFMI, [518](#)
- FileExplicitFilter, [518](#)
- GetFile, [519](#)
- ProcessDataSet, [519](#)
- SetChangePrivateTags, [519](#)
- SetFile, [519](#)
- SetRecomputeItemLength, [519](#)
- SetRecomputeSequenceLength, [520](#)
- SetUseVRUN, [520](#)
- gdcmm::FileMetaInformation, [520](#)
- ~FileMetaInformation, [524](#)
- AppendImplementationClassUID, [525](#)
- ComputeDataSetMediaStorageSOPClass, [525](#)
- ComputeDataSetTransferSyntax, [525](#)
- DataSetMS, [530](#)
- DataSetTS, [530](#)
- Default, [525](#)
- FileMetaInformation, [524](#), [525](#)
- FillFromDataSet, [525](#)
- GetDataSetTransferSyntax, [525](#)
- GetFileMetaInformationVersion, [526](#)
- GetFullLength, [526](#)
- GetGDCMImplementationClassUID, [526](#)
- GetGDCMImplementationVersionName, [526](#)
- GetGDCMSourceApplicationEntityTitle, [526](#)
- GetImplementationClassUID, [526](#)
- GetImplementationVersionName, [526](#)
- GetMediaStorage, [526](#)
- GetMediaStorageAsString, [527](#)
- GetMetaInformationTS, [527](#)
- GetPreamble, [527](#)
- GetSourceApplicationEntityTitle, [527](#)
- Insert, [527](#)
- IsValid, [527](#)
- MetaInformationTS, [530](#)
- operator<<, [529](#)
- operator=, [527](#)
- Read, [528](#)
- ReadCompat, [528](#)
- ReadCompatInternal, [528](#)
- Replace, [528](#)
- SetDataSetTransferSyntax, [528](#)
- SetImplementationClassUID, [528](#)
- SetImplementationVersionName, [529](#)
- SetPreamble, [529](#)
- SetSourceApplicationEntityTitle, [529](#)
- Write, [529](#)
- gdcmm::Filename, [530](#)
- EndWith, [531](#)
- Filename, [531](#)
- GetExtension, [531](#)
- GetFileName, [531](#)
- GetName, [531](#)
- GetPath, [532](#)
- IsEmpty, [532](#)
- IsIdentical, [532](#)
- Join, [532](#)
- operator const char *, [532](#)
- ToUnixSlashes, [532](#)
- ToWindowsSlashes, [533](#)
- gdcmm::FileNameEvent, [533](#)
- ~FileNameEvent, [535](#)
- CheckEvent, [536](#)
- FileNameEvent, [535](#)
- GetEventName, [536](#)
- GetFileName, [536](#)
- MakeObject, [536](#)
- operator=, [536](#)
- Self, [535](#)
- SetFileName, [536](#)
- Superclass, [535](#)
- gdcmm::FilenameGenerator, [537](#)
- ~FilenameGenerator, [538](#)
- FilenameGenerator, [538](#)
- FilenameType, [538](#)
- FilenameType, [538](#)
- Generate, [538](#)

- GetFilename, [538](#)
- GetFileNames, [539](#)
- GetNumberOfFileNames, [539](#)
- GetPattern, [539](#)
- GetPrefix, [539](#)
- SetNumberOfFileNames, [539](#)
- SetPattern, [539](#)
- SetPrefix, [540](#)
- SizeType, [538](#)
- gdcmm::FileSet, [540](#)
 - AddFile, [541](#)
 - FileSet, [541](#)
 - FilesType, [541](#)
 - FileType, [541](#)
 - GetFiles, [541](#)
 - operator<<, [542](#)
 - SetFiles, [542](#)
- gdcmm::FileStreamer, [542](#)
 - ~FileStreamer, [545](#)
 - AppendToDataElement, [545](#)
 - AppendToGroupDataElement, [545](#)
 - CheckDataElement, [545](#)
 - CheckTemplateFileName, [545](#)
 - FileStreamer, [545](#)
 - New, [546](#)
 - ReserveDataElement, [546](#)
 - ReserveGroupDataElement, [546](#)
 - SetOutputFileName, [546](#)
 - SetTemplateFileName, [546](#)
 - StartDataElement, [547](#)
 - StartGroupDataElement, [547](#)
 - StopDataElement, [547](#)
 - StopGroupDataElement, [547](#)
- gdcmm::FileWithName, [548](#)
 - filename, [550](#)
 - FileWithName, [550](#)
- gdcmm::FindPatientRootQuery, [551](#)
 - FindPatientRootQuery, [553](#)
 - GetAbstractSyntaxUID, [553](#)
 - GetTagListByLevel, [553](#)
 - InitializeDataSet, [554](#)
 - QueryFactory, [554](#)
 - ValidateQuery, [554](#)
- gdcmm::FindStudyRootQuery, [555](#)
 - FindStudyRootQuery, [557](#)
 - GetAbstractSyntaxUID, [557](#)
 - GetTagListByLevel, [557](#)
 - InitializeDataSet, [558](#)
 - QueryFactory, [558](#)
 - ValidateQuery, [558](#)
- gdcmm::Fragment, [559](#)
 - ComputeLength, [562](#)
 - Fragment, [562](#)
 - GetLength, [562](#)
 - operator<<, [563](#)
 - Read, [562](#)
 - ReadBacktrack, [562](#)
 - ReadPreValue, [562](#)
 - ReadValue, [563](#)
 - Write, [563](#)
- gdcmm::Global, [564](#)
 - ~Global, [565](#)
 - Append, [565](#)
 - GetDefs, [565](#)
 - GetDicts, [565](#), [566](#)
 - GetInstance, [566](#)
 - Global, [565](#)
 - LoadResourcesFiles, [566](#)
 - Locate, [566](#)
 - operator<<, [567](#)
 - operator=, [567](#)
 - Prepend, [567](#)
- gdcmm::GroupDict, [567](#)
 - ~GroupDict, [568](#)
 - Add, [569](#)
 - GetAbbreviation, [569](#)
 - GetName, [569](#)
 - GroupDict, [568](#)
 - GroupStringVector, [568](#)
 - Insert, [569](#)
 - operator<<, [570](#)
 - Size, [569](#)
- gdcmm::IconImageFilter, [570](#)
 - ~IconImageFilter, [571](#)
 - Extract, [572](#)
 - ExtractIconImages, [572](#)
 - ExtractVeprolIconImages, [572](#)
 - GetFile, [572](#)
 - GetIconImage, [572](#)
 - GetNumberOfIconImages, [572](#)
 - IconImageFilter, [571](#)
 - SetFile, [573](#)
- gdcmm::IconImageGenerator, [573](#)
 - ~IconImageGenerator, [574](#)
 - AutoPixelMinMax, [574](#)
 - ConvertRGBToPaletteColor, [574](#)
 - Generate, [575](#)
 - GetIconImage, [575](#)
 - GetPixmap, [575](#)
 - IconImageGenerator, [574](#)
 - SetOutputDimensions, [575](#)
 - SetOutsideValuePixel, [575](#)
 - SetPixelMinMax, [576](#)
 - SetPixmap, [576](#)
- gdcmm::ignore_char, [576](#)
 - ignore_char, [577](#)
 - m_char, [577](#)
- gdcmm::Image, [577](#)

- ~Image, 582
- GetDirectionCosines, 583
- GetIntercept, 583
- GetOrigin, 583
- GetSlope, 583
- GetSpacing, 583
- Image, 582
- Print, 584
- SetDirectionCosines, 584
- SetIntercept, 584
- SetOrigin, 584, 585
- SetSlope, 585
- SetSpacing, 585
- gdcmm::ImageApplyLookupTable, 586
 - ~ImageApplyLookupTable, 588
 - Apply, 589
 - ImageApplyLookupTable, 588
 - SetRGB8, 589
- gdcmm::ImageChangePhotometricInterpretation, 589
 - ~ImageChangePhotometricInterpretation, 592
 - Change, 592
 - ChangeMonochrome, 592
 - ChangeRGB2YBR, 592
 - ChangeYBR2RGB, 592
 - GetPhotometricInterpretation, 592
 - ImageChangePhotometricInterpretation, 592
 - RGB2YBR, 593
 - SetPhotometricInterpretation, 593
 - YBR2RGB, 593
- gdcmm::ImageChangePlanarConfiguration, 594
 - ~ImageChangePlanarConfiguration, 597
 - Change, 597
 - GetPlanarConfiguration, 597
 - ImageChangePlanarConfiguration, 597
 - RGBPixelsToRGBPlanes, 597
 - RGBPlanesToRGBPixels, 597
 - SetPlanarConfiguration, 598
- gdcmm::ImageChangeTransferSyntax, 598
 - ~ImageChangeTransferSyntax, 602
 - Change, 602
 - GetTransferSyntax, 602
 - ImageChangeTransferSyntax, 602
 - SetCompressIconImage, 603
 - SetForce, 603
 - SetTransferSyntax, 603
 - SetUserCodec, 603
 - TryJPEG2000Codec, 604
 - TryJPEGCodec, 604
 - TryJPEGLSCodec, 604
 - TryRAWCodec, 604
 - TryRLECodec, 604
- gdcmm::ImageCodec, 605
 - ~ImageCodec, 608
 - AppendFrameEncode, 608
 - AppendRowEncode, 608
 - CanCode, 609
 - CanDecode, 609
 - CleanupUnusedBits, 609
 - Clone, 609
 - Decode, 609
 - DecodeByStreams, 610
 - Dimensions, 616
 - DoByteSwap, 610
 - DoInvertMonochrome, 610
 - DoOverlayCleanup, 610
 - DoPaddedCompositePixelCode, 610
 - DoPlanarConfiguration, 610
 - DoSimpleCopy, 611
 - DoYBR, 611
 - DoYBRFull422, 611
 - FileChangeTransferSyntax, 615
 - GetDimensions, 611
 - GetHeaderInfo, 611
 - GetLossyFlag, 611
 - GetLUT, 611
 - GetNeedByteSwap, 612
 - GetNumberOfDimensions, 612
 - GetPhotometricInterpretation, 612
 - GetPixelFormat, 612
 - GetPlanarConfiguration, 612
 - ImageChangePhotometricInterpretation, 615
 - ImageCodec, 608
 - IsFrameEncoder, 612
 - IsLossy, 613
 - IsRowEncoder, 613
 - IsValid, 613
 - LossyFlag, 616
 - LUT, 616
 - LUTPtr, 608
 - NeedByteSwap, 616
 - NeedOverlayCleanup, 616
 - NumberOfDimensions, 616
 - PF, 616
 - PI, 617
 - PlanarConfiguration, 617
 - RequestPaddedCompositePixelCode, 617
 - RequestPlanarConfiguration, 617
 - SetDimensions, 613
 - SetLossyFlag, 613
 - SetLUT, 613
 - SetNeedByteSwap, 614
 - SetNeedOverlayCleanup, 614
 - SetNumberOfDimensions, 614
 - SetPhotometricInterpretation, 614
 - SetPixelFormat, 614
 - SetPlanarConfiguration, 615
 - StartEncode, 615
 - StopEncode, 615

- gdcm::ImageConverter, 617
 - ~ImageConverter, 618
 - Convert, 618
 - GetOutput, 618
 - ImageConverter, 618
 - SetInput, 618
- gdcm::ImageFragmentSplitter, 619
 - ~ImageFragmentSplitter, 621
 - GetFragmentSizeMax, 622
 - ImageFragmentSplitter, 621
 - SetForce, 622
 - SetFragmentSizeMax, 622
 - Split, 622
- gdcm::ImageHelper, 622
 - ComputeMediaStorageFromModality, 624
 - ComputeSpacingFromImagePositionPatient, 624
 - GetDimensionsValue, 624
 - GetDirectionCosinesFromDataSet, 624
 - GetDirectionCosinesValue, 625
 - GetForcePixelSpacing, 625
 - GetForceRescaleInterceptSlope, 625
 - GetLUT, 625
 - GetOriginValue, 625
 - GetPhotometricInterpretationValue, 625
 - GetPixelFormatValue, 625
 - GetPlanarConfigurationValue, 626
 - GetPMSRescaleInterceptSlope, 626
 - GetPointerFromElement, 626
 - GetRealWorldValueMappingContent, 626
 - GetRescaleInterceptSlopeValue, 626
 - GetSecondaryCaptureImagePlaneModule, 626
 - GetSpacingTagFromMediaStorage, 627
 - GetSpacingValue, 627
 - GetZSpacingTagFromMediaStorage, 627
 - SetDimensionsValue, 627
 - SetDirectionCosinesValue, 627
 - SetForcePixelSpacing, 627
 - SetForceRescaleInterceptSlope, 627
 - SetOriginValue, 628
 - SetPMSRescaleInterceptSlope, 628
 - SetRescaleInterceptSlopeValue, 628
 - SetSecondaryCaptureImagePlaneModule, 628
 - SetSpacingValue, 628
- gdcm::ImageReader, 629
 - ~ImageReader, 632
 - GetImage, 632
 - ImageReader, 632
 - Read, 633
 - ReadACRNEMAIImage, 633
 - ReadImage, 633
- gdcm::ImageRegionReader, 634
 - ~ImageRegionReader, 637
 - ComputeBufferLength, 638
 - GetRegion, 638
 - ImageRegionReader, 637
 - Read, 638
 - ReadInformation, 638
 - ReadIntoBuffer, 638
 - SetRegion, 639
- gdcm::ImageToImageFilter, 639
 - ~ImageToImageFilter, 641
 - GetInput, 641
 - GetOutput, 641
 - ImageToImageFilter, 641
- gdcm::ImageWriter, 642
 - ~ImageWriter, 645
 - ComputeTargetMediaStorage, 645
 - GetImage, 645, 646
 - ImageWriter, 645
 - Write, 646
- gdcm::ImplicitDataElement, 650
 - GetLength, 653
 - Read, 653
 - ReadPreValue, 653
 - ReadValue, 653
 - ReadValueWithLength, 653
 - ReadWithLength, 653
 - Write, 653
- gdcm::InitializeEvent, 654
- gdcm::IOD, 655
 - AddIODEntry, 657
 - Clear, 657
 - GetIODEntry, 657
 - GetNumberOfIODs, 657
 - GetTypeFromTag, 657
 - IOD, 657
 - MapIODEntry, 656
 - operator<<, 658
 - SizeType, 656
- gdcm::IODEntry, 658
 - GetIE, 659
 - GetName, 659
 - GetRef, 660
 - GetUsage, 660
 - GetUsageType, 660
 - IODEntry, 659
 - operator<<, 661
 - SetIE, 660
 - SetName, 660
 - SetRef, 660
 - SetUsage, 660
- gdcm::IODs, 661
 - AddIOD, 663
 - Begin, 663
 - Clear, 663
 - End, 663
 - GetIOD, 663
 - IODMapType, 662

- IODMapTypeConstIterator, 662
- IODName, 662
- IODs, 662
- operator<=, 663
- gdcm::IPPSorter, 664
 - ComputeZSpacing, 669
 - DirCosTolerance, 669
 - DropDuplicatePositions, 669
 - GetDirectionCosinesTolerance, 666
 - GetZSpacing, 666
 - GetZSpacingTolerance, 667
 - IPPSorter, 666
 - SetComputeZSpacing, 667
 - SetDirectionCosinesTolerance, 667
 - SetDropDuplicatePositions, 668
 - SetZSpacingTolerance, 668
 - Sort, 668
 - ZSpacing, 669
 - ZTolerance, 669
- gdcm::Item, 670
 - Clear, 673
 - FindDataElement, 673
 - GetDataElement, 674
 - GetLength, 674
 - GetNestedDataSet, 674
 - InsertDataElement, 674
 - Item, 673
 - operator<=, 675
 - Read, 674
 - SetNestedDataSet, 675
 - Write, 675
- gdcm::IterationEvent, 676
- gdcm::JPEG12Codec, 677
 - ~JPEG12Codec, 681
 - DecodeByStreams, 681
 - EncodeBuffer, 681
 - GetHeaderInfo, 681
 - InternalCode, 681
 - IsStateSuspension, 681
 - JPEG12Codec, 681
- gdcm::JPEG16Codec, 682
 - ~JPEG16Codec, 686
 - DecodeByStreams, 686
 - EncodeBuffer, 686
 - GetHeaderInfo, 686
 - InternalCode, 686
 - IsStateSuspension, 686
 - JPEG16Codec, 686
- gdcm::JPEG2000Codec, 687
 - ~JPEG2000Codec, 690
 - AppendFrameEncode, 690
 - AppendRowEncode, 690
 - Bitmap, 694
 - CanCode, 691
 - CanDecode, 691
 - Clone, 691
 - Code, 691
 - Decode, 691
 - DecodeByStreams, 692
 - DecodeExtent, 692
 - GetHeaderInfo, 692
 - GetQuality, 692
 - GetRate, 692
 - ImageRegionReader, 694
 - IsFrameEncoder, 693
 - IsRowEncoder, 693
 - JPEG2000Codec, 690
 - SetMCT, 693
 - SetNumberOfResolutions, 693
 - SetNumberOfThreadsForDecompression, 693
 - SetQuality, 693
 - SetRate, 693
 - SetReversible, 694
 - SetTitleSize, 694
 - StartEncode, 694
 - StopEncode, 694
- gdcm::JPEG8Codec, 695
 - ~JPEG8Codec, 699
 - DecodeByStreams, 699
 - EncodeBuffer, 699
 - GetHeaderInfo, 699
 - InternalCode, 699
 - IsStateSuspension, 699
 - JPEG8Codec, 699
- gdcm::JPEGCodec, 700
 - ~JPEGCodec, 704
 - AppendFrameEncode, 704
 - AppendRowEncode, 704
 - BitSample, 709
 - CanCode, 704
 - CanDecode, 704
 - Clone, 705
 - Code, 705
 - ComputeOffsetTable, 705
 - Decode, 705
 - DecodeByStreams, 705
 - DecodeExtent, 706
 - EncodeBuffer, 706
 - GetHeaderInfo, 706
 - GetLossless, 706
 - GetQuality, 706
 - ImageRegionReader, 708
 - IsFrameEncoder, 707
 - IsRowEncoder, 707
 - IsStateSuspension, 707
 - IsValid, 707
 - JPEGCodec, 704
 - Quality, 709

- SetBitSample, [707](#)
- SetLossless, [707](#)
- SetPixelFormat, [707](#)
- SetQuality, [708](#)
- StartEncode, [708](#)
- StopEncode, [708](#)
- gdcm::JPEGLSCodec, [709](#)
 - ~JPEGLSCodec, [712](#)
 - AppendFrameEncode, [713](#)
 - AppendRowEncode, [713](#)
 - CanCode, [713](#)
 - CanDecode, [713](#)
 - Clone, [713](#)
 - Code, [714](#)
 - Decode, [714](#)
 - DecodeExtent, [714](#)
 - GetBufferLength, [714](#)
 - GetHeaderInfo, [715](#)
 - GetLossless, [715](#)
 - ImageRegionReader, [716](#)
 - IsFrameEncoder, [715](#)
 - IsRowEncoder, [715](#)
 - JPEGLSCodec, [712](#)
 - SetBufferLength, [715](#)
 - SetLossless, [715](#)
 - SetLossyError, [715](#)
 - StartEncode, [715](#)
 - StopEncode, [716](#)
- gdcm::JSON, [716](#)
 - ~JSON, [717](#)
 - Code, [717](#)
 - Decode, [717](#)
 - GetPrettyPrint, [717](#)
 - JSON, [717](#)
 - PrettyPrintOff, [717](#)
 - PrettyPrintOn, [718](#)
 - SetPrettyPrint, [718](#)
- gdcm::KAKADUCodec, [718](#)
 - ~KAKADUCodec, [721](#)
 - CanCode, [721](#)
 - CanDecode, [721](#)
 - Clone, [721](#)
 - Code, [721](#)
 - Decode, [722](#)
 - KAKADUCodec, [721](#)
- gdcm::LO, [722](#)
 - const_iterator, [724](#)
 - const_reference, [724](#)
 - const_reverse_iterator, [724](#)
 - difference_type, [724](#)
 - IsValid, [725](#)
 - iterator, [724](#)
 - LO, [725](#)
 - pointer, [724](#)
 - reference, [724](#)
 - reverse_iterator, [724](#)
 - size_type, [724](#)
 - Superclass, [724](#)
 - value_type, [725](#)
- gdcm::LookupTable, [726](#)
 - ~LookupTable, [728](#)
 - Allocate, [729](#)
 - BitSample, [733](#)
 - BLUE, [728](#)
 - Clear, [729](#)
 - Decode, [729](#)
 - Decode8, [729](#)
 - GetBitSample, [730](#)
 - GetBufferAsRGBA, [730](#)
 - GetLUT, [730](#)
 - GetLUTDescriptor, [730](#)
 - GetLUTLength, [730](#)
 - GetPointer, [730](#)
 - GRAY, [728](#)
 - GREEN, [728](#)
 - IncompleteLUT, [733](#)
 - InitializeBlueLUT, [731](#)
 - Initialized, [731](#)
 - InitializeGreenLUT, [731](#)
 - InitializeLUT, [731](#)
 - InitializeRedLUT, [731](#)
 - Internal, [733](#)
 - IsRGB8, [731](#)
 - LookupTable, [728](#), [729](#)
 - LookupTableType, [728](#)
 - Print, [732](#)
 - RED, [728](#)
 - SetBlueLUT, [732](#)
 - SetGreenLUT, [732](#)
 - SetLUT, [732](#)
 - SetRedLUT, [732](#)
 - UNKNOWN, [728](#)
 - WriteBufferAsRGBA, [732](#)
- gdcm::Macro, [736](#)
 - AddMacroEntry, [737](#)
 - ArrayIncludeMacrosType, [736](#)
 - Clear, [737](#)
 - FindMacroEntry, [737](#)
 - GetMacroEntry, [737](#)
 - GetName, [737](#)
 - Macro, [737](#)
 - MapModuleEntry, [736](#)
 - operator<<, [738](#)
 - SetName, [737](#)
 - Verify, [738](#)
- gdcm::Macros, [738](#)
 - AddMacro, [739](#)
 - Clear, [739](#)

- GetMacro, [740](#)
- IsEmpty, [740](#)
- Macros, [739](#)
- ModuleMapType, [739](#)
- operator<<, [740](#)
- gdcmm::MD5, [742](#)
 - Compute, [742](#)
 - ComputeFile, [742](#)
- gdcmm::MEC_MR3, [743](#)
 - GetCanonMECMR3Tag, [743](#)
 - GetPMTFInformationDataTag, [743](#)
 - GetToshibaMECMR3Tag, [743](#)
 - Print, [744](#)
- gdcmm::MediaStorage, [744](#)
 - AmbulatoryECGWaveformStorage, [748](#)
 - Audio, [750](#)
 - BasicTextSR, [749](#)
 - BasicVoiceAudioWaveformStorage, [748](#)
 - BreastProjectionXRayImageStorageForPresentation, [750](#)
 - BreastProjectionXRayImageStorageForProcessing, [750](#)
 - BreastTomosynthesisImageStorage, [749](#)
 - CardiacElectrophysiologyWaveformStorage, [748](#)
 - ComprehensiveSR, [749](#)
 - ComputedRadiographylImageStorage, [748](#)
 - CSANonImageStorage, [749](#)
 - CTImageStorage, [748](#)
 - DetachedPatientManagementSOPClass, [749](#)
 - DetachedStudyManagementSOPClass, [749](#)
 - DetachedVisitManagementSOPClass, [749](#)
 - DigitalIntraoralXRayImageStorageForPresentation, [748](#)
 - DigitalIntraoralXRayImageStorageForProcessing, [748](#)
 - DigitalMammographylImageStorageForPresentation, [748](#)
 - DigitalMammographylImageStorageForProcessing, [748](#)
 - DigitalXRayImageStorageForPresentation, [748](#)
 - DigitalXRayImageStorageForProcessing, [748](#)
 - EncapsulatedCDASStorage, [749](#)
 - EncapsulatedPDFStorage, [749](#)
 - EnhancedCTImageStorage, [748](#)
 - EnhancedMRColorImageStorage, [750](#)
 - EnhancedMRIImageStorage, [748](#)
 - EnhancedPETImageStorage, [749](#)
 - EnhancedSR, [749](#)
 - EnhancedUSVolumeStorage, [749](#)
 - EnhancedXAImageStorage, [749](#)
 - FujiPrivateCRImageStorage, [749](#)
 - FujiPrivateMammoCRImageStorage, [750](#)
 - GeneralECGWaveformStorage, [748](#)
 - GeneralElectricMagneticResonanceImageStorage, [749](#)
 - GEPrivate3DModelStorage, [749](#)
 - GetModality, [751](#)
 - GetModalityDimension, [751](#)
 - GetMSString, [751](#)
 - GetMSType, [751](#)
 - GetNumberOfModality, [751](#)
 - GetNumberOfMSString, [751](#)
 - GetNumberOfMSType, [751](#)
 - GetString, [752](#)
 - GrayscaleSoftcopyPresentationStateStorageSOPClass, [748](#)
 - GuessFromModality, [752](#)
 - HangingProtocolStorage, [749](#)
 - HardcopyColorImageStorage, [750](#)
 - HardcopyGrayscaleImageStorage, [749](#)
 - HemodynamicWaveformStorage, [748](#)
 - IsImage, [752](#)
 - IsUndefined, [752](#)
 - IVOCTForPresentation, [750](#)
 - IVOCTForProcessing, [750](#)
 - KeyObjectSelectionDocument, [749](#)
 - LeadECGWaveformStorage, [748](#)
 - LegacyConvertedEnhancedCTImageStorage, [750](#)
 - LegacyConvertedEnhancedMRIImageStorage, [750](#)
 - LegacyConvertedEnhancedPETImageStorage, [750](#)
 - MammographyCADSR, [749](#)
 - MediaStorage, [750](#)
 - MediaStorageDirectoryStorage, [748](#)
 - ModalityPerformedProcedureStepSOPClass, [749](#)
 - MRIImageStorage, [748](#)
 - MRSpectroscopyStorage, [748](#)
 - MS_END, [750](#)
 - MSType, [747](#)
 - MultiframeGrayscaleByteSecondaryCaptureImageStorage, [748](#)
 - MultiframeGrayscaleWordSecondaryCaptureImageStorage, [748](#)
 - MultiframeSingleBitSecondaryCaptureImageStorage, [748](#)
 - MultiframeTrueColorSecondaryCaptureImageStorage, [748](#)
 - NoObject, [750](#)
 - NuclearMedicineImageStorage, [748](#)
 - NuclearMedicineImageStorageRetired, [748](#)
 - ObjectEnd, [750](#)
 - ObjectType, [750](#)
 - operator MSType, [752](#)
 - operator<<, [754](#)
 - OphthalmicPhotography16BitImageStorage, [750](#)
 - OphthalmicPhotography8BitImageStorage, [749](#)
 - OphthalmicTomographylImageStorage, [749](#)
 - PDF, [750](#)

- PETImageStorage, [748](#)
- Philips3D, [749](#)
- PhilipsPrivateMRSyntheticImageStorage, [749](#)
- RawDataStorage, [748](#)
- RTDoseStorage, [749](#)
- RTImageStorage, [748](#)
- RTIonBeamsTreatmentRecordStorage, [749](#)
- RTIonPlanStorage, [749](#)
- RTPlanStorage, [749](#)
- RTStructureSetStorage, [749](#)
- RTTreatmentSummaryRecordStorage, [749](#)
- SecondaryCaptureImageStorage, [748](#)
- Segmentation, [750](#)
- SegmentationStorage, [749](#)
- SetFromDataSet, [753](#)
- SetFromFile, [753](#)
- SetFromHeader, [753](#)
- SetFromModality, [753](#)
- SetFromSourceImageSequence, [753](#)
- SpacialFiducialsStorage, [748](#)
- SpacialRegistrationStorage, [748](#)
- StandaloneCurveStorage, [748](#)
- StandaloneModalityLUTStorage, [748](#)
- StandaloneOverlayStorage, [748](#)
- StandaloneVOILUTStorage, [748](#)
- StudyComponentManagementSOPClass, [749](#)
- SurfaceSegmentationStorage, [749](#)
- ToshibaPrivateDataStorage, [749](#)
- UltrasoundImageStorage, [748](#)
- UltrasoundImageStorageRetired, [748](#)
- UltrasoundMultiFrameImageStorage, [748](#)
- UltrasoundMultiFrameImageStorageRetired, [748](#)
- URI, [750](#)
- Video, [750](#)
- VideoEndoscopicImageStorage, [749](#)
- VideoMicroscopicImageStorage, [750](#)
- VideoPhotographicImageStorage, [749](#)
- VLEndoscopicImageStorage, [749](#)
- VLMicroscopicImageStorage, [749](#)
- VLPhotographicImageStorage, [749](#)
- VLWholeSlideMicroscopyImageStorage, [749](#)
- Waveform, [750](#)
- XRay3DAngiographicImageStorage, [749](#)
- XRay3DCraniofacialImageStorage, [750](#)
- XRayAngiographicBiPlanarImageStorageRetired, [748](#)
- XRayAngiographicImageStorage, [748](#)
- XRayRadiationDoseSR, [749](#)
- XRayRadiofluoroscopicImageStorage, [748](#)
- gdcm::MemberCommand< T >, [754](#)
 - ~MemberCommand, [757](#)
 - Execute, [758](#)
 - m_ConstMemberFunction, [759](#)
 - m_MemberFunction, [759](#)
 - m_This, [759](#)
 - MemberCommand, [757](#)
 - New, [758](#)
 - operator=, [758](#)
 - Self, [757](#)
 - SetCallbackFunction, [758](#), [759](#)
 - TConstMemberFunctionPointer, [757](#)
 - TMemberFunctionPointer, [757](#)
- gdcm::MeshPrimitive, [760](#)
 - ~MeshPrimitive, [763](#)
 - AddPrimitiveData, [763](#)
 - EDGE, [762](#)
 - FACET, [762](#)
 - GetMPType, [763](#)
 - GetMPTypeString, [763](#)
 - GetNumberOfPrimitivesData, [763](#)
 - GetPrimitiveData, [763](#), [764](#)
 - GetPrimitivesData, [764](#)
 - GetPrimitiveType, [764](#)
 - LINE, [762](#)
 - MeshPrimitive, [763](#)
 - MPType, [762](#)
 - MPType_END, [762](#)
 - PrimitiveData, [765](#)
 - PrimitivesData, [762](#)
 - PrimitiveType, [765](#)
 - SetPrimitiveData, [764](#)
 - SetPrimitivesData, [764](#)
 - SetPrimitiveType, [764](#)
 - TRIANGLE, [762](#)
 - TRIANGLE_FAN, [762](#)
 - TRIANGLE_STRIP, [762](#)
 - VERTEX, [762](#)
- gdcm::ModalityPerformedProcedureStepCreateQuery, [765](#)
 - GetAbstractSyntaxUID, [768](#)
 - GetRequiredDataSet, [768](#)
 - ModalityPerformedProcedureStepCreateQuery, [767](#)
 - QueryFactory, [768](#)
 - ValidateQuery, [768](#)
- gdcm::ModalityPerformedProcedureStepSetQuery, [769](#)
 - GetAbstractSyntaxUID, [771](#)
 - GetRequiredDataSet, [771](#)
 - ModalityPerformedProcedureStepSetQuery, [771](#)
 - QueryFactory, [772](#)
 - ValidateQuery, [771](#)
- gdcm::ModifiedEvent, [772](#)
- gdcm::Module, [773](#)
 - AddMacro, [775](#)
 - AddModuleEntry, [775](#)
 - ArrayIncludeMacrosType, [774](#)
 - Clear, [775](#)
 - FindModuleEntryInMacros, [775](#)
 - GetModuleEntryInMacros, [775](#)
 - GetName, [776](#)

- MapModuleEntry, [774](#)
- Module, [775](#)
- operator<<, [776](#)
- SetName, [776](#)
- Verify, [776](#)
- gdcmmodule::ModuleEntry, [777](#)
 - ~ModuleEntry, [779](#)
 - DataElementType, [780](#)
 - Description, [778](#)
 - DescriptionField, [780](#)
 - GetDescription, [779](#)
 - GetName, [779](#)
 - GetType, [779](#)
 - ModuleEntry, [779](#)
 - Name, [781](#)
 - operator<<, [780](#)
 - SetDescription, [779](#)
 - SetName, [780](#)
 - SetType, [780](#)
- gdcmmodule::Modules, [781](#)
 - AddModule, [782](#)
 - Clear, [782](#)
 - GetModule, [783](#)
 - IsEmpty, [783](#)
 - ModuleMapType, [782](#)
 - Modules, [782](#)
 - operator<<, [783](#)
- gdcmmodule::MovePatientRootQuery, [784](#)
 - GetAbstractSyntaxUID, [786](#)
 - GetTagListByLevel, [786](#)
 - InitializeDataSet, [787](#)
 - MovePatientRootQuery, [786](#)
 - QueryFactory, [787](#)
 - ValidateQuery, [787](#)
- gdcmmodule::MoveStudyRootQuery, [788](#)
 - GetAbstractSyntaxUID, [790](#)
 - GetTagListByLevel, [790](#)
 - InitializeDataSet, [791](#)
 - MoveStudyRootQuery, [790](#)
 - QueryFactory, [791](#)
 - ValidateQuery, [791](#)
- gdcmmodule::MrProtocol, [792](#)
 - ~MrProtocol, [792](#)
 - FindMrProtocolByName, [793](#)
 - GetMrProtocolByName, [793](#)
 - GetSliceArray, [793](#)
 - GetVersion, [793](#)
 - Load, [793](#)
 - MrProtocol, [792](#)
 - operator<<, [794](#)
 - Print, [793](#)
- gdcmmodule::MrProtocol::Slice, [1080](#)
 - Normal, [1081](#)
 - Position, [1081](#)
- gdcmmodule::MrProtocol::SliceArray, [1081](#)
 - Slices, [1082](#)
- gdcmmodule::MrProtocol::Vector3, [1356](#)
 - dCor, [1356](#)
 - dSag, [1356](#)
 - dTra, [1356](#)
- gdcmmodule::NestedModuleEntries, [803](#)
 - AddModuleEntry, [805](#)
 - GetModuleEntry, [805](#)
 - GetNumberOfModuleEntries, [806](#)
 - NestedModuleEntries, [805](#)
 - operator<<, [806](#)
 - SizeType, [805](#)
- gdcmmodule::network, [74](#)
 - cMaxEventID, [80](#)
 - cMaxStateID, [80](#)
 - eAABORTPDUReturnedOpen, [79](#)
 - eAABORTRequest, [79](#)
 - eAASSOCIATE_RQPDUReturned, [78](#)
 - eAASSOCIATERequestLocalUser, [78](#)
 - eAASSOCIATEResponseAccept, [78](#)
 - eAASSOCIATEResponseReject, [78](#)
 - eARELEASE_RPPDUReturned, [79](#)
 - eARELEASE_RQPDUReturnedOpen, [79](#)
 - eARELEASERequest, [79](#)
 - eARELEASEResponse, [79](#)
 - eARTIMTimerExpired, [79](#)
 - eASSOCIATE_ACPDUReturned, [78](#)
 - eASSOCIATE_RJPDUReturned, [78](#)
 - eEventDoesNotExist, [79](#)
 - EEventID, [78](#)
 - ePDATArequest, [78](#)
 - ePDATATFPDU, [78](#)
 - eSta10ReleaseCollisionAc, [79](#)
 - eSta11ReleaseCollisionRq, [79](#)
 - eSta12ReleaseCollisionAcLocal, [79](#)
 - eSta13AwaitingClose, [79](#)
 - eSta1Idle, [79](#)
 - eSta2Open, [79](#)
 - eSta3WaitLocalAssoc, [79](#)
 - eSta4LocalAssocDone, [79](#)
 - eSta5WaitRemoteAssoc, [79](#)
 - eSta6TransferReady, [79](#)
 - eSta7WaitRelease, [79](#)
 - eSta8WaitLocalRelease, [79](#)
 - eSta9ReleaseCollisionRqLocal, [79](#)
 - eStaDoesNotExist, [79](#)
 - EStateID, [79](#)
 - eTransportConnConfirmLocal, [78](#)
 - eTransportConnectionClosed, [79](#)
 - eTransportConnIndicLocal, [78](#)
 - eUnrecognizedPDUReturned, [79](#)
 - GetStateIndex, [79](#)
- gdcmmodule::network::AAabortPDU, [85](#)

- AAAbortPDU, [86](#)
- IsLastFragment, [86](#)
- Print, [86](#)
- Read, [86](#)
- SetReason, [87](#)
- SetSource, [87](#)
- Size, [87](#)
- Write, [87](#)
- gdcmm::network::AAAssociateACPDU, [88](#)
 - AAAssociateACPDU, [89](#)
 - AAAssociateRQPDU, [91](#)
 - AddPresentationContextAC, [90](#)
 - GetNumberOfPresentationContextAC, [90](#)
 - GetPresentationContextAC, [90](#)
 - GetUserInformation, [90](#)
 - InitFromRQ, [90](#)
 - IsLastFragment, [90](#)
 - Print, [90](#)
 - Read, [90](#)
 - SetCalledAETitle, [91](#)
 - SetCallingAETitle, [91](#)
 - Size, [91](#)
 - SizeType, [89](#)
 - Write, [91](#)
- gdcmm::network::AAAssociateRJPDU, [92](#)
 - AAAssociateRJPDU, [93](#)
 - IsLastFragment, [93](#)
 - Print, [93](#)
 - Read, [93](#)
 - Size, [93](#)
 - Write, [93](#)
- gdcmm::network::AAAssociateRQPDU, [94](#)
 - AAAssociateACPDU, [99](#)
 - AAAssociateRQPDU, [96](#)
 - AddPresentationContext, [96](#)
 - GetCalledAETitle, [96](#)
 - GetCallingAETitle, [96](#)
 - GetNumberOfPresentationContext, [97](#)
 - GetPresentationContext, [97](#)
 - GetPresentationContextByAbstractSyntax, [97](#)
 - GetPresentationContextByID, [97](#)
 - GetPresentationContexts, [97](#)
 - GetReserved43_74, [97](#)
 - GetUserInformation, [97](#)
 - IsAETitleValid, [97](#)
 - IsLastFragment, [98](#)
 - PresentationContextArrayType, [96](#)
 - Print, [98](#)
 - Read, [98](#)
 - SetCalledAETitle, [98](#)
 - SetCallingAETitle, [98](#)
 - SetUserInformation, [98](#)
 - Size, [98](#)
 - SizeType, [96](#)
 - Write, [99](#)
- gdcmm::network::AbstractSyntax, [100](#)
 - AbstractSyntax, [101](#)
 - GetAsDataElement, [101](#)
 - GetName, [101](#)
 - operator==, [101](#)
 - Print, [101](#)
 - Read, [102](#)
 - SetName, [102](#)
 - SetNameFromUID, [102](#)
 - Size, [102](#)
 - Write, [102](#)
- gdcmm::network::ApplicationContext, [116](#)
 - ApplicationContext, [117](#)
 - GetName, [117](#)
 - Print, [117](#)
 - Read, [117](#)
 - SetName, [117](#)
 - Size, [117](#)
 - Write, [117](#)
- gdcmm::network::AReleaseRPPDU, [120](#)
 - AReleaseRPPDU, [121](#)
 - IsLastFragment, [121](#)
 - Print, [121](#)
 - Read, [122](#)
 - Size, [122](#)
 - Write, [122](#)
- gdcmm::network::AReleaseRQPDU, [122](#)
 - AReleaseRQPDU, [124](#)
 - IsLastFragment, [124](#)
 - Print, [124](#)
 - Read, [124](#)
 - Size, [124](#)
 - Write, [124](#)
- gdcmm::network::ARTIMTimer, [125](#)
 - ARTIMTimer, [125](#)
 - GetElapsedTime, [125](#)
 - GetHasExpired, [125](#)
 - GetTimeout, [126](#)
 - SetTimeout, [126](#)
 - Start, [126](#)
 - Stop, [126](#)
- gdcmm::network::AsynchronousOperationsWindowSub, [128](#)
 - AsynchronousOperationsWindowSub, [128](#)
 - Print, [129](#)
 - Read, [129](#)
 - Size, [129](#)
 - Write, [129](#)
- gdcmm::network::BaseCompositeMessage, [196](#)
 - ~BaseCompositeMessage, [197](#)
 - ConstructPDV, [197](#)
- gdcmm::network::BaseNormalizedMessage, [197](#)
 - ~BaseNormalizedMessage, [199](#)

- ConstructPDV, 199
- gdcmm::network::BasePDU, 200
 - ~BasePDU, 201
 - IsLastFragment, 201
 - Print, 201
 - Read, 201
 - Size, 201
 - Write, 202
- gdcmm::network::CEchoRQ, 260
 - AffectedSOPClassUID, 262
 - ConstructPDV, 262
 - MessageID, 262
- gdcmm::network::CEchoRSP, 262
 - ConstructPDVByDataSet, 263
- gdcmm::network::CFind, 263
- gdcmm::network::CFindCancelRQ, 264
 - ConstructPDVByDataSet, 265
- gdcmm::network::CFindRQ, 265
 - ConstructPDV, 266
- gdcmm::network::CFindRSP, 267
 - ConstructPDVByDataSet, 268
- gdcmm::network::CMoveCancelRq, 275
 - ConstructPDVByDataSet, 276
- gdcmm::network::CMoveRQ, 277
 - ConstructPDV, 278
- gdcmm::network::CMoveRSP, 278
 - ConstructPDVByDataSet, 279
- gdcmm::network::CompositeMessageFactory, 295
 - ConstructCEchoRQ, 296
 - ConstructCFindRQ, 296
 - ConstructCMoveRQ, 296
 - ConstructCStoreRQ, 296
 - ConstructCStoreRSP, 296
- gdcmm::network::CStoreRQ, 331
 - ConstructPDV, 333
- gdcmm::network::CStoreRSP, 333
 - ConstructPDV, 334
- gdcmm::network::DIMSE, 410
 - C_CANCEL_RQ, 411
 - C_ECHO_RQ, 411
 - C_ECHO_RSP, 411
 - C_FIND_RQ, 411
 - C_FIND_RSP, 411
 - C_GET_RQ, 411
 - C_GET_RSP, 411
 - C_MOVE_RQ, 411
 - C_MOVE_RSP, 411
 - C_STORE_RQ, 411
 - C_STORE_RSP, 411
 - CommandTypes, 411
 - N_ACTION_RQ, 411
 - N_ACTION_RSP, 411
 - N_CREATE_RQ, 411
 - N_CREATE_RSP, 411
- N_DELETE_RQ, 411
- N_DELETE_RSP, 411
- N_EVENT_REPORT_RQ, 411
- N_EVENT_REPORT_RSP, 411
- N_GET_RQ, 411
- N_GET_RSP, 411
- N_SET_RQ, 411
- N_SET_RSP, 411
- gdcmm::network::ImplementationClassUIDSub, 646
 - ImplementationClassUIDSub, 647
 - Print, 647
 - Read, 647
 - Size, 647
 - Write, 647
- gdcmm::network::ImplementationUIDSub, 648
 - ImplementationUIDSub, 648
 - Write, 648
- gdcmm::network::ImplementationVersionNameSub, 648
 - ImplementationVersionNameSub, 649
 - Print, 649
 - Read, 649
 - Size, 649
 - Write, 649
- gdcmm::network::MaximumLengthSub, 740
 - GetMaximumLength, 741
 - MaximumLengthSub, 741
 - Print, 741
 - Read, 741
 - SetMaximumLength, 741
 - Size, 741
 - Write, 741
- gdcmm::network::NActionRQ, 794
 - ConstructPDV, 795
- gdcmm::network::NActionRSP, 795
 - ConstructPDVByDataSet, 796
- gdcmm::network::NCreateRQ, 797
 - ConstructPDV, 798
- gdcmm::network::NCreateRSP, 798
 - ConstructPDVByDataSet, 799
- gdcmm::network::NDeleteRQ, 800
 - ConstructPDV, 801
- gdcmm::network::NDeleteRSP, 801
 - ConstructPDVByDataSet, 802
- gdcmm::network::NEventReportRQ, 806
 - ConstructPDV, 807
- gdcmm::network::NEventReportRSP, 808
 - ConstructPDVByDataSet, 809
- gdcmm::network::NGetRQ, 809
 - ConstructPDV, 810
- gdcmm::network::NGetRSP, 811
 - ConstructPDVByDataSet, 812
- gdcmm::network::NormalizedMessageFactory, 813
 - ConstructNAction, 813
 - ConstructNCreate, 813

- ConstructNDelete, [814](#)
- ConstructNEventReport, [814](#)
- ConstructNGet, [814](#)
- ConstructNSet, [814](#)
- gdcmm::network::NSetRQ, [817](#)
 - ConstructPDV, [818](#)
- gdcmm::network::NSetRSP, [818](#)
 - ConstructPDVByDataSet, [819](#)
- gdcmm::network::PDataTFPDU, [853](#)
 - AddPresentationDataValue, [855](#)
 - GetNumberOfPresentationDataValues, [855](#)
 - GetPresentationDataValue, [855](#)
 - IsLastFragment, [855](#)
 - PDataTFPDU, [854](#)
 - Print, [855](#)
 - Read, [855](#)
 - ReadInto, [855](#)
 - Size, [856](#)
 - SizeType, [854](#)
 - Write, [856](#)
- gdcmm::network::PDUFactory, [864](#)
 - ConstructAbortPDU, [865](#)
 - ConstructPDU, [865](#)
 - ConstructReleasePDU, [865](#)
 - CreateCEchoPDU, [866](#)
 - CreateCFindPDU, [866](#)
 - CreateCMovePDU, [866](#)
 - CreateCStoreRQPDU, [866](#)
 - CreateCStoreRSPDPDU, [866](#)
 - CreateNActionPDU, [866](#)
 - CreateNCreatePDU, [866](#)
 - CreateNDeletePDU, [867](#)
 - CreateNEventReportPDU, [867](#)
 - CreateNGetPDU, [867](#)
 - CreateNSetPDU, [867](#)
 - DetermineEventByPDU, [867](#)
 - GetPDVs, [867](#)
- gdcmm::network::PresentationContextAC, [918](#)
 - GetPresentationContextID, [919](#)
 - GetReason, [919](#)
 - GetTransferSyntax, [919](#)
 - PresentationContextAC, [919](#)
 - Print, [919](#)
 - Read, [920](#)
 - SetPresentationContextID, [920](#)
 - SetReason, [920](#)
 - SetTransferSyntax, [920](#)
 - Size, [920](#)
 - Write, [920](#)
- gdcmm::network::PresentationContextRQ, [924](#)
 - AddTransferSyntax, [925](#)
 - GetAbstractSyntax, [925](#)
 - GetNumberOfTransferSyntaxes, [925](#)
 - GetPresentationContextID, [925](#)
 - GetTransferSyntax, [926](#)
 - GetTransferSyntaxes, [926](#)
 - operator==, [926](#)
 - PresentationContextRQ, [925](#)
 - Print, [926](#)
 - Read, [926](#)
 - SetAbstractSyntax, [926](#)
 - SetPresentationContextID, [926](#)
 - Size, [927](#)
 - SizeType, [924](#)
 - Write, [927](#)
- gdcmm::network::PresentationDataValue, [927](#)
 - ConcatenatePDVBlobs, [928](#)
 - ConcatenatePDVBlobsAsExplicit, [928](#)
 - GetBlob, [928](#)
 - GetIsCommand, [928](#)
 - GetIsLastFragment, [928](#)
 - GetMessageHeader, [929](#)
 - GetPresentationContextID, [929](#)
 - PresentationDataValue, [928](#)
 - Print, [929](#)
 - Read, [929](#)
 - ReadInto, [929](#)
 - SetBlob, [929](#)
 - SetCommand, [929](#)
 - SetDataSet, [929](#)
 - SetLastFragment, [930](#)
 - SetMessageHeader, [930](#)
 - SetPresentationContextID, [930](#)
 - Size, [930](#)
 - Write, [930](#)
- gdcmm::network::RoleSelectionSub, [994](#)
 - Print, [995](#)
 - Read, [995](#)
 - RoleSelectionSub, [994](#)
 - SetTuple, [995](#)
 - Size, [995](#)
 - Write, [995](#)
- gdcmm::network::ServiceClassApplicationInformation, [1060](#)
 - Print, [1061](#)
 - Read, [1061](#)
 - ServiceClassApplicationInformation, [1060](#)
 - SetTuple, [1061](#)
 - Size, [1061](#)
 - Write, [1061](#)
- gdcmm::network::SOPClassExtendedNegotiationSub, [1086](#)
 - Print, [1086](#)
 - Read, [1086](#)
 - SetTuple, [1086](#)
 - Size, [1087](#)
 - SOPClassExtendedNegotiationSub, [1086](#)
 - Write, [1087](#)
- gdcmm::network::TableRow, [1190](#)

- ~TableRow, 1191
- TableRow, 1191
- transitions, 1191
- gdcmm::network::TransferSyntaxSub, 1221
 - GetName, 1222
 - operator==, 1222
 - Print, 1222
 - Read, 1222
 - SetName, 1222
 - SetNameFromUID, 1222
 - Size, 1222
 - TransferSyntaxSub, 1222
 - Write, 1223
- gdcmm::network::Transition, 1223
 - ~Transition, 1224
 - mAction, 1224
 - MakeNew, 1224
 - mEnd, 1224
 - Transition, 1224
- gdcmm::network::ULAction, 1268
 - ~ULAction, 1269
 - operator=, 1270
 - PerformAction, 1270
 - ULAction, 1269, 1270
- gdcmm::network::ULActionAA1, 1271
 - PerformAction, 1272
- gdcmm::network::ULActionAA2, 1272
 - PerformAction, 1273
- gdcmm::network::ULActionAA3, 1273
 - PerformAction, 1274
- gdcmm::network::ULActionAA4, 1275
 - PerformAction, 1276
- gdcmm::network::ULActionAA5, 1276
 - PerformAction, 1277
- gdcmm::network::ULActionAA6, 1277
 - PerformAction, 1278
- gdcmm::network::ULActionAA7, 1279
 - PerformAction, 1280
- gdcmm::network::ULActionAA8, 1280
 - PerformAction, 1281
- gdcmm::network::ULActionAE1, 1281
 - PerformAction, 1282
- gdcmm::network::ULActionAE2, 1283
 - PerformAction, 1284
- gdcmm::network::ULActionAE3, 1284
 - PerformAction, 1285
- gdcmm::network::ULActionAE4, 1285
 - PerformAction, 1286
- gdcmm::network::ULActionAE5, 1287
 - PerformAction, 1288
- gdcmm::network::ULActionAE6, 1288
 - PerformAction, 1289
- gdcmm::network::ULActionAE7, 1289
 - PerformAction, 1290
- gdcmm::network::ULActionAE8, 1291
 - PerformAction, 1292
- gdcmm::network::ULActionAR1, 1292
 - PerformAction, 1293
- gdcmm::network::ULActionAR10, 1293
 - PerformAction, 1294
- gdcmm::network::ULActionAR2, 1295
 - PerformAction, 1296
- gdcmm::network::ULActionAR3, 1296
 - PerformAction, 1297
- gdcmm::network::ULActionAR4, 1297
 - PerformAction, 1298
- gdcmm::network::ULActionAR5, 1299
 - PerformAction, 1300
- gdcmm::network::ULActionAR6, 1300
 - PerformAction, 1301
- gdcmm::network::ULActionAR7, 1301
 - PerformAction, 1302
- gdcmm::network::ULActionAR8, 1303
 - PerformAction, 1304
- gdcmm::network::ULActionAR9, 1304
 - PerformAction, 1305
- gdcmm::network::ULActionDT1, 1305
 - PerformAction, 1306
- gdcmm::network::ULActionDT2, 1307
 - PerformAction, 1308
- gdcmm::network::ULBasicCallback, 1308
 - ~ULBasicCallback, 1310
 - GetDataSets, 1310
 - GetResponses, 1310
 - HandleDataSet, 1310
 - HandleResponse, 1310
 - ULBasicCallback, 1310
- gdcmm::network::ULConnection, 1311
 - ~ULConnection, 1312
 - AddAcceptedPresentationContext, 1312
 - FindContext, 1312
 - GetAcceptedPresentationContexts, 1313
 - GetConnectionInfo, 1313
 - GetMaxPDUSize, 1313
 - GetPresentationContextACByID, 1313
 - GetPresentationContextIDFromPresentationContext, 1313
 - GetPresentationContextRQByID, 1313
 - GetPresentationContexts, 1313
 - GetProtocol, 1314
 - GetState, 1314
 - GetTimer, 1314
 - InitializeConnection, 1314
 - InitializeIncomingConnection, 1314
 - operator=, 1314
 - SetMaxPDUSize, 1314
 - SetPresentationContexts, 1314, 1315
 - SetState, 1315

- StopProtocol, [1315](#)
- ULActionAE6, [1315](#)
- ULConnection, [1312](#)
- ULConnectionManager, [1315](#)
- gdcmm::network::ULConnectionCallback, [1316](#)
 - ~ULConnectionCallback, [1317](#)
 - DataSetHandled, [1317](#)
 - DataSetHandles, [1317](#)
 - HandleDataSet, [1317](#)
 - HandleResponse, [1317](#)
 - mImplicit, [1318](#)
 - ResetHandledDataSet, [1317](#)
 - SetImplicitFlag, [1317](#)
 - ULConnectionCallback, [1317](#)
- gdcmm::network::ULConnectionInfo, [1318](#)
 - GetCalledAETitle, [1319](#)
 - GetCalledComputerName, [1319](#)
 - GetCalledIPAddress, [1319](#)
 - GetCalledIPPort, [1319](#)
 - GetCallingAETitle, [1319](#)
 - GetMaxPDULength, [1319](#)
 - Initialize, [1319](#)
 - SetMaxPDULength, [1319](#)
 - ULConnectionInfo, [1319](#)
- gdcmm::network::ULConnectionManager, [1320](#)
 - ~ULConnectionManager, [1323](#)
 - BreakConnection, [1323](#)
 - BreakConnectionNow, [1323](#)
 - EstablishConnection, [1323](#)
 - EstablishConnectionMove, [1324](#)
 - mConnection, [1327](#)
 - mSecondaryConnection, [1327](#)
 - mTransitions, [1327](#)
 - RunEventLoop, [1324](#)
 - RunMoveEventLoop, [1324](#)
 - SendEcho, [1324](#)
 - SendFind, [1324](#), [1325](#)
 - SendMove, [1325](#)
 - SendNAction, [1325](#)
 - SendNCreate, [1325](#)
 - SendNDelete, [1326](#)
 - SendNEventReport, [1326](#)
 - SendNGet, [1326](#)
 - SendNSet, [1326](#)
 - SendStore, [1327](#)
 - ULConnectionManager, [1323](#)
- gdcmm::network::ULError, [1328](#)
 - ~ULError, [1328](#)
 - GetDataSetPos, [1329](#)
 - GetEvent, [1329](#)
 - GetStream, [1329](#)
 - GetPDUs, [1329](#)
 - SetEvent, [1329](#)
 - SetPDU, [1329](#)
 - ULError, [1328](#)
- gdcmm::network::ULTransitionTable, [1329](#)
 - HandleEvent, [1330](#)
 - PrintTable, [1330](#)
 - ULTransitionTable, [1330](#)
- gdcmm::network::ULWritingCallback, [1331](#)
 - ~ULWritingCallback, [1332](#)
 - HandleDataSet, [1332](#)
 - HandleResponse, [1332](#)
 - SetDirectory, [1332](#)
 - ULWritingCallback, [1332](#)
- gdcmm::network::UserInformation, [1346](#)
 - ~UserInformation, [1347](#)
 - AddRoleSelectionSub, [1347](#)
 - AddSOPClassExtendedNegotiationSub, [1347](#)
 - GetMaximumLengthSub, [1347](#)
 - operator=, [1347](#)
 - Print, [1348](#)
 - Read, [1348](#)
 - Size, [1348](#)
 - UserInformation, [1347](#)
 - Write, [1348](#)
- gdcmm::NoEvent, [812](#)
- gdcmm::NormalizedNetworkFunctions, [814](#)
 - ConstructQuery, [815](#)
 - NAction, [815](#)
 - NCreate, [816](#)
 - NDelete, [816](#)
 - NEventReport, [816](#)
 - NGet, [816](#)
 - NSet, [816](#)
- gdcmm::Object, [820](#)
 - ~Object, [821](#)
 - Object, [821](#)
 - operator<=, [822](#)
 - operator=, [822](#)
 - Print, [822](#)
 - Register, [822](#)
 - SmartPointer, [822](#)
 - UnRegister, [822](#)
- gdcmm::OpenSSLCryptoFactory, [823](#)
 - CreateCMSProvider, [825](#)
 - InitOpenSSL, [825](#)
 - OpenSSLCryptoFactory, [824](#)
- gdcmm::OpenSSLCryptographicMessageSyntax, [825](#)
 - ~OpenSSLCryptographicMessageSyntax, [827](#)
 - Decrypt, [827](#)
 - Encrypt, [827](#)
 - GetCipherType, [827](#)
 - OpenSSLCryptographicMessageSyntax, [827](#)
 - ParseCertificateFile, [827](#)
 - ParseKeyFile, [828](#)
 - SetCipherType, [828](#)
 - SetPassword, [828](#)

- gdcm::OpenSSLP7CryptoFactory, 829
 - CreateCMSProvider, 830
 - OpenSSLP7CryptoFactory, 830
- gdcm::OpenSSLP7CryptographicMessageSyntax, 831
 - ~OpenSSLP7CryptographicMessageSyntax, 832
 - Decrypt, 832
 - Encrypt, 832
 - GetCipherType, 833
 - OpenSSLP7CryptographicMessageSyntax, 832
 - ParseCertificateFile, 833
 - ParseKeyFile, 833
 - SetCipherType, 833
 - SetPassword, 833
- gdcm::Orientation, 834
 - ~Orientation, 835
 - AXIAL, 835
 - CORONAL, 835
 - GetLabel, 836
 - GetMajorAxisFromPatientRelativeDirectionCosine, 836
 - GetObliquityThresholdCosineValue, 836
 - GetType, 836
 - OBLIQUE, 835
 - operator<=, 837
 - Orientation, 835
 - OrientationType, 835
 - Print, 836
 - SAGITTAL, 835
 - SetObliquityThresholdCosineValue, 836
 - UNKNOWN, 835
- gdcm::Overlay, 837
 - ~Overlay, 840
 - Decompress, 841
 - GetBitPosition, 841
 - GetBitsAllocated, 841
 - GetColumns, 841
 - GetDescription, 841
 - GetGroup, 841
 - GetOrigin, 842
 - GetOverlayData, 842
 - GetOverlayTypeAsString, 842
 - GetOverlayTypeFromString, 842
 - GetRows, 842
 - GetType, 842
 - GetTypeAsEnum, 842
 - GetUnpackBuffer, 843
 - GetUnpackBufferLength, 843
 - GrabOverlayFromPixelData, 843
 - Graphics, 840
 - Invalid, 840
 - IsEmpty, 843
 - IsInPixelData, 843
 - IsZero, 843
 - operator=, 844
 - Overlay, 840, 841
 - OverlayType, 840
 - Print, 844
 - ROI, 840
 - SetBitPosition, 844
 - SetBitsAllocated, 844
 - SetColumns, 844
 - SetDescription, 844
 - SetFrameOrigin, 845
 - SetGroup, 845
 - SetNumberOfFrames, 845
 - SetOrigin, 845
 - SetOverlay, 845
 - SetRows, 845
 - SetType, 846
 - Update, 846
- gdcm::ParseException, 846
 - ~ParseException, 848
 - GetLastElement, 848
 - operator=, 848
 - ParseException, 848
 - SetLastElement, 848
- gdcm::Parser, 849
 - ~Parser, 851
 - DuplicateAttributeError, 850
 - EndElementHandler, 850
 - ErrorType, 850
 - GetBuffer, 851
 - GetCurrentByteIndex, 851
 - GetErrorCode, 851
 - GetErrorString, 851
 - GetUserData, 851
 - JunkAfterDocElementError, 850
 - NoElementsError, 850
 - NoError, 850
 - NoMemoryError, 850
 - Parse, 851
 - ParseBuffer, 851
 - Parser, 851
 - Process, 852
 - SetElementHandler, 852
 - SetUserData, 852
 - StartElementHandler, 850
 - SyntaxError, 850
 - TagMismatchError, 850
 - UndefinedEntityError, 850
 - UnexpectedStateError, 850
- gdcm::Patient, 852
 - Patient, 853
- gdcm::PDBElement, 856
 - GetName, 857
 - GetValue, 857
 - NameField, 859
 - operator<=, 858

- operator==, [858](#)
- PDBElement, [857](#)
- SetName, [858](#)
- SetValue, [858](#)
- ValueField, [859](#)
- gdcmm::PDBHeader, [859](#)
 - ~PDBHeader, [860](#)
 - FindPDBElementByName, [860](#)
 - GetPDBEEnd, [860](#)
 - GetPDBElementByName, [861](#)
 - GetPDBInfoTag, [861](#)
 - LoadFromDataElement, [861](#)
 - operator<<, [861](#)
 - PDBHeader, [860](#)
 - Print, [861](#)
- gdcmm::PDFCodec, [862](#)
 - ~PDFCodec, [863](#)
 - CanCode, [864](#)
 - CanDecode, [864](#)
 - Decode, [864](#)
 - PDFCodec, [863](#)
- gdcmm::PersonName, [868](#)
 - Component, [869](#)
 - GetMaxLength, [868](#)
 - GetNumberOfComponents, [868](#)
 - MaxLength, [869](#)
 - MaxNumberOfComponents, [870](#)
 - Padding, [870](#)
 - Print, [869](#)
 - Separator, [870](#)
 - SetBlob, [869](#)
 - SetComponents, [869](#)
- gdcmm::PGXCodec, [870](#)
 - ~PGXCodec, [873](#)
 - CanCode, [873](#)
 - CanDecode, [873](#)
 - Clone, [874](#)
 - GetHeaderInfo, [874](#)
 - PGXCodec, [873](#)
 - Read, [874](#)
 - Write, [874](#)
- gdcmm::PhotometricInterpretation, [874](#)
 - ARGB, [876](#)
 - CMYK, [876](#)
 - GetPIString, [876](#)
 - GetPIType, [876](#)
 - GetSamplesPerPixel, [877](#)
 - GetString, [877](#)
 - GetType, [877](#)
 - HSV, [876](#)
 - IsLossless, [877](#)
 - IsLossy, [877](#)
 - IsRetired, [877](#)
 - IsSameColorSpace, [877](#)
 - MONOCHROME1, [876](#)
 - MONOCHROME2, [876](#)
 - operator PIType, [877](#)
 - operator<<, [878](#)
 - PALETTE_COLOR, [876](#)
 - PhotometricInterpretation, [876](#)
 - PI_END, [876](#)
 - PIType, [876](#)
 - RGB, [876](#)
 - UNKNOWN, [876](#)
 - YBR_FULL, [876](#)
 - YBR_FULL_422, [876](#)
 - YBR_ICT, [876](#)
 - YBR_PARTIAL_420, [876](#)
 - YBR_PARTIAL_422, [876](#)
 - YBR_RCT, [876](#)
- gdcmm::PixelFormat, [878](#)
 - Bitmap, [886](#)
 - FLOAT16, [880](#)
 - FLOAT32, [880](#)
 - FLOAT64, [880](#)
 - GetBitsAllocated, [881](#)
 - GetBitsStored, [881](#)
 - GetHighBit, [881](#)
 - GetMax, [882](#)
 - GetMin, [882](#)
 - GetPixelRepresentation, [882](#)
 - GetPixelSize, [882](#)
 - GetSamplesPerPixel, [882](#)
 - GetScalarType, [883](#)
 - GetScalarTypeAsString, [883](#)
 - INT12, [880](#)
 - INT16, [880](#)
 - INT32, [880](#)
 - INT64, [880](#)
 - INT8, [880](#)
 - IsCompatible, [883](#)
 - IsValid, [883](#)
 - operator ScalarType, [883](#)
 - operator!=, [884](#)
 - operator<<, [886](#)
 - operator==, [884](#)
 - PixelFormat, [881](#)
 - Print, [884](#)
 - ScalarType, [880](#)
 - SetBitsAllocated, [884](#)
 - SetBitsStored, [885](#)
 - SetHighBit, [885](#)
 - SetPixelRepresentation, [885](#)
 - SetSamplesPerPixel, [885](#)
 - SetScalarType, [885](#)
 - SINGLEBIT, [880](#)
 - UINT12, [880](#)
 - UINT16, [880](#)

- UINT32, 880
- UINT64, 880
- UINT8, 880
- UNKNOWN, 880
- Validate, 886
- gdcm::Pixmap, 887
 - ~Pixmap, 891
 - AreOverlaysInPixelData, 891
 - Curves, 893
 - GetCurve, 891
 - GetIconImage, 891
 - GetNumberOfCurves, 892
 - GetNumberOfOverlays, 892
 - GetOverlay, 892
 - Icon, 893
 - Overlays, 894
 - Pixmap, 891
 - Print, 892
 - RemoveOverlay, 892
 - SetIconImage, 893
 - SetNumberOfCurves, 893
 - SetNumberOfOverlays, 893
 - UnusedBitsPresentInPixelData, 893
- gdcm::PixmapReader, 894
 - ~PixmapReader, 897
 - GetPixmap, 897
 - PixelData, 898
 - PixmapReader, 897
 - Read, 897
 - ReadACRNEMAImage, 897
 - ReadImage, 898
 - ReadImageInternal, 898
- gdcm::PixmapToPixmapFilter, 898
 - ~PixmapToPixmapFilter, 900
 - GetInput, 900
 - GetOutput, 900
 - GetOutputAsPixmap, 900
 - PixmapToPixmapFilter, 900
- gdcm::PixmapWriter, 901
 - ~PixmapWriter, 904
 - DolconImage, 904
 - GetImage, 904
 - GetPixmap, 904
 - PixelData, 906
 - PixmapWriter, 904
 - PrepareWrite, 905
 - SetImage, 905
 - SetPixmap, 905
 - Write, 905
- gdcm::PNMCodec, 906
 - ~PNMCodec, 909
 - CanCode, 909
 - CanDecode, 909
 - Clone, 910
 - GetBufferLength, 910
 - GetHeaderInfo, 910
 - PNMCodec, 909
 - Read, 910
 - SetBufferLength, 910
 - Write, 910
- gdcm::Preamble, 911
 - ~Preamble, 912
 - Clear, 912
 - Create, 912
 - GetInternal, 913
 - GetLength, 913
 - IsEmpty, 913
 - IsValid, 913
 - operator<<, 914
 - operator=, 913
 - Preamble, 912
 - Print, 913
 - Read, 913
 - Remove, 914
 - Valid, 914
 - Write, 914
- gdcm::PresentationContext, 915
 - AbstractSyntax, 918
 - AddTransferSyntax, 917
 - GetAbstractSyntax, 917
 - GetNumberOfTransferSyntaxes, 917
 - GetPresentationContextID, 917
 - GetTransferSyntax, 917
 - ID, 918
 - operator==, 917
 - PresentationContext, 916
 - Print, 917
 - SetAbstractSyntax, 917
 - SetPresentationContextID, 918
 - SizeType, 916
 - TransferSyntaxArrayType, 916
 - TransferSyntaxes, 918
- gdcm::PresentationContextGenerator, 921
 - AddFromFile, 922
 - AddPresentationContext, 922
 - GenerateFromFilenames, 922
 - GenerateFromUID, 922
 - GetDefaultTransferSyntax, 923
 - GetPresentationContexts, 923
 - PresentationContextArrayType, 922
 - PresentationContextGenerator, 922
 - SetDefaultTransferSyntax, 923
 - SetMergeModeToAbstractSyntax, 923
 - SetMergeModeToTransferSyntax, 923
 - SizeType, 922
- gdcm::Printer, 931
 - ~Printer, 933
 - CONDENSED_STYLE, 933

- CXX, [933](#)
- F, [935](#)
- GetPrintStyle, [933](#)
- MaxPrintLength, [935](#)
- Print, [933](#)
- PrintDataElement, [933](#)
- PrintDataSet, [934](#)
- Printer, [933](#)
- PrintSQ, [934](#)
- PrintStyle, [935](#)
- PrintStyles, [932](#)
- SetColor, [934](#)
- SetFile, [934](#)
- SetStyle, [934](#)
- VERBOSE_STYLE, [933](#)
- XML, [933](#)
- gdcm::PrivateDict, [935](#)
 - ~PrivateDict, [936](#)
 - AddDictEntry, [936](#)
 - Dicts, [937](#)
 - FindDictEntry, [936](#)
 - GetDictEntry, [936](#)
 - IsEmpty, [937](#)
 - LoadDefault, [937](#)
 - operator<, [937](#)
 - PrintXML, [937](#)
 - PrivateDict, [936](#)
 - RemoveDictEntry, [937](#)
- gdcm::PrivateTag, [938](#)
 - GetAsDataElement, [941](#)
 - GetOwner, [941](#)
 - operator!=, [941](#)
 - operator<, [942](#)
 - operator<<, [943](#)
 - operator=, [942](#)
 - operator==, [942](#)
 - PrivateTag, [941](#)
 - ReadFromCommaSeparatedString, [942](#)
 - SetOwner, [942](#)
- gdcm::ProgressEvent, [943](#)
 - ~ProgressEvent, [945](#)
 - CheckEvent, [946](#)
 - GetEventName, [946](#)
 - GetProgress, [946](#)
 - MakeObject, [946](#)
 - operator=, [946](#)
 - ProgressEvent, [945](#)
 - Self, [945](#)
 - SetProgress, [946](#)
 - Superclass, [945](#)
- gdcm::PVRGCodec, [947](#)
 - ~PVRGCodec, [950](#)
 - CanCode, [950](#)
 - CanDecode, [950](#)
 - Clone, [950](#)
 - Code, [951](#)
 - Decode, [951](#)
 - PVRGCodec, [950](#)
 - SetLossyFlag, [951](#)
- gdcm::PythonFilter, [951](#)
 - ~PythonFilter, [952](#)
 - GetFile, [952](#)
 - PythonFilter, [952](#)
 - SetDicts, [952](#)
 - SetFile, [952](#)
 - ToPyObject, [953](#)
 - UseDictAlways, [953](#)
- gdcm::QueryBase, [953](#)
 - ~QueryBase, [954](#)
 - GetAllRequiredTags, [954](#)
 - GetAllTags, [954](#)
 - GetHierarchicalSearchTags, [954](#)
 - GetName, [955](#)
 - GetOptionalTags, [955](#)
 - GetQueryLevel, [955](#)
 - GetRequiredTags, [955](#)
 - GetUniqueTags, [955](#)
- gdcm::QueryFactory, [956](#)
 - GetCharacterFromCurrentLocale, [956](#)
 - ListCharSets, [956](#)
 - ProduceCharacterSetDataElement, [956](#)
 - ProduceQuery, [957](#)
- gdcm::QueryImage, [957](#)
 - GetHierarchicalSearchTags, [958](#)
 - GetName, [958](#)
 - GetOptionalTags, [959](#)
 - GetQueryLevel, [959](#)
 - GetRequiredTags, [959](#)
 - GetUniqueTags, [959](#)
- gdcm::QueryPatient, [960](#)
 - GetHierarchicalSearchTags, [961](#)
 - GetName, [961](#)
 - GetOptionalTags, [961](#)
 - GetQueryLevel, [961](#)
 - GetRequiredTags, [961](#)
 - GetUniqueTags, [962](#)
- gdcm::QuerySeries, [962](#)
 - GetHierarchicalSearchTags, [963](#)
 - GetName, [963](#)
 - GetOptionalTags, [964](#)
 - GetQueryLevel, [964](#)
 - GetRequiredTags, [964](#)
 - GetUniqueTags, [964](#)
- gdcm::QueryStudy, [965](#)
 - GetHierarchicalSearchTags, [966](#)
 - GetName, [966](#)
 - GetOptionalTags, [966](#)
 - GetQueryLevel, [966](#)

- GetRequiredTags, 966
- GetUniqueTags, 967
- gdcmm::RAWCodec, 967
 - ~RAWCodec, 970
 - CanCode, 970
 - CanDecode, 970
 - Clone, 970
 - Code, 971
 - Decode, 971
 - DecodeByStreams, 971
 - DecodeBytes, 971
 - GetHeaderInfo, 971
 - RAWCodec, 970
- gdcmm::Reader, 972
 - ~Reader, 975
 - CanRead, 975
 - F, 979
 - GetFile, 975
 - GetStreamCurrentPosition, 975
 - GetStreamPtr, 976
 - Read, 976
 - ReadDataSet, 976
 - Reader, 975
 - ReadMetaInformation, 976
 - ReadPreamble, 976
 - ReadSelectedPrivateTags, 977
 - ReadSelectedTags, 977
 - ReadUpToTag, 977
 - SetFile, 977
 - SetFileName, 977
 - SetStream, 978
 - StreamImageReader, 978
- gdcmm::RealWorldValueMappingContent, 979
 - CodeMeaning, 980
 - CodeValue, 980
 - RealWorldValueIntercept, 980
 - RealWorldValueSlope, 980
- gdcmm::Region, 980
 - ~Region, 981
 - Area, 981
 - Clone, 981
 - ComputeBoundingBox, 982
 - Empty, 982
 - IsValid, 982
 - Print, 982
 - Region, 981
- gdcmm::Rescaler, 983
 - ~Rescaler, 984
 - ComputeInterceptSlopePixelType, 984
 - ComputePixelTypeFromMinMax, 984
 - GetIntercept, 985
 - GetSlope, 985
 - InverseRescale, 985
 - InverseRescaleFunctionIntoBestFit, 985
 - Rescale, 985
 - RescaleFunctionIntoBestFit, 985
 - Rescaler, 984
 - SetIntercept, 986
 - SetMinMaxForPixelType, 986
 - SetPixelFormat, 986
 - SetSlope, 986
 - SetTargetPixelType, 986
 - SetUseTargetPixelType, 987
- gdcmm::RLECodec, 987
 - ~RLECodec, 990
 - AppendFrameEncode, 991
 - AppendRowEncode, 991
 - CanCode, 991
 - CanDecode, 991
 - Clone, 991
 - Code, 991
 - Decode, 992
 - DecodeByStreams, 992
 - DecodeExtent, 992
 - GetBufferLength, 992
 - GetHeaderInfo, 992
 - ImageRegionReader, 994
 - IsFrameEncoder, 993
 - IsRowEncoder, 993
 - RLECodec, 990
 - SetBufferLength, 993
 - SetLength, 993
 - StartEncode, 993
 - StopEncode, 993
- gdcmm::Scanner, 996
 - ~Scanner, 1000
 - AddPrivateTag, 1000
 - AddSkipTag, 1000
 - AddTag, 1000
 - Begin, 1001
 - ClearSkipTags, 1001
 - ClearTags, 1001
 - ConstIterator, 999
 - End, 1001
 - GetAllFilenamesFromTagToValue, 1001
 - GetFilenameFromTagToValue, 1001
 - GetFilenames, 1001
 - GetKeys, 1002
 - GetMapping, 1002
 - GetMappingFromTagToValue, 1002
 - GetMapping, 1002
 - GetOrderedValues, 1002
 - GetValue, 1002
 - GetValues, 1003
 - IsKey, 1003
 - MappingType, 999
 - New, 1003
 - operator<<, 1005

Print, [1004](#)
PrintTable, [1004](#)
ProcessPublicTag, [1004](#)
Scan, [1004](#)
Scanner, [1000](#)
TagToValue, [999](#)
TagToValueValueType, [999](#)
ValuesType, [1000](#)
gdcmm::Scanner2, [1005](#)
 ~Scanner2, [1010](#)
 AddPrivateTag, [1010](#)
 AddPublicTag, [1010](#)
 AddSkipTag, [1010](#)
 Begin, [1010](#)
 ClearPrivateTags, [1010](#)
 ClearPublicTags, [1011](#)
 ClearSkipTags, [1011](#)
 End, [1011](#)
 GetAllFilenamesFromPrivateTagToValue, [1011](#)
 GetAllFilenamesFromPublicTagToValue, [1011](#)
 GetFilenameFromPrivateTagToValue, [1011](#)
 GetFilenameFromPublicTagToValue, [1011](#)
 GetFilenames, [1011](#)
 GetKeys, [1012](#)
 GetMappingFromPrivateTagToValue, [1012](#)
 GetMappingFromPublicTagToValue, [1012](#)
 GetPrivateMapping, [1012](#)
 GetPrivateMappings, [1012](#)
 GetPrivateOrderedValues, [1012](#)
 GetPrivateValue, [1012](#)
 GetPrivateValues, [1013](#)
 GetPublicMapping, [1013](#)
 GetPublicMappings, [1013](#)
 GetPublicOrderedValues, [1013](#)
 GetPublicValue, [1013](#)
 GetPublicValues, [1013](#)
 GetValues, [1014](#)
 IsKey, [1014](#)
 New, [1014](#)
 operator<<, [1015](#)
 Print, [1014](#)
 PrintTable, [1014](#)
 PrivateBegin, [1014](#)
 PrivateConstIterator, [1009](#)
 PrivateEnd, [1015](#)
 PrivateMappingType, [1009](#)
 PrivateTagToValue, [1009](#)
 PrivateTagToValueValueType, [1009](#)
 ProcessPrivateTag, [1015](#)
 ProcessPublicTag, [1015](#)
 PublicConstIterator, [1009](#)
 PublicMappingType, [1009](#)
 PublicTagToValue, [1009](#)
 PublicTagToValueValueType, [1009](#)
 Scan, [1015](#)
 Scanner2, [1010](#)
 ValuesType, [1009](#)
gdcmm::Scanner2::Itstr, [733](#)
 operator(), [734](#)
gdcmm::Scanner::Itstr, [734](#)
 operator(), [734](#)
gdcmm::Segment, [1016](#)
 ~Segment, [1019](#)
 AddSurface, [1019](#)
 ALGOType, [1018](#)
 ALGOType_END, [1019](#)
 AnatomicRegion, [1023](#)
 AnatomicRegionModifiers, [1023](#)
 AUTOMATIC, [1019](#)
 BasicCodedEntryVector, [1018](#)
 GetALGOType, [1019](#)
 GetALGOTypeString, [1019](#)
 GetAnatomicRegion, [1019](#)
 GetAnatomicRegionModifiers, [1020](#)
 GetPropertyCategory, [1020](#)
 GetPropertyType, [1020](#)
 GetPropertyTypeModifiers, [1020](#)
 GetSegmentAlgorithmName, [1020](#)
 GetSegmentAlgorithmType, [1020](#)
 GetSegmentDescription, [1021](#)
 GetSegmentLabel, [1021](#)
 GetSegmentNumber, [1021](#)
 GetSurface, [1021](#)
 GetSurfaceCount, [1021](#)
 GetSurfaces, [1021](#)
 MANUAL, [1019](#)
 PropertyCategory, [1023](#)
 PropertyType, [1023](#)
 PropertyTypeModifiers, [1023](#)
 Segment, [1019](#)
 SegmentAlgorithmName, [1023](#)
 SegmentAlgorithmType, [1023](#)
 SegmentDescription, [1024](#)
 SegmentLabel, [1024](#)
 SegmentNumber, [1024](#)
 SEMAUTOMATIC, [1019](#)
 SetAnatomicRegion, [1021](#)
 SetAnatomicRegionModifiers, [1021](#)
 SetPropertyCategory, [1022](#)
 SetPropertyType, [1022](#)
 SetPropertyTypeModifiers, [1022](#)
 SetSegmentAlgorithmName, [1022](#)
 SetSegmentAlgorithmType, [1022](#)
 SetSegmentDescription, [1022](#)
 SetSegmentLabel, [1022](#)
 SetSegmentNumber, [1023](#)
 SetSurfaceCount, [1023](#)
 SurfaceCount, [1024](#)

- Surfaces, [1024](#)
- SurfaceVector, [1018](#)
- gdcmm::SegmentedPaletteColorLookupTable, [1025](#)
 - ~SegmentedPaletteColorLookupTable, [1027](#)
 - Print, [1028](#)
 - SegmentedPaletteColorLookupTable, [1027](#)
 - SetLUT, [1028](#)
- gdcmm::SegmentHelper, [80](#)
- gdcmm::SegmentHelper::BasicCodedEntry, [212](#)
 - BasicCodedEntry, [214](#)
 - CM, [215](#)
 - CSD, [215](#)
 - CSV, [215](#)
 - CV, [215](#)
 - IsEmpty, [214](#)
- gdcmm::SegmentReader, [1028](#)
 - ~SegmentReader, [1031](#)
 - GetSegments, [1031](#)
 - Read, [1031](#)
 - ReadSegment, [1032](#)
 - ReadSegments, [1032](#)
 - SegmentMap, [1031](#)
 - SegmentReader, [1031](#)
 - Segments, [1032](#)
 - SegmentVector, [1031](#)
- gdcmm::SegmentWriter, [1032](#)
 - ~SegmentWriter, [1036](#)
 - AddSegment, [1036](#)
 - GetNumberOfSegments, [1036](#)
 - GetSegment, [1036](#)
 - GetSegments, [1036](#)
 - PrepareWrite, [1036](#)
 - Segments, [1037](#)
 - SegmentVector, [1036](#)
 - SegmentWriter, [1036](#)
 - SetNumberOfSegments, [1037](#)
 - SetSegments, [1037](#)
 - Write, [1037](#)
- gdcmm::SequenceOfFragments, [1038](#)
 - AddFragment, [1041](#)
 - Begin, [1041](#)
 - Clear, [1041](#)
 - ComputeByteLength, [1041](#)
 - ComputeLength, [1042](#)
 - ConstIterator, [1040](#)
 - End, [1042](#)
 - FragmentVector, [1040](#)
 - GetBuffer, [1042](#)
 - GetFragBuffer, [1042](#)
 - GetFragment, [1042](#)
 - GetLength, [1042](#)
 - GetNumberOfFragments, [1043](#)
 - GetTable, [1043](#)
 - Iterator, [1040](#)
 - New, [1043](#)
 - operator==, [1043](#)
 - Print, [1043](#)
 - Read, [1044](#)
 - ReadPreValue, [1044](#)
 - ReadValue, [1044](#)
 - SequenceOfFragments, [1041](#)
 - SetLength, [1044](#)
 - SizeType, [1040](#)
 - Write, [1044](#)
 - WriteBuffer, [1045](#)
- gdcmm::SequenceOfItems, [1045](#)
 - AddItem, [1049](#)
 - AddNewUndefinedLengthItem, [1049](#)
 - Begin, [1049](#), [1050](#)
 - Clear, [1050](#)
 - ComputeLength, [1050](#)
 - ConstIterator, [1048](#)
 - End, [1050](#)
 - FindDataElement, [1050](#)
 - GetItem, [1050](#), [1051](#)
 - GetLength, [1051](#)
 - GetNumberOfItems, [1051](#)
 - IsEmpty, [1051](#)
 - IsUndefinedLength, [1051](#)
 - Items, [1054](#)
 - ItemVector, [1048](#)
 - Iterator, [1048](#)
 - New, [1052](#)
 - operator=, [1052](#)
 - operator==, [1052](#)
 - Print, [1052](#)
 - Read, [1052](#)
 - RemoveItemByIndex, [1053](#)
 - SequenceLengthField, [1054](#)
 - SequenceOfItems, [1049](#)
 - SetLength, [1053](#)
 - SetLengthToUndefined, [1053](#)
 - SetNumberOfItems, [1053](#)
 - SizeType, [1049](#)
 - Write, [1053](#)
- gdcmm::SerieHelper, [1054](#)
 - ~SerieHelper, [1057](#)
 - AddFile, [1057](#)
 - AddFileName, [1057](#)
 - AddRestriction, [1057](#)
 - Clear, [1057](#)
 - CreateDefaultUniqueSeriesIdentifier, [1058](#)
 - CreateUniqueSeriesIdentifier, [1058](#)
 - FileNameOrdering, [1058](#)
 - GetFirstSingleSerieUIDFileSet, [1058](#)
 - GetNextSingleSerieUIDFileSet, [1058](#)
 - ImageNumberOrdering, [1058](#)
 - ImagePositionPatientOrdering, [1058](#)

- ItFileSetHt, [1059](#)
- OrderFileList, [1058](#)
- Rule, [1056](#)
- SerieHelper, [1057](#)
- SerieRestrictions, [1056](#)
- SetDirectory, [1058](#)
- SetLoadMode, [1059](#)
- SetUseSeriesDetails, [1059](#)
- SingleSerieUIDFileSetHT, [1059](#)
- SingleSerieUIDFileSetmap, [1056](#)
- UserOrdering, [1059](#)
- gdcm::Series, [1059](#)
 - Series, [1060](#)
- gdcm::ServiceClassUser, [1062](#)
 - ~ServiceClassUser, [1065](#)
 - GetAETitle, [1065](#)
 - GetCalledAETitle, [1065](#)
 - GetTimeout, [1065](#)
 - InitializeConnection, [1065](#)
 - IsPresentationContextAccepted, [1066](#)
 - New, [1066](#)
 - operator=, [1066](#)
 - SendEcho, [1066](#)
 - SendFind, [1066](#)
 - SendMove, [1066](#), [1067](#)
 - SendStore, [1067](#)
 - ServiceClassUser, [1065](#)
 - SetAETitle, [1068](#)
 - SetCalledAETitle, [1068](#)
 - SetHostname, [1068](#)
 - SetPort, [1068](#)
 - SetPortSCP, [1068](#)
 - SetPresentationContexts, [1069](#)
 - SetTimeout, [1069](#)
 - StartAssociation, [1069](#)
 - StopAssociation, [1069](#)
- gdcm::SHA1, [1070](#)
 - ~SHA1, [1071](#)
 - Compute, [1071](#)
 - ComputeFile, [1071](#)
 - operator=, [1071](#)
 - SHA1, [1071](#)
- gdcm::SimpleMemberCommand< T >, [1072](#)
 - ~SimpleMemberCommand, [1075](#)
 - Execute, [1076](#)
 - m_MemberFunction, [1077](#)
 - m_This, [1077](#)
 - New, [1076](#)
 - operator=, [1076](#)
 - Self, [1075](#)
 - SetCallbackFunction, [1076](#)
 - SimpleMemberCommand, [1075](#)
 - TMemberFunctionPointer, [1075](#)
- gdcm::SimpleSubjectWatcher, [1077](#)
 - ~SimpleSubjectWatcher, [1078](#)
 - EndFilter, [1078](#)
 - operator=, [1078](#)
 - ShowAbort, [1078](#)
 - ShowAnonymization, [1079](#)
 - ShowData, [1079](#)
 - ShowDataSet, [1079](#)
 - ShowFileName, [1079](#)
 - ShowIteration, [1079](#)
 - ShowProgress, [1079](#)
 - SimpleSubjectWatcher, [1078](#)
 - StartFilter, [1079](#)
 - TestAbortOff, [1080](#)
 - TestAbortOn, [1080](#)
- gdcm::SmartPointer< ObjectType >, [1082](#)
 - ~SmartPointer, [1084](#)
 - GetPointer, [1084](#)
 - operator ObjectType *, [1084](#)
 - operator->, [1085](#)
 - operator=, [1085](#)
 - operator*, [1085](#)
 - SmartPointer, [1084](#)
- gdcm::SOPClassUIDToIOD, [1087](#)
 - const, [1088](#)
 - GetIOD, [1088](#)
 - GetIODFromSOPClassUID, [1088](#)
 - GetNumberOfSOPClassToIOD, [1088](#)
 - GetSOPClassUIDFromIOD, [1088](#)
 - GetSOPClassUIDToIOD, [1088](#)
 - GetSOPClassUIDToIODs, [1089](#)
- gdcm::Sorter, [1089](#)
 - ~Sorter, [1091](#)
 - AddSelect, [1091](#)
 - Filenames, [1093](#)
 - GetFilenames, [1091](#)
 - operator<=, [1093](#)
 - Print, [1091](#)
 - Selection, [1093](#)
 - SelectionMap, [1091](#)
 - SetSortFunction, [1092](#)
 - SetTagsToRead, [1092](#)
 - Sort, [1092](#)
 - Sorter, [1091](#)
 - SortFunc, [1093](#)
 - SortFunction, [1091](#)
 - StableSort, [1092](#)
 - TagsToRead, [1093](#)
- gdcm::Spacing, [1094](#)
 - ~Spacing, [1095](#)
 - CALIBRATED, [1095](#)
 - ComputePixelAspectRatioFromPixelSpacing, [1096](#)
 - DETECTOR, [1095](#)
 - MAGNIFIED, [1095](#)
 - Spacing, [1095](#)

- SpacingType, [1095](#)
- UNKNOWN, [1095](#)
- gdcmm::Spectroscopy, [1096](#)
 - Spectroscopy, [1096](#)
- gdcmm::SplitMosaicFilter, [1097](#)
 - ~SplitMosaicFilter, [1098](#)
 - ComputeCSAImageHeaderInfo, [1098](#)
 - ComputeCSASeriesHeaderInfo, [1098](#)
 - ComputeMOSAICDimensions, [1098](#)
 - ComputeMOSAICImagePositionPatient, [1098](#)
 - ComputeMOSAICSliceNormal, [1098](#)
 - ComputeMOSAICSlicePosition, [1099](#)
 - GetAcquisitionSize, [1099](#)
 - GetFile, [1099](#)
 - GetImage, [1099](#)
 - GetNumberOfImagesInMosaic, [1099](#)
 - SetFile, [1100](#)
 - SetImage, [1100](#)
 - Split, [1100](#)
 - SplitMosaicFilter, [1098](#)
- gdcmm::StartEvent, [1100](#)
- gdcmm::static_assert_test< x >, [1101](#)
- gdcmm::STATIC_ASSERTION_FAILURE< true >, [1102](#)
 - value, [1103](#)
- gdcmm::STATIC_ASSERTION_FAILURE< x >, [1102](#)
- gdcmm::StreamImageReader, [1103](#)
 - ~StreamImageReader, [1104](#)
 - CanReadImage, [1105](#)
 - DefinePixelExtent, [1105](#)
 - DefineProperBufferLength, [1105](#)
 - GetDimensionsValueForResolution, [1105](#)
 - GetFile, [1106](#)
 - Read, [1106](#)
 - ReadImageInformation, [1106](#)
 - SetFileName, [1106](#)
 - SetStream, [1107](#)
 - StreamImageReader, [1104](#)
- gdcmm::StreamImageWriter, [1107](#)
 - ~StreamImageWriter, [1109](#)
 - CanWriteFile, [1110](#)
 - DefinePixelExtent, [1110](#)
 - DefineProperBufferLength, [1110](#)
 - mElementOffsets, [1112](#)
 - mElementOffsets1, [1112](#)
 - mSPFile, [1112](#)
 - mWriter, [1113](#)
 - mXMax, [1113](#)
 - mXMin, [1113](#)
 - mYMax, [1113](#)
 - mYMin, [1113](#)
 - mZMax, [1113](#)
 - mZMin, [1113](#)
 - SetFile, [1110](#)
 - SetFileName, [1111](#)
- SetStream, [1111](#)
- StreamImageWriter, [1109](#)
- Write, [1111](#)
- WriteImageInformation, [1111](#)
- WriteImageSubregionRAW, [1112](#)
- WriteRawHeader, [1112](#)
- gdcmm::StrictScanner, [1114](#)
 - ~StrictScanner, [1118](#)
 - AddPrivateTag, [1118](#)
 - AddSkipTag, [1118](#)
 - AddTag, [1119](#)
 - Begin, [1119](#)
 - ClearSkipTags, [1119](#)
 - ClearTags, [1119](#)
 - ConstIterator, [1117](#)
 - End, [1119](#)
 - GetAllFileNamesFromTagToValue, [1119](#)
 - GetFilenameFromTagToValue, [1119](#)
 - GetFileNames, [1120](#)
 - GetKeys, [1120](#)
 - GetMapping, [1120](#)
 - GetMappingFromTagToValue, [1120](#)
 - GetMappings, [1120](#)
 - GetOrderedValues, [1120](#)
 - GetValue, [1121](#)
 - GetValues, [1121](#)
 - IsKey, [1121](#)
 - MappingType, [1117](#)
 - New, [1121](#)
 - operator<<, [1123](#)
 - Print, [1122](#)
 - PrintTable, [1122](#)
 - ProcessPublicTag, [1122](#)
 - Scan, [1122](#)
 - StrictScanner, [1118](#)
 - TagToValue, [1117](#)
 - TagToValueValueType, [1118](#)
 - ValuesType, [1118](#)
- gdcmm::StrictScanner2, [1123](#)
 - ~StrictScanner2, [1128](#)
 - AddPrivateTag, [1128](#)
 - AddPublicTag, [1128](#)
 - AddSkipTag, [1128](#)
 - Begin, [1128](#)
 - ClearPrivateTags, [1128](#)
 - ClearPublicTags, [1129](#)
 - ClearSkipTags, [1129](#)
 - End, [1129](#)
 - GetAllFileNamesFromPrivateTagToValue, [1129](#)
 - GetAllFileNamesFromPublicTagToValue, [1129](#)
 - GetFilenameFromPrivateTagToValue, [1129](#)
 - GetFilenameFromPublicTagToValue, [1129](#)
 - GetFileNames, [1129](#)
 - GetKeys, [1130](#)

- GetMappingFromPrivateTagToValue, [1130](#)
- GetMappingFromPublicTagToValue, [1130](#)
- GetPrivateMapping, [1130](#)
- GetPrivateMappings, [1130](#)
- GetPrivateOrderedValues, [1130](#)
- GetPrivateValue, [1130](#)
- GetPrivateValues, [1131](#)
- GetPublicMapping, [1131](#)
- GetPublicMappings, [1131](#)
- GetPublicOrderedValues, [1131](#)
- GetPublicValue, [1131](#)
- GetPublicValues, [1131](#)
- GetValues, [1132](#)
- IsKey, [1132](#)
- New, [1132](#)
- operator<<, [1133](#)
- Print, [1132](#)
- PrintTable, [1132](#)
- PrivateBegin, [1132](#)
- PrivateConstIterator, [1127](#)
- PrivateEnd, [1133](#)
- PrivateMappingType, [1127](#)
- PrivateTagToValue, [1127](#)
- PrivateTagToValueValueType, [1127](#)
- ProcessPrivateTag, [1133](#)
- ProcessPublicTag, [1133](#)
- PublicConstIterator, [1127](#)
- PublicMappingType, [1127](#)
- PublicTagToValue, [1127](#)
- PublicTagToValueValueType, [1127](#)
- Scan, [1133](#)
- StrictScanner2, [1128](#)
- ValuesType, [1127](#)
- gdcmm::StrictScanner2::ltstr, [734](#)
- operator(), [735](#)
- gdcmm::StrictScanner::ltstr, [735](#)
- operator(), [735](#)
- gdcmm::String< TDelimiter, TMaxLength, TPadChar >, [1134](#)
- const_iterator, [1135](#)
- const_reference, [1135](#)
- const_reverse_iterator, [1136](#)
- difference_type, [1136](#)
- IsValid, [1137](#)
- iterator, [1136](#)
- operator const char *, [1137](#)
- pointer, [1136](#)
- reference, [1136](#)
- reverse_iterator, [1136](#)
- size_type, [1136](#)
- String, [1137](#)
- Trim, [1138](#)
- Truncate, [1138](#)
- value_type, [1136](#)
- gdcmm::StringFilter, [1138](#)
- ~StringFilter, [1139](#)
- ExecuteQuery, [1140](#)
- FromString, [1140](#)
- GetFile, [1140](#)
- SetDicts, [1140](#)
- SetFile, [1140](#)
- StringFilter, [1139](#)
- ToString, [1141](#)
- ToStringPair, [1141](#), [1142](#)
- UseDictAlways, [1142](#)
- gdcmm::Study, [1142](#)
- Study, [1142](#)
- gdcmm::Subject, [1143](#)
- ~Subject, [1144](#)
- AddObserver, [1145](#)
- GetCommand, [1145](#)
- HasObserver, [1145](#)
- InvokeEvent, [1145](#)
- RemoveAllObservers, [1146](#)
- RemoveObserver, [1146](#)
- Subject, [1144](#)
- gdcmm::Surface, [1146](#)
- ~Surface, [1150](#)
- GetAlgorithmFamily, [1150](#)
- GetAlgorithmName, [1150](#)
- GetAlgorithmVersion, [1150](#)
- GetAxisOfRotation, [1151](#)
- GetCenterOfRotation, [1151](#)
- GetFiniteVolume, [1151](#)
- GetManifold, [1151](#)
- GetMaximumPointDistance, [1151](#)
- GetMeanPointDistance, [1151](#)
- GetMeshPrimitive, [1151](#)
- GetNumberOfSurfacePoints, [1152](#)
- GetNumberOfVectors, [1152](#)
- GetPointCoordinatesData, [1152](#)
- GetPointPositionAccuracy, [1152](#)
- GetPointsBoundingBoxCoordinates, [1152](#)
- GetProcessingAlgorithm, [1152](#)
- GetRecommendedDisplayCIELabValue, [1153](#)
- GetRecommendedDisplayGrayscaleValue, [1153](#)
- GetRecommendedPresentationOpacity, [1153](#)
- GetRecommendedPresentationType, [1153](#)
- GetSTATES, [1153](#)
- GetSTATESString, [1153](#)
- GetSurfaceComments, [1153](#)
- GetSurfaceNumber, [1153](#)
- GetSurfaceProcessing, [1154](#)
- GetSurfaceProcessingDescription, [1154](#)
- GetSurfaceProcessingRatio, [1154](#)
- GetVectorAccuracy, [1154](#)
- GetVectorCoordinateData, [1154](#)
- GetVectorDimensionality, [1154](#)

- GetVIEWType, 1154
- GetVIEWTypeString, 1154
- NO, 1149
- POINTS, 1150
- SetAlgorithmFamily, 1155
- SetAlgorithmName, 1155
- SetAlgorithmVersion, 1155
- SetAxisOfRotation, 1155
- SetCenterOfRotation, 1155
- SetFiniteVolume, 1155
- SetManifold, 1155
- SetMaximumPointDistance, 1155
- SetMeanPointDistance, 1156
- SetMeshPrimitive, 1156
- SetNumberOfSurfacePoints, 1156
- SetNumberOfVectors, 1156
- SetPointCoordinatesData, 1156
- SetPointPositionAccuracy, 1156
- SetPointsBoundingBoxCoordinates, 1156
- SetProcessingAlgorithm, 1156
- SetRecommendedDisplayCIELabValue, 1157
- SetRecommendedDisplayGrayscaleValue, 1157
- SetRecommendedPresentationOpacity, 1157
- SetRecommendedPresentationType, 1157
- SetSurfaceComments, 1157
- SetSurfaceNumber, 1157
- SetSurfaceProcessing, 1158
- SetSurfaceProcessingDescription, 1158
- SetSurfaceProcessingRatio, 1158
- SetVectorAccuracy, 1158
- SetVectorCoordinateData, 1158
- SetVectorDimensionality, 1158
- STATES, 1149
- STATES_END, 1149
- SURFACE, 1150
- Surface, 1150
- UNKNOWN, 1149
- VIEWType, 1149
- VIEWType_END, 1150
- WIREFRAME, 1150
- YES, 1149
- gdcmm::SurfaceHelper, 1159
 - ColorArray, 1159
 - RecommendedDisplayCIELabToRGB, 1160
 - RGBToRecommendedDisplayCIELab, 1161
 - RGBToRecommendedDisplayGrayscale, 1161
- gdcmm::SurfaceReader, 1162
 - ~SurfaceReader, 1165
 - GetNumberOfSurfaces, 1165
 - Read, 1165
 - ReadPointMacro, 1166
 - ReadSurface, 1166
 - ReadSurfaces, 1166
 - SurfaceReader, 1165
- gdcmm::SurfaceWriter, 1166
 - ~SurfaceWriter, 1170
 - ComputeNumberOfSurfaces, 1170
 - GetNumberOfSurfaces, 1170
 - NumberOfSurfaces, 1171
 - PrepareWrite, 1171
 - PrepareWritePointMacro, 1171
 - SetNumberOfSurfaces, 1171
 - SurfaceWriter, 1170
 - Write, 1171
- gdcmm::SwapCode, 1171
 - BadBigEndian, 1172
 - BadLittleEndian, 1172
 - BigEndian, 1172
 - GetIndex, 1173
 - GetSwapCodeString, 1173
 - LittleEndian, 1172
 - operator SwapCode::SwapCodeType, 1173
 - operator<<, 1173
 - SwapCode, 1173
 - SwapCodeType, 1172
 - Unknown, 1172
- gdcmm::SwapperDoOp, 1174
 - Swap, 1174
 - SwapArray, 1174
- gdcmm::SwapperNoOp, 1174
 - Swap, 1175
 - SwapArray, 1175
- gdcmm::System, 1175
 - ConvertToUNC, 1177
 - DeleteDirectory, 1177
 - EncodeBytes, 1177
 - FileExists, 1177
 - FileIsDirectory, 1177
 - FileIsSymlink, 1178
 - FileSize, 1178
 - FileTime, 1178
 - FormatDateTime, 1178
 - GetCurrentDateTime, 1179
 - GetCurrentModuleFileName, 1179
 - GetCurrentProcessFileName, 1179
 - GetCurrentResourcesDirectory, 1179
 - GetCWD, 1179
 - GetHostName, 1179
 - GetLastSystemError, 1180
 - GetLocaleCharset, 1180
 - GetPermissions, 1180
 - GetTimezoneOffsetFromUTC, 1180
 - MakeDirectory, 1180
 - ParseDateTime, 1180, 1181
 - RemoveFile, 1181
 - SetPermissions, 1181
 - StrCaseCmp, 1181
 - StrNCaseCmp, 1181

- StrSep, [1182](#)
- StrTokR, [1182](#)
- gdcmm::Table, [1182](#)
 - ~Table, [1184](#)
 - GetTableEntry, [1184](#)
 - InsertEntry, [1184](#)
 - MapTableEntry, [1184](#)
 - operator<<, [1185](#)
 - operator=, [1185](#)
 - Table, [1184](#)
 - TableInternal, [1185](#)
- gdcmm::TableEntry, [1185](#)
 - ~TableEntry, [1186](#)
 - TableEntry, [1186](#)
- gdcmm::TableReader, [1186](#)
 - ~TableReader, [1187](#)
 - CharacterDataHandler, [1188](#)
 - EndElement, [1188](#)
 - GetDefs, [1188](#)
 - GetFilename, [1188](#)
 - HandleIOD, [1188](#)
 - HandleIODEntry, [1188](#)
 - HandleMacro, [1188](#)
 - HandleMacroEntry, [1188](#)
 - HandleMacroEntryDescription, [1189](#)
 - HandleModule, [1189](#)
 - HandleModuleEntry, [1189](#)
 - HandleModuleEntryDescription, [1189](#)
 - HandleModuleInclude, [1189](#)
 - Read, [1189](#)
 - SetFilename, [1189](#)
 - StartElement, [1189](#)
 - TableReader, [1187](#)
- gdcmm::Tag, [1191](#)
 - bytes, [1201](#)
 - GetElement, [1194](#)
 - GetElementTag, [1194](#)
 - GetGroup, [1195](#)
 - GetLength, [1195](#)
 - GetPrivateCreator, [1195](#)
 - IsGroupLength, [1195](#)
 - IsGroupXX, [1195](#)
 - IsIllegal, [1196](#)
 - IsPrivate, [1196](#)
 - IsPrivateCreator, [1196](#)
 - IsPublic, [1196](#)
 - operator!=, [1197](#)
 - operator<, [1197](#)
 - operator<<, [1201](#)
 - operator<=, [1197](#)
 - operator>>, [1201](#)
 - operator=, [1197](#)
 - operator==, [1197](#)
 - operator[], [1197](#), [1198](#)
 - PrintAsContinuousString, [1198](#)
 - PrintAsContinuousUpperCaseString, [1198](#)
 - PrintAsPipeSeparatedString, [1198](#)
 - Read, [1198](#)
 - ReadFromCommaSeparatedString, [1199](#)
 - ReadFromContinuousString, [1199](#)
 - ReadFromPipeSeparatedString, [1199](#)
 - SetElement, [1199](#)
 - SetElementTag, [1199](#), [1200](#)
 - SetGroup, [1200](#)
 - SetPrivateCreator, [1200](#)
 - Tag, [1194](#)
 - tag, [1201](#)
 - tags, [1201](#)
 - Write, [1200](#)
- gdcmm::TagPath, [1202](#)
 - ~TagPath, [1202](#)
 - ConstructFromString, [1203](#)
 - ConstructFromTagList, [1203](#)
 - IsValid, [1203](#)
 - Print, [1203](#)
 - Push, [1203](#)
 - TagPath, [1202](#)
- gdcmm::terminal, [80](#)
 - Attribute, [81](#)
 - black, [81](#)
 - blink, [81](#)
 - blue, [81](#)
 - bright, [81](#)
 - Color, [81](#)
 - CONSOLE, [83](#)
 - cyan, [81](#)
 - dim, [81](#)
 - green, [81](#)
 - hidden, [81](#)
 - magenta, [81](#)
 - Mode, [81](#)
 - red, [81](#)
 - reset, [81](#)
 - reverse, [81](#)
 - setattribute, [83](#)
 - setbgcolor, [83](#)
 - setfgcolor, [83](#)
 - setmode, [83](#)
 - underline, [81](#)
 - VT100, [83](#)
 - white, [81](#)
 - yellow, [81](#)
- gdcmm::Testing, [1204](#)
 - ~Testing, [1205](#)
 - ComputeFileMD5, [1206](#)
 - ComputeMD5, [1206](#)
 - GetDataExtraRoot, [1206](#)
 - GetDataRoot, [1206](#)

- GetFileName, [1206](#)
- GetFileNames, [1207](#)
- GetLossyFlagFromFile, [1207](#)
- GetMD5DataImage, [1207](#)
- GetMD5DataImages, [1207](#)
- GetMD5FromBrokenFile, [1207](#)
- GetMD5FromFile, [1207](#)
- GetMediaStorageDataFile, [1208](#)
- GetMediaStorageDataFiles, [1208](#)
- GetMediaStorageFromFile, [1208](#)
- GetNumberOfFileNames, [1208](#)
- GetNumberOfMD5DataImages, [1208](#)
- GetNumberOfMediaStorageDataFiles, [1208](#)
- GetPixelSpacingDataRoot, [1208](#)
- GetSelectedPrivateGroupOffsetFromFile, [1209](#)
- GetSelectedTagsOffsetFromFile, [1209](#)
- GetSourceDirectory, [1209](#)
- GetStreamOffsetFromFile, [1209](#)
- GetTempDirectory, [1209](#)
- GetTempDirectoryW, [1209](#)
- GetTempFilename, [1210](#)
- GetTempFilenameW, [1210](#)
- MD5DataImagesType, [1205](#)
- MediaStorageDataFilesType, [1205](#)
- Print, [1210](#)
- Testing, [1205](#)
- gdcm::Trace, [1210](#)
 - ~Trace, [1212](#)
 - DebugOff, [1212](#)
 - DebugOn, [1212](#)
 - ErrorOff, [1212](#)
 - ErrorOn, [1212](#)
 - GetDebugFlag, [1212](#)
 - GetDebugStream, [1213](#)
 - GetErrorFlag, [1213](#)
 - GetErrorStream, [1213](#)
 - GetStream, [1213](#)
 - GetWarningFlag, [1213](#)
 - GetWarningStream, [1213](#)
 - SetDebug, [1213](#)
 - SetDebugStream, [1213](#)
 - SetError, [1214](#)
 - SetErrorStream, [1214](#)
 - SetStream, [1214](#)
 - SetStreamToFile, [1214](#)
 - SetWarning, [1214](#)
 - SetWarningStream, [1215](#)
 - Trace, [1212](#)
 - WarningOff, [1215](#)
 - WarningOn, [1215](#)
- gdcm::TransferSyntax, [1215](#)
 - CanStoreLossy, [1219](#)
 - CT_private_ELE, [1218](#)
 - DeflatedExplicitVRLittleEndian, [1218](#)
 - Explicit, [1217](#)
 - ExplicitVRBigEndian, [1218](#)
 - ExplicitVRLittleEndian, [1218](#)
 - GetNegociatedType, [1219](#)
 - GetString, [1219](#)
 - GetSwapCode, [1219](#)
 - GetTSString, [1219](#)
 - GetTSType, [1219](#)
 - HTJ2K, [1218](#)
 - HTJ2KLossless, [1218](#)
 - HTJ2KRPCLLossless, [1218](#)
 - Implicit, [1217](#)
 - ImplicitVRBigEndianACRNEMA, [1218](#)
 - ImplicitVRBigEndianPrivateGE, [1218](#)
 - ImplicitVRLittleEndian, [1218](#)
 - IsEncapsulated, [1220](#)
 - IsEncoded, [1220](#)
 - IsExplicit, [1220](#)
 - IsImplicit, [1220](#)
 - IsLossless, [1220](#)
 - IsLossy, [1220](#)
 - IsValid, [1220](#)
 - JPEG2000, [1218](#)
 - JPEG2000Lossless, [1218](#)
 - JPEG2000Part2, [1218](#)
 - JPEG2000Part2Lossless, [1218](#)
 - JPEGBaselineProcess1, [1218](#)
 - JPEGExtendedProcess2_4, [1218](#)
 - JPEGExtendedProcess3_5, [1218](#)
 - JPEGFullProgressionProcess10_12, [1218](#)
 - JPEGLosslessProcess14, [1218](#)
 - JPEGLosslessProcess14_1, [1218](#)
 - JPEGLSLossless, [1218](#)
 - JPEGLSNearLossless, [1218](#)
 - JPEGSpectralSelectionProcess6_8, [1218](#)
 - JPIPRreferenced, [1218](#)
 - MPEG2MainProfile, [1218](#)
 - MPEG2MainProfileHighLevel, [1218](#)
 - MPEG4AVCH264BDcompatibleHighProfileLevel4_1, [1218](#)
 - MPEG4AVCH264HighProfileLevel4_1, [1218](#)
 - NegociatedType, [1217](#)
 - operator TSType, [1220](#)
 - operator <=, [1221](#)
 - RLELossless, [1218](#)
 - TransferSyntax, [1218](#)
 - TS_END, [1218](#)
 - TSType, [1217](#)
 - Unknown, [1217](#)
 - WeirdPapryus, [1218](#)
- gdcm::Type, [1225](#)
 - GetTypeString, [1227](#)
 - GetTypeType, [1227](#)
 - operator TypeType, [1227](#)

- operator<<, [1227](#)
- T1, [1226](#)
- T1C, [1226](#)
- T2, [1226](#)
- T2C, [1226](#)
- T3, [1226](#)
- Type, [1226](#)
- TypeType, [1226](#)
- UNKNOWN, [1226](#)
- gdcmm::UI, [1227](#)
 - Internal, [1228](#)
 - operator<<, [1228](#)
- gdcmm::UIDGenerator, [1228](#)
 - Generate, [1229](#)
 - GenerateUUID, [1229](#)
 - GetGDCMUID, [1229](#)
 - GetRoot, [1230](#)
 - IsValid, [1230](#)
 - SetRoot, [1230](#)
 - UIDGenerator, [1229](#)
- gdcmm::UIDs, [1231](#)
 - AbstractMultiDimensionalImageModel, [1256](#)
 - AcquisitionContextSRStorage, [1255](#)
 - AdultMouseAnatomyOntology, [1253](#)
 - AdvancedBlendingPresentationStateStorage, [1254](#)
 - AmbulatoryECGWaveformStorage, [1250](#)
 - ArterialPulseWaveformStorage, [1254](#)
 - AudioSRStorageTrialRetired, [1251](#)
 - AutorefractionMeasurementsStorage, [1254](#)
 - BasicAnnotationBoxSOPClass, [1249](#)
 - BasicColorImageBoxSOPClass, [1249](#)
 - BasicColorPrintManagementMetaSOPClass, [1249](#)
 - BasicFilmBoxSOPClass, [1249](#)
 - BasicFilmSessionSOPClass, [1249](#)
 - BasicGrayscaleImageBoxSOPClass, [1249](#)
 - BasicGrayscalePrintManagementMetaSOPClass, [1249](#)
 - BasicPrintImageOverlayBoxSOPClassRetired, [1249](#)
 - BasicStructuredDisplayStorage, [1255](#)
 - BasicStudyContentNotificationSOPClassRetired, [1248](#)
 - BasicTextSRStorage, [1251](#)
 - BasicVoiceAudioWaveformStorage, [1250](#)
 - BlendingSoftcopyPresentationStateStorageSOPClass, [1250](#)
 - BreastImagingRelevantPatientInformationQuery, [1252](#)
 - BreastProjectionXRayImageStorageForPresentation, [1254](#)
 - BreastProjectionXRayImageStorageForProcessing, [1254](#)
 - BreastTomosynthesisImageStorage, [1253](#)
 - CardiacElectrophysiologyWaveformStorage, [1250](#)
 - CardiacRelevantPatientInformationQuery, [1252](#)
 - ChestCADSRStorage, [1251](#)
 - ColonCADSRStorage, [1255](#)
 - ColorPaletteQueryRetrieveInformationModelFIND, [1256](#)
 - ColorPaletteQueryRetrieveInformationModelGET, [1256](#)
 - ColorPaletteQueryRetrieveInformationModelMOVE, [1256](#)
 - ColorPaletteStorage, [1256](#)
 - ColorSoftcopyPresentationStateStorageSOPClass, [1250](#)
 - CompositeInstanceRetrieveWithoutBulkDataGET, [1255](#)
 - CompositeInstanceRootRetrieveGET, [1255](#)
 - CompositeInstanceRootRetrieveMOVE, [1255](#)
 - CompositingPlanarMPRVolumetricPresentationStateStorage, [1254](#)
 - Comprehensive3DSRStorage, [1255](#)
 - ComprehensiveSRStorage, [1251](#)
 - ComprehensiveSRStorageTrialRetired, [1251](#)
 - ComputedRadiographylImageStorage, [1249](#)
 - ContentAssessmentResultsStorage, [1255](#)
 - CornealTopographyMapStorage, [1255](#)
 - CTDefinedProcedureProtocolStorage, [1255](#)
 - CTImageStorage, [1249](#)
 - CTPerformedProcedureProtocolStorage, [1255](#)
 - DefinedProcedureProtocolInformationModelFIND, [1255](#)
 - DefinedProcedureProtocolInformationModelGET, [1255](#)
 - DefinedProcedureProtocolInformationModelMOVE, [1255](#)
 - DeflatedExplicitVRLittleEndian, [1247](#)
 - DeformableSpatialRegistrationStorage, [1250](#)
 - DetachedInterpretationManagementSOPClassRetired, [1249](#)
 - DetachedPatientManagementMetaSOPClassRetired, [1248](#)
 - DetachedPatientManagementSOPClassRetired, [1248](#)
 - DetachedResultsManagementMetaSOPClassRetired, [1249](#)
 - DetachedResultsManagementSOPClassRetired, [1249](#)
 - DetachedStudyManagementMetaSOPClassRetired, [1249](#)
 - DetachedStudyManagementSOPClassRetired, [1248](#)
 - DetachedVisitManagementSOPClassRetired, [1248](#)
 - DetailSRStorageTrialRetired, [1251](#)
 - dicomAETitle, [1252](#)
 - dicomApplicationCluster, [1252](#)
 - DICOMApplicationContextName, [1248](#)
 - dicomAssociationAcceptor, [1252](#)
 - dicomAssociationInitiator, [1252](#)

- dicomAuthorizedNodeCertificateReference, 1253
- dicomConfigurationRoot, 1253
- DICOMContentMappingResource, 1256
- DICOMControlledTerminology, 1248
- dicomDescription, 1252
- dicomDevice, 1253
- dicomDeviceName, 1252
- dicomDeviceSerialNumber, 1253
- dicomDevicesRoot, 1253
- dicomHostname, 1252
- dicomInstalled, 1253
- dicomInstitutionAddress, 1253
- dicomInstitutionDepartmentName, 1253
- dicomInstitutionName, 1253
- dicomIssuerOfPatientID, 1253
- dicomManufacturer, 1252
- dicomManufacturerModelName, 1252
- dicomNetworkAE, 1253
- dicomNetworkConnection, 1253
- dicomNetworkConnectionReference, 1252
- dicomPort, 1252
- dicomPreferredCalledAETitle, 1252
- dicomPreferredCallingAETitle, 1253
- dicomPrimaryDeviceType, 1252
- dicomRelatedDeviceReference, 1252
- dicomSoftwareVersion, 1252
- dicomSOPClass, 1252
- dicomStationName, 1253
- dicomSupportedCharacterSet, 1253
- dicomThisNodeCertificateReference, 1253
- dicomTLSCyphersuite, 1253
- dicomTransferCapability, 1253
- dicomTransferRole, 1252
- dicomTransferSyntax, 1252
- DICOMUIDRegistry, 1248
- dicomUniqueAETitle, 1253
- dicomUniqueAETitlesRegistryRoot, 1253
- dicomVendorData, 1252
- DICOS2DAITStorage, 1255
- DICOS3DAITStorage, 1255
- DICOSCTImageStorage, 1255
- DICOSDigitalXRayImageStorageForPresentation, 1255
- DICOSDigitalXRayImageStorageForProcessing, 1255
- DICOSQuadrupoleResonanceQRStorage, 1255
- DICOSThreatDetectionReportStorage, 1255
- DigitalIntraoralXRayImageStorageForPresentation, 1249
- DigitalIntraoralXRayImageStorageForProcessing, 1249
- DigitalMammographyXRayImageStorageForPresentation, 1249
- DigitalMammographyXRayImageStorageForProcessing, 1249
- DigitalXRayImageStorageForPresentation, 1249
- DigitalXRayImageStorageForProcessing, 1249
- DisplaySystemSOPClass, 1254
- DisplaySystemSOPInstance, 1254
- ECG12leadWaveformStorage, 1250
- EddyCurrentImageStorage, 1255
- EddyCurrentMultiframeImageStorage, 1255
- EncapsulatedCDASStorage, 1251
- EncapsulatedPDFStorage, 1251
- EncapsulatedSTLStorage, 1255
- EnhancedCTImageStorage, 1249
- EnhancedMRColorImageStorage, 1256
- EnhancedMRIImageStorage, 1250
- EnhancedPETImageStorage, 1255
- EnhancedSRStorage, 1251
- EnhancedUSVolumeStorage, 1253
- EnhancedXAImageStorage, 1250
- EnhancedXRFImageStorage, 1250
- ExplicitVRBigEndian, 1247
- ExplicitVRLittleEndian, 1247
- ExtensibleSRStorage, 1255
- FallColorPaletteSOPInstance, 1253
- GeneralAudioWaveformStorage, 1254
- GeneralECGWaveformStorage, 1250
- GeneralPurposePerformedProcedureStepSOP-Class, 1252
- GeneralPurposeScheduledProcedureStepSOP-Class, 1252
- GeneralPurposeWorklistInformationModelFIND, 1252
- GeneralPurposeWorklistManagementMetaSOP-Class, 1252
- GeneralRelevantPatientInformationQuery, 1252
- GenericImplantTemplateInformationModelFIND, 1256
- GenericImplantTemplateInformationModelGET, 1256
- GenericImplantTemplateInformationModelMOVE, 1256
- GenericImplantTemplateStorage, 1256
- GetName, 1266
- GetNumberOfTransferSyntaxStrings, 1266
- GetString, 1266
- GetTransferSyntaxString, 1266
- GetTransferSyntaxStrings, 1266
- GetUIDName, 1267
- GetUIDString, 1267
- GrayscalePlanarMPRVolumetricPresentationStateStorage, 1254
- GrayscaleSoftcopyPresentationStateStorageSOP-Class, 1250
- HangingProtocolInformationModelFIND, 1252
- HangingProtocolInformationModelGET, 1256

- HangingProtocolInformationModelMOVE, [1252](#)
- HangingProtocolStorage, [1252](#)
- HardcopyColorImageStorageSOPClassRetired, [1249](#)
- HardcopyGrayscaleImageStorageSOPClassRetired, [1249](#)
- HemodynamicWaveformStorage, [1250](#)
- HEVCH_265Main10ProfileLevel5_1, [1254](#)
- HEVCH_265MainProfileLevel5_1, [1254](#)
- HotIronColorPaletteSOPInstance, [1254](#)
- HotMetalBlueColorPaletteSOPInstance, [1253](#)
- ICBM452T1FrameofReference, [1248](#)
- ICBMSingleSubjectMRIFrameofReference, [1248](#)
- ICD11, [1253](#)
- ImageBiomarkerStandardisationInitiative, [1254](#)
- ImageOverlayBoxSOPClassRetired, [1249](#)
- ImplantAssemblyTemplateInformationModelFIND, [1256](#)
- ImplantAssemblyTemplateInformationModelGET, [1256](#)
- ImplantAssemblyTemplateInformationModelMOVE, [1256](#)
- ImplantAssemblyTemplateStorage, [1256](#)
- ImplantationPlanSRStorage, [1255](#)
- ImplantTemplateGroupInformationModelFIND, [1256](#)
- ImplantTemplateGroupInformationModelGET, [1256](#)
- ImplantTemplateGroupInformationModelMOVE, [1256](#)
- ImplantTemplateGroupStorage, [1256](#)
- ImplicitVRLittleEndianDefaultTransferSyntaxforDICOM, [1247](#)
- InstanceAvailabilityNotificationSOPClass, [1252](#)
- IntegratedTaxonomicInformationSystemITISTaxonomicSerialNumberTSN, [1253](#)
- IntraocularLensCalculationsStorage, [1255](#)
- IntravascularOpticalCoherenceTomographyImageStorageForPresentation, [1254](#)
- IntravascularOpticalCoherenceTomographyImageStorageForProcessing, [1254](#)
- JPEG2000ImageCompression, [1247](#)
- JPEG2000ImageCompressionLosslessOnly, [1247](#)
- JPEG2000Part2MulticomponentImageCompression, [1247](#)
- JPEG2000Part2MulticomponentImageCompressionLosslessOnly,Class, [1249](#)
- JPEGBaselineProcess1DefaultTransferSyntaxforLossyJPG8BitImageCompression, [1247](#)
- JPEGExtendedHierarchicalProcess1618Retired, [1247](#)
- JPEGExtendedHierarchicalProcess1719Retired, [1247](#)
- JPEGExtendedProcess24DefaultTransferSyntaxforLossyJPG8BitImageCompression, [1247](#)
- JPEGExtendedProcess35Retired, [1247](#)
- JPEGFullProgressionHierarchicalProcess2426Retired, [1247](#)
- JPEGFullProgressionHierarchicalProcess2527Retired, [1247](#)
- JPEGFullProgressionNonHierarchicalProcess1012Retired, [1247](#)
- JPEGFullProgressionNonHierarchicalProcess1113Retired, [1247](#)
- JPEGLosslessHierarchicalProcess28Retired, [1247](#)
- JPEGLosslessHierarchicalProcess29Retired, [1247](#)
- JPEGLosslessNonHierarchicalFirstOrderPrediction-Process14SelectionValue1DefaultTransferSyntaxforLosslessJPG8BitImageCompression, [1247](#)
- JPEGLosslessNonHierarchicalProcess14, [1247](#)
- JPEGLosslessNonHierarchicalProcess15Retired, [1247](#)
- JPEGLSLosslessImageCompression, [1247](#)
- JPEGLSLossyNearLosslessImageCompression, [1247](#)
- JPEGSpectralSelectionHierarchicalProcess2022Retired, [1247](#)
- JPEGSpectralSelectionHierarchicalProcess2123Retired, [1247](#)
- JPEGSpectralSelectionNonHierarchicalProcess68Retired, [1247](#)
- JPEGSpectralSelectionNonHierarchicalProcess79Retired, [1247](#)
- JPIPRReferenced, [1247](#)
- JPIPRReferencedDeflate, [1248](#)
- KeratometryMeasurementsStorage, [1254](#)
- KeyObjectSelectionDocumentStorage, [1251](#)
- LegacyConvertedEnhancedCTImageStorage, [1253](#)
- LegacyConvertedEnhancedMRIImageStorage, [1253](#)
- LegacyConvertedEnhancedPETImageStorage, [1253](#)
- LensometryMeasurementsStorage, [1254](#)
- MacularGridThicknessandVolumeReportStorage, [1255](#)
- MammographyCADSRStorage, [1251](#)
- MayoClinicNonradiologicalImagesSBSAnatomical-SurfaceRegionGuide, [1254](#)
- MediaCreationManagementSOPClassUID, [1249](#)
- MediaStorageDirectoryStorage, [1248](#)
- ModalityPerformedProcedureStepNotificationSOP-Class, [1248](#)
- ModalityPerformedProcedureStepRetrieveSOP-Class, [1248](#)
- ModalityPerformedProcedureStepSOPClass, [1248](#)
- ModalityWorklistInformationModelFIND, [1252](#)
- MouseGenomeInitiativeMGI, [1253](#)
- MPEG2MainProfileHighLevel, [1253](#)
- MPEG2MainProfileMainLevel, [1248](#)
- MPEG4AVCH_264HighProfileLevel4_1, [1253](#)
- MPEG4AVCH_264HighProfileLevel4_2For2DVideo, [1253](#)

- 1254
- MPEG4AVCH_264HighProfileLevel4_2For3DVideo, 1254
- MPEG4AVCH_264StereoHighProfileLevel4_2, 1254
- MRImageStorage, 1250
- MRSpectroscopyStorage, 1250
- MultiframeGrayscaleByteSecondaryCaptureImageStorage, 1250
- MultiframeGrayscaleWordSecondaryCaptureImageStorage, 1250
- MultiframeSingleBitSecondaryCaptureImageStorage, 1250
- MultiframeTrueColorSecondaryCaptureImageStorage, 1250
- MultipleVolumeRenderingVolumetricPresentationStateStorage, 1254
- NativeDICOMModel, 1256
- NewYorkUniversityMelanomaClinicalCooperativeGroup, 1254
- NuclearMedicineImageStorage, 1250
- NuclearMedicineImageStorageRetired, 1250
- Null0, 1254
- Null1, 1254
- operator TSType, 1267
- OphthalmicAxialMeasurementsStorage, 1254
- OphthalmicOpticalCoherenceTomographyBscanVolumeAnalysisStorage, 1254
- OphthalmicOpticalCoherenceTomographyEnFaceImageStorage, 1254
- OphthalmicPhotography16BitImageStorage, 1251
- OphthalmicPhotography8BitImageStorage, 1251
- OphthalmicThicknessMapStorage, 1255
- OphthalmicTomographyImageStorage, 1251
- OphthalmicVisualFieldStaticPerimetryMeasurementsStorage, 1255
- Papyrus3ImplicitVRLittleEndian, 1253
- ParametricMapStorage, 1254
- PatientRadiationDoseSRStorage, 1255
- PatientRootQueryRetrieveInformationModelFIND, 1251
- PatientRootQueryRetrieveInformationModelGET, 1251
- PatientRootQueryRetrieveInformationModelMOVE, 1251
- PatientStudyOnlyQueryRetrieveInformationModelFINDRetired, 1251
- PatientStudyOnlyQueryRetrieveInformationModelGETRetired, 1252
- PatientStudyOnlyQueryRetrieveInformationModelMOVETRetired, 1252
- PerformedImagingAgentAdministrationSRStorage, 1255
- PET20StepColorPaletteSOPInstance, 1253
- PETColorPaletteSOPInstance, 1253
- PlannedImagingAgentAdministrationSRStorage, 1255
- PositronEmissionTomographyImageStorage, 1251
- PresentationLUTSOPClass, 1249
- PrinterConfigurationRetrievalSOPClass, 1249
- PrinterConfigurationRetrievalSOPInstance, 1249
- PrinterSOPClass, 1249
- PrinterSOPInstance, 1249
- PrintJobSOPClass, 1249
- PrintQueueManagementSOPClassRetired, 1249
- PrintQueueSOPInstanceRetired, 1249
- ProceduralEventLoggingSOPClass, 1248
- ProceduralEventLoggingSOPInstance, 1248
- ProcedureLogStorage, 1251
- ProductCharacteristicsQuerySOPClass, 1252
- ProtocolApprovalInformationModelFIND, 1255
- ProtocolApprovalInformationModelGET, 1255
- ProtocolApprovalInformationModelMOVE, 1255
- ProtocolApprovalStorage, 1255
- PseudoColorSoftcopyPresentationStateStorageSOPClass, 1250
- PubChemCompoundCID, 1253
- PullPrintRequestSOPClassRetired, 1249
- PullStoredPrintManagementMetaSOPClassRetired, 1249
- RadiomicsOntology, 1254
- RadiopharmaceuticalRadiationDoseSRStorage, 1255
- RawDataStorage, 1250
- RealWorldValueMappingStorage, 1250
- ReferencedColorPrintManagementMetaSOPClassRetired, 1249
- ReferencedGrayscalePrintManagementMetaSOPClassRetired, 1249
- ReferencedImageBoxSOPClassRetired, 1249
- RespiratoryWaveformStorage, 1254
- RFC2557MIMEencapsulation, 1248
- RLELossless, 1248
- RTBeamsDeliveryInstructionStorage, 1256
- RTBeamsDeliveryInstructionStorageSupplement74FrozenDraft, 1252
- RTBeamsTreatmentRecordStorage, 1251
- RTBrachyApplicationSetupDeliveryInstructionStorage, 1256
- RTBrachyTreatmentRecordStorage, 1251
- RTConventionalMachineVerification, 1256
- RTConventionalMachineVerificationSupplement74FrozenDraft, 1252
- RTDoseStorage, 1251
- RTImageStorage, 1251
- RTIonBeamsTreatmentRecordStorage, 1251
- RTIonMachineVerification, 1256
- RTIonMachineVerificationSupplement74FrozenDraft, 1252

- RTIonPlanStorage, [1251](#)
- RTPhysicianIntentStorage, [1255](#)
- RTPlanStorage, [1251](#)
- RTSegmentAnnotationStorage, [1255](#)
- RTStructureSetStorage, [1251](#)
- RTTreatmentSummaryRecordStorage, [1251](#)
- SecondaryCaptureImageStorage, [1250](#)
- SegmentationStorage, [1250](#)
- SegmentedVolumeRenderingVolumetricPresentationStateStorage, [1254](#)
- SetFromUID, [1267](#)
- SimplifiedAdultEchoSRStorage, [1255](#)
- SpatialFiducialsStorage, [1250](#)
- SpatialRegistrationStorage, [1250](#)
- SpectaclePrescriptionReportStorage, [1254](#)
- SPM2AVG152PDFFrameofReference, [1248](#)
- SPM2AVG152T1FrameofReference, [1248](#)
- SPM2AVG152T2FrameofReference, [1248](#)
- SPM2AVG305T1FrameofReference, [1248](#)
- SPM2BRAINMASKFrameofReference, [1248](#)
- SPM2CSFFFrameofReference, [1248](#)
- SPM2EPIFrameofReference, [1248](#)
- SPM2FILT1FrameofReference, [1248](#)
- SPM2GRAYFrameofReference, [1248](#)
- SPM2PDFFrameofReference, [1248](#)
- SPM2PETFrameofReference, [1248](#)
- SPM2SINGLESUBJT1FrameofReference, [1248](#)
- SPM2SPECTFrameofReference, [1248](#)
- SPM2T1FrameofReference, [1248](#)
- SPM2T2FrameofReference, [1248](#)
- SPM2TRANSMFrameofReference, [1248](#)
- SPM2WHITEFrameofReference, [1248](#)
- SpringColorPaletteSOPInstance, [1253](#)
- StandaloneCurveStorageRetired, [1250](#)
- StandaloneModalityLUTStorageRetired, [1250](#)
- StandaloneOverlayStorageRetired, [1250](#)
- StandalonePETCurveStorageRetired, [1251](#)
- StandaloneVOILUTStorageRetired, [1250](#)
- StereometricRelationshipStorage, [1251](#)
- StorageCommitmentPullModelSOPClassRetired, [1248](#)
- StorageCommitmentPullModelSOPInstanceRetired, [1248](#)
- StorageCommitmentPushModelSOPClass, [1248](#)
- StorageCommitmentPushModelSOPInstance, [1248](#)
- StorageServiceClass, [1249](#)
- StoredPrintStorageSOPClassRetired, [1249](#)
- StudyComponentManagementSOPClassRetired, [1248](#)
- StudyRootQueryRetrieveInformationModelIFIND, [1251](#)
- StudyRootQueryRetrieveInformationModelIGET, [1251](#)
- StudyRootQueryRetrieveInformationModelMOVE, [1251](#)
- SubjectiveRefractionMeasurementsStorage, [1254](#)
- SubstanceAdministrationLoggingSOPClass, [1248](#)
- SubstanceAdministrationLoggingSOPInstance, [1248](#)
- SubstanceApprovalQuerySOPClass, [1252](#)
- SummerColorPaletteSOPInstance, [1253](#)
- SurfaceScanMeshStorage, [1254](#)
- SurfaceScanPointCloudStorage, [1254](#)
- SurfaceSegmentationStorage, [1253](#)
- TalairachBrainAtlasFrameofReference, [1248](#)
- TextSRStorageTrialRetired, [1251](#)
- TractographyResultsStorage, [1254](#)
- TransferSyntaxStringsType, [1247](#)
- TSName, [1247](#)
- TSType, [1256](#)
- UberonOntology, [1253](#)
- uid_1_2_840_10008_15_0_3_1, [1262](#)
- uid_1_2_840_10008_15_0_3_10, [1262](#)
- uid_1_2_840_10008_15_0_3_11, [1262](#)
- uid_1_2_840_10008_15_0_3_12, [1262](#)
- uid_1_2_840_10008_15_0_3_13, [1262](#)
- uid_1_2_840_10008_15_0_3_14, [1262](#)
- uid_1_2_840_10008_15_0_3_15, [1262](#)
- uid_1_2_840_10008_15_0_3_16, [1262](#)
- uid_1_2_840_10008_15_0_3_17, [1262](#)
- uid_1_2_840_10008_15_0_3_18, [1262](#)
- uid_1_2_840_10008_15_0_3_19, [1262](#)
- uid_1_2_840_10008_15_0_3_2, [1262](#)
- uid_1_2_840_10008_15_0_3_20, [1262](#)
- uid_1_2_840_10008_15_0_3_21, [1262](#)
- uid_1_2_840_10008_15_0_3_22, [1262](#)
- uid_1_2_840_10008_15_0_3_23, [1262](#)
- uid_1_2_840_10008_15_0_3_24, [1262](#)
- uid_1_2_840_10008_15_0_3_25, [1262](#)
- uid_1_2_840_10008_15_0_3_26, [1262](#)
- uid_1_2_840_10008_15_0_3_27, [1262](#)
- uid_1_2_840_10008_15_0_3_28, [1262](#)
- uid_1_2_840_10008_15_0_3_29, [1262](#)
- uid_1_2_840_10008_15_0_3_3, [1262](#)
- uid_1_2_840_10008_15_0_3_30, [1262](#)
- uid_1_2_840_10008_15_0_3_31, [1262](#)
- uid_1_2_840_10008_15_0_3_4, [1262](#)
- uid_1_2_840_10008_15_0_3_5, [1262](#)
- uid_1_2_840_10008_15_0_3_6, [1262](#)
- uid_1_2_840_10008_15_0_3_7, [1262](#)
- uid_1_2_840_10008_15_0_3_8, [1262](#)
- uid_1_2_840_10008_15_0_3_9, [1262](#)
- uid_1_2_840_10008_15_0_4_1, [1262](#)
- uid_1_2_840_10008_15_0_4_2, [1262](#)
- uid_1_2_840_10008_15_0_4_3, [1262](#)
- uid_1_2_840_10008_15_0_4_4, [1262](#)
- uid_1_2_840_10008_15_0_4_5, [1262](#)
- uid_1_2_840_10008_15_0_4_6, [1262](#)

uid_1_2_840_10008_15_0_4_7, [1262](#)
uid_1_2_840_10008_15_0_4_8, [1262](#)
uid_1_2_840_10008_15_1_1, [1265](#)
uid_1_2_840_10008_1_1, [1256](#)
uid_1_2_840_10008_1_2, [1256](#)
uid_1_2_840_10008_1_20, [1263](#)
uid_1_2_840_10008_1_20_1, [1258](#)
uid_1_2_840_10008_1_20_1_1, [1258](#)
uid_1_2_840_10008_1_20_2, [1258](#)
uid_1_2_840_10008_1_20_2_1, [1258](#)
uid_1_2_840_10008_1_2_1, [1256](#)
uid_1_2_840_10008_1_2_1_99, [1256](#)
uid_1_2_840_10008_1_2_2, [1256](#)
uid_1_2_840_10008_1_2_4_100, [1257](#)
uid_1_2_840_10008_1_2_4_101, [1263](#)
uid_1_2_840_10008_1_2_4_102, [1263](#)
uid_1_2_840_10008_1_2_4_103, [1263](#)
uid_1_2_840_10008_1_2_4_104, [1263](#)
uid_1_2_840_10008_1_2_4_105, [1263](#)
uid_1_2_840_10008_1_2_4_106, [1263](#)
uid_1_2_840_10008_1_2_4_107, [1263](#)
uid_1_2_840_10008_1_2_4_108, [1263](#)
uid_1_2_840_10008_1_2_4_50, [1257](#)
uid_1_2_840_10008_1_2_4_51, [1257](#)
uid_1_2_840_10008_1_2_4_52, [1257](#)
uid_1_2_840_10008_1_2_4_53, [1257](#)
uid_1_2_840_10008_1_2_4_54, [1257](#)
uid_1_2_840_10008_1_2_4_55, [1257](#)
uid_1_2_840_10008_1_2_4_56, [1257](#)
uid_1_2_840_10008_1_2_4_57, [1257](#)
uid_1_2_840_10008_1_2_4_58, [1257](#)
uid_1_2_840_10008_1_2_4_59, [1257](#)
uid_1_2_840_10008_1_2_4_60, [1257](#)
uid_1_2_840_10008_1_2_4_61, [1257](#)
uid_1_2_840_10008_1_2_4_62, [1257](#)
uid_1_2_840_10008_1_2_4_63, [1257](#)
uid_1_2_840_10008_1_2_4_64, [1257](#)
uid_1_2_840_10008_1_2_4_65, [1257](#)
uid_1_2_840_10008_1_2_4_66, [1257](#)
uid_1_2_840_10008_1_2_4_70, [1257](#)
uid_1_2_840_10008_1_2_4_80, [1257](#)
uid_1_2_840_10008_1_2_4_81, [1257](#)
uid_1_2_840_10008_1_2_4_90, [1257](#)
uid_1_2_840_10008_1_2_4_91, [1257](#)
uid_1_2_840_10008_1_2_4_92, [1257](#)
uid_1_2_840_10008_1_2_4_93, [1257](#)
uid_1_2_840_10008_1_2_4_94, [1257](#)
uid_1_2_840_10008_1_2_4_95, [1257](#)
uid_1_2_840_10008_1_2_5, [1257](#)
uid_1_2_840_10008_1_2_6_1, [1257](#)
uid_1_2_840_10008_1_2_6_2, [1257](#)
uid_1_2_840_10008_1_3_10, [1257](#)
uid_1_2_840_10008_1_40, [1258](#)
uid_1_2_840_10008_1_40_1, [1258](#)

uid_1_2_840_10008_1_42, [1258](#)
uid_1_2_840_10008_1_42_1, [1258](#)
uid_1_2_840_10008_1_4_1_1, [1257](#)
uid_1_2_840_10008_1_4_1_10, [1257](#)
uid_1_2_840_10008_1_4_1_11, [1257](#)
uid_1_2_840_10008_1_4_1_12, [1257](#)
uid_1_2_840_10008_1_4_1_13, [1257](#)
uid_1_2_840_10008_1_4_1_14, [1257](#)
uid_1_2_840_10008_1_4_1_15, [1257](#)
uid_1_2_840_10008_1_4_1_16, [1258](#)
uid_1_2_840_10008_1_4_1_17, [1258](#)
uid_1_2_840_10008_1_4_1_18, [1258](#)
uid_1_2_840_10008_1_4_1_2, [1257](#)
uid_1_2_840_10008_1_4_1_3, [1257](#)
uid_1_2_840_10008_1_4_1_4, [1257](#)
uid_1_2_840_10008_1_4_1_5, [1257](#)
uid_1_2_840_10008_1_4_1_6, [1257](#)
uid_1_2_840_10008_1_4_1_7, [1257](#)
uid_1_2_840_10008_1_4_1_8, [1257](#)
uid_1_2_840_10008_1_4_1_9, [1257](#)
uid_1_2_840_10008_1_4_2_1, [1258](#)
uid_1_2_840_10008_1_4_2_2, [1258](#)
uid_1_2_840_10008_1_5_1, [1263](#)
uid_1_2_840_10008_1_5_2, [1263](#)
uid_1_2_840_10008_1_5_3, [1263](#)
uid_1_2_840_10008_1_5_4, [1263](#)
uid_1_2_840_10008_1_5_5, [1263](#)
uid_1_2_840_10008_1_5_6, [1263](#)
uid_1_2_840_10008_1_5_7, [1263](#)
uid_1_2_840_10008_1_5_8, [1263](#)
uid_1_2_840_10008_1_9, [1258](#)
uid_1_2_840_10008_2_16_10, [1263](#)
uid_1_2_840_10008_2_16_11, [1263](#)
uid_1_2_840_10008_2_16_12, [1263](#)
uid_1_2_840_10008_2_16_13, [1263](#)
uid_1_2_840_10008_2_16_14, [1263](#)
uid_1_2_840_10008_2_16_4, [1258](#)
uid_1_2_840_10008_2_16_5, [1263](#)
uid_1_2_840_10008_2_16_6, [1263](#)
uid_1_2_840_10008_2_16_7, [1263](#)
uid_1_2_840_10008_2_16_8, [1263](#)
uid_1_2_840_10008_2_16_9, [1263](#)
uid_1_2_840_10008_2_6_1, [1258](#)
uid_1_2_840_10008_3_1_1_1, [1258](#)
uid_1_2_840_10008_3_1_2_1_1, [1258](#)
uid_1_2_840_10008_3_1_2_1_4, [1258](#)
uid_1_2_840_10008_3_1_2_2_1, [1258](#)
uid_1_2_840_10008_3_1_2_3_1, [1258](#)
uid_1_2_840_10008_3_1_2_3_2, [1258](#)
uid_1_2_840_10008_3_1_2_3_3, [1258](#)
uid_1_2_840_10008_3_1_2_3_4, [1258](#)
uid_1_2_840_10008_3_1_2_3_5, [1258](#)
uid_1_2_840_10008_3_1_2_5_1, [1258](#)
uid_1_2_840_10008_3_1_2_5_4, [1258](#)

uid_1_2_840_10008_3_1_2_5_5, [1258](#)
uid_1_2_840_10008_3_1_2_6_1, [1258](#)
uid_1_2_840_10008_4_2, [1258](#)
uid_1_2_840_10008_5_1_1_1, [1258](#)
uid_1_2_840_10008_5_1_1_14, [1258](#)
uid_1_2_840_10008_5_1_1_15, [1258](#)
uid_1_2_840_10008_5_1_1_16, [1258](#)
uid_1_2_840_10008_5_1_1_16_376, [1258](#)
uid_1_2_840_10008_5_1_1_17, [1258](#)
uid_1_2_840_10008_5_1_1_17_376, [1258](#)
uid_1_2_840_10008_5_1_1_18, [1258](#)
uid_1_2_840_10008_5_1_1_18_1, [1258](#)
uid_1_2_840_10008_5_1_1_2, [1258](#)
uid_1_2_840_10008_5_1_1_22, [1258](#)
uid_1_2_840_10008_5_1_1_23, [1259](#)
uid_1_2_840_10008_5_1_1_24, [1259](#)
uid_1_2_840_10008_5_1_1_24_1, [1259](#)
uid_1_2_840_10008_5_1_1_25, [1259](#)
uid_1_2_840_10008_5_1_1_26, [1259](#)
uid_1_2_840_10008_5_1_1_27, [1259](#)
uid_1_2_840_10008_5_1_1_29, [1259](#)
uid_1_2_840_10008_5_1_1_30, [1259](#)
uid_1_2_840_10008_5_1_1_31, [1259](#)
uid_1_2_840_10008_5_1_1_32, [1259](#)
uid_1_2_840_10008_5_1_1_33, [1259](#)
uid_1_2_840_10008_5_1_1_4, [1258](#)
uid_1_2_840_10008_5_1_1_40, [1263](#)
uid_1_2_840_10008_5_1_1_40_1, [1263](#)
uid_1_2_840_10008_5_1_1_4_1, [1258](#)
uid_1_2_840_10008_5_1_1_4_2, [1258](#)
uid_1_2_840_10008_5_1_1_9, [1258](#)
uid_1_2_840_10008_5_1_1_9_1, [1258](#)
uid_1_2_840_10008_5_1_4_1_1_1, [1259](#)
uid_1_2_840_10008_5_1_4_1_1_10, [1259](#)
uid_1_2_840_10008_5_1_4_1_1_104_1, [1261](#)
uid_1_2_840_10008_5_1_4_1_1_104_2, [1261](#)
uid_1_2_840_10008_5_1_4_1_1_104_3, [1264](#)
uid_1_2_840_10008_5_1_4_1_1_11, [1259](#)
uid_1_2_840_10008_5_1_4_1_1_11_1, [1259](#)
uid_1_2_840_10008_5_1_4_1_1_11_10, [1263](#)
uid_1_2_840_10008_5_1_4_1_1_11_11, [1263](#)
uid_1_2_840_10008_5_1_4_1_1_11_2, [1259](#)
uid_1_2_840_10008_5_1_4_1_1_11_3, [1260](#)
uid_1_2_840_10008_5_1_4_1_1_11_4, [1260](#)
uid_1_2_840_10008_5_1_4_1_1_11_5, [1263](#)
uid_1_2_840_10008_5_1_4_1_1_11_6, [1263](#)
uid_1_2_840_10008_5_1_4_1_1_11_7, [1263](#)
uid_1_2_840_10008_5_1_4_1_1_11_8, [1263](#)
uid_1_2_840_10008_5_1_4_1_1_11_9, [1263](#)
uid_1_2_840_10008_5_1_4_1_1_128, [1261](#)
uid_1_2_840_10008_5_1_4_1_1_128_1, [1262](#)
uid_1_2_840_10008_5_1_4_1_1_129, [1261](#)
uid_1_2_840_10008_5_1_4_1_1_12_1, [1260](#)
uid_1_2_840_10008_5_1_4_1_1_12_1_1, [1260](#)
uid_1_2_840_10008_5_1_4_1_1_12_2, [1260](#)
uid_1_2_840_10008_5_1_4_1_1_12_2_1, [1260](#)
uid_1_2_840_10008_5_1_4_1_1_12_3, [1260](#)
uid_1_2_840_10008_5_1_4_1_1_12_77, [1263](#)
uid_1_2_840_10008_5_1_4_1_1_130, [1264](#)
uid_1_2_840_10008_5_1_4_1_1_131, [1264](#)
uid_1_2_840_10008_5_1_4_1_1_13_1_1, [1260](#)
uid_1_2_840_10008_5_1_4_1_1_13_1_2, [1260](#)
uid_1_2_840_10008_5_1_4_1_1_13_1_3, [1262](#)
uid_1_2_840_10008_5_1_4_1_1_13_1_4, [1263](#)
uid_1_2_840_10008_5_1_4_1_1_13_1_5, [1263](#)
uid_1_2_840_10008_5_1_4_1_1_14_1, [1263](#)
uid_1_2_840_10008_5_1_4_1_1_14_2, [1263](#)
uid_1_2_840_10008_5_1_4_1_1_1_1, [1259](#)
uid_1_2_840_10008_5_1_4_1_1_1_1_1, [1259](#)
uid_1_2_840_10008_5_1_4_1_1_1_2, [1259](#)
uid_1_2_840_10008_5_1_4_1_1_1_2_1, [1259](#)
uid_1_2_840_10008_5_1_4_1_1_1_3, [1259](#)
uid_1_2_840_10008_5_1_4_1_1_1_3_1, [1259](#)
uid_1_2_840_10008_5_1_4_1_1_2, [1259](#)
uid_1_2_840_10008_5_1_4_1_1_20, [1260](#)
uid_1_2_840_10008_5_1_4_1_1_200_1, [1264](#)
uid_1_2_840_10008_5_1_4_1_1_200_2, [1264](#)
uid_1_2_840_10008_5_1_4_1_1_200_3, [1264](#)
uid_1_2_840_10008_5_1_4_1_1_200_4, [1264](#)
uid_1_2_840_10008_5_1_4_1_1_200_5, [1264](#)
uid_1_2_840_10008_5_1_4_1_1_200_6, [1264](#)
uid_1_2_840_10008_5_1_4_1_1_2_1, [1259](#)
uid_1_2_840_10008_5_1_4_1_1_2_2, [1262](#)
uid_1_2_840_10008_5_1_4_1_1_3, [1259](#)
uid_1_2_840_10008_5_1_4_1_1_30, [1263](#)
uid_1_2_840_10008_5_1_4_1_1_3_1, [1259](#)
uid_1_2_840_10008_5_1_4_1_1_4, [1259](#)
uid_1_2_840_10008_5_1_4_1_1_40, [1263](#)
uid_1_2_840_10008_5_1_4_1_1_481_1, [1261](#)
uid_1_2_840_10008_5_1_4_1_1_481_10, [1264](#)
uid_1_2_840_10008_5_1_4_1_1_481_11, [1264](#)
uid_1_2_840_10008_5_1_4_1_1_481_2, [1261](#)
uid_1_2_840_10008_5_1_4_1_1_481_3, [1261](#)
uid_1_2_840_10008_5_1_4_1_1_481_4, [1261](#)
uid_1_2_840_10008_5_1_4_1_1_481_5, [1261](#)
uid_1_2_840_10008_5_1_4_1_1_481_6, [1261](#)
uid_1_2_840_10008_5_1_4_1_1_481_7, [1261](#)
uid_1_2_840_10008_5_1_4_1_1_481_8, [1261](#)
uid_1_2_840_10008_5_1_4_1_1_481_9, [1261](#)
uid_1_2_840_10008_5_1_4_1_1_4_1, [1259](#)
uid_1_2_840_10008_5_1_4_1_1_4_2, [1259](#)
uid_1_2_840_10008_5_1_4_1_1_4_3, [1265](#)
uid_1_2_840_10008_5_1_4_1_1_4_4, [1262](#)
uid_1_2_840_10008_5_1_4_1_1_5, [1259](#)
uid_1_2_840_10008_5_1_4_1_1_501_1, [1264](#)
uid_1_2_840_10008_5_1_4_1_1_501_2_1, [1264](#)
uid_1_2_840_10008_5_1_4_1_1_501_2_2, [1265](#)
uid_1_2_840_10008_5_1_4_1_1_501_3, [1265](#)

Generated by Doxygen

uid_1_2_840_10008_5_1_4_33, [1261](#)
 uid_1_2_840_10008_5_1_4_34_1, [1261](#)
 uid_1_2_840_10008_5_1_4_34_10, [1265](#)
 uid_1_2_840_10008_5_1_4_34_2, [1261](#)
 uid_1_2_840_10008_5_1_4_34_3, [1261](#)
 uid_1_2_840_10008_5_1_4_34_4, [1261](#)
 uid_1_2_840_10008_5_1_4_34_4_1, [1261](#)
 uid_1_2_840_10008_5_1_4_34_4_2, [1261](#)
 uid_1_2_840_10008_5_1_4_34_4_3, [1261](#)
 uid_1_2_840_10008_5_1_4_34_4_4, [1261](#)
 uid_1_2_840_10008_5_1_4_34_5, [1261](#)
 uid_1_2_840_10008_5_1_4_34_5_1, [1265](#)
 uid_1_2_840_10008_5_1_4_34_6, [1265](#)
 uid_1_2_840_10008_5_1_4_34_6_1, [1265](#)
 uid_1_2_840_10008_5_1_4_34_6_2, [1265](#)
 uid_1_2_840_10008_5_1_4_34_6_3, [1265](#)
 uid_1_2_840_10008_5_1_4_34_6_4, [1265](#)
 uid_1_2_840_10008_5_1_4_34_7, [1265](#)
 uid_1_2_840_10008_5_1_4_34_8, [1265](#)
 uid_1_2_840_10008_5_1_4_34_9, [1265](#)
 uid_1_2_840_10008_5_1_4_37_1, [1261](#)
 uid_1_2_840_10008_5_1_4_37_2, [1261](#)
 uid_1_2_840_10008_5_1_4_37_3, [1261](#)
 uid_1_2_840_10008_5_1_4_38_1, [1261](#)
 uid_1_2_840_10008_5_1_4_38_2, [1261](#)
 uid_1_2_840_10008_5_1_4_38_3, [1261](#)
 uid_1_2_840_10008_5_1_4_38_4, [1265](#)
 uid_1_2_840_10008_5_1_4_39_1, [1265](#)
 uid_1_2_840_10008_5_1_4_39_2, [1265](#)
 uid_1_2_840_10008_5_1_4_39_3, [1265](#)
 uid_1_2_840_10008_5_1_4_39_4, [1265](#)
 uid_1_2_840_10008_5_1_4_41, [1261](#)
 uid_1_2_840_10008_5_1_4_42, [1261](#)
 uid_1_2_840_10008_5_1_4_43_1, [1265](#)
 uid_1_2_840_10008_5_1_4_43_2, [1265](#)
 uid_1_2_840_10008_5_1_4_43_3, [1265](#)
 uid_1_2_840_10008_5_1_4_43_4, [1265](#)
 uid_1_2_840_10008_5_1_4_44_1, [1265](#)
 uid_1_2_840_10008_5_1_4_44_2, [1265](#)
 uid_1_2_840_10008_5_1_4_44_3, [1265](#)
 uid_1_2_840_10008_5_1_4_44_4, [1265](#)
 uid_1_2_840_10008_5_1_4_45_1, [1265](#)
 uid_1_2_840_10008_5_1_4_45_2, [1265](#)
 uid_1_2_840_10008_5_1_4_45_3, [1265](#)
 uid_1_2_840_10008_5_1_4_45_4, [1265](#)
 uid_1_2_840_10008_7_1_1, [1265](#)
 uid_1_2_840_10008_7_1_2, [1265](#)
 uid_1_2_840_10008_8_1_1, [1265](#)
 UIDs, [1266](#)
 UltrasoundImageStorage, [1250](#)
 UltrasoundImageStorageRetired, [1250](#)
 UltrasoundMultiframeImageStorage, [1250](#)
 UltrasoundMultiframeImageStorageRetired, [1249](#)
 UnifiedProcedureStepEventSOPClass, [1252](#)

UnifiedProcedureStepEventSOPClass1, [1256](#)
 UnifiedProcedureStepPullSOPClass, [1252](#)
 UnifiedProcedureStepPullSOPClass1, [1256](#)
 UnifiedProcedureStepPushSOPClass, [1252](#)
 UnifiedProcedureStepPushSOPClass1, [1256](#)
 UnifiedProcedureStepWatchSOPClass, [1252](#)
 UnifiedProcedureStepWatchSOPClass1, [1256](#)
 UnifiedWorklistandProcedureStepServiceClass, [1252](#)
 UnifiedWorklistandProcedureStepServiceClass1, [1256](#)
 UnifiedWorklistandProcedureStepSOPInstance, [1252](#)
 UniversalCoordinatedTime, [1256](#)
 UPSFilteredGlobalSubscriptionSOPInstance, [1255](#)
 VerificationSOPClass, [1247](#)
 VideoEndoscopicImageStorage, [1251](#)
 VideoMicroscopicImageStorage, [1251](#)
 VideoPhotographicImageStorage, [1251](#)
 VisualAcuityMeasurementsStorage, [1254](#)
 VLEndoscopicImageStorage, [1251](#)
 VLImageStorageTrialRetired, [1250](#)
 VLMicroscopicImageStorage, [1251](#)
 VLMultiframeImageStorageTrialRetired, [1250](#)
 VLPhotographicImageStorage, [1251](#)
 VLSlideCoordinatesMicroscopicImageStorage, [1251](#)
 VLWholeSlideMicroscopyImageStorage, [1253](#)
 VOILUTBoxSOPClass, [1249](#)
 VolumeRenderingVolumetricPresentationStateStorage, [1254](#)
 WaveformStorageTrialRetired, [1250](#)
 WideFieldOphthalmicPhotography3DCoordinatesImageStorage, [1254](#)
 WideFieldOphthalmicPhotographyStereographicProjectionImageStorage, [1254](#)
 WinterColorPaletteSOPInstance, [1253](#)
 XAXRFGayscaleSoftcopyPresentationStateStorage, [1254](#)
 XMLEncoding, [1248](#)
 XRay3DAngiographicImageStorage, [1250](#)
 XRay3DCraniofacialImageStorage, [1250](#)
 XRayAngiographicBiPlaneImageStorageRetired, [1250](#)
 XRayAngiographicImageStorage, [1250](#)
 XRayRadiationDoseSRStorage, [1251](#)
 XRayRadiofluoroscopicImageStorage, [1250](#)
 gdcmm::UNExplicitDataElement, [1333](#)
 GetLength, [1336](#)
 Read, [1336](#)
 ReadPreValue, [1336](#)
 ReadValue, [1336](#)
 ReadWithLength, [1336](#)
 gdcmm::UNExplicitImplicitDataElement, [1337](#)
 GetLength, [1340](#)

- Read, [1340](#)
- ReadPreValue, [1340](#)
- ReadValue, [1340](#)
- gdcmm::Unpacker12Bits, [1341](#)
 - Pack, [1341](#)
 - Unpack, [1341](#)
- gdcmm::Usage, [1342](#)
 - Conditional, [1343](#)
 - GetUsageString, [1344](#)
 - GetUsageType, [1344](#)
 - Invalid, [1343](#)
 - Mandatory, [1343](#)
 - operator UsageType, [1344](#)
 - operator<<, [1344](#)
 - Usage, [1343](#)
 - UsageType, [1343](#)
 - UserOption, [1343](#)
- gdcmm::UserEvent, [1345](#)
- gdcmm::UUIDGenerator, [1348](#)
 - Generate, [1349](#)
 - IsValid, [1349](#)
- gdcmm::Validate, [1349](#)
 - ~Validate, [1350](#)
 - F, [1351](#)
 - GetValidatedFile, [1351](#)
 - SetFile, [1351](#)
 - V, [1351](#)
 - Validate, [1350](#)
 - Validation, [1351](#)
- gdcmm::Value, [1352](#)
 - ~Value, [1353](#)
 - Clear, [1354](#)
 - DataElement, [1355](#)
 - GetLength, [1354](#)
 - operator==, [1354](#)
 - SetLength, [1354](#)
 - SetLengthOnly, [1354](#)
 - Value, [1353](#)
- gdcmm::ValueIO< TDE, TSwap, TType >, [1355](#)
 - Read, [1355](#)
 - Write, [1355](#)
- gdcmm::Version, [1357](#)
 - ~Version, [1357](#)
 - GetBuildVersion, [1358](#)
 - GetMajorVersion, [1358](#)
 - GetMinorVersion, [1358](#)
 - GetVersion, [1358](#)
 - operator<<, [1358](#)
 - Print, [1358](#)
 - Version, [1357](#)
- gdcmm::VL, [1359](#)
 - GetLength, [1360](#)
 - GetVL16Max, [1360](#)
 - GetVL32Max, [1361](#)
- IsOdd, [1361](#)
- IsUndefined, [1361](#)
- operator uint32_t, [1361](#)
- operator<<, [1363](#)
- operator++, [1361](#)
- operator+=, [1361](#)
- Read, [1362](#)
- Read16, [1362](#)
- SetToUndefined, [1362](#)
- Type, [1360](#)
- VL, [1360](#)
- Write, [1362](#)
- Write16, [1362](#)
- gdcmm::VM, [1363](#)
 - Compatible, [1367](#)
 - GetIndex, [1367](#)
 - GetLength, [1367](#)
 - GetNumberOfElementsFromArray, [1367](#)
 - GetVMString, [1367](#)
 - GetVMType, [1367](#)
 - GetVMTypeFromLength, [1368](#)
 - IsValid, [1368](#)
 - operator VMType, [1368](#)
 - operator<<, [1368](#)
 - VM, [1366](#)
 - VM0, [1366](#)
 - VM1, [1366](#)
 - VM10, [1366](#)
 - VM12, [1366](#)
 - VM16, [1366](#)
 - VM18, [1366](#)
 - VM1_2, [1366](#)
 - VM1_3, [1366](#)
 - VM1_32, [1366](#)
 - VM1_4, [1366](#)
 - VM1_5, [1366](#)
 - VM1_8, [1366](#)
 - VM1_99, [1366](#)
 - VM1_n, [1366](#)
 - VM2, [1366](#)
 - VM24, [1366](#)
 - VM256, [1366](#)
 - VM28, [1366](#)
 - VM2_2n, [1366](#)
 - VM2_n, [1366](#)
 - VM3, [1366](#)
 - VM30_30n, [1366](#)
 - VM32, [1366](#)
 - VM35, [1366](#)
 - VM3_3n, [1366](#)
 - VM3_4, [1366](#)
 - VM3_n, [1366](#)
 - VM4, [1366](#)
 - VM47_47n, [1366](#)

- VM4_4n, [1366](#)
- VM5, [1366](#)
- VM6, [1366](#)
- VM6_6n, [1366](#)
- VM6_n, [1366](#)
- VM7_7n, [1366](#)
- VM8, [1366](#)
- VM9, [1366](#)
- VM99, [1366](#)
- VM_END, [1366](#)
- VMType, [1365](#)
- gdcmm::VMToLength< T >, [1368](#)
- gdcmm::VR, [1369](#)
 - AE, [1371](#)
 - AS, [1371](#)
 - AT, [1371](#)
 - CanDisplay, [1372](#)
 - Compatible, [1372](#)
 - CS, [1371](#)
 - DA, [1371](#)
 - DS, [1371](#)
 - DT, [1371](#)
 - FD, [1371](#)
 - FL, [1371](#)
 - GetLength, [1372](#)
 - GetSize, [1373](#)
 - GetSizeof, [1373](#)
 - GetVRString, [1373](#)
 - GetVRStringFromFile, [1373](#)
 - GetVRType, [1373](#)
 - GetVRTypeFromFile, [1373](#)
 - INVALID, [1371](#)
 - IS, [1371](#)
 - IsASCII, [1373](#)
 - IsASCII2, [1374](#)
 - IsBinary, [1374](#)
 - IsBinary2, [1374](#)
 - IsDual, [1374](#)
 - IsSwap, [1374](#)
 - IsValid, [1374](#)
 - IsVRFile, [1374](#)
 - LO, [1371](#)
 - LT, [1371](#)
 - OB, [1371](#)
 - OB_OW, [1371](#)
 - OD, [1371](#)
 - OF, [1371](#)
 - OL, [1371](#)
 - operator VRTYPE, [1375](#)
 - operator< <, [1375](#)
 - OV, [1371](#)
 - OW, [1371](#)
 - PN, [1371](#)
 - Read, [1375](#)
 - SH, [1371](#)
 - SL, [1371](#)
 - SQ, [1371](#)
 - SS, [1371](#)
 - ST, [1371](#)
 - SV, [1371](#)
 - TM, [1371](#)
 - UC, [1371](#)
 - UI, [1371](#)
 - UL, [1371](#)
 - UN, [1371](#)
 - UR, [1371](#)
 - US, [1371](#)
 - US_OW, [1371](#)
 - US_SS, [1371](#)
 - US_SS_OW, [1371](#)
 - UT, [1371](#)
 - UV, [1371](#)
 - VL16, [1371](#)
 - VL32, [1371](#)
 - VR, [1372](#)
 - VR_END, [1371](#)
 - VR_VM1, [1371](#)
 - VRALL, [1371](#)
 - VRASCII, [1371](#)
 - VRBINARY, [1371](#)
 - VRTYPE, [1370](#)
 - Write, [1375](#)
- gdcmm::VR16ExplicitDataElement, [1376](#)
 - GetLength, [1378](#)
 - Read, [1378](#)
 - ReadPreValue, [1379](#)
 - ReadValue, [1379](#)
 - ReadWithLength, [1379](#)
- gdcmm::VRTToEncoding< T >, [1379](#)
- gdcmm::VRTToType< T >, [1380](#)
- gdcmm::VRVLSIZE< 0 >, [1381](#)
 - Read, [1381](#)
 - Write, [1381](#)
- gdcmm::VRVLSIZE< 1 >, [1382](#)
 - Read, [1383](#)
 - Write, [1383](#)
- gdcmm::VRVLSIZE< T >, [1380](#)
- gdcmm::Waveform, [1493](#)
 - Waveform, [1494](#)
- gdcmm::WLMFindQuery, [1494](#)
 - GetAbstractSyntaxUID, [1497](#)
 - GetTagListByLevel, [1497](#)
 - GetValidDataSet, [1497](#)
 - InitializeDataSet, [1497](#)
 - QueryFactory, [1498](#)
 - ValidateQuery, [1497](#)
 - WLMFindQuery, [1497](#)
- gdcmm::Writer, [1498](#)

- ~Writer, [1501](#)
- CheckFileMetaInformationOff, [1501](#)
- CheckFileMetaInformationOn, [1501](#)
- GetCheckFileMetaInformation, [1501](#)
- GetFile, [1501](#)
- GetStreamPtr, [1501](#)
- Ofstream, [1503](#)
- SetCheckFileMetaInformation, [1502](#)
- SetFile, [1502](#)
- SetFileName, [1502](#)
- SetStream, [1502](#)
- SetWriteDataSetOnly, [1503](#)
- Stream, [1503](#)
- StreamImageWriter, [1503](#)
- Write, [1503](#)
- Writer, [1501](#)
- gdcm::XMLDictReader, [1504](#)
 - ~XMLDictReader, [1505](#)
 - CharacterDataHandler, [1506](#)
 - EndElement, [1506](#)
 - GetDict, [1506](#)
 - HandleDescription, [1506](#)
 - HandleEntry, [1506](#)
 - StartElement, [1506](#)
 - XMLDictReader, [1505](#)
- gdcm::XMLPrinter, [1507](#)
 - ~XMLPrinter, [1508](#)
 - F, [1510](#)
 - GetPrintStyle, [1508](#)
 - HandleBulkData, [1508](#)
 - LOADBULKDATA, [1508](#)
 - OnlyUUID, [1508](#)
 - Print, [1508](#)
 - PrintDataElement, [1509](#)
 - PrintDataSet, [1509](#)
 - PrintSQ, [1509](#)
 - PrintStyle, [1510](#)
 - PrintStyles, [1508](#)
 - SetFile, [1509](#)
 - SetStyle, [1509](#)
 - XMLPrinter, [1508](#)
- gdcm::XMLPrivateDictReader, [1510](#)
 - ~XMLPrivateDictReader, [1512](#)
 - CharacterDataHandler, [1512](#)
 - EndElement, [1512](#)
 - GetPrivateDict, [1512](#)
 - HandleDescription, [1512](#)
 - HandleEntry, [1513](#)
 - StartElement, [1513](#)
 - XMLPrivateDictReader, [1512](#)
- gdcm_assert
 - gdcmException.h, [1542](#)
- gdcm_debug_assert
 - gdcmException.h, [1543](#)
- GDCM_DIFFERENT
 - gdcm, [61](#)
- GDCM_DO_JOIN
 - gdcmStaticAssert.h, [1570](#)
- GDCM_DO_JOIN2
 - gdcmStaticAssert.h, [1570](#)
- GDCM_EQUAL
 - gdcm, [61](#)
- GDCM_EXPORT
 - gdcmWin32.h, [1598](#)
- gdcm_forced_assert
 - gdcmException.h, [1543](#)
- GDCM_FUNCTION
 - gdcmTrace.h, [1589](#)
- GDCM_GREATER
 - gdcm, [61](#)
- GDCM_GREATEROREQUAL
 - gdcm, [61](#)
- GDCM_JOIN
 - gdcmStaticAssert.h, [1570](#)
- GDCM_LEGACY
 - gdcmLegacyMacro.h, [1550](#)
- GDCM_LEGACY_BODY
 - gdcmLegacyMacro.h, [1550](#)
- GDCM_LEGACY_REPLACED_BODY
 - gdcmLegacyMacro.h, [1550](#)
- GDCM_LESS
 - gdcm, [61](#)
- GDCM_LESOREQUAL
 - gdcm, [61](#)
- GDCM_NOOP_STATEMENT
 - gdcmLegacyMacro.h, [1550](#)
- GDCM_STATIC_ASSERT
 - gdcm::Attribute< Group, Element, TVR, TVM >, [132](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM1 >, [142](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM1_3 >, [149](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM1_8 >, [155](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM1_n >, [161](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM2_2n >, [169](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM2_n >, [175](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM3_3n >, [182](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM3_n >, [188](#)
 - gdcmStaticAssert.h, [1570](#)
- gdcmAAabortPDU.h, [2020](#), [2021](#)
- gdcmAAAssociateACPDU.h, [2021](#), [2022](#)
- gdcmAAAssociateRJPDU.h, [2024](#)

gdcmAAssociateRQPDU.h, 2025, 2026
gdcmAbstractSyntax.h, 2028, 2029
gdcmAnonymizeEvent.h, 1827, 1829
gdcmAnonymizer.h, 1829, 1830
gdcmApplicationContext.h, 2030, 2031
gdcmApplicationEntity.h, 1832
gdcmAReleaseRPPDU.h, 2031, 2032
gdcmAReleaseRQPDU.h, 2033, 2034
gdcmARTIMTimer.h, 2034, 2035
gdcmASN1.h, 1515, 1516
gdcmAssertAlwaysMacro
 gdcmTrace.h, 1589
gdcmAssertMacro
 gdcmTrace.h, 1589
gdcmAsynchronousOperationsWindowSub.h, 2036
gdcmAttribute.h, 1636, 1637
gdcmAudioCodec.h, 1833, 1834
gdcmBase64.h, 1517
gdcmBaseCompositeMessage.h, 2037, 2038
gdcmBaseNormalizedMessage.h, 2039, 2040
gdcmBasePDU.h, 2040, 2041
gdcmBaseQuery.h, 2042, 2043
gdcmBaseRootQuery.h, 2044, 2045
gdcmBasicOffsetTable.h, 1650, 1651
gdcmBitmap.h, 1834, 1835
gdcmBitmapToBitmapFilter.h, 1838
gdcmBoxRegion.h, 1518, 1519
gdcmByteBuffer.h, 1653, 1654
gdcmByteSwap.h, 1519, 1520
gdcmByteSwapFilter.h, 1656
gdcmByteValue.h, 1657, 1658
gdcmCAPICryptoFactory.h, 1521, 1522
gdcmCAPICryptographicMessageSyntax.h, 1522, 1523
gdcmCEchoMessages.h, 2046, 2047
gdcmCFindMessages.h, 2047, 2048
gdcmCleaner.h, 1839, 1840
gdcmCMoveMessages.h, 2049, 2050
gdcmCodec.h, 1841, 1842
gdcmCoder.h, 1842, 1843
gdcmCodeString.h, 1661, 1662
gdcmCommand.h, 1525, 1526
gdcmCommandDataSet.h, 2050, 2051
gdcmCompositeMessageFactory.h, 2052, 2053
gdcmCompositeNetworkFunctions.h, 2053, 2054
gdcmConstCharWrapper.h, 1844
gdcmCP246ExplicitDataElement.h, 1663, 1664
gdcmCryptoFactory.h, 1528, 1529
gdcmCryptographicMessageSyntax.h, 1530, 1531
gdcmCSAElement.h, 1664, 1666
gdcmCSAHeader.h, 1668
gdcmCSAHeaderDict.h, 1599, 1600
gdcmCSAHeaderDictEntry.h, 1602, 1603
gdcmCStoreMessages.h, 2055, 2056
gdcmCurve.h, 1845, 1846
gdcmDataElement.h, 1670, 1671
gdcmDataEvent.h, 1532, 1533
gdcmDataSet.h, 1674, 1675
gdcmDataSetEvent.h, 1678, 1679
gdcmDataSetHelper.h, 1847, 1848
gdcmDebugMacro
 gdcmTrace.h, 1590
gdcmDecoder.h, 1848, 1849
gdcmDefinedTerms.h, 1776, 1777
gdcmDeflateStream.h, 1534
gdcmDefs.h, 1777, 1779
gdcmDeltaEncodingCodec.h, 1850, 1851
gdcmDICOMDIR.h, 1851, 1852
gdcmDICOMDIRGenerator.h, 1853, 1854
gdcmDict.h, 1605, 1606
gdcmDictConverter.h, 1610, 1611
gdcmDictEntry.h, 1612, 1613
gdcmDictPrinter.h, 1855
gdcmDicts.h, 1615, 1616
gdcmDIMSE.h, 2057
gdcmDirectionCosines.h, 1856, 1857
gdcmDirectory.h, 1534, 1535
gdcmDirectoryHelper.h, 1857, 1858
gdcmDPath.h, 1859, 1860
gdcmDummyValueGenerator.h, 1537
gdcmDumper.h, 1861, 1862
gdcmElement.h, 1680, 1681
gdcmEmptyMaskGenerator.h, 1863
gdcmEncapsulatedDocument.h, 1864, 1865
gdcmEnumeratedValues.h, 1780
gdcmEquipmentManufacturer.h, 1865, 1866
gdcmErrorMacro
 gdcmTrace.h, 1590
gdcmEvent.h, 1538, 1540
 gdcmEventMacro, 1539
gdcmEventMacro
 gdcmEvent.h, 1539
gdcmException.h, 1541, 1543
 gdcm_assert, 1542
 gdcm_debug_assert, 1543
 gdcm_forced_assert, 1543
gdcmExplicitDataElement.h, 1692, 1693
gdcmExplicitImplicitDataElement.h, 1694, 1695
gdcmFiducials.h, 1867
gdcmFile.h, 1696, 1697
gdcmFileAnonymizer.h, 1868, 1869
gdcmFileChangeTransferSyntax.h, 1869, 1870
gdcmFileDecompressLookupTable.h, 1871, 1872
gdcmFileDerivation.h, 1873
gdcmFileExplicitFilter.h, 1874, 1875
gdcmFileMetaInformation.h, 1697, 1699
gdcmFilename.h, 1545
gdcmFileNameEvent.h, 1546, 1547
gdcmFilenameGenerator.h, 1548

gdcmlFileSet.h, 1700, 1702
 gdcmlFileStreamer.h, 1876
 gdcmlFindPatientRootQuery.h, 2059, 2060
 gdcmlFindStudyRootQuery.h, 2061
 gdcmlFragment.h, 1702, 1704
 gdcmlGlobal.h, 1617, 1618
 gdcmlGroupDict.h, 1619, 1620
 gdcmlIconImage.h, 1877, 1878
 gdcmlIconImageFilter.h, 1879, 1880
 gdcmlIconImageGenerator.h, 1881, 1882
 gdcmlImage.h, 1882, 1884
 gdcmlImageApplyLookupTable.h, 1885
 gdcmlImageChangePhotometricInterpretation.h, 1886, 1887
 gdcmlImageChangePlanarConfiguration.h, 1889
 gdcmlImageChangeTransferSyntax.h, 1890, 1891
 gdcmlImageCodec.h, 1892, 1893
 gdcmlImageConverter.h, 1895, 1896
 gdcmlImageFragmentSplitter.h, 1897
 gdcmlImageHelper.h, 1898, 1899
 gdcmlImageReader.h, 1900, 1901
 gdcmlImageRegionReader.h, 1902, 1903
 gdcmlImageToImageFilter.h, 1904
 gdcmlImageWriter.h, 1905, 1906
 gdcmlImplementationClassUIDSub.h, 2062, 2063
 gdcmlImplementationUIDSub.h, 2064
 gdcmlImplementationVersionNameSub.h, 2065, 2066
 gdcmlImplicitDataElement.h, 1707
 gdcmlIOD.h, 1781, 1782
 gdcmlIODEntry.h, 1784, 1786
 gdcmlIODs.h, 1786, 1788
 gdcmlIPPSorter.h, 1906, 1907
 gdcmlItem.h, 1708, 1709
 gdcmlJPEG12Codec.h, 1908, 1909
 gdcmlJPEG16Codec.h, 1910
 gdcmlJPEG2000Codec.h, 1911, 1912
 gdcmlJPEG8Codec.h, 1913, 1914
 gdcmlJPEGCodec.h, 1915, 1916
 gdcmlJPEGLSCodec.h, 1917, 1918
 gdcmlJSON.h, 1919
 gdcmlKAKADUCodec.h, 1921
 gdcmlLegacyMacro.h, 1549, 1551
 GDCM_LEGACY, 1550
 GDCM_LEGACY_BODY, 1550
 GDCM_LEGACY_REPLACED_BODY, 1550
 GDCM_NOOP_STATEMENT, 1550
 gdcmlLO.h, 1714
 gdcmlLookupTable.h, 1922, 1923
 gdcmlMacro.h, 1789, 1790
 gdcmlMacroEntry.h, 1792, 1794
 GDCMMACROENTRY_H, 1793
 GDCMMACROENTRY_H
 gdcmlMacroEntry.h, 1793
 gdcmlMacros.h, 1795, 1796
 gdcmlMaximumLengthSub.h, 2067, 2068
 gdcmlMD5.h, 1552
 gdcmlMEC_MR3.h, 1924, 1925
 gdcmlMediaStorage.h, 1715, 1716
 gdcmlMeshPrimitive.h, 1925, 1927
 gdcmlModalityPerformedProcedureStepCreateQuery.h, 2069
 gdcmlModalityPerformedProcedureStepSetQuery.h, 2070, 2071
 gdcmlModule.h, 1797, 1799
 gdcmlModuleEntry.h, 1800, 1802
 gdcmlModules.h, 1803, 1804
 gdcmlMovePatientRootQuery.h, 2071, 2072
 gdcmlMoveStudyRootQuery.h, 2073
 gdcmlMrProtocol.h, 1719, 1720
 gdcmlNActionMessages.h, 2074, 2075
 gdcmlNCreateMessages.h, 2075, 2076
 gdcmlNDeleteMessages.h, 2077
 gdcmlNestedModuleEntries.h, 1805, 1807
 gdcmlNetworkEvents.h, 2078, 2079
 gdcmlNetworkStateID.h, 2080, 2081
 gdcmlNEventReportMessages.h, 2082, 2083
 gdcmlNGetMessages.h, 2083, 2084
 gdcmlNormalizedMessageFactory.h, 2084, 2085
 gdcmlNormalizedNetworkFunctions.h, 2086, 2087
 gdcmlNSetMessages.h, 2088
 gdcmlObject.h, 1553, 1554
 gdcmlOpenSSLCryptoFactory.h, 1555, 1556
 gdcmlOpenSSLCryptographicMessageSyntax.h, 1556, 1558
 gdcmlOpenSSLP7CryptoFactory.h, 1558, 1559
 gdcmlOpenSSLP7CryptographicMessageSyntax.h, 1560, 1561
 gdcmlOrientation.h, 1928, 1929
 gdcmlOverlay.h, 1929, 1930
 gdcmlParseException.h, 1721, 1722
 gdcmlParser.h, 1723, 1724
 gdcmlPatient.h, 1807, 1808
 gdcmlPDataTFPDU.h, 2089, 2090
 gdcmlPDElement.h, 1726, 1727
 gdcmlPDBHeader.h, 1728, 1729
 gdcmlPDFCodec.h, 1932
 gdcmlPDUFactory.h, 2091
 gdcmlPersonName.h, 1933, 1934
 gdcmlPGXCodec.h, 1935, 1936
 gdcmlPhotometricInterpretation.h, 1936, 1937
 gdcmlPixelFormat.h, 1938, 1940
 gdcmlPixmap.h, 1942, 1943
 gdcmlPixmapReader.h, 1945, 1946
 gdcmlPixmapToPixmapFilter.h, 1947
 gdcmlPixmapWriter.h, 1948, 1949
 gdcmlPNMCodec.h, 1950, 1951
 gdcmlPreamble.h, 1730, 1731
 gdcmlPresentationContext.h, 2092, 2094

gdcmPresentationContextAC.h, 2094, 2096
gdcmPresentationContextGenerator.h, 2096, 2097
gdcmPresentationContextRQ.h, 2098, 2099
gdcmPresentationDataValue.h, 2100, 2101
gdcmPrinter.h, 1951, 1953
gdcmPrivateTag.h, 1732, 1733
gdcmProgressEvent.h, 1562, 1563
gdcmPVRGCodec.h, 1954, 1955
gdcmPythonFilter.h, 2196, 2197
gdcmQueryBase.h, 2102, 2104
gdcmQueryFactory.h, 2105, 2106
gdcmQueryImage.h, 2106, 2107
gdcmQueryPatient.h, 2108, 2109
gdcmQuerySeries.h, 2110, 2111
gdcmQueryStudy.h, 2112, 2113
gdcmRAWCodec.h, 1956
gdcmReader.h, 1734, 1735
gdcmRegion.h, 1563, 1565
gdcmRescaler.h, 1957, 1958
gdcmRLECodec.h, 1959
gdcmRoleSelectionSub.h, 2113, 2114
gdcmScanner.h, 1960, 1961
gdcmScanner2.h, 1963, 1964
gdcmSegment.h, 1966, 1968
gdcmSegmentedPaletteColorLookupTable.h, 1970
gdcmSegmentHelper.h, 1971, 1972
gdcmSegmentReader.h, 1973, 1975
gdcmSegmentWriter.h, 1975, 1977
gdcmSequenceOfFragments.h, 1736, 1737
gdcmSequenceOfItems.h, 1741, 1742
gdcmSerieHelper.h, 1977, 1979
gdcmSeries.h, 1809, 1810
gdcmServiceClassApplicationInformation.h, 2115, 2116
gdcmServiceClassUser.h, 2116, 2117
gdcmSHA1.h, 1566
gdcmSimpleSubjectWatcher.h, 1980, 1981
gdcmSmartPointer.h, 1567, 1568
gdcmSOPClassExtendedNegotiationSub.h, 2119
gdcmSOPClassUIDToIOD.h, 1621
gdcmSorter.h, 1982, 1984
gdcmSpacing.h, 1985
gdcmSpectroscopy.h, 1986, 1987
gdcmSplitMosaicFilter.h, 1987, 1988
gdcmStaticAssert.h, 1569, 1571
 GDCM_DO_JOIN, 1570
 GDCM_DO_JOIN2, 1570
 GDCM_JOIN, 1570
 GDCM_STATIC_ASSERT, 1570
gdcmStreamImageReader.h, 1990
gdcmStreamImageWriter.h, 1991, 1992
gdcmStrictScanner.h, 1993, 1994
gdcmStrictScanner2.h, 1996, 1997
gdcmString.h, 1571, 1573
gdcmStringFilter.h, 1999, 2000
gdcmStudy.h, 1810, 1812
gdcmSubject.h, 1575
gdcmSurface.h, 2000, 2002
gdcmSurfaceHelper.h, 2005
gdcmSurfaceReader.h, 2007, 2008
gdcmSurfaceWriter.h, 2009, 2010
gdcmSwapCode.h, 1576, 1577
gdcmSwapper.h, 1578, 1579
gdcmSystem.h, 1581
gdcmTable.h, 1812, 1813
gdcmTableEntry.h, 1814, 1816
gdcmTableReader.h, 1816, 1818
gdcmTag.h, 1745, 1747
gdcmTagPath.h, 2010, 2011
gdcmTagToVR.h, 1750
gdcmTerminal.h, 1583, 1584
gdcmTestDriver.h, 1585
gdcmTesting.h, 1586
gdcmTrace.h, 1588, 1592
 GDCM_FUNCTION, 1589
 gdcmAssertAlwaysMacro, 1589
 gdcmAssertMacro, 1589
 gdcmDebugMacro, 1590
 gdcmErrorMacro, 1590
 gdcmWarningMacro, 1591
gdcmTransferSyntax.h, 1751, 1752
gdcmTransferSyntaxSub.h, 2120, 2122
gdcmType.h, 1819, 1820
gdcmTypes.h, 1594
gdcmUIDGenerator.h, 2012, 2013
gdcmUIDs.h, 1622, 1623
gdcmULAction.h, 2122, 2123
gdcmULActionAA.h, 2124, 2125
gdcmULActionAE.h, 2126, 2127
gdcmULActionAR.h, 2128, 2129
gdcmULActionDT.h, 2131
gdcmULBasicCallback.h, 2132, 2133
gdcmULConnection.h, 2133, 2134
gdcmULConnectionCallback.h, 2136, 2137
gdcmULConnectionInfo.h, 2137, 2139
gdcmULConnectionManager.h, 2139, 2140
gdcmULEvent.h, 2142, 2143
gdcmULTransitionTable.h, 2144, 2145
gdcmULWritingCallback.h, 2147
gdcmUNExplicitDataElement.h, 1753, 1754
gdcmUNExplicitImplicitDataElement.h, 1755, 1756
gdcmUnpacker12Bits.h, 1595, 1596
gdcmUsage.h, 1821, 1824
gdcmUserInformation.h, 2148, 2149
gdcmUUIDGenerator.h, 2014
gdcmValidate.h, 2015, 2016
gdcmValue.h, 1756, 1757
gdcmValueIO.h, 1758, 1759
gdcmVersion.h, 1596, 1597

- gdcmVL.h, [1759](#), [1760](#)
- gdcmVM.h, [1762](#), [1764](#)
 - TYPETOLENGTH, [1763](#)
- gdcmVR.h, [1765](#), [1768](#)
 - TYPETOENCODING, [1767](#)
 - VRTypeTemplateCase, [1767](#)
- gdcmVR16ExplicitDataElement.h, [1772](#), [1773](#)
- gdcmWarningMacro
 - gdcmTrace.h, [1591](#)
- gdcmWaveform.h, [2016](#), [2017](#)
- gdcmWin32.h, [1597](#), [1598](#)
 - GDCM_EXPORT, [1598](#)
- gdcmWLMFindQuery.h, [2150](#), [2151](#)
- gdcmWriter.h, [1774](#), [1775](#)
- gdcmXMLDictReader.h, [1824](#), [1825](#)
- gdcmXMLPrinter.h, [2017](#), [2018](#)
- gdcmXMLPrivateDictReader.h, [1826](#)
- GEMS
 - gdcm::Dicts, [407](#)
 - gdcm::EquipmentManufacturer, [481](#)
- GeneralAudioWaveformStorage
 - gdcm::UIDs, [1254](#)
- GeneralECGWaveformStorage
 - gdcm::MediaStorage, [748](#)
 - gdcm::UIDs, [1250](#)
- GeneralElectricMagneticResonanceImageStorage
 - gdcm::MediaStorage, [749](#)
- GeneralPurposePerformedProcedureStepSOPClass
 - gdcm::UIDs, [1252](#)
- GeneralPurposeScheduledProcedureStepSOPClass
 - gdcm::UIDs, [1252](#)
- GeneralPurposeWorklistInformationModelFIND
 - gdcm::UIDs, [1252](#)
- GeneralPurposeWorklistManagementMetaSOPClass
 - gdcm::UIDs, [1252](#)
- GeneralRelevantPatientInformationQuery
 - gdcm::UIDs, [1252](#)
- Generate
 - gdcm::DICOMDIRGenerator, [388](#)
 - gdcm::DummyValueGenerator, [424](#)
 - gdcm::FilenameGenerator, [538](#)
 - gdcm::IconImageGenerator, [575](#)
 - gdcm::UIDGenerator, [1229](#)
 - gdcm::UUIDGenerator, [1349](#)
- GenerateFromFilenames
 - gdcm::PresentationContextGenerator, [922](#)
- GenerateFromUID
 - gdcm::PresentationContextGenerator, [922](#)
- GenerateUUID
 - gdcm::UIDGenerator, [1229](#)
- GenericImplantTemplateInformationModelFIND
 - gdcm::UIDs, [1256](#)
- GenericImplantTemplateInformationModelGET
 - gdcm::UIDs, [1256](#)
- GenericImplantTemplateInformationModelMOVE
 - gdcm::UIDs, [1256](#)
- GenericImplantTemplateStorage
 - gdcm::UIDs, [1256](#)
- GEPrivate3DModelStorage
 - gdcm::MediaStorage, [749](#)
- Get
 - gdcm::ByteBuffer, [242](#)
- GetAbbreviation
 - gdcm::GroupDict, [569](#)
- GetAbstractSyntax
 - gdcm::network::PresentationContextRQ, [925](#)
 - gdcm::PresentationContext, [917](#)
- GetAbstractSyntaxUID
 - gdcm::BaseQuery, [204](#)
 - gdcm::FindPatientRootQuery, [553](#)
 - gdcm::FindStudyRootQuery, [557](#)
 - gdcm::ModalityPerformedProcedureStepCreateQuery, [768](#)
 - gdcm::ModalityPerformedProcedureStepSetQuery, [771](#)
 - gdcm::MovePatientRootQuery, [786](#)
 - gdcm::MoveStudyRootQuery, [790](#)
 - gdcm::WLMFindQuery, [1497](#)
- GetAcceptedPresentationContexts
 - gdcm::network::ULConnection, [1313](#)
- GetAcquisitionSize
 - gdcm::SplitMosaicFilter, [1099](#)
- GetAETitle
 - gdcm::ServiceClassUser, [1065](#)
- GetAlgorithmFamily
 - gdcm::Surface, [1150](#)
- GetAlgorithmName
 - gdcm::Surface, [1150](#)
- GetAlgorithmVersion
 - gdcm::Surface, [1150](#)
- GetALGOType
 - gdcm::Segment, [1019](#)
- GetALGOTypeString
 - gdcm::Segment, [1019](#)
- GetAllFilenamesFromPrivateTagToValue
 - gdcm::Scanner2, [1011](#)
 - gdcm::StrictScanner2, [1129](#)
- GetAllFilenamesFromPublicTagToValue
 - gdcm::Scanner2, [1011](#)
 - gdcm::StrictScanner2, [1129](#)
- GetAllFilenamesFromTagToValue
 - gdcm::Scanner, [1001](#)
 - gdcm::StrictScanner, [1119](#)
- GetAllRequiredTags
 - gdcm::QueryBase, [954](#)
- GetAllTags
 - gdcm::QueryBase, [954](#)
- GetAnatomicRegion

- gdcM::Segment, [1019](#)
- GetAnatomicRegionModifiers
 - gdcM::Segment, [1020](#)
- GetAsDataElement
 - gdcM::Attribute< Group, Element, TVR, TVM >, [132](#)
 - gdcM::Attribute< Group, Element, TVR, VM::VM1 >, [142](#)
 - gdcM::Attribute< Group, Element, TVR, VM::VM1_3 >, [149](#)
 - gdcM::Attribute< Group, Element, TVR, VM::VM1_8 >, [155](#)
 - gdcM::Attribute< Group, Element, TVR, VM::VM1_n >, [161](#)
 - gdcM::Attribute< Group, Element, TVR, VM::VM2_2n >, [169](#)
 - gdcM::Attribute< Group, Element, TVR, VM::VM2_n >, [175](#)
 - gdcM::Attribute< Group, Element, TVR, VM::VM3_3n >, [182](#)
 - gdcM::Attribute< Group, Element, TVR, VM::VM3_n >, [188](#)
 - gdcM::Element< TVR, TVM >, [429](#)
 - gdcM::Element< TVR, VM::VM1_2 >, [436](#)
 - gdcM::Element< TVR, VM::VM2_2n >, [441](#)
 - gdcM::Element< TVR, VM::VM3_3n >, [446](#)
 - gdcM::Element< TVR, VM::VM3_4 >, [451](#)
 - gdcM::Element< VR::AS, VM::VM5 >, [455](#)
 - gdcM::Element< VR::OB, VM::VM1 >, [460](#)
 - gdcM::Element< VR::OW, VM::VM1 >, [465](#)
 - gdcM::network::AbstractSyntax, [101](#)
 - gdcM::PrivateTag, [941](#)
- GetAsPoints
 - gdcM::Curve, [337](#)
- GetAsString
 - gdcM::CodeString, [286](#)
- GetAxisOfRotation
 - gdcM::Surface, [1151](#)
- GetBasicApplicationLevelConfidentialityProfileAttributes
 - gdcM::Anonymizer, [111](#)
- GetBitPosition
 - gdcM::Overlay, [841](#)
- GetBitsAllocated
 - gdcM::Overlay, [841](#)
 - gdcM::PixelFormat, [881](#)
- GetBitSample
 - gdcM::LookupTable, [730](#)
- GetBitsStored
 - gdcM::PixelFormat, [881](#)
- GetBlob
 - gdcM::network::PresentationDataValue, [928](#)
- GetBuffer
 - gdcM::Bitmap, [224](#)
 - gdcM::ByteValue, [250](#)
 - gdcM::Parser, [851](#)
 - gdcM::SequenceOfFragments, [1042](#)
- GetBuffer2
 - gdcM::Bitmap, [224](#)
- GetBufferAsRGBA
 - gdcM::LookupTable, [730](#)
- GetBufferLength
 - gdcM::Bitmap, [224](#)
 - gdcM::JPEGLSCodec, [714](#)
 - gdcM::PNMCodec, [910](#)
 - gdcM::RLECodec, [992](#)
- GetBuildVersion
 - gdcM::Version, [1358](#)
- GetByteValue
 - gdcM::CSAElement, [314](#)
 - gdcM::DataElement, [343](#)
- GetCalledAETitle
 - gdcM::network::AAssociateRQPDU, [96](#)
 - gdcM::network::ULConnectionInfo, [1319](#)
 - gdcM::ServiceClassUser, [1065](#)
- GetCalledComputerName
 - gdcM::network::ULConnectionInfo, [1319](#)
- GetCalledIPAddress
 - gdcM::network::ULConnectionInfo, [1319](#)
- GetCalledIPPort
 - gdcM::network::ULConnectionInfo, [1319](#)
- GetCallingAETitle
 - gdcM::network::AAssociateRQPDU, [96](#)
 - gdcM::network::ULConnectionInfo, [1319](#)
- GetCanonMECMR3Tag
 - gdcM::MEC_MR3, [743](#)
- GetCenterOfRotation
 - gdcM::Surface, [1151](#)
- GetCharacterFromCurrentLocale
 - gdcM::QueryFactory, [956](#)
- GetCheckFileMetaInformation
 - gdcM::Writer, [1501](#)
- GetCipherType
 - gdcM::CAPICryptographicMessageSyntax, [259](#)
 - gdcM::CryptographicMessageSyntax, [310](#)
 - gdcM::OpenSSLCryptographicMessageSyntax, [827](#)
 - gdcM::OpenSSL7CryptographicMessageSyntax, [833](#)
- GetCodec
 - gdcM::FileChangeTransferSyntax, [509](#)
- GetColorLevel
 - vtkImageColorViewer, [1453](#)
- GetColorWindow
 - vtkImageColorViewer, [1453](#)
- GetColumns
 - gdcM::Bitmap, [224](#)
 - gdcM::Overlay, [841](#)
- GetCommand
 - gdcM::Subject, [1145](#)
- GetConnectionInfo

- gdcm::network::ULConnection, [1313](#)
- GetConstructorString
 - gdcm::Dicts, [408](#)
- GetContourReferencedFrameOfReferenceClassUID
 - vtkRTStructSetProperties, [1486](#)
- GetContourReferencedFrameOfReferenceInstanceUID
 - vtkRTStructSetProperties, [1486](#)
- GetCryptographicMessageSyntax
 - gdcm::Anonymizer, [111](#)
- GetCSADataInfo
 - gdcm::CSAHeader, [322](#)
- GetCSAEEnd
 - gdcm::CSAHeader, [322](#)
- GetCSAElementByName
 - gdcm::CSAHeader, [322](#)
- GetCSAHeaderDict
 - gdcm::Dicts, [408](#)
- GetCSAHeaderDictEntry
 - gdcm::CSAHeaderDict, [326](#)
- GetCSAImageHeaderInfoTag
 - gdcm::CSAHeader, [322](#)
- GetCSASeriesHeaderInfoTag
 - gdcm::CSAHeader, [323](#)
- GetCTImageSeriesUIDs
 - gdcm::DirectoryHelper, [419](#)
- GetCurrentByteIndex
 - gdcm::Parser, [851](#)
- GetCurrentDateTime
 - gdcm::System, [1179](#)
- GetCurrentModuleFileName
 - gdcm::System, [1179](#)
- GetCurrentProcessFileName
 - gdcm::System, [1179](#)
- GetCurrentResourcesDirectory
 - gdcm::System, [1179](#)
- GetCurve
 - gdcm::Pixmap, [891](#)
- GetCurveDataDescriptor
 - gdcm::Curve, [337](#)
- GetCWD
 - gdcm::System, [1179](#)
- GetData
 - gdcm::DataSetEvent, [357](#)
- GetDataElement
 - gdcm::Bitmap, [224](#)
 - gdcm::DataSet, [363](#), [364](#)
 - gdcm::Item, [674](#)
- GetDataExtraRoot
 - gdcm::Testing, [1206](#)
- GetDataLength
 - gdcm::DataSetEvent, [357](#)
- GetDataRoot
 - gdcm::Testing, [1206](#)
- GetDataSet
 - gdcm::CSAHeader, [323](#)
 - gdcm::DataSetEvent, [373](#)
 - gdcm::File, [499](#)
- GetDataSetPos
 - gdcm::network::ULEvent, [1329](#)
- GetDataSets
 - gdcm::network::ULBasicCallback, [1310](#)
- GetDataSetTransferSyntax
 - gdcm::FileMetaInformation, [525](#)
- GetDataValueRepresentation
 - gdcm::Curve, [337](#)
- GetDebugFlag
 - gdcm::Trace, [1212](#)
- GetDebugStream
 - gdcm::Trace, [1213](#)
- GetDecodeLength
 - gdcm::Base64, [195](#)
- GetDEEnd
 - gdcm::DataSet, [364](#)
- GetDefaultTransferSyntax
 - gdcm::PresentationContextGenerator, [923](#)
- GetDefs
 - gdcm::Global, [565](#)
 - gdcm::TableReader, [1188](#)
- GetDES
 - gdcm::DataSet, [364](#)
- GetDescription
 - gdcm::CSAHeaderDictEntry, [329](#)
 - gdcm::Exception, [486](#)
 - gdcm::ModuleEntry, [779](#)
 - gdcm::Overlay, [841](#)
- GetDescriptiveName
 - vtkGDCMImageReader, [1387](#)
 - vtkGDCMImageReader2, [1401](#)
 - vtkGDCMImageWriter, [1416](#)
- GetDict
 - gdcm::XMLDictReader, [1506](#)
- GetDictEntry
 - gdcm::Dict, [392](#)
 - gdcm::Dicts, [408](#)
 - gdcm::PrivateDict, [936](#)
- GetDictEntryByKeyword
 - gdcm::Dict, [392](#)
- GetDictEntryByName
 - gdcm::Dict, [393](#)
- GetDictName
 - gdcm::DictConverter, [396](#)
- GetDicts
 - gdcm::Global, [565](#), [566](#)
- GetDictVM
 - gdcm::Attribute< Group, Element, TVR, TVM >, [133](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM1 >, [142](#)

- gdcm::Attribute< Group, Element, TVR, VM::VM1_3 >, [149](#)
- gdcm::Attribute< Group, Element, TVR, VM::VM1_8 >, [155](#)
- gdcm::Attribute< Group, Element, TVR, VM::VM1_n >, [161](#)
- gdcm::Attribute< Group, Element, TVR, VM::VM2_2n >, [170](#)
- gdcm::Attribute< Group, Element, TVR, VM::VM2_n >, [175](#)
- gdcm::Attribute< Group, Element, TVR, VM::VM3_3n >, [182](#)
- gdcm::Attribute< Group, Element, TVR, VM::VM3_n >, [188](#)
- GetDictVR
 - gdcm::Attribute< Group, Element, TVR, TVM >, [133](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM1 >, [143](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM1_3 >, [149](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM1_8 >, [155](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM1_n >, [162](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM2_2n >, [170](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM2_n >, [175](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM3_3n >, [182](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM3_n >, [188](#)
- GetDimension
 - gdcm::Bitmap, [225](#)
- GetDimensions
 - gdcm::Bitmap, [225](#)
 - gdcm::Curve, [337](#)
 - gdcm::ImageCodec, [611](#)
- GetDimensionsValue
 - gdcm::ImageHelper, [624](#)
- GetDimensionsValueForResolution
 - gdcm::StreamImageReader, [1105](#)
- GetDirectionCosines
 - gdcm::Image, [583](#)
- GetDirectionCosinesFromDataSet
 - gdcm::ImageHelper, [624](#)
- GetDirectionCosinesTolerance
 - gdcm::IPPSorter, [666](#)
- GetDirectionCosinesValue
 - gdcm::ImageHelper, [625](#)
- GetDirectories
 - gdcm::Directory, [417](#)
- GetElapsedTime
 - gdcm::network::ARTIMTimer, [125](#)
- GetElement
 - gdcm::Tag, [1194](#)
- GetElementTag
 - gdcm::Tag, [1194](#)
- GetEncodeLength
 - gdcm::Base64, [195](#)
- GetErrorCode
 - gdcm::Parser, [851](#)
- GetErrorFlag
 - gdcm::Trace, [1213](#)
- GetErrorStream
 - gdcm::Trace, [1213](#)
- GetErrorString
 - gdcm::Parser, [851](#)
- GetEvent
 - gdcm::network::ULEvent, [1329](#)
- GetEventName
 - gdcm::AnonymizeEvent, [105](#)
 - gdcm::DataEvent, [357](#)
 - gdcm::DataSetEvent, [373](#)
 - gdcm::Event, [483](#)
 - gdcm::FileNameEvent, [536](#)
 - gdcm::ProgressEvent, [946](#)
- GetExtension
 - gdcm::Filename, [531](#)
- GetFactoryInstance
 - gdcm::CryptoFactory, [307](#)
- GetFile
 - gdcm::Anonymizer, [112](#)
 - gdcm::Cleaner, [272](#)
 - gdcm::DICOMDIRGenerator, [389](#)
 - gdcm::FileDecompressLookupTable, [512](#)
 - gdcm::FileDerivation, [515](#), [516](#)
 - gdcm::FileExplicitFilter, [519](#)
 - gdcm::IconImageFilter, [572](#)
 - gdcm::PythonFilter, [952](#)
 - gdcm::Reader, [975](#)
 - gdcm::SplitMosaicFilter, [1099](#)
 - gdcm::StreamImageReader, [1106](#)
 - gdcm::StringFilter, [1140](#)
 - gdcm::Writer, [1501](#)
 - vtkGDCMMedicalImageProperties, [1423](#)
- GetFileExtensions
 - vtkGDCMImageReader, [1387](#)
 - vtkGDCMImageReader2, [1401](#)
 - vtkGDCMImageWriter, [1416](#)
- GetFileMetaInformationVersion
 - gdcm::FileMetaInformation, [526](#)
- GetFileName
 - gdcm::Filename, [531](#)
 - gdcm::FileNameEvent, [536](#)
 - gdcm::Testing, [1206](#)
 - vtkGDCMImageWriter, [1416](#)
 - vtkGDCMThreadedImageReader2, [1445](#)

- GetFilename
 - gdcm::FilenameGenerator, 538
 - gdcm::TableReader, 1188
- GetFilenameFromPrivateTagToValue
 - gdcm::Scanner2, 1011
 - gdcm::StrictScanner2, 1129
- GetFilenameFromPublicTagToValue
 - gdcm::Scanner2, 1011
 - gdcm::StrictScanner2, 1129
- GetFilenameFromTagToValue
 - gdcm::Scanner, 1001
 - gdcm::StrictScanner, 1119
- GetFileNames
 - gdcm::Testing, 1207
- GetFileNames
 - gdcm::Directory, 417
 - gdcm::FilenameGenerator, 539
 - gdcm::Scanner, 1001
 - gdcm::Scanner2, 1011
 - gdcm::Sorter, 1091
 - gdcm::StrictScanner, 1120
 - gdcm::StrictScanner2, 1129
- GetFileNamesFromSeriesUIDs
 - gdcm::DirectoryHelper, 419
- GetFiles
 - gdcm::FileSet, 541
- GetFiniteVolume
 - gdcm::Surface, 1151
- GetFirstSingleSerieUIDFileSet
 - gdcm::SerieHelper, 1058
- GetForcePixelSpacing
 - gdcm::ImageHelper, 625
- GetForceRescaleInterceptSlope
 - gdcm::ImageHelper, 625
- GetFormat
 - gdcm::CSAHeader, 323
- GetFragBuffer
 - gdcm::SequenceOfFragments, 1042
- GetFragment
 - gdcm::SequenceOfFragments, 1042
- GetFragmentSizeMax
 - gdcm::ImageFragmentSplitter, 622
- GetFrameOfReference
 - gdcm::DirectoryHelper, 419
- GetFullLength
 - gdcm::FileMetaInformation, 526
- GetGDCMDataRoot
 - vtkGDCMTesting, 1436
- GetGDCMImplementationClassUID
 - gdcm::FileMetaInformation, 526
- GetGDCMImplementationVersionName
 - gdcm::FileMetaInformation, 526
- GetGDCMSourceApplicationEntityTitle
 - gdcm::FileMetaInformation, 526
- GetGDCMUID
 - gdcm::UIDGenerator, 1229
- GetGroup
 - gdcm::Curve, 337
 - gdcm::Overlay, 841
 - gdcm::Tag, 1195
- GetHasExpired
 - gdcm::network::ARTIMTimer, 125
- GetHeader
 - gdcm::File, 500
- GetHeaderInfo
 - gdcm::ImageCodec, 611
 - gdcm::JPEG12Codec, 681
 - gdcm::JPEG16Codec, 686
 - gdcm::JPEG2000Codec, 692
 - gdcm::JPEG8Codec, 699
 - gdcm::JPEGCodec, 706
 - gdcm::JPEGLSCodec, 715
 - gdcm::PGXCodec, 874
 - gdcm::PNMCodec, 910
 - gdcm::RAWCodec, 971
 - gdcm::RLECodec, 992
- GetHierarchicalSearchTags
 - gdcm::QueryBase, 954
 - gdcm::QueryImage, 958
 - gdcm::QueryPatient, 961
 - gdcm::QuerySeries, 963
 - gdcm::QueryStudy, 966
- GetHighBit
 - gdcm::PixelFormat, 881
- GetHostName
 - gdcm::System, 1179
- GetIconImage
 - gdcm::IconImageFilter, 572
 - gdcm::IconImageGenerator, 575
 - gdcm::Pixmap, 891
 - vtkGDCMImageReader, 1387
 - vtkGDCMImageReader2, 1402
- GetIconImagePort
 - vtkGDCMImageReader2, 1402
- GetIE
 - gdcm::IODEntry, 659
- GetImage
 - gdcm::ImageReader, 632
 - gdcm::ImageWriter, 645, 646
 - gdcm::PixmapWriter, 904
 - gdcm::SplitMosaicFilter, 1099
- GetImplementationClassUID
 - gdcm::FileMetaInformation, 526
- GetImplementationVersionName
 - gdcm::FileMetaInformation, 526
- GetIndex
 - gdcm::SwapCode, 1173
 - gdcm::VM, 1367

- GetInitialized
 - gdcm::CAPICryptographicMessageSyntax, [259](#)
- GetInput
 - gdcm::ImageToImageFilter, [641](#)
 - gdcm::PixmapToPixmapFilter, [900](#)
 - vtkImageColorViewer, [1453](#)
- GetInputFilename
 - gdcm::DictConverter, [397](#)
- GetInstance
 - gdcm::Global, [566](#)
- GetIntercept
 - gdcm::Image, [583](#)
 - gdcm::Rescaler, [985](#)
- GetInterfile
 - gdcm::CSAHeader, [323](#)
- GetInternal
 - gdcm::Preamble, [913](#)
- GetIOD
 - gdcm::IODs, [663](#)
 - gdcm::SOPClassUIDToIOD, [1088](#)
- GetIODEntry
 - gdcm::IOD, [657](#)
- GetIODFromFile
 - gdcm::Defs, [379](#)
- GetIODFromSOPClassUID
 - gdcm::SOPClassUIDToIOD, [1088](#)
- GetIODNameFromMediaStorage
 - gdcm::Defs, [379](#)
- GetIODs
 - gdcm::Defs, [379](#)
- GetIsCommand
 - gdcm::network::PresentationDataValue, [928](#)
- GetIsLastFragment
 - gdcm::network::PresentationDataValue, [928](#)
- GetStream
 - gdcm::network::ULEvent, [1329](#)
- GetItem
 - gdcm::SequenceOfItems, [1050](#), [1051](#)
- GetKey
 - gdcm::CSAElement, [314](#)
- GetKeys
 - gdcm::Scanner, [1002](#)
 - gdcm::Scanner2, [1012](#)
 - gdcm::StrictScanner, [1120](#)
 - gdcm::StrictScanner2, [1130](#)
- GetKeyword
 - gdcm::DictEntry, [400](#)
- GetKeywordFromTag
 - gdcm::Dict, [393](#)
- GetLabel
 - gdcm::Orientation, [836](#)
- GetLastElement
 - gdcm::ParseException, [848](#)
- GetLastSystemError
 - gdcm::System, [1180](#)
- GetLength
 - gdcm::ByteValue, [250](#)
 - gdcm::CP246ExplicitDataElement, [304](#)
 - gdcm::DataElement, [344](#)
 - gdcm::DataSet, [365](#)
 - gdcm::Element< TVR, TVM >, [429](#)
 - gdcm::Element< TVR, VM::VM1_2 >, [436](#)
 - gdcm::Element< TVR, VM::VM2_2n >, [441](#)
 - gdcm::Element< TVR, VM::VM3_3n >, [446](#)
 - gdcm::Element< TVR, VM::VM3_4 >, [451](#)
 - gdcm::Element< VR::AS, VM::VM5 >, [455](#)
 - gdcm::Element< VR::OB, VM::VM1 >, [460](#)
 - gdcm::Element< VR::OW, VM::VM1 >, [465](#)
 - gdcm::ExplicitDataElement, [491](#)
 - gdcm::ExplicitImplicitDataElement, [495](#)
 - gdcm::Fragment, [562](#)
 - gdcm::ImplicitDataElement, [653](#)
 - gdcm::Item, [674](#)
 - gdcm::Preamble, [913](#)
 - gdcm::SequenceOfFragments, [1042](#)
 - gdcm::SequenceOfItems, [1051](#)
 - gdcm::Tag, [1195](#)
 - gdcm::UNExplicitDataElement, [1336](#)
 - gdcm::UNExplicitImplicitDataElement, [1340](#)
 - gdcm::Value, [1354](#)
 - gdcm::VL, [1360](#)
 - gdcm::VM, [1367](#)
 - gdcm::VR, [1372](#)
 - gdcm::VR16ExplicitDataElement, [1378](#)
- GetLocaleCharSet
 - gdcm::System, [1180](#)
- GetLossless
 - gdcm::JPEGCodec, [706](#)
 - gdcm::JPEGLSCCodec, [715](#)
- GetLossyFlag
 - gdcm::ImageCodec, [611](#)
- GetLossyFlagFromFile
 - gdcm::Testing, [1207](#)
- GetLUT
 - gdcm::Bitmap, [225](#)
 - gdcm::ImageCodec, [611](#)
 - gdcm::ImageHelper, [625](#)
 - gdcm::LookupTable, [730](#)
- GetLUTDescriptor
 - gdcm::LookupTable, [730](#)
- GetLUTLength
 - gdcm::LookupTable, [730](#)
- GetMacro
 - gdcm::Macros, [740](#)
- GetMacroEntry
 - gdcm::Macro, [737](#)
- GetMacros
 - gdcm::Defs, [380](#)

- GetMajorAxisFromPatientRelativeDirectionCosine
 - gdcm::Orientation, [836](#)
- GetMajorVersion
 - gdcm::Version, [1358](#)
- GetManifold
 - gdcm::Surface, [1151](#)
- GetMapping
 - gdcm::Scanner, [1002](#)
 - gdcm::StrictScanner, [1120](#)
- GetMappingFromPrivateTagToValue
 - gdcm::Scanner2, [1012](#)
 - gdcm::StrictScanner2, [1130](#)
- GetMappingFromPublicTagToValue
 - gdcm::Scanner2, [1012](#)
 - gdcm::StrictScanner2, [1130](#)
- GetMappingFromTagToValue
 - gdcm::Scanner, [1002](#)
 - gdcm::StrictScanner, [1120](#)
- GetMappings
 - gdcm::Scanner, [1002](#)
 - gdcm::StrictScanner, [1120](#)
- GetMax
 - gdcm::PixelFormat, [882](#)
- GetMaximumLength
 - gdcm::network::MaximumLengthSub, [741](#)
- GetMaximumLengthSub
 - gdcm::network::UserInformation, [1347](#)
- GetMaximumPointDistance
 - gdcm::Surface, [1151](#)
- GetMaxLength
 - gdcm::PersonName, [868](#)
- GetMaxPDULength
 - gdcm::network::ULConnectionInfo, [1319](#)
- GetMaxPDUSize
 - gdcm::network::ULConnection, [1313](#)
- GetMD5DataImage
 - gdcm::Testing, [1207](#)
- GetMD5DataImages
 - gdcm::Testing, [1207](#)
- GetMD5FromBrokenFile
 - gdcm::Testing, [1207](#)
- GetMD5FromFile
 - gdcm::Testing, [1207](#)
- GetMD5MetaImage
 - vtkGDCMTesting, [1436](#)
- GetMeanPointDistance
 - gdcm::Surface, [1151](#)
- GetMediaStorage
 - gdcm::DataSet, [365](#)
 - gdcm::FileMetaInformation, [526](#)
- GetMediaStorageAsString
 - gdcm::FileMetaInformation, [527](#)
- GetMediaStorageDataFile
 - gdcm::Testing, [1208](#)
- GetMediaStorageDataFiles
 - gdcm::Testing, [1208](#)
- GetMediaStorageFromFile
 - gdcm::Testing, [1208](#)
- GetMeshPrimitive
 - gdcm::Surface, [1151](#)
- GetMessageHeader
 - gdcm::network::PresentationDataValue, [929](#)
- GetMetaInformationTS
 - gdcm::FileMetaInformation, [527](#)
- GetMHDMD5FromFile
 - vtkGDCMTesting, [1436](#)
- GetMin
 - gdcm::PixelFormat, [882](#)
- GetMinorVersion
 - gdcm::Version, [1358](#)
- GetModality
 - gdcm::MediaStorage, [751](#)
- GetModalityDimension
 - gdcm::MediaStorage, [751](#)
- GetModule
 - gdcm::Modules, [783](#)
- GetModuleEntry
 - gdcm::NestedModuleEntries, [805](#)
- GetModuleEntryInMacros
 - gdcm::Module, [775](#)
- GetModules
 - gdcm::Defs, [380](#)
- GetMPTType
 - gdcm::MeshPrimitive, [763](#)
- GetMPTTypeString
 - gdcm::MeshPrimitive, [763](#)
- GetMRImageSeriesUIDs
 - gdcm::DirectoryHelper, [420](#)
- GetMrProtocol
 - gdcm::CSAHeader, [323](#)
- GetMrProtocolByName
 - gdcm::MrProtocol, [793](#)
- GetMSString
 - gdcm::MediaStorage, [751](#)
- GetMSType
 - gdcm::MediaStorage, [751](#)
- GetMTime
 - vtkImageMapToColors16, [1464](#)
- GetName
 - gdcm::CSAElement, [314](#)
 - gdcm::CSAHeaderDictEntry, [329](#)
 - gdcm::DictEntry, [400](#)
 - gdcm::Filename, [531](#)
 - gdcm::GroupDict, [569](#)
 - gdcm::IODEntry, [659](#)
 - gdcm::Macro, [737](#)
 - gdcm::Module, [776](#)
 - gdcm::ModuleEntry, [779](#)

- gdcm::network::AbstractSyntax, [101](#)
- gdcm::network::ApplicationContext, [117](#)
- gdcm::network::TransferSyntaxSub, [1222](#)
- gdcm::PDBelement, [857](#)
- gdcm::QueryBase, [955](#)
- gdcm::QueryImage, [958](#)
- gdcm::QueryPatient, [961](#)
- gdcm::QuerySeries, [963](#)
- gdcm::QueryStudy, [966](#)
- gdcm::UIDs, [1266](#)
- GetNeedByteSwap
 - gdcm::Bitmap, [225](#)
 - gdcm::ImageCodec, [612](#)
- GetNegotiatedType
 - gdcm::TransferSyntax, [1219](#)
- GetNestedDataSet
 - gdcm::Item, [674](#)
- GetNextSingleSerieUIDFileSet
 - gdcm::SerieHelper, [1058](#)
- GetNoOfItems
 - gdcm::CSAElement, [314](#)
- GetNumberOfComponents
 - gdcm::PersonName, [868](#)
- GetNumberOfContourReferencedFrameOfReferences
 - vtkRTStructSetProperties, [1486](#)
- GetNumberOfCurves
 - gdcm::Curve, [337](#)
 - gdcm::Pixmap, [892](#)
- GetNumberOfDimensions
 - gdcm::Bitmap, [226](#)
 - gdcm::ImageCodec, [612](#)
- GetNumberOfElementsFromArray
 - gdcm::VM, [1367](#)
- GetNumberOfFileNames
 - gdcm::Testing, [1208](#)
- GetNumberOfFilenames
 - gdcm::FilenameGenerator, [539](#)
- GetNumberOfFragments
 - gdcm::SequenceOfFragments, [1043](#)
- GetNumberOfIconImages
 - gdcm::IconImageFilter, [572](#)
- GetNumberOfImagesInMosaic
 - gdcm::SplitMosaicFilter, [1099](#)
- GetNumberOfIODs
 - gdcm::IOD, [657](#)
- GetNumberOfItems
 - gdcm::SequenceOfItems, [1051](#)
- GetNumberOfMD5DataImages
 - gdcm::Testing, [1208](#)
- GetNumberOfMD5MetaImages
 - vtkGDCMTesting, [1436](#)
- GetNumberOfMediaStorageDataFiles
 - gdcm::Testing, [1208](#)
- GetNumberOfModality
 - gdcm::MediaStorage, [751](#)
- GetNumberOfModuleEntries
 - gdcm::NestedModuleEntries, [806](#)
- GetNumberOfMSString
 - gdcm::MediaStorage, [751](#)
- GetNumberOfMSType
 - gdcm::MediaStorage, [751](#)
- GetNumberOfOverlays
 - gdcm::Pixmap, [892](#)
- GetNumberOfPoints
 - gdcm::Curve, [337](#)
- GetNumberOfPresentationContext
 - gdcm::network::AAssociateRQPDU, [97](#)
- GetNumberOfPresentationContextAC
 - gdcm::network::AAssociateACPDU, [90](#)
- GetNumberOfPresentationDataValues
 - gdcm::network::PDataTFPDU, [855](#)
- GetNumberOfPrimitivesData
 - gdcm::MeshPrimitive, [763](#)
- GetNumberOfReferencedFrameOfReferences
 - vtkRTStructSetProperties, [1487](#)
- GetNumberOfSegments
 - gdcm::SegmentWriter, [1036](#)
- GetNumberOfSOPClassToIOD
 - gdcm::SOPClassUIDToIOD, [1088](#)
- GetNumberOfStructureSetROIs
 - vtkRTStructSetProperties, [1487](#)
- GetNumberOfSurfacePoints
 - gdcm::Surface, [1152](#)
- GetNumberOfSurfaces
 - gdcm::SurfaceReader, [1165](#)
 - gdcm::SurfaceWriter, [1170](#)
- GetNumberOfTransferSyntaxes
 - gdcm::network::PresentationContextRQ, [925](#)
 - gdcm::PresentationContext, [917](#)
- GetNumberOfTransferSyntaxStrings
 - gdcm::UIDs, [1266](#)
- GetNumberOfValues
 - gdcm::Attribute< Group, Element, TVR, TVM >, [133](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM1 >, [143](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM1_3 >, [150](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM1_8 >, [155](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM1_n >, [162](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM2_2n >, [170](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM2_n >, [176](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM3_3n >, [182](#)

- gdcmm::Attribute< Group, Element, TVR, VM::VM3_n
>, 188
- GetNumberOfVectors
 - gdcmm::Surface, 1152
- GetObliquityThresholdCosineValue
 - gdcmm::Orientation, 836
- GetOffScreenRendering
 - vtkImageColorViewer, 1453
- GetOptionalTags
 - gdcmm::QueryBase, 955
 - gdcmm::QueryImage, 959
 - gdcmm::QueryPatient, 961
 - gdcmm::QuerySeries, 964
 - gdcmm::QueryStudy, 966
- GetOrderedValues
 - gdcmm::Scanner, 1002
 - gdcmm::StrictScanner, 1120
- GetOrigin
 - gdcmm::Image, 583
 - gdcmm::Overlay, 842
- GetOriginValue
 - gdcmm::ImageHelper, 625
- GetOutput
 - gdcmm::ImageConverter, 618
- GetOutput
 - gdcmm::BitmapToBitmapFilter, 236
 - gdcmm::ImageToImageFilter, 641
 - gdcmm::PixmapToPixmapFilter, 900
- GetOutputAsBitmap
 - gdcmm::BitmapToBitmapFilter, 236
- GetOutputAsPixmap
 - gdcmm::PixmapToPixmapFilter, 900
- GetOutputFilename
 - gdcmm::DictConverter, 397
- GetOutputType
 - gdcmm::DictConverter, 397
- GetOverlay
 - gdcmm::Pixmap, 892
 - vtkGDCMImageReader, 1387
 - vtkGDCMImageReader2, 1402
- GetOverlayData
 - gdcmm::Overlay, 842
- GetOverlayPort
 - vtkGDCMImageReader2, 1402
- GetOverlayTypeAsString
 - gdcmm::Overlay, 842
- GetOverlayTypeFromString
 - gdcmm::Overlay, 842
- GetOverlayVisibility
 - vtkImageColorViewer, 1453
- GetOwner
 - gdcmm::PrivateTag, 941
- GetPath
 - gdcmm::Filename, 532
- GetPattern
 - gdcmm::FilenameGenerator, 539
- GetPDBEEnd
 - gdcmm::PDBHeader, 860
- GetPDBElementByName
 - gdcmm::PDBHeader, 861
- GetPDBInfoTag
 - gdcmm::PDBHeader, 861
- GetPDUs
 - gdcmm::network::ULEvent, 1329
- GetPDVs
 - gdcmm::network::PDUFactory, 867
- GetPermissions
 - gdcmm::System, 1180
- GetPhotometricInterpretation
 - gdcmm::Bitmap, 226
 - gdcmm::ImageChangePhotometricInterpretation, 592
 - gdcmm::ImageCodec, 612
- GetPhotometricInterpretationValue
 - gdcmm::ImageHelper, 625
- GetPIString
 - gdcmm::PhotometricInterpretation, 876
- GetPIType
 - gdcmm::PhotometricInterpretation, 876
- GetPixelFormat
 - gdcmm::Bitmap, 226
 - gdcmm::ImageCodec, 612
- GetPixelFormatValue
 - gdcmm::ImageHelper, 625
- GetPixelRepresentation
 - gdcmm::PixelFormat, 882
- GetPixelSize
 - gdcmm::PixelFormat, 882
- GetPixelSpacingDataRoot
 - gdcmm::Testing, 1208
- GetPixmap
 - gdcmm::FileDecompressLookupTable, 513
 - gdcmm::IconImageGenerator, 575
 - gdcmm::PixmapReader, 897
 - gdcmm::PixmapWriter, 904
- GetPlanarConfiguration
 - gdcmm::Bitmap, 226
 - gdcmm::ImageChangePlanarConfiguration, 597
 - gdcmm::ImageCodec, 612
- GetPlanarConfigurationValue
 - gdcmm::ImageHelper, 626
- GetPMSRescaleInterceptSlope
 - gdcmm::ImageHelper, 626
- GetPMTFInformationDataTag
 - gdcmm::MEC_MR3, 743
- GetPointCoordinatesData
 - gdcmm::Surface, 1152
- GetPointer
 - gdcmm::ByteValue, 251

- gdcm::LookupTable, 730
- gdcm::SmartPointer< ObjectType >, 1084
- vtkLookupTable16, 1481
- GetPointerFromElement
 - gdcm::ImageHelper, 626
- GetPointPositionAccuracy
 - gdcm::Surface, 1152
- GetPointsBoundingBoxCoordinates
 - gdcm::Surface, 1152
- GetPosition
 - vtkImageColorViewer, 1454
- GetPreamble
 - gdcm::FileMetaInformation, 527
- GetPrefix
 - gdcm::FilenameGenerator, 539
- GetPresentationContext
 - gdcm::network::AAssociateRQPDU, 97
- GetPresentationContextAC
 - gdcm::network::AAssociateACPDU, 90
- GetPresentationContextACByID
 - gdcm::network::ULConnection, 1313
- GetPresentationContextByAbstractSyntax
 - gdcm::network::AAssociateRQPDU, 97
- GetPresentationContextByID
 - gdcm::network::AAssociateRQPDU, 97
- GetPresentationContextID
 - gdcm::network::PresentationContextAC, 919
 - gdcm::network::PresentationContextRQ, 925
 - gdcm::network::PresentationDataValue, 929
 - gdcm::PresentationContext, 917
- GetPresentationContextIDFromPresentationContext
 - gdcm::network::ULConnection, 1313
- GetPresentationContextRQByID
 - gdcm::network::ULConnection, 1313
- GetPresentationContexts
 - gdcm::network::AAssociateRQPDU, 97
 - gdcm::network::ULConnection, 1313
 - gdcm::PresentationContextGenerator, 923
- GetPresentationDataValue
 - gdcm::network::PDataTFPDU, 855
- GetPrettyPrint
 - gdcm::JSON, 717
- GetPrimitiveData
 - gdcm::MeshPrimitive, 763, 764
- GetPrimitivesData
 - gdcm::MeshPrimitive, 764
- GetPrimitiveType
 - gdcm::MeshPrimitive, 764
- GetPrintStyle
 - gdcm::Printer, 933
 - gdcm::XMLPrinter, 1508
- GetPrivateCreator
 - gdcm::DataSet, 365
 - gdcm::Tag, 1195
- GetPrivateDict
 - gdcm::Dicts, 408
 - gdcm::XMLPrivateDictReader, 1512
- GetPrivateMapping
 - gdcm::Scanner2, 1012
 - gdcm::StrictScanner2, 1130
- GetPrivateMappings
 - gdcm::Scanner2, 1012
 - gdcm::StrictScanner2, 1130
- GetPrivateOrderedValues
 - gdcm::Scanner2, 1012
 - gdcm::StrictScanner2, 1130
- GetPrivateTag
 - gdcm::DataSet, 365
- GetPrivateValue
 - gdcm::Scanner2, 1012
 - gdcm::StrictScanner2, 1130
- GetPrivateValues
 - gdcm::Scanner2, 1013
 - gdcm::StrictScanner2, 1131
- GetProcessingAlgorithm
 - gdcm::Surface, 1152
- GetProgress
 - gdcm::ProgressEvent, 946
- GetPropertyCategory
 - gdcm::Segment, 1020
- GetPropertyType
 - gdcm::Segment, 1020
- GetPropertyTypeModifiers
 - gdcm::Segment, 1020
- GetProtocol
 - gdcm::network::ULConnection, 1314
- GetPublicDict
 - gdcm::Dicts, 409
- GetPublicMapping
 - gdcm::Scanner2, 1013
 - gdcm::StrictScanner2, 1131
- GetPublicMappings
 - gdcm::Scanner2, 1013
 - gdcm::StrictScanner2, 1131
- GetPublicOrderedValues
 - gdcm::Scanner2, 1013
 - gdcm::StrictScanner2, 1131
- GetPublicValue
 - gdcm::Scanner2, 1013
 - gdcm::StrictScanner2, 1131
- GetPublicValues
 - gdcm::Scanner2, 1013
 - gdcm::StrictScanner2, 1131
- GetQuality
 - gdcm::JPEG2000Codec, 692
 - gdcm::JPEGCodec, 706
- GetQueryDataSet
 - gdcm::BaseQuery, 205

- GetQueryLevel
 - gdcm::QueryBase, [955](#)
 - gdcm::QueryImage, [959](#)
 - gdcm::QueryPatient, [961](#)
 - gdcm::QuerySeries, [964](#)
 - gdcm::QueryStudy, [966](#)
- GetQueryLevelFromQueryRoot
 - gdcm::BaseRootQuery, [210](#)
- GetQueryLevelFromString
 - gdcm::BaseRootQuery, [210](#)
- GetQueryLevelString
 - gdcm::BaseRootQuery, [210](#)
- GetRate
 - gdcm::JPEG2000Codec, [692](#)
- GetRAWMD5FromFile
 - vtkGDCMTesting, [1436](#)
- GetRealWorldValueMappingContent
 - gdcm::ImageHelper, [626](#)
- GetReason
 - gdcm::network::PresentationContextAC, [919](#)
- GetRecommendedDisplayCIELabValue
 - gdcm::Surface, [1153](#)
- GetRecommendedDisplayGrayscaleValue
 - gdcm::Surface, [1153](#)
- GetRecommendedPresentationOpacity
 - gdcm::Surface, [1153](#)
- GetRecommendedPresentationType
 - gdcm::Surface, [1153](#)
- GetRef
 - gdcm::IODEntry, [660](#)
- GetReferencedFrameOfReferenceClassUID
 - vtkRTStructSetProperties, [1487](#)
- GetReferencedFrameOfReferenceInstanceUID
 - vtkRTStructSetProperties, [1487](#)
- GetRegion
 - gdcm::ImageRegionReader, [638](#)
- GetRequiredDataSet
 - gdcm::ModalityPerformedProcedureStepCreateQuery, [768](#)
 - gdcm::ModalityPerformedProcedureStepSetQuery, [771](#)
- GetRequiredTags
 - gdcm::QueryBase, [955](#)
 - gdcm::QueryImage, [959](#)
 - gdcm::QueryPatient, [961](#)
 - gdcm::QuerySeries, [964](#)
 - gdcm::QueryStudy, [966](#)
- GetRescaleInterceptSlopeValue
 - gdcm::ImageHelper, [626](#)
- GetReserved43_74
 - gdcm::network::AAssociateRQPDU, [97](#)
- GetResponses
 - gdcm::network::ULBasicCallback, [1310](#)
- GetRetired
 - gdcm::DictEntry, [400](#)
- GetRoot
 - gdcm::UIDGenerator, [1230](#)
- GetRows
 - gdcm::Bitmap, [227](#)
 - gdcm::Overlay, [842](#)
- GetRTStructSeriesUIDs
 - gdcm::DirectoryHelper, [420](#)
- GetSamplesPerPixel
 - gdcm::PhotometricInterpretation, [877](#)
 - gdcm::PixelFormat, [882](#)
- GetScalarType
 - gdcm::PixelFormat, [883](#)
- GetScalarTypeAsString
 - gdcm::PixelFormat, [883](#)
- GetScanner
 - gdcm::DICOMDIRGenerator, [389](#)
- GetSecondaryCaptureImagePlaneModule
 - gdcm::ImageHelper, [626](#)
- GetSegment
 - gdcm::SegmentWriter, [1036](#)
- GetSegmentAlgorithmName
 - gdcm::Segment, [1020](#)
- GetSegmentAlgorithmType
 - gdcm::Segment, [1020](#)
- GetSegmentDescription
 - gdcm::Segment, [1021](#)
- GetSegmentLabel
 - gdcm::Segment, [1021](#)
- GetSegmentNumber
 - gdcm::Segment, [1021](#)
- GetSegments
 - gdcm::SegmentReader, [1031](#)
 - gdcm::SegmentWriter, [1036](#)
- GetSelectedPrivateGroupOffsetFromFile
 - gdcm::Testing, [1209](#)
- GetSelectedTagsOffsetFromFile
 - gdcm::Testing, [1209](#)
- GetSequenceOfFragments
 - gdcm::DataElement, [344](#)
- GetSeriesUIDsBySOPClassUID
 - gdcm::DirectoryHelper, [420](#)
- GetSize
 - gdcm::VR, [1373](#)
 - vtkImageColorViewer, [1454](#)
- GetSizeof
 - gdcm::VR, [1373](#)
- GetSliceArray
 - gdcm::MrProtocol, [793](#)
- GetSliceMax
 - vtkImageColorViewer, [1454](#)
- GetSliceMin
 - vtkImageColorViewer, [1454](#)
- GetSliceRange

- vtkImageColorViewer, [1454](#)
- GetSlope
 - gdcm::Image, [583](#)
 - gdcm::Rescaler, [985](#)
- GetSOPClassUID
 - gdcm::DirectoryHelper, [420](#)
- GetSOPClassUIDFromIOD
 - gdcm::SOPClassUIDToIOD, [1088](#)
- GetSOPClassUIDToIOD
 - gdcm::SOPClassUIDToIOD, [1088](#)
- GetSOPClassUIDToIODs
 - gdcm::SOPClassUIDToIOD, [1089](#)
- GetSOPInstanceUID
 - gdcm::BaseQuery, [205](#)
- GetSourceApplicationEntityTitle
 - gdcm::FileMetaInformation, [527](#)
- GetSourceDirectory
 - gdcm::Testing, [1209](#)
- GetSpacing
 - gdcm::Image, [583](#)
- GetSpacingTagFromMediaStorage
 - gdcm::ImageHelper, [627](#)
- GetSpacingValue
 - gdcm::ImageHelper, [627](#)
- GetStart
 - gdcm::ByteBuffer, [242](#)
- GetState
 - gdcm::network::ULConnection, [1314](#)
- GetStateIndex
 - gdcm::network, [79](#)
- GetSTATES
 - gdcm::Surface, [1153](#)
- GetSTATESString
 - gdcm::Surface, [1153](#)
- GetStream
 - gdcm::Trace, [1213](#)
- GetStreamCurrentPosition
 - gdcm::Reader, [975](#)
- GetStreamOffsetFromFile
 - gdcm::Testing, [1209](#)
- GetStreamPtr
 - gdcm::Reader, [976](#)
 - gdcm::Writer, [1501](#)
- GetString
 - gdcm::MediaStorage, [752](#)
 - gdcm::PhotometricInterpretation, [877](#)
 - gdcm::TransferSyntax, [1219](#)
 - gdcm::UIDs, [1266](#)
- GetStringValueFromTag
 - gdcm::DirectoryHelper, [420](#)
- GetStructureSetObservationNumber
 - vtkRTStructSetProperties, [1487](#)
- GetStructureSetROIDescription
 - vtkRTStructSetProperties, [1487](#)
- GetStructureSetROIGenerationAlgorithm
 - vtkRTStructSetProperties, [1487](#)
- GetStructureSetROIName
 - vtkRTStructSetProperties, [1487](#)
- GetStructureSetROINumber
 - vtkRTStructSetProperties, [1488](#)
- GetStructureSetROIObservationLabel
 - vtkRTStructSetProperties, [1488](#)
- GetStructureSetROIRefFrameRefUID
 - vtkRTStructSetProperties, [1488](#)
- GetStructureSetRTROIInterpretedType
 - vtkRTStructSetProperties, [1488](#)
- GetSurface
 - gdcm::Segment, [1021](#)
- GetSurfaceComments
 - gdcm::Surface, [1153](#)
- GetSurfaceCount
 - gdcm::Segment, [1021](#)
- GetSurfaceNumber
 - gdcm::Surface, [1153](#)
- GetSurfaceProcessing
 - gdcm::Surface, [1154](#)
- GetSurfaceProcessingDescription
 - gdcm::Surface, [1154](#)
- GetSurfaceProcessingRatio
 - gdcm::Surface, [1154](#)
- GetSurfaces
 - gdcm::Segment, [1021](#)
- GetSwapCode
 - gdcm::TransferSyntax, [1219](#)
- GetSwapCodeString
 - gdcm::SwapCode, [1173](#)
- GetSyngoDT
 - gdcm::CSAElement, [314](#)
- GetTable
 - gdcm::SequenceOfFragments, [1043](#)
- GetTableEntry
 - gdcm::Table, [1184](#)
- GetTag
 - gdcm::AnonymizeEvent, [105](#)
 - gdcm::Attribute< Group, Element, TVR, TVM >, [133](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM1 >, [143](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM1_3 >, [150](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM1_8 >, [155](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM1_n >, [162](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM2_2n >, [170](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM2_n >, [176](#)

- gdcmm::Attribute< Group, Element, TVR, VM::VM3_3n >, 182
- gdcmm::Attribute< Group, Element, TVR, VM::VM3_n >, 188
- gdcmm::DataElement, 344, 345
- GetTagListByLevel
 - gdcmm::BaseRootQuery, 210
 - gdcmm::FindPatientRootQuery, 553
 - gdcmm::FindStudyRootQuery, 557
 - gdcmm::MovePatientRootQuery, 786
 - gdcmm::MoveStudyRootQuery, 790
 - gdcmm::WLMFindQuery, 1497
- GetTempDirectory
 - gdcmm::Testing, 1209
- GetTempDirectoryW
 - gdcmm::Testing, 1209
- GetTempFilename
 - gdcmm::Testing, 1210
- GetTempFilenameW
 - gdcmm::Testing, 1210
- GetTimeout
 - gdcmm::network::ARTIMTimer, 126
 - gdcmm::ServiceClassUser, 1065
- GetTimer
 - gdcmm::network::ULConnection, 1314
- GetTimezoneOffsetFromUTC
 - gdcmm::System, 1180
- GetToplevel
 - gdcmm::Directory, 417
- GetToshibaMECMR3Tag
 - gdcmm::MEC_MR3, 743
- GetTransferSyntax
 - gdcmm::Bitmap, 227
 - gdcmm::ImageChangeTransferSyntax, 602
 - gdcmm::network::PresentationContextAC, 919
 - gdcmm::network::PresentationContextRQ, 926
 - gdcmm::PresentationContext, 917
- GetTransferSyntaxes
 - gdcmm::network::PresentationContextRQ, 926
- GetTransferSyntaxString
 - gdcmm::UIDs, 1266
- GetTransferSyntaxStrings
 - gdcmm::UIDs, 1266
- GetTSString
 - gdcmm::TransferSyntax, 1219
- GetTSType
 - gdcmm::TransferSyntax, 1219
- GetType
 - gdcmm::ModuleEntry, 779
 - gdcmm::Orientation, 836
 - gdcmm::Overlay, 842
 - gdcmm::PhotometricInterpretation, 877
- GetTypeAsEnum
 - gdcmm::Overlay, 842
- GetTypeFromTag
 - gdcmm::Defs, 380
 - gdcmm::IOD, 657
- GetTypeOfData
 - gdcmm::Curve, 337
- GetTypeOfDataDescription
 - gdcmm::Curve, 338
- GetTypeString
 - gdcmm::Type, 1227
- GetTypeType
 - gdcmm::Type, 1227
- GetUIDName
 - gdcmm::UIDs, 1267
- GetUIDString
 - gdcmm::UIDs, 1267
- GetUniqueTags
 - gdcmm::QueryBase, 955
 - gdcmm::QueryImage, 959
 - gdcmm::QueryPatient, 962
 - gdcmm::QuerySeries, 964
 - gdcmm::QueryStudy, 967
- GetUnpackBuffer
 - gdcmm::Overlay, 843
- GetUnpackBufferLength
 - gdcmm::Overlay, 843
- GetUsage
 - gdcmm::IODEntry, 660
- GetUsageString
 - gdcmm::Usage, 1344
- GetUsageType
 - gdcmm::IODEntry, 660
 - gdcmm::Usage, 1344
- GetUserData
 - gdcmm::Parser, 851
- GetUserInfo
 - gdcmm::network::AAAssociateACPDU, 90
 - gdcmm::network::AAAssociateRQPDU, 97
- GetValidatedFile
 - gdcmm::Validate, 1351
- GetValidDataSet
 - gdcmm::WLMFindQuery, 1497
- GetValue
 - gdcmm::Attribute< Group, Element, TVR, TVM >, 134
 - gdcmm::Attribute< Group, Element, TVR, VM::VM1_ >, 143
 - gdcmm::Attribute< Group, Element, TVR, VM::VM1_3 >, 150
 - gdcmm::Attribute< Group, Element, TVR, VM::VM1_8 >, 155
 - gdcmm::Attribute< Group, Element, TVR, VM::VM1_n >, 162
 - gdcmm::Attribute< Group, Element, TVR, VM::VM2_2n >, 170

- gdcmm::Attribute< Group, Element, TVR, VM::VM2_n >, 176
- gdcmm::Attribute< Group, Element, TVR, VM::VM3_3n >, 182
- gdcmm::Attribute< Group, Element, TVR, VM::VM3_n >, 188
- gdcmm::CSAElement, 315
- gdcmm::DataElement, 345
- gdcmm::Element< TVR, TVM >, 430
- gdcmm::Element< TVR, VM::VM1_2 >, 436
- gdcmm::Element< TVR, VM::VM2_2n >, 441
- gdcmm::Element< TVR, VM::VM3_3n >, 446
- gdcmm::Element< TVR, VM::VM3_4 >, 451
- gdcmm::Element< VR::AS, VM::VM5 >, 455
- gdcmm::Element< VR::OB, VM::VM1 >, 460
- gdcmm::Element< VR::OW, VM::VM1 >, 465
- gdcmm::PDBelement, 857
- gdcmm::Scanner, 1002
- gdcmm::StrictScanner, 1121
- GetValueAsSQ
 - gdcmm::DataElement, 345
- GetValues
 - gdcmm::Attribute< Group, Element, TVR, TVM >, 134
 - gdcmm::Attribute< Group, Element, TVR, VM::VM1 >, 143
 - gdcmm::Attribute< Group, Element, TVR, VM::VM1_3 >, 150
 - gdcmm::Attribute< Group, Element, TVR, VM::VM1_8 >, 155
 - gdcmm::Attribute< Group, Element, TVR, VM::VM1_n >, 162
 - gdcmm::Attribute< Group, Element, TVR, VM::VM2_2n >, 170
 - gdcmm::Attribute< Group, Element, TVR, VM::VM2_n >, 176
 - gdcmm::Attribute< Group, Element, TVR, VM::VM3_3n >, 182
 - gdcmm::Attribute< Group, Element, TVR, VM::VM3_n >, 188
 - gdcmm::Element< TVR, TVM >, 430
 - gdcmm::Element< TVR, VM::VM1_2 >, 436
 - gdcmm::Element< TVR, VM::VM2_2n >, 441
 - gdcmm::Element< TVR, VM::VM3_3n >, 446
 - gdcmm::Element< TVR, VM::VM3_4 >, 451
 - gdcmm::Element< VR::AS, VM::VM5 >, 455
 - gdcmm::Element< VR::OB, VM::VM1 >, 460
 - gdcmm::Element< VR::OW, VM::VM1 >, 465
 - gdcmm::Scanner, 1003
 - gdcmm::Scanner2, 1014
 - gdcmm::StrictScanner, 1121
 - gdcmm::StrictScanner2, 1132
- GetVectorAccuracy
 - gdcmm::Surface, 1154
- GetVectorCoordinateData
 - gdcmm::Surface, 1154
- GetVectorDimensionality
 - gdcmm::Surface, 1154
- GetVersion
 - gdcmm::MrProtocol, 793
 - gdcmm::Version, 1358
- GetVIEWType
 - gdcmm::Surface, 1154
- GetVIEWTypeString
 - gdcmm::Surface, 1154
- GetVL
 - gdcmm::DataElement, 346
- GetVL16Max
 - gdcmm::VL, 1360
- GetVL32Max
 - gdcmm::VL, 1361
- GetVM
 - gdcmm::Attribute< Group, Element, TVR, TVM >, 134
 - gdcmm::Attribute< Group, Element, TVR, VM::VM1 >, 143
 - gdcmm::Attribute< Group, Element, TVR, VM::VM1_3 >, 150
 - gdcmm::Attribute< Group, Element, TVR, VM::VM1_8 >, 156
 - gdcmm::Attribute< Group, Element, TVR, VM::VM1_n >, 163
 - gdcmm::Attribute< Group, Element, TVR, VM::VM2_2n >, 170
 - gdcmm::Attribute< Group, Element, TVR, VM::VM2_n >, 176
 - gdcmm::Attribute< Group, Element, TVR, VM::VM3_3n >, 183
 - gdcmm::Attribute< Group, Element, TVR, VM::VM3_n >, 188
 - gdcmm::CSAElement, 315
 - gdcmm::CSAHeaderDictEntry, 329
 - gdcmm::DictEntry, 400
 - gdcmm::Element< TVR, TVM >, 430
 - gdcmm::Element< TVR, VM::VM1_2 >, 436
 - gdcmm::Element< TVR, VM::VM2_2n >, 441
 - gdcmm::Element< TVR, VM::VM3_3n >, 446
 - gdcmm::Element< TVR, VM::VM3_4 >, 451
 - gdcmm::Element< VR::AS, VM::VM5 >, 455
 - gdcmm::Element< VR::OB, VM::VM1 >, 460
 - gdcmm::Element< VR::OW, VM::VM1 >, 465
- GetVMString
 - gdcmm::VM, 1367
- GetVMType
 - gdcmm::VM, 1367
- GetVMTypeFromLength
 - gdcmm::VM, 1368
- GetVoidPointer
 - gdcmm::ByteValue, 251
- GetVR

- gdcm::Attribute< Group, Element, TVR, TVM >, [135](#)
- gdcm::Attribute< Group, Element, TVR, VM::VM1 >, [144](#)
- gdcm::Attribute< Group, Element, TVR, VM::VM1_3 >, [150](#)
- gdcm::Attribute< Group, Element, TVR, VM::VM1_8 >, [156](#)
- gdcm::Attribute< Group, Element, TVR, VM::VM1_n >, [163](#)
- gdcm::Attribute< Group, Element, TVR, VM::VM2_2n >, [170](#)
- gdcm::Attribute< Group, Element, TVR, VM::VM2_n >, [176](#)
- gdcm::Attribute< Group, Element, TVR, VM::VM3_3n >, [183](#)
- gdcm::Attribute< Group, Element, TVR, VM::VM3_n >, [189](#)
- gdcm::CSAElement, [315](#)
- gdcm::CSAHeaderDictEntry, [329](#)
- gdcm::DataElement, [346](#)
- gdcm::DictEntry, [400](#)
- gdcm::Element< TVR, TVM >, [430](#)
- gdcm::Element< TVR, VM::VM1_2 >, [436](#)
- gdcm::Element< TVR, VM::VM2_2n >, [441](#)
- gdcm::Element< TVR, VM::VM3_3n >, [446](#)
- gdcm::Element< TVR, VM::VM3_4 >, [451](#)
- gdcm::Element< VR::AS, VM::VM5 >, [456](#)
- gdcm::Element< VR::OB, VM::VM1 >, [460](#)
- gdcm::Element< VR::OW, VM::VM1 >, [465](#)
- GetVRFromTag
 - gdcm, [63](#)
- GetVRString
 - gdcm::VR, [1373](#)
- GetVRStringFromFile
 - gdcm::VR, [1373](#)
- GetVRType
 - gdcm::VR, [1373](#)
- GetVRTypeFromFile
 - gdcm::VR, [1373](#)
- GetVTKDataRoot
 - vtkGDCMTesting, [1436](#)
- GetWarningFlag
 - gdcm::Trace, [1213](#)
- GetWarningStream
 - gdcm::Trace, [1213](#)
- GetWindowName
 - vtkImageColorViewer, [1454](#)
- GetXMax
 - gdcm::BoxRegion, [240](#)
- GetXMin
 - gdcm::BoxRegion, [240](#)
- GetYMax
 - gdcm::BoxRegion, [240](#)
- GetYMin
 - gdcm::BoxRegion, [240](#)
- GetZMax
 - gdcm::BoxRegion, [240](#)
- GetZMin
 - gdcm::BoxRegion, [241](#)
- GetZSpacing
 - gdcm::IPPSorter, [666](#)
- GetZSpacingTagFromMediaStorage
 - gdcm::ImageHelper, [627](#)
- GetZSpacingTolerance
 - gdcm::IPPSorter, [667](#)
- Global
 - gdcm::Defs, [381](#)
 - gdcm::Dicts, [409](#)
 - gdcm::Global, [565](#)
- GlobalInstance
 - gdcm, [74](#)
- GrabOverlayFromPixelData
 - gdcm::Overlay, [843](#)
- Graphics
 - gdcm::Overlay, [840](#)
- GRAY
 - gdcm::LookupTable, [728](#)
- GrayscalePlanarMPRVolumetricPresentationStateStorage
 - gdcm::UIDs, [1254](#)
- GrayscaleSoftcopyPresentationStateStorageSOPClass
 - gdcm::MediaStorage, [748](#)
 - gdcm::UIDs, [1250](#)
- GREEN
 - gdcm::LookupTable, [728](#)
- green
 - gdcm::terminal, [81](#)
- GroupDict
 - gdcm::GroupDict, [568](#)
- GroupStringVector
 - gdcm::GroupDict, [568](#)
- GuessFromModality
 - gdcm::MediaStorage, [752](#)
- HandleBulkData
 - gdcm::XMLPrinter, [1508](#)
- HandleDataSet
 - gdcm::network::ULBasicCallback, [1310](#)
 - gdcm::network::ULConnectionCallback, [1317](#)
 - gdcm::network::ULWritingCallback, [1332](#)
- HandleDescription
 - gdcm::XMLDictReader, [1506](#)
 - gdcm::XMLPrivateDictReader, [1512](#)
- HandleEntry
 - gdcm::XMLDictReader, [1506](#)
 - gdcm::XMLPrivateDictReader, [1513](#)
- HandleEvent
 - gdcm::network::ULTransitionTable, [1330](#)
- HandleIOD

- gdcmm::TableReader, 1188
- HandleIODEntry
 - gdcmm::TableReader, 1188
- HandleMacro
 - gdcmm::TableReader, 1188
- HandleMacroEntry
 - gdcmm::TableReader, 1188
- HandleMacroEntryDescription
 - gdcmm::TableReader, 1189
- HandleModule
 - gdcmm::TableReader, 1189
- HandleModuleEntry
 - gdcmm::TableReader, 1189
- HandleModuleEntryDescription
 - gdcmm::TableReader, 1189
- HandleModuleInclude
 - gdcmm::TableReader, 1189
- HandleResponse
 - gdcmm::network::ULBasicCallback, 1310
 - gdcmm::network::ULConnectionCallback, 1317
 - gdcmm::network::ULWritingCallback, 1332
- HangingProtocolInformationModelFIND
 - gdcmm::UIDs, 1252
- HangingProtocolInformationModelGET
 - gdcmm::UIDs, 1256
- HangingProtocolInformationModelMOVE
 - gdcmm::UIDs, 1252
- HangingProtocolStorage
 - gdcmm::MediaStorage, 749
 - gdcmm::UIDs, 1252
- HardcopyColorImageStorage
 - gdcmm::MediaStorage, 750
- HardcopyColorImageStorageSOPClassRetired
 - gdcmm::UIDs, 1249
- HardcopyGrayscaleImageStorage
 - gdcmm::MediaStorage, 749
- HardcopyGrayscaleImageStorageSOPClassRetired
 - gdcmm::UIDs, 1249
- HasObserver
 - gdcmm::Subject, 1145
- HemodynamicWaveformStorage
 - gdcmm::MediaStorage, 748
 - gdcmm::UIDs, 1250
- HEVCH_265Main10ProfileLevel5_1
 - gdcmm::UIDs, 1254
- HEVCH_265MainProfileLevel5_1
 - gdcmm::UIDs, 1254
- hidden
 - gdcmm::terminal, 81
- HITACHI
 - gdcmm::EquipmentManufacturer, 481
- HotIronColorPaletteSOPInstance
 - gdcmm::UIDs, 1254
- HotMetalBlueColorPaletteSOPInstance
 - gdcmm::UIDs, 1253
- HSV
 - gdcmm::PhotometricInterpretation, 876
- HTJ2K
 - gdcmm::TransferSyntax, 1218
- HTJ2KLossless
 - gdcmm::TransferSyntax, 1218
- HTJ2KRPCLLossless
 - gdcmm::TransferSyntax, 1218
- ICBM452T1FrameofReference
 - gdcmm::UIDs, 1248
- ICBMSingleSubjectMRIFrameofReference
 - gdcmm::UIDs, 1248
- ICD11
 - gdcmm::UIDs, 1253
- Icon
 - gdcmm::Pixmap, 893
- IconDataScalarType
 - vtkGDCMImageReader, 1396
 - vtkGDCMImageReader2, 1411
- IconImage
 - gdcmm, 59
- IconImageDataExtent
 - vtkGDCMImageReader, 1396
 - vtkGDCMImageReader2, 1411
- IconImageFilter
 - gdcmm::IconImageFilter, 571
- IconImageGenerator
 - gdcmm::IconImageGenerator, 574
- IconNumberOfScalarComponents
 - vtkGDCMImageReader, 1396
 - vtkGDCMImageReader2, 1411
- ID
 - gdcmm::PresentationContext, 918
- ignore_char
 - gdcmm::ignore_char, 577
- Image
 - gdcmm::Image, 582
- ImageActor
 - vtkImageColorViewer, 1461
- ImageApplyLookupTable
 - gdcmm::ImageApplyLookupTable, 588
- ImageBiomarkerStandardisationInitiative
 - gdcmm::UIDs, 1254
- ImageChangePhotometricInterpretation
 - gdcmm::ImageChangePhotometricInterpretation, 592
 - gdcmm::ImageCodec, 615
- ImageChangePlanarConfiguration
 - gdcmm::ImageChangePlanarConfiguration, 597
- ImageChangeTransferSyntax
 - gdcmm::Bitmap, 232
 - gdcmm::ImageChangeTransferSyntax, 602
- ImageCodec

- gdcmm::ImageCodec, 608
- ImageConverter
 - gdcmm::ImageConverter, 618
- ImageFormat
 - vtkGDCMImageReader, 1396
 - vtkGDCMImageReader2, 1411
- ImageFragmentSplitter
 - gdcmm::ImageFragmentSplitter, 621
- ImageNumberOrdering
 - gdcmm::SerieHelper, 1058
- ImageOrientationPatient
 - vtkGDCMImageReader, 1396
 - vtkGDCMImageReader2, 1411
- ImageOverlayBoxSOPClassRetired
 - gdcmm::UIDs, 1249
- ImagePositionPatient
 - vtkGDCMImageReader, 1396
 - vtkGDCMImageReader2, 1411
- ImagePositionPatientOrdering
 - gdcmm::SerieHelper, 1058
- ImageReader
 - gdcmm::ImageReader, 632
- ImageRegionReader
 - gdcmm::ImageRegionReader, 637
 - gdcmm::JPEG2000Codec, 694
 - gdcmm::JPEGCodec, 708
 - gdcmm::JPEGLSCCodec, 716
 - gdcmm::RLECodec, 994
- ImageToImageFilter
 - gdcmm::ImageToImageFilter, 641
- ImageWriter
 - gdcmm::ImageWriter, 645
- ImplantAssemblyTemplateInformationModelFIND
 - gdcmm::UIDs, 1256
- ImplantAssemblyTemplateInformationModelGET
 - gdcmm::UIDs, 1256
- ImplantAssemblyTemplateInformationModelMOVE
 - gdcmm::UIDs, 1256
- ImplantAssemblyTemplateStorage
 - gdcmm::UIDs, 1256
- ImplantationPlanSRStorage
 - gdcmm::UIDs, 1255
- ImplantTemplateGroupInformationModelFIND
 - gdcmm::UIDs, 1256
- ImplantTemplateGroupInformationModelGET
 - gdcmm::UIDs, 1256
- ImplantTemplateGroupInformationModelMOVE
 - gdcmm::UIDs, 1256
- ImplantTemplateGroupStorage
 - gdcmm::UIDs, 1256
- ImplementationClassUIDSub
 - gdcmm::network::ImplementationClassUIDSub, 647
- ImplementationUIDSub
 - gdcmm::network::ImplementationUIDSub, 648
- ImplementationVersionNameSub
 - gdcmm::network::ImplementationVersionNameSub, 649
- Implicit
 - gdcmm::TransferSyntax, 1217
- ImplicitVRBigEndianACRNEMA
 - gdcmm::TransferSyntax, 1218
- ImplicitVRBigEndianPrivateGE
 - gdcmm::TransferSyntax, 1218
- ImplicitVRLittleEndian
 - gdcmm::TransferSyntax, 1218
- ImplicitVRLittleEndianDefaultTransferSyntaxforDICOM
 - gdcmm::UIDs, 1247
- IncompleteLUT
 - gdcmm::LookupTable, 733
- InitFromRQ
 - gdcmm::network::AAssociateACPDU, 90
- Initialize
 - gdcmm::network::ULConnectionInfo, 1319
- InitializeBlueLUT
 - gdcmm::LookupTable, 731
- InitializeConnection
 - gdcmm::network::ULConnection, 1314
 - gdcmm::ServiceClassUser, 1065
- Initialized
 - gdcmm::LookupTable, 731
- InitializeDataSet
 - gdcmm::BaseRootQuery, 210
 - gdcmm::FindPatientRootQuery, 554
 - gdcmm::FindStudyRootQuery, 558
 - gdcmm::MovePatientRootQuery, 787
 - gdcmm::MoveStudyRootQuery, 791
 - gdcmm::WLMFindQuery, 1497
- InitializeGreenLUT
 - gdcmm::LookupTable, 731
- InitializeIncomingConnection
 - gdcmm::network::ULConnection, 1314
- InitializeLUT
 - gdcmm::LookupTable, 731
- InitializeRedLUT
 - gdcmm::LookupTable, 731
- InitializeRTStructSet
 - vtkGDCMPolyDataWriter, 1431
- InitOpenSSL
 - gdcmm::OpenSSLCryptoFactory, 825
- Input
 - gdcmm::BitmapToBitmapFilter, 236
- Insert
 - gdcmm::CommandDataSet, 294
 - gdcmm::DataSet, 365
 - gdcmm::FileMetaInformation, 527
 - gdcmm::GroupDict, 569
- InsertDataElement
 - gdcmm::DataSet, 366

- gdcM::Item, [674](#)
- InsertEntry
 - gdcM::Table, [1184](#)
- InstallPipeline
 - vtkImageColorViewer, [1455](#)
- InstanceAvailabilityNotificationSOPClass
 - gdcM::UIDs, [1252](#)
- INT12
 - gdcM::PixelFormat, [880](#)
- INT16
 - gdcM::PixelFormat, [880](#)
- INT32
 - gdcM::PixelFormat, [880](#)
- INT64
 - gdcM::PixelFormat, [880](#)
- INT8
 - gdcM::PixelFormat, [880](#)
- IntegratedTaxonomicInformationSystemITISTaxonomicSerialNumber
 - gdcM::UIDs, [1253](#)
- Interactor
 - vtkImageColorViewer, [1461](#)
- InteractorStyle
 - vtkImageColorViewer, [1461](#)
- INTERFILE
 - gdcM::CSAHeader, [321](#)
- Internal
 - gdcM::ApplicationEntity, [120](#)
 - gdcM::Attribute< Group, Element, TVR, TVM >, [138](#)
 - gdcM::Attribute< Group, Element, TVR, VM::VM1 >, [146](#)
 - gdcM::Attribute< Group, Element, TVR, VM::VM1_3 >, [152](#)
 - gdcM::Attribute< Group, Element, TVR, VM::VM1_8 >, [158](#)
 - gdcM::Attribute< Group, Element, TVR, VM::VM2_2n >, [172](#)
 - gdcM::Attribute< Group, Element, TVR, VM::VM2_n >, [178](#)
 - gdcM::Attribute< Group, Element, TVR, VM::VM3_3n >, [185](#)
 - gdcM::Attribute< Group, Element, TVR, VM::VM3_n >, [190](#)
 - gdcM::Element< TVR, TVM >, [433](#)
 - gdcM::Element< TVR, VM::VM1_2 >, [438](#)
 - gdcM::Element< TVR, VM::VM2_2n >, [443](#)
 - gdcM::Element< TVR, VM::VM3_3n >, [448](#)
 - gdcM::Element< TVR, VM::VM3_4 >, [453](#)
 - gdcM::Element< VR::AS, VM::VM5 >, [457](#)
 - gdcM::Element< VR::OB, VM::VM1 >, [462](#)
 - gdcM::Element< VR::OW, VM::VM1 >, [467](#)
 - gdcM::LookupTable, [733](#)
 - gdcM::UI, [1228](#)
- InternalCode
 - gdcM::Coder, [282](#)
- gdcM::JPEG12Codec, [681](#)
- gdcM::JPEG16Codec, [686](#)
- gdcM::JPEG8Codec, [699](#)
- Internals
 - vtkRTStructSetProperties, [1492](#)
- IntraocularLensCalculationsStorage
 - gdcM::UIDs, [1255](#)
- IntravascularOpticalCoherenceTomographyImageStorageForPresentation
 - gdcM::UIDs, [1254](#)
- IntravascularOpticalCoherenceTomographyImageStorageForProcessing
 - gdcM::UIDs, [1254](#)
- INVALID
 - gdcM::VR, [1371](#)
- Invalid
 - gdcM::Overlay, [840](#)
 - gdcM::Usage, [1343](#)
- InverseRescale
 - gdcM::Rescaler, [985](#)
- InverseRescaleFunctionIntoBestFit
 - gdcM::Rescaler, [985](#)
- InvokeEvent
 - gdcM::Subject, [1145](#)
- IOD
 - gdcM::IOD, [657](#)
- IODEntry
 - gdcM::IODEntry, [659](#)
- IODMapType
 - gdcM::IODs, [662](#)
- IODMapTypeConstIterator
 - gdcM::IODs, [662](#)
- IODName
 - gdcM::IODs, [662](#)
- IODs
 - gdcM::IODs, [662](#)
- IPPSorter
 - gdcM::IPPSorter, [666](#)
- IS
 - gdcM::VR, [1371](#)
- IsAETitleValid
 - gdcM::network::AAssociateRQPDU, [97](#)
- IsASCII
 - gdcM::VR, [1373](#)
- IsASCII2
 - gdcM::VR, [1374](#)
- IsBinary
 - gdcM::VR, [1374](#)
- IsBinary2
 - gdcM::VR, [1374](#)
- IsCompatible
 - gdcM::PixelFormat, [883](#)
- IsDual
 - gdcM::VR, [1374](#)
- IsEmpty
 - gdcM::Bitmap, [227](#)

- gdcm::ByteValue, 251
- gdcm::CSAElement, 315
- gdcm::CSAHeaderDict, 327
- gdcm::Curve, 338
- gdcm::DataElement, 347
- gdcm::DataSet, 366
- gdcm::Defs, 380
- gdcm::Dict, 393
- gdcm::Dicts, 409
- gdcm::Filename, 532
- gdcm::Macros, 740
- gdcm::Modules, 783
- gdcm::Overlay, 843
- gdcm::Preamble, 913
- gdcm::PrivateDict, 937
- gdcm::SegmentHelper::BasicCodedEntry, 214
- gdcm::SequenceOfItems, 1051
- IsEncapsulated
 - gdcm::TransferSyntax, 1220
- IsEncoded
 - gdcm::TransferSyntax, 1220
- IsExplicit
 - gdcm::TransferSyntax, 1220
- IsFrameEncoder
 - gdcm::ImageCodec, 612
 - gdcm::JPEG2000Codec, 693
 - gdcm::JPEGCodec, 707
 - gdcm::JPEGLSCodec, 715
 - gdcm::RLECodec, 993
- IsGroupLength
 - gdcm::Tag, 1195
- IsGroupXX
 - gdcm::Tag, 1195
- IsIdentical
 - gdcm::Filename, 532
- IsIllegal
 - gdcm::Tag, 1196
- IsImage
 - gdcm::MediaStorage, 752
- IsImplicit
 - gdcm::TransferSyntax, 1220
- IsInPixelData
 - gdcm::Overlay, 843
- IsKey
 - gdcm::Scanner, 1003
 - gdcm::Scanner2, 1014
 - gdcm::StrictScanner, 1121
 - gdcm::StrictScanner2, 1132
- IsLastFragment
 - gdcm::network::AAAbortPDU, 86
 - gdcm::network::AAAssociateACPDU, 90
 - gdcm::network::AAAssociateRJPDU, 93
 - gdcm::network::AAAssociateRQPDU, 98
 - gdcm::network::AReleaseRPPDU, 121
 - gdcm::network::AReleaseRQPDU, 124
 - gdcm::network::BasePDU, 201
 - gdcm::network::PDataTFPDU, 855
- IsLossless
 - gdcm::PhotometricInterpretation, 877
 - gdcm::TransferSyntax, 1220
- IsLossy
 - gdcm::Bitmap, 227
 - gdcm::ImageCodec, 613
 - gdcm::PhotometricInterpretation, 877
 - gdcm::TransferSyntax, 1220
- IsOdd
 - gdcm::VL, 1361
- IsPresentationContextAccepted
 - gdcm::ServiceClassUser, 1066
- IsPrintable
 - gdcm::ByteValue, 252
- IsPrivate
 - gdcm::Tag, 1196
- IsPrivateCreator
 - gdcm::Tag, 1196
- IsPublic
 - gdcm::Tag, 1196
- IsRetired
 - gdcm::PhotometricInterpretation, 877
- IsRGB8
 - gdcm::LookupTable, 731
- IsRowEncoder
 - gdcm::ImageCodec, 613
 - gdcm::JPEG2000Codec, 693
 - gdcm::JPEGCodec, 707
 - gdcm::JPEGLSCodec, 715
 - gdcm::RLECodec, 993
- IsSameColorSpace
 - gdcm::PhotometricInterpretation, 877
- IsStateSuspension
 - gdcm::JPEG12Codec, 681
 - gdcm::JPEG16Codec, 686
 - gdcm::JPEG8Codec, 699
 - gdcm::JPEGCodec, 707
- IsSwap
 - gdcm::VR, 1374
- IsTransferSyntaxCompatible
 - gdcm::Bitmap, 227
- IsUndefined
 - gdcm::MediaStorage, 752
 - gdcm::VL, 1361
- IsUndefinedLength
 - gdcm::DataElement, 347
 - gdcm::SequenceOfItems, 1051
- IsUnique
 - gdcm::DictEntry, 401
- IsValid
 - gdcm::ApplicationEntity, 119

- gdcm::BoxRegion, [241](#)
- gdcm::CodeString, [286](#)
- gdcm::DirectionCosines, [414](#)
- gdcm::DPath, [422](#)
- gdcm::FileMetaInformation, [527](#)
- gdcm::ImageCodec, [613](#)
- gdcm::JPEGCodec, [707](#)
- gdcm::LO, [725](#)
- gdcm::PixelFormat, [883](#)
- gdcm::Preamble, [913](#)
- gdcm::Region, [982](#)
- gdcm::String< TDelimiter, TMaxLength, TPadChar
>, [1137](#)
- gdcm::TagPath, [1203](#)
- gdcm::TransferSyntax, [1220](#)
- gdcm::UIDGenerator, [1230](#)
- gdcm::UUIDGenerator, [1349](#)
- gdcm::VM, [1368](#)
- gdcm::VR, [1374](#)
- IsVRFile
 - gdcm::VR, [1374](#)
- IsZero
 - gdcm::Overlay, [843](#)
- Item
 - gdcm::Item, [673](#)
- Items
 - gdcm::SequenceOfItems, [1054](#)
- ItemVector
 - gdcm::SequenceOfItems, [1048](#)
- Iterator
 - gdcm::CSAHeaderDict, [325](#)
 - gdcm::DataSet, [361](#)
 - gdcm::Dict, [391](#)
 - gdcm::SequenceOfFragments, [1040](#)
 - gdcm::SequenceOfItems, [1048](#)
- iterator
 - gdcm::CodeString, [285](#)
 - gdcm::LO, [724](#)
 - gdcm::String< TDelimiter, TMaxLength, TPadChar
>, [1136](#)
- ItFileSetHt
 - gdcm::SerieHelper, [1059](#)
- IVOCTForPresentation
 - gdcm::MediaStorage, [750](#)
- IVOCTForProcessing
 - gdcm::MediaStorage, [750](#)
- Join
 - gdcm::Filename, [532](#)
- JPEG12Codec
 - gdcm::JPEG12Codec, [681](#)
- JPEG16Codec
 - gdcm::JPEG16Codec, [686](#)
- JPEG2000
 - gdcm::TransferSyntax, [1218](#)
- JPEG2000_COMPRESSION
 - vtkGDCMImageWriter, [1415](#)
- JPEG2000Codec
 - gdcm::JPEG2000Codec, [690](#)
- JPEG2000ImageCompression
 - gdcm::UIDs, [1247](#)
- JPEG2000ImageCompressionLosslessOnly
 - gdcm::UIDs, [1247](#)
- JPEG2000Lossless
 - gdcm::TransferSyntax, [1218](#)
- JPEG2000Part2
 - gdcm::TransferSyntax, [1218](#)
- JPEG2000Part2Lossless
 - gdcm::TransferSyntax, [1218](#)
- JPEG2000Part2MulticomponentImageCompression
 - gdcm::UIDs, [1247](#)
- JPEG2000Part2MulticomponentImageCompressionLosslessOnly
 - gdcm::UIDs, [1247](#)
- JPEG8Codec
 - gdcm::JPEG8Codec, [699](#)
- JPEG_COMPRESSION
 - vtkGDCMImageWriter, [1415](#)
- JPEGBaselineProcess1
 - gdcm::TransferSyntax, [1218](#)
- JPEGBaselineProcess1DefaultTransferSyntaxforLossyJPEG8BitImageComp
 - gdcm::UIDs, [1247](#)
- JPEGCodec
 - gdcm::JPEGCodec, [704](#)
- JPEGExtendedHierarchicalProcess1618Retired
 - gdcm::UIDs, [1247](#)
- JPEGExtendedHierarchicalProcess1719Retired
 - gdcm::UIDs, [1247](#)
- JPEGExtendedProcess24DefaultTransferSyntaxforLossyJPEG12BitImageC
 - gdcm::UIDs, [1247](#)
- JPEGExtendedProcess2_4
 - gdcm::TransferSyntax, [1218](#)
- JPEGExtendedProcess35Retired
 - gdcm::UIDs, [1247](#)
- JPEGExtendedProcess3_5
 - gdcm::TransferSyntax, [1218](#)
- JPEGFullProgressionHierarchicalProcess2426Retired
 - gdcm::UIDs, [1247](#)
- JPEGFullProgressionHierarchicalProcess2527Retired
 - gdcm::UIDs, [1247](#)
- JPEGFullProgressionNonHierarchicalProcess1012Retired
 - gdcm::UIDs, [1247](#)
- JPEGFullProgressionNonHierarchicalProcess1113Retired
 - gdcm::UIDs, [1247](#)
- JPEGFullProgressionProcess10_12
 - gdcm::TransferSyntax, [1218](#)
- JPEGLosslessHierarchicalProcess28Retired
 - gdcm::UIDs, [1247](#)
- JPEGLosslessHierarchicalProcess29Retired

- gdcm::UIDs, [1247](#)
- JPEGLosslessNonHierarchicalFirstOrderPredictionProcess14Retired
 - gdcm::UIDs, [1247](#)
- JPEGLosslessNonHierarchicalProcess14
 - gdcm::UIDs, [1247](#)
- JPEGLosslessNonHierarchicalProcess15Retired
 - gdcm::UIDs, [1247](#)
- JPEGLosslessProcess14
 - gdcm::TransferSyntax, [1218](#)
- JPEGLosslessProcess14_1
 - gdcm::TransferSyntax, [1218](#)
- JPEGLS_COMPRESSION
 - vtkGDCMImageWriter, [1415](#)
- JPEGLSCodec
 - gdcm::JPEGLSCodec, [712](#)
- JPEGLSLossless
 - gdcm::TransferSyntax, [1218](#)
- JPEGLSLosslessImageCompression
 - gdcm::UIDs, [1247](#)
- JPEGLSLossyNearLosslessImageCompression
 - gdcm::UIDs, [1247](#)
- JPEGLSNearLossless
 - gdcm::TransferSyntax, [1218](#)
- JPEGSpectralSelectionHierarchicalProcess2022Retired
 - gdcm::UIDs, [1247](#)
- JPEGSpectralSelectionHierarchicalProcess2123Retired
 - gdcm::UIDs, [1247](#)
- JPEGSpectralSelectionNonHierarchicalProcess68Retired
 - gdcm::UIDs, [1247](#)
- JPEGSpectralSelectionNonHierarchicalProcess79Retired
 - gdcm::UIDs, [1247](#)
- JPEGSpectralSelectionProcess6_8
 - gdcm::TransferSyntax, [1218](#)
- JPIPReferenced
 - gdcm::TransferSyntax, [1218](#)
 - gdcm::UIDs, [1247](#)
- JPIPReferencedDeflate
 - gdcm::UIDs, [1248](#)
- JSON
 - gdcm::JSON, [717](#)
- JunkAfterDocElementError
 - gdcm::Parser, [850](#)
- KAKADUCodec
 - gdcm::KAKADUCodec, [721](#)
- KeratometryMeasurementsStorage
 - gdcm::UIDs, [1254](#)
- KeyField
 - gdcm::CSAElement, [318](#)
- KeyObjectSelectionDocument
 - gdcm::MediaStorage, [749](#)
- KeyObjectSelectionDocumentStorage
 - gdcm::UIDs, [1251](#)
- KeyValuePairArrayType
 - gdcm::CompositeNetworkFunctions, [297](#)
- KeyObjectPairType
 - gdcm::CompositeNetworkFunctions, [297](#)
- KODAK
 - gdcm::EquipmentManufacturer, [481](#)
- LD_ALL
 - gdcm, [62](#)
- LD_NOSEQ
 - gdcm, [62](#)
- LD_NOSHADOW
 - gdcm, [62](#)
- LD_NOSHADOWSEQ
 - gdcm, [62](#)
- LeadECGWaveformStorage
 - gdcm::MediaStorage, [748](#)
- LegacyConvertedEnhancedCTImageStorage
 - gdcm::MediaStorage, [750](#)
 - gdcm::UIDs, [1253](#)
- LegacyConvertedEnhancedMRImageStorage
 - gdcm::MediaStorage, [750](#)
 - gdcm::UIDs, [1253](#)
- LegacyConvertedEnhancedPETImageStorage
 - gdcm::MediaStorage, [750](#)
 - gdcm::UIDs, [1253](#)
- LensometryMeasurementsStorage
 - gdcm::UIDs, [1254](#)
- Level
 - vtkImageMapToWindowLevelColors2, [1472](#)
- LINE
 - gdcm::MeshPrimitive, [762](#)
- ListCharSets
 - gdcm::QueryFactory, [956](#)
- LittleEndian
 - gdcm::SwapCode, [1172](#)
- LO
 - gdcm::LO, [725](#)
 - gdcm::VR, [1371](#)
- Load
 - gdcm::Directory, [417](#)
 - gdcm::MrProtocol, [793](#)
- LOADBULKDATA
 - gdcm::XMLPrinter, [1508](#)
- LoadDefault
 - gdcm::CSAHeaderDict, [327](#)
 - gdcm::Dict, [393](#)
 - gdcm::PrivateDict, [937](#)
- LoadDefaults
 - gdcm::Defs, [381](#)
 - gdcm::Dicts, [409](#)
- LoadFromDataElement
 - gdcm::CSAHeader, [324](#)
 - gdcm::PDBHeader, [861](#)
- LoadFromFile

- gdcm::Defs, [381](#)
- LoadIconImage
 - vtkGDCMImageReader, [1397](#)
 - vtkGDCMImageReader2, [1411](#)
- LoadImageFromFiles
 - gdcm::DirectoryHelper, [420](#)
- LoadOverlays
 - vtkGDCMImageReader, [1397](#)
 - vtkGDCMImageReader2, [1412](#)
- LoadResourcesFiles
 - gdcm::Global, [566](#)
- LoadSingleFile
 - vtkGDCMImageReader, [1387](#)
 - vtkGDCMImageReader2, [1402](#)
- Locate
 - gdcm::Global, [566](#)
- LOComp
 - gdcm, [59](#)
- LodModeType
 - gdcm, [62](#)
- LookupTable
 - gdcm::LookupTable, [728](#), [729](#)
 - vtkImageMapToColors16, [1468](#)
- LookupTableType
 - gdcm::LookupTable, [728](#)
- LossyFlag
 - gdcm::Bitmap, [233](#)
 - gdcm::ImageCodec, [616](#)
 - vtkGDCMImageReader, [1397](#)
 - vtkGDCMImageReader2, [1412](#)
- LT
 - gdcm::VR, [1371](#)
- LTComp
 - gdcm, [59](#)
- LUT
 - gdcm::Bitmap, [233](#)
 - gdcm::ImageCodec, [616](#)
- LUTPtr
 - gdcm::Bitmap, [223](#)
 - gdcm::ImageCodec, [608](#)
- m_char
 - gdcm::ignore_char, [577](#)
- m_ConstMemberFunction
 - gdcm::MemberCommand< T >, [759](#)
- m_DataSet
 - gdcm::DataSetEvent, [374](#)
- m_MemberFunction
 - gdcm::MemberCommand< T >, [759](#)
 - gdcm::SimpleMemberCommand< T >, [1077](#)
- m_This
 - gdcm::MemberCommand< T >, [759](#)
 - gdcm::SimpleMemberCommand< T >, [1077](#)
- Macro
 - gdcm::Macro, [737](#)
- MacroEntry
 - gdcm, [59](#)
- Macros
 - gdcm::Macros, [739](#)
- mAction
 - gdcm::network::Transition, [1224](#)
- MacularGridThicknessandVolumeReportStorage
 - gdcm::UIDs, [1255](#)
- magenta
 - gdcm::terminal, [81](#)
- MAGNIFIED
 - gdcm::Spacing, [1095](#)
- MakeDirectory
 - gdcm::System, [1180](#)
- MakeNew
 - gdcm::network::Transition, [1224](#)
- MakeObject
 - gdcm::AnonymizeEvent, [105](#)
 - gdcm::DataEvent, [357](#)
 - gdcm::DataSetEvent, [373](#)
 - gdcm::Event, [484](#)
 - gdcm::FileNameEvent, [536](#)
 - gdcm::ProgressEvent, [946](#)
- MammographyCADSR
 - gdcm::MediaStorage, [749](#)
- MammographyCADSRStorage
 - gdcm::UIDs, [1251](#)
- Mandatory
 - gdcm::Usage, [1343](#)
- MANUAL
 - gdcm::Segment, [1019](#)
- MapCSAHeaderDictEntry
 - gdcm::CSAHeaderDict, [326](#)
- MapDictEntry
 - gdcm::Dict, [391](#)
- MapIODEntry
 - gdcm::IOD, [656](#)
- MapModuleEntry
 - gdcm::Macro, [736](#)
 - gdcm::Module, [774](#)
- MappingType
 - gdcm::Scanner, [999](#)
 - gdcm::StrictScanner, [1117](#)
- MapScalarsThroughTable2
 - vtkLookupTable16, [1481](#)
- MapTableEntry
 - gdcm::Table, [1184](#)
- MARCONI
 - gdcm::EquipmentManufacturer, [481](#)
- Match
 - gdcm::DPath, [422](#)
- MaximumLengthSub
 - gdcm::network::MaximumLengthSub, [741](#)

- MaxLength
 - gdcm::ApplicationEntity, [120](#)
 - gdcm::PersonName, [869](#)
- MaxNumberOfComponents
 - gdcm::ApplicationEntity, [120](#)
 - gdcm::PersonName, [870](#)
- MaxPrintLength
 - gdcm::Printer, [935](#)
- MayoClinicNonradiologicalImagesSBSAnatomicalSurfaceRegion
 - gdcm::UIDs, [1254](#)
- mConnection
 - gdcm::network::ULConnectionManager, [1327](#)
- MD5DataImagesType
 - gdcm::Testing, [1205](#)
- MD5MetalImagesType
 - vtkGDCMTesting, [1435](#)
- mDataSet
 - gdcm::BaseQuery, [207](#)
- MediaCreationManagementSOPClassUID
 - gdcm::UIDs, [1249](#)
- MediaStorage
 - gdcm::MediaStorage, [750](#)
- MediaStorageDataFilesType
 - gdcm::Testing, [1205](#)
- MediaStorageDirectoryStorage
 - gdcm::MediaStorage, [748](#)
 - gdcm::UIDs, [1248](#)
- MedicalImageProperties
 - vtkGDCMImageReader, [1397](#)
 - vtkGDCMPolyDataReader, [1428](#)
 - vtkGDCMPolyDataWriter, [1433](#)
- mElementOffsets
 - gdcm::StreamImageWriter, [1112](#)
- mElementOffsets1
 - gdcm::StreamImageWriter, [1112](#)
- MemberCommand
 - gdcm::MemberCommand< T >, [757](#)
- mEnd
 - gdcm::network::Transition, [1224](#)
- MeshPrimitive
 - gdcm::MeshPrimitive, [763](#)
- MessageID
 - gdcm::network::CEchoRQ, [262](#)
- MetaInformationTS
 - gdcm::FileMetaInformation, [530](#)
- mHelpDescription
 - gdcm::BaseRootQuery, [211](#)
- mImage
 - gdcm::BaseRootQuery, [211](#)
- mImplicit
 - gdcm::network::ULConnectionCallback, [1318](#)
- ModalityPerformedProcedureStepCreateQuery
 - gdcm::ModalityPerformedProcedureStepCreateQuery, [767](#)
- ModalityPerformedProcedureStepNotificationSOPClass
 - gdcm::UIDs, [1249](#)
- ModalityPerformedProcedureStepRetrieveSOPClass
 - gdcm::UIDs, [1248](#)
- ModalityPerformedProcedureStepSetQuery
 - gdcm::ModalityPerformedProcedureStepSetQuery, [771](#)
- ModalityPerformedProcedureStepSOPClass
 - gdcm::MediaStorage, [749](#)
 - gdcm::UIDs, [1248](#)
- ModalityWorklistInformationModelFIND
 - gdcm::UIDs, [1252](#)
- Mode
 - gdcm::terminal, [81](#)
- Module
 - gdcm::Module, [775](#)
- ModuleEntry
 - gdcm::ModuleEntry, [779](#)
- ModuleMapType
 - gdcm::Macros, [739](#)
 - gdcm::Modules, [782](#)
- Modules
 - gdcm::Modules, [782](#)
- MONOCHROME1
 - gdcm::PhotometricInterpretation, [876](#)
- MONOCHROME2
 - gdcm::PhotometricInterpretation, [876](#)
- MouseGenomeInitiativeMGI
 - gdcm::UIDs, [1253](#)
- MovePatientRootQuery
 - gdcm::MovePatientRootQuery, [786](#)
- MoveStudyRootQuery
 - gdcm::MoveStudyRootQuery, [790](#)
- mPatient
 - gdcm::BaseRootQuery, [212](#)
- MPEG2MainProfile
 - gdcm::TransferSyntax, [1218](#)
- MPEG2MainProfileHighLevel
 - gdcm::TransferSyntax, [1218](#)
 - gdcm::UIDs, [1253](#)
- MPEG2MainProfileMainLevel
 - gdcm::UIDs, [1248](#)
- MPEG4AVCH264BDcompatibleHighProfileLevel4_1
 - gdcm::TransferSyntax, [1218](#)
- MPEG4AVCH264HighProfileLevel4_1
 - gdcm::TransferSyntax, [1218](#)
- MPEG4AVCH_264BDcompatibleHighProfileLevel4_1
 - gdcm::UIDs, [1253](#)
- MPEG4AVCH_264HighProfileLevel4_1
 - gdcm::UIDs, [1253](#)
- MPEG4AVCH_264HighProfileLevel4_2For2DVideo
 - gdcm::UIDs, [1254](#)
- MPEG4AVCH_264HighProfileLevel4_2For3DVideo
 - gdcm::UIDs, [1254](#)

- MPEG4AVCH_264StereoHighProfileLevel4_2
 - gdcm::UIDs, [1254](#)
- MPTType
 - gdcm::MeshPrimitive, [762](#)
- MPTType_END
 - gdcm::MeshPrimitive, [762](#)
- MRImageStorage
 - gdcm::MediaStorage, [748](#)
 - gdcm::UIDs, [1250](#)
- mRootType
 - gdcm::BaseRootQuery, [212](#)
- MrProtocol
 - gdcm::MrProtocol, [792](#)
- MRSpectroscopyStorage
 - gdcm::MediaStorage, [748](#)
 - gdcm::UIDs, [1250](#)
- MS_END
 - gdcm::MediaStorage, [750](#)
- mSecondaryConnection
 - gdcm::network::ULConnectionManager, [1327](#)
- mSeries
 - gdcm::BaseRootQuery, [212](#)
- mSopInstanceUID
 - gdcm::BaseQuery, [207](#)
- mSPFile
 - gdcm::StreamImageWriter, [1112](#)
- mStudy
 - gdcm::BaseRootQuery, [212](#)
- MSType
 - gdcm::MediaStorage, [747](#)
- mTransitions
 - gdcm::network::ULConnectionManager, [1327](#)
- MultiframeGrayscaleByteSecondaryCaptureImageStorage
 - gdcm::MediaStorage, [748](#)
 - gdcm::UIDs, [1250](#)
- MultiframeGrayscaleWordSecondaryCaptureImageStorage
 - gdcm::MediaStorage, [748](#)
 - gdcm::UIDs, [1250](#)
- MultiframeSingleBitSecondaryCaptureImageStorage
 - gdcm::MediaStorage, [748](#)
 - gdcm::UIDs, [1250](#)
- MultiframeTrueColorSecondaryCaptureImageStorage
 - gdcm::MediaStorage, [748](#)
 - gdcm::UIDs, [1250](#)
- MultipleVolumeRenderingVolumetricPresentationStateStorage
 - gdcm::UIDs, [1254](#)
- mWriter
 - gdcm::StreamImageWriter, [1113](#)
- mXMax
 - gdcm::StreamImageWriter, [1113](#)
- mXMin
 - gdcm::StreamImageWriter, [1113](#)
- mYMax
 - gdcm::StreamImageWriter, [1113](#)
- mYMin
 - gdcm::StreamImageWriter, [1113](#)
- mZMax
 - gdcm::StreamImageWriter, [1113](#)
- mZMin
 - gdcm::StreamImageWriter, [1113](#)
- N_ACTION_RQ
 - gdcm::network::DIMSE, [411](#)
- N_ACTION_RSP
 - gdcm::network::DIMSE, [411](#)
- N_CREATE_RQ
 - gdcm::network::DIMSE, [411](#)
- N_CREATE_RSP
 - gdcm::network::DIMSE, [411](#)
- N_DELETE_RQ
 - gdcm::network::DIMSE, [411](#)
- N_DELETE_RSP
 - gdcm::network::DIMSE, [411](#)
- N_EVENT_REPORT_RQ
 - gdcm::network::DIMSE, [411](#)
- N_EVENT_REPORT_RSP
 - gdcm::network::DIMSE, [411](#)
- N_GET_RQ
 - gdcm::network::DIMSE, [411](#)
- N_GET_RSP
 - gdcm::network::DIMSE, [411](#)
- N_SET_RQ
 - gdcm::network::DIMSE, [411](#)
- N_SET_RSP
 - gdcm::network::DIMSE, [411](#)
- NAction
 - gdcm::NormalizedNetworkFunctions, [815](#)
- Name
 - gdcm::ModuleEntry, [781](#)
- NameField
 - gdcm::CSAElement, [318](#)
 - gdcm::PDBelement, [859](#)
- NativeDICOMModel
 - gdcm::UIDs, [1256](#)
- NCreate
 - gdcm::NormalizedNetworkFunctions, [816](#)
- NDelete
 - gdcm::NormalizedNetworkFunctions, [816](#)
- NeedByteSwap
 - gdcm::Bitmap, [233](#)
 - gdcm::ImageCodec, [616](#)
- NeedOverlayCleanup
 - gdcm::ImageCodec, [616](#)
- NegotiatedType
 - gdcm::TransferSyntax, [1217](#)
- NestedMacroEntries
 - gdcm, [59](#)
- NestedModuleEntries

- gdcmm::NestedModuleEntries, 805
- NEventReport
 - gdcmm::NormalizedNetworkFunctions, 816
- New
 - gdcmm::Anonymizer, 112
 - gdcmm::Cleaner, 272
 - gdcmm::FileChangeTransferSyntax, 509
 - gdcmm::FileStreamer, 546
 - gdcmm::MemberCommand< T >, 758
 - gdcmm::Scanner, 1003
 - gdcmm::Scanner2, 1014
 - gdcmm::SequenceOfFragments, 1043
 - gdcmm::SequenceOfItems, 1052
 - gdcmm::ServiceClassUser, 1066
 - gdcmm::SimpleMemberCommand< T >, 1076
 - gdcmm::StrictScanner, 1121
 - gdcmm::StrictScanner2, 1132
 - vtkGDCMImageReader, 1387
 - vtkGDCMImageReader2, 1402
 - vtkGDCMImageWriter, 1416
 - vtkGDCMMedicalImageProperties, 1423
 - vtkGDCMPolyDataReader, 1426
 - vtkGDCMPolyDataWriter, 1431
 - vtkGDCMTesting, 1436
 - vtkGDCMThreadedImageReader, 1441
 - vtkGDCMThreadedImageReader2, 1445
 - vtkImageColorViewer, 1455
 - vtkImageMapToColors16, 1464
 - vtkImageMapToWindowLevelColors2, 1470
 - vtkImagePlanarComponentsToComponents, 1474
 - vtkImageRGBToYBR, 1476
 - vtkImageYBRToRGB, 1478
 - vtkLookupTable16, 1481
 - vtkRTStructSetProperties, 1488
- NewYorkUniversityMelanomaClinicalCooperativeGroup
 - gdcmm::UIDs, 1254
- NGet
 - gdcmm::NormalizedNetworkFunctions, 816
- NO
 - gdcmm::Surface, 1149
- NO_COMPRESSION
 - vtkGDCMImageWriter, 1415
- NoElementsError
 - gdcmm::Parser, 850
- NoError
 - gdcmm::Parser, 850
- NOMAGIC
 - gdcmm::CSAHeader, 321
- NoMemoryError
 - gdcmm::Parser, 850
- NoObject
 - gdcmm::MediaStorage, 750
- NoOfItemsField
 - gdcmm::CSAElement, 318
- Norm
 - gdcmm::DirectionCosines, 414
- Normal
 - gdcmm::MrProtocol::Slice, 1081
- Normalize
 - gdcmm::DirectionCosines, 414
- NSet
 - gdcmm::NormalizedNetworkFunctions, 816
- NuclearMedicineImageStorage
 - gdcmm::MediaStorage, 748
 - gdcmm::UIDs, 1250
- NuclearMedicineImageStorageRetired
 - gdcmm::MediaStorage, 748
 - gdcmm::UIDs, 1250
- Null0
 - gdcmm::UIDs, 1254
- Null1
 - gdcmm::UIDs, 1254
- NumberOfDimensions
 - gdcmm::Bitmap, 233
 - gdcmm::ImageCodec, 616
- NumberOfIconImages
 - vtkGDCMImageReader, 1397
 - vtkGDCMImageReader2, 1412
- NumberOfOverlays
 - vtkGDCMImageReader, 1397
 - vtkGDCMImageReader2, 1412
- NumberOfSurfaces
 - gdcmm::SurfaceWriter, 1171
- OB
 - gdcmm::VR, 1371
- OB_OW
 - gdcmm::VR, 1371
- Object
 - gdcmm::Object, 821
- ObjectEnd
 - gdcmm::MediaStorage, 750
- ObjectType
 - gdcmm::MediaStorage, 750
- OBLIQUE
 - gdcmm::Orientation, 835
- OD
 - gdcmm::VR, 1371
- OF
 - gdcmm::VR, 1371
- Ofstream
 - gdcmm::Writer, 1503
- OL
 - gdcmm::VR, 1371
- OnlyUUID
 - gdcmm::XMLPrinter, 1508
- OPENSSL
 - gdcmm::CryptoFactory, 306

- OpenSSLCryptoFactory
 - gdcm::OpenSSLCryptoFactory, [824](#)
- OpenSSLCryptographicMessageSyntax
 - gdcm::OpenSSLCryptographicMessageSyntax, [827](#)
- OPENSSLP7
 - gdcm::CryptoFactory, [306](#)
- OpenSSLP7CryptoFactory
 - gdcm::OpenSSLP7CryptoFactory, [830](#)
- OpenSSLP7CryptographicMessageSyntax
 - gdcm::OpenSSLP7CryptographicMessageSyntax, [832](#)
- operator const char *
 - gdcm::ConstCharWrapper, [301](#)
 - gdcm::Filename, [532](#)
 - gdcm::String< TDelimiter, TMaxLength, TPadChar >, [1137](#)
- operator const double *
 - gdcm::DirectionCosines, [414](#)
- operator const std::vector< char > &
 - gdcm::ByteValue, [252](#)
- operator MStype
 - gdcm::MediaStorage, [752](#)
- operator ObjectType *
 - gdcm::SmartPointer< ObjectType >, [1084](#)
- operator PType
 - gdcm::PhotometricInterpretation, [877](#)
- operator ScalarType
 - gdcm::PixelFormat, [883](#)
- operator SwapCode::SwapCodeType
 - gdcm::SwapCode, [1173](#)
- operator TStype
 - gdcm::TransferSyntax, [1220](#)
 - gdcm::UIDs, [1267](#)
- operator TypeType
 - gdcm::Type, [1227](#)
- operator uint32_t
 - gdcm::VL, [1361](#)
- operator UsageType
 - gdcm::Usage, [1344](#)
- operator VMType
 - gdcm::VM, [1368](#)
- operator VRType
 - gdcm::VR, [1375](#)
- operator!=
 - gdcm, [64](#)
 - gdcm::Attribute< Group, Element, TVR, TVM >, [135](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM1 >, [144](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM1_3 >, [150](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM1_8 >, [156](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM1_n >, [163](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM2_2n >, [170](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM2_n >, [176](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM3_3n >, [183](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM3_n >, [189](#)
 - gdcm::CodeString, [287](#)
 - gdcm::PixelFormat, [884](#)
 - gdcm::PrivateTag, [941](#)
 - gdcm::Tag, [1197](#)
- operator<
 - gdcm::Attribute< Group, Element, TVR, TVM >, [135](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM1 >, [144](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM1_3 >, [150](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM1_8 >, [156](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM1_n >, [163](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM2_2n >, [171](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM2_n >, [176](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM3_3n >, [183](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM3_n >, [189](#)
 - gdcm::CSAElement, [316](#)
 - gdcm::CSAHeaderDictEntry, [329](#)
 - gdcm::DataElement, [347](#)
 - gdcm::DPath, [422](#)
 - gdcm::PrivateTag, [942](#)
 - gdcm::Tag, [1197](#)
- operator<<
 - gdcm, [64–72](#)
 - gdcm::BasicOffsetTable, [219](#)
 - gdcm::CodeString, [287](#)
 - gdcm::CommandDataSet, [295](#)
 - gdcm::CSAElement, [318](#)
 - gdcm::CSAHeader, [324](#)
 - gdcm::CSAHeaderDict, [327](#)
 - gdcm::CSAHeaderDictEntry, [330](#)
 - gdcm::DataElement, [352](#)
 - gdcm::DataSet, [370](#)
 - gdcm::Dict, [394](#)
 - gdcm::DictEntry, [402](#)
 - gdcm::Dicts, [409](#)
 - gdcm::Directory, [418](#)
 - gdcm::DPath, [423](#)
 - gdcm::File, [501](#)
 - gdcm::FileMetaInformation, [529](#)

- gdcm::FileSet, 542
- gdcm::Fragment, 563
- gdcm::Global, 567
- gdcm::GroupDict, 570
- gdcm::IOD, 658
- gdcm::IODEntry, 661
- gdcm::IODs, 663
- gdcm::Item, 675
- gdcm::Macro, 738
- gdcm::Macros, 740
- gdcm::MediaStorage, 754
- gdcm::Module, 776
- gdcm::ModuleEntry, 780
- gdcm::Modules, 783
- gdcm::MrProtocol, 794
- gdcm::NestedModuleEntries, 806
- gdcm::Object, 822
- gdcm::Orientation, 837
- gdcm::PDBelement, 858
- gdcm::PDBHeader, 861
- gdcm::PhotometricInterpretation, 878
- gdcm::PixelFormat, 886
- gdcm::Preamble, 914
- gdcm::PrivateDict, 937
- gdcm::PrivateTag, 943
- gdcm::Scanner, 1005
- gdcm::Scanner2, 1015
- gdcm::Sorter, 1093
- gdcm::StrictScanner, 1123
- gdcm::StrictScanner2, 1133
- gdcm::SwapCode, 1173
- gdcm::Table, 1185
- gdcm::Tag, 1201
- gdcm::TransferSyntax, 1221
- gdcm::Type, 1227
- gdcm::UI, 1228
- gdcm::Usage, 1344
- gdcm::Version, 1358
- gdcm::VL, 1363
- gdcm::VM, 1368
- gdcm::VR, 1375
- operator<=
 - gdcm::Tag, 1197
- operator>>
 - gdcm, 72, 73
 - gdcm::Tag, 1201
- operator()
 - gdcm::DataSet, 366
 - gdcm::Scanner2::Itstr, 734
 - gdcm::Scanner::Itstr, 734
 - gdcm::StrictScanner2::Itstr, 735
 - gdcm::StrictScanner::Itstr, 735
- operator++
 - gdcm::VL, 1361
- operator+=
 - gdcm::VL, 1361
- operator->
 - gdcm::SmartPointer< ObjectType >, 1085
- operator=
 - gdcm::AnonymizeEvent, 106
 - gdcm::ASN1, 127
 - gdcm::Base64, 195
 - gdcm::BoxRegion, 241
 - gdcm::ByteSwapFilter, 246
 - gdcm::ByteValue, 252
 - gdcm::Command, 290
 - gdcm::CryptographicMessageSyntax, 310
 - gdcm::CSAEelement, 316
 - gdcm::CSAHeaderDict, 327
 - gdcm::DataElement, 348
 - gdcm::DataEvent, 357
 - gdcm::DataSet, 366
 - gdcm::DataSetEvent, 374
 - gdcm::Defs, 381
 - gdcm::Dict, 393
 - gdcm::Dicts, 409
 - gdcm::Event, 484
 - gdcm::FileMetaInformation, 527
 - gdcm::FileNameEvent, 536
 - gdcm::Global, 567
 - gdcm::MemberCommand< T >, 758
 - gdcm::network::ULAction, 1270
 - gdcm::network::ULConnection, 1314
 - gdcm::network::UserInformation, 1347
 - gdcm::Object, 822
 - gdcm::Overlay, 844
 - gdcm::ParseException, 848
 - gdcm::Preamble, 913
 - gdcm::PrivateTag, 942
 - gdcm::ProgressEvent, 946
 - gdcm::SequenceOfItems, 1052
 - gdcm::ServiceClassUser, 1066
 - gdcm::SHA1, 1071
 - gdcm::SimpleMemberCommand< T >, 1076
 - gdcm::SimpleSubjectWatcher, 1078
 - gdcm::SmartPointer< ObjectType >, 1085
 - gdcm::Table, 1185
 - gdcm::Tag, 1197
- operator==
 - gdcm, 72
 - gdcm::Attribute< Group, Element, TVR, TVM >, 135
 - gdcm::Attribute< Group, Element, TVR, VM::VM1 >, 144
 - gdcm::Attribute< Group, Element, TVR, VM::VM1_3 >, 150
 - gdcm::Attribute< Group, Element, TVR, VM::VM1_8 >, 156

- gdcmm::Attribute< Group, Element, TVR, VM::VM1_n >, [163](#)
- gdcmm::Attribute< Group, Element, TVR, VM::VM2_2n >, [171](#)
- gdcmm::Attribute< Group, Element, TVR, VM::VM2_n >, [176](#)
- gdcmm::Attribute< Group, Element, TVR, VM::VM3_3n >, [183](#)
- gdcmm::Attribute< Group, Element, TVR, VM::VM3_n >, [189](#)
- gdcmm::ByteValue, [252](#)
- gdcmm::CodeString, [287](#)
- gdcmm::CSAElement, [316](#)
- gdcmm::DataElement, [348](#)
- gdcmm::network::AbstractSyntax, [101](#)
- gdcmm::network::PresentationContextRQ, [926](#)
- gdcmm::network::TransferSyntaxSub, [1222](#)
- gdcmm::PDBelement, [858](#)
- gdcmm::PixelFormat, [884](#)
- gdcmm::PresentationContext, [917](#)
- gdcmm::PrivateTag, [942](#)
- gdcmm::SequenceOfFragments, [1043](#)
- gdcmm::SequenceOfItems, [1052](#)
- gdcmm::Tag, [1197](#)
- gdcmm::Value, [1354](#)
- operator[]
 - gdcmm::Attribute< Group, Element, TVR, TVM >, [135](#), [136](#)
 - gdcmm::Attribute< Group, Element, TVR, VM::VM1 >, [144](#)
 - gdcmm::Attribute< Group, Element, TVR, VM::VM1_3 >, [151](#)
 - gdcmm::Attribute< Group, Element, TVR, VM::VM1_8 >, [156](#)
 - gdcmm::Attribute< Group, Element, TVR, VM::VM1_n >, [163](#)
 - gdcmm::Attribute< Group, Element, TVR, VM::VM2_2n >, [171](#)
 - gdcmm::Attribute< Group, Element, TVR, VM::VM2_n >, [177](#)
 - gdcmm::Attribute< Group, Element, TVR, VM::VM3_3n >, [183](#)
 - gdcmm::Attribute< Group, Element, TVR, VM::VM3_n >, [189](#)
 - gdcmm::DataSet, [367](#)
 - gdcmm::Element< TVR, TVM >, [431](#)
 - gdcmm::Element< TVR, VM::VM1_2 >, [437](#)
 - gdcmm::Element< TVR, VM::VM2_2n >, [442](#)
 - gdcmm::Element< TVR, VM::VM3_3n >, [447](#)
 - gdcmm::Element< TVR, VM::VM3_4 >, [452](#)
 - gdcmm::Element< VR::AS, VM::VM5 >, [456](#)
 - gdcmm::Element< VR::OB, VM::VM1 >, [460](#)
 - gdcmm::Element< VR::OW, VM::VM1 >, [465](#)
 - gdcmm::Tag, [1197](#), [1198](#)
- operator*
 - gdcmm::SmartPointer< ObjectType >, [1085](#)
- OphthalmicAxialMeasurementsStorage
 - gdcmm::UIDs, [1254](#)
- OphthalmicOpticalCoherenceTomographyBscanVolumeAnalysisStorage
 - gdcmm::UIDs, [1254](#)
- OphthalmicOpticalCoherenceTomographyEnFacelImageStorage
 - gdcmm::UIDs, [1254](#)
- OphthalmicPhotography16BitImageStorage
 - gdcmm::MediaStorage, [750](#)
 - gdcmm::UIDs, [1251](#)
- OphthalmicPhotography8BitImageStorage
 - gdcmm::MediaStorage, [749](#)
 - gdcmm::UIDs, [1251](#)
- OphthalmicThicknessMapStorage
 - gdcmm::UIDs, [1255](#)
- OphthalmicTomographyImageStorage
 - gdcmm::MediaStorage, [749](#)
 - gdcmm::UIDs, [1251](#)
- OphthalmicVisualFieldStaticPerimetryMeasurementsStorage
 - gdcmm::UIDs, [1255](#)
- OrderFileList
 - gdcmm::SerieHelper, [1058](#)
- Orientation
 - gdcmm::Orientation, [835](#)
- OrientationType
 - gdcmm::Orientation, [835](#)
- Output
 - gdcmm::BitmapToBitmapFilter, [236](#)
- OutputFormat
 - vtkImageMapToColors16, [1468](#)
- OutputTypes
 - gdcmm::DictConverter, [395](#)
- OV
 - gdcmm::VR, [1371](#)
- Overlay
 - gdcmm::Overlay, [840](#), [841](#)
- OverlayImageActor
 - vtkImageColorViewer, [1461](#)
- Overlays
 - gdcmm::Pixmap, [894](#)
- OverlayType
 - gdcmm::Overlay, [840](#)
- OW
 - gdcmm::VR, [1371](#)
- Pack
 - gdcmm::Unpacker12Bits, [1341](#)
- Padding
 - gdcmm::ApplicationEntity, [120](#)
 - gdcmm::PersonName, [870](#)
- PALETTE_COLOR
 - gdcmm::PhotometricInterpretation, [876](#)
- Papyrus3ImplicitVRLittleEndian

- gdcM::UIDs, [1253](#)
- ParametricMapStorage
 - gdcM::UIDs, [1254](#)
- Parent
 - gdcM::Element< TVR, VM::VM1_2 >, [436](#)
 - gdcM::Element< TVR, VM::VM2_2n >, [441](#)
 - gdcM::Element< TVR, VM::VM3_3n >, [446](#)
 - gdcM::Element< TVR, VM::VM3_4 >, [451](#)
- Parse
 - gdcM::Parser, [851](#)
- ParseBuffer
 - gdcM::Parser, [851](#)
- ParseCertificateFile
 - gdcM::CAPICryptographicMessageSyntax, [259](#)
 - gdcM::CryptographicMessageSyntax, [310](#)
 - gdcM::OpenSSLCryptographicMessageSyntax, [827](#)
 - gdcM::OpenSSL7CryptographicMessageSyntax, [833](#)
- ParseDateTime
 - gdcM::System, [1180](#), [1181](#)
- ParseDump
 - gdcM::ASN1, [127](#)
- ParseDumpFile
 - gdcM::ASN1, [127](#)
- ParseException
 - gdcM::ParseException, [848](#)
- ParseKeyFile
 - gdcM::CAPICryptographicMessageSyntax, [259](#)
 - gdcM::CryptographicMessageSyntax, [310](#)
 - gdcM::OpenSSLCryptographicMessageSyntax, [828](#)
 - gdcM::OpenSSL7CryptographicMessageSyntax, [833](#)
- Parser
 - gdcM::Parser, [851](#)
- PassAlphaToOutput
 - vtkImageMapToColors16, [1468](#)
- Patient
 - gdcM::Patient, [853](#)
- PatientRadiationDoseSRStorage
 - gdcM::UIDs, [1255](#)
- PatientRootQueryRetrieveInformationModelFIND
 - gdcM::UIDs, [1251](#)
- PatientRootQueryRetrieveInformationModelGET
 - gdcM::UIDs, [1251](#)
- PatientRootQueryRetrieveInformationModelMOVE
 - gdcM::UIDs, [1251](#)
- PatientStudyOnlyQueryRetrieveInformationModelFINDRetired
 - gdcM::UIDs, [1251](#)
- PatientStudyOnlyQueryRetrieveInformationModelGETRetired
 - gdcM::UIDs, [1252](#)
- PatientStudyOnlyQueryRetrieveInformationModelMOVERetired
 - gdcM::UIDs, [1252](#)
- PDataTFPDU
 - gdcM::network::PDataTFPDU, [854](#)
- PDBElement
 - gdcM::PDBElement, [857](#)
- PDBHeader
 - gdcM::PDBHeader, [860](#)
- PDF
 - gdcM::MediaStorage, [750](#)
- PDFCodec
 - gdcM::PDFCodec, [863](#)
- PerformAction
 - gdcM::network::ULAction, [1270](#)
 - gdcM::network::ULActionAA1, [1272](#)
 - gdcM::network::ULActionAA2, [1273](#)
 - gdcM::network::ULActionAA3, [1274](#)
 - gdcM::network::ULActionAA4, [1276](#)
 - gdcM::network::ULActionAA5, [1277](#)
 - gdcM::network::ULActionAA6, [1278](#)
 - gdcM::network::ULActionAA7, [1280](#)
 - gdcM::network::ULActionAA8, [1281](#)
 - gdcM::network::ULActionAE1, [1282](#)
 - gdcM::network::ULActionAE2, [1284](#)
 - gdcM::network::ULActionAE3, [1285](#)
 - gdcM::network::ULActionAE4, [1286](#)
 - gdcM::network::ULActionAE5, [1288](#)
 - gdcM::network::ULActionAE6, [1289](#)
 - gdcM::network::ULActionAE7, [1290](#)
 - gdcM::network::ULActionAE8, [1292](#)
 - gdcM::network::ULActionAR1, [1293](#)
 - gdcM::network::ULActionAR10, [1294](#)
 - gdcM::network::ULActionAR2, [1296](#)
 - gdcM::network::ULActionAR3, [1297](#)
 - gdcM::network::ULActionAR4, [1298](#)
 - gdcM::network::ULActionAR5, [1300](#)
 - gdcM::network::ULActionAR6, [1301](#)
 - gdcM::network::ULActionAR7, [1302](#)
 - gdcM::network::ULActionAR8, [1304](#)
 - gdcM::network::ULActionAR9, [1305](#)
 - gdcM::network::ULActionDT1, [1306](#)
 - gdcM::network::ULActionDT2, [1308](#)
- PerformedImagingAgentAdministrationSRStorage
 - gdcM::UIDs, [1255](#)
- PET20StepColorPaletteSOPInstance
 - gdcM::UIDs, [1253](#)
- PETColorPaletteSOPInstance
 - gdcM::UIDs, [1253](#)
- PETImageStorage
 - gdcM::MediaStorage, [748](#)
- gdcM::Bitmap, [233](#)
- gdcM::ImageCodec, [616](#)
- PGXCodec
 - gdcM::PGXCodec, [873](#)
- PHILIPS
 - gdcM::Dicts, [407](#)
- Philips3D

- gdcm::MediaStorage, [749](#)
- PhilipsPrivateMRSyntheticImageStorage
 - gdcm::MediaStorage, [749](#)
- PhotometricInterpretation
 - gdcm::PhotometricInterpretation, [876](#)
- PI
 - gdcm::Bitmap, [233](#)
 - gdcm::ImageCodec, [617](#)
- PI_END
 - gdcm::PhotometricInterpretation, [876](#)
- PIType
 - gdcm::PhotometricInterpretation, [876](#)
- PixelData
 - gdcm::Bitmap, [234](#)
 - gdcm::PixmapReader, [898](#)
 - gdcm::PixmapWriter, [906](#)
- PixelFormat
 - gdcm::PixelFormat, [881](#)
- Pixmap
 - gdcm::Pixmap, [891](#)
- PixmapReader
 - gdcm::Bitmap, [232](#)
 - gdcm::PixmapReader, [897](#)
- PixmapToPixmapFilter
 - gdcm::PixmapToPixmapFilter, [900](#)
- PixmapWriter
 - gdcm::PixmapWriter, [904](#)
- PlanarConfiguration
 - gdcm::Bitmap, [234](#)
 - gdcm::ImageCodec, [617](#)
 - vtkGDCMImageReader, [1397](#)
 - vtkGDCMImageReader2, [1412](#)
- PlannedImagingAgentAdministrationSRStorage
 - gdcm::UIDs, [1255](#)
- PMS
 - gdcm::EquipmentManufacturer, [481](#)
- PN
 - gdcm::VR, [1371](#)
- PNComp
 - gdcm, [59](#)
- PNMCodec
 - gdcm::PNMCodec, [909](#)
- pointer
 - gdcm::CodeString, [285](#)
 - gdcm::LO, [724](#)
 - gdcm::String< TDelimiter, TMaxLength, TPadChar >, [1136](#)
- POINTS
 - gdcm::Surface, [1150](#)
- Position
 - gdcm::MrProtocol::Slice, [1081](#)
- PositronEmissionTomographyImageStorage
 - gdcm::UIDs, [1251](#)
- Preamble
 - gdcm::Preamble, [912](#)
- PrepareWrite
 - gdcm::PixmapWriter, [905](#)
 - gdcm::SegmentWriter, [1036](#)
 - gdcm::SurfaceWriter, [1171](#)
- PrepareWritePointMacro
 - gdcm::SurfaceWriter, [1171](#)
- Prepend
 - gdcm::Global, [567](#)
- PresentationContext
 - gdcm::PresentationContext, [916](#)
- PresentationContextAC
 - gdcm::network::PresentationContextAC, [919](#)
- PresentationContextArrayType
 - gdcm::network::AAssociateRQPDU, [96](#)
 - gdcm::PresentationContextGenerator, [922](#)
- PresentationContextGenerator
 - gdcm::PresentationContextGenerator, [922](#)
- PresentationContextRQ
 - gdcm::network::PresentationContextRQ, [925](#)
- PresentationDataValue
 - gdcm::network::PresentationDataValue, [928](#)
- PresentationLUTSOPClass
 - gdcm::UIDs, [1249](#)
- Preserve
 - gdcm::Cleaner, [273](#)
- PrettyPrintOff
 - gdcm::JSON, [717](#)
- PrettyPrintOn
 - gdcm::JSON, [718](#)
- PrimitiveData
 - gdcm::MeshPrimitive, [765](#)
- PrimitivesData
 - gdcm::MeshPrimitive, [762](#)
- PrimitiveType
 - gdcm::MeshPrimitive, [765](#)
- Print
 - gdcm::ApplicationEntity, [119](#)
 - gdcm::Attribute< Group, Element, TVR, TVM >, [136](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM1 >, [144](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM1_3 >, [151](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM1_8 >, [156](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM1_n >, [164](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM2_2n >, [171](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM2_n >, [177](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM3_3n >, [183](#)

- gdcm::Attribute< Group, Element, TVR, VM::VM3_n
>, 189
- gdcm::BaseQuery, 205
- gdcm::Bitmap, 227
- gdcm::BoxRegion, 241
- gdcm::ByteValue, 252
- gdcm::CSAHeader, 324
- gdcm::Curve, 338
- gdcm::DataSet, 367
- gdcm::DictPrinter, 405
- gdcm::DirectionCosines, 414
- gdcm::Directory, 418
- gdcm::DPath, 423
- gdcm::Element< TVR, TVM >, 431
- gdcm::Element< TVR, VM::VM1_2 >, 437
- gdcm::Element< TVR, VM::VM2_2n >, 442
- gdcm::Element< TVR, VM::VM3_3n >, 447
- gdcm::Element< TVR, VM::VM3_4 >, 452
- gdcm::Element< VR::AS, VM::VM5 >, 456
- gdcm::Element< VR::OB, VM::VM1 >, 461
- gdcm::Element< VR::OW, VM::VM1 >, 466
- gdcm::Event, 484
- gdcm::Image, 584
- gdcm::LookupTable, 732
- gdcm::MEC_MR3, 744
- gdcm::MrProtocol, 793
- gdcm::network::AAAbortPDU, 86
- gdcm::network::AAAssociateACPDU, 90
- gdcm::network::AAAssociateRJPDU, 93
- gdcm::network::AAAssociateRQPDU, 98
- gdcm::network::AbstractSyntax, 101
- gdcm::network::ApplicationContext, 117
- gdcm::network::AReleaseRPPDU, 121
- gdcm::network::AReleaseRQPDU, 124
- gdcm::network::AsynchronousOperationsWindowSub,
129
- gdcm::network::BasePDU, 201
- gdcm::network::ImplementationClassUIDSub, 647
- gdcm::network::ImplementationVersionNameSub,
649
- gdcm::network::MaximumLengthSub, 741
- gdcm::network::PDataTFPDU, 855
- gdcm::network::PresentationContextAC, 919
- gdcm::network::PresentationContextRQ, 926
- gdcm::network::PresentationDataValue, 929
- gdcm::network::RoleSelectionSub, 995
- gdcm::network::ServiceClassApplicationInformation,
1061
- gdcm::network::SOPClassExtendedNegociationSub,
1086
- gdcm::network::TransferSyntaxSub, 1222
- gdcm::network::UserInformation, 1348
- gdcm::Object, 822
- gdcm::Orientation, 836
- gdcm::Overlay, 844
- gdcm::PDBHeader, 861
- gdcm::PersonName, 869
- gdcm::PixelFormat, 884
- gdcm::Pixmap, 892
- gdcm::Preamble, 913
- gdcm::PresentationContext, 917
- gdcm::Printer, 933
- gdcm::Region, 982
- gdcm::Scanner, 1004
- gdcm::Scanner2, 1014
- gdcm::SegmentedPaletteColorLookupTable, 1028
- gdcm::SequenceOfFragments, 1043
- gdcm::SequenceOfItems, 1052
- gdcm::Sorter, 1091
- gdcm::StrictScanner, 1122
- gdcm::StrictScanner2, 1132
- gdcm::TagPath, 1203
- gdcm::Testing, 1210
- gdcm::Version, 1358
- gdcm::XMLPrinter, 1508
- PrintASCII
 - gdcm::ByteValue, 253
- PrintASCIIXML
 - gdcm::ByteValue, 253
- PrintAsContinuousString
 - gdcm::Tag, 1198
- PrintAsContinuousUpperCaseString
 - gdcm::Tag, 1198
- PrintAsPipeSeparatedString
 - gdcm::Tag, 1198
- PrintDataElement
 - gdcm::Printer, 933
 - gdcm::XMLPrinter, 1509
- PrintDataElement2
 - gdcm::DictPrinter, 405
- PrintDataSet
 - gdcm::Printer, 934
 - gdcm::XMLPrinter, 1509
- PrintDataSet2
 - gdcm::DictPrinter, 405
- Printer
 - gdcm::Printer, 933
- PrinterConfigurationRetrievalSOPClass
 - gdcm::UIDs, 1249
- PrinterConfigurationRetrievalSOPInstance
 - gdcm::UIDs, 1249
- PrinterSOPClass
 - gdcm::UIDs, 1249
- PrinterSOPInstance
 - gdcm::UIDs, 1249
- PrintGroupLength
 - gdcm::ByteValue, 253
- PrintHex

- gdcmm::ByteValue, 253
- PrintHexXML
 - gdcmm::ByteValue, 253
- PrintJobSOPClass
 - gdcmm::UIDs, 1249
- PrintPNXML
 - gdcmm::ByteValue, 253
- PrintQueueManagementSOPClassRetired
 - gdcmm::UIDs, 1249
- PrintQueueSOPInstanceRetired
 - gdcmm::UIDs, 1249
- PrintSelf
 - vtkGDCMImageReader, 1388
 - vtkGDCMImageReader2, 1402
 - vtkGDCMImageWriter, 1416
 - vtkGDCMMedicalImageProperties, 1423
 - vtkGDCMPolyDataReader, 1426
 - vtkGDCMPolyDataWriter, 1431
 - vtkGDCMTesting, 1437
 - vtkGDCMThreadedImageReader, 1441
 - vtkGDCMThreadedImageReader2, 1445
 - vtkImageColorViewer, 1455
 - vtkImageMapToColors16, 1464
 - vtkImageMapToWindowLevelColors2, 1470
 - vtkImagePlanarComponentsToComponents, 1474
 - vtkImageRGBToYBR, 1476
 - vtkImageYBRToRGB, 1478
 - vtkLookupTable16, 1481
 - vtkRTStructSetProperties, 1488
- PrintSQ
 - gdcmm::Printer, 934
 - gdcmm::XMLPrinter, 1509
- PrintStyle
 - gdcmm::Printer, 935
 - gdcmm::XMLPrinter, 1510
- PrintStyles
 - gdcmm::Printer, 932
 - gdcmm::XMLPrinter, 1508
- PrintTable
 - gdcmm::network::ULTransitionTable, 1330
 - gdcmm::Scanner, 1004
 - gdcmm::Scanner2, 1014
 - gdcmm::StrictScanner, 1122
 - gdcmm::StrictScanner2, 1132
- PrintXML
 - gdcmm::PrivateDict, 937
- PrivateBegin
 - gdcmm::Scanner2, 1014
 - gdcmm::StrictScanner2, 1132
- PrivateConstIterator
 - gdcmm::Scanner2, 1009
 - gdcmm::StrictScanner2, 1127
- PrivateDict
 - gdcmm::PrivateDict, 936
- PrivateEnd
 - gdcmm::Scanner2, 1015
 - gdcmm::StrictScanner2, 1133
- PrivateMappingType
 - gdcmm::Scanner2, 1009
 - gdcmm::StrictScanner2, 1127
- PrivateTag
 - gdcmm::PrivateTag, 941
- PrivateTagToValue
 - gdcmm::Scanner2, 1009
 - gdcmm::StrictScanner2, 1127
- PrivateTagToValueValueType
 - gdcmm::Scanner2, 1009
 - gdcmm::StrictScanner2, 1127
- ProceduralEventLoggingSOPClass
 - gdcmm::UIDs, 1248
- ProceduralEventLoggingSOPInstance
 - gdcmm::UIDs, 1248
- ProcedureLogStorage
 - gdcmm::UIDs, 1251
- Process
 - gdcmm::Parser, 852
- ProcessDataSet
 - gdcmm::FileExplicitFilter, 519
- ProcessPrivateTag
 - gdcmm::Scanner2, 1015
 - gdcmm::StrictScanner2, 1133
- ProcessPublicTag
 - gdcmm::Scanner, 1004
 - gdcmm::Scanner2, 1015
 - gdcmm::StrictScanner, 1122
 - gdcmm::StrictScanner2, 1133
- ProcessRequest
 - vtkGDCMImageReader2, 1403
- ProduceCharacterSetDataElement
 - gdcmm::QueryFactory, 956
- ProduceQuery
 - gdcmm::QueryFactory, 957
- ProductCharacteristicsQuerySOPClass
 - gdcmm::UIDs, 1252
- ProgressEvent
 - gdcmm::ProgressEvent, 945
- PropertyCategory
 - gdcmm::Segment, 1023
- PropertyType
 - gdcmm::Segment, 1023
- PropertyTypeModifiers
 - gdcmm::Segment, 1023
- ProtocolApprovalInformationModelFIND
 - gdcmm::UIDs, 1255
- ProtocolApprovalInformationModelGET
 - gdcmm::UIDs, 1255
- ProtocolApprovalInformationModelMOVE
 - gdcmm::UIDs, 1255

- ProtocolApprovalStorage
 - gdcm::UIDs, [1255](#)
- PseudoColorSoftcopyPresentationStateStorageSOPClass
 - gdcm::UIDs, [1250](#)
- PubChemCompoundCID
 - gdcm::UIDs, [1253](#)
- PublicConstIterator
 - gdcm::Scanner2, [1009](#)
 - gdcm::StrictScanner2, [1127](#)
- PublicMappingType
 - gdcm::Scanner2, [1009](#)
 - gdcm::StrictScanner2, [1127](#)
- PublicTagToValue
 - gdcm::Scanner2, [1009](#)
 - gdcm::StrictScanner2, [1127](#)
- PublicTagToValueValueType
 - gdcm::Scanner2, [1009](#)
 - gdcm::StrictScanner2, [1127](#)
- PullPrintRequestSOPClassRetired
 - gdcm::UIDs, [1249](#)
- PullStoredPrintManagementMetaSOPClassRetired
 - gdcm::UIDs, [1249](#)
- Push
 - gdcm::TagPath, [1203](#)
- PushBackFile
 - vtkGDCMMedicalImageProperties, [1423](#)
- PVRGCodec
 - gdcm::PVRGCodec, [950](#)
- PythonFilter
 - gdcm::PythonFilter, [952](#)
- Quality
 - gdcm::JPEGCodec, [709](#)
- QueryFactory
 - gdcm::BaseQuery, [206](#)
 - gdcm::BaseRootQuery, [211](#)
 - gdcm::FindPatientRootQuery, [554](#)
 - gdcm::FindStudyRootQuery, [558](#)
 - gdcm::ModalityPerformedProcedureStepCreateQuery, [768](#)
 - gdcm::ModalityPerformedProcedureStepSetQuery, [772](#)
 - gdcm::MovePatientRootQuery, [787](#)
 - gdcm::MoveStudyRootQuery, [791](#)
 - gdcm::WLMFindQuery, [1498](#)
- RadiomicsOntology
 - gdcm::UIDs, [1254](#)
- RadiopharmaceuticalRadiationDoseSRStorage
 - gdcm::UIDs, [1255](#)
- RAWCodec
 - gdcm::RAWCodec, [970](#)
- RawDataStorage
 - gdcm::MediaStorage, [748](#)
 - gdcm::UIDs, [1250](#)
- Read
 - gdcm::BasicOffsetTable, [219](#)
 - gdcm::ByteValue, [253](#), [254](#)
 - gdcm::CommandDataSet, [294](#)
 - gdcm::CP246ExplicitDataElement, [304](#)
 - gdcm::DataElement, [348](#)
 - gdcm::DataSet, [367](#)
 - gdcm::Element< TVR, TVM >, [431](#)
 - gdcm::Element< TVR, VM::VM1_2 >, [437](#)
 - gdcm::Element< TVR, VM::VM2_2n >, [442](#)
 - gdcm::Element< TVR, VM::VM3_3n >, [447](#)
 - gdcm::Element< TVR, VM::VM3_4 >, [452](#)
 - gdcm::Element< VR::AS, VM::VM5 >, [456](#)
 - gdcm::Element< VR::OB, VM::VM1 >, [461](#)
 - gdcm::Element< VR::OW, VM::VM1 >, [466](#)
 - gdcm::EncodingImplementation< VR::VRASCII >, [475](#)
 - gdcm::EncodingImplementation< VR::VRBINARY >, [477](#)
 - gdcm::ExplicitDataElement, [491](#)
 - gdcm::ExplicitImplicitDataElement, [495](#)
 - gdcm::File, [500](#)
 - gdcm::FileMetaInformation, [528](#)
 - gdcm::Fragment, [562](#)
 - gdcm::ImageReader, [633](#)
 - gdcm::ImageRegionReader, [638](#)
 - gdcm::ImplicitDataElement, [653](#)
 - gdcm::Item, [674](#)
 - gdcm::network::AAabortPDU, [86](#)
 - gdcm::network::AAssociateACPDU, [90](#)
 - gdcm::network::AAssociateRJPDU, [93](#)
 - gdcm::network::AAssociateRQPDU, [98](#)
 - gdcm::network::AbstractSyntax, [102](#)
 - gdcm::network::ApplicationContext, [117](#)
 - gdcm::network::AReleaseRPPDU, [122](#)
 - gdcm::network::AReleaseRQPDU, [124](#)
 - gdcm::network::AsynchronousOperationsWindowSub, [129](#)
 - gdcm::network::BasePDU, [201](#)
 - gdcm::network::ImplementationClassUIDSub, [647](#)
 - gdcm::network::ImplementationVersionNameSub, [649](#)
 - gdcm::network::MaximumLengthSub, [741](#)
 - gdcm::network::PDataTFPDU, [855](#)
 - gdcm::network::PresentationContextAC, [920](#)
 - gdcm::network::PresentationContextRQ, [926](#)
 - gdcm::network::PresentationDataValue, [929](#)
 - gdcm::network::RoleSelectionSub, [995](#)
 - gdcm::network::ServiceClassApplicationInformation, [1061](#)
 - gdcm::network::SOPClassExtendedNegotiationSub, [1086](#)
 - gdcm::network::TransferSyntaxSub, [1222](#)
 - gdcm::network::UserInformation, [1348](#)

- gdcm::PGXCodec, [874](#)
- gdcm::PixmapReader, [897](#)
- gdcm::PNMCodec, [910](#)
- gdcm::Preamble, [913](#)
- gdcm::Reader, [976](#)
- gdcm::SegmentReader, [1031](#)
- gdcm::SequenceOfFragments, [1044](#)
- gdcm::SequenceOfItems, [1052](#)
- gdcm::StreamImageReader, [1106](#)
- gdcm::SurfaceReader, [1165](#)
- gdcm::TableReader, [1189](#)
- gdcm::Tag, [1198](#)
- gdcm::UNExplicitDataElement, [1336](#)
- gdcm::UNExplicitImplicitDataElement, [1340](#)
- gdcm::ValueIO< TDE, TSwap, TType >, [1355](#)
- gdcm::VL, [1362](#)
- gdcm::VR, [1375](#)
- gdcm::VR16ExplicitDataElement, [1378](#)
- gdcm::VRVLSIZE< 0 >, [1381](#)
- gdcm::VRVLSIZE< 1 >, [1383](#)
- Read16
 - gdcm::VL, [1362](#)
- ReadACRNEMAIImage
 - gdcm::ImageReader, [633](#)
 - gdcm::PixmapReader, [897](#)
- ReadBacktrack
 - gdcm::Fragment, [562](#)
- ReadCompat
 - gdcm::FileMetaInformation, [528](#)
- ReadCompatInternal
 - gdcm::FileMetaInformation, [528](#)
- ReadComputeLength
 - gdcm::EncodingImplementation< VR::VRASCII >, [475](#)
 - gdcm::EncodingImplementation< VR::VRBINARY >, [477](#)
- ReadDataSet
 - gdcm::Reader, [976](#)
- Reader
 - gdcm::Reader, [975](#)
- ReadFiles
 - vtkGDCMThreadedImageReader, [1441](#)
- ReadFromCommaSeparatedString
 - gdcm::PrivateTag, [942](#)
 - gdcm::Tag, [1199](#)
- ReadFromContinuousString
 - gdcm::Tag, [1199](#)
- ReadFromPipeSeparatedString
 - gdcm::Tag, [1199](#)
- ReadImage
 - gdcm::ImageReader, [633](#)
 - gdcm::PixmapReader, [898](#)
- ReadImageInformation
 - gdcm::StreamImageReader, [1106](#)
- ReadImageInternal
 - gdcm::PixmapReader, [898](#)
- ReadInformation
 - gdcm::ImageRegionReader, [638](#)
- ReadInto
 - gdcm::network::PDataTFPDU, [855](#)
 - gdcm::network::PresentationDataValue, [929](#)
- ReadIntoBuffer
 - gdcm::ImageRegionReader, [638](#)
- README.txt, [1515](#)
- ReadMetaInformation
 - gdcm::Reader, [976](#)
- ReadNested
 - gdcm::DataSet, [367](#)
- ReadNoSwap
 - gdcm::EncodingImplementation< VR::VRASCII >, [475](#)
 - gdcm::EncodingImplementation< VR::VRBINARY >, [477](#)
- ReadOrSkip
 - gdcm::DataElement, [348](#)
- ReadPointMacro
 - gdcm::SurfaceReader, [1166](#)
- ReadPreamble
 - gdcm::Reader, [976](#)
- ReadPreValue
 - gdcm::CP246ExplicitDataElement, [305](#)
 - gdcm::DataElement, [348](#)
 - gdcm::ExplicitDataElement, [491](#)
 - gdcm::ExplicitImplicitDataElement, [495](#)
 - gdcm::Fragment, [562](#)
 - gdcm::ImplicitDataElement, [653](#)
 - gdcm::SequenceOfFragments, [1044](#)
 - gdcm::UNExplicitDataElement, [1336](#)
 - gdcm::UNExplicitImplicitDataElement, [1340](#)
 - gdcm::VR16ExplicitDataElement, [1379](#)
- ReadSegment
 - gdcm::SegmentReader, [1032](#)
- ReadSegments
 - gdcm::SegmentReader, [1032](#)
- ReadSelectedPrivateTags
 - gdcm::DataSet, [367](#)
 - gdcm::Reader, [977](#)
- ReadSelectedPrivateTagsWithLength
 - gdcm::DataSet, [367](#)
- ReadSelectedTags
 - gdcm::DataSet, [368](#)
 - gdcm::Reader, [977](#)
- ReadSelectedTagsWithLength
 - gdcm::DataSet, [368](#)
- ReadSurface
 - gdcm::SurfaceReader, [1166](#)
- ReadSurfaces
 - gdcm::SurfaceReader, [1166](#)

- Readuint16
 - gdcm::DictConverter, [397](#)
- ReadUpToTag
 - gdcm::DataSet, [368](#)
 - gdcm::Reader, [977](#)
- ReadUpToTagWithLength
 - gdcm::DataSet, [368](#)
- ReadValue
 - gdcm::CP246ExplicitDataElement, [305](#)
 - gdcm::DataElement, [349](#)
 - gdcm::ExplicitDataElement, [492](#)
 - gdcm::ExplicitImplicitDataElement, [496](#)
 - gdcm::Fragment, [563](#)
 - gdcm::ImplicitDataElement, [653](#)
 - gdcm::SequenceOfFragments, [1044](#)
 - gdcm::UNExplicitDataElement, [1336](#)
 - gdcm::UNExplicitImplicitDataElement, [1340](#)
 - gdcm::VR16ExplicitDataElement, [1379](#)
- ReadValueWithLength
 - gdcm::DataElement, [349](#)
 - gdcm::ImplicitDataElement, [653](#)
- ReadVM
 - gdcm::DictConverter, [397](#)
- ReadVR
 - gdcm::DictConverter, [397](#)
- ReadWithLength
 - gdcm::CP246ExplicitDataElement, [305](#)
 - gdcm::DataElement, [349](#)
 - gdcm::DataSet, [368](#)
 - gdcm::ExplicitDataElement, [492](#)
 - gdcm::ExplicitImplicitDataElement, [496](#)
 - gdcm::ImplicitDataElement, [653](#)
 - gdcm::UNExplicitDataElement, [1336](#)
 - gdcm::VR16ExplicitDataElement, [1379](#)
- RealWorldValueIntercept
 - gdcm::RealWorldValueMappingContent, [980](#)
- RealWorldValueMappingStorage
 - gdcm::UIDs, [1250](#)
- RealWorldValueSlope
 - gdcm::RealWorldValueMappingContent, [980](#)
- RecommendedDisplayCIELabToRGB
 - gdcm::SurfaceHelper, [1160](#)
- RecurseDataSet
 - gdcm::Anonymizer, [112](#)
- RED
 - gdcm::LookupTable, [728](#)
- red
 - gdcm::terminal, [81](#)
- reference
 - gdcm::CodeString, [285](#)
 - gdcm::LO, [724](#)
 - gdcm::String< TDelimiter, TMaxLength, TPadChar
>, [1136](#)
- ReferencedColorPrintManagementMetaSOPClassRetired
 - gdcm::UIDs, [1249](#)
- ReferencedGrayscalePrintManagementMetaSOPClassRetired
 - gdcm::UIDs, [1249](#)
- ReferencedImageBoxSOPClassRetired
 - gdcm::UIDs, [1249](#)
- ReferenceFrameOfReferenceUID
 - vtkRTStructSetProperties, [1492](#)
- ReferenceSeriesInstanceUID
 - vtkRTStructSetProperties, [1492](#)
- Region
 - gdcm::Region, [981](#)
- Register
 - gdcm::Object, [822](#)
- Remove
 - gdcm::Anonymizer, [112](#)
 - gdcm::Cleaner, [273](#)
 - gdcm::DataSet, [369](#)
 - gdcm::FileAnonymizer, [504](#)
 - gdcm::Preamble, [914](#)
- RemoveAllGroupLength
 - gdcm::Cleaner, [273](#)
- RemoveAllIllegal
 - gdcm::Cleaner, [274](#)
- RemoveAllMissingPrivateCreator
 - gdcm::Cleaner, [274](#)
- RemoveAllObservers
 - gdcm::Subject, [1146](#)
- RemoveDictEntry
 - gdcm::PrivateDict, [937](#)
- RemoveFile
 - gdcm::System, [1181](#)
- RemoveGroupLength
 - gdcm::Anonymizer, [112](#)
- RemoveItemByIndex
 - gdcm::SequenceOfItems, [1053](#)
- RemoveMissingPrivateCreator
 - gdcm::Cleaner, [274](#)
- RemoveObserver
 - gdcm::Subject, [1146](#)
- RemoveOverlay
 - gdcm::Pixmap, [892](#)
- RemovePrivateTags
 - gdcm::Anonymizer, [113](#)
- RemoveRetired
 - gdcm::Anonymizer, [113](#)
- Render
 - vtkImageColorViewer, [1455](#)
- Renderer
 - vtkImageColorViewer, [1461](#)
- RenderWindow
 - vtkImageColorViewer, [1461](#)
- Replace
 - gdcm::Anonymizer, [113](#), [114](#)
 - gdcm::CommandDataSet, [294](#)

- gdcm::DataSet, [369](#)
- gdcm::FileAnonymizer, [505](#)
- gdcm::FileMetaInformation, [528](#)
- ReplaceCodeMeaning
 - gdcm::Cleaner, [274](#)
- ReplaceEmpty
 - gdcm::DataSet, [369](#)
- RequestData
 - vtkGDCMImageReader2, [1403](#)
 - vtkGDCMPolyDataReader, [1427](#)
 - vtkImageMapToColors16, [1464](#)
 - vtkImageMapToWindowLevelColors2, [1470](#)
 - vtkImagePlanarComponentsToComponents, [1474](#)
- RequestData_HemodynamicWaveformStorage
 - vtkGDCMPolyDataReader, [1427](#)
- RequestData_RTStructureSetStorage
 - vtkGDCMPolyDataReader, [1427](#)
- RequestDataCompat
 - vtkGDCMImageReader, [1388](#)
 - vtkGDCMImageReader2, [1403](#)
 - vtkGDCMThreadedImageReader, [1441](#)
- RequestInformation
 - vtkGDCMImageReader2, [1403](#)
 - vtkGDCMPolyDataReader, [1427](#)
 - vtkGDCMThreadedImageReader2, [1445](#)
 - vtkImageMapToColors16, [1465](#)
 - vtkImageMapToWindowLevelColors2, [1470](#)
- RequestInformation_HemodynamicWaveformStorage
 - vtkGDCMPolyDataReader, [1427](#)
- RequestInformation_RTStructureSetStorage
 - vtkGDCMPolyDataReader, [1427](#)
- RequestInformationCompat
 - vtkGDCMImageReader, [1388](#)
 - vtkGDCMImageReader2, [1403](#)
- RequestPaddedCompositePixelCode
 - gdcm::ImageCodec, [617](#)
- RequestPlanarConfiguration
 - gdcm::ImageCodec, [617](#)
- Rescale
 - gdcm::Rescaler, [985](#)
- RescaleFunctionIntoBestFit
 - gdcm::Rescaler, [985](#)
- Rescaler
 - gdcm::Rescaler, [984](#)
- ReserveDataElement
 - gdcm::FileStreamer, [546](#)
- ReserveGroupDataElement
 - gdcm::FileStreamer, [546](#)
- reset
 - gdcm::terminal, [81](#)
- ResetHandledDataSet
 - gdcm::network::ULConnectionCallback, [1317](#)
- RespiratoryWaveformStorage
 - gdcm::UIDs, [1254](#)
- RetrieveSOPInstanceUIDFromIndex
 - gdcm::DirectoryHelper, [420](#)
- RetrieveSOPInstanceUIDFromZPosition
 - gdcm::DirectoryHelper, [421](#)
- reverse
 - gdcm::terminal, [81](#)
- reverse_iterator
 - gdcm::CodeString, [285](#)
 - gdcm::LO, [724](#)
 - gdcm::String< TDelimiter, TMaxLength, TPadChar >, [1136](#)
- RFC2557MIMEencapsulation
 - gdcm::UIDs, [1248](#)
- RGB
 - gdcm::PhotometricInterpretation, [876](#)
- RGB2YBR
 - gdcm::ImageChangePhotometricInterpretation, [593](#)
- RGBPixelsToRGBPlanes
 - gdcm::ImageChangePlanarConfiguration, [597](#)
- RGBPlanesToRGBPixels
 - gdcm::ImageChangePlanarConfiguration, [597](#)
- RGBToRecommendedDisplayCIELab
 - gdcm::SurfaceHelper, [1161](#)
- RGBToRecommendedDisplayGrayscale
 - gdcm::SurfaceHelper, [1161](#)
- RLE_COMPRESSION
 - vtkGDCMImageWriter, [1415](#)
- RLECodec
 - gdcm::RLECodec, [990](#)
- RLELossless
 - gdcm::TransferSyntax, [1218](#)
 - gdcm::UIDs, [1248](#)
- ROI
 - gdcm::Overlay, [840](#)
- RoleSelectionSub
 - gdcm::network::RoleSelectionSub, [994](#)
- Round
 - gdcm, [73](#)
- roundat
 - gdcm, [73](#)
- RTBeamsDeliveryInstructionStorage
 - gdcm::UIDs, [1256](#)
- RTBeamsDeliveryInstructionStorageSupplement74FrozenDraft
 - gdcm::UIDs, [1252](#)
- RTBeamsTreatmentRecordStorage
 - gdcm::UIDs, [1251](#)
- RTBrachyApplicationSetupDeliveryInstructionStorage
 - gdcm::UIDs, [1256](#)
- RTBrachyTreatmentRecordStorage
 - gdcm::UIDs, [1251](#)
- RTConventionalMachineVerification
 - gdcm::UIDs, [1256](#)
- RTConventionalMachineVerificationSupplement74FrozenDraft
 - gdcm::UIDs, [1252](#)

- RTDoseStorage
 - gdcm::MediaStorage, [749](#)
 - gdcm::UIDs, [1251](#)
- RTImageStorage
 - gdcm::MediaStorage, [748](#)
 - gdcm::UIDs, [1251](#)
- RTIonBeamsTreatmentRecordStorage
 - gdcm::MediaStorage, [749](#)
 - gdcm::UIDs, [1251](#)
- RTIonMachineVerification
 - gdcm::UIDs, [1256](#)
- RTIonMachineVerificationSupplement74FrozenDraft
 - gdcm::UIDs, [1252](#)
- RTIonPlanStorage
 - gdcm::MediaStorage, [749](#)
 - gdcm::UIDs, [1251](#)
- RTPhysicianIntentStorage
 - gdcm::UIDs, [1255](#)
- RTPlanStorage
 - gdcm::MediaStorage, [749](#)
 - gdcm::UIDs, [1251](#)
- RTSegmentAnnotationStorage
 - gdcm::UIDs, [1255](#)
- RTStructSetProperties
 - vtkGDCMPolyDataReader, [1429](#)
 - vtkGDCMPolyDataWriter, [1433](#)
- RTStructureSetStorage
 - gdcm::MediaStorage, [749](#)
 - gdcm::UIDs, [1251](#)
- RTTreatmentSummaryRecordStorage
 - gdcm::MediaStorage, [749](#)
 - gdcm::UIDs, [1251](#)
- Rule
 - gdcm::SerieHelper, [1056](#)
- RunEventLoop
 - gdcm::network::ULConnectionManager, [1324](#)
- RunMoveEventLoop
 - gdcm::network::ULConnectionManager, [1324](#)
- SAGITTAL
 - gdcm::Orientation, [835](#)
- SAMSUNG
 - gdcm::EquipmentManufacturer, [481](#)
- ScalarType
 - gdcm::PixelFormat, [880](#)
- Scale
 - vtkGDCMImageReader, [1398](#)
 - vtkGDCMImageReader2, [1412](#)
- Scan
 - gdcm::Scanner, [1004](#)
 - gdcm::Scanner2, [1015](#)
 - gdcm::StrictScanner, [1122](#)
 - gdcm::StrictScanner2, [1133](#)
- Scanner
 - gdcm::Scanner, [1000](#)
- Scanner2
 - gdcm::Scanner2, [1010](#)
- Scrub
 - gdcm::Cleaner, [274](#), [275](#)
- SecondaryCaptureImageStorage
 - gdcm::MediaStorage, [748](#)
 - gdcm::UIDs, [1250](#)
- Segment
 - gdcm::Segment, [1019](#)
- SegmentAlgorithmName
 - gdcm::Segment, [1023](#)
- SegmentAlgorithmType
 - gdcm::Segment, [1023](#)
- Segmentation
 - gdcm::MediaStorage, [750](#)
- SegmentationStorage
 - gdcm::MediaStorage, [749](#)
 - gdcm::UIDs, [1250](#)
- SegmentDescription
 - gdcm::Segment, [1024](#)
- SegmentedPaletteColorLookupTable
 - gdcm::SegmentedPaletteColorLookupTable, [1027](#)
- SegmentedVolumeRenderingVolumetricPresentationStateStorage
 - gdcm::UIDs, [1254](#)
- SegmentLabel
 - gdcm::Segment, [1024](#)
- SegmentMap
 - gdcm::SegmentReader, [1031](#)
- SegmentNumber
 - gdcm::Segment, [1024](#)
- SegmentReader
 - gdcm::SegmentReader, [1031](#)
- Segments
 - gdcm::SegmentReader, [1032](#)
 - gdcm::SegmentWriter, [1037](#)
- SegmentVector
 - gdcm::SegmentReader, [1031](#)
 - gdcm::SegmentWriter, [1036](#)
- SegmentWriter
 - gdcm::SegmentWriter, [1036](#)
- Selection
 - gdcm::Sorter, [1093](#)
- SelectionMap
 - gdcm::Sorter, [1091](#)
- Self
 - gdcm::AnonymizeEvent, [104](#)
 - gdcm::DataEvent, [356](#)
 - gdcm::DataSetEvent, [372](#)
 - gdcm::FileNameEvent, [535](#)
 - gdcm::MemberCommand< T >, [757](#)
 - gdcm::ProgressEvent, [945](#)
 - gdcm::SimpleMemberCommand< T >, [1075](#)
- SEMIAUTOMATIC

- gdcmm::Segment, [1019](#)
- SendEcho
 - gdcmm::network::ULConnectionManager, [1324](#)
 - gdcmm::ServiceClassUser, [1066](#)
- SendFind
 - gdcmm::network::ULConnectionManager, [1324](#), [1325](#)
 - gdcmm::ServiceClassUser, [1066](#)
- SendMove
 - gdcmm::network::ULConnectionManager, [1325](#)
 - gdcmm::ServiceClassUser, [1066](#), [1067](#)
- SendNAction
 - gdcmm::network::ULConnectionManager, [1325](#)
- SendNCreate
 - gdcmm::network::ULConnectionManager, [1325](#)
- SendNDelete
 - gdcmm::network::ULConnectionManager, [1326](#)
- SendNEventReport
 - gdcmm::network::ULConnectionManager, [1326](#)
- SendNGet
 - gdcmm::network::ULConnectionManager, [1326](#)
- SendNSet
 - gdcmm::network::ULConnectionManager, [1326](#)
- SendStore
 - gdcmm::network::ULConnectionManager, [1327](#)
 - gdcmm::ServiceClassUser, [1067](#)
- Separator
 - gdcmm::ApplicationEntity, [120](#)
 - gdcmm::PersonName, [870](#)
- SequenceLengthField
 - gdcmm::SequenceOfItems, [1054](#)
- SequenceOfFragments
 - gdcmm::SequenceOfFragments, [1041](#)
- SequenceOfItems
 - gdcmm::SequenceOfItems, [1049](#)
- SerieHelper
 - gdcmm::SerieHelper, [1057](#)
- SerieRestrictions
 - gdcmm::SerieHelper, [1056](#)
- Series
 - gdcmm::Series, [1060](#)
- SeriesInstanceUID
 - vtkRTStructSetProperties, [1492](#)
- ServiceClassApplicationInformation
 - gdcmm::network::ServiceClassApplicationInformation, [1060](#)
- ServiceClassUser
 - gdcmm::ServiceClassUser, [1065](#)
- Set
 - gdcmm::Attribute< Group, Element, TVR, TVM >, [136](#)
 - gdcmm::Attribute< Group, Element, TVR, VM::VM1_>, [145](#)
 - gdcmm::Attribute< Group, Element, TVR, VM::VM1_3 >, [151](#)
 - gdcmm::Attribute< Group, Element, TVR, VM::VM1_8 >, [156](#)
 - gdcmm::Attribute< Group, Element, TVR, VM::VM1_n >, [164](#)
 - gdcmm::Attribute< Group, Element, TVR, VM::VM2_2n >, [171](#)
 - gdcmm::Attribute< Group, Element, TVR, VM::VM2_n >, [177](#)
 - gdcmm::Attribute< Group, Element, TVR, VM::VM3_3n >, [183](#)
 - gdcmm::Attribute< Group, Element, TVR, VM::VM3_n >, [189](#)
 - gdcmm::Element< TVR, TVM >, [431](#)
 - gdcmm::Element< TVR, VM::VM1_2 >, [437](#)
 - gdcmm::Element< TVR, VM::VM2_2n >, [442](#)
 - gdcmm::Element< TVR, VM::VM3_3n >, [447](#)
 - gdcmm::Element< TVR, VM::VM3_4 >, [452](#)
 - gdcmm::Element< VR::AS, VM::VM5 >, [456](#)
 - gdcmm::Element< VR::OB, VM::VM1 >, [461](#)
 - gdcmm::Element< VR::OW, VM::VM1 >, [466](#)
- SetAbstractSyntax
 - gdcmm::network::PresentationContextRQ, [926](#)
 - gdcmm::PresentationContext, [917](#)
- SetAETitle
 - gdcmm::ServiceClassUser, [1068](#)
- SetAlgorithmFamily
 - gdcmm::Surface, [1155](#)
- SetAlgorithmName
 - gdcmm::Surface, [1155](#)
- SetAlgorithmVersion
 - gdcmm::Surface, [1155](#)
- SetAnatomicRegion
 - gdcmm::Segment, [1021](#)
- SetAnatomicRegionModifiers
 - gdcmm::Segment, [1021](#)
- SetAppendDerivationHistory
 - gdcmm::FileDerivation, [516](#)
- setAttribute
 - gdcmm::terminal, [83](#)
- SetAxisOfRotation
 - gdcmm::Surface, [1155](#)
- setbgcolor
 - gdcmm::terminal, [83](#)
- SetBitPosition
 - gdcmm::Overlay, [844](#)
- SetBitsAllocated
 - gdcmm::Overlay, [844](#)
 - gdcmm::PixelFormat, [884](#)
- SetBitSample
 - gdcmm::JPEGCodec, [707](#)
- SetBitsStored
 - gdcmm::PixelFormat, [885](#)
- SetBlob
 - gdcmm::ApplicationEntity, [119](#)

- gdcm::network::PresentationDataValue, [929](#)
- gdcm::PersonName, [869](#)
- SetBlueLUT
 - gdcm::LookupTable, [732](#)
- SetBufferLength
 - gdcm::JPEGLSCodec, [715](#)
 - gdcm::PNMCodec, [910](#)
 - gdcm::RLECodec, [993](#)
- SetByteSwapTag
 - gdcm::ByteSwapFilter, [246](#)
- SetByteValue
 - gdcm::Attribute< Group, Element, TVR, TVM >, [136](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM1 >, [145](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM1_3 >, [151](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM1_8 >, [157](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM1_n >, [164](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM2_2n >, [171](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM2_n >, [177](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM3_3n >, [184](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM3_n >, [189](#)
 - gdcm::CSAElement, [316](#)
 - gdcm::DataElement, [349](#)
- SetByteValueNoSwap
 - gdcm::Attribute< Group, Element, TVR, TVM >, [136](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM1 >, [145](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM1_3 >, [151](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM1_8 >, [157](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM1_n >, [164](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM2_2n >, [171](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM2_n >, [177](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM3_3n >, [184](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM3_n >, [190](#)
- SetCallbackFunction
 - gdcm::MemberCommand< T >, [758](#), [759](#)
 - gdcm::SimpleMemberCommand< T >, [1076](#)
- SetCalledAETitle
 - gdcm::network::AAssociateACPDU, [91](#)
 - gdcm::network::AAssociateRQPDU, [98](#)
- gdcm::ServiceClassUser, [1068](#)
- SetCallingAETitle
 - gdcm::network::AAssociateACPDU, [91](#)
 - gdcm::network::AAssociateRQPDU, [98](#)
- SetCenterOfRotation
 - gdcm::Surface, [1155](#)
- SetChangePrivateTags
 - gdcm::FileExplicitFilter, [519](#)
- SetCheckFileMetaInformation
 - gdcm::Writer, [1502](#)
- SetCipherType
 - gdcm::CAPICryptographicMessageSyntax, [259](#)
 - gdcm::CryptographicMessageSyntax, [310](#)
 - gdcm::OpenSSLCryptographicMessageSyntax, [828](#)
 - gdcm::OpenSSL7CryptographicMessageSyntax, [833](#)
- SetColor
 - gdcm::Printer, [934](#)
- SetColorLevel
 - vtkImageColorViewer, [1455](#)
- SetColorWindow
 - vtkImageColorViewer, [1455](#)
- SetColumns
 - gdcm::Bitmap, [228](#)
 - gdcm::Overlay, [844](#)
- SetCommand
 - gdcm::network::PresentationDataValue, [929](#)
- SetComponents
 - gdcm::PersonName, [869](#)
- SetCompressIconImage
 - gdcm::ImageChangeTransferSyntax, [603](#)
- SetComputeZSpacing
 - gdcm::IPPSorter, [667](#)
- SetCoordinateStartValue
 - gdcm::Curve, [338](#)
- SetCoordinateStepValue
 - gdcm::Curve, [338](#)
- SetCryptographicMessageSyntax
 - gdcm::Anonymizer, [114](#)
- SetCurve
 - gdcm::Curve, [338](#)
 - vtkGDCMImageReader, [1388](#)
 - vtkGDCMImageReader2, [1404](#)
- SetCurveDataDescriptor
 - gdcm::Curve, [338](#)
- SetCurveDescription
 - gdcm::Curve, [338](#)
- SetData
 - gdcm::DataEvent, [358](#)
- SetDataElement
 - gdcm::Bitmap, [228](#)
- SetDataSet
 - gdcm::File, [500](#)
 - gdcm::network::PresentationDataValue, [929](#)

- SetDataSetTransferSyntax
 - gdcm::FileMetaInformation, [528](#)
- SetDataValueRepresentation
 - gdcm::Curve, [339](#)
- SetDebug
 - gdcm::Trace, [1213](#)
- SetDebugStream
 - gdcm::Trace, [1213](#)
- SetDefaultTransferSyntax
 - gdcm::PresentationContextGenerator, [923](#)
- SetDerivationCodeSequenceCodeValue
 - gdcm::FileDerivation, [516](#)
- SetDerivationDescription
 - gdcm::FileDerivation, [516](#)
- SetDescription
 - gdcm::CSAHeaderDictEntry, [330](#)
 - gdcm::ModuleEntry, [779](#)
 - gdcm::Overlay, [844](#)
- SetDescriptor
 - gdcm::DICOmdirGenerator, [389](#)
- SetDictName
 - gdcm::DictConverter, [397](#)
- SetDicts
 - gdcm::PythonFilter, [952](#)
 - gdcm::StringFilter, [1140](#)
- SetDimension
 - gdcm::Bitmap, [228](#)
- SetDimensions
 - gdcm::Bitmap, [228](#)
 - gdcm::Curve, [339](#)
 - gdcm::ImageCodec, [613](#)
- SetDimensionsValue
 - gdcm::ImageHelper, [627](#)
- SetDirectionCosines
 - gdcm::Image, [584](#)
 - vtkGDCMImageWriter, [1416](#)
- SetDirectionCosinesFromImageOrientationPatient
 - vtkGDCMImageWriter, [1416](#)
- SetDirectionCosinesTolerance
 - gdcm::IPPSorter, [667](#)
- SetDirectionCosinesValue
 - gdcm::ImageHelper, [627](#)
- SetDirectory
 - gdcm::network::ULWritingCallback, [1332](#)
 - gdcm::SerieHelper, [1058](#)
- SetDisplayId
 - vtkImageColorViewer, [1455](#)
- SetDomain
 - gdcm::BoxRegion, [241](#)
- SetDropDuplicatePositions
 - gdcm::IPPSorter, [668](#)
- SetElement
 - gdcm::Tag, [1199](#)
- SetElementHandler
 - gdcm::Parser, [852](#)
- SetElementTag
 - gdcm::Tag, [1199](#), [1200](#)
- SetElementXX
 - gdcm::DictEntry, [401](#)
- SetError
 - gdcm::Trace, [1214](#)
- SetErrorStream
 - gdcm::Trace, [1214](#)
- SetEvent
 - gdcm::network::ULEvent, [1329](#)
- setfgcolor
 - gdcm::terminal, [83](#)
- SetFile
 - gdcm::Anonymizer, [114](#)
 - gdcm::Cleaner, [275](#)
 - gdcm::DICOmdirGenerator, [389](#)
 - gdcm::FileDecompressLookupTable, [513](#)
 - gdcm::FileDerivation, [516](#)
 - gdcm::FileExplicitFilter, [519](#)
 - gdcm::IconImageFilter, [573](#)
 - gdcm::Printer, [934](#)
 - gdcm::PythonFilter, [952](#)
 - gdcm::Reader, [977](#)
 - gdcm::SplitMosaicFilter, [1100](#)
 - gdcm::StreamImageWriter, [1110](#)
 - gdcm::StringFilter, [1140](#)
 - gdcm::Validate, [1351](#)
 - gdcm::Writer, [1502](#)
 - gdcm::XMLPrinter, [1509](#)
- SetFileName
 - gdcm::FileNameEvent, [536](#)
 - gdcm::Reader, [977](#)
 - gdcm::StreamImageReader, [1106](#)
 - gdcm::StreamImageWriter, [1111](#)
 - gdcm::Writer, [1502](#)
 - vtkGDCMThreadedImageReader2, [1445](#)
- SetFilename
 - gdcm::TableReader, [1189](#)
- SetFileNames
 - vtkGDCMImageReader, [1388](#)
 - vtkGDCMImageWriter, [1417](#)
 - vtkGDCMThreadedImageReader2, [1445](#)
- SetFilenames
 - gdcm::DICOmdirGenerator, [389](#)
- SetFilePattern
 - vtkGDCMImageReader, [1389](#)
 - vtkGDCMImageReader2, [1404](#)
- SetFilePrefix
 - vtkGDCMImageReader, [1389](#)
 - vtkGDCMImageReader2, [1404](#)
- SetFiles
 - gdcm::FileSet, [542](#)
- SetFiniteVolume

- gdcM::Surface, [1155](#)
- SetForce
 - gdcM::ImageChangeTransferSyntax, [603](#)
 - gdcM::ImageFragmentSplitter, [622](#)
- SetForcePixelSpacing
 - gdcM::ImageHelper, [627](#)
- SetForceRescaleInterceptSlope
 - gdcM::ImageHelper, [627](#)
- SetFragmentSizeMax
 - gdcM::ImageFragmentSplitter, [622](#)
- SetFrameOrigin
 - gdcM::Overlay, [845](#)
- SetFromDataElement
 - gdcM::Attribute< Group, Element, TVR, TVM >, [137](#)
 - gdcM::Attribute< Group, Element, TVR, VM::VM1 >, [145](#)
 - gdcM::Attribute< Group, Element, TVR, VM::VM1_3 >, [151](#)
 - gdcM::Attribute< Group, Element, TVR, VM::VM1_8 >, [157](#)
 - gdcM::Attribute< Group, Element, TVR, VM::VM1_n >, [164](#)
 - gdcM::Attribute< Group, Element, TVR, VM::VM2_2n >, [171](#)
 - gdcM::Attribute< Group, Element, TVR, VM::VM2_n >, [177](#)
 - gdcM::Attribute< Group, Element, TVR, VM::VM3_3n >, [184](#)
 - gdcM::Attribute< Group, Element, TVR, VM::VM3_n >, [190](#)
 - gdcM::Element< TVR, TVM >, [431](#)
 - gdcM::Element< TVR, VM::VM1_2 >, [437](#)
 - gdcM::Element< TVR, VM::VM2_2n >, [442](#)
 - gdcM::Element< TVR, VM::VM3_3n >, [447](#)
 - gdcM::Element< TVR, VM::VM3_4 >, [452](#)
 - gdcM::Element< VR::AS, VM::VM5 >, [456](#)
 - gdcM::Element< VR::OB, VM::VM1 >, [461](#)
 - gdcM::Element< VR::OW, VM::VM1 >, [466](#)
- SetFromDataSet
 - gdcM::Attribute< Group, Element, TVR, TVM >, [137](#)
 - gdcM::Attribute< Group, Element, TVR, VM::VM1 >, [145](#)
 - gdcM::Attribute< Group, Element, TVR, VM::VM1_3 >, [151](#)
 - gdcM::Attribute< Group, Element, TVR, VM::VM1_8 >, [157](#)
 - gdcM::Attribute< Group, Element, TVR, VM::VM1_n >, [164](#)
 - gdcM::Attribute< Group, Element, TVR, VM::VM2_2n >, [172](#)
 - gdcM::Attribute< Group, Element, TVR, VM::VM2_n >, [177](#)
 - gdcM::Attribute< Group, Element, TVR, VM::VM3_3n >, [184](#)
- gdcM::Attribute< Group, Element, TVR, VM::VM3_n >, [190](#)
- gdcM::MediaStorage, [753](#)
- SetFromFile
 - gdcM::MediaStorage, [753](#)
- SetFromHeader
 - gdcM::MediaStorage, [753](#)
- SetFromModality
 - gdcM::MediaStorage, [753](#)
- SetFromSourceImageSequence
 - gdcM::MediaStorage, [753](#)
- SetFromString
 - gdcM::DirectionCosines, [414](#)
- SetFromUID
 - gdcM::UIDs, [1267](#)
- SetGreenLUT
 - gdcM::LookupTable, [732](#)
- SetGroup
 - gdcM::Curve, [339](#)
 - gdcM::Overlay, [845](#)
 - gdcM::Tag, [1200](#)
- SetGroupXX
 - gdcM::DictEntry, [401](#)
- SetHeader
 - gdcM::File, [501](#)
- SetHighBit
 - gdcM::PixelFormat, [885](#)
- SetHostname
 - gdcM::ServiceClassUser, [1068](#)
- SetIconImage
 - gdcM::Pixmap, [893](#)
- SetIE
 - gdcM::IODEntry, [660](#)
- SetImage
 - gdcM::PixmapWriter, [905](#)
 - gdcM::SplitMosaicFilter, [1100](#)
- SetImplementationClassUID
 - gdcM::FileMetaInformation, [528](#)
- SetImplementationVersionName
 - gdcM::FileMetaInformation, [529](#)
- SetImplicitFlag
 - gdcM::network::ULConnectionCallback, [1317](#)
- SetInput
 - gdcM::BitmapToBitmapFilter, [236](#)
 - gdcM::ImageConverter, [618](#)
 - vtkImageColorViewer, [1456](#)
- SetInputConnection
 - vtkImageColorViewer, [1456](#)
- SetInputDirectory
 - gdcM::EmptyMaskGenerator, [471](#)
- SetInputFileName
 - gdcM::DictConverter, [397](#)
 - gdcM::FileAnonymizer, [505](#)
 - gdcM::FileChangeTransferSyntax, [509](#)

- SetIntercept
 - gdcm::Image, [584](#)
 - gdcm::Rescaler, [986](#)
- SetKey
 - gdcm::CSAElement, [316](#)
- SetKeyword
 - gdcm::DictEntry, [401](#)
- SetLastElement
 - gdcm::ParseException, [848](#)
- SetLastFragment
 - gdcm::network::PresentationDataValue, [930](#)
- SetLength
 - gdcm::ByteValue, [254](#)
 - gdcm::Element< TVR, VM::VM1_2 >, [437](#)
 - gdcm::Element< TVR, VM::VM2_2n >, [442](#)
 - gdcm::Element< TVR, VM::VM3_3n >, [447](#)
 - gdcm::Element< TVR, VM::VM3_4 >, [452](#)
 - gdcm::RLECodec, [993](#)
 - gdcm::SequenceOfFragments, [1044](#)
 - gdcm::SequenceOfItems, [1053](#)
 - gdcm::Value, [1354](#)
- SetLengthOnly
 - gdcm::ByteValue, [254](#)
 - gdcm::Value, [1354](#)
- SetLengthToUndefined
 - gdcm::SequenceOfItems, [1053](#)
- SetLoadMode
 - gdcm::SerieHelper, [1059](#)
- SetLookupTable
 - vtkImageMapToColors16, [1465](#)
- SetLossless
 - gdcm::JPEGCodec, [707](#)
 - gdcm::JPEGLSCodec, [715](#)
- SetLossyError
 - gdcm::JPEGLSCodec, [715](#)
- SetLossyFlag
 - gdcm::Bitmap, [229](#)
 - gdcm::ImageCodec, [613](#)
 - gdcm::PVRGCodec, [951](#)
- SetLUT
 - gdcm::Bitmap, [229](#)
 - gdcm::ImageCodec, [613](#)
 - gdcm::LookupTable, [732](#)
 - gdcm::SegmentedPaletteColorLookupTable, [1028](#)
- SetManifold
 - gdcm::Surface, [1155](#)
- SetMaximumLength
 - gdcm::network::MaximumLengthSub, [741](#)
- SetMaximumPointDistance
 - gdcm::Surface, [1155](#)
- SetMaxPDULength
 - gdcm::network::ULConnectionInfo, [1319](#)
- SetMaxPDUSize
 - gdcm::network::ULConnection, [1314](#)
- SetMCT
 - gdcm::JPEG2000Codec, [693](#)
- SetMeanPointDistance
 - gdcm::Surface, [1156](#)
- SetMedicalImageProperties
 - vtkGDCMImageReader, [1389](#)
 - vtkGDCMImageReader2, [1404](#)
 - vtkGDCMImageWriter, [1417](#)
 - vtkGDCMPolyDataWriter, [1432](#)
- SetMergeModeToAbstractSyntax
 - gdcm::PresentationContextGenerator, [923](#)
- SetMergeModeToTransferSyntax
 - gdcm::PresentationContextGenerator, [923](#)
- SetMeshPrimitive
 - gdcm::Surface, [1156](#)
- SetMessageHeader
 - gdcm::network::PresentationDataValue, [930](#)
- SetMinMaxForPixelType
 - gdcm::Rescaler, [986](#)
- setmode
 - gdcm::terminal, [83](#)
- SetName
 - gdcm::CSAElement, [317](#)
 - gdcm::CSAHeaderDictEntry, [330](#)
 - gdcm::DictEntry, [401](#)
 - gdcm::IODEntry, [660](#)
 - gdcm::Macro, [737](#)
 - gdcm::Module, [776](#)
 - gdcm::ModuleEntry, [780](#)
 - gdcm::network::AbstractSyntax, [102](#)
 - gdcm::network::ApplicationContext, [117](#)
 - gdcm::network::TransferSyntaxSub, [1222](#)
 - gdcm::PDBElement, [858](#)
- SetNameFromUID
 - gdcm::network::AbstractSyntax, [102](#)
 - gdcm::network::TransferSyntaxSub, [1222](#)
- SetNeedByteSwap
 - gdcm::Bitmap, [229](#)
 - gdcm::ImageCodec, [614](#)
- SetNeedOverlayCleanup
 - gdcm::ImageCodec, [614](#)
- SetNestedDataSet
 - gdcm::Item, [675](#)
- SetNoOfItems
 - gdcm::CSAElement, [317](#)
- SetNoSwap
 - gdcm::Element< TVR, TVM >, [432](#)
 - gdcm::Element< TVR, VM::VM1_2 >, [437](#)
 - gdcm::Element< TVR, VM::VM2_2n >, [442](#)
 - gdcm::Element< TVR, VM::VM3_3n >, [447](#)
 - gdcm::Element< TVR, VM::VM3_4 >, [452](#)
 - gdcm::Element< VR::AS, VM::VM5 >, [456](#)
 - gdcm::Element< VR::OB, VM::VM1 >, [461](#)
 - gdcm::Element< VR::OW, VM::VM1 >, [466](#)

- SetNumberOfCurves
 - gdcm::Pixmap, [893](#)
- SetNumberOfDimensions
 - gdcm::Bitmap, [229](#)
 - gdcm::ImageCodec, [614](#)
- SetNumberOfFilenames
 - gdcm::FilenameGenerator, [539](#)
- SetNumberOfFrames
 - gdcm::Overlay, [845](#)
- SetNumberOfInputPorts
 - vtkGDCMPolyDataWriter, [1432](#)
- SetNumberOfItems
 - gdcm::SequenceOfItems, [1053](#)
- SetNumberOfOverlays
 - gdcm::Pixmap, [893](#)
- SetNumberOfPoints
 - gdcm::Curve, [339](#)
- SetNumberOfResolutions
 - gdcm::JPEG2000Codec, [693](#)
- SetNumberOfSegments
 - gdcm::SegmentWriter, [1037](#)
- SetNumberOfSurfacePoints
 - gdcm::Surface, [1156](#)
- SetNumberOfSurfaces
 - gdcm::SurfaceWriter, [1171](#)
- SetNumberOfTableValues
 - vtkLookupTable16, [1481](#)
- SetNumberOfThreadsForDecompression
 - gdcm::JPEG2000Codec, [693](#)
- SetNumberOfValues
 - gdcm::Attribute< Group, Element, TVR, VM::VM1_n
>, [165](#)
- SetNumberOfVectors
 - gdcm::Surface, [1156](#)
- SetObliquityThresholdCosineValue
 - gdcm::Orientation, [836](#)
- SetOffScreenRendering
 - vtkImageColorViewer, [1456](#)
- SetOrigin
 - gdcm::Image, [584](#), [585](#)
 - gdcm::Overlay, [845](#)
- SetOriginValue
 - gdcm::ImageHelper, [628](#)
- SetOutputDimensions
 - gdcm::IconImageGenerator, [575](#)
- SetOutputDirectory
 - gdcm::EmptyMaskGenerator, [471](#)
- SetOutputFileName
 - gdcm::DictConverter, [398](#)
 - gdcm::FileAnonymizer, [505](#)
 - gdcm::FileChangeTransferSyntax, [509](#)
 - gdcm::FileStreamer, [546](#)
- SetOutputFormatToLuminance
 - vtkImageMapToColors16, [1465](#)
- SetOutputFormatToLuminanceAlpha
 - vtkImageMapToColors16, [1465](#)
- SetOutputFormatToRGB
 - vtkImageMapToColors16, [1465](#)
- SetOutputFormatToRGBA
 - vtkImageMapToColors16, [1465](#)
- SetOutputType
 - gdcm::DictConverter, [398](#)
- SetOutsideValuePixel
 - gdcm::IconImageGenerator, [575](#)
- SetOverlay
 - gdcm::Overlay, [845](#)
- SetOverlayVisibility
 - vtkImageColorViewer, [1456](#)
- SetOwner
 - gdcm::PrivateTag, [942](#)
- SetParentId
 - vtkImageColorViewer, [1456](#)
- SetPassword
 - gdcm::CAPICryptographicMessageSyntax, [259](#)
 - gdcm::CryptographicMessageSyntax, [311](#)
 - gdcm::OpenSSLCryptographicMessageSyntax, [828](#)
 - gdcm::OpenSSL7CryptographicMessageSyntax,
[833](#)
- SetPattern
 - gdcm::FilenameGenerator, [539](#)
- SetPDU
 - gdcm::network::ULEvent, [1329](#)
- SetPermissions
 - gdcm::System, [1181](#)
- SetPhotometricInterpretation
 - gdcm::Bitmap, [229](#)
 - gdcm::ImageChangePhotometricInterpretation, [593](#)
 - gdcm::ImageCodec, [614](#)
- SetPixelFormat
 - gdcm::Bitmap, [230](#)
 - gdcm::ImageCodec, [614](#)
 - gdcm::JPEGCodec, [707](#)
 - gdcm::Rescaler, [986](#)
- SetPixelMinMax
 - gdcm::IconImageGenerator, [576](#)
- SetPixelRepresentation
 - gdcm::PixelFormat, [885](#)
- SetPixmap
 - gdcm::FileDecompressLookupTable, [513](#)
 - gdcm::IconImageGenerator, [576](#)
 - gdcm::PixmapWriter, [905](#)
- SetPlanarConfiguration
 - gdcm::Bitmap, [230](#)
 - gdcm::ImageChangePlanarConfiguration, [598](#)
 - gdcm::ImageCodec, [615](#)
- SetPMSRescaleInterceptSlope
 - gdcm::ImageHelper, [628](#)
- SetPointCoordinatesData

- gdcm::Surface, [1156](#)
- SetPointPositionAccuracy
 - gdcm::Surface, [1156](#)
- SetPointsBoundingBoxCoordinates
 - gdcm::Surface, [1156](#)
- SetPort
 - gdcm::ServiceClassUser, [1068](#)
- SetPortSCP
 - gdcm::ServiceClassUser, [1068](#)
- SetPosition
 - vtkImageColorViewer, [1456](#)
- SetPreamble
 - gdcm::FileMetaInformation, [529](#)
- SetPrefix
 - gdcm::FilenameGenerator, [540](#)
- SetPresentationContextID
 - gdcm::network::PresentationContextAC, [920](#)
 - gdcm::network::PresentationContextRQ, [926](#)
 - gdcm::network::PresentationDataValue, [930](#)
 - gdcm::PresentationContext, [918](#)
- SetPresentationContexts
 - gdcm::network::ULConnection, [1314](#), [1315](#)
 - gdcm::ServiceClassUser, [1069](#)
- SetPrettyPrint
 - gdcm::JSON, [718](#)
- SetPrimitiveData
 - gdcm::MeshPrimitive, [764](#)
- SetPrimitivesData
 - gdcm::MeshPrimitive, [764](#)
- SetPrimitiveType
 - gdcm::MeshPrimitive, [764](#)
- SetPrivateCreator
 - gdcm::Tag, [1200](#)
- SetProcessingAlgorithm
 - gdcm::Surface, [1156](#)
- SetProgress
 - gdcm::ProgressEvent, [946](#)
- SetPropertyCategory
 - gdcm::Segment, [1022](#)
- SetPropertyType
 - gdcm::Segment, [1022](#)
- SetPropertyTypeModifiers
 - gdcm::Segment, [1022](#)
- SetPurposeOfReferenceCodeSequenceCodeValue
 - gdcm::FileDerivation, [517](#)
- SetQuality
 - gdcm::JPEG2000Codec, [693](#)
 - gdcm::JPEGCodec, [708](#)
- SetRate
 - gdcm::JPEG2000Codec, [693](#)
- SetReason
 - gdcm::network::AAAbortPDU, [87](#)
 - gdcm::network::PresentationContextAC, [920](#)
- SetRecommendedDisplayCIELabValue
 - gdcm::Surface, [1157](#)
- SetRecommendedDisplayGrayscaleValue
 - gdcm::Surface, [1157](#)
- SetRecommendedPresentationOpacity
 - gdcm::Surface, [1157](#)
- SetRecommendedPresentationType
 - gdcm::Surface, [1157](#)
- SetRecomputeItemLength
 - gdcm::FileExplicitFilter, [519](#)
- SetRecomputeSequenceLength
 - gdcm::FileExplicitFilter, [520](#)
- SetRedLUT
 - gdcm::LookupTable, [732](#)
- SetRef
 - gdcm::IODEntry, [660](#)
- SetRegion
 - gdcm::ImageRegionReader, [639](#)
- SetRenderer
 - vtkImageColorViewer, [1457](#)
- SetRenderWindow
 - vtkImageColorViewer, [1457](#)
- SetRescaleInterceptSlopeValue
 - gdcm::ImageHelper, [628](#)
- SetRetired
 - gdcm::DictEntry, [401](#)
- SetReversible
 - gdcm::JPEG2000Codec, [694](#)
- SetRGB8
 - gdcm::ImageApplyLookupTable, [589](#)
- SetRoot
 - gdcm::UIDGenerator, [1230](#)
- SetRootDirectory
 - gdcm::DICOMDIRGenerator, [390](#)
- SetRows
 - gdcm::Bitmap, [230](#)
 - gdcm::Overlay, [845](#)
- SetRTStructSetProperties
 - vtkGDCMPolyDataWriter, [1432](#)
- SetSamplesPerPixel
 - gdcm::PixelFormat, [885](#)
- SetScalarType
 - gdcm::PixelFormat, [885](#)
- SetSearchParameter
 - gdcm::BaseQuery, [205](#)
- SetSecondaryCaptureImagePlaneModule
 - gdcm::ImageHelper, [628](#)
- SetSegmentAlgorithmName
 - gdcm::Segment, [1022](#)
- SetSegmentAlgorithmType
 - gdcm::Segment, [1022](#)
- SetSegmentDescription
 - gdcm::Segment, [1022](#)
- SetSegmentLabel
 - gdcm::Segment, [1022](#)

- SetSegmentNumber
 - gdcm::Segment, [1023](#)
- SetSegments
 - gdcm::SegmentWriter, [1037](#)
- SetSize
 - vtkImageColorViewer, [1457](#)
- SetSlice
 - vtkImageColorViewer, [1457](#)
- SetSliceOrientation
 - vtkImageColorViewer, [1457](#)
- SetSliceOrientationToXY
 - vtkImageColorViewer, [1458](#)
- SetSliceOrientationToXZ
 - vtkImageColorViewer, [1458](#)
- SetSliceOrientationToYZ
 - vtkImageColorViewer, [1458](#)
- SetSlope
 - gdcm::Image, [585](#)
 - gdcm::Rescaler, [986](#)
- SetSOPClassUIDMode
 - gdcm::EmptyMaskGenerator, [472](#)
- SetSOPInstanceUID
 - gdcm::BaseQuery, [206](#)
- SetSortFunction
 - gdcm::Sorter, [1092](#)
- SetSource
 - gdcm::network::AAbortPDU, [87](#)
- SetSourceApplicationEntityTitle
 - gdcm::FileMetaInformation, [529](#)
- SetSpacing
 - gdcm::Image, [585](#)
- SetSpacingValue
 - gdcm::ImageHelper, [628](#)
- SetState
 - gdcm::network::ULConnection, [1315](#)
- SetStream
 - gdcm::Reader, [978](#)
 - gdcm::StreamImageReader, [1107](#)
 - gdcm::StreamImageWriter, [1111](#)
 - gdcm::Trace, [1214](#)
 - gdcm::Writer, [1502](#)
- SetStreamToFile
 - gdcm::Trace, [1214](#)
- SetStyle
 - gdcm::Printer, [934](#)
 - gdcm::XMLPrinter, [1509](#)
- SetSurfaceComments
 - gdcm::Surface, [1157](#)
- SetSurfaceCount
 - gdcm::Segment, [1023](#)
- SetSurfaceNumber
 - gdcm::Surface, [1157](#)
- SetSurfaceProcessing
 - gdcm::Surface, [1158](#)
- SetSurfaceProcessingDescription
 - gdcm::Surface, [1158](#)
- SetSurfaceProcessingRatio
 - gdcm::Surface, [1158](#)
- SetSyngoDT
 - gdcm::CSAElement, [317](#)
- SetTag
 - gdcm::AnonymizeEvent, [106](#)
 - gdcm::DataElement, [350](#)
- SetTagsToRead
 - gdcm::Sorter, [1092](#)
- SetTargetPixelType
 - gdcm::Rescaler, [986](#)
- SetTemplateFileName
 - gdcm::FileStreamer, [546](#)
- SetTileSize
 - gdcm::JPEG2000Codec, [694](#)
- SetTimeout
 - gdcm::network::ARTIMTimer, [126](#)
 - gdcm::ServiceClassUser, [1069](#)
- SetToUndefined
 - gdcm::VL, [1362](#)
- SetTransferSyntax
 - gdcm::Bitmap, [230](#)
 - gdcm::FileChangeTransferSyntax, [510](#)
 - gdcm::ImageChangeTransferSyntax, [603](#)
 - gdcm::network::PresentationContextAC, [920](#)
- SetTuple
 - gdcm::network::RoleSelectionSub, [995](#)
 - gdcm::network::ServiceClassApplicationInformation, [1061](#)
 - gdcm::network::SOPClassExtendedNegotiationSub, [1086](#)
- SetType
 - gdcm::ModuleEntry, [780](#)
 - gdcm::Overlay, [846](#)
- SetTypeOfData
 - gdcm::Curve, [339](#)
- SetupInteractor
 - vtkImageColorViewer, [1458](#)
- SetUsage
 - gdcm::IODEntry, [660](#)
- SetUserCodec
 - gdcm::ImageChangeTransferSyntax, [603](#)
- SetUserData
 - gdcm::Parser, [852](#)
- SetUserInfo
 - gdcm::network::AAssociateRQPDU, [98](#)
- SetUseSeriesDetails
 - gdcm::SerieHelper, [1059](#)
- SetUseTargetPixelType
 - gdcm::Rescaler, [987](#)
- SetUseVRUN
 - gdcm::FileExplicitFilter, [520](#)

- SetValue
 - gdcm::Attribute< Group, Element, TVR, TVM >, [137](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM1 >, [146](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM1_3 >, [151](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM1_8 >, [157](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM1_n >, [165](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM2_2n >, [172](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM2_n >, [177](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM3_3n >, [184](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM3_n >, [190](#)
 - gdcm::CSAElement, [317](#)
 - gdcm::DataElement, [350](#)
 - gdcm::Element< TVR, TVM >, [432](#)
 - gdcm::Element< TVR, VM::VM1_2 >, [437](#)
 - gdcm::Element< TVR, VM::VM2_2n >, [442](#)
 - gdcm::Element< TVR, VM::VM3_3n >, [447](#)
 - gdcm::Element< TVR, VM::VM3_4 >, [452](#)
 - gdcm::Element< VR::AS, VM::VM5 >, [456](#)
 - gdcm::Element< VR::OB, VM::VM1 >, [461](#)
 - gdcm::Element< VR::OW, VM::VM1 >, [466](#)
 - gdcm::PDBelement, [858](#)
- SetValueFieldLength
 - gdcm::DataElement, [351](#)
- SetValues
 - gdcm::Attribute< Group, Element, TVR, TVM >, [138](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM1 >, [146](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM1_3 >, [152](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM1_8 >, [157](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM1_n >, [165](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM2_2n >, [172](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM2_n >, [178](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM3_3n >, [184](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM3_n >, [190](#)
- SetVectorAccuracy
 - gdcm::Surface, [1158](#)
- SetVectorCoordinateData
 - gdcm::Surface, [1158](#)
- SetVectorDimensionality
 - gdcm::Surface, [1158](#)
- SetVL
 - gdcm::DataElement, [351](#)
- SetVLToUndefined
 - gdcm::DataElement, [351](#)
- SetVM
 - gdcm::CSAElement, [317](#)
 - gdcm::CSAHeaderDictEntry, [330](#)
 - gdcm::DictEntry, [402](#)
- SetVR
 - gdcm::CSAElement, [317](#)
 - gdcm::CSAHeaderDictEntry, [330](#)
 - gdcm::DataElement, [351](#)
 - gdcm::DictEntry, [402](#)
- SetWarning
 - gdcm::Trace, [1214](#)
- SetWarningStream
 - gdcm::Trace, [1215](#)
- SetWindowId
 - vtkImageColorViewer, [1458](#)
- SetWriteDataSetOnly
 - gdcm::Writer, [1503](#)
- SetZSpacingTolerance
 - gdcm::IPPSorter, [668](#)
- SH
 - gdcm::VR, [1371](#)
- SHA1
 - gdcm::SHA1, [1071](#)
- SHComp
 - gdcm, [60](#)
- Shift
 - vtkGDCMImageReader, [1398](#)
 - vtkGDCMImageReader2, [1412](#)
- ShiftEnd
 - gdcm::ByteBuffer, [242](#)
- ShowAbort
 - gdcm::SimpleSubjectWatcher, [1078](#)
- ShowAnonymization
 - gdcm::SimpleSubjectWatcher, [1079](#)
- ShowData
 - gdcm::SimpleSubjectWatcher, [1079](#)
- ShowDataSet
 - gdcm::SimpleSubjectWatcher, [1079](#)
- ShowFileName
 - gdcm::SimpleSubjectWatcher, [1079](#)
- ShowIteration
 - gdcm::SimpleSubjectWatcher, [1079](#)
- ShowProgress
 - gdcm::SimpleSubjectWatcher, [1079](#)
- SIEMENS
 - gdcm::Dicts, [407](#)
 - gdcm::EquipmentManufacturer, [481](#)
- SimpleMemberCommand
 - gdcm::SimpleMemberCommand< T >, [1075](#)

- SimpleSubjectWatcher
 - gdcm::SimpleSubjectWatcher, [1078](#)
- SimplifiedAdultEchoSRStorage
 - gdcm::UIDs, [1255](#)
- SINGLEBIT
 - gdcm::PixelFormat, [880](#)
- SingleSerieUIDFileSetHT
 - gdcm::SerieHelper, [1059](#)
- SingleSerieUIDFileSetmap
 - gdcm::SerieHelper, [1056](#)
- Size
 - gdcm::CodeString, [286](#)
 - gdcm::DataSet, [369](#)
 - gdcm::GroupDict, [569](#)
 - gdcm::network::AAAbortPDU, [87](#)
 - gdcm::network::AAssociateACPDU, [91](#)
 - gdcm::network::AAssociateRJPDU, [93](#)
 - gdcm::network::AAssociateRQPDU, [98](#)
 - gdcm::network::AbstractSyntax, [102](#)
 - gdcm::network::ApplicationContext, [117](#)
 - gdcm::network::AReleaseRPPDU, [122](#)
 - gdcm::network::AReleaseRQPDU, [124](#)
 - gdcm::network::AsynchronousOperationsWindowSub, [129](#)
 - gdcm::network::BasePDU, [201](#)
 - gdcm::network::ImplementationClassUIDSub, [647](#)
 - gdcm::network::ImplementationVersionNameSub, [649](#)
 - gdcm::network::MaximumLengthSub, [741](#)
 - gdcm::network::PDataTFPDU, [856](#)
 - gdcm::network::PresentationContextAC, [920](#)
 - gdcm::network::PresentationContextRQ, [927](#)
 - gdcm::network::PresentationDataValue, [930](#)
 - gdcm::network::RoleSelectionSub, [995](#)
 - gdcm::network::ServiceClassApplicationInformation, [1061](#)
 - gdcm::network::SOPClassExtendedNegociationSub, [1087](#)
 - gdcm::network::TransferSyntaxSub, [1222](#)
 - gdcm::network::UserInformation, [1348](#)
- size_type
 - gdcm::CodeString, [285](#)
 - gdcm::LO, [724](#)
 - gdcm::String< TDelimiter, TMaxLength, TPadChar >, [1136](#)
- SizeType
 - gdcm::DataSet, [361](#)
 - gdcm::FilenameGenerator, [538](#)
 - gdcm::IOD, [656](#)
 - gdcm::NestedModuleEntries, [805](#)
 - gdcm::network::AAssociateACPDU, [89](#)
 - gdcm::network::AAssociateRQPDU, [96](#)
 - gdcm::network::PDataTFPDU, [854](#)
 - gdcm::network::PresentationContextRQ, [924](#)
 - gdcm::PresentationContext, [916](#)
 - gdcm::PresentationContextGenerator, [922](#)
 - gdcm::SequenceOfFragments, [1040](#)
 - gdcm::SequenceOfItems, [1049](#)
- SL
 - gdcm::VR, [1371](#)
- Slice
 - vtkImageColorViewer, [1461](#)
- SLICE_ORIENTATION_XY
 - vtkImageColorViewer, [1452](#)
- SLICE_ORIENTATION_XZ
 - vtkImageColorViewer, [1452](#)
- SLICE_ORIENTATION_YZ
 - vtkImageColorViewer, [1452](#)
- SliceOrientation
 - vtkImageColorViewer, [1462](#)
- Slices
 - gdcm::MrProtocol::SliceArray, [1082](#)
- SmartPointer
 - gdcm::Object, [822](#)
 - gdcm::SmartPointer< ObjectType >, [1084](#)
- SOPClassExtendedNegociationSub
 - gdcm::network::SOPClassExtendedNegociationSub, [1086](#)
- SOPClassUIDMode
 - gdcm::EmptyMaskGenerator, [471](#)
- SOPInstanceUID
 - vtkRTStructSetProperties, [1492](#)
- Sort
 - gdcm::IPPSorter, [668](#)
 - gdcm::Sorter, [1092](#)
- Sorter
 - gdcm::Sorter, [1091](#)
- SortFunc
 - gdcm::Sorter, [1093](#)
- SortFunction
 - gdcm::Sorter, [1091](#)
- SpacialFiducialsStorage
 - gdcm::MediaStorage, [748](#)
- SpacialRegistrationStorage
 - gdcm::MediaStorage, [748](#)
- Spacing
 - gdcm::Spacing, [1095](#)
- SpacingType
 - gdcm::Spacing, [1095](#)
- SpatialFiducialsStorage
 - gdcm::UIDs, [1250](#)
- SpatialRegistrationStorage
 - gdcm::UIDs, [1250](#)
- SpectaclePrescriptionReportStorage
 - gdcm::UIDs, [1254](#)
- Spectroscopy
 - gdcm::Spectroscopy, [1096](#)
- Split

- gdcm::ImageFragmentSplitter, [622](#)
- gdcm::SplitMosaicFilter, [1100](#)
- SplitExtent
 - vtkGDCMThreadedImageReader2, [1445](#)
- SplitMosaicFilter
 - gdcm::SplitMosaicFilter, [1098](#)
- SPM2AVG152PDFrameofReference
 - gdcm::UIDs, [1248](#)
- SPM2AVG152T1FrameofReference
 - gdcm::UIDs, [1248](#)
- SPM2AVG152T2FrameofReference
 - gdcm::UIDs, [1248](#)
- SPM2AVG305T1FrameofReference
 - gdcm::UIDs, [1248](#)
- SPM2BRAINMASKFrameofReference
 - gdcm::UIDs, [1248](#)
- SPM2CSFFrameofReference
 - gdcm::UIDs, [1248](#)
- SPM2EPIFrameofReference
 - gdcm::UIDs, [1248](#)
- SPM2FILT1FrameofReference
 - gdcm::UIDs, [1248](#)
- SPM2GRAYFrameofReference
 - gdcm::UIDs, [1248](#)
- SPM2PDFrameofReference
 - gdcm::UIDs, [1248](#)
- SPM2PETFrameofReference
 - gdcm::UIDs, [1248](#)
- SPM2SINGLESUBJT1FrameofReference
 - gdcm::UIDs, [1248](#)
- SPM2SPECTFrameofReference
 - gdcm::UIDs, [1248](#)
- SPM2T1FrameofReference
 - gdcm::UIDs, [1248](#)
- SPM2T2FrameofReference
 - gdcm::UIDs, [1248](#)
- SPM2TRANSMFrameofReference
 - gdcm::UIDs, [1248](#)
- SPM2WHITEFrameofReference
 - gdcm::UIDs, [1248](#)
- SpringColorPaletteSOPInstance
 - gdcm::UIDs, [1253](#)
- SQ
 - gdcm::VR, [1371](#)
- Squeeze
 - gdcm::ApplicationEntity, [119](#)
- SS
 - gdcm::VR, [1371](#)
- ST
 - gdcm::VR, [1371](#)
- StableSort
 - gdcm::Sorter, [1092](#)
- StandaloneCurveStorage
 - gdcm::MediaStorage, [748](#)
- StandaloneCurveStorageRetired
 - gdcm::UIDs, [1250](#)
- StandaloneModalityLUTStorage
 - gdcm::MediaStorage, [748](#)
- StandaloneModalityLUTStorageRetired
 - gdcm::UIDs, [1250](#)
- StandaloneOverlayStorage
 - gdcm::MediaStorage, [748](#)
- StandaloneOverlayStorageRetired
 - gdcm::UIDs, [1250](#)
- StandalonePETCurveStorageRetired
 - gdcm::UIDs, [1251](#)
- StandaloneVOILUTStorage
 - gdcm::MediaStorage, [748](#)
- StandaloneVOILUTStorageRetired
 - gdcm::UIDs, [1250](#)
- Start
 - gdcm::network::ARTIMTimer, [126](#)
- StartAssociation
 - gdcm::ServiceClassUser, [1069](#)
- StartDataElement
 - gdcm::FileStreamer, [547](#)
- StartElement
 - gdcm::TableReader, [1189](#)
 - gdcm::XMLDictReader, [1506](#)
 - gdcm::XMLPrivateDictReader, [1513](#)
- StartElementHandler
 - gdcm::Parser, [850](#)
- StartEncode
 - gdcm::ImageCodec, [615](#)
 - gdcm::JPEG2000Codec, [694](#)
 - gdcm::JPEGCodec, [708](#)
 - gdcm::JPEGLSCodec, [715](#)
 - gdcm::RLECodec, [993](#)
- StartFilter
 - gdcm::SimpleSubjectWatcher, [1079](#)
- StartGroupDataElement
 - gdcm::FileStreamer, [547](#)
- STATES
 - gdcm::Surface, [1149](#)
- STATES_END
 - gdcm::Surface, [1149](#)
- STComp
 - gdcm, [60](#)
- StereometricRelationshipStorage
 - gdcm::UIDs, [1251](#)
- Stop
 - gdcm::network::ARTIMTimer, [126](#)
- StopAssociation
 - gdcm::ServiceClassUser, [1069](#)
- StopDataElement
 - gdcm::FileStreamer, [547](#)
- StopEncode
 - gdcm::ImageCodec, [615](#)

- gdcm::JPEG2000Codec, [694](#)
- gdcm::JPEGCodec, [708](#)
- gdcm::JPEGLSCodec, [716](#)
- gdcm::RLECodec, [993](#)
- StopGroupDataElement
 - gdcm::FileStreamer, [547](#)
- StopProtocol
 - gdcm::network::ULConnection, [1315](#)
- StorageCommitmentPullModelSOPClassRetired
 - gdcm::UIDs, [1248](#)
- StorageCommitmentPullModelSOPInstanceRetired
 - gdcm::UIDs, [1248](#)
- StorageCommitmentPushModelSOPClass
 - gdcm::UIDs, [1248](#)
- StorageCommitmentPushModelSOPInstance
 - gdcm::UIDs, [1248](#)
- StorageServiceClass
 - gdcm::UIDs, [1249](#)
- StoredPrintStorageSOPClassRetired
 - gdcm::UIDs, [1249](#)
- StrCaseCmp
 - gdcm::System, [1181](#)
- Stream
 - gdcm::Writer, [1503](#)
- StreamImageReader
 - gdcm::Reader, [978](#)
 - gdcm::StreamImageReader, [1104](#)
- StreamImageWriter
 - gdcm::StreamImageWriter, [1109](#)
 - gdcm::Writer, [1503](#)
- StrictScanner
 - gdcm::StrictScanner, [1118](#)
- StrictScanner2
 - gdcm::StrictScanner2, [1128](#)
- String
 - gdcm::String< TDelimiter, TMaxLength, TPadChar >, [1137](#)
- StringFilter
 - gdcm::StringFilter, [1139](#)
- StrNCaseCmp
 - gdcm::System, [1181](#)
- StrSep
 - gdcm::System, [1182](#)
- StrTokR
 - gdcm::System, [1182](#)
- StructureSetDate
 - vtkRTStructSetProperties, [1492](#)
- StructureSetLabel
 - vtkRTStructSetProperties, [1492](#)
- StructureSetName
 - vtkRTStructSetProperties, [1493](#)
- StructureSetTime
 - vtkRTStructSetProperties, [1493](#)
- Study
 - gdcm::Study, [1142](#)
- StudyComponentManagementSOPClass
 - gdcm::MediaStorage, [749](#)
- StudyComponentManagementSOPClassRetired
 - gdcm::UIDs, [1248](#)
- StudyInstanceUID
 - vtkRTStructSetProperties, [1493](#)
- StudyRootQueryRetrieveInformationModelFIND
 - gdcm::UIDs, [1251](#)
- StudyRootQueryRetrieveInformationModelGET
 - gdcm::UIDs, [1251](#)
- StudyRootQueryRetrieveInformationModelMOVE
 - gdcm::UIDs, [1251](#)
- Subject
 - gdcm::Subject, [1144](#)
- SubjectiveRefractionMeasurementsStorage
 - gdcm::UIDs, [1254](#)
- SubstanceAdministrationLoggingSOPClass
 - gdcm::UIDs, [1248](#)
- SubstanceAdministrationLoggingSOPInstance
 - gdcm::UIDs, [1248](#)
- SubstanceApprovalQuerySOPClass
 - gdcm::UIDs, [1252](#)
- SummerColorPaletteSOPInstance
 - gdcm::UIDs, [1253](#)
- Superclass
 - gdcm::AnonymizeEvent, [104](#)
 - gdcm::DataEvent, [356](#)
 - gdcm::DataSetEvent, [372](#)
 - gdcm::FileNameEvent, [535](#)
 - gdcm::LO, [724](#)
 - gdcm::ProgressEvent, [945](#)
- SURFACE
 - gdcm::Surface, [1150](#)
- Surface
 - gdcm::Surface, [1150](#)
- SurfaceCount
 - gdcm::Segment, [1024](#)
- SurfaceReader
 - gdcm::SurfaceReader, [1165](#)
- Surfaces
 - gdcm::Segment, [1024](#)
- SurfaceScanMeshStorage
 - gdcm::UIDs, [1254](#)
- SurfaceScanPointCloudStorage
 - gdcm::UIDs, [1254](#)
- SurfaceSegmentationStorage
 - gdcm::MediaStorage, [749](#)
 - gdcm::UIDs, [1253](#)
- SurfaceVector
 - gdcm::Segment, [1018](#)
- SurfaceWriter
 - gdcm::SurfaceWriter, [1170](#)
- SV

- gdcmm::VR, [1371](#)
- SV10
 - gdcmm::CSAHeader, [321](#)
- Swap
 - gdcmm::ByteSwap< T >, [243](#)
 - gdcmm::SwapperDoOp, [1174](#)
 - gdcmm::SwapperNoOp, [1175](#)
- SwapArray
 - gdcmm::SwapperDoOp, [1174](#)
 - gdcmm::SwapperNoOp, [1175](#)
- SwapCode
 - gdcmm::SwapCode, [1173](#)
- SwapCodeType
 - gdcmm::SwapCode, [1172](#)
- SwapFromSwapCodeIntoSystem
 - gdcmm::ByteSwap< T >, [243](#)
- SwapRange
 - gdcmm::ByteSwap< T >, [244](#)
- SwapRangeFromSwapCodeIntoSystem
 - gdcmm::ByteSwap< T >, [244](#)
- SyngoDTField
 - gdcmm::CSAElement, [318](#)
- SyntaxError
 - gdcmm::Parser, [850](#)
- SystemIsBigEndian
 - gdcmm::ByteSwap< T >, [244](#)
- SystemIsLittleEndian
 - gdcmm::ByteSwap< T >, [244](#)
- T1
 - gdcmm::Type, [1226](#)
- T1C
 - gdcmm::Type, [1226](#)
- T2
 - gdcmm::Type, [1226](#)
- T2C
 - gdcmm::Type, [1226](#)
- T3
 - gdcmm::Type, [1226](#)
- Table
 - gdcmm::Table, [1184](#)
- Table16
 - vtkLookupTable16, [1482](#)
- TableEntry
 - gdcmm::TableEntry, [1186](#)
- TableInternal
 - gdcmm::Table, [1185](#)
- TableReader
 - gdcmm::TableReader, [1187](#)
- TableRow
 - gdcmm::network::TableRow, [1191](#)
- Tag
 - gdcmm::Tag, [1194](#)
- tag
 - gdcmm::Tag, [1201](#)
- TagField
 - gdcmm::DataElement, [353](#)
- TagMismatchError
 - gdcmm::Parser, [850](#)
- TagPath
 - gdcmm::TagPath, [1202](#)
- tags
 - gdcmm::Tag, [1201](#)
- TagsToRead
 - gdcmm::Sorter, [1093](#)
- TagToValue
 - gdcmm::Scanner, [999](#)
 - gdcmm::StrictScanner, [1117](#)
- TagToValueValueType
 - gdcmm::Scanner, [999](#)
 - gdcmm::StrictScanner, [1118](#)
- TalairachBrainAtlasFrameofReference
 - gdcmm::UIDs, [1248](#)
- TConstMemberFunctionPointer
 - gdcmm::MemberCommand< T >, [757](#)
- TestAbortOff
 - gdcmm::SimpleSubjectWatcher, [1080](#)
- TestAbortOn
 - gdcmm::SimpleSubjectWatcher, [1080](#)
- Testing
 - gdcmm::Testing, [1205](#)
- TestPBKDF2
 - gdcmm::ASN1, [128](#)
- TestsList.txt, [1515](#)
- TextSRStorageTrialRetired
 - gdcmm::UIDs, [1251](#)
- ThreadedExecute
 - vtkImageRGBToYBR, [1476](#)
 - vtkImageYBRToRGB, [1478](#)
- ThreadedRequestData
 - vtkGDCMThreadedImageReader2, [1445](#)
 - vtkImageMapToColors16, [1465](#)
 - vtkImageMapToWindowLevelColors2, [1470](#)
- TM
 - gdcmm::VR, [1371](#)
- TMComp
 - gdcmm, [60](#)
- TMemberFunctionPointer
 - gdcmm::MemberCommand< T >, [757](#)
 - gdcmm::SimpleMemberCommand< T >, [1075](#)
- Todo List, [3](#)
- ToPyObject
 - gdcmm::PythonFilter, [953](#)
- TOSHIBA
 - gdcmm::EquipmentManufacturer, [481](#)
- ToshibaPrivateDataStorage
 - gdcmm::MediaStorage, [749](#)
- ToString

- gdcM::StringFilter, [1141](#)
- ToStringPair
 - gdcM::StringFilter, [1141](#), [1142](#)
- ToUnixSlashes
 - gdcM::Filename, [532](#)
- ToWindowsSlashes
 - gdcM::Filename, [533](#)
- Trace
 - gdcM::Trace, [1212](#)
- TractographyResultsStorage
 - gdcM::UIDs, [1254](#)
- TransferSyntax
 - gdcM::TransferSyntax, [1218](#)
- TransferSyntaxArrayType
 - gdcM::PresentationContext, [916](#)
- TransferSyntaxes
 - gdcM::PresentationContext, [918](#)
- TransferSyntaxStringsType
 - gdcM::UIDs, [1247](#)
- TransferSyntaxSub
 - gdcM::network::TransferSyntaxSub, [1222](#)
- Transition
 - gdcM::network::Transition, [1224](#)
- transitions
 - gdcM::network::TableRow, [1191](#)
- TRIANGLE
 - gdcM::MeshPrimitive, [762](#)
- TRIANGLE_FAN
 - gdcM::MeshPrimitive, [762](#)
- TRIANGLE_STRIP
 - gdcM::MeshPrimitive, [762](#)
- Trim
 - gdcM::String< TDelimiter, TMaxLength, TPadChar >, [1138](#)
- TrimInternal
 - gdcM::CodeString, [286](#)
- Truncate
 - gdcM::String< TDelimiter, TMaxLength, TPadChar >, [1138](#)
- TryJPEG2000Codec
 - gdcM::Bitmap, [231](#)
 - gdcM::ImageChangeTransferSyntax, [604](#)
- TryJPEG2000Codec2
 - gdcM::Bitmap, [231](#)
- TryJPEGCodec
 - gdcM::Bitmap, [231](#)
 - gdcM::ImageChangeTransferSyntax, [604](#)
- TryJPEGCodec2
 - gdcM::Bitmap, [231](#)
- TryJPEGLSCoec
 - gdcM::Bitmap, [231](#)
 - gdcM::ImageChangeTransferSyntax, [604](#)
- TryKAKADUCoec
 - gdcM::Bitmap, [231](#)
- TryPVRGCoec
 - gdcM::Bitmap, [232](#)
- TryRAWCoec
 - gdcM::Bitmap, [232](#)
 - gdcM::ImageChangeTransferSyntax, [604](#)
- TryRLECoec
 - gdcM::Bitmap, [232](#)
 - gdcM::ImageChangeTransferSyntax, [604](#)
- TS
 - gdcM::Bitmap, [234](#)
- TS_END
 - gdcM::TransferSyntax, [1218](#)
- TSName
 - gdcM::UIDs, [1247](#)
- TSType
 - gdcM::TransferSyntax, [1217](#)
 - gdcM::UIDs, [1256](#)
- Type
 - gdcM::Element< TVR, TVM >, [429](#)
 - gdcM::Element< TVR, VM::VM1_2 >, [436](#)
 - gdcM::Element< TVR, VM::VM2_2n >, [441](#)
 - gdcM::Element< TVR, VM::VM3_3n >, [446](#)
 - gdcM::Element< TVR, VM::VM3_4 >, [451](#)
 - gdcM::Element< VR::AS, VM::VM5 >, [455](#)
 - gdcM::Element< VR::OB, VM::VM1 >, [460](#)
 - gdcM::Element< VR::OW, VM::VM1 >, [465](#)
 - gdcM::EquipmentManufacturer, [481](#)
 - gdcM::Type, [1226](#)
 - gdcM::VL, [1360](#)
- TYPETOENCODING
 - gdcMVR.h, [1767](#)
- TYPETOLENGTH
 - gdcMVM.h, [1763](#)
- TypeToString
 - gdcM::EquipmentManufacturer, [481](#)
- TypeType
 - gdcM::Type, [1226](#)
- UberonOntology
 - gdcM::UIDs, [1253](#)
- UC
 - gdcM::VR, [1371](#)
- UCComp
 - gdcM, [60](#)
- UI
 - gdcM::VR, [1371](#)
- UIComp
 - gdcM, [60](#)
- uid_1_2_840_10008_15_0_3_1
 - gdcM::UIDs, [1262](#)
- uid_1_2_840_10008_15_0_3_10
 - gdcM::UIDs, [1262](#)
- uid_1_2_840_10008_15_0_3_11
 - gdcM::UIDs, [1262](#)

uid_1_2_840_10008_15_0_3_12
gdcn::UIDs, [1262](#)

uid_1_2_840_10008_15_0_3_13
gdcn::UIDs, [1262](#)

uid_1_2_840_10008_15_0_3_14
gdcn::UIDs, [1262](#)

uid_1_2_840_10008_15_0_3_15
gdcn::UIDs, [1262](#)

uid_1_2_840_10008_15_0_3_16
gdcn::UIDs, [1262](#)

uid_1_2_840_10008_15_0_3_17
gdcn::UIDs, [1262](#)

uid_1_2_840_10008_15_0_3_18
gdcn::UIDs, [1262](#)

uid_1_2_840_10008_15_0_3_19
gdcn::UIDs, [1262](#)

uid_1_2_840_10008_15_0_3_2
gdcn::UIDs, [1262](#)

uid_1_2_840_10008_15_0_3_20
gdcn::UIDs, [1262](#)

uid_1_2_840_10008_15_0_3_21
gdcn::UIDs, [1262](#)

uid_1_2_840_10008_15_0_3_22
gdcn::UIDs, [1262](#)

uid_1_2_840_10008_15_0_3_23
gdcn::UIDs, [1262](#)

uid_1_2_840_10008_15_0_3_24
gdcn::UIDs, [1262](#)

uid_1_2_840_10008_15_0_3_25
gdcn::UIDs, [1262](#)

uid_1_2_840_10008_15_0_3_26
gdcn::UIDs, [1262](#)

uid_1_2_840_10008_15_0_3_27
gdcn::UIDs, [1262](#)

uid_1_2_840_10008_15_0_3_28
gdcn::UIDs, [1262](#)

uid_1_2_840_10008_15_0_3_29
gdcn::UIDs, [1262](#)

uid_1_2_840_10008_15_0_3_3
gdcn::UIDs, [1262](#)

uid_1_2_840_10008_15_0_3_30
gdcn::UIDs, [1262](#)

uid_1_2_840_10008_15_0_3_31
gdcn::UIDs, [1262](#)

uid_1_2_840_10008_15_0_3_4
gdcn::UIDs, [1262](#)

uid_1_2_840_10008_15_0_3_5
gdcn::UIDs, [1262](#)

uid_1_2_840_10008_15_0_3_6
gdcn::UIDs, [1262](#)

uid_1_2_840_10008_15_0_3_7
gdcn::UIDs, [1262](#)

uid_1_2_840_10008_15_0_3_8
gdcn::UIDs, [1262](#)

uid_1_2_840_10008_15_0_3_9
gdcn::UIDs, [1262](#)

uid_1_2_840_10008_15_0_4_1
gdcn::UIDs, [1262](#)

uid_1_2_840_10008_15_0_4_2
gdcn::UIDs, [1262](#)

uid_1_2_840_10008_15_0_4_3
gdcn::UIDs, [1262](#)

uid_1_2_840_10008_15_0_4_4
gdcn::UIDs, [1262](#)

uid_1_2_840_10008_15_0_4_5
gdcn::UIDs, [1262](#)

uid_1_2_840_10008_15_0_4_6
gdcn::UIDs, [1262](#)

uid_1_2_840_10008_15_0_4_7
gdcn::UIDs, [1262](#)

uid_1_2_840_10008_15_0_4_8
gdcn::UIDs, [1262](#)

uid_1_2_840_10008_15_1_1
gdcn::UIDs, [1265](#)

uid_1_2_840_10008_1_1
gdcn::UIDs, [1256](#)

uid_1_2_840_10008_1_2
gdcn::UIDs, [1256](#)

uid_1_2_840_10008_1_20
gdcn::UIDs, [1263](#)

uid_1_2_840_10008_1_20_1
gdcn::UIDs, [1258](#)

uid_1_2_840_10008_1_20_1_1
gdcn::UIDs, [1258](#)

uid_1_2_840_10008_1_20_2
gdcn::UIDs, [1258](#)

uid_1_2_840_10008_1_20_2_1
gdcn::UIDs, [1258](#)

uid_1_2_840_10008_1_2_1
gdcn::UIDs, [1256](#)

uid_1_2_840_10008_1_2_1_99
gdcn::UIDs, [1256](#)

uid_1_2_840_10008_1_2_2
gdcn::UIDs, [1256](#)

uid_1_2_840_10008_1_2_4_100
gdcn::UIDs, [1257](#)

uid_1_2_840_10008_1_2_4_101
gdcn::UIDs, [1263](#)

uid_1_2_840_10008_1_2_4_102
gdcn::UIDs, [1263](#)

uid_1_2_840_10008_1_2_4_103
gdcn::UIDs, [1263](#)

uid_1_2_840_10008_1_2_4_104
gdcn::UIDs, [1263](#)

uid_1_2_840_10008_1_2_4_105
gdcn::UIDs, [1263](#)

uid_1_2_840_10008_1_2_4_106
gdcn::UIDs, [1263](#)

uid_1_2_840_10008_1_2_4_107
gdcmm::UIDs, [1263](#)

uid_1_2_840_10008_1_2_4_108
gdcmm::UIDs, [1263](#)

uid_1_2_840_10008_1_2_4_50
gdcmm::UIDs, [1257](#)

uid_1_2_840_10008_1_2_4_51
gdcmm::UIDs, [1257](#)

uid_1_2_840_10008_1_2_4_52
gdcmm::UIDs, [1257](#)

uid_1_2_840_10008_1_2_4_53
gdcmm::UIDs, [1257](#)

uid_1_2_840_10008_1_2_4_54
gdcmm::UIDs, [1257](#)

uid_1_2_840_10008_1_2_4_55
gdcmm::UIDs, [1257](#)

uid_1_2_840_10008_1_2_4_56
gdcmm::UIDs, [1257](#)

uid_1_2_840_10008_1_2_4_57
gdcmm::UIDs, [1257](#)

uid_1_2_840_10008_1_2_4_58
gdcmm::UIDs, [1257](#)

uid_1_2_840_10008_1_2_4_59
gdcmm::UIDs, [1257](#)

uid_1_2_840_10008_1_2_4_60
gdcmm::UIDs, [1257](#)

uid_1_2_840_10008_1_2_4_61
gdcmm::UIDs, [1257](#)

uid_1_2_840_10008_1_2_4_62
gdcmm::UIDs, [1257](#)

uid_1_2_840_10008_1_2_4_63
gdcmm::UIDs, [1257](#)

uid_1_2_840_10008_1_2_4_64
gdcmm::UIDs, [1257](#)

uid_1_2_840_10008_1_2_4_65
gdcmm::UIDs, [1257](#)

uid_1_2_840_10008_1_2_4_66
gdcmm::UIDs, [1257](#)

uid_1_2_840_10008_1_2_4_70
gdcmm::UIDs, [1257](#)

uid_1_2_840_10008_1_2_4_80
gdcmm::UIDs, [1257](#)

uid_1_2_840_10008_1_2_4_81
gdcmm::UIDs, [1257](#)

uid_1_2_840_10008_1_2_4_90
gdcmm::UIDs, [1257](#)

uid_1_2_840_10008_1_2_4_91
gdcmm::UIDs, [1257](#)

uid_1_2_840_10008_1_2_4_92
gdcmm::UIDs, [1257](#)

uid_1_2_840_10008_1_2_4_93
gdcmm::UIDs, [1257](#)

uid_1_2_840_10008_1_2_4_94
gdcmm::UIDs, [1257](#)

uid_1_2_840_10008_1_2_4_95
gdcmm::UIDs, [1257](#)

uid_1_2_840_10008_1_2_5
gdcmm::UIDs, [1257](#)

uid_1_2_840_10008_1_2_6_1
gdcmm::UIDs, [1257](#)

uid_1_2_840_10008_1_2_6_2
gdcmm::UIDs, [1257](#)

uid_1_2_840_10008_1_3_10
gdcmm::UIDs, [1257](#)

uid_1_2_840_10008_1_40
gdcmm::UIDs, [1258](#)

uid_1_2_840_10008_1_40_1
gdcmm::UIDs, [1258](#)

uid_1_2_840_10008_1_42
gdcmm::UIDs, [1258](#)

uid_1_2_840_10008_1_42_1
gdcmm::UIDs, [1258](#)

uid_1_2_840_10008_1_4_1_1
gdcmm::UIDs, [1257](#)

uid_1_2_840_10008_1_4_1_10
gdcmm::UIDs, [1257](#)

uid_1_2_840_10008_1_4_1_11
gdcmm::UIDs, [1257](#)

uid_1_2_840_10008_1_4_1_12
gdcmm::UIDs, [1257](#)

uid_1_2_840_10008_1_4_1_13
gdcmm::UIDs, [1257](#)

uid_1_2_840_10008_1_4_1_14
gdcmm::UIDs, [1257](#)

uid_1_2_840_10008_1_4_1_15
gdcmm::UIDs, [1257](#)

uid_1_2_840_10008_1_4_1_16
gdcmm::UIDs, [1258](#)

uid_1_2_840_10008_1_4_1_17
gdcmm::UIDs, [1258](#)

uid_1_2_840_10008_1_4_1_18
gdcmm::UIDs, [1258](#)

uid_1_2_840_10008_1_4_1_2
gdcmm::UIDs, [1257](#)

uid_1_2_840_10008_1_4_1_3
gdcmm::UIDs, [1257](#)

uid_1_2_840_10008_1_4_1_4
gdcmm::UIDs, [1257](#)

uid_1_2_840_10008_1_4_1_5
gdcmm::UIDs, [1257](#)

uid_1_2_840_10008_1_4_1_6
gdcmm::UIDs, [1257](#)

uid_1_2_840_10008_1_4_1_7
gdcmm::UIDs, [1257](#)

uid_1_2_840_10008_1_4_1_8
gdcmm::UIDs, [1257](#)

uid_1_2_840_10008_1_4_1_9
gdcmm::UIDs, [1257](#)

uid_1_2_840_10008_1_4_2_1
gdcml::UIDs, [1258](#)

uid_1_2_840_10008_1_4_2_2
gdcml::UIDs, [1258](#)

uid_1_2_840_10008_1_5_1
gdcml::UIDs, [1263](#)

uid_1_2_840_10008_1_5_2
gdcml::UIDs, [1263](#)

uid_1_2_840_10008_1_5_3
gdcml::UIDs, [1263](#)

uid_1_2_840_10008_1_5_4
gdcml::UIDs, [1263](#)

uid_1_2_840_10008_1_5_5
gdcml::UIDs, [1263](#)

uid_1_2_840_10008_1_5_6
gdcml::UIDs, [1263](#)

uid_1_2_840_10008_1_5_7
gdcml::UIDs, [1263](#)

uid_1_2_840_10008_1_5_8
gdcml::UIDs, [1263](#)

uid_1_2_840_10008_1_9
gdcml::UIDs, [1258](#)

uid_1_2_840_10008_2_16_10
gdcml::UIDs, [1263](#)

uid_1_2_840_10008_2_16_11
gdcml::UIDs, [1263](#)

uid_1_2_840_10008_2_16_12
gdcml::UIDs, [1263](#)

uid_1_2_840_10008_2_16_13
gdcml::UIDs, [1263](#)

uid_1_2_840_10008_2_16_14
gdcml::UIDs, [1263](#)

uid_1_2_840_10008_2_16_4
gdcml::UIDs, [1258](#)

uid_1_2_840_10008_2_16_5
gdcml::UIDs, [1263](#)

uid_1_2_840_10008_2_16_6
gdcml::UIDs, [1263](#)

uid_1_2_840_10008_2_16_7
gdcml::UIDs, [1263](#)

uid_1_2_840_10008_2_16_8
gdcml::UIDs, [1263](#)

uid_1_2_840_10008_2_16_9
gdcml::UIDs, [1263](#)

uid_1_2_840_10008_2_6_1
gdcml::UIDs, [1258](#)

uid_1_2_840_10008_3_1_1_1
gdcml::UIDs, [1258](#)

uid_1_2_840_10008_3_1_2_1_1
gdcml::UIDs, [1258](#)

uid_1_2_840_10008_3_1_2_1_4
gdcml::UIDs, [1258](#)

uid_1_2_840_10008_3_1_2_2_1
gdcml::UIDs, [1258](#)

uid_1_2_840_10008_3_1_2_3_1
gdcml::UIDs, [1258](#)

uid_1_2_840_10008_3_1_2_3_2
gdcml::UIDs, [1258](#)

uid_1_2_840_10008_3_1_2_3_3
gdcml::UIDs, [1258](#)

uid_1_2_840_10008_3_1_2_3_4
gdcml::UIDs, [1258](#)

uid_1_2_840_10008_3_1_2_3_5
gdcml::UIDs, [1258](#)

uid_1_2_840_10008_3_1_2_5_1
gdcml::UIDs, [1258](#)

uid_1_2_840_10008_3_1_2_5_4
gdcml::UIDs, [1258](#)

uid_1_2_840_10008_3_1_2_5_5
gdcml::UIDs, [1258](#)

uid_1_2_840_10008_3_1_2_6_1
gdcml::UIDs, [1258](#)

uid_1_2_840_10008_4_2
gdcml::UIDs, [1258](#)

uid_1_2_840_10008_5_1_1_1
gdcml::UIDs, [1258](#)

uid_1_2_840_10008_5_1_1_14
gdcml::UIDs, [1258](#)

uid_1_2_840_10008_5_1_1_15
gdcml::UIDs, [1258](#)

uid_1_2_840_10008_5_1_1_16
gdcml::UIDs, [1258](#)

uid_1_2_840_10008_5_1_1_16_376
gdcml::UIDs, [1258](#)

uid_1_2_840_10008_5_1_1_17
gdcml::UIDs, [1258](#)

uid_1_2_840_10008_5_1_1_17_376
gdcml::UIDs, [1258](#)

uid_1_2_840_10008_5_1_1_18
gdcml::UIDs, [1258](#)

uid_1_2_840_10008_5_1_1_18_1
gdcml::UIDs, [1258](#)

uid_1_2_840_10008_5_1_1_2
gdcml::UIDs, [1258](#)

uid_1_2_840_10008_5_1_1_22
gdcml::UIDs, [1258](#)

uid_1_2_840_10008_5_1_1_23
gdcml::UIDs, [1259](#)

uid_1_2_840_10008_5_1_1_24
gdcml::UIDs, [1259](#)

uid_1_2_840_10008_5_1_1_24_1
gdcml::UIDs, [1259](#)

uid_1_2_840_10008_5_1_1_25
gdcml::UIDs, [1259](#)

uid_1_2_840_10008_5_1_1_26
gdcml::UIDs, [1259](#)

uid_1_2_840_10008_5_1_1_27
gdcml::UIDs, [1259](#)

uid_1_2_840_10008_5_1_1_29
gdcm::UIDs, [1259](#)

uid_1_2_840_10008_5_1_1_30
gdcm::UIDs, [1259](#)

uid_1_2_840_10008_5_1_1_31
gdcm::UIDs, [1259](#)

uid_1_2_840_10008_5_1_1_32
gdcm::UIDs, [1259](#)

uid_1_2_840_10008_5_1_1_33
gdcm::UIDs, [1259](#)

uid_1_2_840_10008_5_1_1_4
gdcm::UIDs, [1258](#)

uid_1_2_840_10008_5_1_1_40
gdcm::UIDs, [1263](#)

uid_1_2_840_10008_5_1_1_40_1
gdcm::UIDs, [1263](#)

uid_1_2_840_10008_5_1_1_4_1
gdcm::UIDs, [1258](#)

uid_1_2_840_10008_5_1_1_4_2
gdcm::UIDs, [1258](#)

uid_1_2_840_10008_5_1_1_9
gdcm::UIDs, [1258](#)

uid_1_2_840_10008_5_1_1_9_1
gdcm::UIDs, [1258](#)

uid_1_2_840_10008_5_1_4_1_1_1
gdcm::UIDs, [1259](#)

uid_1_2_840_10008_5_1_4_1_1_10
gdcm::UIDs, [1259](#)

uid_1_2_840_10008_5_1_4_1_1_104_1
gdcm::UIDs, [1261](#)

uid_1_2_840_10008_5_1_4_1_1_104_2
gdcm::UIDs, [1261](#)

uid_1_2_840_10008_5_1_4_1_1_104_3
gdcm::UIDs, [1264](#)

uid_1_2_840_10008_5_1_4_1_1_11
gdcm::UIDs, [1259](#)

uid_1_2_840_10008_5_1_4_1_1_11_1
gdcm::UIDs, [1259](#)

uid_1_2_840_10008_5_1_4_1_1_11_10
gdcm::UIDs, [1263](#)

uid_1_2_840_10008_5_1_4_1_1_11_11
gdcm::UIDs, [1263](#)

uid_1_2_840_10008_5_1_4_1_1_11_2
gdcm::UIDs, [1259](#)

uid_1_2_840_10008_5_1_4_1_1_11_3
gdcm::UIDs, [1260](#)

uid_1_2_840_10008_5_1_4_1_1_11_4
gdcm::UIDs, [1260](#)

uid_1_2_840_10008_5_1_4_1_1_11_5
gdcm::UIDs, [1263](#)

uid_1_2_840_10008_5_1_4_1_1_11_6
gdcm::UIDs, [1263](#)

uid_1_2_840_10008_5_1_4_1_1_11_7
gdcm::UIDs, [1263](#)

uid_1_2_840_10008_5_1_4_1_1_11_8
gdcm::UIDs, [1263](#)

uid_1_2_840_10008_5_1_4_1_1_11_9
gdcm::UIDs, [1263](#)

uid_1_2_840_10008_5_1_4_1_1_128
gdcm::UIDs, [1261](#)

uid_1_2_840_10008_5_1_4_1_1_128_1
gdcm::UIDs, [1262](#)

uid_1_2_840_10008_5_1_4_1_1_129
gdcm::UIDs, [1261](#)

uid_1_2_840_10008_5_1_4_1_1_12_1
gdcm::UIDs, [1260](#)

uid_1_2_840_10008_5_1_4_1_1_12_1_1
gdcm::UIDs, [1260](#)

uid_1_2_840_10008_5_1_4_1_1_12_2
gdcm::UIDs, [1260](#)

uid_1_2_840_10008_5_1_4_1_1_12_2_1
gdcm::UIDs, [1260](#)

uid_1_2_840_10008_5_1_4_1_1_12_3
gdcm::UIDs, [1260](#)

uid_1_2_840_10008_5_1_4_1_1_12_77
gdcm::UIDs, [1263](#)

uid_1_2_840_10008_5_1_4_1_1_130
gdcm::UIDs, [1264](#)

uid_1_2_840_10008_5_1_4_1_1_131
gdcm::UIDs, [1264](#)

uid_1_2_840_10008_5_1_4_1_1_13_1_1
gdcm::UIDs, [1260](#)

uid_1_2_840_10008_5_1_4_1_1_13_1_2
gdcm::UIDs, [1260](#)

uid_1_2_840_10008_5_1_4_1_1_13_1_3
gdcm::UIDs, [1262](#)

uid_1_2_840_10008_5_1_4_1_1_13_1_4
gdcm::UIDs, [1263](#)

uid_1_2_840_10008_5_1_4_1_1_13_1_5
gdcm::UIDs, [1263](#)

uid_1_2_840_10008_5_1_4_1_1_14_1
gdcm::UIDs, [1263](#)

uid_1_2_840_10008_5_1_4_1_1_14_2
gdcm::UIDs, [1263](#)

uid_1_2_840_10008_5_1_4_1_1_1_1
gdcm::UIDs, [1259](#)

uid_1_2_840_10008_5_1_4_1_1_1_1_1
gdcm::UIDs, [1259](#)

uid_1_2_840_10008_5_1_4_1_1_1_2
gdcm::UIDs, [1259](#)

uid_1_2_840_10008_5_1_4_1_1_1_2_1
gdcm::UIDs, [1259](#)

uid_1_2_840_10008_5_1_4_1_1_1_3
gdcm::UIDs, [1259](#)

uid_1_2_840_10008_5_1_4_1_1_1_3_1
gdcm::UIDs, [1259](#)

uid_1_2_840_10008_5_1_4_1_1_2
gdcm::UIDs, [1259](#)

uid_1_2_840_10008_5_1_4_1_1_20
gdcm::UIDs, [1260](#)

uid_1_2_840_10008_5_1_4_1_1_200_1
gdcm::UIDs, [1264](#)

uid_1_2_840_10008_5_1_4_1_1_200_2
gdcm::UIDs, [1264](#)

uid_1_2_840_10008_5_1_4_1_1_200_3
gdcm::UIDs, [1264](#)

uid_1_2_840_10008_5_1_4_1_1_200_4
gdcm::UIDs, [1264](#)

uid_1_2_840_10008_5_1_4_1_1_200_5
gdcm::UIDs, [1264](#)

uid_1_2_840_10008_5_1_4_1_1_200_6
gdcm::UIDs, [1264](#)

uid_1_2_840_10008_5_1_4_1_1_2_1
gdcm::UIDs, [1259](#)

uid_1_2_840_10008_5_1_4_1_1_2_2
gdcm::UIDs, [1262](#)

uid_1_2_840_10008_5_1_4_1_1_3
gdcm::UIDs, [1259](#)

uid_1_2_840_10008_5_1_4_1_1_30
gdcm::UIDs, [1263](#)

uid_1_2_840_10008_5_1_4_1_1_3_1
gdcm::UIDs, [1259](#)

uid_1_2_840_10008_5_1_4_1_1_4
gdcm::UIDs, [1259](#)

uid_1_2_840_10008_5_1_4_1_1_40
gdcm::UIDs, [1263](#)

uid_1_2_840_10008_5_1_4_1_1_481_1
gdcm::UIDs, [1261](#)

uid_1_2_840_10008_5_1_4_1_1_481_10
gdcm::UIDs, [1264](#)

uid_1_2_840_10008_5_1_4_1_1_481_11
gdcm::UIDs, [1264](#)

uid_1_2_840_10008_5_1_4_1_1_481_2
gdcm::UIDs, [1261](#)

uid_1_2_840_10008_5_1_4_1_1_481_3
gdcm::UIDs, [1261](#)

uid_1_2_840_10008_5_1_4_1_1_481_4
gdcm::UIDs, [1261](#)

uid_1_2_840_10008_5_1_4_1_1_481_5
gdcm::UIDs, [1261](#)

uid_1_2_840_10008_5_1_4_1_1_481_6
gdcm::UIDs, [1261](#)

uid_1_2_840_10008_5_1_4_1_1_481_7
gdcm::UIDs, [1261](#)

uid_1_2_840_10008_5_1_4_1_1_481_8
gdcm::UIDs, [1261](#)

uid_1_2_840_10008_5_1_4_1_1_481_9
gdcm::UIDs, [1261](#)

uid_1_2_840_10008_5_1_4_1_1_4_1
gdcm::UIDs, [1259](#)

uid_1_2_840_10008_5_1_4_1_1_4_2
gdcm::UIDs, [1259](#)

uid_1_2_840_10008_5_1_4_1_1_4_3
gdcm::UIDs, [1265](#)

uid_1_2_840_10008_5_1_4_1_1_4_4
gdcm::UIDs, [1262](#)

uid_1_2_840_10008_5_1_4_1_1_5
gdcm::UIDs, [1259](#)

uid_1_2_840_10008_5_1_4_1_1_501_1
gdcm::UIDs, [1264](#)

uid_1_2_840_10008_5_1_4_1_1_501_2_1
gdcm::UIDs, [1264](#)

uid_1_2_840_10008_5_1_4_1_1_501_2_2
gdcm::UIDs, [1265](#)

uid_1_2_840_10008_5_1_4_1_1_501_3
gdcm::UIDs, [1265](#)

uid_1_2_840_10008_5_1_4_1_1_501_4
gdcm::UIDs, [1265](#)

uid_1_2_840_10008_5_1_4_1_1_501_5
gdcm::UIDs, [1265](#)

uid_1_2_840_10008_5_1_4_1_1_501_6
gdcm::UIDs, [1265](#)

uid_1_2_840_10008_5_1_4_1_1_6
gdcm::UIDs, [1259](#)

uid_1_2_840_10008_5_1_4_1_1_601_1
gdcm::UIDs, [1265](#)

uid_1_2_840_10008_5_1_4_1_1_601_2
gdcm::UIDs, [1265](#)

uid_1_2_840_10008_5_1_4_1_1_66
gdcm::UIDs, [1260](#)

uid_1_2_840_10008_5_1_4_1_1_66_1
gdcm::UIDs, [1260](#)

uid_1_2_840_10008_5_1_4_1_1_66_2
gdcm::UIDs, [1260](#)

uid_1_2_840_10008_5_1_4_1_1_66_3
gdcm::UIDs, [1260](#)

uid_1_2_840_10008_5_1_4_1_1_66_4
gdcm::UIDs, [1260](#)

uid_1_2_840_10008_5_1_4_1_1_66_5
gdcm::UIDs, [1262](#)

uid_1_2_840_10008_5_1_4_1_1_66_6
gdcm::UIDs, [1264](#)

uid_1_2_840_10008_5_1_4_1_1_67
gdcm::UIDs, [1260](#)

uid_1_2_840_10008_5_1_4_1_1_68_1
gdcm::UIDs, [1264](#)

uid_1_2_840_10008_5_1_4_1_1_68_2
gdcm::UIDs, [1264](#)

uid_1_2_840_10008_5_1_4_1_1_6_1
gdcm::UIDs, [1259](#)

uid_1_2_840_10008_5_1_4_1_1_6_2
gdcm::UIDs, [1262](#)

uid_1_2_840_10008_5_1_4_1_1_7
gdcm::UIDs, [1259](#)

uid_1_2_840_10008_5_1_4_1_1_77_1
gdcm::UIDs, [1260](#)

uid_1_2_840_10008_5_1_4_1_1_77_1_1
gdcm::UIDs, [1260](#)

uid_1_2_840_10008_5_1_4_1_1_77_1_1_1
gdcm::UIDs, [1260](#)

uid_1_2_840_10008_5_1_4_1_1_77_1_2
gdcm::UIDs, [1260](#)

uid_1_2_840_10008_5_1_4_1_1_77_1_2_1
gdcm::UIDs, [1260](#)

uid_1_2_840_10008_5_1_4_1_1_77_1_3
gdcm::UIDs, [1260](#)

uid_1_2_840_10008_5_1_4_1_1_77_1_4
gdcm::UIDs, [1260](#)

uid_1_2_840_10008_5_1_4_1_1_77_1_4_1
gdcm::UIDs, [1260](#)

uid_1_2_840_10008_5_1_4_1_1_77_1_5_1
gdcm::UIDs, [1260](#)

uid_1_2_840_10008_5_1_4_1_1_77_1_5_2
gdcm::UIDs, [1260](#)

uid_1_2_840_10008_5_1_4_1_1_77_1_5_3
gdcm::UIDs, [1260](#)

uid_1_2_840_10008_5_1_4_1_1_77_1_5_4
gdcm::UIDs, [1260](#)

uid_1_2_840_10008_5_1_4_1_1_77_1_5_5
gdcm::UIDs, [1264](#)

uid_1_2_840_10008_5_1_4_1_1_77_1_5_6
gdcm::UIDs, [1264](#)

uid_1_2_840_10008_5_1_4_1_1_77_1_5_7
gdcm::UIDs, [1264](#)

uid_1_2_840_10008_5_1_4_1_1_77_1_5_8
gdcm::UIDs, [1264](#)

uid_1_2_840_10008_5_1_4_1_1_77_1_6
gdcm::UIDs, [1262](#)

uid_1_2_840_10008_5_1_4_1_1_77_2
gdcm::UIDs, [1260](#)

uid_1_2_840_10008_5_1_4_1_1_78_1
gdcm::UIDs, [1264](#)

uid_1_2_840_10008_5_1_4_1_1_78_2
gdcm::UIDs, [1264](#)

uid_1_2_840_10008_5_1_4_1_1_78_3
gdcm::UIDs, [1264](#)

uid_1_2_840_10008_5_1_4_1_1_78_4
gdcm::UIDs, [1264](#)

uid_1_2_840_10008_5_1_4_1_1_78_5
gdcm::UIDs, [1264](#)

uid_1_2_840_10008_5_1_4_1_1_78_6
gdcm::UIDs, [1264](#)

uid_1_2_840_10008_5_1_4_1_1_78_7
gdcm::UIDs, [1264](#)

uid_1_2_840_10008_5_1_4_1_1_78_8
gdcm::UIDs, [1264](#)

uid_1_2_840_10008_5_1_4_1_1_79_1
gdcm::UIDs, [1264](#)

uid_1_2_840_10008_5_1_4_1_1_7_1
gdcm::UIDs, [1259](#)

uid_1_2_840_10008_5_1_4_1_1_7_2
gdcm::UIDs, [1259](#)

uid_1_2_840_10008_5_1_4_1_1_7_3
gdcm::UIDs, [1259](#)

uid_1_2_840_10008_5_1_4_1_1_7_4
gdcm::UIDs, [1259](#)

uid_1_2_840_10008_5_1_4_1_1_8
gdcm::UIDs, [1259](#)

uid_1_2_840_10008_5_1_4_1_1_80_1
gdcm::UIDs, [1264](#)

uid_1_2_840_10008_5_1_4_1_1_81_1
gdcm::UIDs, [1264](#)

uid_1_2_840_10008_5_1_4_1_1_82_1
gdcm::UIDs, [1264](#)

uid_1_2_840_10008_5_1_4_1_1_88_1
gdcm::UIDs, [1260](#)

uid_1_2_840_10008_5_1_4_1_1_88_11
gdcm::UIDs, [1260](#)

uid_1_2_840_10008_5_1_4_1_1_88_2
gdcm::UIDs, [1260](#)

uid_1_2_840_10008_5_1_4_1_1_88_22
gdcm::UIDs, [1260](#)

uid_1_2_840_10008_5_1_4_1_1_88_3
gdcm::UIDs, [1260](#)

uid_1_2_840_10008_5_1_4_1_1_88_33
gdcm::UIDs, [1260](#)

uid_1_2_840_10008_5_1_4_1_1_88_34
gdcm::UIDs, [1264](#)

uid_1_2_840_10008_5_1_4_1_1_88_35
gdcm::UIDs, [1264](#)

uid_1_2_840_10008_5_1_4_1_1_88_4
gdcm::UIDs, [1260](#)

uid_1_2_840_10008_5_1_4_1_1_88_40
gdcm::UIDs, [1260](#)

uid_1_2_840_10008_5_1_4_1_1_88_50
gdcm::UIDs, [1260](#)

uid_1_2_840_10008_5_1_4_1_1_88_59
gdcm::UIDs, [1260](#)

uid_1_2_840_10008_5_1_4_1_1_88_65
gdcm::UIDs, [1260](#)

uid_1_2_840_10008_5_1_4_1_1_88_67
gdcm::UIDs, [1261](#)

uid_1_2_840_10008_5_1_4_1_1_88_68
gdcm::UIDs, [1264](#)

uid_1_2_840_10008_5_1_4_1_1_88_69
gdcm::UIDs, [1264](#)

uid_1_2_840_10008_5_1_4_1_1_88_70
gdcm::UIDs, [1264](#)

uid_1_2_840_10008_5_1_4_1_1_88_71
gdcm::UIDs, [1264](#)

uid_1_2_840_10008_5_1_4_1_1_88_72
gdcm::UIDs, [1264](#)

uid_1_2_840_10008_5_1_4_1_1_88_73
gdcm::UIDs, [1264](#)

uid_1_2_840_10008_5_1_4_1_1_88_74
gdcm::UIDs, [1264](#)

uid_1_2_840_10008_5_1_4_1_1_88_75
gdcm::UIDs, [1264](#)

uid_1_2_840_10008_5_1_4_1_1_9
gdcm::UIDs, [1259](#)

uid_1_2_840_10008_5_1_4_1_1_90_1
gdcm::UIDs, [1264](#)

uid_1_2_840_10008_5_1_4_1_1_9_1
gdcm::UIDs, [1259](#)

uid_1_2_840_10008_5_1_4_1_1_9_1_1
gdcm::UIDs, [1259](#)

uid_1_2_840_10008_5_1_4_1_1_9_1_2
gdcm::UIDs, [1259](#)

uid_1_2_840_10008_5_1_4_1_1_9_1_3
gdcm::UIDs, [1259](#)

uid_1_2_840_10008_5_1_4_1_1_9_2_1
gdcm::UIDs, [1259](#)

uid_1_2_840_10008_5_1_4_1_1_9_3_1
gdcm::UIDs, [1259](#)

uid_1_2_840_10008_5_1_4_1_1_9_4_1
gdcm::UIDs, [1259](#)

uid_1_2_840_10008_5_1_4_1_1_9_4_2
gdcm::UIDs, [1263](#)

uid_1_2_840_10008_5_1_4_1_1_9_5_1
gdcm::UIDs, [1263](#)

uid_1_2_840_10008_5_1_4_1_1_9_6_1
gdcm::UIDs, [1263](#)

uid_1_2_840_10008_5_1_4_1_2_1_1
gdcm::UIDs, [1261](#)

uid_1_2_840_10008_5_1_4_1_2_1_2
gdcm::UIDs, [1261](#)

uid_1_2_840_10008_5_1_4_1_2_1_3
gdcm::UIDs, [1261](#)

uid_1_2_840_10008_5_1_4_1_2_2_1
gdcm::UIDs, [1261](#)

uid_1_2_840_10008_5_1_4_1_2_2_2
gdcm::UIDs, [1261](#)

uid_1_2_840_10008_5_1_4_1_2_2_3
gdcm::UIDs, [1261](#)

uid_1_2_840_10008_5_1_4_1_2_3_1
gdcm::UIDs, [1261](#)

uid_1_2_840_10008_5_1_4_1_2_3_2
gdcm::UIDs, [1261](#)

uid_1_2_840_10008_5_1_4_1_2_3_3
gdcm::UIDs, [1261](#)

uid_1_2_840_10008_5_1_4_1_2_4_2
gdcm::UIDs, [1265](#)

uid_1_2_840_10008_5_1_4_1_2_4_3
gdcm::UIDs, [1265](#)

uid_1_2_840_10008_5_1_4_1_2_5_3
gdcm::UIDs, [1265](#)

uid_1_2_840_10008_5_1_4_20_1
gdcm::UIDs, [1265](#)

uid_1_2_840_10008_5_1_4_20_2
gdcm::UIDs, [1265](#)

uid_1_2_840_10008_5_1_4_20_3
gdcm::UIDs, [1265](#)

uid_1_2_840_10008_5_1_4_31
gdcm::UIDs, [1261](#)

uid_1_2_840_10008_5_1_4_32
gdcm::UIDs, [1261](#)

uid_1_2_840_10008_5_1_4_32_1
gdcm::UIDs, [1261](#)

uid_1_2_840_10008_5_1_4_32_2
gdcm::UIDs, [1261](#)

uid_1_2_840_10008_5_1_4_32_3
gdcm::UIDs, [1261](#)

uid_1_2_840_10008_5_1_4_33
gdcm::UIDs, [1261](#)

uid_1_2_840_10008_5_1_4_34_1
gdcm::UIDs, [1261](#)

uid_1_2_840_10008_5_1_4_34_10
gdcm::UIDs, [1265](#)

uid_1_2_840_10008_5_1_4_34_2
gdcm::UIDs, [1261](#)

uid_1_2_840_10008_5_1_4_34_3
gdcm::UIDs, [1261](#)

uid_1_2_840_10008_5_1_4_34_4
gdcm::UIDs, [1261](#)

uid_1_2_840_10008_5_1_4_34_4_1
gdcm::UIDs, [1261](#)

uid_1_2_840_10008_5_1_4_34_4_2
gdcm::UIDs, [1261](#)

uid_1_2_840_10008_5_1_4_34_4_3
gdcm::UIDs, [1261](#)

uid_1_2_840_10008_5_1_4_34_4_4
gdcm::UIDs, [1261](#)

uid_1_2_840_10008_5_1_4_34_5
gdcm::UIDs, [1261](#)

uid_1_2_840_10008_5_1_4_34_5_1
gdcm::UIDs, [1265](#)

uid_1_2_840_10008_5_1_4_34_6
gdcm::UIDs, [1265](#)

uid_1_2_840_10008_5_1_4_34_6_1
gdcm::UIDs, [1265](#)

uid_1_2_840_10008_5_1_4_34_6_2
gdcm::UIDs, [1265](#)

uid_1_2_840_10008_5_1_4_34_6_3
gdcm::UIDs, [1265](#)

uid_1_2_840_10008_5_1_4_34_6_4
gdcm::UIDs, [1265](#)

uid_1_2_840_10008_5_1_4_34_7
gdcm::UIDs, [1265](#)

uid_1_2_840_10008_5_1_4_34_8
gdcm::UIDs, [1265](#)

uid_1_2_840_10008_5_1_4_34_9
gdcm::UIDs, [1265](#)

- uid_1_2_840_10008_5_1_4_37_1
 - gdcm::UIDs, [1261](#)
- uid_1_2_840_10008_5_1_4_37_2
 - gdcm::UIDs, [1261](#)
- uid_1_2_840_10008_5_1_4_37_3
 - gdcm::UIDs, [1261](#)
- uid_1_2_840_10008_5_1_4_38_1
 - gdcm::UIDs, [1261](#)
- uid_1_2_840_10008_5_1_4_38_2
 - gdcm::UIDs, [1261](#)
- uid_1_2_840_10008_5_1_4_38_3
 - gdcm::UIDs, [1261](#)
- uid_1_2_840_10008_5_1_4_38_4
 - gdcm::UIDs, [1265](#)
- uid_1_2_840_10008_5_1_4_39_1
 - gdcm::UIDs, [1265](#)
- uid_1_2_840_10008_5_1_4_39_2
 - gdcm::UIDs, [1265](#)
- uid_1_2_840_10008_5_1_4_39_3
 - gdcm::UIDs, [1265](#)
- uid_1_2_840_10008_5_1_4_39_4
 - gdcm::UIDs, [1265](#)
- uid_1_2_840_10008_5_1_4_41
 - gdcm::UIDs, [1261](#)
- uid_1_2_840_10008_5_1_4_42
 - gdcm::UIDs, [1261](#)
- uid_1_2_840_10008_5_1_4_43_1
 - gdcm::UIDs, [1265](#)
- uid_1_2_840_10008_5_1_4_43_2
 - gdcm::UIDs, [1265](#)
- uid_1_2_840_10008_5_1_4_43_3
 - gdcm::UIDs, [1265](#)
- uid_1_2_840_10008_5_1_4_43_4
 - gdcm::UIDs, [1265](#)
- uid_1_2_840_10008_5_1_4_44_1
 - gdcm::UIDs, [1265](#)
- uid_1_2_840_10008_5_1_4_44_2
 - gdcm::UIDs, [1265](#)
- uid_1_2_840_10008_5_1_4_44_3
 - gdcm::UIDs, [1265](#)
- uid_1_2_840_10008_5_1_4_44_4
 - gdcm::UIDs, [1265](#)
- uid_1_2_840_10008_5_1_4_45_1
 - gdcm::UIDs, [1265](#)
- uid_1_2_840_10008_5_1_4_45_2
 - gdcm::UIDs, [1265](#)
- uid_1_2_840_10008_5_1_4_45_3
 - gdcm::UIDs, [1265](#)
- uid_1_2_840_10008_5_1_4_45_4
 - gdcm::UIDs, [1265](#)
- uid_1_2_840_10008_7_1_1
 - gdcm::UIDs, [1265](#)
- uid_1_2_840_10008_7_1_2
 - gdcm::UIDs, [1265](#)
- uid_1_2_840_10008_8_1_1
 - gdcm::UIDs, [1265](#)
- UIDGenerator
 - gdcm::UIDGenerator, [1229](#)
- UIDs
 - gdcm::UIDs, [1266](#)
- UIH
 - gdcm::EquipmentManufacturer, [481](#)
- UINT12
 - gdcm::PixelFormat, [880](#)
- UINT16
 - gdcm::PixelFormat, [880](#)
- UINT32
 - gdcm::PixelFormat, [880](#)
- UINT64
 - gdcm::PixelFormat, [880](#)
- UINT8
 - gdcm::PixelFormat, [880](#)
- UL
 - gdcm::VR, [1371](#)
- ULAction
 - gdcm::network::ULAction, [1269](#), [1270](#)
- ULActionAE6
 - gdcm::network::ULConnection, [1315](#)
- ULBasicCallback
 - gdcm::network::ULBasicCallback, [1310](#)
- ULConnection
 - gdcm::network::ULConnection, [1312](#)
- ULConnectionCallback
 - gdcm::network::ULConnectionCallback, [1317](#)
- ULConnectionInfo
 - gdcm::network::ULConnectionInfo, [1319](#)
- ULConnectionManager
 - gdcm::network::ULConnection, [1315](#)
 - gdcm::network::ULConnectionManager, [1323](#)
- ULEvent
 - gdcm::network::ULEvent, [1328](#)
- ULTransitionTable
 - gdcm::network::ULTransitionTable, [1330](#)
- UltrasoundImageStorage
 - gdcm::MediaStorage, [748](#)
 - gdcm::UIDs, [1250](#)
- UltrasoundImageStorageRetired
 - gdcm::MediaStorage, [748](#)
 - gdcm::UIDs, [1250](#)
- UltrasoundMultiFrameImageStorage
 - gdcm::MediaStorage, [748](#)
- UltrasoundMultiframeImageStorage
 - gdcm::UIDs, [1250](#)
- UltrasoundMultiFrameImageStorageRetired
 - gdcm::MediaStorage, [748](#)
- UltrasoundMultiframeImageStorageRetired
 - gdcm::UIDs, [1249](#)
- ULWritingCallback

- gdcm::network::ULWritingCallback, [1332](#)
- UN
 - gdcm::VR, [1371](#)
- UndefinedEntityError
 - gdcm::Parser, [850](#)
- underline
 - gdcm::terminal, [81](#)
- UnexpectedStateError
 - gdcm::Parser, [850](#)
- UnifiedProcedureStepEventSOPClass
 - gdcm::UIDs, [1252](#)
- UnifiedProcedureStepEventSOPClass1
 - gdcm::UIDs, [1256](#)
- UnifiedProcedureStepPullSOPClass
 - gdcm::UIDs, [1252](#)
- UnifiedProcedureStepPullSOPClass1
 - gdcm::UIDs, [1256](#)
- UnifiedProcedureStepPushSOPClass
 - gdcm::UIDs, [1252](#)
- UnifiedProcedureStepPushSOPClass1
 - gdcm::UIDs, [1256](#)
- UnifiedProcedureStepWatchSOPClass
 - gdcm::UIDs, [1252](#)
- UnifiedProcedureStepWatchSOPClass1
 - gdcm::UIDs, [1256](#)
- UnifiedWorklistandProcedureStepServiceClass
 - gdcm::UIDs, [1252](#)
- UnifiedWorklistandProcedureStepServiceClass1
 - gdcm::UIDs, [1256](#)
- UnifiedWorklistandProcedureStepSOPInstance
 - gdcm::UIDs, [1252](#)
- UnInstallPipeline
 - vtkImageColorViewer, [1458](#)
- UniversalCoordinatedTime
 - gdcm::UIDs, [1256](#)
- UNKNOWN
 - gdcm::CSAHeader, [321](#)
 - gdcm::EquipmentManufacturer, [481](#)
 - gdcm::LookupTable, [728](#)
 - gdcm::Orientation, [835](#)
 - gdcm::PhotometricInterpretation, [876](#)
 - gdcm::PixelFormat, [880](#)
 - gdcm::Spacing, [1095](#)
 - gdcm::Surface, [1149](#)
 - gdcm::Type, [1226](#)
- Unknown
 - gdcm::SwapCode, [1172](#)
 - gdcm::TransferSyntax, [1217](#)
- Unpack
 - gdcm::Unpacker12Bits, [1341](#)
- UnRegister
 - gdcm::Object, [822](#)
- UnusedBitsPresentInPixelData
 - gdcm::Bitmap, [232](#)
- gdcm::Pixmap, [893](#)
- Update
 - gdcm::Curve, [339](#)
 - gdcm::Overlay, [846](#)
- UpdateDisplayExtent
 - vtkImageColorViewer, [1458](#)
- UpdateOrientation
 - vtkImageColorViewer, [1459](#)
- UpdatePosition
 - gdcm::ByteBuffer, [243](#)
- UPSFilteredGlobalSubscriptionSOPInstance
 - gdcm::UIDs, [1255](#)
- UR
 - gdcm::VR, [1371](#)
- URComp
 - gdcm, [60](#)
- URI
 - gdcm::MediaStorage, [750](#)
- US
 - gdcm::VR, [1371](#)
- US_OW
 - gdcm::VR, [1371](#)
- US_SS
 - gdcm::VR, [1371](#)
- US_SS_OW
 - gdcm::VR, [1371](#)
- Usage
 - gdcm::Usage, [1343](#)
- UsageType
 - gdcm::Usage, [1343](#)
- UseDictAlways
 - gdcm::PythonFilter, [953](#)
 - gdcm::StringFilter, [1142](#)
- UseGrayscaleSecondaryImageStorage
 - gdcm::EmptyMaskGenerator, [471](#)
- UseOriginalSOPClassUID
 - gdcm::EmptyMaskGenerator, [471](#)
- UserInfoation
 - gdcm::network::UserInformation, [1347](#)
- UserOption
 - gdcm::Usage, [1343](#)
- UserOrdering
 - gdcm::SerieHelper, [1059](#)
- UT
 - gdcm::VR, [1371](#)
- UTComp
 - gdcm, [60](#)
- UV
 - gdcm::VR, [1371](#)
- V
 - gdcm::Validate, [1351](#)
- Valid
 - gdcm::Preamble, [914](#)

- Validate
 - gdcm::PixelFormat, [886](#)
 - gdcm::Validate, [1350](#)
- ValidateQuery
 - gdcm::BaseQuery, [206](#)
 - gdcm::BaseRootQuery, [211](#)
 - gdcm::FindPatientRootQuery, [554](#)
 - gdcm::FindStudyRootQuery, [558](#)
 - gdcm::ModalityPerformedProcedureStepCreateQuery, [768](#)
 - gdcm::ModalityPerformedProcedureStepSetQuery, [771](#)
 - gdcm::MovePatientRootQuery, [787](#)
 - gdcm::MoveStudyRootQuery, [791](#)
 - gdcm::WLMFindQuery, [1497](#)
- Validation
 - gdcm::Validate, [1351](#)
- ValidDataSet
 - gdcm::BaseQuery, [206](#)
- Value
 - gdcm::Value, [1353](#)
- value
 - gdcm::STATIC_ASSERTION_FAILURE< true >, [1103](#)
- value_type
 - gdcm::CodeString, [285](#)
 - gdcm::LO, [725](#)
 - gdcm::String< TDelimiter, TMaxLength, TPadChar >, [1136](#)
- ValueField
 - gdcm::DataElement, [353](#)
 - gdcm::PDBElement, [859](#)
- ValueLengthField
 - gdcm::DataElement, [353](#)
- ValueMultiplicityField
 - gdcm::CSAElement, [319](#)
- ValuePtr
 - gdcm::DataElement, [343](#)
- ValueType
 - gdcm::Scanner, [1000](#)
 - gdcm::Scanner2, [1009](#)
 - gdcm::StrictScanner, [1118](#)
 - gdcm::StrictScanner2, [1127](#)
- VERBOSE_STYLE
 - gdcm::Printer, [933](#)
- VerificationSOPClass
 - gdcm::UIDs, [1247](#)
- Verify
 - gdcm::Defs, [381](#)
 - gdcm::Macro, [738](#)
 - gdcm::Module, [776](#)
- Version
 - gdcm::Version, [1357](#)
- VERTEX
 - gdcm::MeshPrimitive, [762](#)
- Video
 - gdcm::MediaStorage, [750](#)
- VideoEndoscopicImageStorage
 - gdcm::MediaStorage, [749](#)
 - gdcm::UIDs, [1251](#)
- VideoMicroscopicImageStorage
 - gdcm::MediaStorage, [750](#)
 - gdcm::UIDs, [1251](#)
- VideoPhotographicImageStorage
 - gdcm::MediaStorage, [749](#)
 - gdcm::UIDs, [1251](#)
- VIEWType
 - gdcm::Surface, [1149](#)
- VIEWType_END
 - gdcm::Surface, [1150](#)
- VisualAcuityMeasurementsStorage
 - gdcm::UIDs, [1254](#)
- VL
 - gdcm::VL, [1360](#)
- VL16
 - gdcm::VR, [1371](#)
- VL32
 - gdcm::VR, [1371](#)
- VLEndoscopicImageStorage
 - gdcm::MediaStorage, [749](#)
 - gdcm::UIDs, [1251](#)
- VLImageStorageTrialRetired
 - gdcm::UIDs, [1250](#)
- VLMicroscopicImageStorage
 - gdcm::MediaStorage, [749](#)
 - gdcm::UIDs, [1251](#)
- VLMultiframeImageStorageTrialRetired
 - gdcm::UIDs, [1250](#)
- VLPhotographicImageStorage
 - gdcm::MediaStorage, [749](#)
 - gdcm::UIDs, [1251](#)
- VLSlideCoordinatesMicroscopicImageStorage
 - gdcm::UIDs, [1251](#)
- VLWholeSlideMicroscopyImageStorage
 - gdcm::MediaStorage, [749](#)
 - gdcm::UIDs, [1253](#)
- VM
 - gdcm::VM, [1366](#)
- VM0
 - gdcm::VM, [1366](#)
- VM1
 - gdcm::VM, [1366](#)
- VM10
 - gdcm::VM, [1366](#)
- VM12
 - gdcm::VM, [1366](#)
- VM16
 - gdcm::VM, [1366](#)

- VM18
 - gdcm::VM, [1366](#)
- VM1_2
 - gdcm::VM, [1366](#)
- VM1_3
 - gdcm::VM, [1366](#)
- VM1_32
 - gdcm::VM, [1366](#)
- VM1_4
 - gdcm::VM, [1366](#)
- VM1_5
 - gdcm::VM, [1366](#)
- VM1_8
 - gdcm::VM, [1366](#)
- VM1_99
 - gdcm::VM, [1366](#)
- VM1_n
 - gdcm::VM, [1366](#)
- VM2
 - gdcm::VM, [1366](#)
- VM24
 - gdcm::VM, [1366](#)
- VM256
 - gdcm::VM, [1366](#)
- VM28
 - gdcm::VM, [1366](#)
- VM2_2n
 - gdcm::VM, [1366](#)
- VM2_n
 - gdcm::VM, [1366](#)
- VM3
 - gdcm::VM, [1366](#)
- VM30_30n
 - gdcm::VM, [1366](#)
- VM32
 - gdcm::VM, [1366](#)
- VM35
 - gdcm::VM, [1366](#)
- VM3_3n
 - gdcm::VM, [1366](#)
- VM3_4
 - gdcm::VM, [1366](#)
- VM3_n
 - gdcm::VM, [1366](#)
- VM4
 - gdcm::VM, [1366](#)
- VM47_47n
 - gdcm::VM, [1366](#)
- VM4_4n
 - gdcm::VM, [1366](#)
- VM5
 - gdcm::VM, [1366](#)
- VM6
 - gdcm::VM, [1366](#)
- VM6_6n
 - gdcm::VM, [1366](#)
- VM6_n
 - gdcm::VM, [1366](#)
- VM7_7n
 - gdcm::VM, [1366](#)
- VM8
 - gdcm::VM, [1366](#)
- VM9
 - gdcm::VM, [1366](#)
- VM99
 - gdcm::VM, [1366](#)
- VM_END
 - gdcm::VM, [1366](#)
- VMType
 - gdcm::Attribute< Group, Element, TVR, TVM >, [132](#)
 - gdcm::Attribute< Group, Element, TVR, VM::VM1 >, [142](#)
 - gdcm::VM, [1365](#)
- VOILUTBoxSOPClass
 - gdcm::UIDs, [1249](#)
- VolumeRenderingVolumetricPresentationStateStorage
 - gdcm::UIDs, [1254](#)
- VR
 - gdcm::VR, [1372](#)
- VR_END
 - gdcm::VR, [1371](#)
- VR_VM1
 - gdcm::VR, [1371](#)
- VRALL
 - gdcm::VR, [1371](#)
- VRASCII
 - gdcm::VR, [1371](#)
- VRBINARY
 - gdcm::VR, [1371](#)
- VRField
 - gdcm::CSAElement, [319](#)
 - gdcm::DataElement, [353](#)
- VRType
 - gdcm::VR, [1370](#)
- VRTypeTemplateCase
 - gdcmVR.h, [1767](#)
- VT100
 - gdcm::terminal, [83](#)
- VTK_CMYK
 - vtkGDCMImageReader.h, [2153](#)
 - vtkGDCMImageReader2.h, [2158](#)
- VTK_INVERSE_LUMINANCE
 - vtkGDCMImageReader.h, [2153](#)
 - vtkGDCMImageReader2.h, [2158](#)
- VTK_LOOKUP_TABLE
 - vtkGDCMImageReader.h, [2153](#)
 - vtkGDCMImageReader2.h, [2158](#)
- VTK_YBR

- vtkGDCMImageReader.h, 2153
- vtkGDCMImageReader2.h, 2158
- vtkBooleanMacro
 - vtkGDCMImageReader, 1389, 1390
 - vtkGDCMImageReader2, 1404, 1405
 - vtkGDCMImageWriter, 1417
 - vtkGDCMThreadedImageReader, 1441
 - vtkGDCMThreadedImageReader2, 1446
 - vtkImageColorViewer, 1459
 - vtkImageMapToColors16, 1466
- vtkGDCMImageReader, 1383
 - ~vtkGDCMImageReader, 1386
 - ApplyInverseVideo, 1395
 - ApplyLookupTable, 1395
 - ApplyPlanarConfiguration, 1395
 - ApplyShiftScale, 1395
 - ApplyYBRToRGB, 1395
 - CanReadFile, 1386
 - Curve, 1395
 - DirectionCosines, 1395
 - ExecuteData, 1386
 - ExecuteInformation, 1387
 - FileNames, 1396
 - FillMedicalImageInformation, 1387
 - ForceRescale, 1396
 - GetDescriptiveName, 1387
 - GetFileExtensions, 1387
 - GetIconImage, 1387
 - GetOverlay, 1387
 - IconDataScalarType, 1396
 - IconImageDataExtent, 1396
 - IconNumberOfScalarComponents, 1396
 - ImageFormat, 1396
 - ImageOrientationPatient, 1396
 - ImagePositionPatient, 1396
 - LoadIconImage, 1397
 - LoadOverlays, 1397
 - LoadSingleFile, 1387
 - LossyFlag, 1397
 - MedicalImageProperties, 1397
 - New, 1387
 - NumberOfIconImages, 1397
 - NumberOfOverlays, 1397
 - PlanarConfiguration, 1397
 - PrintSelf, 1388
 - RequestDataCompat, 1388
 - RequestInformationCompat, 1388
 - Scale, 1398
 - SetCurve, 1388
 - SetFileNames, 1388
 - SetFilePattern, 1389
 - SetFilePrefix, 1389
 - SetMedicalImageProperties, 1389
 - Shift, 1398
 - vtkBooleanMacro, 1389, 1390
 - vtkGDCMImageReader, 1386
 - vtkGDCMMedicalImageProperties, 1424
 - vtkGetMacro, 1390–1392
 - vtkGetObjectMacro, 1392, 1393
 - vtkGetStringMacro, 1393
 - vtkGetVector3Macro, 1393
 - vtkGetVector6Macro, 1393
 - vtkSetMacro, 1393, 1394
 - vtkSetVector6Macro, 1394
 - vtkTypeMacro, 1394
- vtkGDCMImageReader.h, 2151, 2153
 - VTK_CMYK, 2153
 - VTK_INVERSE_LUMINANCE, 2153
 - VTK_LOOKUP_TABLE, 2153
 - VTK_YBR, 2153
- vtkGDCMImageReader2, 1398
 - ~vtkGDCMImageReader2, 1401
 - ApplyInverseVideo, 1410
 - ApplyLookupTable, 1410
 - ApplyPlanarConfiguration, 1410
 - ApplyShiftScale, 1410
 - ApplyYBRToRGB, 1410
 - CanReadFile, 1401
 - Curve, 1410
 - DirectionCosines, 1410
 - FillMedicalImageInformation, 1401
 - ForceRescale, 1411
 - GetDescriptiveName, 1401
 - GetFileExtensions, 1401
 - GetIconImage, 1402
 - GetIconImagePort, 1402
 - GetOverlay, 1402
 - GetOverlayPort, 1402
 - IconDataScalarType, 1411
 - IconImageDataExtent, 1411
 - IconNumberOfScalarComponents, 1411
 - ImageFormat, 1411
 - ImageOrientationPatient, 1411
 - ImagePositionPatient, 1411
 - LoadIconImage, 1411
 - LoadOverlays, 1412
 - LoadSingleFile, 1402
 - LossyFlag, 1412
 - New, 1402
 - NumberOfIconImages, 1412
 - NumberOfOverlays, 1412
 - PlanarConfiguration, 1412
 - PrintSelf, 1402
 - ProcessRequest, 1403
 - RequestData, 1403
 - RequestDataCompat, 1403
 - RequestInformation, 1403
 - RequestInformationCompat, 1403

- Scale, [1412](#)
- SetCurve, [1404](#)
- SetFilePattern, [1404](#)
- SetFilePrefix, [1404](#)
- SetMedicalImageProperties, [1404](#)
- Shift, [1412](#)
- vtkBooleanMacro, [1404](#), [1405](#)
- vtkGDCMImageReader2, [1401](#)
- vtkGDCMMedicalImageProperties, [1424](#)
- vtkGetMacro, [1405–1407](#)
- vtkGetObjectMacro, [1407](#)
- vtkGetStringMacro, [1408](#)
- vtkGetVector3Macro, [1408](#)
- vtkGetVector6Macro, [1408](#)
- vtkSetMacro, [1408](#), [1409](#)
- vtkSetVector6Macro, [1409](#)
- vtkTypeMacro, [1409](#)
- vtkGDCMImageReader2.h, [2157](#), [2159](#)
 - VTK_CMYK, [2158](#)
 - VTK_INVERSE_LUMINANCE, [2158](#)
 - VTK_LOOKUP_TABLE, [2158](#)
 - VTK_YBR, [2158](#)
- vtkGDCMImageWriter, [1413](#)
 - ~vtkGDCMImageWriter, [1415](#)
 - CompressionTypes, [1415](#)
 - GetDescriptiveName, [1416](#)
 - GetFileExtensions, [1416](#)
 - GetFileName, [1416](#)
 - JPEG2000_COMPRESSION, [1415](#)
 - JPEG_COMPRESSION, [1415](#)
 - JPEGLS_COMPRESSION, [1415](#)
 - New, [1416](#)
 - NO_COMPRESSION, [1415](#)
 - PrintSelf, [1416](#)
 - RLE_COMPRESSION, [1415](#)
 - SetDirectionCosines, [1416](#)
 - SetDirectionCosinesFromImageOrientationPatient, [1416](#)
 - SetFileNames, [1417](#)
 - SetMedicalImageProperties, [1417](#)
 - vtkBooleanMacro, [1417](#)
 - vtkGDCMImageWriter, [1415](#)
 - vtkGDCMMedicalImageProperties, [1424](#)
 - vtkGetMacro, [1417](#), [1418](#)
 - vtkGetObjectMacro, [1418](#), [1419](#)
 - vtkGetStringMacro, [1419](#)
 - vtkSetMacro, [1419](#), [1420](#)
 - vtkSetStringMacro, [1420](#)
 - vtkTypeMacro, [1420](#)
 - Write, [1420](#)
 - WriteGDCMData, [1421](#)
 - WriteSlice, [1421](#)
- vtkGDCMImageWriter.h, [2162](#), [2163](#)
- vtkGDCMMedicalImageProperties, [1421](#)
 - ~vtkGDCMMedicalImageProperties, [1422](#)
 - Clear, [1423](#)
 - GetFile, [1423](#)
 - New, [1423](#)
 - PrintSelf, [1423](#)
 - PushBackFile, [1423](#)
 - vtkGDCMImageReader, [1424](#)
 - vtkGDCMImageReader2, [1424](#)
 - vtkGDCMImageWriter, [1424](#)
 - vtkGDCMMedicalImageProperties, [1422](#)
 - vtkTypeMacro, [1423](#)
- vtkGDCMMedicalImageProperties.h, [2165](#), [2166](#)
- vtkGDCMPolyDataReader, [1424](#)
 - ~vtkGDCMPolyDataReader, [1426](#)
 - FileName, [1428](#)
 - FillMedicalImageInformation, [1426](#)
 - MedicalImageProperties, [1428](#)
 - New, [1426](#)
 - PrintSelf, [1426](#)
 - RequestData, [1427](#)
 - RequestData_HemodynamicWaveformStorage, [1427](#)
 - RequestData_RTStructureSetStorage, [1427](#)
 - RequestInformation, [1427](#)
 - RequestInformation_HemodynamicWaveformStorage, [1427](#)
 - RequestInformation_RTStructureSetStorage, [1427](#)
 - RTStructSetProperties, [1429](#)
 - vtkGDCMPolyDataReader, [1426](#)
 - vtkGetObjectMacro, [1427](#), [1428](#)
 - vtkGetStringMacro, [1428](#)
 - vtkSetStringMacro, [1428](#)
 - vtkTypeMacro, [1428](#)
- vtkGDCMPolyDataReader.h, [2171](#)
- vtkGDCMPolyDataWriter, [1429](#)
 - ~vtkGDCMPolyDataWriter, [1431](#)
 - InitializeRTStructSet, [1431](#)
 - MedicalImageProperties, [1433](#)
 - New, [1431](#)
 - PrintSelf, [1431](#)
 - RTStructSetProperties, [1433](#)
 - SetMedicalImageProperties, [1432](#)
 - SetNumberOfInputPorts, [1432](#)
 - SetRTStructSetProperties, [1432](#)
 - vtkGDCMPolyDataWriter, [1431](#)
 - vtkTypeMacro, [1432](#)
 - WriteData, [1432](#)
 - WriteRTSTRUCTData, [1433](#)
 - WriteRTSTRUCTInfo, [1433](#)
- vtkGDCMPolyDataWriter.h, [2172](#), [2173](#)
- vtkGDCMTesting, [1434](#)
 - ~vtkGDCMTesting, [1435](#)
 - GetGDCMDataRoot, [1436](#)
 - GetMD5MetaImage, [1436](#)

- GetMHDMD5FromFile, 1436
- GetNumberOfMD5MetalImages, 1436
- GetRAWMD5FromFile, 1436
- GetVTKDataRoot, 1436
- MD5MetalImagesType, 1435
- New, 1436
- PrintSelf, 1437
- vtkGDCMTesting, 1435
- vtkTypeMacro, 1437
- vtkGDCMTesting.h, 2174, 2175
- vtkGDCMThreadedImageReader, 1437
 - ~vtkGDCMThreadedImageReader, 1440
 - ExecuteData, 1440
 - ExecuteInformation, 1440
 - New, 1441
 - PrintSelf, 1441
 - ReadFiles, 1441
 - RequestDataCompat, 1441
 - vtkBooleanMacro, 1441
 - vtkGDCMThreadedImageReader, 1440
 - vtkGetMacro, 1441
 - vtkSetMacro, 1441, 1442
 - vtkTypeMacro, 1442
- vtkGDCMThreadedImageReader.h, 2176
- vtkGDCMThreadedImageReader2, 1443
 - ~vtkGDCMThreadedImageReader2, 1444
 - GetFileName, 1445
 - New, 1445
 - PrintSelf, 1445
 - RequestInformation, 1445
 - SetFileName, 1445
 - SetFileNames, 1445
 - SplitExtent, 1445
 - ThreadedRequestData, 1445
 - vtkBooleanMacro, 1446
 - vtkGDCMThreadedImageReader2, 1444
 - vtkGetMacro, 1446, 1447
 - vtkGetObjectMacro, 1447
 - vtkGetVector3Macro, 1447, 1448
 - vtkGetVector6Macro, 1448
 - vtkSetMacro, 1448, 1449
 - vtkSetVector3Macro, 1449
 - vtkSetVector6Macro, 1449
 - vtkTypeMacro, 1449
- vtkGDCMThreadedImageReader2.h, 2178
- vtkGetMacro
 - vtkGDCMImageReader, 1390–1392
 - vtkGDCMImageReader2, 1405–1407
 - vtkGDCMImageWriter, 1417, 1418
 - vtkGDCMThreadedImageReader, 1441
 - vtkGDCMThreadedImageReader2, 1446, 1447
 - vtkImageColorViewer, 1459
 - vtkImageMapToColors16, 1466
 - vtkImageMapToWindowLevelColors2, 1471
- vtkGetObjectMacro
 - vtkGDCMImageReader, 1392, 1393
 - vtkGDCMImageReader2, 1407
 - vtkGDCMImageWriter, 1418, 1419
 - vtkGDCMPolyDataReader, 1427, 1428
 - vtkGDCMThreadedImageReader2, 1447
 - vtkImageColorViewer, 1459, 1460
 - vtkImageMapToColors16, 1466
- vtkGetStringMacro
 - vtkGDCMImageReader, 1393
 - vtkGDCMImageReader2, 1408
 - vtkGDCMImageWriter, 1419
 - vtkGDCMPolyDataReader, 1428
 - vtkRTStructSetProperties, 1488–1490
- vtkGetVector3Macro
 - vtkGDCMImageReader, 1393
 - vtkGDCMImageReader2, 1408
 - vtkGDCMThreadedImageReader2, 1447, 1448
- vtkGetVector6Macro
 - vtkGDCMImageReader, 1393
 - vtkGDCMImageReader2, 1408
 - vtkGDCMThreadedImageReader2, 1448
- vtkImageColorViewer, 1450
 - ~vtkImageColorViewer, 1453
 - AddInput, 1453
 - AddInputConnection, 1453
 - FirstRender, 1461
 - GetColorLevel, 1453
 - GetColorWindow, 1453
 - GetInput, 1453
 - GetOffScreenRendering, 1453
 - GetOverlayVisibility, 1453
 - GetPosition, 1454
 - GetSize, 1454
 - GetSliceMax, 1454
 - GetSliceMin, 1454
 - GetSliceRange, 1454
 - GetWindowName, 1454
 - ImageActor, 1461
 - InstallPipeline, 1455
 - Interactor, 1461
 - InteractorStyle, 1461
 - New, 1455
 - OverlayImageActor, 1461
 - PrintSelf, 1455
 - Render, 1455
 - Renderer, 1461
 - RenderWindow, 1461
 - SetColorLevel, 1455
 - SetColorWindow, 1455
 - SetDisplayId, 1455
 - SetInput, 1456
 - SetInputConnection, 1456
 - SetOffScreenRendering, 1456

- SetOverlayVisibility, [1456](#)
- SetParentId, [1456](#)
- SetPosition, [1456](#)
- SetRenderer, [1457](#)
- SetRenderWindow, [1457](#)
- SetSize, [1457](#)
- SetSlice, [1457](#)
- SetSliceOrientation, [1457](#)
- SetSliceOrientationToXY, [1458](#)
- SetSliceOrientationToXZ, [1458](#)
- SetSliceOrientationToYZ, [1458](#)
- SetupInteractor, [1458](#)
- SetWindowId, [1458](#)
- Slice, [1461](#)
- SLICE_ORIENTATION_XY, [1452](#)
- SLICE_ORIENTATION_XZ, [1452](#)
- SLICE_ORIENTATION_YZ, [1452](#)
- SliceOrientation, [1462](#)
- UnInstallPipeline, [1458](#)
- UpdateDisplayExtent, [1458](#)
- UpdateOrientation, [1459](#)
- vtkBooleanMacro, [1459](#)
- vtkGetMacro, [1459](#)
- vtkGetObjectMacro, [1459](#), [1460](#)
- vtkImageColorViewer, [1453](#)
- vtkImageColorViewerCallback, [1460](#)
- vtkTypeMacro, [1460](#)
- WindowLevel, [1462](#)
- vtkImageColorViewer.h, [2180](#), [2181](#)
- vtkImageColorViewerCallback
 - vtkImageColorViewer, [1460](#)
- vtkImageMapToColors16, [1462](#)
 - ~vtkImageMapToColors16, [1464](#)
 - ActiveComponent, [1467](#)
 - DataWasPassed, [1467](#)
 - GetMTime, [1464](#)
 - LookupTable, [1468](#)
 - New, [1464](#)
 - OutputFormat, [1468](#)
 - PassAlphaToOutput, [1468](#)
 - PrintSelf, [1464](#)
 - RequestData, [1464](#)
 - RequestInformation, [1465](#)
 - SetLookupTable, [1465](#)
 - SetOutputFormatToLuminance, [1465](#)
 - SetOutputFormatToLuminanceAlpha, [1465](#)
 - SetOutputFormatToRGB, [1465](#)
 - SetOutputFormatToRGBA, [1465](#)
 - ThreadedRequestData, [1465](#)
 - vtkBooleanMacro, [1466](#)
 - vtkGetMacro, [1466](#)
 - vtkGetObjectMacro, [1466](#)
 - vtkImageMapToColors16, [1464](#)
 - vtkSetMacro, [1467](#)
 - vtkTypeMacro, [1467](#)
- vtkImageMapToColors16.h, [2184](#)
- vtkImageMapToWindowLevelColors2, [1468](#)
 - ~vtkImageMapToWindowLevelColors2, [1470](#)
 - Level, [1472](#)
 - New, [1470](#)
 - PrintSelf, [1470](#)
 - RequestData, [1470](#)
 - RequestInformation, [1470](#)
 - ThreadedRequestData, [1470](#)
 - vtkGetMacro, [1471](#)
 - vtkImageMapToWindowLevelColors2, [1470](#)
 - vtkSetMacro, [1471](#)
 - vtkTypeMacro, [1471](#)
 - Window, [1472](#)
- vtkImageMapToWindowLevelColors2.h, [2186](#)
- vtkImagePlanarComponentsToComponents, [1472](#)
 - ~vtkImagePlanarComponentsToComponents, [1473](#)
 - New, [1474](#)
 - PrintSelf, [1474](#)
 - RequestData, [1474](#)
 - vtkImagePlanarComponentsToComponents, [1473](#)
 - vtkTypeMacro, [1474](#)
- vtkImagePlanarComponentsToComponents.h, [2188](#)
- vtkImageRGBToYBR, [1475](#)
 - ~vtkImageRGBToYBR, [1476](#)
 - New, [1476](#)
 - PrintSelf, [1476](#)
 - ThreadedExecute, [1476](#)
 - vtkImageRGBToYBR, [1476](#)
 - vtkTypeMacro, [1476](#)
- vtkImageRGBToYBR.h, [2189](#), [2190](#)
- vtkImageYBRToRGB, [1477](#)
 - ~vtkImageYBRToRGB, [1478](#)
 - New, [1478](#)
 - PrintSelf, [1478](#)
 - ThreadedExecute, [1478](#)
 - vtkImageYBRToRGB, [1478](#)
 - vtkTypeMacro, [1479](#)
- vtkImageYBRToRGB.h, [2191](#)
- vtkLookupTable16, [1479](#)
 - ~vtkLookupTable16, [1480](#)
 - Build, [1481](#)
 - GetPointer, [1481](#)
 - MapScalarsThroughTable2, [1481](#)
 - New, [1481](#)
 - PrintSelf, [1481](#)
 - SetNumberOfTableValues, [1481](#)
 - Table16, [1482](#)
 - vtkLookupTable16, [1480](#)
 - vtkTypeMacro, [1482](#)
 - WritePointer, [1482](#)
- vtkLookupTable16.h, [2192](#), [2193](#)
- vtkRTStructSetProperties, [1483](#)

- ~vtkRTStructSetProperties, 1485
- AddContourReferencedFrameOfReference, 1485
- AddReferencedFrameOfReference, 1485
- AddStructureSetROI, 1485
- AddStructureSetROIObservation, 1486
- Clear, 1486
- DeepCopy, 1486
- GetContourReferencedFrameOfReferenceClassUID, 1486
- GetContourReferencedFrameOfReferenceInstanceUID, 1486
- GetNumberOfContourReferencedFrameOfReferences, 1486
- GetNumberOfReferencedFrameOfReferences, 1487
- GetNumberOfStructureSetROIs, 1487
- GetReferencedFrameOfReferenceClassUID, 1487
- GetReferencedFrameOfReferenceInstanceUID, 1487
- GetStructureSetObservationNumber, 1487
- GetStructureSetROIDescription, 1487
- GetStructureSetROIGenerationAlgorithm, 1487
- GetStructureSetROIName, 1487
- GetStructureSetROINumber, 1488
- GetStructureSetROIObservationLabel, 1488
- GetStructureSetROIRefFrameRefUID, 1488
- GetStructureSetRTROIInterpretedType, 1488
- Internals, 1492
- New, 1488
- PrintSelf, 1488
- ReferenceFrameOfReferenceUID, 1492
- ReferenceSeriesInstanceUID, 1492
- SeriesInstanceUID, 1492
- SOPInstanceUID, 1492
- StructureSetDate, 1492
- StructureSetLabel, 1492
- StructureSetName, 1493
- StructureSetTime, 1493
- StudyInstanceUID, 1493
- vtkGetStringMacro, 1488–1490
- vtkRTStructSetProperties, 1485
- vtkSetStringMacro, 1490, 1491
- vtkTypeMacro, 1491
- vtkRTStructSetProperties.h, 2194, 2195
- vtkSetMacro
 - vtkGDCMImageReader, 1393, 1394
 - vtkGDCMImageReader2, 1408, 1409
 - vtkGDCMImageWriter, 1419, 1420
 - vtkGDCMThreadedImageReader, 1441, 1442
 - vtkGDCMThreadedImageReader2, 1448, 1449
 - vtkImageMapToColors16, 1467
 - vtkImageMapToWindowLevelColors2, 1471
- vtkSetStringMacro
 - vtkGDCMImageWriter, 1420
 - vtkGDCMPolyDataReader, 1428
 - vtkRTStructSetProperties, 1490, 1491
- vtkSetVector3Macro
 - vtkGDCMThreadedImageReader2, 1449
- vtkSetVector6Macro
 - vtkGDCMImageReader, 1394
 - vtkGDCMImageReader2, 1409
 - vtkGDCMThreadedImageReader2, 1449
- vtkTypeMacro
 - vtkGDCMImageReader, 1394
 - vtkGDCMImageReader2, 1409
 - vtkGDCMImageWriter, 1420
 - vtkGDCMMedicalImageProperties, 1423
 - vtkGDCMPolyDataReader, 1428
 - vtkGDCMPolyDataWriter, 1432
 - vtkGDCMTesting, 1437
 - vtkGDCMThreadedImageReader, 1442
 - vtkGDCMThreadedImageReader2, 1449
 - vtkImageColorViewer, 1460
 - vtkImageMapToColors16, 1467
 - vtkImageMapToWindowLevelColors2, 1471
 - vtkImagePlanarComponentsToComponents, 1474
 - vtkImageRGBToYBR, 1476
 - vtkImageYBRToRGB, 1479
 - vtkLookupTable16, 1482
 - vtkRTStructSetProperties, 1491
- WarningOff
 - gdcm::Trace, 1215
- WarningOn
 - gdcm::Trace, 1215
- Waveform
 - gdcm::MediaStorage, 750
 - gdcm::Waveform, 1494
- WaveformStorageTrialRetired
 - gdcm::UIDs, 1250
- WeirdPapryus
 - gdcm::TransferSyntax, 1218
- what
 - gdcm::Exception, 486
- white
 - gdcm::terminal, 81
- WideFieldOphthalmicPhotography3DCoordinatesImageStorage
 - gdcm::UIDs, 1254
- WideFieldOphthalmicPhotographyStereographicProjectionImageStorage
 - gdcm::UIDs, 1254
- Window
 - vtkImageMapToWindowLevelColors2, 1472
- WindowLevel
 - vtkImageColorViewer, 1462
- WinterColorPaletteSOPInstance
 - gdcm::UIDs, 1253
- WIREFRAME
 - gdcm::Surface, 1150
- WLMFindQuery
 - gdcm::WLMFindQuery, 1497

Write

- gdcm::ByteValue, [254](#)
- gdcm::CommandDataSet, [294](#)
- gdcm::DataElement, [352](#)
- gdcm::DataSet, [370](#)
- gdcm::Element< TVR, TVM >, [432](#)
- gdcm::Element< TVR, VM::VM1_2 >, [438](#)
- gdcm::Element< TVR, VM::VM2_2n >, [443](#)
- gdcm::Element< TVR, VM::VM3_3n >, [448](#)
- gdcm::Element< TVR, VM::VM3_4 >, [453](#)
- gdcm::Element< VR::AS, VM::VM5 >, [457](#)
- gdcm::Element< VR::OB, VM::VM1 >, [461](#)
- gdcm::Element< VR::OW, VM::VM1 >, [466](#)
- gdcm::EncodingImplementation< VR::VRASCII >, [475](#), [476](#)
- gdcm::EncodingImplementation< VR::VRBINARY >, [478](#)
- gdcm::ExplicitDataElement, [492](#)
- gdcm::File, [501](#)
- gdcm::FileAnonymizer, [506](#)
- gdcm::FileMetaInformation, [529](#)
- gdcm::Fragment, [563](#)
- gdcm::ImageWriter, [646](#)
- gdcm::ImplicitDataElement, [653](#)
- gdcm::Item, [675](#)
- gdcm::network::AAabortPDU, [87](#)
- gdcm::network::AAAssociateACPDU, [91](#)
- gdcm::network::AAAssociateRJPDU, [93](#)
- gdcm::network::AAAssociateRQPDU, [99](#)
- gdcm::network::AbstractSyntax, [102](#)
- gdcm::network::ApplicationContext, [117](#)
- gdcm::network::AReleaseRPPDU, [122](#)
- gdcm::network::AReleaseRQPDU, [124](#)
- gdcm::network::AsynchronousOperationsWindowSub, [129](#)
- gdcm::network::BasePDU, [202](#)
- gdcm::network::ImplementationClassUIDSub, [647](#)
- gdcm::network::ImplementationUIDSub, [648](#)
- gdcm::network::ImplementationVersionNameSub, [649](#)
- gdcm::network::MaximumLengthSub, [741](#)
- gdcm::network::PDataTFPDU, [856](#)
- gdcm::network::PresentationContextAC, [920](#)
- gdcm::network::PresentationContextRQ, [927](#)
- gdcm::network::PresentationDataValue, [930](#)
- gdcm::network::RoleSelectionSub, [995](#)
- gdcm::network::ServiceClassApplicationInformation, [1061](#)
- gdcm::network::SOPClassExtendedNegociationSub, [1087](#)
- gdcm::network::TransferSyntaxSub, [1223](#)
- gdcm::network::UserInformation, [1348](#)
- gdcm::PGXCodec, [874](#)
- gdcm::PixmapWriter, [905](#)
- gdcm::PNMCodec, [910](#)
- gdcm::Preamble, [914](#)
- gdcm::SegmentWriter, [1037](#)
- gdcm::SequenceOfFragments, [1044](#)
- gdcm::SequenceOfItems, [1053](#)
- gdcm::StreamImageWriter, [1111](#)
- gdcm::SurfaceWriter, [1171](#)
- gdcm::Tag, [1200](#)
- gdcm::ValueIO< TDE, TSwap, TType >, [1355](#)
- gdcm::VL, [1362](#)
- gdcm::VR, [1375](#)
- gdcm::VRVLSIZE< 0 >, [1381](#)
- gdcm::VRVLSIZE< 1 >, [1383](#)
- gdcm::Writer, [1503](#)
- vtkGDCMImageWriter, [1420](#)
- Write16
 - gdcm::VL, [1362](#)
- WriteBuffer
 - gdcm::ByteValue, [255](#)
 - gdcm::SequenceOfFragments, [1045](#)
- WriteBufferAsRGBA
 - gdcm::LookupTable, [732](#)
- WriteData
 - vtkGDCMPolyDataWriter, [1432](#)
- WriteFooter
 - gdcm::DictConverter, [398](#)
- WriteGDCMData
 - vtkGDCMImageWriter, [1421](#)
- WriteHeader
 - gdcm::DictConverter, [398](#)
- WriteHelpFile
 - gdcm::BaseQuery, [206](#)
- WriteImageInformation
 - gdcm::StreamImageWriter, [1111](#)
- WriteImageSubregionRAW
 - gdcm::StreamImageWriter, [1112](#)
- WritePointer
 - vtkLookupTable16, [1482](#)
- WriteQuery
 - gdcm::BaseQuery, [206](#)
- Writer
 - gdcm::Writer, [1501](#)
- WriteRawHeader
 - gdcm::StreamImageWriter, [1112](#)
- WriteRTSTRUCTData
 - vtkGDCMPolyDataWriter, [1433](#)
- WriteRTSTRUCTInfo
 - vtkGDCMPolyDataWriter, [1433](#)
- WriteSlice
 - vtkGDCMImageWriter, [1421](#)
- x16printf
 - gdcm, [73](#)
- XAXRFGayscaleSoftcopyPresentationStateStorage

- gdcM::UIDs, [1254](#)
- XML
 - gdcM::Printer, [933](#)
- XMLDictReader
 - gdcM::XMLDictReader, [1505](#)
- XMLEncoding
 - gdcM::UIDs, [1248](#)
- XMLPrinter
 - gdcM::XMLPrinter, [1508](#)
- XMLPrivateDictReader
 - gdcM::XMLPrivateDictReader, [1512](#)
- XRay3DAngiographicImageStorage
 - gdcM::MediaStorage, [749](#)
 - gdcM::UIDs, [1250](#)
- XRay3DCraniofacialImageStorage
 - gdcM::MediaStorage, [750](#)
 - gdcM::UIDs, [1250](#)
- XRayAngiographicBiPlaneImageStorageRetired
 - gdcM::MediaStorage, [748](#)
 - gdcM::UIDs, [1250](#)
- XRayAngiographicImageStorage
 - gdcM::MediaStorage, [748](#)
 - gdcM::UIDs, [1250](#)
- XRayRadiationDoseSR
 - gdcM::MediaStorage, [749](#)
- XRayRadiationDoseSRStorage
 - gdcM::UIDs, [1251](#)
- XRayRadiofluoroscopicImageStorage
 - gdcM::UIDs, [1250](#)
- XRayRadiofluoroscopicImageStorage
 - gdcM::MediaStorage, [748](#)
- YBR2RGB
 - gdcM::ImageChangePhotometricInterpretation, [593](#)
- YBR_FULL
 - gdcM::PhotometricInterpretation, [876](#)
- YBR_FULL_422
 - gdcM::PhotometricInterpretation, [876](#)
- YBR_ICT
 - gdcM::PhotometricInterpretation, [876](#)
- YBR_PARTIAL_420
 - gdcM::PhotometricInterpretation, [876](#)
- YBR_PARTIAL_422
 - gdcM::PhotometricInterpretation, [876](#)
- YBR_RCT
 - gdcM::PhotometricInterpretation, [876](#)
- yellow
 - gdcM::terminal, [81](#)
- YES
 - gdcM::Surface, [1149](#)
- ZEROED_OUT
 - gdcM::CSAHeader, [321](#)
- ZSpacing
 - gdcM::IPPSorter, [669](#)
- ZTolerance
 - gdcM::IPPSorter, [669](#)